Sequencer64 Developer Reference Manual 0.9.10

Generated by Doxygen 1.8.11

Contents

1	Seq	uencer6	64		1
	1.1	Introdu	uction		1
2	MID	l File Pa	ırsing in S	Sequencer64	3
	2.1	Introdu	uction		3
	2.2	SMF 1	Parsing .		3
		2.2.1	MIDI File	Header, MThd	3
		2.2.2	MIDI Tra	ck, MTrk	4
			2.2.2.1	Channel Events	4
			2.2.2.2	Meta Events	5
		2.2.3	Meta Eve	ents Summary	6
			2.2.3.1	Sequence Number (0x00)	6
			2.2.3.2	Track/Sequence Name (0x03)	7
			2.2.3.3	End of Track (0x2F)	7
			2.2.3.4	Set Tempo Event (0x51)	7
			2.2.3.5	Time Signature Event (0x58)	8
			2.2.3.6	SysEx Event (0xF0)	9
			2.2.3.7	Sequencer Specific (0x7F)	10
			2.2.3.8	Non-Specific End of Sequence	10
	2.3	SMF 0	Parsing .		10
	24	Runnir	na Status		11

iv CONTENTS

3	JAC	K, Live, and Song Modes in Sequencer64				
	3.1	Introduction	13			
	3.2	JACK Functions	13			
		3.2.1 jack_client_open()	14			
		3.2.2 jack_on_shutdown()	14			
		3.2.3 jack_set_sync_callback()	14			
		3.2.4 jack_set_process_callback()	15			
		3.2.5 jack_set_session_callback()	15			
		3.2.6 jack_activate()	15			
		3.2.7 jack_release_timebase()	15			
		3.2.8 jack_client_close()	15			
		3.2.9 jack_transport_start()	15			
		3.2.10 jack_transport_stop()	15			
		3.2.11 jack_transport_locate()	15			
		3.2.12 jack_transport_reposition()	16			
		3.2.13 jack_transport_query()	16			
	3.3	Modes Operation	16			
		3.3.1 No JACK, Live Mode	16			
		3.3.2 No JACK, Song Mode	16			
		3.3.3 JACK Transport	17			
	3.4	Breakage	17			
	3.5	JACK References	18			
4	Heer	r Testing of Sequencer64 with Yoshimi	19			
•	4.1	Introduction	19			
	4.1	Smoke Test	19			
	4.3	Tests in the Patterns Window	20			
		4.3.1 Button Clicks on a Pattern	21			
		· · · · · · · · · · · · · · · · · · ·				
	4.4	4.3.3 The Sequencer64 User File	21			
	4.4	Tests Using Valgrind	21			
		4.4.1 Valgrind Suppressions	22			
		4.4.2 Full Valgrind Leak-Checking	22			
		4.4.2.1 Leak-Checking Basic Operation	23			
	4.5	Specific Fault Debugging	23			
	4.6	Snipping of a MIDI file.	23			

CONTENTS

5	Lice	nses	25
	5.1	License Terms for the This Project	25
	5.2	XPC Application License	25
	5.3	XPC Library License	26
	5.4	XPC Documentation License	26
	5.5	XPC Affero License	27
	5.6	XPC License Summary	27
6	Todo	o List	29
7	Depi	recated List	31
8	Nam	nespace Index	33
	8.1	Namespace List	33
9	Hiera	archical Index	35
	9.1	Class Hierarchy	35
10	Data	Structure Index	37
	10.1	Data Structures	37
11	Nam	nespace Documentation	41
	11.1	seq64 Namespace Reference	41
		11.1.1 Detailed Description	48
		11.1.2 Typedef Documentation	48
		11.1.2.1 midipulse	48
		11.1.3 Enumeration Type Documentation	48
		11.1.3.1 seq_modifier_t	48
		11.1.3.2 seq_event_type_t	48
		11.1.3.3 seq_scroll_direction_t	49
		11.1.3.4 clock_e	49
		11.1.3.5 interaction_method_t	49
		11.1.3.6 c_music_scales	49
		11.1.3.7 draw_type	49

vi CONTENTS

11.1.4	Function	Documentation	50
	11.1.4.1	extract_timing_numbers(const std::string &s, std::string ∂_1, std::string ∂_2, std::string ∂_3, std::string &fraction)	50
	11.1.4.2	pulses_to_string(midipulse p)	50
	11.1.4.3	pulses_to_measurestring(midipulse p, const midi_timing &seqparms)	50
	11.1.4.4	pulses_to_midi_measures(midipulse p, const midi_timing &seqparms, midi_← measures &measures)	50
	11.1.4.5	pulses_to_timestring(midipulse p, int bpm, int ppqn)	51
	11.1.4.6	pulses_to_timestring(midipulse p, const midi_timing &timinginfo)	51
	11.1.4.7	measurestring_to_pulses(const std::string &measures, const midi_timing &seq-parms)	51
	11.1.4.8	midi_measures_to_pulses(const midi_measures &measures, const midi_timing &seqparms)	52
	11.1.4.9	timestring_to_pulses(const std::string ×tring, int bpm, int ppqn)	52
	11.1.4.10	string_to_pulses(const std::string &s, const midi_timing &mt)	52
	11.1.4.11	string_to_midibyte(const std::string &s)	53
	11.1.4.12	shorten_file_spec(const std::string &fpath, int leng)	53
	11.1.4.13	string_not_void(const std::string &s)	53
	11.1.4.14	string_is_void(const std::string &s)	54
	11.1.4.15	strings_match(const std::string ⌖, const std::string &x)	54
	11.1.4.16	log2_time_sig_value(int tsd)	54
	11.1.4.17	tempo_to_bytes(midibyte t[3], int tempo_us)	55
	11.1.4.18	zoom_power_of_2(int ppqn)	55
	11.1.4.19	beats_per_minute_from_tempo(double tempo)	55
	11.1.4.20	tempo_from_beats_per_minute(double bpm)	56
	11.1.4.21	pulse_length_us(int bpm, int ppqn)	56
	11.1.4.22	delta_time_us_to_ticks(unsigned long us, int bpm, int ppqn)	56
	11.1.4.23	ticks_to_delta_time_us(midipulse delta_ticks, int bpm, int ppqn)	57
	11.1.4.24	clock_tick_duration_bogus(int bpm, int ppqn)	57
	11.1.4.25	clock_ticks_from_ppqn(int ppqn)	57
	11.1.4.26	double_ticks_from_ppqn(int ppqn)	58
	11.1.4.27	measures_to_ticks(int bpm, int ppqn, int bw, int measures=1)	58

CONTENTS vii

11.1.4.28 help_check(int argc, char *argv[])	59
11.1.4.29 parse_options_files(perform &p, int argc, char *argv[])	59
11.1.4.30 parse_command_line_options(int argc, char *argv[])	60
11.1.4.31 write_options_files(const perform &p)	60
11.1.4.32 to_string(const event &ev)	60
11.1.4.33 file_exists(const std::string &filename)	60
11.1.4.34 file_readable(const std::string &filename)	60
11.1.4.35 file_writable(const std::string &filename)	61
11.1.4.36 file_accessible(const std::string &filename)	61
11.1.4.37 file_executable(const std::string &filename)	61
11.1.4.38 file_is_directory(const std::string &filename)	61
11.1.4.39 make_directory(const std::string &pathname)	62
11.1.4.40 rc()	62
11.1.4.41 choose_ppqn(int ppqn)	62
11.1.4.42 ppqn_is_valid(int ppqn)	62
11.1.4.43 jack_sync_callback(jack_transport_state_t state, jack_position_t *pos, void *arg)	63
11.1.4.44 jack_shutdown_callback(void *arg)	63
11.1.4.45 jack_timebase_callback(jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)	63
11.1.4.46 jack_session_callback(jack_session_event_t *ev, void *arg)	64
11.1.4.47 create_lash_driver(perform &p, int argc, char **argv)	64
11.1.4.48 lash_driver()	65
11.1.4.49 delete_lash_driver()	65
11.1.4.50 output_thread_func(void *p)	65
11.1.4.51 min(long a, long b)	65
11.1.4.52 font_render()	65
11.1.4.53 adjustment_dummy()	66
Variable Documentation	66
11.1.5.1 c_controller_names	66
11.1.5.2 EVENT_ANY	66
11.1.5.3 EVENT_MIDI_SYSEX	66

11.1.5

viii CONTENTS

		11.1.5.4 EVENT_NULL_CHANNEL	. 66
		11.1.5.5 c_midibus_output_size	. 67
		11.1.5.6 c_midibus	. 67
		11.1.5.7 c_midi_track_ctrl	. 67
		11.1.5.8 c_scales_policy	. 68
		11.1.5.9 c_scales_transpose_up	. 68
		11.1.5.10 c_scales_transpose_dn_neg	. 68
		11.1.5.11 c_chord_text	. 69
		11.1.5.12 c_max_instruments	. 69
		11.1.5.13 versiontext	. 69
		11.1.5.14 long_options	. 69
		11.1.5.15 s_global_lash_driver	. 69
		11.1.5.16 c_mainwid_x	. 69
		11.1.5.17 c_select_all_notes	. 69
12 Da	ıta Struct	cure Documentation	71
		::AbstractPerfInput Class Reference	
		::automutex Class Reference	
		Detailed Description	. 72
12	.3 seq64	Detailed Description	
12	•	::click Class Reference	. 72
12	12.3.1	::click Class Reference	. 72 . 73
12	12.3.1	Detailed Description Constructor & Destructor Documentation	. 72 . 73 . 73
12	12.3.1	::click Class Reference	. 72 . 73 . 73
12	12.3.1	Detailed Description Constructor & Destructor Documentation	. 72 . 73 . 73 . 73
12	12.3.1	Detailed Description Constructor & Destructor Documentation 12.3.2.1 click() 12.3.2.2 click(int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SEQ64_NO_MASK)	. 72 . 73 . 73 . 73 . 74
12	12.3.1	Detailed Description Constructor & Destructor Documentation 12.3.2.1 click() 12.3.2.2 click(int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SEQ64_NO_MASK) 12.3.2.3 click(const click &rhs)	. 72 . 73 . 73 . 73 . 74
12	12.3.1 12.3.2 12.3.3	Detailed Description Constructor & Destructor Documentation	. 72 . 73 . 73 . 73 . 74 . 74
12	12.3.1 12.3.2 12.3.3	Detailed Description Constructor & Destructor Documentation	. 72 . 73 . 73 . 73 . 74 . 74 . 74
12	12.3.1 12.3.2 12.3.3	Detailed Description Constructor & Destructor Documentation 12.3.2.1 click() 12.3.2.2 click(int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SEQ64_NO_MASK) 12.3.2.3 click(const click &rhs) Member Function Documentation 12.3.3.1 operator=(const click &rhs) Field Documentation	. 72 . 73 . 73 . 74 . 74 . 74

CONTENTS

	12.3.4.3 m_button	74
	12.3.4.4 m_modifier	74
12.4 seq64::	condition_var Class Reference	75
12.4.1	Detailed Description	76
12.4.2	Field Documentation	76
	12.4.2.1 cond	76
12.5 seq64::	configfile Class Reference	76
12.5.1	Constructor & Destructor Documentation	77
	12.5.1.1 configfile(const std::string &name)	77
12.5.2	Member Function Documentation	77
	12.5.2.1 next_data_line(std::ifstream &file)	77
	12.5.2.2 line_after(std::ifstream &file, const std::string &tag)	78
12.5.3	Field Documentation	78
	12.5.3.1 m_line	78
12.6 seq64::	editable_event Class Reference	78
12.6.1	Detailed Description	82
12.6.2	Member Enumeration Documentation	82
	12.6.2.1 category_t	82
	12.6.2.2 timestamp_format_t	82
12.6.3	Constructor & Destructor Documentation	83
	12.6.3.1 editable_event(const editable_events &parent)	83
	12.6.3.2 editable_event(const editable_events &parent, const event &ev)	83
	12.6.3.3 editable_event(const editable_event &rhs)	83
12.6.4	Member Function Documentation	83
	12.6.4.1 value_to_name(midibyte value, category_t cat)	83
	12.6.4.2 name_to_value(const std::string &name, category_t cat)	83
	12.6.4.3 category(category_t c)	84
	12.6.4.4 category(const std::string &cs)	84
	12.6.4.5 timestamp(midipulse ts)	84
	12.6.4.6 timestamp(const std::string &ts_string)	84

CONTENTS

		12.6.4.7 tir	me_as_measures()	84
		12.6.4.8 tir	me_as_minutes()	85
			et_status_from_string(const std::string &ts, const std::string &s, const std::string &d0, const std::string &sd1)	85
		12.6.4.10 fo	rmat_timestamp()	85
		12.6.4.11 st	ock_event_string()	85
		12.6.4.12 ar	nalyze()	85
	12.6.5	Field Docum	nentation	86
		12.6.5.1 sr	m_category_names	86
		12.6.5.2 sr	m_channel_event_names	86
		12.6.5.3 sr	m_system_event_names	86
		12.6.5.4 sr	m_meta_event_names	86
		12.6.5.5 sr	m_prop_event_names	86
		12.6.5.6 sr	m_category_arrays	86
		12.6.5.7 m	_parent	87
		12.6.5.8 m	_category	87
		12.6.5.9 m	_format_timestamp	87
		12.6.5.10 m	_name_status	87
		12.6.5.11 m	_name_meta	87
12.7	seq64::	editable_eve	nts Class Reference	87
	12.7.1	Member Typ	pedef Documentation	89
		12.7.1.1 Ke	ey	89
	12.7.2	Constructor	& Destructor Documentation	89
		12.7.2.1 ed	ditable_events(sequence &seq, int bpm)	89
		12.7.2.2 ed	ditable_events(const editable_events &rhs)	89
	12.7.3	Member Fur	nction Documentation	89
		12.7.3.1 op	perator=(const editable_events &rhs)	89
		12.7.3.2 lo	ad_events()	89
		12.7.3.3 sa	ave_events()	90
		12.7.3.4 co	ount() const	90
		12.7.3.5 ac	dd(const event &e)	90

CONTENTS xi

		12.7.3.6	add(const editable_event &e)	90
	12.7.4	Field Doc	umentation	91
		12.7.4.1	m_current_event	91
		12.7.4.2	m_sequence	91
		12.7.4.3	m_midi_parameters	91
12.8	seq64:	event Clas	ss Reference	91
	12.8.1	Detailed I	Description	95
	12.8.2	Construct	or & Destructor Documentation	96
		12.8.2.1	event(const event &rhs)	96
		12.8.2.2	\sim event()	96
	12.8.3	Member F	Function Documentation	96
		12.8.3.1	operator=(const event &rhs)	96
		12.8.3.2	operator<(const event &rhsevent) const	96
		12.8.3.3	check_channel(int channel) const	97
		12.8.3.4	is_channel_msg(midibyte m)	97
		12.8.3.5	is_one_byte_msg(midibyte m)	98
		12.8.3.6	is_two_byte_msg(midibyte m)	98
		12.8.3.7	is_note_msg(midibyte m)	98
		12.8.3.8	is_desired_cc_or_not_cc(midibyte m, midibyte cc, midibyte datum)	98
		12.8.3.9	mod_timestamp(midipulse a_mod)	99
		12.8.3.10	set_status(midibyte status)	99
		12.8.3.11	set_status(midibyte eventcode, midibyte channel)	99
		12.8.3.12	set_channel(midibyte channel)	100
		12.8.3.13	set_data(midibyte d1)	100
		12.8.3.14	set_data(midibyte d1, midibyte d2)	100
		12.8.3.15	get_data(midibyte &d0, midibyte &d1) const	100
		12.8.3.16	append_sysex(midibyte *data, int len)	100
		12.8.3.17	get_rank() const	101
	12.8.4	Field Doc	umentation	101
		12.8.4.1	m_status	101

xii CONTENTS

12.8.4.2 m_channel
12.8.4.3 m_data
12.8.4.4 m_sysex
12.8.4.5 m_has_link
12.9 seq64::event_list::event_key Class Reference
12.9.1 Detailed Description
12.9.2 Constructor & Destructor Documentation
12.9.2.1 event_key(midipulse tstamp, int rank)
12.9.2.2 event_key(const event &e)
12.9.3 Member Function Documentation
12.9.3.1 operator<(const event_key &rhs) const
12.9.4 Field Documentation
12.9.4.1 m_timestamp
12.9.4.2 m_rank
12.10seq64::event_list Class Reference
12.10.1 Detailed Description
12.10.2 Constructor & Destructor Documentation
12.10.2.1 event_list(const event_list &a_rhs)
12.10.3 Member Function Documentation
12.10.3.1 operator=(const event_list &a_rhs)
12.10.3.2 count() const
12.10.3.3 add(const event &e, bool postsort=true)
12.10.3.4 unmodify()
12.10.3.5 remove(iterator ie)
12.10.3.6 clear()
12.10.3.7 merge(event_list ⪙, bool presort=true)
12.10.3.8 link_new()
12.10.3.9 verify_and_link(midipulse slength)
12.10.3.10mark_out_of_range(midipulse slength)
12.10.3.11mark_all()

CONTENTS xiii

12.10.3.12any_selected_notes() const
12.10.3.13count_selected_events(midibyte status, midibyte cc) const
12.10.4 Field Documentation
12.10.4.1 m_is_modified
12.11 seq64::eventedit Class Reference
12.11.1 Constructor & Destructor Documentation
12.11.1.1 eventedit(perform &p, sequence &seq)
12.11.1.2 ~eventedit()
12.11.2 Member Function Documentation
12.11.2.1 set_seq_title(const std::string &title)
12.11.2.2 set_seq_time_sig(const std::string &sig)
12.11.2.3 set_seq_ppqn(const std::string &p)
12.11.2.4 set_event_category(const std::string &c)
12.11.2.5 set_event_timestamp(const std::string &ts)
12.11.2.6 set_event_name(const std::string &n)
12.11.2.7 set_event_data_0(const std::string &d)
12.11.2.8 set_event_data_1(const std::string &d)
12.11.2.9 set_dirty(bool flag=true)
12.11.2.10v_adjustment(int value)
12.11.2.11v_adjustment(int value, int lower, int upper)
12.11.2.12handle_insert()
12.11.2.13handle_modify()
12.11.2.14handle_save()
12.11.2.15on_key_press_event(GdkEventKey *ev)
12.11.2.16on_delete_event(GdkEventAny *event)
12.12seq64::eventslots Class Reference
12.12.1 Member Function Documentation
12.12.1.1 load_events()
12.12.1.2 set_current_event(const_editable_events::iterator_ei, int_index, bool_full_const_editable_events::iterator_ei, int_index, bool_full_const_editable_events::
redraw=true)
12.12.1.3 Insert evenitconsteurable event &edev)

XIV

12.12.1.4 insert_event(const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)	121
12.12.1.5 delete_current_event()	121
12.12.1.6 modify_current_event(const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)	122
12.12.1.7 save_events()	122
12.12.1.8 select_event(int event_index=SEQ64_NULL_EVENT_INDEX, bool full_← redraw=true)	123
12.12.1.9 set_text(const_std::string &evcategory, const_std::string &evtimestamp, const_std::string &evdata0, const_std::string &evdata1)	123
12.12.1.1@onvert_y(int y)	123
12.12.1.11draw_event(editable_events::iterator ei, int index)	124
12.12.1.12draw_events()	124
12.12.1.13change_vert()	124
12.12.1.14page_movement(int new_value)	124
12.12.1.15page_topper(editable_events::iterator newcurrent)	125
12.12.1.16decrement_top()	125
12.12.1.17increment_top()	125
12.12.1.18decrement_current()	125
12.12.1.19ncrement_current()	125
12.12.1.20decrement_bottom()	126
12.12.1.21increment_bottom()	126
12.12.1.22on_realize()	126
12.12.1.23on_expose_event(GdkEventExpose *ev)	126
12.12.1.24on_focus_in_event(GdkEventFocus *ev)	126
12.12.1.25on_size_allocate(Gtk::Allocation &)	126
12.12.1.26on_move_up()	126
12.12.1.27on_move_down()	126
12.12.2 Field Documentation	127
12.12.2.1 m_slots_chars	127
12.12.2.2 m_char_w	127
12.12.2.3 m_setbox_w	127

CONTENTS xv

12.12.2.4 m_slots_y	127
12.12.2.5 m_xy_offset	127
12.12.2.6 m_top_index	127
12.12.2.7 m_current_index	127
12.13seq64::font Class Reference	127
12.13.1 Member Enumeration Documentation	129
12.13.1.1 Color	129
12.13.2 Member Function Documentation	129
12.13.2.1 init(Glib::RefPtr< Gdk::Window > windo)	129
$12.13.2.2\ render_string_on_drawable (Glib::RefPtr < Gdk::GC > m_gc,\ int\ x,\ int\ y,\ Glib:: \hookleftarrow RefPtr < Gdk::Drawable > drawable,\ const\ char\ *str,\ font::Color\ col)\ const \ . \ . \ .$	129
12.13.3 Field Documentation	129
12.13.3.1 m_font_w	130
12.13.3.2 m_font_h	130
12.13.3.3 m_pixmap	130
12.13.3.4 m_black_pixmap	130
12.13.3.5 m_white_pixmap	130
12.13.3.6 m_b_on_y_pixmap	130
12.13.3.7 m_y_on_b_pixmap	130
12.13.3.8 m_b_on_c_pixmap	130
12.13.3.9 m_c_on_b_pixmap	130
12.13.3.10m_clip_mask	131
12.14seq64::gui_assistant Class Reference	131
12.14.1 Detailed Description	132
12.14.2 Constructor & Destructor Documentation	132
12.14.2.1 gui_assistant(keys_perform &kp)	132
12.15seq64::gui_assistant_gtk2 Class Reference	132
12.15.1 Member Function Documentation	133
12.15.1.1 lash_timeout_connect(lash *lashobject)	133
12.15.1.2 jack_idle_connect(jack_assistant &jack)	134
12.15.2 Field Documentation	134

xvi CONTENTS

12.15.2.1 sm_internal_keys	134
12.16seq64::gui_drawingarea_gtk2 Class Reference	134
12.16.1 Detailed Description	137
12.16.2 Member Function Documentation	137
12.16.2.1 force_draw()	137
12.16.2.2 clear_window()	137
12.16.2.3 set_line(Gdk::LineStyle Is, int width=1)	137
12.16.2.4 draw_line(int x1, int y1, int x2, int y2)	137
12.16.2.5 draw_line(const Color &c, int x1, int y1, int x2, int y2)	138
12.16.2.6 draw_line_on_pixmap(int x1, int y1, int x2, int y2)	138
12.16.2.7 draw_line_on_pixmap(const Color &c, int x1, int y1, int x2, int y2)	138
$12.16.2.8 \ draw_line(Glib::RefPtr < Gdk::Pixmap > \&pixmap, int x1, int y1, int x2, int y2) \ . \ .$	138
12.16.2.9 draw_line(Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x1, int y1, int x2, int y2)	139
12.16.2.10draw_line(Glib::RefPtr< Gdk::Drawable > &drawable, int x1, int y1, int x2, int y2)	139
12.16.2.11draw_line(Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x1, int y1, int x2, int y2)	139
12.16.2.12render_string(int x, int y, const std::string &s, font::Color color)	139
12.16.2.13render_string_on_pixmap(int x, int y, const std::string &s, font::Color color)	139
12.16.2.14draw_rectangle(int x, int y, int lx, int ly, bool fill=true)	140
12.16.2.15draw_rectangle(const Color &c, int x, int y, int lx, int ly, bool fill=true)	140
12.16.2.16draw_rectangle(Glib::RefPtr< Gdk::Drawable > &drawable, int x, int y, int lx, int ly, bool fill=true)	140
12.16.2.17draw_rectangle(Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x, int y, int lx, int ly, bool fill=true)	141
12.16.2.1&draw_rectangle(Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, int lx, int ly, bool fill=true)	141
12.16.2.19draw_rectangle(Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x, int y, int lx, int ly, bool fill=true)	141
12.16.2.20draw_rectangle_on_pixmap(int x, int y, int lx, int ly, bool fill=true)	142
12.16.2.21draw_rectangle_on_pixmap(const Color &c, int x, int y, int lx, int ly, bool fill=true)	142
12.16.2.22draw_normal_rectangle_on_pixmap(int x, int y, int lx, int ly, bool fill=true)	142
12.16.2.23scroll_adjust(Gtk::Adjustment &adjust, double step)	142

CONTENTS xvii

12.16.2.24on_realize()	143
12.16.3 Field Documentation	143
12.16.3.1 m_window	143
12.16.3.2 m_pixmap	143
12.16.3.3 m_background	143
12.16.3.4 m_foreground	143
12.16.3.5 m_mainperf	143
12.16.3.6 m_window_x	143
12.16.3.7 m_drop_x	143
12.17seq64::gui_palette_gtk2 Class Reference	144
12.17.1 Detailed Description	145
12.17.2 Constructor & Destructor Documentation	145
12.17.2.1 gui_palette_gtk2()	145
12.17.3 Member Function Documentation	145
12.17.3.1 line_color() const	145
12.17.3.2 progress_color() const	145
12.18seq64::gui_window_gtk2 Class Reference	146
12.18.1 Constructor & Destructor Documentation	147
12.18.1.1 gui_window_gtk2(perform &p, int window_x=0, int window_y=0)	147
12.18.2 Member Function Documentation	147
12.18.2.1 scroll_adjust(Gtk::Adjustment &adjust, double step)	147
12.18.3 Field Documentation	147
12.18.3.1 m_window_x	147
12.18.3.2 m_redraw_period_ms	148
12.19seq64::jack_assistant Class Reference	148
12.19.1 Constructor & Destructor Documentation	150
12.19.1.1 jack_assistant(perform &parent, int bpminute=SEQ64_DEFAULT_BPM, int ppqn=SEQ64_USE_DEFAULT_PPQN, int bpm=SEQ64_DEFAULT_BEAT← S_PER_MEASURE, int beatwidth=SEQ64_DEFAULT_BEAT_WIDTH)	150
12.19.1.2 ~jack_assistant()	150
12.19.2 Member Function Documentation	150

xviii CONTENTS

12.19.2.1 set_beats_per_minute(int bpminute)	150
12.19.2.2 init()	150
12.19.2.3 deinit()	151
12.19.2.4 session_event()	151
12.19.2.5 start()	151
12.19.2.6 stop()	151
12.19.2.7 position(bool to_left_tick, bool relocate=false)	151
12.19.2.8 output(jack_scratchpad &pad)	152
12.19.2.9 set_ppqn(int ppqn)	152
12.19.2.10nfo_message(const std::string &msg)	153
12.19.2.11error_message(const std::string &msg)	153
12.19.2.12client_open(const std::string &clientname)	153
12.19.2.13show_statuses(unsigned bits)	154
12.19.2.14show_position(const jack_position_t &pos) const	154
12.19.2.15sync(jack_transport_state_t state=(jack_transport_state_t)(-1))	155
12.19.2.16set_position(midipulse currenttick)	155
12.19.3 Friends And Related Function Documentation	155
12.19.3.1 jack_shutdown_callback	155
12.19.3.2 jack_sync_callback	156
12.19.3.3 jack_timebase_callback	156
12.19.3.4 jack_session_callback	157
12.19.4 Field Documentation	157
12.19.4.1 sm_status_pairs	157
12.20seq64::jack_scratchpad Class Reference	157
12.20.1 Detailed Description	157
12.21seq64::keybindentry Class Reference	157
12.21.1 Member Enumeration Documentation	158
12.21.1.1 type	158
12.21.2 Constructor & Destructor Documentation	158
12.21.2.1 keybindentry(type t, unsigned int *location_to_write=nullptr, perform *p=nullptr, long s=0)	158

CONTENTS xix

12.21.3 Member Function Documentation	159
12.21.3.1 set(unsigned int val)	159
12.21.3.2 on_key_press_event(GdkEventKey *event)	159
12.21.4 Field Documentation	159
12.21.4.1 m_key	159
12.22seq64::keys_perform Class Reference	159
12.22.1 Detailed Description	161
12.22.2 Constructor & Destructor Documentation	161
12.22.2.1 ~keys_perform()	161
12.22.3 Member Function Documentation	161
12.22.3.1 set_keys(const keys_perform_transfer &kpt)	161
12.22.3.2 get_keys(keys_perform_transfer &kpt)	162
12.22.3.3 show_ui_sequence_key() const	162
12.22.3.4 show_ui_sequence_number() const	162
12.22.3.5 key_name(unsigned int key) const	162
12.22.3.6 set_all_key_events()	162
12.22.3.7 set_all_key_groups()	162
12.22.3.8 set_key_event(unsigned int keycode, long sequence_slot)	163
12.22.3.9 set_key_group(unsigned int keycode, long group_slot)	163
12.22.4 Field Documentation	163
12.22.4.1 m_key_show_ui_sequence_number	163
12.22.4.2 m_key_bpm_up	163
12.23seq64::keys_perform_gtk2 Class Reference	163
12.23.1 Detailed Description	165
12.23.2 Constructor & Destructor Documentation	165
12.23.2.1 ~keys_perform_gtk2()	165
12.23.3 Member Function Documentation	165
12.23.3.1 key_name(unsigned int key) const	165
12.23.3.2 set_all_key_events()	165
12.23.3.3 set_all_key_groups()	165

CONTENTS

12.24seq64::keys_perform_transfer Struct Reference	65
12.25seq64::keystroke Class Reference	66
12.25.1 Detailed Description	66
12.25.2 Constructor & Destructor Documentation	66
12.25.2.1 keystroke(unsigned int key, bool press=SEQ64_KEYSTROKE_PRESS, int modkey=int(SEQ64_NO_MASK))	66
12.25.2.2 keystroke(const keystroke &rhs)	67
12.25.3 Member Function Documentation	67
12.25.3.1 operator=(const keystroke &rhs)	67
12.25.3.2 is_letter(int ch=SEQ64_KEYSTROKE_BAD_VALUE) const	67
12.25.4 Field Documentation	67
12.25.4.1 m_is_press	67
12.25.4.2 m_key	68
12.25.4.3 m_modifier	68
12.26seq64::lash Class Reference	68
12.26.1 Detailed Description	68
12.26.2 Constructor & Destructor Documentation	68
12.26.2.1 lash(perform &p, int argc, char **argv)	68
12.26.3 Member Function Documentation	69
12.26.3.1 set_alsa_client_id(int id)	69
12.26.3.2 process_events()	69
12.26.3.3 init()	69
12.26.3.4 handle_event(lash_event_t *conf)	69
12.26.3.5 handle_config(lash_config_t *conf)	69
12.27seq64::maintime Class Reference	69
12.27.1 Detailed Description	71
12.27.2 Constructor & Destructor Documentation	71
12.27.2.1 maintime(perform &p, int ppqn=SEQ64_USE_DEFAULT_PPQN)	71
12.27.3 Member Function Documentation	72
12.27.3.1 idle_progress(midipulse ticks)	72
12.27.3.2 on_realize()	73

CONTENTS xxi

12.27.3.3 on_expose_event(GdkEventExpose *ev)	173
12.27.4 Field Documentation	173
12.27.4.1 m_beat_width	173
12.27.4.2 m_bar_width	173
12.27.4.3 m_box_width	173
12.27.4.4 m_box_height	173
12.27.4.5 m_flash_width	173
12.27.4.6 m_flash_height	174
12.27.4.7 m_tick	174
12.27.4.8 m_ppqn	174
12.28seq64::mainwid Class Reference	174
12.28.1 Constructor & Destructor Documentation	177
12.28.1.1 mainwid(perform &p)	177
12.28.2 Member Function Documentation	177
12.28.2.1 set_screenset(int ss)	177
12.28.2.2 redraw(int seq)	177
12.28.2.3 draw_marker_on_sequence(int seq, int tick)	178
12.28.2.4 update_sequences_on_window()	178
12.28.2.5 update_markers(int ticks)	178
12.28.2.6 valid_sequence(int seq)	178
12.28.2.7 draw_sequence_on_pixmap(int seq)	178
12.28.2.8 draw_sequences_on_pixmap()	179
12.28.2.9 draw_sequence_pixmap_on_window(int seq)	179
12.28.2.10seq_from_xy(int x, int y)	179
12.28.2.11timeout()	179
12.28.2.12calculate_base_sizes(int seq, int &basex, int &basey)	180
12.28.2.13on_realize()	180
12.28.2.14on_expose_event(GdkEventExpose *ev)	180
12.28.2.15on_button_press_event(GdkEventButton *ev)	180
12.28.2.16on_button_release_event(GdkEventButton *ev)	181

xxii CONTENTS

12.28.2.17on_motion_notify_event(GdkEventMotion *p0)	181
12.28.2.1&n_focus_in_event(GdkEventFocus *)	181
12.28.2.19on_focus_out_event(GdkEventFocus *)	182
12.28.3 Field Documentation	182
12.28.3.1 m_moving_seq	182
12.28.3.2 m_button_down	182
12.28.3.3 m_screenset_slots	182
12.28.3.4 m_screenset_offset	182
12.29seq64::mainwnd Class Reference	182
12.29.1 Constructor & Destructor Documentation	186
12.29.1.1 mainwnd(perform &a_p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAU←	100
LT_PPQN)	
12.29.2 Member Function Documentation	187
12.29.2.1 open_file(const std::string &)	187
12.29.2.2 ppqn(int ppqn)	187
12.29.2.3 file_import_dialog()	187
12.29.2.4 about_dialog()	188
12.29.2.5 adj_callback_ss()	188
12.29.2.6 adj_callback_bpm()	188
12.29.2.7 edit_callback_notepad()	188
12.29.2.8 timer_callback()	188
12.29.2.9 set_image(bool isrunning)	188
12.29.2.10start_playing()	189
12.29.2.11pause_playing()	189
12.29.2.12stop_playing()	189
12.29.2.13toggle_playing()	189
12.29.2.14open_performance_edit()	189
12.29.2.15open_performance_edit_2()	189
12.29.2.16update_window_title()	189
12.29.2.17new_file()	190
12.29.2.18save_file()	190

CONTENTS xxiii

190
190
190
190
190
191
191
191
191
191
191
191
193
193
194
194
194
194
194 194
194
194 195
194 195 195
194 195 195
194 195 195 195
194 195 195 195 195
194 195 195 195 195 195
194 195 195 195 195 195 196
194 195 195 195 195 195 196

xxiv CONTENTS

12.30.2.15set_sequence_input(bool a_state, sequence *a_seq)	196
12.30.2.16sysex(event *a_event)	197
12.30.2.17port_start(int a_client, int a_port)	197
12.30.2.1&port_exit(int a_client, int a_port)	197
12.30.2.19play(bussbyte bus, event *a_e24, midibyte a_channel)	197
12.30.2.20set_clock(bussbyte bus, clock_e a_clock_type)	198
12.30.2.21get_clock(bussbyte bus)	198
12.30.2.22set_input(bussbyte bus, bool a_inputing)	198
12.30.2.23get_input(bussbyte bus)	198
12.30.3 Field Documentation	198
12.30.3.1 m_beats_per_minute	198
12.31seq64::midi_container Class Reference	199
12.31.1 Member Function Documentation	200
12.31.1.1 fill(int tracknumber)	200
12.31.1.2 put(midibyte b)=0	201
12.31.1.3 get()=0	201
12.31.1.4 position() const	201
12.31.1.5 add_variable(midipulse v)	201
12.31.1.6 add_long(midipulse x)	201
12.32seq64::midi_list Class Reference	202
12.32.1 Member Typedef Documentation	203
12.32.1.1 CharList	203
12.32.2 Member Function Documentation	203
12.32.2.1 put(midibyte b)	203
12.32.2.2 get()	203
12.33seq64::midi_measures Class Reference	203
12.33.1 Detailed Description	204
12.33.2 Field Documentation	204
12.33.2.1 m_divisions	204
12.34seq64::midi_splitter Class Reference	204

CONTENTS xxv

12.34.1 Detailed Description	205
12.34.2 Constructor & Destructor Documentation	205
12.34.2.1 midi_splitter(int ppqn=SEQ64_USE_DEFAULT_PPQN)	205
12.34.3 Member Function Documentation	206
12.34.3.1 increment(int channel)	206
12.34.3.2 split(perform &p, int screenset)	206
12.34.3.3 ppqn() const	206
12.34.3.4 split_channel(const sequence &main_seq, sequence *seq, int channel)	207
12.34.4 Field Documentation	207
12.34.4.1 m_smf0_channels_count	207
12.34.4.2 m_smf0_channels	207
12.34.4.3 m_smf0_seq_number	207
12.35seq64::midi_timing Class Reference	207
12.35.1 Detailed Description	208
12.35.2 Field Documentation	208
12.35.2.1 m_beats_per_minute	208
12.35.2.2 m_beats_per_measure	209
12.35.2.3 m_beat_width	209
12.35.2.4 m_ppqn	209
12.36seq64::midi_vector Class Reference	209
12.36.1 Member Function Documentation	210
12.36.1.1 put(midibyte b)	210
12.36.1.2 get()	210
12.37seq64::midibus Class Reference	210
12.37.1 Constructor & Destructor Documentation	212
12.37.1.1 midibus(int localclient, int destclient, int destport, snd_seq_t *seq, const char *client_name, const char *port_name, int id, int queue, int ppqn=SEQ64_U ← SE_DEFAULT_PPQN)	212
12.37.1.2 midibus(int localclient, snd_seq_t ∗seq, int id, int queue, int ppqn=SEQ64_US↔ E_DEFAULT_PPQN)	213
12.37.2 Member Function Documentation	213
12.37.2.1 init_out()	213

xxvi CONTENTS

12.37.2.2 init_in()	213
12.37.2.3 deinit_in()	213
12.37.2.4 init_out_sub()	214
12.37.2.5 init_in_sub()	214
12.37.2.6 play(event *e24, midibyte channel)	214
12.37.2.7 sysex(event *e24)	214
12.37.2.8 clock(midipulse tick)	214
12.37.2.9 continue_from(midipulse tick)	214
12.37.2.1@nit_clock(midipulse tick)	214
12.37.2.11set_input(bool inputing)	215
12.37.3 Field Documentation	215
12.37.3.1 m_clock_mod	215
12.38seq64::midifile Class Reference	215
12.38.1 Detailed Description	217
12.38.2 Constructor & Destructor Documentation	218
12.38.2.1 midifile(const std::string &name, int ppgn=SEQ64 USE DEFAULT PPQN, bool	
oldformat=false, bool globalbgs=true)	
	218
oldformat=false, bool globalbgs=true)	218 218
oldformat=false, bool globalbgs=true)	218218218
oldformat=false, bool globalbgs=true)	218218218219
oldformat=false, bool globalbgs=true)	218218218219219
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const	218218218219219220
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const 12.38.3.4 parse_smf_0(perform &p, int screenset)	218218219219220220
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const 12.38.3.4 parse_smf_0(perform &p, int screenset) 12.38.3.5 parse_smf_1(perform &p, int screenset, bool is_smf0=false)	218 218 219 219 220 220
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const 12.38.3.4 parse_smf_0(perform &p, int screenset) 12.38.3.5 parse_smf_1(perform &p, int screenset, bool is_smf0=false) 12.38.3.6 parse_prop_header(int file_size)	218 218 219 219 220 220 221
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const 12.38.3.4 parse_smf_0(perform &p, int screenset) 12.38.3.5 parse_smf_1(perform &p, int screenset, bool is_smf0=false) 12.38.3.6 parse_prop_header(int file_size) 12.38.3.7 parse_proprietary_track(perform &a_perf, int file_size)	218 218 219 219 220 220 221 222
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const 12.38.3.4 parse_smf_0(perform &p, int screenset) 12.38.3.5 parse_smf_1(perform &p, int screenset, bool is_smf0=false) 12.38.3.6 parse_prop_header(int file_size) 12.38.3.7 parse_proprietary_track(perform &a_perf, int file_size) 12.38.3.8 pow2(int logbase2)	218 218 219 219 220 220 221 222
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const 12.38.3.4 parse_smf_0(perform &p, int screenset) 12.38.3.5 parse_smf_1(perform &p, int screenset, bool is_smf0=false) 12.38.3.6 parse_prop_header(int file_size) 12.38.3.7 parse_proprietary_track(perform &a_perf, int file_size) 12.38.3.8 pow2(int logbase2) 12.38.3.9 checklen(midilong len, midibyte type)	218 218 219 219 220 220 221 222 222
oldformat=false, bool globalbgs=true) 12.38.3 Member Function Documentation 12.38.3.1 parse(perform &a_perf, int a_screen_set=0) 12.38.3.2 write(perform &a_perf) 12.38.3.3 ppqn() const 12.38.3.4 parse_smf_0(perform &p, int screenset) 12.38.3.5 parse_smf_1(perform &p, int screenset, bool is_smf0=false) 12.38.3.6 parse_prop_header(int file_size) 12.38.3.7 parse_proprietary_track(perform &a_perf, int file_size) 12.38.3.8 pow2(int logbase2) 12.38.3.9 checklen(midilong len, midibyte type) 12.38.3.10add_trigger(sequence &seq, midishort ppqn)	218 218 219 219 220 220 221 222 222 222

CONTENTS xxvii

12.38.3.14write_short(midishort value)	223
12.38.3.15read_byte_array(midibyte *b, int len)	223
12.38.3.16write_byte(midibyte c)	223
12.38.3.17write_varinum(midilong)	223
12.38.3.18write_track_name(const std::string &trackname)	224
12.38.3.19read_track_name()	224
12.38.3.20write_seq_number(midishort seqnum)	224
12.38.3.21read_seq_number()	224
12.38.3.22write_prop_header(midilong tag, long len)	224
12.38.3.23write_proprietary_track(perform &a_perf)	225
12.38.3.24varinum_size(long len) const	226
12.38.3.25prop_item_size(long datalen) const	226
12.38.3.26errdump(const std::string &msg)	226
12.38.3.27errdump(const std::string &msg, unsigned long p)	226
12.38.3.28s_sysex_special_id(midibyte ch)	227
12.38.4 Field Documentation	227
12.38.4.1 m_file_size	227
12.38.4.2 m_error_message	227
12.38.4.3 m_error_is_fatal	227
12.38.4.4 m_disable_reported	227
12.38.4.5 m_pos	227
12.38.4.6 m_data	227
12.38.4.7 m_char_list	227
12.38.4.8 m_new_format	228
12.38.4.9 m_smf0_splitter	228
12.39seq64::mutex Class Reference	228
12.39.1 Field Documentation	229
12.39.1.1 sm_recursive_mutex	229
12.40seq64::options Class Reference	229
12.40.1 Member Enumeration Documentation	230
12.40.1 Member Enumeration Documentation	230

xxviii CONTENTS

12.40.1.1 button	230
12.40.2 Field Documentation	230
12.40.2.1 m_notebook	230
12.41seq64::optionsfile Class Reference	230
12.41.1 Detailed Description	231
12.41.2 Member Function Documentation	232
12.41.2.1 parse(perform &perf)	232
12.41.2.2 write(const perform &perf)	233
12.42seq64::perfedit Class Reference	233
12.42.1 Detailed Description	236
12.42.2 Constructor & Destructor Documentation	236
12.42.2.1 perfedit(perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFA ↔ ULT_PPQN)	236
12.42.2.2 ~perfedit()	237
12.42.3 Member Function Documentation	237
12.42.3.1 init_before_show()	237
12.42.3.2 enqueue_draw(bool forward=true)	237
12.42.3.3 zoom_check(int z)	237
12.42.3.4 enregister_peer(perfedit *peer)	237
12.42.3.5 set_beats_per_bar(int bpm)	237
12.42.3.6 set_beat_width(int bw)	238
12.42.3.7 set_snap(int snap)	238
12.42.3.8 set_guides()	238
12.42.3.9 grow()	238
12.42.3.10expand()	238
12.42.3.11collapse()	238
12.42.3.12copy()	238
12.42.3.13undo()	239
12.42.3.14timeout()	239
12.42.3.15start_playing()	239
12.42.3.1@pause_playing()	239

CONTENTS xxix

12.42.3.17toggle_playing()	239
12.42.4 Field Documentation	239
12.42.4.1 m_bpm	239
12.42.4.2 m_bw	239
12.43seq64::perfnames Class Reference	240
12.43.1 Detailed Description	242
12.43.2 Constructor & Destructor Documentation	242
12.43.2.1 perfnames(perform &p, perfedit &parent, Gtk::Adjustment &vadjust)	242
12.43.3 Member Function Documentation	242
12.43.3.1 enqueue_draw()	242
12.43.3.2 draw_sequence(int sequence)	242
12.43.3.3 on_realize()	242
12.43.3.4 on_expose_event(GdkEventExpose *ev)	242
12.43.3.5 on_size_allocate(Gtk::Allocation &)	242
12.43.4 Field Documentation	242
12.43.4.1 m_parent	242
12.43.4.2 m_names_chars	243
12.43.4.3 m_char_w	243
12.43.4.4 m_setbox_w	243
12.43.4.5 m_namebox_w	243
12.43.4.6 m_names_y	243
12.43.4.7 m_xy_offset	243
12.44seq64::perform Class Reference	243
12.44.1 Detailed Description	251
12.44.2 Constructor & Destructor Documentation	251
12.44.2.1 perform(gui_assistant &mygui, int ppqn=SEQ64_USE_DEFAULT_PPQN)	251
12.44.2.2 ~perform()	252
12.44.3 Member Function Documentation	252
12.44.3.1 modify()	252
12.44.3.2 sequence_count() const	252

CONTENTS

12.44.3.3 clear_all()
12.44.3.4 launch(int ppqn)
12.44.3.5 new_sequence(int seq)
12.44.3.6 add_sequence(sequence *seq, int perf)
12.44.3.7 delete_sequence(int seq)
12.44.3.8 clear_sequence_triggers(int seq)
12.44.3.9 finish()
12.44.3.10set_left_tick(midipulse tick, bool setstart=true)
12.44.3.11get_max_tick() const
12.44.3.12set_right_tick(midipulse tick, bool setstart=true)
12.44.3.13move_triggers(bool direction)
12.44.3.14copy_triggers()
12.44.3.15push_trigger_undo()
12.44.3.16get_max_trigger()
12.44.3.17midi_control_toggle(int seq)
12.44.3.18midi_control_on(int seq)
12.44.3.19midi_control_off(int seq)
12.44.3.20handle_midi_control(int control, bool state)
12.44.3.21get_screen_set_notepad(int screen_set) const
12.44.3.22set_screen_set_notepad(int screenset, const std::string ¬e)
12.44.3.23set_screenset(int ss)
12.44.3.24set_playing_screenset()
12.44.3.25select_group_mute(int g_mute)
12.44.3.26unset_mode_group_learn()
12.44.3.27select_mute_group(int group)
12.44.3.28start(bool state)
12.44.3.29stop()
12.44.3.30position_jack(bool state)
12.44.3.31all_notes_off()
12.44.3.32set_active(int seq, bool active)

CONTENTS xxxi

12.44.3.33set_was_active(int seq)
12.44.3.34is_dirty_main(int seq)
12.44.3.35s_dirty_edit(int seq)
12.44.3.36s_dirty_perf(int seq)
12.44.3.37/s_dirty_names(int seq)
12.44.3.38s_active(int seq) const
12.44.3.39get_sequence(int seq)
12.44.3.40reset_sequences(bool pause=false)
12.44.3.41play(midipulse tick)
12.44.3.42set_orig_ticks(midipulse tick)
12.44.3.43set_beats_per_minute(int bpm)
12.44.3.44set_sequence_control_status(int status)
12.44.3.45unset_sequence_control_status(int status)
12.44.3.46sequence_playing_on(int seq)
12.44.3.47sequence_playing_off(int seq)
12.44.3.48set_group_mute_state(int g_track, bool mute_state)
12.44.3.49get_group_mute_state(int g_track)
12.44.3.5\(\text{Output_func}\)\() 261
12.44.3.51set_offset(int offset)
12.44.3.52save_playing_state()
12.44.3.53show_ui_sequence_key() const
12.44.3.54show_ui_sequence_number() const
12.44.3.55ookup_keyevent_key(long seqnum)
12.44.3.56start_playing(bool songmode=false)
12.44.3.57pause_playing()
12.44.3.5⊤_playing()
12.44.3.59start_key(bool songmode=false)
12.44.3.60pause_key(bool songmode=false)
12.44.3.61stop_key()
12.44.3.62decrement_beats_per_minute()

xxxii CONTENTS

12.44.3.63ncrement_beats_per_minute()	. 264
12.44.3.64highlight(const sequence &seq) const	. 264
12.44.3.65sequence_label(const sequence &seq)	. 264
12.44.3.66set_input_bus(int bus, bool input_active)	. 264
12.44.3.67mainwnd_key_event(const keystroke &k)	. 265
12.44.3.6&perfroll_key_event(const keystroke &k, int drop_sequence)	. 265
12.44.3.69playback_key_event(const keystroke &k, bool songmode=false)	. 265
12.44.3.70aunch_input_thread()	. 265
12.44.3.71launch_output_thread()	. 266
12.44.3.72nit_jack()	. 266
12.44.3.73deinit_jack()	. 266
12.44.3.74seq_in_playing_screen(int seq)	. 266
12.44.3.75s_midi_control_valid(int seq) const	. 266
12.44.3.76s_screenset_valid(int screenset) const	. 266
12.44.3.77is_seq_valid(int seq) const	. 267
12.44.3.78s_mseq_valid(int seq) const	. 267
12.44.3.79nstall_sequence(sequence *seq, int seqnum)	. 267
12.44.3.8űnner_start(bool state)	. 268
12.44.3.81inner_stop()	. 268
12.44.3.82clamp_track(int track) const	. 268
12.44.3.83set_key_event(unsigned int keycode, long sequence_slot)	. 268
12.44.3.84set_key_group(unsigned int keycode, long group_slot)	. 269
12.44.4 Friends And Related Function Documentation	. 269
12.44.4.1 jack_sync_callback	. 269
12.44.5 Field Documentation	. 269
12.44.5.1 sm_mc_dummy	. 269
12.44.5.2 m_playscreen_offset	. 269
12.44.5.3 m_seqs	. 269
12.44.5.4 m_playback_mode	. 270
12.44.5.5 m_beats_per_bar	. 270

CONTENTS xxxiii

1	I2.44.5.6 m_beat_width	270
1	12.44.5.7 m_one_measure	270
1	12.44.5.8 m_left_tick	270
1	12.44.5.9 m_right_tick	270
1	12.44.5.10m_starting_tick	270
1	12.44.5.11m_tick	270
1	12.44.5.12m_seqs_in_set	270
1	12.44.5.13m_max_sets	271
1	12.44.5.14m_sequence_count	271
1	12.44.5.15m_sequence_max	271
1	12.44.5.16m_is_modified	271
12.45seq64::p	erformcallback Struct Reference	271
12.45.1 [Detailed Description	272
12.46seq64::p	erfroll Class Reference	272
12.46.1 (Constructor & Destructor Documentation	275
1	12.46.1.1 ~perfroll()	275
12.46.2 N	Member Function Documentation	276
1	12.46.2.1 set_guides(int snap, int measure, int beat)	276
1	12.46.2.2 update_sizes()	276
1	12.46.2.3 init_before_show()	276
1	12.46.2.4 fill_background_pixmap()	276
1	12.46.2.5 draw_progress()	277
1	12.46.2.6 set_ppqn(int ppqn)	277
1	12.46.2.7 convert_xy(int x, int y, midipulse &ticks, int &seq)	277
1	12.46.2.8 convert_x(int x, midipulse &ticks)	277
1	12.46.2.9 snap_x(int &x)	277
1	12.46.2.10draw_sequence_on(int seqnum)	278
1	12.46.2.11draw_drawable_row(long y)	278
1	12.46.2.12enqueue_draw()	278
1	12.46.2.13set_zoom(int z)	278

CONTENTS

12.46.2.14on_realize()	278
12.46.2.15on_expose_event(GdkEventExpose *ev)	278
12.46.2.16on_button_press_event(GdkEventButton *ev)	278
12.46.2.17on_button_release_event(GdkEventButton *ev)	278
12.46.2.1&n_key_press_event(GdkEventKey *ev)	279
12.46.3 Friends And Related Function Documentation	279
12.46.3.1 FruityPerfInput	279
12.46.4 Field Documentation	279
12.46.4.1 m_parent	279
12.46.4.2 m_h_page_increment	279
12.46.4.3 m_v_page_increment	279
12.46.4.4 m_fruity_interaction	279
12.47seq64::perftime Class Reference	280
12.47.1 Constructor & Destructor Documentation	282
12.47.1.1 perftime(perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, int ppqn=S↔ EQ64_USE_DEFAULT_PPQN)	282
12.47.2 Member Function Documentation	282
12.47.2.1 set_guides(int snap, int measure)	
12.47.2.1 set_guides(int snap, int measure)	282
	282 283
12.47.2.2 enqueue_draw()	282 283 283
12.47.2.2 enqueue_draw()	282 283 283 283
12.47.2.2 enqueue_draw()	282 283 283 283 283
12.47.2.2 enqueue_draw()	282 283 283 283 283 283
12.47.2.2 enqueue_draw()	282 283 283 283 283 283
12.47.2.2 enqueue_draw()	282 283 283 283 283 283 283
12.47.2.2 enqueue_draw() 12.47.2.3 on_realize() 12.47.2.4 on_expose_event(GdkEventExpose *ev) 12.47.2.5 key_press_event(GdkEventKey *ev) 12.47.3 Field Documentation 12.47.3.1 m_parent 12.47.3.2 m_measure_length	282 283 283 283 283 283 283 283 284
12.47.2.2 enqueue_draw() 12.47.2.3 on_realize() 12.47.2.4 on_expose_event(GdkEventExpose *ev) 12.47.2.5 key_press_event(GdkEventKey *ev) 12.47.3 Field Documentation 12.47.3.1 m_parent 12.47.3.2 m_measure_length 12.47.3.3 m_left_marker_tick	282 283 283 283 283 283 283 284 284
12.47.2.2 enqueue_draw() 12.47.2.3 on_realize() 12.47.2.4 on_expose_event(GdkEventExpose *ev) 12.47.2.5 key_press_event(GdkEventKey *ev) 12.47.3 Field Documentation 12.47.3.1 m_parent 12.47.3.2 m_measure_length 12.47.3.3 m_left_marker_tick 12.47.3.4 m_right_marker_tick	282 283 283 283 283 283 283 284 284 284
12.47.2.2 enqueue_draw() 12.47.2.3 on_realize() 12.47.2.4 on_expose_event(GdkEventExpose *ev) 12.47.2.5 key_press_event(GdkEventKey *ev) 12.47.3 Field Documentation 12.47.3.1 m_parent 12.47.3.2 m_measure_length 12.47.3.3 m_left_marker_tick 12.47.3.4 m_right_marker_tick 12.48seq64::rc_settings Class Reference	282 283 283 283 283 283 284 284 284 284

CONTENTS XXXV

12.50seq64::gui_drawingarea_gtk2::rect Struct Reference	286
12.51seq64::Seq24PerfInput Class Reference	287
12.51.1 Member Function Documentation	288
12.51.1.1 on_button_press_event(GdkEventButton *a_ev, perfroll &roll)	288
12.51.1.2 on_button_release_event(GdkEventButton *a_ev, perfroll &roll)	288
12.51.1.3 on_motion_notify_event(GdkEventMotion *a_ev, perfroll &roll)	288
12.51.1.4 set_adding(bool a_adding, perfroll &roll)	288
12.51.1.5 handle_motion_key(bool is_left, perfroll &roll)	288
12.52seq64::Seq24SeqEventInput Struct Reference	289
12.52.1 Member Function Documentation	289
12.52.1.1 set_adding(bool a_adding, seqevent &ths)	289
12.52.1.2 on_button_press_event(GdkEventButton *a_ev, seqevent &ths)	289
12.52.1.3 on_button_release_event(GdkEventButton *a_ev, seqevent &ths)	290
12.52.1.4 on_motion_notify_event(GdkEventMotion *a_ev, seqevent &ths)	290
12.53seq64::Seq24SeqRollInput Class Reference	290
12.53.1 Member Function Documentation	290
12.53.1.1 set_adding(bool a_adding, seqroll &ths)	290
12.53.1.2 on_button_press_event(GdkEventButton *a_ev, seqroll &ths)	290
12.53.1.3 on_button_release_event(GdkEventButton *a_ev, seqroll &ths)	291
12.54seq64::seqdata Class Reference	291
12.54.1 Constructor & Destructor Documentation	294
12.54.1.1 seqdata(sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust)	294
12.54.2 Member Function Documentation	294
12.54.2.1 reset()	294
12.54.2.2 set_data_type(midibyte status, midibyte control)	294
12.54.2.3 idle_redraw()	294
12.54.2.4 update_sizes()	294
12.54.2.5 xy_to_rect(int x1, int y1, int x2, int y2, int ℞, int &ry, int &rw, int &rh)	294
12.54.2.6 draw_events_on(Glib::RefPtr< Gdk::Drawable > drawable)	294
12.54.2.7 change_horz()	295

xxxvi CONTENTS

12.54.2.8 on_realize()	295
12.54.2.9 on_expose_event(GdkEventExpose *ev)	295
12.54.2.10on_button_press_event(GdkEventButton *ev)	295
12.54.2.11on_button_release_event(GdkEventButton *ev)	295
12.54.2.12on_motion_notify_event(GdkEventMotion *ev)	295
12.54.2.13on_scroll_event(GdkEventScroll *ev)	296
12.54.3 Field Documentation	296
12.54.3.1 m_number_w	296
12.54.3.2 m_number_h	296
12.54.3.3 m_number_offset_y	296
12.55seq64::seqedit Class Reference	296
12.55.1 Detailed Description	300
12.55.2 Constructor & Destructor Documentation	301
12.55.2.1 seqedit(perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFA ← ULT_PPQN)	301
12.55.3 Member Function Documentation	301
12.55.3.1 set_zoom(int zoom)	301
12.55.3.2 set_snap(int snap)	301
12.55.3.3 set_note_length(int note_length)	301
12.55.3.4 horizontal_adjust(double step)	302
12.55.3.5 set_measures(int lim)	302
12.55.3.6 apply_length(int bpm, int bw, int measures)	302
12.55.3.7 get_measures()	302
12.55.3.8 set_midi_channel(int midichannel)	302
12.55.3.9 set_midi_bus(int midibus)	302
12.55.3.10set_scale(int scale)	302
12.55.3.11set_key(int note)	303
12.55.3.12set_background_sequence(int seq)	303
12.55.3.13name_change_callback()	303
12.55.3.14set_data_type(midibyte status, midibyte control=0)	303
12.55.3.15fill_top_bar()	303

CONTENTS xxxvii

12.55.3.16create_menus()	303
12.55.3.17popup_event_menu()	304
12.55.3.1&popup_midibus_menu()	304
12.55.3.19popup_sequence_menu()	304
12.55.3.20popup_tool_menu()	304
12.55.3.21timeout()	304
12.55.3.22do_action(int action, int var)	305
12.55.3.23on_delete_event(GdkEventAny *event)	305
12.55.3.24on_scroll_event(GdkEventScroll *ev)	305
12.55.3.25on_key_press_event(GdkEventKey *ev)	305
12.55.4 Field Documentation	305
12.55.4.1 m_initial_snap	305
12.55.4.2 m_zoom	306
12.55.4.3 m_pos	306
12.55.4.4 m_seqkeys_wid	306
12.55.4.5 m_seqtime_wid	306
12.55.4.6 m_seqdata_wid	306
12.55.4.7 m_table	306
12.56seq64::seqevent Class Reference	306
12.56.1 Member Function Documentation	309
12.56.1.1 reset()	309
12.56.1.2 redraw()	309
12.56.1.3 set_snap(int a_snap)	309
12.56.1.4 set_data_type(midibyte a_status, midibyte a_control)	309
12.56.1.5 update_sizes()	310
12.56.1.6 draw_background()	310
12.56.1.7 draw_pixmap_on_window()	310
12.56.1.8 idle_redraw()	310
12.56.1.9 x_to_w(int a_x1, int a_x2, int &a_x, int &a_w)	310
12.56.1.10drop_event(midipulse a_tick)	310

xxxviii CONTENTS

12.56.1.11draw_events_on(Glib::RefPtr< Gdk::Drawable > a_draw)	310
12.56.1.12start_paste()	310
12.56.1.13change_horz()	311
12.56.1.14convert_x(int x, midipulse &tick)	311
12.56.1.15convert_t(midipulse ticks, int &x)	311
12.56.1.16snap_x(int &a_x)	311
12.56.1.17on_realize()	311
12.56.1.1&n_button_press_event(GdkEventButton *a_ev)	311
12.56.1.19on_button_release_event(GdkEventButton *a_ev)	311
12.56.1.20on_motion_notify_event(GdkEventMotion *a_ev)	312
12.56.1.21on_key_press_event(GdkEventKey *a_p0)	312
12.57seq64::seqkeys Class Reference	312
12.57.1 Member Function Documentation	314
12.57.1.1 set_hint_state(bool a_state)	314
12.57.1.2 force_draw()	315
12.57.1.3 draw_key(int a_key, bool a_state)	315
12.57.1.4 on_realize()	315
12.57.1.5 on_button_press_event(GdkEventButton *a_ev)	315
12.57.1.6 on_button_release_event(GdkEventButton *a_ev)	315
12.57.1.7 on_motion_notify_event(GdkEventMotion *a_p0)	316
12.57.1.8 on_enter_notify_event(GdkEventCrossing *p0)	316
12.57.1.9 on_leave_notify_event(GdkEventCrossing *p0)	316
12.57.1.10on_scroll_event(GdkEventScroll *a_ev)	316
12.57.1.11on_size_allocate(Gtk::Allocation &)	316
12.58seq64::seqmenu Class Reference	316
12.58.1 Detailed Description	319
12.58.2 Constructor & Destructor Documentation	319
12.58.2.1 seqmenu(perform &a_p)	319
12.58.2.2 ~seqmenu()	319
12.58.3 Member Function Documentation	320

CONTENTS xxxix

12.58.3.1 is_edit_sequence(int seqnum) const	320
12.58.3.2 popup_menu()	320
12.58.3.3 seq_edit()	320
12.58.3.4 seq_event_edit()	320
12.58.3.5 seq_new()	320
12.58.3.6 seq_copy()	320
12.58.3.7 seq_cut()	321
12.58.3.8 seq_paste()	321
12.58.3.9 seq_clear_perf()	321
12.58.4 Field Documentation	321
12.58.4.1 m_seqedit	321
12.58.4.2 m_modified	321
12.59seq64::seqroll Class Reference	321
12.59.1 Constructor & Destructor Documentation	325
12.59.1.1 seqroll(perform &perf, sequence &seq, int zoom, int snap, seqkeys &seqkeys_wid,	
int pos, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=SEQ64←USE_DEFAULT_PPQN)	325
_USE_DEFAULT_PPQN)	326
_USE_DEFAULT_PPQN)	326 326
_USE_DEFAULT_PPQN)	326 326 326
USE_DEFAULT_PPQN)	326 326 326
USE_DEFAULT_PPQN)	326 326 326 326 326
USE_DEFAULT_PPQN) 12.59.1.2 ~seqroll() 12.59.2 Member Function Documentation 12.59.2.1 set_zoom(int zoom) 12.59.2.2 set_key(int key) 12.59.2.3 set_scale(int scale)	326 326 326 326 326
USE_DEFAULT_PPQN) 12.59.1.2 ~seqroll() 12.59.2 Member Function Documentation 12.59.2.1 set_zoom(int zoom) 12.59.2.2 set_key(int key) 12.59.2.3 set_scale(int scale) 12.59.2.4 set_data_type(midibyte status, midibyte control)	326 326 326 326 326 326
USE_DEFAULT_PPQN) 12.59.1.2 ~seqroll() 12.59.2 Member Function Documentation 12.59.2.1 set_zoom(int zoom) 12.59.2.2 set_key(int key) 12.59.2.3 set_scale(int scale) 12.59.2.4 set_data_type(midibyte status, midibyte control) 12.59.2.5 set_background_sequence(bool state, int seq)	326 326 326 326 326 326 326
USE_DEFAULT_PPQN) 12.59.1.2 ~seqroll() 12.59.2 Member Function Documentation 12.59.2.1 set_zoom(int zoom) 12.59.2.2 set_key(int key) 12.59.2.3 set_scale(int scale) 12.59.2.4 set_data_type(midibyte status, midibyte control) 12.59.2.5 set_background_sequence(bool state, int seq) 12.59.2.6 update_sizes()	326 326 326 326 326 326 326 327
_USE_DEFAULT_PPQN) 12.59.1.2 ~seqroll() 12.59.2 Member Function Documentation 12.59.2.1 set_zoom(int zoom) 12.59.2.2 set_key(int key) 12.59.2.3 set_scale(int scale) 12.59.2.4 set_data_type(midibyte status, midibyte control) 12.59.2.5 set_background_sequence(bool state, int seq) 12.59.2.6 update_sizes() 12.59.2.7 update_background()	326 326 326 326 326 326 327 327
_USE_DEFAULT_PPQN) 12.59.1.2 ~seqroll() 12.59.2 Member Function Documentation 12.59.2.1 set_zoom(int zoom) 12.59.2.2 set_key(int key) 12.59.2.3 set_scale(int scale) 12.59.2.4 set_data_type(midibyte status, midibyte control) 12.59.2.5 set_background_sequence(bool state, int seq) 12.59.2.6 update_sizes() 12.59.2.7 update_background() 12.59.2.8 draw_events_on_pixmap()	326 326 326 326 326 326 327 327
_USE_DEFAULT_PPQN) 12.59.1.2 ~seqroll() 12.59.2 Member Function Documentation 12.59.2.1 set_zoom(int zoom) 12.59.2.2 set_key(int key) 12.59.2.3 set_scale(int scale) 12.59.2.4 set_data_type(midibyte status, midibyte control) 12.59.2.5 set_background_sequence(bool state, int seq) 12.59.2.6 update_sizes() 12.59.2.7 update_background() 12.59.2.8 draw_events_on_pixmap() 12.59.2.9 draw_progress_on_window()	326 326 326 326 326 326 327 327 327

xI CONTENTS

12.59.2.13follow_progress()	327
12.59.2.14horizontal_adjust(double step)	328
12.59.2.15snap_y(int &y)	328
12.59.2.16snap_x(int &x)	328
12.59.2.17convert_tn(midipulse ticks, int note, int &x, int &y)	328
12.59.2.18xy_to_rect(int x1, int y1, int x2, int y2, int &x, int &y, int &w, int &h)	328
12.59.2.19draw_events_on(Glib::RefPtr< Gdk::Drawable > draw)	328
12.59.2.2@hange_horz()	329
12.59.2.21on_key_press_event(GdkEventKey *ev)	329
12.59.2.22on_scroll_event(GdkEventScroll *a_ev)	329
12.59.3 Field Documentation	329
12.59.3.1 m_pos	329
12.60seq64::seqtime Class Reference	329
12.60.1 Constructor & Destructor Documentation	331
12.60.1.1 seqtime(sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)	331
12.60.2 Member Function Documentation	331
12.60.2.1 reset()	331
12.60.2.2 update_pixmap()	332
12.60.2.3 on_realize()	332
12.60.2.4 on_button_press_event(GdkEventButton *)	332
12.60.2.5 on_button_release_event(GdkEventButton *)	332
12.61 seq64::sequence Class Reference	332
12.61.1 Detailed Description	340
12.61.2 Member Enumeration Documentation	341
12.61.2.1 select_action_e	341
12.61.3 Member Function Documentation	341
12.61.3.1 partial_assign(const sequence &rhs)	341
12.61.3.2 event_count() const	341
12.61.3.3 push_undo()	341
12.61.3.4 pop_undo()	341

CONTENTS xli

12.61.3.5 pop_redo()
12.61.3.6 push_trigger_undo()
12.61.3.7 set_beats_per_bar(int beatspermeasure)
12.61.3.8 set_beat_width(int beatwidth)
12.61.3.9 get_beat_width() const
12.61.3.10set_rec_vol(int rec_vol)
12.61.3.11get_name() const
12.61.3.12set_length(midipulse len, bool adjust_triggers=true) 342
12.61.3.13get_last_tick()
12.61.3.14set_last_tick(midipulse tick)
12.61.3.15mod_last_tick()
12.61.3.16set_playing(bool)
12.61.3.17loggle_queued()
12.61.3.18off_queued()
12.61.3.19set_recording(bool)
12.61.3.20set_snap_tick(int st)
12.61.3.21set_quantized_rec(bool qr)
12.61.3.22set_thru(bool)
12.61.3.23s_dirty_main()
12.61.3.24is_dirty_edit()
12.61.3.25s_dirty_perf()
12.61.3.26s_dirty_names()
12.61.3.27set_dirty_mp()
12.61.3.28set_dirty()
12.61.3.29set_midi_channel(midibyte ch)
12.61.3.3(print() const
12.61.3.31print_triggers() const
12.61.3.32play(midipulse tick, bool playback_mode)
12.61.3.33add_event(const event &er)
12.61.3.34add_trigger(midipulse tick, midipulse len, midipulse offset=0, bool adjust_← offset=true)

xlii CONTENTS

12.61.3.35split_trigger(midipulse tick)	346
12.61.3.36grow_trigger(midipulse tick_from, midipulse tick_to, midipulse len)	346
12.61.3.37del_trigger(midipulse tick)	346
12.61.3.3&get_trigger_state(midipulse tick)	346
12.61.3.3%select_trigger(midipulse tick)	346
12.61.3.40unselect_triggers()	347
12.61.3.41intersect_triggers(midipulse position, midipulse &start, midipulse &ender)	347
12.61.3.42ntersect_notes(midipulse position, midipulse position_note, midipulse &start, midipulse &ender, int ¬e)	347
12.61.3.43ntersect_events(midipulse posstart, midipulse posend, midibyte status, midipulse &start)	348
12.61.3.44paste_trigger()	348
12.61.3.45move_selected_triggers_to(midipulse tick, bool adjust_offset, int which=2)	348
12.61.3.46selected_trigger_start()	349
12.61.3.47selected_trigger_end()	349
12.61.3.48get_max_trigger()	349
12.61.3.49move_triggers(midipulse start_tick, midipulse distance, bool direction)	349
12.61.3.50copy_triggers(midipulse start_tick, midipulse distance)	349
12.61.3.51clear_triggers()	349
12.61.3.52set_midi_bus(char mb)	349
12.61.3.53set_master_midi_bus(mastermidibus *mmb)	349
12.61.3.54select_note_events(midipulse tick_s, int note_h, midipulse tick_f, int note_← l, select_action_e action)	350
12.61.3.55select_events(midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)	350
12.61.3.56select_events(midibyte status, midibyte cc, bool inverse=false)	350
12.61.3.57get_num_selected_notes() const	350
12.61.3.5&get_num_selected_events(midibyte status, midibyte cc) const	350
12.61.3.59select_all()	350
12.61.3.60copy_selected()	351
12.61.3.61cut_selected(bool copyevents=true)	351
12.61.3.62paste_selected(midipulse tick, int note)	351

CONTENTS xliii

12.61.3.63get_selected_box(midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l) .	351
12.61.3.64get_clipboard_box(midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)	351
12.61.3.65move_selected_notes(midipulse deltatick, int deltanote)	351
12.61.3.66add_note(midipulse tick, midipulse len, int note, bool paint=false)	351
12.61.3.67add_event(midipulse tick, midibyte status, midibyte d0, midibyte d1, bool paint=false)	352
12.61.3.68stream_event(event &ev)	352
12.61.3.69change_event_data_range(midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int d_s, int d_f)	352
12.61.3.7@ncrement_selected(midibyte status, midibyte control)	353
12.61.3.71decrement_selected(midibyte status, midibyte control)	353
12.61.3.72grow_selected(midipulse deltatick)	353
12.61.3.73stretch_selected(midipulse deltatick)	354
12.61.3.74remove_marked()	354
12.61.3.75mark_selected()	354
12.61.3.76unpaint_all()	354
12.61.3.77unselect()	354
12.61.3.78/erify_and_link()	354
12.61.3.79ink_new()	354
12.61.3.80zero_markers()	354
12.61.3.81play_note_on(int note)	355
12.61.3.82play_note_off(int note)	355
12.61.3.83off_playing_notes()	355
12.61.3.84pause()	355
12.61.3.85reset(bool live_mode)	355
12.61.3.86reset_draw_marker()	355
12.61.3.87reset_draw_trigger_marker()	355
12.61.3.88get_next_note_event(midipulse *tick_s, midipulse *tick_f, int *note, bool *selected, int *velocity)	355
12.61.3.89get_minmax_note_events(int &lowest, int &highest)	356
12.61.3.90get_next_event(midibyte status, midibyte cc, midipulse *tick, midibyte *d0, midibyte *d1, bool *selected)	356

XIIV CONTENTS

12.61.3.91get_next_event(midibyte *status, midibyte *cc)	 356
12.61.3.92ill_container(midi_container &c, int tracknumber)	 356
12.61.3.93 ranspose_notes(int steps, int scale)	 357
12.61.3.94background_sequence(int bs)	 357
12.61.3.95copy_events(const event_list &newevents)	 357
12.61.3.96set_parent(perform *p)	 357
12.61.3.97put_event_on_bus(event &ev)	 357
12.61.3.98set_trigger_offset(midipulse trigger_offset)	 358
12.61.3.99split_trigger(trigger &trig, midipulse splittick)	 358
12.61.3.10@djust_trigger_offsets_to_length(midipulse newlen)	 358
12.61.3.10 move (event_list::iterator i)	 358
12.61.3.102emove(event &e)	 358
12.61.3.10@move_all()	 358
12.61.4 Field Documentation	 359
12.61.4.1 m_parent	 359
12.61.4.2 m_midi_channel	 359
12.61.4.3 m_playing_notes	 359
12.61.4.4 m_raise	 359
12.61.4.5 m_seq_number	 359
12.61.4.6 m_length	 359
12.61.4.7 m_snap_tick	 359
12.61.4.8 m_time_beats_per_measure	 359
12.61.4.9 m_time_beat_width	 359
12.61.4.10m_clocks_per_metronome	 360
12.61.4.11m_32nds_per_quarter	 360
12.61.4.12m_us_per_quarter_note	 360
12.61.4.13m_musical_key	 360
12.61.4.14m_musical_scale	 360
12.61.4.15m_background_sequence	 360
12.61.4.16m_mutex	 360

CONTENTS xlv

12.62seq64::trigger Class Reference
12.62.1 Detailed Description
12.62.2 Member Function Documentation
12.62.2.1 operator<(const trigger &rhs)
12.63seq64::triggers Class Reference
12.63.1 Constructor & Destructor Documentation
12.63.1.1 triggers(sequence &parent)
12.63.2 Member Function Documentation
12.63.2.1 operator=(const triggers &rhs)
12.63.2.2 set_length(int len)
12.63.2.3 print(const std::string &seqname) const
12.63.2.4 play(midipulse &starttick, midipulse &endtick)
12.63.2.5 add(midipulse tick, midipulse len, midipulse offset=0, bool adjustoffset=true) 365
12.63.2.6 adjust_offsets_to_length(midipulse newlen)
12.63.2.7 split(midipulse tick)
12.63.2.8 split(trigger &trig, midipulse splittick)
12.63.2.9 grow(midipulse tickfrom, midipulse tickto, midipulse length)
12.63.2.10remove(midipulse tick)
12.63.2.11get_state(midipulse tick)
12.63.2.12select(midipulse tick)
12.63.2.13unselect()
12.63.2.14ntersect(midipulse position, midipulse &start, midipulse &end)
12.63.2.15paste()
12.63.2.16move_selected(midipulse tick, bool adjustoffset, int which=2)
12.63.2.17get_selected_start()
12.63.2.1&get_selected_end()
12.63.2.19get_maximum()
12.63.2.20move(midipulse starttick, midipulse distance, bool direction)
12.63.2.21copy(midipulse starttick, midipulse distance)
12.63.2.22next(midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)370

XIVI

12.63.2.23next_trigger()
12.63.2.24adjust_offset(midipulse offset)
12.63.3 Field Documentation
12.63.3.1 m_ppqn
12.63.3.2 m_length
12.64seq64::user_instrument Class Reference
12.64.1 Detailed Description
12.64.2 Member Function Documentation
12.64.2.1 set_defaults()
12.64.2.2 controller_max() const
12.64.2.3 controller_name(int c) const
12.64.2.4 controller_active(int c) const
12.64.2.5 set_controller(int c, const std::string &cname, bool isactive) 37
12.64.2.6 set_name(const std::string &instname)
12.64.2.7 copy_definitions(const user_instrument &rhs)
12.64.3 Field Documentation
12.64.3.1 m_is_valid
12.64.3.2 m_controller_count
12.65seq64::user_instrument_t Struct Reference
12.65.1 Field Documentation
12.65.1.1 instrument
12.65.1.2 controllers
12.65.1.3 controllers_active
12.66seq64::user_midi_bus Class Reference
12.66.1 Detailed Description
12.66.2 Member Function Documentation
12.66.2.1 set_defaults()
12.66.2.2 channel_count() const
12.66.2.3 channel_max() const
12.66.2.4 instrument(int channel) const

CONTENTS xlvii

12.66.2.5 set_instrument(int channel, int instrum)	375
12.66.2.6 copy_definitions(const user_midi_bus &rhs)	376
12.66.3 Field Documentation	376
12.66.3.1 m_is_valid	376
12.66.3.2 m_channel_count	376
12.67seq64::user_midi_bus_t Struct Reference	376
12.67.1 Field Documentation	376
12.67.1.1 alias	376
12.67.1.2 instrument	376
12.68seq64::user_settings Class Reference	376
12.68.1 Detailed Description	383
12.68.2 Member Typedef Documentation	383
12.68.2.1 Busses	383
12.68.2.2 Instruments	383
12.68.3 Member Enumeration Documentation	383
12.68.3.1 mainwid_grid_style_t	383
12.68.4 Member Function Documentation	384
12.68.4.1 set_defaults()	384
12.68.4.2 bus(int index)	384
12.68.4.3 instrument(int index)	384
12.68.4.4 controller_active(int buss, int channel, int cc)	384
12.68.4.5 controller_name(int buss, int channel, int cc)	384
12.68.4.6 zoom(int value)	384
12.68.4.7 mainwnd_rows(int value)	384
12.68.4.8 mainwnd_cols(int value)	384
12.68.4.9 max_sets(int value)	384
12.68.4.10(ext_x(int value)	385
12.68.4.11text_y(int value)	385
12.68.4.12mainwid_border(int value)	385
12.68.4.13mainwid_spacing(int value)	385

xlviii CONTENTS

12.68.4.14control_height(int value)	35
12.68.4.15dump_summary()	35
12.68.4.16perf_h_page_increment(int inc)	35
12.68.4.17perf_v_page_increment(int inc)	35
12.68.4.18midi_ppqn(int ppqn)	35
12.68.4.19midi_buss_override(char buss)	36
12.68.4.20midi_beats_per_bar(int beatsperbar)	36
12.68.4.21midi_beats_per_minute(int beatsperminute)	36
12.68.4.22midi_beat_width(int beatwidth)	36
12.68.4.23private_bus(int buss)	36
12.68.4.24private_instrument(int instrum)	36
12.68.5 Field Documentation	36
12.68.5.1 m_midi_buses	36
12.68.5.2 m_instruments	36
12.68.5.3 m_grid_style	37
12.68.5.4 m_grid_brackets	37
12.68.5.5 m_mainwnd_rows	37
12.68.5.6 m_mainwnd_cols	37
12.68.5.7 m_max_sets	37
12.68.5.8 m_mainwid_border	37
12.68.5.9 m_control_height	38
12.68.5.10m_current_zoom	38
12.68.5.11m_global_seq_feature_save	88
12.68.5.12m_seqedit_scale	38
12.68.5.13m_seqedit_key	88
12.68.5.14m_seqedit_bgsequence	38
12.68.5.15m_use_new_font	38
12.68.5.16m_allow_two_perfedits	39
12.68.5.17m_h_perf_page_increment	39
12.68.5.18m_v_perf_page_increment	39

CONTENTS xlix

12.68.5.19m_progress_bar_colored	389
12.68.5.20m_progress_bar_thick	389
12.68.5.21m_window_redraw_rate_ms	389
12.68.5.22m_text_x	389
12.68.5.23m_seqchars_x	390
12.68.5.24m_midi_ppqn	390
12.68.5.25m_midi_beats_per_measure	390
12.68.5.26m_midi_beats_per_minute	390
12.68.5.27m_midi_beat_width	390
12.68.5.28m_midi_buss_override	390
12.68.5.29m_seqs_in_set	390
12.68.5.30m_gmute_tracks	391
12.68.5.31m_max_sequence	391
12.68.5.32m_seqarea_x	391
12.68.5.33m_seqarea_seq_x	391
12.68.5.34m_mainwid_x	391
12.68.5.35m_save_user_config	391
12.68.5.36mc_min_zoom	391
12.68.5.37mc_max_zoom	392
12.68.5.38mc_baseline_ppqn	392
12.69seq64::userfile Class Reference	392
12.69.1 Member Function Documentation	393
12.69.1.1 parse(perform &a_perf)	393
12.69.1.2 write(const perform &a_perf)	393
12.69.1.3 dump_setting_summary()	393
	205

Index

Chapter 1

Sequencer64

Author(s) Chris Ahlstrom 2015-11-27

1.1 Introduction

Sequencer64 is a major cleanup, refactoring, and documentation of the Seq24 live-play MIDI sequencer.

The current document, generated by Doxygen, describes the functions, classes, modules, and other entities used in this project.

Also read the ROADMAP, README, and contrib/bugs_to_investigate files to understand the genesis of this project and the things that still need to be done with Sequencer64.

Also, we have pretty deeply documented *Seq24* and *Sequencer64* with PDF files that can be generated by git-cloning the following projects, installing a number of tools related to PDF and LaTeX, and running "make":

- https://github.com/ahlstromcj/seg24-doc.git
- https://github.com/ahlstromcj/sequencer64-doc.git

These project also have prebuilt PDFs should one not want to bother building them.

In the present document, we've left out a fair amount of side-code to cut down on the size of the document. For example, the main module, redundant Windows support, utility headers like easy_macros.h, standard stuff like the mutex module, the fruity variants (at least the ones already refactored into their own modules), etc., are all left out. Still, the resulting PDF is over 300 pages long.

Some useful references:

- http://acad.carleton.edu/courses/musc108-00-f14/pages/04/04StandardMID← IFiles.html
- http://www.midimusicadventures.com/qs/midi-zips/soundtracks/kq6gm.zip

2 Sequencer64

Chapter 2

MIDI File Parsing in Sequencer64

Author(s) Chris Ahlstrom 2016-02-13

2.1 Introduction

This section describes the parsing of a MIDI file (and a few other topics). We wanted to add the reading of SMF 0 files to *Sequencer64*. We started with the main format that is supported, SMF 1. Once we understood that we, we figured out how to split a SMF 0 tracks correctly.

We split the midifile::parse() function into two sections. The first section analyzes the header of the MIDI. Then, based on whether the file is SMF 1 (the normal case) or SMF 0, either the parse_smf_1() function of or the parse—smf_0() function is called. The parse_smf_0() function creates one sequence object per channel present in the SMF 0 file, plus the original track. The last pattern slot (sequence 16) will contain the original track data, and the rest will contain common data and then channel data for each channel. After the parsing is done, all the tracks (including the original track) will be added to the performance. The user then has the option of deleting the original track, which will be the last track.

2.2 SMF 1 Parsing

This section describes the parsing of the header chunk, MThd, and the track chunk, MTrk.

The midifile::parse() function starts by opening the MIDI file, getting its file-size, pre-allocating the data vector to that size, reading all of the characters into that vector, and then closing the file.

2.2.1 MIDI File Header, MThd

The data of the header is read:

```
Header ID: "MThd" read_long() 4 bytes
MThd length: 6 read_long() 4 bytes
Format: 0, 1, 2 read_short() 2 bytes
No. of track: 1 or more read_short() 2 bytes
PPQN: 192 read_short() 2 bytes
```

The header ID and it's length are always the same values. The formats that Sequencer64 supports are 0 or 1. SMF 0 has only one track, while SMF 1 can support an arbitary number of tracks. The last value in the header is the PPQN value, which specifies the "pulses per quarter note", which is the basic time-resolution of events in the MIDI file. Common values are 96 or 192, but higher values are also common. Sequencer64 and its precursor, Seq24, default to 192.

2.2.2 MIDI Track, MTrk

Sequencer64 next reads the tracks specified in the file. Each track is assumed to cover a different MIDI channel, but always the same MIDI buss. (The MIDI buss is not a data item in standard MIDI files, but it is a special data item in Seq24/Sequencer64 MIDI files.) Each track is tagged by a standard chunk marker, "MTrk". Other markers are possible, and are to be ignored, if nothing else. Here are the values read at the beginning of a track:

```
Track ID: "MTrk" read_long() 4 bytes
Track length: varies read_long() 4 bytes
```

The track length is the number of bytes that need to be read in order to get all of the data in the track.

Next, a new sequence object is created, with the PPQN value passed to its constructor. The sequence then is hooked to the master MIDI buss object. The "RunningTime" accumulator is set to 0 for that track.

Next, the parse() function loops through the rest of the track, reading data and logging it to the sequence. Let's go through the loop, which is the meat of the processing.

TODO: An empty event is created before track processing, and re-used for every track and event. This seems dangerous. We moved the event constructor two levels of nesting deeper, and it seems to work fine.

Delta time. The amount time that passes from one event to the next is the *delta time*. For some events, the time doesn't matter, and is set to 0. This values is a *variable length value*, also known as a "VLV" or a "varinum". It provides a way of encoding arbitrarily large values, a byte at a time. For now, just note that a varinum is 1 or more bytes, and MIDI provides a way to tell when the varinum is complete.

```
Delta time: varies read_varinum() 1 or more bytes
```

2.2.2.1 Channel Events

Status. The byte after the delta time is examined by masking it against 0x80 to check the high bit. If not set, it is a "running status", it is replaced with the "last status", which is 0 at first.

```
Status byte: varies read_byte() 1 byte
```

If the high bit is set, it is a status, and is passed to the setter $event::set_status()$.

The "RunningTime" accumulator is incremented by the delta-time. The current time is adjusted as per the PPQN ratio, if needed, and passed to the setter $event::set_timestamp()$.

Now what does the status mean? First, the channel part of the status is masked out using the 0xF0 mask.

If it is a 2-data-byte event (note on, note off, aftertouch, control-change, or pitch-wheel), then the two data bytes are read:

```
Data byte 0: varies read_byte() 1 byte
Data byte 1: varies read_byte() 1 byte
```

If the status is a note-on event, with data[1] = 0, then it is converted to a note-off event, a fix for the output quirks of some MIDI devices, and the status of the event is amended to EVENT_NOTE_OFF.

If it is a 1-data-btye event (program change or channel pressure), then only data byte 0 is read.

Then the one or two data bytes are added to the event by overloads of event::set_data(), the event is added to the current sequence by sequence::add_event(), and the MIDI channel of the sequence is set by sequence::set_midi_channel().

Note that this is the point where parsing could detect a change in channel, and select a new sequence to support that channel, and add the events to that sequence, if the file were SMF 0.

Also note that the channel of the sequence is set every a new channel event/status is read. This should be done once, and then simply warned about if a non-matching channel occurs.

Lastly, note that it might be better to do the sequence function calls at the end of processing the event.

2.2 SMF 1 Parsing 5

2.2.2.2 Meta Events

If the event status masks off to 0xF0 (0xF0 to 0xFF), then it is a meta event. If the status is 0xFF, it is called a "Sequencer-specific", or "SeqSpec" event. For this kind of event, then a type byte and the length of the event are read.

```
Meta type: varies read_byte() 1 byte
Meta length: varies read_varinum() 1 or more bytes
```

If the type of the SeqSpec (0xFF) meta event is 0x7F, parsing checks to see if it is one of the Seq24 "proprietary" events. These events are tagged with various values that mask off to 0x24240000. The parser reads the tag:

```
Prop tag: 0x242400nn read_long() 4 bytes
```

These tags provide a way to save and recover Seq24/Sequencer64 properties from the MIDI file: MIDI buss, MIDI channel, time signature, sequence triggers, and (new), the key, scale, and background sequence to use with the track/sequence. Any leftover data for the tagged event is let go. Unknown tags ate skipped.

If the type of the SeqSpec (0xFF) meta event is 0x2F, then it is the End-of-Track marker. The current time is set using $sequence::set_length()$ and then $sequence::zero_markers()$ is called, and parsing is done for that track.

If the type of the SeqSpec (0xFF) meta event is 0x03, then it is the sequence name. The "length" number of bytes are read, and loaded by $sequence::set_name()$.

If the type of the SeqSpec (0xFF) meta event is 0x00, then it is the sequence number, which is read:

```
Seq number: varies read_short() 2 bytes
```

Note that the sequence number might be modified latter to account for the current screenset in force for a file import operation.

Anything other SeqSpec type is simply skipped by reading the "length" number of bytes.

To summarize the process, here are the relevant event and sequence setter calls typically made while parsing a MIDI track:

```
1. perform::add_sequence()
   (a) sequence::sequence()
   (b) sequence::set_master_midi_bus())
   (c) sequence::add_event()
        i. event::event()
        ii. event::set_status()
        iii. event::set_timestamp()
        iv. event::set_data()
   (d) sequence::set_midi_channel()
        (e) sequence::set_length()
        (f) sequence::set_name()
        (g) sequence::set_midi_bus()
2. xxxxx::yyyy()
```

2.2.3 Meta Events Summary

Here, we summarize the MIDI meta events for your edification.

```
1. FF 00 02 ssss: Sequence Number.
```

- 2. FF 01 len text: Text Event.
- 3. FF 02 len text: Copyright Notice.
- 4. FF 03 len text: Sequence/Track Name.
- 5. FF 04 len text: Instrument Name.
- 6. FF 05 len text: Lyric.
- 7. FF 06 len text: Marker.
- 8. FF 07 len text: Cue Point.
- 9. FF 08 len text: Patch/program Name.
- 10. FF 09 len text: Device Name.
- 11. FF 0A through 0F len text: Other kinds of text events.
- 12. FF 20 01 cc: MIDI channel (obsolete, used by Cakewalk)
- 13. FF 21 01 pp: MIDI port (obsolete, used by Cakewalk)
- 14. FF 2F 00: End of Track.
- 15. FF 51 03 tttttt: Set Tempo, us/qn.
- 16. FF 54 05 hr mn se fr ff: SMPTE Offset.
- 17. FF 58 04 nn dd cc bb: Time Signature.
- 18. FF 59 02 sf mi: Key Signature.
- 19. FF 7F len data: Sequencer-Specific.

The next sections describe the events that Sequencer tries to handle. These are

- Sequence Number (0x00)
- Track Name (0x03)
- End-of-Track (0x2F)
- Set Tempo (0x51) (Sequencer64 only)
- Time Signature (0x58) (Sequencer64 only)
- Sequencer-Specific (0x7F)
- System Exclusive (0xF0) Sort of handled, functionality incomplete..

2.2.3.1 Sequence Number (0x00)

```
FF 00 02 ss ss
```

This optional event must occur at the beginning of a track, before any non-zero delta-times, and before any transmittable MIDI events. It specifies the number of a sequence.

2.2 SMF 1 Parsing 7

2.2.3.2 Track/Sequence Name (0x03)

```
FF 03 len text
```

If in a format 0 track, or the first track in a format 1 file, the name of the sequence. Otherwise, the name of the track.

2.2.3.3 End of Track (0x2F)

```
FF 2F 00
```

This event is not optional. It is included so that an exact ending point may be specified for the track, so that it has an exact length, which is necessary for tracks which are looped or concatenated.

2.2.3.4 Set Tempo Event (0x51)

The MIDI Set Tempo meta event sets the tempo of a MIDI sequence in terms of the microseconds per quarter note. This is a meta message, so this event is never sent over MIDI ports to a MIDI device.

After the delta time, this event consists of six bytes of data:

```
FF 51 03 tt tt tt
```

Example:

```
FF 51 03 07 A1 20
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x51 the meta event type that signifies this is a Set Tempo event.
- 3. 0x03 is the length of the event, always 3 bytes.
- 4. The remaining three bytes carry the number of microseconds per quarter note. For example, the three bytes above form the hexadecimal value 0x07A120 (500000 decimal), which means that there are 500,000 microseconds per quarter note.

Since there are 60,000,000 microseconds per minute, the event above translates to: set the tempo to 60,000,000 / 500,000 = 120 quarter notes per minute (120 beats per minute). This is a 24-bit binary value, so each byte covers the full range of 0x00 to 0xFF.

This event normally appears in the first track. If not, the default tempo is 120 beats per minute. This event is important if the MIDI time division is specified in "pulses per quarter note", which does not itself define the length of the quarter note. The length of the quarter note is then determined by the Set Tempo meta event.

Representing tempos as time per beat instead of beat per time allows absolutely exact DWORD-term synchronization with a time-based sync protocol such as SMPTE time code or MIDI time code. This amount of accuracy provided by this tempo resolution allows a four-minute piece at 120 beats per minute to be accurate within 500 usec at the end of the piece.

We have now added the Tempo meta event (and the Time Signature meta event) to the track, which allows other sequencers to obtain these values from a Sequencer64 MIDI file. Here are the original headers for a normal MIDI file and its legacy (Seq24) conversion, as shown by the midicvt application:

```
hymne.asc
                                        hymne-ppqn-384.asc
MThd 1 4 96
                                        MThd 1 4 384
                                        MTrk
0 Meta SeqName "Vangelis: Hymne"
                                        0 SeqNr 0
0 TimeSig 4/4 24 8
                                        0 Meta SeqName "Vangelis: Hymne"
                                       0 SeqSpec 24 24 00 08 (no triggers)
0 SeqSpec 24 24 00 01 00 (MIDI buss 0)
0 Tempo 750000
0 Meta TrkEnd
                                        0 SeqSpec 24 24 00 06 04 04 (beats, width)
TrkEnd
                                        0 SeqSpec 24 24 00 02 00 (MIDI ch. 0)
                                        96 Meta TrkEnd
                                        TrkEnd
```

Here is the header data that result from the new conversion, which is used if the "legacy" option is not in force:

```
MThd 1 4 192
MTrk
0 SeqNr 0
0 Meta SeqName "Vangelis: Hymne"
0 TimeSig 4/4 24 8
0 Tempo 750000
0 SeqSpec 24 24 00 08
0 SeqSpec 24 24 00 01 00
0 SeqSpec 24 24 00 06 04 04
0 SeqSpec 24 24 00 02 00
48 Meta TrkEnd
TrkEnd
```

2.2.3.5 Time Signature Event (0x58)

After the delta time, this event consists of seven bytes of data:

```
FF 58 04 nn dd cc bb
```

The time signature is expressed as four numbers. nn and dd represent the numerator and denominator of the time signature as it would be notated. The numerator counts the number of beats in a measure (beats per measure or beats per bar). The denominator is a negative power of two: 2 represents a quarter-note, 3 represents an eighthnote, etc. The denominator specifies the unit of the beat (e.g. 4 or 8). In Seq24/Sequencer64, this value is also called the "beat width".

The CC parameter expresses the number of MIDI clocks (or "ticks", or "pulses") in a metronome click. The standard MIDI clock ticks 24 times per quarter note, so a value of 6 would mean the metronome clicks every 1/8th note. A CC value of 6 would mean that the metronome clicks once every 1/8th of a note (quaver). This MIDI clock is different from the clock (PPQN) that determines the start time and duration of the notes.

The bb parameter expresses the number of notated 32nd-notes in a MIDI quarter note (24 MIDI Clocks). The usual value for this parameter is 8, though some sequencers allow the user to specify that what MIDI thinks of as a quarter note, should be notated as something else. For example, a value of 16 means that the music plays two quarter notes for each quarter note metered out by the MIDI clock, so that the music plays at double speed.

Examples:

```
FF 58 04 04 02 18 08
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x58 the meta event type that signifies this is a Time Signature event.

2.2 SMF 1 Parsing 9

- 3. 0x04 is the length of the event, always 4 bytes.
- 4. 0x04 is the numerator of the time signature, and ranges from 0x00 to 0xFF.
- 5. 0x02 is the log base 2 of the denominator, and is the power to which 2 must be raised to get the denominator. Here, the denominator is 2 to 0x02, or 4, so the time signature is 4/4.
- 6. 0x18 is the metronome pulse in terms of the number of MIDI clock ticks per click. Assuming 24 MIDI clocks per quarter note, the value here (0x18 = 24) indidicates that the metronome will tick every 24/24 quarter note. If the value of the sixth byte were 0x30 = 48, the metronome clicks every two quarter notes, i.e. every half-note.
- 7. 0x08 defines the number of 32nd notes per beat. This byte is usually 8 as there is usually one quarter note per beat, and one quarter note contains eight 32nd notes.

A time signature of 6/8, with a metronome click every 3rd 1/8 note, would be encoded:

```
FF 58 04 06 03 24 08
```

Remember, a 1/4 note is 24 MIDI Clocks, therefore a bar of 6/8 is 72 MIDI Clocks. Hence 3 1/8 notes is 36 (=0x24) MIDI Clocks.

There should generally be a Time Signature Meta event at the beginning of a track (at time = 0), otherwise a default 4/4 time signature will be assumed. Thereafter they can be used to effect an immediate time signature change at any point within a track.

For a format 1 MIDI file, Time Signature Meta events should only occur within the first MTrk chunk.

If a time signature event is not present in a MIDI sequence, 4/4 signature is assumed.

In Sequencer64, the c_timesig SeqSpec event is given priority. The conventional time signature is used only if the c_timesig SeqSpec is not present in the file. NEEDS TO BE TESTED.

```
2.2.3.6 SysEx Event (0xF0)
```

If the meta event status value is 0xF0, it is called a "System-exclusive", or "SysEx" event.

```
F0 len data F7
```

Sequencer64 has some code in place to store these messages, but the data is currently not actually stored or used. Although there is some infrastructure to support storing the SysEx event within a sequence, the SysEx information is simply skipped. Sequencer64 warns if the terminating 0xF7 SysEx terminator is not found at the expected length. Also, some malformed SysEx events have been encountered, and those are detected and skipped as well.

2.2.3.7 Sequencer Specific (0x7F)

This data, also known as SeqSpec data, provides a way to encode information that a specific sequencer application needs, while marking it so that other sequences can safely ignore the information.

```
FF 7F len data
```

In *Seq24* and *Sequencer64*, the data portion starts with four bytes that indicate the kind of data for a particular SeqSpec event:

In Seq24, these events are placed at the end of the song, but are not marked as SeqSpec data. Most MIDI applications handle this situation fine, but some (e.g. midicvt) do not. Therefore, Sequencer64 makes sure to wrap each data item in the 0xFF 0x7F wrapper.

Also, the last three items above (key, scale, and background sequence) can also be stored (by *Sequencer64*) with a particular sequence/track, as well as at the end of the song. Not sure if this bit of extra flexibility is useful, but it is there.

2.2.3.8 Non-Specific End of Sequence

Any other statuses are deemed unsupportable in Sequencer64, and abort parsing with an error.

If the —bus option is in force, sequence::set_midi_bus() is called to override the buss number (if any) stored with the sequence.

Finally, $perform::add_sequence()$ adds the sequence to the encoded tune.

2.3 SMF 0 Parsing

After parsing SMF 1 track data, we end up with a number of sequences, each on a different MIDI channel. With SMF 0, data for all channels is present in a single track. Sequencer64 will read SMF 0 data, but we really need to be able to have one MIDI channel per track. So we need to take the data from the sequence and use it to make more sequences.

```
sequence::add_event().
sequence::set_midi_channel().
sequence::set_length().
sequence::set_midi_bus().
perform::add_sequence().
```

This code basically works. For now, please look at the source code for more details. Also, the reading of SMF 0 MIDI files is described in the *sequencer64-doc* project on GitHub.

2.4 Running Status

2.4 Running Status

When we apply the midicvt application to a file saved by Sequencer64, we can end up with a successful ASCII conversion that ends with an error message:

```
$ midicvt hymne-seq64.midi -o hymne-seq64.asc
? Error at MIDI file offset 12155 [0x2f7b]
Error: Garbage at end 'readtrack(): unexpected running status'
```

Is this a problem in midicvt or Sequencer4? Let's learn about running status.

Running status is a way to speed up the sending of MIDI bytes to a synthesizer or sequencer by taking advantage of redundancy where possible. For example, if we're sending a consecutive group of Note On and Note Off messages to a particular channel, we can save some time by not sending the channel status byte after the first time. Here's an example with Note On on channel 1:

```
0x90 3C 7F
0x90 40 7F
0x90 43 F3
```

Since no change in status occurs after the first of these three events, we can drop the subsequent status bytes:

```
0x90 3C 7F
40 7F
43 F3
```

The 0x90 byte is saved in a "running status buffer" (RSB), and is filled in by the receiving device.

Here is the sequence of events for operating with running status.

- 1. Clear the RSB buffer (RSB = 0) to start.
- 2. If a **Voice Category Status** (VCS) byte is received, then set RSB = VCS. VCS bytes range from 0x80 to 0xEF. This is binary 1000000 to 11100000.
- 3. If a data byte is received (data bytes range from 0x00 to 0x7F, binary 0000000 to 0111111; that is, bit 7 is always 0 in a data byte):
 - (a) If RSB != 0, first insert the RSB into the incoming data stream, then insert the data byte.
 - (b) If RSB == 0, then just insert the data byte into the incoming data stream.
- 4. Clear the RSB buffer (RSB = 0) when a System Common Message (SCM) status byte is received. SCM bytes range from 0xF0 to 0xF7.
- 5. The message after an SCM must begin with a status byte. That is a byte with bit 7 set.
- 6. Do no special action when a Realtime Category Message (RCM) byte is received. RCM bytes range from 0xF8 to 0xFF.

Note that some events, such as Tempo, assume that its bytes are all data bytes.

Chapter 3

JACK, Live, and Song Modes in Sequencer64

Author(s) Chris Ahlstrom 2016-01-23

3.1 Introduction

This section describes the interactions between JACK settings and the Live/Song Mode settings, with an eye to describing the proper behavior of Sequencer64 with JACK settings, how the Live/Song modes are supposed to work, and what bugs or issues remain in Sequencer64's JACK handling.

I'm not sure why Doxygen is applying the "code" font so often here. Weird, annoying.

3.2 JACK Functions

Please study the following URL and note these important points:

http://jackaudio.org/files/docs/html/transport-design.html

- The timebase master continuously updates position information, beats, timecode, etc. There is at most one
 master active at a time. If no client is registered as timebase master, frame numbers will be the only position
 information available.
- The timebase master registers a callback that updates position information while transport is rolling. Its output affects the following process cycle. This function is called immediately after the process callback in the same thread whenever the transport is rolling, or when any client has set a new position in the previous cycle.
- Clients that don't declare a sync callback are assumed ready immediately, anytime the transport wants to start. If a client doesn't require slow-sync processing, it can set its sync callback to NULL.
- The transport state is always valid; initially it is JackTransportStopped.
- When someone calls <code>jack_transport_start()</code>, the engine resets the poll bits and changes to a new state, <code>JackTransportStarting</code>.
- · When all slow-sync clients are ready, the state changes to JackTransportRolling.

Does Sequencer64 need a latency callback?

http://jackaudio.org/files/docs/html/group__ClientCallbacks.html

(We need to see why most of the following is in a monospaced font. Is there a new Doxygen feature?)

Here are summaries of the JACK functions used in the jack_assistant module:

3.2.1 jack_client_open()

```
Open a client session with a JACK server. More complex and powerful than <tt>jack_client_new()</tt>.

Clients choose which of several servers to connect, and how to start the server automatically, if not already running. There is also an option for JACK to generate a unique client name.

const char * client_name, jack_options_t options, jack_status_t * status,
```

client_name of at most jack_client_name_size() characters. The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

options formed by OR-ing together JackOptions bits. Only the JackOpenOptions bits are allowed.

status (if non-NULL) an address for JACK to return information from the open operation. This status word is formed by OR-ing together the relevant JackStatus bits.

Optional parameters: depending on corresponding [options bits] additional parameters may follow status (in this order).

[JackServerName] (char *) server_name selects from among several possible concurrent server instances. Server names are unique to each user. If unspecified, use "default" unless \$JACK_DEFAULT_SERVER is defined in the process environment.

Returns:

Opaque client handle if successful. If this is NULL, the open operation failed, and *status includes JackFailure, and the caller is not a JACK client.

3.2.2 jack_on_shutdown()

Registers a function to call when the JACK server shuts down the client thread. It must be an asynchonrous POSIX signal handler: only async-safe functions, executed from another thread. A typical function might set a flag or write to a pipe so that the rest of the application knows that the JACK client thread has shut down. Clients do not need to call this function. It only helps clients understand what is going on. It should be called before <tt>jack_client_activate()</tt>.

3.2.3 jack_set_sync_callback()

Register/unregister as a slow-sync client; it can't respond immediately to transport position changes. The callback is run at the first opportunity after registration: if the client is active, this is the next process cycle, otherwise it is the first cycle after <tt>jack_activate()</tt>. After that, it runs as per JackSyncCallback rules. Clients that don't set this callback are assumed ready immediately any time the transport wants to start.

3.2 JACK Functions 15

3.2.4 jack_set_process_callback()

Tells the JACK server to call the callback whenever there is work. The function must be suitable for real-time execution, it cannot call functions that might block for a long time: malloc(), free(), printf(), pthread_mutex_lock(), sleep(), wait(), poll(), select(), pthread_join(), pthread_cond_wait(), etc. In the current class, this function is a do-nothing function.

3.2.5 jack set session callback()

Tells the JACK server to call the callback when a session event is delivered. Setting more than one session callback per process is probably a design error. For a multiclient application, it's more sensible to create a JACK client with only one session callback.

3.2.6 jack_activate()

Tells the JACK server that the application is ready to start processing.

3.2.7 jack release timebase()

TODO

3.2.8 jack client close()

TODO

3.2.9 jack_transport_start()

Starts the JACK transport rolling. Any client can make this request at any time. It takes effect no sooner than the next process cycle, perhaps later if there are slow-sync clients. This function is realtime-safe. No return code.

3.2.10 jack_transport_stop()

3.2.11 jack_transport_locate()

Repositions the transport to a new frame number. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

3.2.12 jack_transport_reposition()

```
Request a new transport position. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe. This call, made in the position() function, is currently disabled.
```

3.2.13 jack transport query()

Query the current transport state and position. This function is realtime-safe, and can be called from any thread. If called from the process thread, pos corresponds to the first frame of the current cycle and the state returned is valid for the entire cycle.

The first parameter is the client, which is a pointer to the JACK client structure.

The second parameter is a pointer to structure for returning current transport position; pos->valid will show which fields contain valid data. If pos is NULL, do not return position information.

This function returns the current transport state.

3.3 Modes Operation

3.3.1 No JACK, Live Mode

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack_master = 0
- jack master cond = 0
- jack_start_mode = 0

By changing the start mode to 0 (false), Sequencer64 is put into Live Mode. With this setting, control of the muting and unmuting of patterns resides in the main window (the patterns window). One can start the playback in the performance (song) window, but it will not affect which patterns play, at all.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.3.2 No JACK, Song Mode

In \sim /.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack master = 0
- jack_master_cond = 0
- jack_start_mode = 1

By changing the start mode to 1 (true), Sequencer64 is put into Song Mode.

With this setting, control of the muting and unmuting of patterns resides in the song window (the performance window). The patterns shown in the pattern slots of the main window turn on and off whenever the progress bar is in the pattern as drawn in the perforance window.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.4 Breakage 17

3.3.3 JACK Transport

In ~/.config/sequencer64/sequencer64.rc, set:

```
• jack_transport = 1
```

- jack_master = 0
- jack master cond = 0
- jack_start_mode = 0 or 1 (see previous section)

The current behavior is that qjackctl and sequencer64 playback/progress seem to be independent of each other.

The workaround seems to be to set seq24/sequencer64 as JACK Master, or if another application (e.g. Qtractor) is JACK Master.

OLD BEHAVIOR:

```
Start qjackctl, verify that it sets up correctly, then click it's "play" button to start the transport rolling. Run sequencer64, load a file. Then note that starting playback (whether in the main window or in the performance window) is ineffective, but resets the time counter in qjackctl. Why? With JACK sync enabled by the macro:

[JACK transport slave]
```

```
jack transport slave|
jack sync(): zero frame rate [single report]!?
[JackTransportRolling]
[JackTransportStarting] (every time space bar pressed)
[Start playback]
```

END OF OLD BEHAVIOR.

3.4 Breakage

Old message about seq24 being broken:

 $\verb|http://lists.linuxaudio.org/pipermail/linux-audio-user/2010-November/073848. \leftarrow \verb|htm||$

```
i dont see the transport synchronisation working with a jackl svn version. you are still using only a sync callback.

and you are relying on the transport to go through the JackTransportStarting state.

this issue should be fixed.
iirc we came to the conclusion, that seq24 is broken, and we will not revert the changes in jack, which break it.

the quick and dirty fix on your side, would be to register an empty process_callback.

but the issue still remains. seq24 is NOT a slow sync client. but it registers a sync_callback.
and it even takes a lock in the sync callback.

the patch for jack-session support didnt get merged either.
```

Another one (no need for a URL):

I use seq24 for the majority of my projects but it isn't ideal (I should point out that I never finish anything). I don't like seq24's pianoroll editor, the way you do CC envelopes isn't ideal, it uses alsa-midi, there's unnecessary complexity in switching from pattern-trigger mode to song mode, and its insistence on being transport master while not even being able to adjust tempo when live is annoying

3.5 JACK References

- $\bullet \ \text{http://libremusicproduction.com/articles/demystifying-jack-\$E2\$80\$93-beginners-guidents.} \\$
- http://jackaudio.org/files/docs/html/transport-design.html
- http://kxstudio.linuxaudio.org/Repositories

Chapter 4

User Testing of Sequencer64 with Yoshimi

Author(s) Chris Ahlstrom 2016-03-04

4.1 Introduction

This section describes user testing of Sequencer64 using Yoshimi. It will expand as we work our way through all the many use-cases that can be achieved with Sequencer64 and Yoshimi.

Please note that the most advanced and recent testing can be found currently in the document contrib/notes/jack-testing txt. We will eventually merge the final tests here... someday.

4.2 Smoke Test

Every so often we run Sequencer64 with a software synthesizer to make sure we haven't broken any functionality via our major refactoring efforts. We call it a "smoke test". We fire up the two application, and see if anything smokes.

This smoke test sets up Yoshimi with a very simple ALSA setup, and no instruments are loaded. Instead, only the "Simple Sound" is used on all channels. We've been doing this test with Yoshimi 1.3.6. The current Debian Sid ("testing") version of Yoshimi is 1.3.6-2, pulled from SourceForge. It seems to have issues, so we've been cloning and pulling the code from:

```
https://github.com/Yoshimi/yoshimi.git
```

After getting the application build and installed, the next step is to run it, using ALSA for MIDI and for audio:

```
$ yoshimi -a -A &
```

Next, fix up the configuration files for Sequencer64, \sim /.config/sequencer64/sequencer64.rc and \sim /.config/sequencer64/sequencer64.usr.

First hide sequencer64.usr somewhere, or delete it, as it will determine what MIDI devices are available, and we don't want that (yet). Second, make sure that sequencer64.rc makes the following setting:

```
[manual-alsa-ports]
# Set to 1 if you want sequencer64 to create its own ALSA ports and
# not connect to other clients
0  # number of manual ALSA ports
```

Next, run the newly-built version of Sequencer64. If desired, use the –bus option described below to force the buss number to the buss you need, as shown in the second version of the command:

```
$ sequencer64/sequencer64 &
$ sequencer64/sequencer64 --bus 5 &
```

In File / Options / MIDI Clock, observe the MIDI inputs made available by your system. Our system shows:

```
[0] 14:0 (Midi Through Port-0)

[1] 128:0 (TiMidity port 0)

[2] 128:0 (TiMidity port 1)

[3] 128:0 (TiMidity port 2)

[4] 128:0 (TiMidity port 3)

[5] 129:0 (input)
```

For some reason (a bug in Yoshimi?), input "[5]" doesn't indicate that it is Yoshimi, but it is. Take note of that input number... that is the MIDI buss number that is needed to drive Yoshimi.

Also make sure that of the clock settings for those busses are "Off".

The next instruction still works, but it is easier to simply pass the option -bus 5 to Sequencer64 when starting it up.

Now open the file sequencer64/contrib/midi/b4uacuse-GM-format.midi in Sequencer64. For all of the patterns (slots) that have lots of data in them, right click on the pattern and select *Midi Bus / [5] 129:0 (input)* and the desired channel number. (Doesn't matter much, just use up the lower channel numbers first).

Back in Yoshimi, select each Part corresponding to the channels you selected. Make sure *Enabled* is checked for each desired channel.

Back in Sequencer64, click on each pattern you want to hear, which highlights them in black. Now click the play button (green triangle). The song should play, with each part using the "Simple Sound". Not too bad for a bunch of sine waves, eh?

Now we can test the application more fully. Note that the instructions here are very light. Detailed instructions on the usage of Sequencer64 can be found in the following project, which contains a PDF file and the LaTeX code used to build it:

```
https://github.com/ahlstromcj/sequencer64-doc.git
```

Although it applies to an earlier version of the project, it still mostly holds true for Sequencer64.

4.3 Tests in the Patterns Window

The Patterns window is the inside portion of the main window, supported by the mainwid class. it contains a grid of boxes or slots, with each slot potentially containing a pattern, sequence, or track. Empty tracks (i.e. tracks that contain no events, like title-only tracks) are highlighted in yellow.

This window supports only a single variant of mouse-handling.

4.3.1 Button Clicks on a Pattern

A left-click on a pattern slot should cause the following to happen:

- 1. The pattern will be highlighted (white on a black background). This won't occur until the button is released.
- 2. During playback, the pattern will emit MIDI events and play its sequence.
- 3. If the pattern is dragged to another slot, whether playing is in progress or not, releasing the button in the destination slot will move the pattern to that slot.

A right-click on a pattern slot should cause the following to happen:

- 1. If the pattern is empty, then a pop-up menu to make a New pattern, paste a pattern, or make other selections will appear.
- 2. If the pattern is active, then a pop-up menu to Edit the pattern or make other selections will appear.
- 3. A second right-click, just off the menu, will dismiss the menu.

4.3.2 Patterns Window Key Shortcuts

First, note the selection of the File / Options / Keyboard / Show keys option. The tests here should work whether or not it is selected. The only difference is if the keys are shown.

We got a segfault during this test, when we weren't being systematic about it.

4.3.3 The Sequencer64 User File

To be discussed.

4.4 Tests Using Valgrind

Valgrind is a very useful tool for unearthing memory issues and other issues in an application, especially when one has the source code and can build the code with debugging information.

One runs the application from the command line, preceding its command line with valgrind and some of its options.

4.4.1 Valgrind Suppressions

One problem with valgrind is that it also uncovers errors in system libraries that one has no control over. These errors clutter the output, so we suppress them using a valgrind "suppressions" file. Here's how to create one:

```
$ valgrind --gen-suppressions=yes --log-file=val.supp ./Sequencer64/sequencer64
$ valgrind --gen-suppressions=all --log-file=val.supp ./Sequencer64/sequencer64
```

As the program runs, one is asked to print a suppression. If the error is due to a system or third-party library, answer "Y return", and then copy-and-paste the suppression to a file, giving it a name. For example, we provide a file contrib/seq64.supp containing suppressions of errors that annoy us. There are way too many "errors" in ALSA, GTK+, gtkmm, glibc, and more.

The second command collects all the suppressions. Passing the val.supp file through sed makes it immediately usable:

```
$ sed -i -e /^==/g val.supp
```

Running valgrind like this then shows mostly the errors we care about:

```
$ valgrind --suppressions=val.supp ./Sequencer64/sequencer64
```

We've added some other suppression files to the contrib directory. Too much! For example:

```
https://github.com/dtrebbien/GNOME.supp
```

However, overall this process is very painful, and we're going to eventually do all the valgrind work on the unit-test project for Sequencer64:

```
https://github.com/ahlstromcj/seq64-tests
```

4.4.2 Full Valgrind Leak-Checking

Here's how to capture errors, while suppressing the system errors and while generating a log file:

```
$ valgrind --suppressions=contrib/seq64.supp --leak-check=full \
    --track-origins=yes --log-file=valgrind.log --show-leak-kinds=all \
    ./Sequencer64/sequencer64
```

The errors can be also be re-routed to a log-file via the "2> valgrind.log" shell redirection.

Another idea is to precede the valgrind command with the following construct:

```
$ G_SLICE=debug-blocks valgrind ...
```

G_SLICE=debug-blocks will turn off gtk's advanced memory management to allow valgrind to show correct results. This results in an amazing plethora or invalid read and invalid write errors in GNOME-related libraries. Sheesh!

And don't forget about Valgrind's "massif" memory-tracking tool! (More to come!)

4.4.2.1 Leak-Checking Basic Operation

For the first pass, just run Sequencer64, then immediately exit. Then scan the log file to see if any "errors" can be pinpointed to the application and library code.

Don't forget to run the same scenario without valgrind, in a console window, to see if any of our own debug/problem output occurs.

In any case, leakage tagged as "still reachable" isn't as bad as leakage tagged as "definitely lost" or "indirectly lost".

But good luck finding a Sequencer64 bug buried in the chaff of 3rd-party valgrind reports, even with some suppressions enabled. Apparently a lot of them have to do with data structures that are intended to last the full life of the application.

One can make the search a little easier by searching for the "seq64" namespace in the valgrind log.

4.5 Specific Fault Debugging

This section goes through specific debugging cases we encountered. They should be part of the regular testing of Sequencer64.

4.6 Snipping of a MIDI file.

In order to have a test file for the *seq64-tests* project, we loaded up the b4uacuse-GM-format.midi file, removed all but four of the tracks, and saved it as b4uacuse-snipped.midi. Loading this file into Sequencer64 caused the following:

```
$ ./Sequencer64/sequencer64
[Reading user configuration /home/ahlstrom/.config/sequencer64/sequencer64.usr]
[Reading rc configuration /home/ahlstrom/.config/sequencer64/sequencer64.rc]
get_sequence(): m_seqs[4] not null
Segmentation fault
```

First step, fire up a debugger and see what happened. We use cgdb, a text-based front-end for gdb with a "vi" feel.

```
$ cgdb ./Sequencer64/sequencer64
```

Just hit "r", do File / Open, navigate to b4uacuse-snipped.midi, select it, and watch what happens.

The "bt" (backtrace) command shows a pretty large stack, 52 items. Page up to the top of the stack, and select frame 1 ("fr 1"). This shows a mutex at a very low address, 0x650! Frame 2 shows we are in the automutex constructor, calling lock() on that same badly-located mutex. Frame 3 is in sequence::event_count(), same bad mutex, and the m_events member is at address 0x0. Obviously, we're dealing with an unallocated sequence.

Frame 4 is in mainwid::draw_sequence_on_pixmap(), just after we've retrieved the next sequence via perform ::get_sequence(4). But that would be the fifth sequence (the sequence numbers start at 0), and we snipped all but 4 from the file before we saved it.

So, one thing we need to do is *check* the value returned by get_sequence() before we try to use it. The other thing to do is figure out how we got to the fifth sequence, and fix that code as well. Using the command "p perf(). \leftarrow sequence_count()", we verify that there are indeed only 4 sequences allocated.

Frame 5 is in mainwid::draw_sequences_on_pixmap(). That function tries to load all sequences on the current screen-set, from 0 to 31, without checking to see how many their actually are. Inefficient and dangerous.

Frame 6 is in mainwid::reset(). We could pass perf().sequence_count() here for checking, or get it in mainwid ::draw_sequences_on_pixmap().

Before we fix this issue, we need to load a file that works, to see why it does not fail for most files. We will put a breakpoint at the top mainwid::draw_sequences_on_pixmap().

We hit the breakpoint before even loading a file, with a sequence_count() of 0. The call to valid_sequence(0) passes the test. We may want to make valid_sequence() take the sequence_count() into account. But the call to perf().is_active(0) prevents anything bad from happening at startup time.

Once we load a good file, the sequence_count() is 14 in mainwid::draw_sequences_on_pixmap(). We turn on the display of "offset" using the command "display offset", and "c" (for "continue") until offset = 14, which means we are beyond that last sequence. That bad access is prevented by perf().is active(14).

So the fundamental problem is that perf().is_active(4) is not protecting the access when we load the "bad file". We need to find and fix that issue before papering over the problem with better access checks.

Start again, putting a breakpoint in the call to "new sequence(m_ppqn)" in midifile. This call sets up some members and clears the list of 256 playing notes. Add another breakpoint at "a_perf.add_sequence()" to see what's happening there.

What we find is that the first two tracks have proper sequence numbers as read from the MIDI file, 0 and 1. But the third one preserves the number from the old file, 4. We have a disjunction between the track number and the sequence number, a conceptual problem. We can leave it as is, and beef up the error-checking, or replace the sequence number with the track number when loading the file. What to do?

- Make sure that the is-active flag for all sequences is "false", that the pointers are always null, and make sure to test both of these items (depending on context) before doing anything with the sequence.
- Convert the sequence number to the track number upon saving the MIDI file, or upon reading the MIDI file, and use that number when adding the sequence to the perform object. This might affect some seq24/sequencer64 functionality, however. It's big move.

We need information on reading and importing.

First, if we look at a file that we created long ago by importing b4uacuse.mid, b4uacuse-GM-format. \leftarrow midi, it has its fourteen sequence numbers identical to their track numbers. No problem.

Second, if we just read b4uacuse.mid, a non-seq24-created MIDI file, we see that each of its tracks have no sequence number – they are all zero. The perform::add_sequence() simple iterates from the beginning of m_seqs[] until it finds an inactive m_seqs[i], and uses that element to hold the sequence pointer.

But now it also segfaults! Let's fix all the non-checked get_sequence() calls right away, it is too big an issue to ignore.

In the end, we have to be aware that a screen-set can have blank (null) slots interspersed amongst the active slots.

Chapter 5

Licenses

Library This application and its libraries, sub-applications, and documents.

Author(s) Chris Ahlstrom 2015-09-10

5.1 License Terms for the This Project.

Wherever the tag \$XPC_SUITE_GPL_LICENSE\$ appears, or wherever reference to the GPL licensing scheme (any version) is mentioned, substitute the appropriate license text, depending on whether the project is a library, application, documentation, or server software. We're not going to include paragraphs of licensing information in every module; you are responsible for coming here to read the licensing information.

These licenses apply to each sub-project and file artifact in the project with which this license description was packaged.

Wherever the term **XPC** is encountered in this project, it refers to my projects, which go beyond the package that contains this document.

5.2 XPC Application License

The **XPC** application license is either the **GNU GPLv2**. or the **GNU GPLv3**. Generally, projects that originate with me use the latter language, while projects I have extended may specify the former license.

Copyright (C) 2015-2015 by Chris Ahlstrom

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU GPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/gpl-3.0.txt
```

26 Licenses

5.3 XPC Library License

The XPC library license is the GNU LGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Lesser Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU LGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/lgpl-3.0.txt
```

5.4 XPC Documentation License

The XPC documentation license is the GNU FDLv1.3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This documentation is free documentation; you can redistribute it and/or modify it under the terms of the GNU Free Documentation License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Free Documentation License along with this documentation; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU FDL version 1.3 license can also be found here:

```
http://www.gnu.org/licenses/fdl.txt
```

5.5 XPC Affero License 27

5.5 XPC Affero License

The XPC "Affero" license is the GNU AGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This server software is free server software; you can redistribute it and/or modify it under the terms of the GNU Affero General Public License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Affero General Public License along with this server software; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU AGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/agpl-3.0.txt
```

At the present time, no XPC project uses the "Affero" license.

5.6 XPC License Summary

Include one of these licenses in your Doxygen documentation with one of the following Doxygen tags specified above:

```
\ref gpl_license_subproject
\ref gpl_license_application
\ref gpl_license_library
\ref gpl_license_documentation
\ref gpl_license_affero
```

For more information on navigating GNU licensing, see this page:

```
http://www.gnu.org/licenses/
```

Copies of these licenses (and some logos) are provided in the licenses directory of the main project (or you can search for them at *gnu.org*).

28 Licenses

Chapter 6

Todo List

File calculations.cpp

There are additional user-interface and MIDI scaling variables in the perfroll module that we need to move here.

File perfnames.cpp

When bringing up this dialog, and starting play from it, some extra horizontal lines are drawn for some of the sequences. This happens even in seq24, so this is long standing behavior. Is it useful, and how? Where is it done? In perfroll?

Global seq64::editable_events::save_events()

Consider what to do about the sequence::m_is_modified flag.

Global seq64::eventedit::handle save ()

Could also support writing the events to a new sequence, for added flexibility.

Global seq64::mainwid::timeout ()

We should use this callback to display the current time in the playback.

Global seq64::mainwnd::mainwnd (perform &a_p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAUL ← T PPQN)

Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

Global seq64::mainwnd::on_key_press_event (GdkEventKey *a_ev)

Test this functionality in old and new application.

Global seq64::mainwnd::on_key_release_event (GdkEventKey *a_ev)

Test this functionality in old and new application.

Global seq64::perfedit::perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAU← LT_PPQN)

Offload most of the work into an initialization function like options does.

Global seq64::perform::add_sequence (sequence *seq, int perf)

Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Global seq64::perform::is_active (int seq) const

We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Global seq64::perform::m_seqs [c_max_sequence]

First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

Global seq64::perform::set_left_tick (midipulse tick, bool setstart=true)

The perform::m_one_measure member is currently hardwired to PPQN * 4.

30 Todo List

Global seq64::pulses_to_string (midipulse p)

Still needs to be unit tested.

Global seq64::pulses_to_timestring (midipulse p, const midi_timing &timinginfo)

Still needs to be unit tested.

Global seq64::seqdata::on scroll event (GdkEventScroll *ev)

DOCUMENT the segdata scrolling behavior in the documentation projects.

Global seq64::seqedit::get measures ()

Create a sequence::set units() function or a sequence::get measures() function to forward to.

Global seq64::seqedit::seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT → PPQN)

Offload most of the work into an initialization function like options does.

Global seq64::seqedit::set background sequence (int seq)

Make the sequence pointer a reference.

Global seq64::segmenu::m_modified

We need to make sure that the perform object is in control of the modification flag.

Global seq64::seqmenu::seq_clear_perf ()

All of seg_paste() can be offloaded to a (new) perform member function.

Global seq64::seqmenu::seq_copy ()

Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

Global seq64::seqmenu::seq_cut ()

A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

Global seq64::seqmenu::seq_paste ()

All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

Global seq64::seqroll::follow_progress ()

If playback is disabled (such as by a trigger), then do not update the page;

- · When it comes back, make sure we're on the correct page;
- · When it stops, put the window back to the beginning, even if the beginning is not defined as "0".

Global seq64::seqtime::update_pixmap ()

Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

Global seq64::sequence::get_minmax_note_events (int &lowest, int &highest)

For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

Global seq64::sequence::remove (event &e)

Use find instead in sequence::remove()!

Global seq64::triggers::next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_← offset)

It would be a bit simpler to simply return a trigger object, wouldn't it?

Chapter 7

Deprecated List

Global seq64::clock_tick_duration_bogus (int bpm, int ppqn)

This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

Global seq64::sequence::get_name () const

32 Deprecated List

Chapter 8

Namespace Index

8.1	Name	espace	List
0.1	Halli	copacc	

Here is a list of all documented namespaces with brief descriptions:	

seq64 Define this macro to use the new seq24 v \dots ??

34 Namespace Index

Chapter 9

Hierarchical Index

9.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

seq64::AbstractPerfInput
seq64::Seq24PerfInput
seq64::automutex
seq64::click
seq64::configfile
seq64::optionsfile
seq64::userfile
seq64::editable_events
seq64::event
seq64::editable_event
seq64::event_list::event_key
seq64::event_list
seq64::font
seq64::gui_assistant
seq64::gui_assistant_gtk2
seq64::gui_palette_gtk2
seq64::gui_drawingarea_gtk2
seq64::eventslots
seq64::maintime
seq64::mainwid
seq64::perfnames
seq64::perfroll
seq64::perftime
seq64::seqdata
seq64::seqkeys
seq64::seqroll
seq64::seqtime
seq64::gui window gtk2
seq64::eventedit
seq64::mainwnd
seq64::perfedit
seq64::seqedit

36 Hierarchical Index

seq64::jack_assistant
seq64::jack_scratchpad
seq64::keybindentry
seq64::keys_perform
seq64::keys_perform_gtk2
seq64::keys perform transfer
seq64::keystroke
seq64::lash
seq64::mastermidibus
seq64::midi_container
seq64::midi_list
seq64::midi_vector
seq64::midi measures
seq64::midi splitter
seq64::midi timing
seq64::midibus
seq64::midifile
seq64::mutex
seq64::condition_var
seq64::options
seq64::perform
seq64::performcallback
seq64::mainwnd
seq64::rc_settings
seq64::rect
seq64::gui drawingarea gtk2::rect
seq64::Seq24SeqEventInput
seq64::Seq24SeqRollInput
seq64::seqmenu
seg64::mainwid
seq64::perfnames
seq64::sequence
seq64::trigger
seq64::triggers
seq64::user instrument
seq64::user_instrument_t
seq64::user_midi_bus
seq64::user_midi_bus_t
seg64::user settings

Chapter 10

Data Structure Index

10.1 Data Structures

Here are the data structures with brief descriptions:

seq64::AbstractPerfInput	
Provides an abstract base class to provide the minimal interface for the various "perf input"	
classes	??
seq64::automutex	
Provides a mutex that locks automatically when created, and unlocks when destroyed	??
seq64::click	
Encapsulates any possible mouse click	??
seq64::condition_var	
A mutex works best in conjunction with a condition variable	??
seq64::configfile	
This class is the abstract base class for optionsfile and userfile	??
seq64::editable_event	
Provides for the management of MIDI editable events	??
seq64::editable_events	
Provides for the management of an ordered collection MIDI editable events	??
seq64::event	
Provides events for management of MIDI events	??
seq64::event_list::event_key	•
Provides a key value for an event map	??
seq64::event_list	•
Receptable for MIDI events	??
seq64::eventedit	
This class supports an Event Editor that is used to tweak the details of events and get a better	20
idea of the mix of events in a sequence	??
seq64::eventslots This class implements the left-side keyboard in the patterns window	??
seq64::font	
This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in	
XPM format	??
seq64::gui_assistant	• •
This class provides an interface for some of the GUI support needed in Sequencer64	??
seq64::gui assistant gtk2	• •
This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64	??
seq64::gui_drawingarea_gtk2	• •
Implements the basic drawing areas of the application	22

38 Data Structure Index

seq64::gui_palette_gtk2	
Implements a stock palette of Gdk::Color elements	??
seq64::gui_window_gtk2 This class supports a basic interface for Gtk::Window-derived objects	??
seq64::jack_assistant	
This class provides the performance mode JACK support	??
seq64::jack_scratchpad	• •
Provide a temporary structure for passing data and results between a perform and jack_assistant	
object	??
seq64::keybindentry Class for management of application key-bindings	??
seq64::keys_perform	
This class supports the performance mode	??
seq64::keys_perform_gtk2	
This class supports the performance mode	??
	• •
seq64::keys_perform_transfer Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf()	??
seq64::keystroke	
Encapsulates any practical keystroke	??
seq64::lash	• •
This class supports LASH operations, if compiled with LASH support (i.e	??
	• •
seq64::maintime This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure	??
seq64::mainwid	
This class implement the piano roll area of the application	??
seq64::mainwnd	
This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class	??
seq64::mastermidibus	
The class that "supervises" all of the midibus objects?	??
This class is the abstract base class for a container of MIDI track information	??
seq64::midi list	• •
• • •	22
This class is the std::list implementation of the midi_container	??
seq64::midi_measures	
Provides a data structure to hold the numeric equivalent of the measures string "measures ↔	
:beats:divisions" ("m:b:d")	??
seq64::midi_splitter	
This class handles the parsing and writing of MIDI files	??
seq64::midi_timing	
We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song	??
seq64::midi_vector	
This class is the std::vector implementation of the midi_container	??
seq64::midibus	
Provides a class for handling the MIDI buss on Linux	??
seq64::midifile	
This class handles the parsing and writing of MIDI files	??
seq64::mutex	_
Simple wrapper for the pthread_mutex_t type used as a recursive mutex	??
seq64::options	
This class supports a full tabbed options dialog	??
seq64::optionsfile	
Provides a file for reading and writing the application' main configuration file	??

10.1 Data Structures 39

seq64::perfedit	
This class supports a Performance Editor that is used to arrange the patterns/sequences defined	•
in the patterns panel	??
seq64::perfnames This class implements the left-side keyboard in the patterns window	??
seq64::perform	
This class supports the performance mode	??
seq64::performcallback Provides for notification of events	??
seq64::perfroll	
This class implements the performance roll user interface	??
seq64::perftime This class implements drawing the piano time at the top of the "performance window" (the "song	
editor")	??
seq64::rc_settings	• •
This class contains the options formerly named "global_xxxxxxx"	??
seq64::rect	
A small helper class representing a rectangle	??
seq64::gui_drawingarea_gtk2::rect	
A small helper structure representing a rectangle	??
seq64::Seq24PerfInput	
Implements the default (Seq24) performance input characteristics of this application	??
seq64::Seq24SeqEventInput	
This structure implement the normal interaction methods for Seq24	??
seq64::Seq24SeqRollInput	
Implements the Seq24 mouse interaction paradigm for the seqroll	??
seq64::seqdata	00
This class supports drawing piano-roll eventis on a window	??
seq64::seqedit Implements the Pattern Editor, which has references to:	??
seq64::seqevent	• •
Implements the piano event drawing area	??
seq64::seqkeys	
This class implements the left side piano of the pattern/sequence editor	??
seq64::seqmenu	
This class handles the right-click menu of the sequence slots in the pattern window seq64::seqroll	??
Implements the piano roll section of the pattern editor	??
seq64::seqtime	
This class implements the piano time, whatever that is	??
seq64::sequence	
Firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern	??
seq64::trigger	
This class hold a single trigger for a sequence object	??
seq64::triggers	
Receptable the triggers that can be used with a sequence object	??
seq64::user_instrument	
Provides data about the MIDI instruments, readable from the "user" configuration file	??
seq64::user_instrument_t	
This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/sequencer64.usr file	??
seq64::user_midi_bus	_
Provides data about the MIDI busses, readable from the "user" configuration file	??
seq64::user_midi_bus_t	
This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the	
application)	??

40 Data Structure Index

seq64::user_settings	
Holds the current values of sequence settings and settings that can modify the number of se-	
quences and the configuration of the user-interface	??
seq64::userfile	
Supports the user's ~/.config/sequencer64/sequencer64.usr and ~/.seq24usr	
configuration file	??

Chapter 11

Namespace Documentation

11.1 seq64 Namespace Reference

Define this macro to use the new seq24 v.

Data Structures

class AbstractPerfInput

Provides an abstract base class to provide the minimal interface for the various "perf input" classes.

· class automutex

Provides a mutex that locks automatically when created, and unlocks when destroyed.

class click

Encapsulates any possible mouse click.

· class condition_var

A mutex works best in conjunction with a condition variable.

· class configfile

This class is the abstract base class for optionsfile and userfile.

class editable_event

Provides for the management of MIDI editable events.

· class editable_events

Provides for the management of an ordered collection MIDI editable events.

· class event

Provides events for management of MIDI events.

· class event_list

The event_list class is a receptable for MIDI events.

· class eventedit

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.

· class eventslots

This class implements the left-side keyboard in the patterns window.

class font

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

· class gui assistant

This class provides an interface for some of the GUI support needed in Sequencer64.

class gui_assistant_gtk2

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

• class gui_drawingarea_gtk2

Implements the basic drawing areas of the application.

· class gui palette gtk2

Implements a stock palette of Gdk::Color elements.

class gui_window_gtk2

This class supports a basic interface for Gtk::Window-derived objects.

· class jack_assistant

This class provides the performance mode JACK support.

· class jack_scratchpad

Provide a temporary structure for passing data and results between a perform and jack_assistant object.

· class keybindentry

Class for management of application key-bindings.

· class keys perform

This class supports the performance mode.

class keys_perform_gtk2

This class supports the performance mode.

struct keys_perform_transfer

Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf().

· class keystroke

Encapsulates any practical keystroke.

· class lash

This class supports LASH operations, if compiled with LASH support (i.e.

· class maintime

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

· class mainwid

This class implement the piano roll area of the application.

class mainwnd

This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.

· class mastermidibus

The class that "supervises" all of the midibus objects?

· class midi container

This class is the abstract base class for a container of MIDI track information.

class midi_list

This class is the std::list implementation of the midi_container.

· class midi measures

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b:d").

· class midi_splitter

This class handles the parsing and writing of MIDI files.

· class midi timing

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

· class midi vector

This class is the std::vector implementation of the midi_container.

· class midibus

Provides a class for handling the MIDI buss on Linux.

· class midifile

This class handles the parsing and writing of MIDI files.

class mutex

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.

· class options

This class supports a full tabbed options dialog.

· class optionsfile

Provides a file for reading and writing the application' main configuration file.

· class perfedit

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

class perfnames

This class implements the left-side keyboard in the patterns window.

· class perform

This class supports the performance mode.

· struct performcallback

Provides for notification of events.

· class perfroll

This class implements the performance roll user interface.

class perftime

This class implements drawing the piano time at the top of the "performance window" (the "song editor").

· class rc_settings

This class contains the options formerly named "global_xxxxxx".

class rect

A small helper class representing a rectangle.

class Seq24PerfInput

Implements the default (Seq24) performance input characteristics of this application.

struct Seq24SeqEventInput

This structure implement the normal interaction methods for Seq24.

class Seg24SegRollInput

Implements the Seq24 mouse interaction paradigm for the seqroll.

class seqdata

This class supports drawing piano-roll eventis on a window.

· class segedit

Implements the Pattern Editor, which has references to:

· class seqevent

Implements the piano event drawing area.

· class seqkeys

This class implements the left side piano of the pattern/sequence editor.

• class segmenu

This class handles the right-click menu of the sequence slots in the pattern window.

class segroll

Implements the piano roll section of the pattern editor.

· class segtime

This class implements the piano time, whatever that is.

· class sequence

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

· class trigger

This class hold a single trigger for a sequence object.

· class triggers

The triggers class is a receptable the triggers that can be used with a sequence object.

· class user instrument

Provides data about the MIDI instruments, readable from the "user" configuration file.

struct user_instrument_t

This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/sequencer file.

class user_midi_bus

Provides data about the MIDI busses, readable from the "user" configuration file.

· struct user midi bus t

This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the application).

· class user settings

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

class userfile

Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24usr configuration file.

Typedefs

· typedef unsigned char midibyte

Provides a fairly common type definition for a byte value.

· typedef unsigned char bussbyte

Distinguishes a bus number from other MIDI bytes.

· typedef unsigned short midishort

Distinguishes a short value from the unsigned short values implicit in short-valued MIDI numbers.

typedef unsigned long midilong

Distinguishes a long value from the unsigned long values implicit in long-valued MIDI numbers.

· typedef long midipulse

Distinguishes a long value from the unsigned long values implicit in MIDI time measurements.

Enumerations

Functions

bool extract_timing_numbers (const std::string &s, std::string &part_1, std::string &part_2, std::string &part_2, std::string &part_3, std::string &fraction)

Extracts up to 4 numbers from a colon-delimited string.

std::string pulses_to_string (midipulse p)

Converts MIDI pulses (also known as ticks, clocks, or divisions) into a string.

std::string pulses_to_measurestring (midipulse p, const midi_timing &seqparms)

Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats⇔:division").

• bool pulses to midi measures (midipulse p, const midi timing &seqparms, midi measures &measures)

Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats⇔:division").

std::string pulses_to_timestring (midipulse p, int bpm, int ppqn)

Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".

• std::string pulses to timestring (midipulse p, const midi timing &timinginfo)

Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".

midipulse measurestring_to_pulses (const std::string &measures, const midi_timing &seqparms)

Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.

· midipulse midi_measures_to_pulses (const midi_measures &measures, const midi_timing &seqparms)

Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.

midipulse timestring_to_pulses (const std::string ×tring, int bpm, int ppqn)

Converts a string that represents "hours:minutes:seconds.fraction" into a MIDI pulse/ticks/clock value.

midipulse string_to_pulses (const std::string &s, const midi_timing &mt)

Converts a time string to pulses.

midibyte string_to_midibyte (const std::string &s)

Converts a string to a MIDI byte.

• std::string shorten file spec (const std::string &fpath, int leng)

Shortens a file-specification to make sure it is no longer than the provided length value.

bool string_not_void (const std::string &s)

Tests that a string is not empty and has non-space characters.

bool string_is_void (const std::string &s)

Tests that a string is empty or has only white-space characters.

• bool strings_match (const std::string &target, const std::string &x)

Compares two strings for a form of semantic equality, for the purposes of editable_event(), for example.

• int log2_time_sig_value (int tsd)

Calculates the log-base-2 value of a number that is already a power of 2.

void tempo_to_bytes (midibyte t[3], int tempo_us)

Provide a way to convert a tempo value (microseconds per quarter note) into the three bytes needed as value in a Tempo meta event.

• int zoom_power_of_2 (int ppqn)

Calculates a suitable starting zoom value for the given PPQN value.

double beats per minute from tempo (double tempo)

This function calculates the effective beats-per-minute based on the value of a Tempo meta-event.

double tempo_from_beats_per_minute (double bpm)

This function is the inverse of beats_per_minute_from_tempo().

double pulse_length_us (int bpm, int ppqn)

Calculates pulse-length from the BPM (beats-per-minute) and PPQN (pulses-per-quarter-note) values.

• double delta_time_us_to_ticks (unsigned long us, int bpm, int ppqn)

Converts delta time in microseconds to ticks.

• double ticks to delta time us (midipulse delta ticks, int bpm, int ppqn)

Converts the time in ticks ("clocks") to delta time in microseconds.

double clock_tick_duration_bogus (int bpm, int ppqn)

Calculates the duration of a clock tick based on PPQN and BPM settings.

int clock_ticks_from_ppqn (int ppqn)

A simple calculation to convert PPQN to MIDI clock ticks.

double double_ticks_from_ppqn (int ppqn)

A simple calculation to convert PPQN to MIDI clock ticks.

• midipulse measures_to_ticks (int bpm, int ppqn, int bw, int measures=1)

Calculates the length of an integral number of measures, in ticks.

bool help_check (int argc, char *argv[])

Checks to see if the first option is a help or version argument, just so we can skip the "Reading configuration ..." messages.

bool parse_options_files (perform &p, int argc, char *argv[])

Provides the command-line option support, as well as some setup support, extracted from the main routine of Sequencer64.

• int parse command line options (int argc, char *argv[])

Parses the command-line options on behalf of the application.

bool write_options_files (const perform &p)

Saves all options to the "rc" and "user" configuration files.

• std::string to_string (const event &ev)

A free function to convert an event into an informative string, just enough to save some debugging time.

bool file_exists (const std::string &filename)

Checks a file for existence.

bool file readable (const std::string &filename)

Checks a file for readability.

bool file writable (const std::string &filename)

Checks a file for writability.

bool file accessible (const std::string &filename)

Checks a file for readability and writability.

bool file_executable (const std::string &filename)

Checks a file for the ability to be executed.

bool file_is_directory (const std::string &filename)

Checks a file to see if it is a directory.

· bool make_directory (const std::string &pathname)

A function to ensure that the \sim /.config/sequencer64 directory exists.

rc_settings & rc ()

Returns a reference to the global rc_settings object.

• user settings & usr ()

Returns a reference to the global user_settings object, for better encapsulation.

int choose_ppqn (int ppqn)

Common code for handling PPQN settings.

bool ppqn_is_valid (int ppqn)

Common code for handling PPQN settings.

int jack sync callback (jack transport state t state, jack position t *pos, void *arg)

Global functions for JACK support and JACK sessions.

void jack_shutdown_callback (void *arg)

This callback is to shutdown JACK by clearing the jack_assistant::m_jack_running flag.

• void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

• void jack_session_callback (jack_session_event_t *ev, void *arg)

Set the m_jsession_ev (event) value of the perform object.

bool create_lash_driver (perform &p, int argc, char **argv)

Creates and starts a lash object.

• lash * lash driver ()

Provides access to the lash object.

void delete_lash_driver ()

Deletes the last object.

void * output thread func (void *p)

Global functions defined in perform.cpp.

void * input_thread_func (void *myperf)

Set up the performance, and set the process to realtime privileges.

• long min (long a, long b)

min() for long values.

• static std::string make section name (const std::string &label, int value)

Provides a purely internal, ad hoc helper function to create numbered section names for the userfile class.

font & font_render ()

The p_font_renderer pointer was once created in the main module, sequencer64.cpp.

• Gtk::Adjustment & adjustment dummy ()

Provides a way to provide a dummy Gtk::Adjustment object, but not create one until it is actually needed, so that the Glib/Gtk infrastructure is ready for it.

Variables

std::string c_controller_names [SEQ64_MIDI_COUNT_MAX]

Provides the default names of MIDI controllers.

const midibyte EVENT STATUS BIT

This highest bit of the status byte is always 1.

const midibyte EVENT_ANY

Channel Voice Messages.

· const midibyte EVENT MIDI SYSEX

System Messages.

const midibyte EVENT_MIDI_META

0xFF is a MIDI "escape code" used in MIDI files to introduce a MIDI meta event.

const midibyte EVENT SYSEX

A MIDI System Exclusive (SYSEX) message starts with F0, followed by the manufacturer ID (how many? bytes), a number of data bytes, and ended by an F7.

const midibyte EVENT_NULL_CHANNEL

This value of 0xFF is Sequencer64's channel value that indicates that the event's m_channel value is bogus.

const midibyte EVENT_GET_CHAN_MASK

These file masks are used to obtain or to mask off the channel data from a status byte.

· const int c_midibus_output_size

Manifest global constants.

· const midilong c midibus

Provides tags used by the midifile class to control the reading and writing of the extra "proprietary" information stored in a Seq24 MIDI file.

· const int c_midi_track_ctrl

Pseudo control values for associating MIDI events (I think) with automation of some of the controls in seq24.

const bool c_scales_policy [c_scale_size][SEQ64_OCTAVE_SIZE]

Each value in the kind of scale is denoted by a true value in these arrays.

const int c_scales_transpose_up [c_scale_size][SEQ64_OCTAVE_SIZE]

Increment values needed to transpose each scale up so that it remains in the same key.

• const int c_scales_transpose_dn_neg [c_scale_size][SEQ64_OCTAVE_SIZE]

Making these positive makes it easier to read.

• const char c_scales_text [c_scale_size][32]

The names of the supported scales.

const char c_key_text [SEQ64_OCTAVE_SIZE][3]

Provides the entries for the Key dropdown menu in the Pattern Editor window.

• const char c_interval_text [16][3]

Provides the entries for the Interval dropdown menu in the Pattern Editor window.

const char c_chord_text [8][5]

Provides the entries for the Chord dropdown menu in the Pattern Editor window.

const int c_max_instruments

Provides the maximum number of instruments that can be defined in the \sim /. seq24usr or \sim /. config/sequencer64/sequencer file.

const int c_max_busses

Provides the maximum number of MIDI buss definitions supported in the "user" file.

static const std::string versiontext

Sets up the "hardwired" version text for Sequencer64.

static struct option long_options []

A structure for command parsing that provides the long forms of command-line arguments, and associates them with their respective short form.

static const std::string s_arg_list

Provides a complete list of the short options, and is passed to getopt_long().

static rc_settings g_rc_settings

Provide the eventual replacement for all of the other "global_xxx" variables.

• static user_settings g_user_settings

Provide the eventual replacement for all of the other settings in the "user" configuration file, plus some of the "constants" in the globals module.

static lash * s global lash driver

The global pointer to the LASH driver instance.

static const int c_status_replace

Purely internal constants used with the functions that implement MIDI control for the application.

const int c mainwid x

The width of the main pattern/sequence grid, in pixels.

• static const int c_select_all_notes

Actions.

11.1.1 Detailed Description

0.9.3 delta-tick calculation code. This code doesn't quite work for generating the proper rate of MIDI clocks, and so have disabled that code until we can figure out what it is we're doing wrong. Do not enable it unless you are willing to test it.

11.1.2 Typedef Documentation

11.1.2.1 typedef long seq64::midipulse

HOWEVER, CURRENTLY, if you make this value unsigned, then perfroll won't show any notes in the sequence bars!!!

11.1.3 Enumeration Type Documentation

11.1.3.1 enum seq64::seq_modifier_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_SUPER_MASK Bits 13 and 14 are used by XKB, bits 15 to 25 are unused. Bit 29 is used internally.

11.1.3.2 enum seq64::seq_event_type_t

Only the values we need have been grabbed. We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64", but, for convenience (to hide errors? :-D), we keep the number the same.

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

11.1.3.3 enum seq64::seq_scroll_direction_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "SEQ64" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

11.1.3.4 enum seq64::clock_e

Enumerator

e_clock_off A clock enumeration. Not sure yet what these mean.

This enumeration was also defined in midibus_portmidi.h, but we put it into this common module to avoid duplication.

```
Corresponds to the "Off" selection in the MIDI Clock tab. With this setting, the MIDI Clock is disabled for the buss using this setting. Notes will still be sent that buss, of course. Some software synthesizer might require this setting in order to make a sound.
```

- e_clock_pos Corresponds to the "Pos" selection in the MIDI Clock tab. With this setting, MIDI Clock will be sent to this buss, and, if playback is starting beyond tick 0, then MIDI Song Position and MIDI Continue will also be sent on this buss.
- e_clock_mod Corresponds to the "Mod" selection in the MIDI Clock tab. With this setting, MIDI Clock and MIDI Start will be sent. But clocking won't begin until the Song Position has reached the start modulo (in 1/16th notes) that is specified.

11.1.3.5 enum seq64::interaction_method_t

Moved here from the globals.h module.

11.1.3.6 enum seq64::c_music_scales

Scales can be shown in the piano roll as gray bars for reference purposes.

We've added three more scales; there are still a number of them that could be fruitfully added to the list of scales.

It would be good to offload this stuff into a new "scale" class.

11.1.3.7 enum seq64::draw_type

Enumerator

DRAW_FIN Provides a set of methods for drawing certain items.

11.1.4 Function Documentation

- 11.1.4.1 bool seq64::extract_timing_numbers (const std::string & s, std::string & part_1, std::string & part_2, std::string & part_3, std::string & fraction)
 - · measures : beats : divisions
 - "213:4:920"
 - "0:1:0"
 - hours : minutes : seconds . fraction
 - "2:04:12.14"
 - "0:1:2"

Warning

This is not the most efficient implementation you'll ever see. At some point we will tighten it up. This function is tested in the seq64-tests project, in the "calculations_unit_test" module.

Returns

Returns true if a reasonable portion (3 numbers) was good for extraction. The fraction part will start with a period for easier conversion to fractional seconds.

11.1.4.2 std::string seq64::pulses_to_string (midipulse p)

Todo Still needs to be unit tested.

11.1.4.3 std::string seq64::pulses_to_measurestring (midipulse p, const midi timing & seqparms)

Parameters

p	The number of MIDI pulses (clocks, divisions, ticks, you name it) to be converted. If the value is SEQ64_ILLEGAL_PULSE, it is converted to 0, because callers don't generally worry about such niceties, and the least we can do is convert illegal measure-strings (like "000:0:000") to a legal value.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration.

11.1.4.4 bool seq64::pulses_to_midi_measures (midipulse p, const midi_timing & seqparms, midi_measures & measures)

$$m = p * W / (4 * P * B)$$

Parameters

p	Provides the MIDI pulses (as in "pulses per quarter note") that are to be converted to MIDI
	measures format.
seqparms	This small structure provides the beats/measure (B), beat-width (W), and PPQN (P) that hold for the sequence involved in this calculation. The beats/minute (T for tempo) value is not needed.
measures	Provides the current MIDI song time structure holding the results, which are the measures, beats, and divisions values for the time of interest. Note that the measures and beats are corrected to be re 1, not 0.

Returns

Returns true if the calculations were able to be made. The P, B, and W values all need to be greater than 0.

11.1.4.5 std::string seq64::pulses_to_timestring (midipulse p, int bpm, int ppqn)

If the fraction part is 0, then it is not shown. Examples:

```
- "0:0:0"

- "0:0:0.102333"

- "12:3:1"

- "12:3:1.000001"
```

Parameters

р	Provides the number of ticks, pulses, or divisions in the MIDI event time.
bpm	Provides the tempo of the song, in beats/minute.
ppqn	Provides the pulse-per-quarter-note of the song.

11.1.4.6 std::string seq64::pulses_to_timestring (midipulse p, const midi_timing & timinginfo)

See the pulses_to_timestring() overload.

Todo Still needs to be unit tested.

Parameters

р	Provides the number of ticks, pulses, or divisions in the MIDI event time.
timinginfo	Provides the tempo of the song, in beats/minute, and the pulse-per-quarter-note of the song.

11.1.4.7 midipulse seq64::measurestring_to_pulses (const std::string & measures, const midi_timing & seqparms)

Parameters

measures	Provides the current MIDI song time in "measures:beats:divisions" format, where divisions are the MIDI pulses in "pulses-per-quarter-note".
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration.

11.1.4.8 midipulse seq64::midi_measures_to_pulses (const midi_measures & measures, const midi_timing & seqparms)

p = 4 * P * m * B / W p == pulse count (ticks or pulses) m == number of measures B == beats per measure (constant) P == pulses per quarter-note (constant) W == beat width in beats per measure (constant)

Note that the 0-pulse MIDI measure is "1:1:0", which means "at the beginning of the first beat of the first measure, no pulses'. It is not "0:0:0" as one might expect.

Parameters

measures	Provides the current MIDI song time structure holding the measures, beats, and divisions values
	for the time of interest.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the
	sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration. If the pulse-value cannot be calculated, then SEQ64_I \leftarrow LLEGAL_PULSE is returned.

11.1.4.9 midipulse seq64::timestring_to_pulses (const std::string & timestring, int bpm, int ppqn)

Parameters

timestring	The time value to be converted, which must be of the form "hh:mm:ss" or "hh:mm:ss.fraction".
bpm	The beats-per-minute tempo (e.g. 120) of the current MIDI song.
ppqn	The parts-per-quarter note precision (e.g. 192) of the current MIDI song.

Returns

Returns 0 if an error occurred or if the number actually translated to 0.

11.1.4.10 midipulse seq64::string_to_pulses (const std::string & s, const midi_timing & mt)

First, the type of string is deduced by the characters in the string. If the string contains two colons and a decimal point, it is assumed to be a time-string ("hh:mm:ss.frac"); in addition ss will have to be less than 60.

If the string just contains two colons, then it is assumed to be a measure-string ("measures:beats:divisions").

If it has none of the above, it is assumed to be pulses. Testing is not rigorous.

Parameters

5	s	Provides the string to convert to pulses.
1	mt	Provides the structures needed to provide BPM and other values needed for some of the conversions.

Returns

Returns the string as converted to MIDI pulses (divisions, clocks, ticks, whatever you call it).

11.1.4.11 midibyte seq64::string_to_midibyte (const std::string & s)

This function bypasses characters until it finds a digit (whether part of the number or a "0x" construct), and then converts it.

11.1.4.12 std::string seq64::shorten_file_spec (const std::string & fpath, int leng)

This is done by removing character in the middle, if necessary, and replacing them with an ellipse.

This function operates by first trying to find the <code>/home directory</code>. If found, it strips off <code>/home/username and</code> replace it with the Linux \sim replacement for the <code>\$HOME</code> environment variable. This function assumes that the "username" portion *must* exist, and that there's no goofy stuff like double-slashes in the path.

Parameters

fpath	The file specification, including the full path to the file, and the name of the file.
leng	Provides the length to which to limit the string.

Returns

Returns the fpath parameter, possibly shortened to fit within the desired length.

11.1.4.13 bool seq64::string_not_void (const std::string & s)

Provides essentially the opposite test that string_is_void() provides.

Parameters

s The string pointer to check for emptin
--

Returns

Returns 'true' if the pointer is valid, the string has a non-zero length, and is not just white-space.

The definition of white-space is provided by the std::isspace() function/macro.

11.1.4.14 bool seq64::string_is_void (const std::string & s)

Meant to have essentially the opposite result of string_not_void(). The meaning of empty is special here, as it refers to a string being useless as a token:

- · The string is of zero length.
- The string has only white-space characters in it, where the isspace() macro provides the definition of white-space.

Parameters

s The string pointer to check for emptiness.

Returns

Returns 'true' if the string has a zero length, or is only white-space.

11.1.4.15 bool seq64::strings_match (const std::string & target, const std::string & x)

The strings_match() function returns true if the comparison items are identical, without case-sensitivity in character content up to the length of the secondary string. This allows abbreviations to match. (And, in scanning routines, the first match is immediately accepted.)

Parameters

target	The primary string in the comparison. This is the target string, the one we hope to match. It is assumed to be non-empty, and the result is false if it is empty.
Х	The secondary string in the comparison. It must be no longer than the target string, or the match is false.

Returns

Returns true if both strings are are identical in characters, up to the length of the secondary string, with the case of the characters being insignificant. Otherwise, false is returned.

11.1.4.16 int seq64::log2_time_sig_value (int tsd)

Useful in converting a time signature's denominator to a Time Signature meta event's "dd" value.

Parameters

tsd The time signature denominator, which must be a power of 2: 2, 4, 8, 16, or 32.

Returns

Returns the power of 2 that achieves the tsd parameter value.

11.1.4.17 void seq64::tempo_to_bytes (midibyte t[3], int tempo_us)

Recall the format of a Tempo event:

0 FF 51 03 t2 t1 t0 (tempo as number of microseconds per quarter note)

This code is the inverse of the lines of code around line 768 in midifile.cpp, which is basically ((t2 * 256) + t1) * 256 + t0.

As a test case, note that the default tempo is 120 beats/minute, which is equivalent to ttttt=500000 (0x07A120).

Parameters

t	Provides a small array of at least 3 elements to hold each tempo byte.
tempo_us	Provides the temp value in microseconds per quarter note.

11.1.4.18 int seq64::zoom_power_of_2 (int ppqn)

The default starting zoom is 2, but this value is suitable only for PPQN of 192 and below. Also, zoom currently works properly only if it is a power of 2. For starters, we scale the zoom to the selected ppqn, and then shift it each way to get a suitable power of two.

Parameters

ppqn	The ppqn of interest.
------	-----------------------

Returns

Returns the power of 2 appropriate for the given PPQN value.

11.1.4.19 double seq64::beats_per_minute_from_tempo (double tempo) [inline]

The tempo event's numeric value is given in 3 bytes, and is in units of microseconds-per-quarter-note (us/qn).

Parameters

tempo	The value of the Tempo meta-event, in units of us/qn. If this value is 0, we'll get an arithmetic exception.
-------	--

Returns

Returns the beats per minute. If the tempo value is too small, then this function will crash. :-D

11.1.4.20 double seq64::tempo_from_beats_per_minute (double bpm) [inline]

Parameters

bpi	n	The value of beats-per-minute. If this value is 0, we'll get an arithmetic exception.
-----	---	---

Returns

Returns the tempo in qn/us. If the bpm value is too small, then this function will crash. :-D

11.1.4.21 double seq64::pulse_length_us (int bpm, int ppqn) [inline]

The formula for the pulse-length in seconds is:

Parameters

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the pulse length in microseconds. If either parameter is invalid, then this function will crash. :-D

11.1.4.22 double seq64::delta_time_us_to_ticks (unsigned long us, int bpm, int ppqn) [inline]

This function is the inverse of ticks_to_delta_time_us().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

Note that this formula assumes that a beat is a quarter note. If a beat is an eighth note, then the P value would be halved, because there would be only 96 pulses per beat. We will implement an additional function to account for the beat; the current function merely blesses some calculations made in the application.

Parameters

us	The number of microseconds in the delta time.
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the tick value.

11.1.4.23 double seq64::ticks_to_delta_time_us (midipulse delta_ticks, int bpm, int ppqn) [inline]

The inverse of delta_time_us_to_ticks().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

Old: 60000000.0 * double(delta_ticks) / (double(bpm) * double(ppqn));

Parameters

delta_ticks	The number of ticks or "clocks".
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the time value in microseconds.

11.1.4.24 double seq64::clock_tick_duration_bogus (int bpm, int ppqn) [inline]

Deprecated This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

 ${\tt MIDI_CLOCK_IN_PPQN \ is \ 24.}$

Parameters

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an
	arithmetic exception.

Returns

Returns the clock tick duration in microseconds. If either parameter is invalid, this will crash. Who wants to waste time on value checks here? :-D

11.1.4.25 int seq64::clock_ticks_from_ppqn (int ppqn) [inline]

Parameters

ppo	qn	The number of pulses per quarter note. For example, the default value for Seq24 is 192.
-----	----	---

Returns

The integer value of ppqn / 24 [MIDI_CLOCK_IN_PPQN] is returned.

```
11.1.4.26 double seq64::double_ticks_from_ppqn ( int ppqn ) [inline]
```

The same as clock_ticks_from_ppqn(), but returned as a double float.

Parameters

ppqn	The number of pulses per quarter note.
------	--

Returns

The double value of ppqn / 24 [SEQ64_MIDI_CLOCK_IN_PPQN]_is returned.

```
11.1.4.27 midipulse seq64::measures_to_ticks (int bpm, int ppqn, int bw, int measures = 1 ) [inline]
```

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks. The number of pulses is given by the number of quarter notes times the pulses per quarter note. The number of quarter notes is given by the measures times the quarter notes per measure. The quarter notes per measure is given by the beats per measure times 4 divided by beat width beats. So:

```
p = 4 * P * m * B / W
    p == pulse count (ticks or pulses)
    m == number of measures
    B == beats per measure (constant)
    P == pulses per quarter-note (constant)
    W == beat width in beats per measure (constant)
For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4,
P can be 192 (but we want to support higher values), and W is 4.
So p = 100 * 4 * 4 * 192 / 4 = 76800 ticks. Seems small.
```

Parameters

bpm	The B value in the equation, beats/measure.
ppqn	The P value in the equation, pulses/qn.
bw	The W value in the equation, the denominator of the time signature. If this value is 0, we'll get an arithmetic exception (crash), so we just return 0 in this case
measures	The M value in the equation. It defaults to 1, in case one desires a simple "ticks per measure"
	number.

Returns

Returns the L value (ticks or pulses) as calculated via the given equation. If bw is 0, then 0 is returned.

```
11.1.4.28 bool seq64::help_check ( int argc, char * argv[])
```

Also check for the –legacy option. Finally, it also checks for the "?" option that people sometimes use as a guess to get help.

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true only if -V, -version, -h, -help, or "?" were encountered. If the legacy options occurred, then rc().legacy format(true) is called, as a side effect, because it will be needed before we parse the options.

```
11.1.4.29 bool seq64::parse_options_files ( perform & p, int argc, char * argv[] )
```

It probably requires this call preceding: Gtk::Main kit(argc, argv), to strip any GTK+-specific parameters the knowledgeable user may have added. Usage:

```
Gtk::Main kit(argc, argv);
seq64::gui_assistant_gtk2 gui;
seq64::perform p(gui);
```

It also requires the caller to call rc().set_defaults() and usr().set_defaults(). The caller can then use the command-line to make any modifications to the setting that will be used here. The biggest example is the -r/-reveal-alsa-ports option, which determines if the MIDI buss definition strings are read from the 'user' configuration file.

Instead of the legacy Seq24 names, we use the new configuration file-names, located in the \sim /.config/sequencer64 directory. However, if they aren't found, we no longer fall back to the legacy configuration file-names. If the – legacy option is in force, use only the legacy configuration file-name. The code also ensures the directory exists. CURRENTLY LINUX-SPECIFIC. See the rc_settings class for how this works.

```
std::string cfg_dir = seq64::rc().home_config_directory();
if (cfg_dir.empty())
    return EXIT_FAILURE;
```

Change Note ca 2016-04-03 We were parsing the user-file first, but we now need to parse the rc-file first, to get the manual-alsa-ports option, so that we can avoid overriding the port names that the ALSA system provides, if the manual-alsa-option is false.

Parameters

р	Provides the perform object that will be affected by the new parameters.
argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true if the reading of both configuration files succeeded.

11.1.4.30 int seq64::parse_command_line_options (int argc, char * argv[])

Note that, since we call this function twice (once before the configuration files are parsed, and once after), we have to make sure that the global value optind is reset to 0 before calling this function. Note that the traditional reset value for optind is 1, but 0 is used in GNU code to trigger the internal initialization routine of get_opt().

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns the value of optind if no help-related options were provided.

11.1.4.31 bool seq64::write_options_files (const perform & p)

This function gets any legacy global variables, on the theory that they might have been changed.

Returns

Returns true if both files were saved successfully. Even if one write failed, the other might have succeeded.

11.1.4.32 std::string seq64::to_string (const event & ev)

Nothing fancy. If you want that, use the midicvt project.

11.1.4.33 bool seq64::file_exists (const std::string & filename)

Parameters

filename	Provides the name of the file to be checked.
----------	--

Returns

Returns 'true' if the file exists.

11.1.4.34 bool seq64::file_readable (const std::string & filename)

filename	Provides the name of the file to be checked.	
----------	--	--

Returns

Returns 'true' if the file is readable.

11.1.4.35 bool seq64::file_writable (const std::string & filename)

Parameters

filename	Provides the name of the file to be checked.
----------	--

Returns

Returns 'true' if the file is writable.

11.1.4.36 bool seq64::file_accessible (const std::string & filename)

An even stronger test than file_exists. At present, we see no need to distinguish read and write permissions. We assume the file is accessible only if the file has both permissions.

Parameters

the file to be checked.	filename Provides the name	filename	
-------------------------	----------------------------	----------	--

Returns

Returns 'true' if the file is readable and writable.

11.1.4.37 bool seq64::file_executable (const std::string & filename)

Parameters

filename Provides the name of the file to be checked.

Returns

Returns 'true' if the file exists.

11.1.4.38 bool seq64::file_is_directory (const std::string & filename)

This function is also used in the function of the same name in fileutilities.cpp.

filename	Provides the name of the directory to be checked.
----------	---

Returns

Returns 'true' if the file is a directory.

11.1.4.39 bool seq64::make_directory (const std::string & pathname)

This function is actually a little more general than that, but it is not sufficiently general, in general.

Parameters

pathname	Provides the name of the path to create.	The parent directory of the final directory must already exist.
----------	--	---

Returns

Returns true if the path-name exists.

```
11.1.4.40 rc_settings & seq64::rc()
```

Why a function instead of direct variable access? Encapsulation. We are then free to change the way "global" settings are accessed, without changing client code.

```
11.1.4.41 int seq64::choose_ppqn(int ppqn) [inline]
```

Putting it here means we can reduce the reliance on the global ppqn.

Parameters

ppqn	Provides the PPQN value to be used.
------	-------------------------------------

Returns

Returns the ppqn parameter, unless that parameter is SEQ64_USE_DEFAULT_PPQN (-1), then usr().midi ← _ppqn is returned.

11.1.4.42 bool seq64::ppqn_is_valid (int ppqn) [inline]

Validates a PPQN value.

ppqn Provides the PPQN value to be used.
--

Returns

Returns true if the ppqn parameter is between MINIMUM_PPQN and MAXIMUM_PPQN, or is set to SE

Q64_USE_DEFAULT_PPQN (-1).

11.1.4.43 int seq64::jack_sync_callback (jack_transport_state_t state, jack_position_t * pos, void * arg)

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

Parameters

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

11.1.4.44 void seq64::jack_shutdown_callback (void * arg)

Parameters

arg Points to the jack_assistant in charge of JACK support for the perform object.

11.1.4.45 void seq64::jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t * pos, int new_pos, void * arg)

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

http://essej.net/sooperlooper/

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

```
-# Calculate the "delta" ticks based on the current frame, the
    ticks_per_beat, the beats_per_minute, and the frame_rate. The old
    code saves this in a local, the new code assigns it to pos->tick.
-# Old code: save this delta as a positive value.
-# Figure out the settings and modify bar, beat, tick, and
    bar_start_tick. The old and new code seem to have the same intent,
    but it seems like the new code is faster and also correct.
- Old code: Calculations are made by division and mod
        operations.
```

New code: Calculations are made by increments and decrements in a while loop.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

```
11.1.4.46 void seq64::jack_session_callback ( jack_session_event_t * ev, void * arg )
```

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseg64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

Parameters

ev	The JACK event to be set.
arg	The pointer to the jack_assistant object. Currently not checked for nullity.

11.1.4.47 bool seq64::create_lash_driver (perform & p, int argc, char ** argv)

Initializes the lash driver (strips lash-specific command line arguments), then connects to the LASH daemon and polls events.

This function will always be called from the main routine, and called only once. Note that we don't need that darn SEQ64 LASH SUPPORT macro in client code anymore.

р	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

Returns

This function returns true if a lash object was created. This function will not create one in not configured to, if the command-line options did not specify the creation of the LASH driver, or if the LASH driver was already created.

11.1.4.48 lash * seq64::lash_driver()

Returns

Returns the pointer to the LASH driver if it exists. Otherwise a null pointer is returned. The caller *must always check* the return value.

11.1.4.49 void seq64::delete_lash_driver()

This function will always be called from the main routine, once. The other lash-pointer functions will know if the pointer has been deleted.

11.1.4.50 void * seq64::output_thread_func (void * myperf)

Set up the performance, set the process to realtime privileges, and then start the output function.

Parameters

myperf	Provides the perform object instance that is to be used. Its output_func() is called.
--------	---

11.1.4.51 long seq64::min (long a, long b) [inline]

Parameters

а	First operand.
b	Second operand.

11.1.4.52 font& seq64::font_render() [inline]

We've going to render this pointer obsolete, though, and use a smart factory function to ensure the existence of this pointer, and return a reference to the font object.

We wanted to make the font a const object, but mainwid::on_realize() calls the font::init() function with its window object, and using const is impractical. We don't want to force every caller to deal with the overhead of passing even a null window pointer, either.

However, at some point we need some quarantee that the init() function is called before rendering a string. Right now, we guarantee it only by build order.

```
11.1.4.53 Gtk::Adjustment & seq64::adjustment_dummy ( )
```

This static object is used so we have an Adjustment to assign to the Adjustment members for classes that don't use them. Clumsy? We shall see.

Anyway, the parameters for this constructor are value, lower, upper, step-increment, and two more values.

11.1.5 Variable Documentation

```
11.1.5.1 std::string seq64::c_controller_names
```

This array is used only by the seqedit class.

11.1.5.2 const midibyte seq64::EVENT_ANY

The following MIDI events are channel messages. The comments represent the one or two data-bytes of the message.

Note that Channel Mode Messages use the same code as the Control Change, but uses reserved controller numbers ranging from 122 to 127.

The EVENT_ANY (0x00) value may prove to be useful in allowing any event to be dealt with. Not sure yet, but the cost is minimal.

11.1.5.3 const midibyte seq64::EVENT_MIDI_SYSEX

The following MIDI events have no channel. We have included redundant constant variables for the SysEx Start and End bytes just to make it clear that they are part of this sequence of values, though usually treated separately.

Only the following constants are followed by some data bytes:

```
- EVENT_MIDI_SYSEX = 0xF0

- EVENT_MIDI_QUARTER_FRAME = 0xF1 // undefined?

- EVENT_MIDI_SONG_POS = 0xF2

- EVENT_MIDI_SONG_SELECT = 0xF3
```

11.1.5.4 const midibyte seg64::EVENT_NULL_CHANNEL

However, it also means that the channel is encoded in the m_status byte itself. This is our work around to be able to hold a multi-channel SMF 0 track in a sequence. In a Sequencer64 SMF 0 track, every event has a channel. In a Sequencer64 SMF 1 track, the events do not have a channel. Instead, the channel is a global value of the sequence, and is stuffed into each event when the event is played or is written to a MIDI file.

11.1.5.5 const int seq64::c_midibus_output_size

These constants were also defined in midibus_portmidi.h, but we made them common to both implementations here.

11.1.5.6 const midilong seq64::c_midibus

Some of the information is stored with each track (and in the midi_container-derived classes), and some is stored in the proprietary header.

Track (sequencer-specific) data:

c_midibus
c_midich
c_timesig
c_triggers
c_triggers_new
c_musickey
c_musicscale

Footer ("proprietary") data:

```
c_midictrl
c_midiclocks
c_notes
c_bpmtag (beats per minute)
c_mutegroups
c_backsequence
```

Also see the PDF file in the following project for more information about the "proprietary" data:

```
https://github.com/ahlstromcj/sequencer64-doc.git
```

Note that the track data is read from the MIDI file, but not written directly to the MIDI file. Instead, it is stored in the MIDI container as sequences are edited to used these "sequencer-specific" features. Also note that c_triggers has been replaced by c_triggers_new as the code that marks the triggers stored with a sequence.

As an extension, we will eventually grab the last key, scale, and background sequence value selected in a sequence and write them as track data, where they can be read in and applied to a specific sequence, when the sequence is created. These values would not be stored in the legacy format.

Something like this could be done in the "user" configuration file, but then the key and scale would apply to all songs. We don't want that.

We could also add snap and note-length to the per-song defaults, but the "user" configuration file seems like a better place to store these preferences.

11.1.5.7 const int seq64::c_midi_track_ctrl

The lowest value is $c_{seqs_in_set} * 2 = 64$.

I think the reason for that value is to perhaps handle two sets or something like that. Will figure it out later.

The controls are read in from the "rc" configuration files, and are written to the c_midictrl section of the "proprietary" final track in a Seq24/Sequencer64 MIDI file.

11.1.5.8 const bool seq64::c_scales_policy[c_scale_size][SEQ64_OCTAVE_SIZE]

See the following sites for more information:

```
http://method-behind-the-music.com/theory/scalesandkeys/
https://en.wikipedia.org/wiki/Heptatonic_scale
```

Note that melodic minor descends in the same way as the natural minor scale, so it descends differently than it ascends. We don't deal with that trick, at all.

11.1.5.9 const int seq64::c_scales_transpose_up[c_scale_size][SEQ64_OCTAVE_SIZE]

For example, if we simply add 1 semitone to each note, it remains a minor key, but it is in a different minor key. Using the transpositions in these arrays, the minor key remains the same minor key.

```
      Major
      C
      .
      D
      .
      E
      F
      .
      G
      .
      A
      .
      B

      Transpose up
      2
      0
      2
      0
      1
      2
      0
      2
      0
      2
      0
      1

      Result up
      D
      .
      E
      .
      F
      .
      G
      G#
      .
      A#
      .

      Transpose up
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      0
      1
      2
      0
      2
      1
      1
      2
      0
      2
      1
      1
      2
      0
```

11.1.5.10 const int seq64::c_scales_transpose_dn_neg[c_scale_size][SEQ64_OCTAVE_SIZE]

Just remember to negate each value before using it.

```
Major
                С
                    D
                         Ε
                            F
                                 G
                                     Α
                1 0 2
Transpose down
                       0
                         2.
                            1
                              0 2
                                   0
                                     2.
                                          2.
               в.
Result down
               C . D D# .
                            F
Minor
                                G G# .
                                        A# .
Transpose down 2 0 2 1
                         0 2 0 2 1
Result down
               A# . C D
                            D#
                                F
                                   G
                                        G#
                         .
                            F
Harmonic minor
              C . D Eb .
                                G Ab .
Transpose down
                    2.
                       1 .
                            2.
                                2.
               1 .
                                   1
Result down
               В
                    С
                       D
                            Eb .
                                F
                                   G
F
                                G
                                     Α
                                          В
                            2
                            Eb .
                                F
                                   G# .
C whole tone
                    D
                       . E
                              F#
Transpose down
                2.
                    2.
                         2.
                              2.
                            . E
                                  F# .
Result down
               A# .
                    С.
                         D
```

11.1.5.11 const char seq64::c_chord_text[8][5]

However, I have not seen this menu in the GUI! Ah, it only appears if the user has selected a musical scale like Major or Minor.

```
11.1.5.12 const int seq64::c_max_instruments
```

With a value of 64, this is more of a sanity-check than a realistic number of instruments defined by a user.

```
11.1.5.13 const std::string seq64::versiontext [static]
```

This value ultimately comes from the configure.ac script.

```
11.1.5.14 struct option seq64::long_options[] [static]
```

Note the terminating null structure..

```
11.1.5.15 lash* seq64::s_global_lash_driver [static]
```

It is actually hidden in this module now, so that a function can be used in its place.

Like the font renderer, This item was once created in the main module, sequencer64.cpp. Now we make it a safer, more fool-proof, function. However, unlike the font-render, which always exists, the LASH driver is conditional, and might not be wanted. Therefore, we cannot return a reference, because there's no such thing as a null reference in C++. We have to return a pointer.

```
11.1.5.16 const int seq64::c_mainwid_x
```

Affected by the c_mainwid_border and c_mainwid_spacing values.

```
11.1.5.17 const int seq64::c_select_all_notes [static]
```

These variables represent actions that can be applied to a selection of notes. One idea would be to add a swing-quantize action. We will reserve the value here, for notes only; not yet used or part of the action menu.


Chapter 12

Data Structure Documentation

12.1 seq64::AbstractPerfInput Class Reference

Provides an abstract base class to provide the minimal interface for the various "perf input" classes.

Inheritance diagram for seq64::AbstractPerfInput:



12.2 seq64::automutex Class Reference

Provides a mutex that locks automatically when created, and unlocks when destroyed.

Public Member Functions

automutex (mutex &my_mutex)

Principal constructor gets a reference to a mutex parameter, and then locks the mutex.

∼automutex ()

The destructor unlocks the mutex.

Private Attributes

• mutex & m_safety_mutex

Provides the mutex reference to be used for locking.

12.2.1 Detailed Description

This has a couple of benefits. First, it is more threadsafe in the face of exception handling. Secondly, it can be done with just one line of code.

12.3 seq64::click Class Reference

Encapsulates any possible mouse click.

Public Member Functions

• click ()

The constructor for class click.

click (int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SE
 — Q64_NO_MASK)

Principal constructor for class click.

• click (const click &rhs)

Provides a stock copy constructor.

click & operator= (const click &rhs)

Provides a stock principal assignment operator.

• bool is_press () const

'Getter' function for member m_is_press

· bool is left () const

'Getter' function for member m_button to test for the left button.

• bool is_middle () const

'Getter' function for member m_button to test for the middle button.

· bool is right () const

'Getter' function for member m_button to test for the right button.

int x () const

'Getter' function for member m_x

• int y () const

'Getter' function for member m_y

• int button () const

'Getter' function for member m_button

• seq_modifier_t modifier () const

'Getter' function for member m_modifier

bool mod_control () const

'Getter' function for member m_modifier tested for Ctrl key.

• bool mod_control_shift () const

'Getter' function for member m_modifier tested for Ctrl and Shift key.

• bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

• bool m_is_press

Determines if the click was a press or a release event.

• int m_x

The x-coordinate of the click.

• int m v

The y-coordinate of the click.

• int m_button

The button that was pressed or released.

• seq_modifier_t m_modifier

The optional modifier value.

12.3.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.3.2 Constructor & Destructor Documentation

```
12.3.2.1 seq64::click::click()
```

Sets all members to false, zero, or the lowest good value.

```
12.3.2.2 seq64::click::click ( int x, int y, int button = SEQ64_CLICK_BUTTON_LEFT, bool press = true, seq_modifier_t modkey = SEQ64_NO_MASK )
```

This function is the only way to set value for the click members (other than the copy constructor and principal assignment operator.

Parameters

X	The putative x value of the button click.
У	The putative y value of the button click.
button	The value of the button that was clicked, set to 1, 2, or 3.
Generated by I Press	Set to true if the event was a button press, false if it was a button release.
modkey	Indicates which modifier key (such as Ctrl or Alt), if any, was pressed at the same time as the click
	action.

12.3.2.3 seq64::click::click (const click & rhs)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be copied.
-----	---

12.3.3 Member Function Documentation

12.3.3.1 click & seq64::click::operator= (const click & rhs)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be assigned from. The assignment is not made if "this" has the same
	address as this parameter.

Returns

Returns a reference to self for usage in a string of assignments.

12.3.4 Field Documentation

```
12.3.4.1 int seq64::click::m_x [private]
```

0 is the left-most coordinate.

```
12.3.4.2 int seq64::click::m_y [private]
```

0 is the top-most coordinate.

```
12.3.4.3 int seq64::click::m_button [private]
```

Left is 1, mmiddle is 2, and right is 3. These numbers are defined via macros, and are Linux-specific and Gtk-specific.


```
12.3.4.4 seq_modifier_t seq64::click::m_modifier [private]
```

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

12.4 seq64::condition_var Class Reference

A mutex works best in conjunction with a condition variable.

Inheritance diagram for seq64::condition_var:



Public Member Functions

• condition_var ()

Initialize the condition variable with the global variable.

• void wait ()

Waits for the confition variable.

• void signal ()

Signals the confition variable.

Private Attributes

pthread_cond_t m_cond

Provides a class-specific condition variable.

Static Private Attributes

• static const pthread_cond_t cond

Provides a "global" condition variable.

Additional Inherited Members

12.4.1 Detailed Description

Therefore this class derives from the mutex class. A "has-a" relationship might be more logical than this "is-a" relationship.

12.4.2 Field Documentation


12.4.2.1 const pthread_cond_t seq64::condition_var::cond [static], [private]

Define the static condition variable used by all mutex locks.

12.5 seq64::configfile Class Reference

This class is the abstract base class for optionsfile and userfile.

Inheritance diagram for seq64::configfile:



Public Member Functions

• configfile (const std::string &name)

Provides the string constructor for a configuration file.

virtual ~configfile ()

A rote destructor needed for a base class.

Protected Member Functions

• bool next_data_line (std::ifstream &file)

Gets the next line of data from an input stream.

void line_after (std::ifstream &file, const std::string &tag)

This function gets a specific line of text, specified as a tag.

Protected Attributes

• std::string m_name

Provides the name of the configuration file.

char * m d

Points to an allocated buffer that holds the data for the configuration file.

char m_line [SEQ64_LINE_MAX]

The current line of text being processed.

12.5.1 Constructor & Destructor Documentation

12.5.1.1 seq64::configfile::configfile (const std::string & name)

Parameters

name The name of the configuration file.

12.5.2 Member Function Documentation

12.5.2.1 bool seq64::configfile::next_data_line (std::ifstream & file) [protected]

If the line starts with a number-sign, a space (!), or a null, it is skipped, to try the next line. This occurs until an EOF is encountered.

Member m line is a "global" return value.

Parameters

file Points to an input stream. We converted this item to a reference; pointers can be subject to problems. For example, what if someone passes a null pointer?

Returns

Returns true if a presumed data line was found. False is returned if not found before an EOF or a section marker ("[") is found. This is a a new (ca 2016-02-14) feature of this function, to assist in adding new data to the file.

12.5.2.2 void seq64::configfile::line_after (std::ifstream & file, const std::string & tag) [protected]

Then it gets the next non-blank line (i.e. data line) after that.

Parameters

file	Points to the input file stream.
tag	Provides a tag to be found. Lines are read until a match occurs with this tag. Normally, the tag is a
	section marker, such as "[user-interface]". Best to assume an exact match is needed.

12.5.3 Field Documentation


12.5.3.1 char seq64::configfile::m_line[SEQ64_LINE_MAX] [protected]

This member receives an input line, and so needs to be a character buffer.

12.6 seq64::editable_event Class Reference

Provides for the management of MIDI editable events.

Inheritance diagram for seq64::editable_event:



Public Types

Public Member Functions

• editable_event (const editable_events &parent)

This constructor simply initializes all of the class members.

• editable_event (const editable_events &parent, const event &ev)

Event constructor.

· editable event (const editable event &rhs)

This copy constructor initializes most of the class members.

virtual ~editable_event ()

This destructor current is a rote virtual function override.

const editable_events & parent () const

'Getter' function for member m_parent

category t category () const

'Getter' function for member m_category

void category (category_t c)

'Setter' function for member m_category by value Also keeps the m_name_category member in synchrony.

· const std::string & category string () const

'Getter' function for member m_category

void category (const std::string &cs)

'Setter' function for member m_category by value Also keeps the m_name_category member in synchrony, but looks up the name, rather than using the name parameter, to avoid storing abbreviations.

const std::string & timestamp string () const

'Getter' function for member m_name_timestamp

· midipulse timestamp () const

'Getter' function for member event::get_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

void timestamp (midipulse ts)

'Setter' function for member event::set_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

• void timestamp (const std::string &ts_string)

'Setter' function for member event::set_timestamp() [string version]

• std::string time_as_pulses ()

Converts the current time-stamp to a string representation in units of pulses.

std::string time_as_measures ()

Converts the current time-stamp to a string representation in units of measures, beats, and divisions.

std::string time_as_minutes ()

Converts the current time-stamp to a string representation in units of hours, minutes, seconds, and fraction.

void set_status_from_string (const std::string &ts, const std::string &ts, const std::string &ts.
 std::string &ts.

Converts a string into an event status, along with timestamp and data bytes.

std::string format_timestamp ()

Formats the current timestamp member as a string.

• std::string stock_event_string ()

Converts the event into a string desribing the full event.

• std::string status_string () const

'Getter' function for member m_name_status

std::string meta_string () const

'Getter' function for member m_name_meta

std::string seqspec_string () const

'Getter' function for member m_name_seqspec

• std::string channel_string () const

'Getter' function for member m_name_channel

• std::string data_string () const

'Getter' function for member m_name_data

Static Public Member Functions

static std::string value_to_name (midibyte value, category_t cat)

Provides a static lookup function that returns the name, if any, associated with a midibyte value.

static unsigned short name_to_value (const std::string &name, category_t cat)

Provides a static lookup function that returns the value, if any, associated with a name string.

Static Public Attributes

• static const name_value_t sm_category_names []

An array of event categories and their names.

static const name_value_t sm_channel_event_names []

An array of MIDI channel events and their names.

• static const name_value_t sm_system_event_names []

An array of MIDI system events and their names.

static const name value t sm meta event names []

An array of Meta events and their names.

static const name_value_t sm_prop_event_names[]

An array of Sequencer64-specific events and their names.

static const name_value_t *const sm_category_arrays[]

Provides for fast access (no ifs) to the correct name array for the given category.

Private Member Functions

void analyze ()

Analyzes an editable-event to make all the settings it needs.

Private Attributes

const editable_events & m_parent

Provides a reference to the container that holds this event.

category_t m_category

Indicates the overall category of this event, which will be category_channel_message, category_system_message, category_meta_event, and category_prop_event.

std::string m_name_category

Holds the name of the event category for this event.

timestamp_format_t m_format_timestamp

Indicates the format to display the time-stamp.

• std::string m_name_timestamp

Holds the string version of the MIDI pulses time-stamp.

std::string m_name_status

Holds the name of the status value for this event.

std::string m_name_meta

Holds the name of the meta message, if applicable.

• std::string m_name_seqspec

If we eventually implement the editing of the Seq24/Sequencer64 "proprietary" meta sequencer-specific events, the name of the SeqSpec will be stored here.

• std::string m_name_channel

Holds the channel description, if applicable.

std::string m_name_data

Holds the data description, if applicable.

12.6.1 Detailed Description

It makes the following members of an event modifiable using human-readable strings:

- m_timestampm_status
- m_channel
- m data[]

Eventually, it would be nice to be able to edit, or at least view, the SysEx events and the Meta events. Those two will require extensions to make events out of them (SysEx is partly supported).

To the concepts of event, the editable_event class adds a category field and strings to represent all of these members

12.6.2 Member Enumeration Documentation

12.6.2.1 enum seq64::editable_event::category_t

Enumerator

category_name These values determine the major kind of event, which determines what types of events are possible for this editable event object. These tags are accompanied by category names in sm_
category_names[]. The enum values are cast to midibyte values for the purposes of using the lookup infrastructure.

```
Indicates that the lookup needs to be done on the category names, as listed in sm_category_names[].
```

- **category_channel_message** Indicates a channel event, with a value ranging from 0x80 through 0xEF. Some examples are note on/off, control change, and program change. Values are looked up in sm_← channel_event_names[].
- category_system_message Indicates a system event, with a value ranging from 0xF0 through 0xFF. Some examples are SysEx start/end, song position, and stop/start/continue/reset. Values are looked up in sm_system_event_names[].
- **category_meta_event** Indicates a meta event, and there is a second value that is used to look up the name of the meta event, in sm_meta_event_names[].
- *category_prop_event* Indicates a "proprietary", Sequencer64 event. Indicates to look up the name of the event in sm_prop_event_names[]. Not sure if these kinds of events will be stored separately.

12.6.2.2 enum seq64::editable event::timestamp format t

Enumerator

timestamp_measures Provides a code to indicate the desired timestamp format. Three are supported. All editable events will share the same timestamp format, but it seems good to make this a event class member, rather than something imposed from an outside static value. We shall see.

```
This format displays the time in "measures:beats:divisions" format, where measures and beats start at 1. Thus, "1:1:0" is equivalent to 0 pulses or to "0:0:0.0.0" in normal time values.
```

- **timestamp_time** This format displays the time in "hh:mm:second.fraction" format. The value displayed should not depend upon the internal timing parameters of the event.
- **timestamp_pulses** This format specifies a bare pulse format for the timestamp a long integer ranging from 0 on up. Obviously, this representation depends on the PPQN value for the sequence holding this event.

12.6.3 Constructor & Destructor Documentation

12.6.3.1 seq64::editable_event::editable_event (const editable_events & parent)

editable_event::editable_event (): event (), m_category (category_name), m_name_category (), m_format_

timestamp (timestamp_measures), m_name_timestamp (), m_name_status (), m_name_meta (), m_name_

seqspec (), m_name_channel (), m_name_data () { // Empty body } Principal constructor.

12.6.3.2 seg64::editable event::editable event (const editable events & parent, const event & ev)

This function basically adds all of the extra editable_event stuff to a standard event, so that the resulting editable event is container-ready.

12.6.3.3 seq64::editable_event::editable_event (const editable_event & rhs)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx editable_events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs	Provides the editable_event object to be copied.
-----	--

12.6.4 Member Function Documentation

12.6.4.1 std::string seq64::editable_event::value_to_name (midibyte value, editable_event::category_t cat)
[static]

Parameters

value	The MIDI byte value to look up.
cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the name associated with the value. If there is no such name, then an empty string is returned.

12.6.4.2 unsigned short seq64::editable_event::name_to_value (const std::string & name, editable_event::category_t cat
) [static]

The string_match() function, which can match abbreviations, case-insensitively, is used to make the string comparisons.

	name	The string value to look up.	
Ī	cat	The category of the MIDI byte. Each category calls a different name array into play.	

Returns

Returns the value associated with the name. If there is no such value, then SEQ64_END_OF_MIDIBYTE $_{\leftarrow}$ TABLE is returned.

12.6.4.3 void seq64::editable_event::category (category_t c)

Note that a bad value is translated to the value of category_name.

12.6.4.4 void seg64::editable_event::category (const std::string & name)

Note that a bad value is translated to the value of category_name.

12.6.4.5 void seq64::editable_event::timestamp (midipulse ts)

Plus, we also have to set the string version at the same time.

Parameters

ts Provides the timestamp in units of MIDI pulses.

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

12.6.4.6 void seq64::editable_event::timestamp (const std::string & ts_string)

Parameters

ts_string	Provides the timestamp in units of MIDI pulses.
-----------	---

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

12.6.4.7 std::string seq64::editable_event::time_as_measures ()

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

```
12.6.4.8 std::string seq64::editable_event::time_as_minutes ( )
```

Cannot be inlined because of a circular dependency between the editable event and editable events classes.

12.6.4.9 void seq64::editable_event::set_status_from_string (const std::string & ts, const std::string & s, const std::string & sd0, const std::string & sd1)

Currently, this function handles only the following two messages:

- · category_channel_message
- · category_system_message

After all of the numbering member items have been set, they are converted and assigned to the string versions via a call to the analyze() function.

Parameters

ts	Provides the time-stamp string of the event.		
s	Provides the name of the event, such as "Program Change".		
sd0 Provides the string defining the first data byte of the event.			
sd1	Provides the string defining the second data byte of the event, if applicable to the event.		

```
12.6.4.10 std::string seq64::editable_event::format_timestamp()
```

The format of the string representation is of the format selected by the m_format_timestamp member.

```
12.6.4.11 std::string seg64::editable_event::stock_event_string( )
```

We get the time-stamp as a string, make sure the event is fully analyzed so that all items and strings are set correctly.

```
12.6.4.12 void seq64::editable_event::analyze( ) [private]
```

Used in the constructors. Some of the setters indirectly set the appropriate string representation, as well.

Category:

```
This function can figure out if the status byte implies a channel message or a system message, and set the category string as well. However, at this time, detection of Meta events (0xFF) or Proprietary/SeqSpec events (0xFF with 0x2424) aren't able to be detected due to lack of context here (and due to the fact that currently such events are not yet stored in a sequence, and the least-significant-byte gets masked off anyway.)
```

Status:

```
We distinguish between channel and system messages, and then one— and two-byte messages, but don't yet distinguish the data values fully.
```

12.6.5 Field Documentation

12.6.5.1 const editable_event::name_value_t seq64::editable_event::sm_category_names [static]

Initializes the array of event/name pairs for the MIDI events categories.

Terminated by an empty string, the latter being the preferred test, for consistency with the other arrays and because 0 is often a legitimate code value.

12.6.5.2 const editable_event::name_value_t seq64::editable_event::sm_channel_event_names [static]

Initializes the array of event/name pairs for the channel MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

12.6.5.3 const editable_event::name_value_t seq64::editable_event::sm_system_event_names [static]

Initializes the array of event/name pairs for the system MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

12.6.5.4 const editable_event::name_value_t seq64::editable_event::sm_meta_event_names [static]

Initializes the array of event/name pairs for all of the Meta events.

Terminated only by the empty string.

12.6.5.5 const editable_event::name_value_t seq64::editable_event::sm_prop_event_names [static]

Initializes the array of event/name pairs for all of the seq24/sequencer64-specific events.

Terminated only by the empty string. Note that the numbers reflect the masking off of the high-order bits by 0x242400FF.

12.6.5.6 const editable_event::name_value_t *const seq64::editable_event::sm_category_arrays [static]

Contains pointers (references cannot be stored in an array) to the desired array for a given category.

Too bad that an array of references is not possible.

This code could be considered a bit rococo.

```
12.6.5.7 const editable_events& seq64::editable_event::m_parent [private]
```

The container's "children" need to go to their "parent" to get certain items of information.

```
12.6.5.8 category_t seq64::editable_event::m_category [private]
```

The category_name value is not set here, since that category is used only for looking up the human-readable form of the category.

```
12.6.5.9 timestamp_format_t seq64::editable_event::m_format_timestamp [private]
```

The default is to display in timestamp_measures format.

```
12.6.5.10 std::string seq64::editable_event::m_name_status [private]
```

It will include the names of the channel messages and the system messages. The latter includes SysEx and Meta messages.

```
12.6.5.11 std::string seq64::editable_event::m_name_meta [private]
```

If not applicable, this name will be empty.

12.7 seg64::editable_events Class Reference

Provides for the management of an ordered collection MIDI editable events.

Public Member Functions

• editable_events (sequence &seq, int bpm)

This constructor hooks into the sequence object.

• editable_events (const editable_events &rhs)

This copy constructor initializes most of the class members.

• editable_events & operator= (const editable_events &rhs)

This principal assignment operator sets most of the class members.

• virtual \sim editable_events ()

This destructor current is a rote virtual function override.

· const midi_timing & timing () const

'Getter' function for member m_midi_parameters

• midipulse string_to_pulses (const std::string &ts_string) const

Calculates the MIDI pulses (divisions) from a string using one of the free functions of the calculations module.

· bool load_events ()

Accesses the sequence's event-list, iterating through it from beginning to end, wrapping each event in the list in an editable event and inserting it into the editable-event container.

bool save_events ()

Erases the sequence's event container and recreates it using the edited container of editable events.

· Events & events ()

'Getter' function for member m events

· iterator begin ()

'Getter' function for member m_events.begin(), non-constant version.

· const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

• iterator end ()

'Getter' function for member $m_{\text{events.end}}$ (), non-constant version.

• const_iterator end () const

'Getter' function for member m_events.end(), constant version.

· int count () const

Returns the number of events stored in m_events.

bool add (const event &e)

Adds an event, converted to an editable_event, to the internal event list.

• bool add (const editable_event &e)

Adds an editable event to the internal event list.

• bool replace (iterator ie, const editable_event &e)

Provides a wrapper for the iterator form of erase(), which is the only one that the editable_events container uses.

• void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

• iterator current_event () const

'Getter' function for member m_current_event The caller must make sure the iterator is not Events::end().

Private Types

typedef event_list::event_key Key

Types to use to with the multimap implementation.

Private Member Functions

• void current event (iterator cei)

'Setter' function for member m_current_event

Private Attributes

• Events m_events

Holds the editable_events.

· iterator m current event

Points to the current event, which is the event that has just been inserted.

• sequence & m sequence

Provides a reference to the sequence containing the events to be edited.

midi_timing m_midi_parameters

Holds the current settings for the sequence (and usually for the whole MIDI tune as well).

12.7.1 Member Typedef Documentation

12.7.1.1 typedef event_list::event_key seq64::editable_events::Key [private]

These typenames are identical to those used in event_list, but of course they are in the editable_events scope instead.

12.7.2 Constructor & Destructor Documentation

12.7.2.1 seq64::editable_events::editable_events (sequence & seq, int bpm)

Parameters

seq	Provides a reference to the sequence object, which provides the events and some of the MIDI timing parameters.
bpm	Provides the beats/minute value, which the caller figures out how to get and provides in this parameter.

12.7.2.2 seq64::editable_events::editable_events (const editable_events & rhs)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs Provides the editable_events object to be copied.

12.7.3 Member Function Documentation

12.7.3.1 editable_events & seq64::editable_events::operator= (const editable_events & rhs)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs Provides the editable_events object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of editable_eventss.

12.7.3.2 bool seq64::editable_events::load_events()

Note that the new events will not have valid links (actually, no links). These links are used for associating Note Off events with their respective Note On events. To be consistent, we must take the time to reconstitute these links, using event_list::verify_and_link().

Returns

Returns true if the size of the final editable_event container matches the size of the original events container.

```
12.7.3.3 bool seq64::editable_events::save_events()
```

Note that the old events are replaced only if the container of editable events is not empty. There are safer ways for the user to erase all the events.

Todo Consider what to do about the sequence::m_is_modified flag.

Returns

Returns true if the size of the final event container matches the size of the original editable events container.

```
12.7.3.4 int seq64::editable_events::count() const [inline]
```

We like returning an integer instead of size_t, and rename the function so nobody is fooled.

12.7.3.5 bool seq64::editable_events::add (const event & e)

Parameters

e Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

12.7.3.6 bool seq64::editable_events::add (const editable_event & e)

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

Parameters

e Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

Side-effect(s) Sets m_current_event, which can be used right-away in a single-threaded context to get an iterator to the event via the current_event() accessor.

12.7.4	Field	Docum	entation
14.7.7	I ICIG	Docum	ciitatioii

12.7.4.1 iterator seq64::editable_events::m_current_event [private]

(From this event we can get the current time and other parameters.) If the container were a plain map, we could instead use a key to access it. But we can at least use an iterator, rather than a bare pointer.

12.7.4.2 sequence seq64::editable_events::m_sequence [private]

Besides the events, this object also holds the beats/measure, beat-width, and the PPQN value. The beats/minute have to be obtained from the application's perform object, and passed to the editable_events constructor by the caller.


12.7.4.3 midi_timing seq64::editable_events::m_midi_parameters [private]

It holds the beats/minute, beats/measure, beat-width, and PPQN values needed to properly convert MIDI pulse timestamps to time and measure values.

12.8 seq64::event Class Reference

Provides events for management of MIDI events.

Inheritance diagram for seq64::event:



Public Member Functions

event ()

This constructor simply initializes all of the class members.

• event (const event &rhs)

This copy constructor initializes most of the class members.

• event & operator= (const event &rhs)

This principal assignment operator sets most of the class members.

virtual ~event ()

This destructor explicitly deletes m sysex and sets it to null.

bool operator< (const event &rhsevent) const

If the current timestamp equal the event's timestamp, then this function returns true if the current rank is less than the event's rank.

void set_timestamp (midipulse time)

'Setter' function for member m_timestamp

• midipulse get_timestamp () const

'Getter' function for member m_timestamp

• midibyte get_channel () const

'Getter' function for member m channel

bool check_channel (int channel) const

Checks the channel number to see if the event's channel matches it, or if the event has no channel.

void mod_timestamp (midipulse a_mod)

Calculates the value of the current timestamp modulo the given parameter.

void set_status (midibyte status)

Sets the m_status member to the value of status.

void set_status (midibyte eventcode, midibyte channel)

This overload is useful when synthesizing events, such as converting a Note On event with a velocity of zero to a Note Off event.

void set channel (midibyte channel)

Sets the channel "nybble", without modifying the status "nybble".

• midibyte get status () const

'Getter' function for member m_status

void set_data (midibyte d1)

Clears the most-significant-bit of the d1 parameter, and sets it into the first byte of m_data.

void set_data (midibyte d1, midibyte d2)

Clears the most-significant-bit of both parameters, and sets them into the first and second bytes of m_data.

void get_data (midibyte &d0, midibyte &d1) const

Retrieves the two data bytes from m_data[] and copies each into its respective parameter.

void increment_data1 ()

Increments the first data byte (m_data[1]) and clears the most significant bit.

void decrement_data1 ()

Decrements the first data byte $(m_data[1])$ and clears the most significant bit.

void increment_data2 ()

Increments the second data byte (m_data[1]) and clears the most significant bit.

void decrement_data2 ()

Decrements the second data byte (m_data[1]) and clears the most significant bit.

void restart_sysex ()

Deletes and clears out the SYSEX buffer.

bool append_sysex (midibyte *data, int len)

Appends SYSEX data to a new buffer.

• midibyte * get_sysex () const

'Getter' function for member m_sysex

void set_sysex_size (int len)

'Setter' function for member m_sysex_size

• int get_sysex_size () const

'Getter' function for member m_sysex_size

void link (event *a event)

Sets m_has_link and sets m_link to the provided event pointer.

event * get_linked () const

'Getter' function for member m_linked

• bool is_linked () const

'Getter' function for member m_has_link

· void clear_link ()

'Setter' function for member m_has_link

• void paint ()

'Setter' function for member m_painted

· void unpaint ()

'Setter' function for member m_painted

• bool is_painted () const

'Getter' function for member m_painted

· void mark ()

'Setter' function for member m_marked

· void unmark ()

 ${\it 'Setter' function for member m_marked}$

bool is_marked () const

'Getter' function for member m_marked

· void select ()

'Setter' function for member m selected

· void unselect ()

'Setter' function for member m_selected

• bool is_selected () const

'Getter' function for member m_selected

void make_clock ()

Sets m_status to EVENT_MIDI_CLOCK;.

• midibyte data (int index) const

'Getter' function for member m_data[]

• midibyte get_note () const

Assuming m_data[] holds a note, get the note number, which is in the first data byte, m_data[0].

void set_note (midibyte note)

Sets the note number, clearing off the most-significant-bit and assigning it to the first data byte, m_data[0].

• midibyte get_note_velocity () const

'Getter' function for member m_data[1], the note velocity.

void set_note_velocity (int a_vel)

Sets the note velocity, with is held in the second data byte, m_data[1].

• bool is_note_on () const

Returns true if m_status is $EVENT_NOTE_ON$.

bool is_note_off () const

Returns true if m_status is EVENT_NOTE_OFF.

void print () const

Prints out the timestamp, data size, the current status byte, any SYSEX data if present, or the two data bytes for the status byte.

• int get_rank () const

This function is used in sorting MIDI status events (e.g.

Static Public Member Functions

static bool is_channel_msg (midibyte m)

Static test for channel messages/statuses.

static bool is_one_byte_msg (midibyte m)

Static test for channel messages that have only one data byte.

static bool is_two_byte_msg (midibyte m)

Static test for channel messages that have two data bytes.

static bool is_note_msg (midibyte m)

Static test for messages that involve notes and velocity.

static bool is_desired_cc_or_not_cc (midibyte m, midibyte cc, midibyte datum)

Static test for channel messages that are either not control-change messages, or are and match the given controller value

Private Attributes

· midipulse m timestamp

Provides the MIDI timestamp in ticks, otherwise known as the "pulses" in "pulses per quarter note" (PPQN).

· midibyte m status

This is the status byte without the channel.

· midibyte m_channel

In order to be able to handle MIDI channel-splitting of an SMF 0 file, we need to store the channel, even if we override it when playing the MIDI data.

midibyte m_data [SEQ64_MIDI_DATA_BYTE_COUNT]

The two bytes of data for the MIDI event.

• midibyte * m_sysex

Points to the data buffer for SYSEX messages.

int m_sysex_size

Gives the size of the SYSEX message.

event * m_linked

This event is used to link Note Ons and Offs together.

· bool m has link

Indicates that a link has been made.

bool m_selected

Answers the question "is this event selected in editing.".

bool m_marked

Answers the question "is this event marked in processing.".

· bool m_painted

Answers the question "is this event being painted.".

12.8.1 Detailed Description

A MIDI event consists of 3 bytes:

```
-# Status byte, 1sssnnn, where the sss bits specify the type of
message, and the nnnn bits denote the channel number.
The status byte always starts with 0.
```

-# The first data byte, 0xxxxxxx, where the data byte always start with 0, and the xxxxxxx values range from 0 to 127.

-# The second data byte, 0xxxxxxx.

This class may have too many member functions.

12.8.2 Constructor & Destructor Documentation

12.8.2.1 seq64::event::event (const event & rhs)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Note that now events are also copied when creating the editable_events container, so this function is even more important. The event links, for linking Note Off events to their respective Note On events, are dropped. Generally, they will need to be reconstituted by calling the event_list::verify_and_link() function.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links, as noted above.

Parameters

rhs Provides the event object to be copied.

12.8.2.2 seq64::event::~**event()** [virtual]

The restart sysex() function does what we need.

12.8.3 Member Function Documentation

12.8.3.1 event & seq64::event::operator= (const event & rhs)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the member are not set to useful value when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs Provides the event object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of events.

12.8.3.2 bool seq64::event::operator< (const event & rhs) const

Otherwise, it returns true if the current timestamp is less than the event's timestamp.

Warning

The less-than operator is supposed to support a "strict weak ordering", and is supposed to leave equivalent values in the same order they were before the sort. However, every time we load and save our sample MIDI file, events get reversed. Here are program-changes that get reversed:

```
Save N: 0070: 6E 00 C4 48 00 C4 0C 00 C4 57 00 C4 19 00 C4 26 Save N+1: 0070: 6E 00 C4 26 00 C4 19 00 C4 57 00 C4 0C 00 C4 48
```

The 0070 is the offset within the versions of the b4uacuse-seq24.midi file.

Because of this mis-feature, and the very slow speed of loading a MIDI file when Sequencer64 is built for debugging, we are exploring using an std::mulitmap instead of an std::list. Search for occurrences of the SEQ64_USE_EVENT_MAP macro. (This actually works better than a list, for loading MIDI event, we have found, but may cause the upper limit of the number of playing sequences to drop a little, due to the overhead of incrementing multimap iterators versus list iterators).

Parameters

rhs	The object to be compared against.
-----	------------------------------------

Returns

Returns true if the time-stamp and "rank" are less than those of the comparison object.

12.8.3.3 bool seg64::event::check_channel(int channel) const [inline]

Used in the SMF 0 track-splitting code.

Parameters

channel	The channel to check.

Returns

Returns true if the given channel matches the event's channel.

12.8.3.4 static bool seq64::event::is_channel_msg(midibyte m) [inline], [static]

This function requires that the channel data have already been masked off.

Parameters

m The channel status or message byte to be tested.

Returns

Returns true if the byte represents a MIDI channel message.

12.8.3.5 static bool seq64::event::is_one_byte_msg(midibyte m) [inline], [static]

The rest have two.

Parameters

m The channel status or message byte to be tested.

Returns

Returns true if the byte represents a MIDI channel message that has only one data byte. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.3.6 static bool seq64::event::is_two_byte_msg(midibyte m) [inline], [static]

Parameters

m The channel status or message byte to be tested.

Returns

Returns true if the byte represents a MIDI channel message that has two data bytes. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.3.7 static bool seq64::event::is_note_msg(midibyte m) [inline], [static]

Parameters

m The channel status or message byte to be tested.

Returns

Returns true if the byte represents a MIDI note message.

12.8.3.8 static bool seq64::event::is_desired_cc_or_not_cc (midibyte *m*, midibyte *cc*, midibyte *datum*) [inline], [static]

Note

The old logic was the first line, but can be simplified to the second line; the third line shows the abstract representation. Also made sure of this using a couple truth tables.

```
(m != EVENT_CONTROL_CHANGE) || (m == EVENT_CONTROL_CHANGE && d == cc)
    (m != EVENT_CONTROL_CHANGE) || (d == cc)
    a || (! a && b) => a || b

\param m
    The channel status or message byte to be tested.

\param cc
    The desired cc value, which the datum must match, if the message is a control-change message.

\param datum
    The current datum, to be compared to cc, if the message is a control-change message.

\return
    Returns true if the message is not a control-change, or if it is and the cc and datum parameters match.
```

12.8.3.9 void seq64::event::mod_timestamp (midipulse a_mod) [inline]

Parameters

a_mod The value to mod the timestamp against.

Returns

Returns a value ranging from 0 to a_mod-1.

12.8.3.10 void seq64::event::set_status (midibyte status)

If a_status is a channel event, then the channel portion of the status is cleared using a bitwise AND against $EVE \leftarrow NT_CLEAR_CHAN_MASK$.

Found in yet another fork of seq24:

```
// ORL fait de la merde
```

He also provided a very similar routine: set_status_midibus().

Parameters

status

The status byte, perhaps read from a MIDI file or edited in the sequencer's event editor. Sometime, this byte will have the channel nybble masked off. If that is the case, the eventcode/channel overload of this function is more appropriate.

12.8.3.11 void seq64::event::set_status (midibyte eventcode, midibyte channel)

Parameters

eventcode	The status byte, perhaps read from a MIDI file. This byte is assumed to have already had its low nybble cleared by masking against EVENT_CLEAR_CHAN_MASK.
channel	The channel byte. Combined with the event-code, this makes a valid MIDI "status" byte. This byte is assume to have already had its high nybble cleared by masking against
	EVENT_GET_CHAN_MASK.

12.8.3.12 void seq64::event::set_channel (midibyte channel) [inline]

Note that the sequence channel generally overrides this value.

Parameters

channel	The channel byte.
cnannei	i ne channel byte.

12.8.3.13 void seq64::event::set_data (midibyte d1) [inline]

Parameters

d1	The byte value to set. We should make these all "midibytes".
----	--

12.8.3.14 void seq64::event::set_data (midibyte d1, midibyte d2) [inline]

Parameters

d1	The first byte value to set.
d2	The second byte value to set.

12.8.3.15 void seq64::event::get_data (midibyte & d0, midibyte & d1) const [inline]

Parameters

a	10	[out] The return reference for the first byte.
а	11	[out] The return reference for the first byte.

12.8.3.16 bool seq64::event::append_sysex (midibyte* data, int dsize)

First, a buffer of size m_sysex_size+dsize is created. The existing SYSEX data (stored in m_sysex) is copied to this buffer. Then the data represented by data and dsize is appended to that data buffer. Then the original SYSEX buffer, m_sysex, is deleted, and m_sysex is assigned to the new buffer.

Parameters

data	Provides the additional SYSEX data. If not provided, nothing is done, and false is returned.
dsize	Provides the size of the additional SYSEX data. If not provided, nothing is done.

Returns

Returns false if there was an EVENT_SYSEX_END byte in the appended data, or if an error occurred, and the caller needs to stop trying to process the data.

12.8.3.17 int seq64::event::get_rank() const

The ranking, from high to low, is note off, note on, aftertouch, channel pressure, and pitch wheel, control change, and program changes.

note on/off, aftertouch, control change, etc.) The sort order is not determined by the actual status values.

The lower the ranking the more upfront an item comes in the sort order.

Returns

Returns the rank of the current m_status byte.

12.8.4 Field Documentation

```
12.8.4.1 midibyte seq64::event::m_status [private]
```

The channel will be appended on the MIDI bus. The high nibble = type of event; The low nibble = channel. Bit 7 is present in all status bytes.

```
12.8.4.2 midibyte seg64::event::m_channel [private]
```

This member adds another 4 bytes to the event object, most likely.

```
12.8.4.3 midibyte seq64::event::m_data[SEQ64_MIDI_DATA_BYTE_COUNT] [private]
```

Remember that the most-significant bit of a data byte is always 0.

```
12.8.4.4 midibyte* seq64::event::m_sysex [private]
```

This really ought to be a Boost or STD scoped pointer. Currently, it doesn't seem to be used.

```
12.8.4.5 bool seq64::event::m_has_link [private]
```

This item is used [via the get_link() and link() accessors] in the sequence class.

12.9 seq64::event_list::event_key Class Reference

Provides a key value for an event map.

Public Member Functions

event_key (midipulse tstamp, int rank)

Principal event key constructor.

event_key (const event &e)

Event-based constructor.

• bool operator< (const event_key &rhs) const

Provides the minimal operator needed to sort events using an event_key.

Private Attributes

• midipulse m_timestamp

The primary key-value for the key.

• int m_rank

The sub-key-value for the key.

12.9.1 Detailed Description

Its types match the m_timestamp and get_rank() function of this event class.

12.9.2 Constructor & Destructor Documentation

12.9.2.1 seq64::event_list::event_key::event_key (midipulse tstamp, int rank)

Parameters

tstamp	The time-stamp is the primary part of the key. It is the most important key item.
rank	Rank is an arbitrary number used to prioritize events that have the same time-stamp. See the
	event::get_rank() function for more information.

12.9.2.2 seq64::event_list::event_key::event_key (const event & rhs)

This constructor makes it even easier to create an event_key. Note that the call to event::get_rank() makes a simple calculation based on the status of the event.

Parameters

rhs Provides the event key to be c	opied.
------------------------------------	--------

12.9.3 Member Function Documentation

12.9.3.1 bool seq64::event_list::event_key::operator< (const event_key & rhs) const

Parameters

rhs Provides the event key to be compared against.

Returns

Returns true if the rank and timestamp of the current object are less than those of rhs.

12.9.4 Field Documentation

```
12.9.4.1 midipulse seq64::event_list::event_key::m_timestamp [private]
```

12.9.4.2 int seq64::event_list::event_key::m_rank [private]

12.10 seq64::event_list Class Reference

The event_list class is a receptable for MIDI events.

Data Structures

class event_key

Provides a key value for an event map.

Public Member Functions

event_list ()

Principal constructor.

event_list (const event_list &a_rhs)

Copy constructor.

event_list & operator= (const event_list &a_rhs)

Principal assignment operator.

∼event_list ()

A rote destructor.

• iterator begin ()

 ${\it 'Getter' function for member m_events.begin(), non-constant version.}$

• const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

• iterator end ()

'Getter' function for member m_events.end(), non-constant version.

• const_iterator end () const

'Getter' function for member m_events.end(), constant version.

• int count () const

Returns the number of events stored in m_events.

· bool empty () const

Returns true if there are no events.

bool add (const event &e, bool postsort=true)

Adds an event to the internal event list in an optionally sorted manner.

· bool is_modified () const

'Getter' function for member m_is_modified

• void unmodify ()

'Setter' function for member m_is_modified This function may be needed by some of the sequence editors.

void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

void merge (event_list &el, bool presort=true)

Provides a merge operation for the event multimap analogous to the merge operation for the event list.

• void sort ()

Wrapper for std::list::sort(), or, since multimaps are always sorted, an empty function.

Static Public Member Functions

• static event & dref (iterator ie)

Dereference access for list or map.

• static const event & dref (const_iterator ie)

Dereference const access for list or map.

Private Types

typedef std::multimap< event_key, event > Events

Types to use to swap between list and multimap implementations.

Private Member Functions

• void link_new ()

Links a new event.

• void clear_links ()

Clears all event links and unmarks them all.

void verify_and_link (midipulse slength)

This function verifies state: all note-ons have an off, and it links note-offs with their note-ons.

• void mark selected ()

Marks all selected events.

• void mark_out_of_range (midipulse slength)

Marks all events that have a time-stamp that is out of range.

• void mark_all ()

Marks all events.

• void unmark_all ()

Unmarks all events.

void unpaint all ()

Unpaints all list-events.

int count_selected_notes () const

Counts the selected note-on events in the event list.

· bool any selected notes () const

Indicates that at least one note is selected.

• int count_selected_events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

void select_all ()

Selects all events, unconditionally.

void unselect_all ()

Deselects all events, unconditionally.

• void print () const

Prints a list of the currently-held events.

· const Events & events () const

'Getter' function for member m_events

Private Attributes

• Events m_events

This list holds the current pattern/sequence events.

• bool m_is_modified

A new flag to indicate if an event was added or removed.

12.10.1 Detailed Description

Two implementations, an std::multimap, and the original, an std::list, are provided for comparison, and are selected at build time, by manually defining the SEQ64_USE_EVENT_MAP macro near the top of this module.

12.10.2 Constructor & Destructor Documentation

12.10.2.1 seq64::event_list::event_list (const event_list & rhs)

Parameters

rhs Provides the event list to be copied.

12.10.3 Member Function Documentation

12.10.3.1 event_list & seq64::event_list::operator= (const event_list & rhs)

Follows the stock rules for such an operator, just assigning member values.

Parameters

rhs Provides the event list to be assigned.

12.10.3.2 int seq64::event_list::count() const [inline]

We like returning an integer instead of size_t, and rename the function so nobody is fooled.

```
12.10.3.3 bool seq64::event_list::add ( const event & e, bool postsort = true )
```

It is a wrapper, wrapper for insert() or push_front(), with an option to call sort().

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. That's why we're exploring using a multimap as the container.

Parameters

е	Provides the event to be added to the list.
postsort	If true, and the std::list implementation has been built in, then the event list is sorted after the
	addition. This is a time-consuming operation.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

```
12.10.3.4 void seq64::event_list::unmodify() [inline]
```

But use it with great caution.

```
12.10.3.5 void seq64::event_list::remove ( iterator ie ) [inline]
```

Currently, no check on removal is performed. Set the modified-flag.

```
12.10.3.6 void seq64::event_list::clear() [inline]
```

Set the modified-flag.

```
12.10.3.7 void seq64::event_list::merge ( event_list & el, bool presort = true )
```

We have certain constraints to preserve, as the following discussion shows.

For std::list, sequence merges list T into list A by first calling T.sort(), and then A.merge(T). The merge() operation merges T into A by transferring all of its elements, at their respective ordered positions, into A. Both containers must already be ordered.

The merge effectively removes all the elements in T (which becomes empty), and inserts them into their ordered position within container (which expands in size by the number of elements transferred). The operation is performed

without constructing nor destroying any element, whether T is an Ivalue or an rvalue, or whether the value-type supports move-construction or not.

Each element of T is inserted at the position that corresponds to its value according to the strict weak ordering defined by operator <. The resulting order of equivalent elements is stable (i.e. equivalent elements preserve the relative order they had before the call, and existing elements precede those equivalent inserted from x). The function does nothing if (8x == this).

For std::multimap, sorting is automatic. However, unless move-construction is supported, merging will be less efficient than for the list version. Also, we need a way to include duplicates of each event, so we need to use a multimap. Once all this setup, merging is really just insertion. And, since sorting isn't needed, the multimap actually turns out to be faster.

Parameters

el	Provides the event list to be merged into the current event list.
	If true, the events are presorted. This is a requirement for merging an std::list, but is a no-op for the std::multimap implementation.

12.10.3.8 void seq64::event_list::link_new() [private]

This function checks for a note on, then look for its note off. This function is provided in the event_list because it does not depend on any external data. Also note that any desired thread-safety must be provided by the caller.

12.10.3.9 void seq64::event_list::verify_and_link(midipulse slength) [private]

Threadsafe

Parameters

slength	Provides the length beyond which events will be pruned.

12.10.3.10 void seq64::event_list::mark_out_of_range(midipulse slength) [private]

Used for killing (pruning) those events not in range. If the current time-stamp is greater than the length, then the event is marked for pruning.

Note

This code was comparing the timestamp as greater than or equal to the sequence length. However, being equal is fine. This may explain why the midifile code would add one tick to the length of the last note when processing the end-of-track.

Parameters

slength	Provides the length beyond which events will be pruned.
---------	---

```
12.10.3.11 void seq64::event_list::mark_all( ) [private]
```

Not yet used, but might come in handy with the event editor dialog.

```
12.10.3.12 bool seq64::event_list::any_selected_notes( ) const [private]
```

Acts like event_list::count_selected_notes(), but stops after finding a selected note. We could add a flag to count
__selected_notes() to break, I suppose.

```
12.10.3.13 int seq64::event_list::count_selected_events ( midibyte status, midibyte cc ) const [private]
```

If the event is a control change (CC), then it must also match the given CC value.

12.10.4 Field Documentation


12.10.4.1 bool seq64::event_list::m_is_modified [private]

We may need to give client code a way to reload the sequence. This is currently an issue when a seqroll and an eventedit/eventslots are active for the same sequence.

12.11 seq64::eventedit Class Reference

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.

Inheritance diagram for seq64::eventedit:



Public Member Functions

- eventedit (perform &p, sequence &seq)
 - Principal constructor, has a reference to a perform object.
- ∼eventedit ()

This rote constructor does nothing.

void enqueue_draw ()

Helper wrapper for calling perfroll::queue_draw() for one or both eventedits.

• void set_seq_title (const std::string &title)

Sets m_label_seq_name to the title.

void set_seq_time_sig (const std::string &sig)

Sets m_label_time_sig to the time-signature string.

void set_seq_ppqn (const std::string &p)

Sets m_label_ppqn to the parts-per-quarter-note string.

void set_seq_count ()

Sets m_label_ev_count to the number-of-events string.

void set_event_category (const std::string &c)

Sets m label category to the category string.

void set_event_timestamp (const std::string &ts)

Sets m_entry_ev_timestamp to the time-stamp string.

void set_event_name (const std::string &n)

Sets m_entry_ev_name to the name-of-event string.

• void set_event_data_0 (const std::string &d)

Sets m_entry_ev_data_0 to the first data byte string.

void set_event_data_1 (const std::string &d)

Sets m_entry_data_1 to the second data byte string.

void perf_modify ()

Provides a way to mark the perform object as modified, when the modified sequence is saved.

void set dirty (bool flag=true)

Sets the "modified" status of the user-interface.

void v_adjustment (int value)

Sets the parameters for the vertical scroll-bar, using only the value parameter.

void v_adjustment (int value, int lower, int upper)

Sets the parameters for the vertical scroll-bar that is associated with the eventslots event-list user-interface.

Private Member Functions

· void handle delete ()

Initiates the deletion of the current editable event.

• void handle insert ()

Initiates the insertion of a new editable event.

• void handle_modify ()

Passes the edited fields to the current editable event in the eventslot.

• void handle_save ()

Handles saving the edited data back to the original sequence.

• void handle_cancel ()

Cancels the edits and closes the dialog box.

• void on_realize ()

This callback function calls the base-class on_realize() function.

bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on_delete_event (GdkEventAny *event)

Handles an on-delete event.

Private Attributes

• Gtk::Table * m_table

A whole horde of GUI elements.

• Gtk::Label * m label index

Items to size the m_indexslots member.

• Gtk::Label * m_label_seq_name

Items for the inside of the m_showbox member.

Gtk::Label * m_label_category

Items for the inside of the m_editbox member.

• Gtk::Label * m_label_right

Padding for the right side of the user-interface.

sequence & m_seq

A reference to the sequence being edited, to control its editing flag.

Additional Inherited Members

12.11.1 Constructor & Destructor Documentation

12.11.1.1 seq64::eventedit::eventedit (perform & p, sequence & seq)

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Adjustment parameters:

```
value initial value lower minimum value upper maximum value step_increment step increment page_increment page_size page size
```

Table constructor parameters:

```
rows
columns
homogenous
```

Table attach() parameters:


```
child widget to add.

left_attach column number to attach left side of a child widget right_attach column number to attach right side of a child widget top_attach row number to attach the top of a child widget bottom_attach row number to attach the bottom of a child widget xoptions properties of the child widget when table resized yoptions same as xoptions, except vertical.

xpadding padding on L and R of widget added to table ypadding amount of padding above and below the child widget
```

Layout:

```
We're going to change the layout.
```



Parameters

р	Refers to the main performance object.
seq	Refers to the sequence holding the event data to be edited.

12.11.1.2 seq64::eventedit::~eventedit()

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.11.2 Member Function Documentation

12.11.2.1 void seq64::eventedit::set_seq_title (const std::string & title)

Parameters

titlo	The name of the sequence.
uue	The name of the sequence.

12.11.2.2 void seq64::eventedit::set_seq_time_sig (const std::string & sig)

Parameters

sig	The time signature of the sequence.

12.11.2.3 void seq64::eventedit::set_seq_ppqn (const std::string & p)

Parameters

p The parts-per-quarter-note string for the sequence.

12.11.2.4 void seq64::eventedit::set_event_category (const std::string & c)

Parameters

c The category string for the current event.

12.11.2.5 void seq64::eventedit::set_event_timestamp (const std::string & ts)

Parameters

ts The time-stamp string for the current event.

12.11.2.6 void seq64::eventedit::set_event_name (const std::string & n)

Parameters

n The name-of-event string for the current event.

12.11.2.7 void seq64::eventedit::set_event_data_0 (const std::string & d)

Parameters

d The first data byte string for the current event.

12.11.2.8 void seq64::eventedit::set_event_data_1 (const std::string & d)

Parameters

d The second data byte string for the current event.

12.11.2.9 void seq64::eventedit::set_dirty (bool flag = true)

This includes changing a label and enabling/disabling the Save button.

Parameters

flag If true, the modified status is indicated, otherwise it is cleared.

12.11.2.10 void seq64::eventedit::v_adjustment (int value)

This function overload provides a common use case.

Parameters

value The new current value to be indicated by the scroll-bar.

```
12.11.2.11 void seq64::eventedit::v_adjustment ( int value, int lower, int upper )
```

It keeps the frame scroll-bar in sync with the frame movement actions. Some of the parameters are obtained from the eventslots object:

```
Page size comes from eventslots::line_maximum().Page increment is a little less than the page-size value.
```

Parameters

value	value The current value to be indicated by the scroll-bar. It will lie between the lower and upper parameter	
lower	The lowest value to be indicated by the scroll-bar.	
upper	The highest value to be indicated by the scroll-bar.	

```
12.11.2.12 void seq64::eventedit::handle_insert() [private]
```

The event's location will be determined by the timestamp and existing events. Note that we have to recalibrate the scroll-bar when we insert/delete events by calling v adjustment().

```
12.11.2.13 void seq64::eventedit::handle_modify() [private]
```

Note that there are two cases to worry about. If the timestamp has not changed, then we can simply modify the existing current event in place. Otherwise, we need to delete the old event and insert the new one. But that is done for us by eventslots::modify_current_event().

```
12.11.2.14 void seq64::eventedit::handle_save( ) [private]
```

The event list in the original sequence is cleared, and the editable events are converted to plain events, and added to the container, one by one.

Todo Could also support writing the events to a new sequence, for added flexibility.

```
12.11.2.15 bool seq64::eventedit::on_key_press_event ( GdkEventKey * ev ) [private]
```

If the Up or Down arrow is pressed (later, k and j :-), then we tell the eventslots object to move the "current event" highlighting up or down. In Gtkmm, these arrows also cause movement from one edit field to the next, so we disable that process if the event was handled here.

Note that some vi-like keys were supported, but they are needed for the edit fields, so cannot be used here. Also, the Delete key is needed for the edit fields. For now, we replace it with the asterisk, which is easy to access from the numeric pad of a keyboard, and allows for rapid deletion. The Insert key also causes confusing effects in the edit fields, so we replace it by the slash. Note that the asterisk and slash should not be required in any of the edit fields.

HOWEVER, there are still some issues with "/", so you'll just have to click the button to insert an event.

Parameters
ev The key event to process.
Returns
Returns true if the event got handled somewhere along the line.
12.11.2.16 bool seq64::eventedit::on_delete_event(GdkEventAny * event) [private]
It sets the sequence object's editing flag to false, and deletes "this". This function is called if the "Close" ("X") button
in the window's title bar is clicked. That is a different action from clicking the Close button.
Returns
Always returns false.
Always returns raise.
12.12 seq64::eventslots Class Reference

This class implements the left-side keyboard in the patterns window.

Inheritance diagram for seq64::eventslots:



Public Member Functions

- eventslots (perform &p, eventedit &parent, sequence &seq, Gtk::Adjustment &vadjust)

 Principal constructor for this user-interface object.
- int event_count () const

'Getter' function for member m_event_count Returns the number of total events in the sequence represented by the eventslots object.

• int line_count () const

'Getter' function for member m_line_count Returns the current number of rows (events) in the eventslots's display.

int line_maximum () const

'Getter' function for member m_line_maximum Returns the maximum number of rows (events) in the eventslots's display.

· int line_increment () const

Provides the "page increment" or "line increment" of the frame, This value is the current line-maximum of the frame minus its overlap value.

int top_index () const

'Getter' function for member m_top_index

· int current index () const

'Getter' function for member m_current_index

• int pager_index () const

'Getter' function for member m_pager_index

Private Member Functions

· bool load events ()

Grabs the event list from the sequence and uses it to fill the editable-event list.

· void set current event (const editable events::iterator ei, int index, bool full redraw=true)

Set the current event, which is the event that is highlighted.

bool insert_event (const editable_event &edev)

Inserts an event.

 bool insert_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Inserts an event based on the setting provided, which the eventedit object gets from its Entry fields.

bool delete_current_event ()

Deletes the current event, and makes adjustments due to that deletion.

bool modify_current_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Modifies the data in the currently-selected event.

· bool save_events ()

Writes the events back to the sequence.

• void select event (int event index=SEQ64 NULL EVENT INDEX, bool full redraw=true)

Selects and highlights the event that is located in the frame at the given event index.

 void set_text (const std::string &evcategory, const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Sets the text in the parent dialog, eventedit.

void enqueue_draw ()

Wraps queue_draw().

int convert_y (int y)

Converts a y-value into an event index relative to 0 (the top of the eventslots window/pixmap) and returns it.

void draw_event (editable_events::iterator ei, int index)

Draw the given slot/event.

• void draw events ()

Draws all of the events in the current eventslots frame.

void change_vert ()

Change the vertical offset of events.

void page movement (int new value)

Adjusts the vertical position of the frame according to the given new scrollbar/vadjust value.

void page_topper (editable_events::iterator newcurrent)

Adjusts the vertical position of the frame according to the given new bottom iterator.

• int decrement_top ()

Decrements the top iterator, if possible.

int increment_top ()

Increments the top iterator, if possible.

• int decrement current ()

Decrements the current iterator, if possible.

int increment current ()

Increments the current iterator, if possible.

• int decrement_bottom ()

Decrements the bottom iterator, if possible.

int increment_bottom ()

Increments the bottom iterator, if possible.

void update pixmap ()

This function does nothing.

· void draw area ()

This function does nothing.

· void redraw ()

Redraw the given sequence.

• void on_realize ()

Handles the callback when the window is realized.

bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

• bool on_button_press_event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button.

• bool on_button_release_event (GdkEventButton *ev)

Handles a button-release for the right button, bringing up a popup menu.

• bool on_focus_in_event (GdkEventFocus *ev)

This callback is an attempt to get keyboard focus into the eventslots pixmap area.

bool on_focus_out_event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

• bool on_scroll_event (GdkEventScroll *ev)

Handle the scrolling of the window.

void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

void on_move_up ()

Move to the previous event.

void on_move_down ()

Move to the next event.

void on_frame_up ()

Move to the previous frame.

• void on_frame_down ()

Move to the next frame.

void on_frame_home ()

Move to the first frame.

• void on frame end ()

Move to the last frame.

Private Attributes

· eventedit & m_parent

Provides a link to the eventedit that created this object.

• sequence & m_seq

Provides a reference to the sequence that this dialog is meant to view or modify.

editable_events m_event_container

Holds the editable events for this sequence.

int m_slots_chars

Provides the number of the characters in the name box.

int m_char_w

Provides the "real" width of a character.

· int m setbox w

Provides the width of the "set number" box.

int m_slots_box_w

Provides the width of the "slot" box.

int m_slots_x

Provides the width of the names box, which is the width of a character for 24 characters.

int m_slots_y

Provides the height of the names box, which is hardwired to 24 pixels.

int m_xy_offset

Provides the horizontal and vertical offsets of the text relative to the names box.

· int m_event_count

The current number of events in the edited container.

• int m_line_count

Counts the number of displayed events, which depends on how many events there are (m_event_count) and the size of the event list (m_line_maximum).

• int m_line_maximum

Counts the maximum number of displayed events, which depends on the size of the event list (and thus the size of the dialog box for the event editor).

· int m_line_overlap

Provides a little overlap for paging through the frame.

int m_top_index

The index of the event that is 0th in the visible list of events.

• int m_current_index

Indicates the index of the current event within the frame.

editable_events::iterator m_top_iterator

Provides the top "pointer" to the start of the editable-events section that is being shown in the user-interface.

• editable_events::iterator m_bottom_iterator

Provides the bottom "pointer" to the end of the editable-events section that is being shown in the user-interface.

• editable_events::iterator m_current_iterator

Provides the "pointer" to the event currently in focus.

· int m pager index

Indicates the event index that matches the index value of the vertical pager.

Additional Inherited Members

12.12.1 Member Function Documentation

12.12.1.1 bool seq64::eventslots::load_events() [private]

Determines how many events can be shown in the GUI [later] and adjusts the top and bottom editable-event iterators to show the first page of events.

Returns

Returns true if the event iterators were able to be set up as valid.

12.12.1.2 void seq64::eventslots::set_current_event (const editable_events::iterator *ei*, int *index*, bool *full_redraw* = true) [private]

Note in the snprintf() calls that the first digit is part of the data byte, so that translation is easier.

Parameters

ei	The iterator that points to the event.
index	The index (re 0) of the event, starting at the top line of the frame. It is a frame index, not a container index.
full_redraw	If true (the default) does a full redraw of the frame. Otherwise, only the current event is drawn. Generally, the only time a single event (actually, two adjacent events) is convenient to draw is when using the arrow keys, where the speed of keystroke auto-repeats makes the full-frame update scrolling very flickery and disconcerting.

12.12.1.3 bool seq64::eventslots::insert_event (const editable_event & edev) [private]

What actually happens here depends if the new event is before the frame, within the frame, or after the frame, based on the timestamp.

If before the frame: To keep the previous events visible, we do not need to increment the iterators (insertion does not affect multimap iterators), but we do need to increment their indices. The contents shown in the frame should not change.

If at the frame top: The new timestamp equals the top timestamp. We don't know exactly where the new event goes in the multimap, but we do have an new event.

If at the frame bottom: TODO

If after the frame: No action needed if the bottom event is actually at the bottom of the frame. But if the frame is not yet filled, we need to increment the bottom iterator, and its index.

Note

Actually, it is far easier to just adjust all the counts and iterators and redraw the screen, as done by the page_topper() function.

Parameters

edev	The event to insert, prebuilt.
------	--------------------------------

Returns

Returns true if the event was inserted.

12.12.1.4 bool seq64::eventslots::insert_event (const std::string & evtimestamp, const std::string & evname, const std::string & evdata0, const std::string & evdata1) [private]

It calls the other insert_event() overload.

Note that we need to qualify the temporary event class object we create below, with the seq64 namespace, otherwise the compiler thinks we're trying to access some Gtkmm thing.

Parameters

evtimestamp	The time-stamp of the new event, as obtained from the event-edit timestamp field.	
evname	The type name (status name) of the new event, as obtained from the event-edit event-name	
	field.	
evdata0	The first data byte of the new event, as obtained from the event-edit data 1 field.	
evdata1	The second data byte of the new event, as obtained from the event-edit data 2 field. Used only	
	for two-parameter events.	

Returns

Returns true if the event was inserted.

```
12.12.1.5 bool seq64::eventslots::delete_current_event( ) [private]
```

To delete the current event, this function moves the current iterator to the next event, deletes the previously-current iterator, adjusts the event count and the bottom iterator, and redraws the pixmap. The exact changes depend upon whether the deleted event was at the top of the visible frame, within the visible frame, or at the bottom the visible frame. Note that only visible events can be the current event, and thus get deleted.

```
Event Index

0
1
2     Top
3     <----- Top case: The new top iterator, index becomes 2
4
.
.     Inside of Visible Frame
.
43
44     Bottom
45     <----- Top case: The new bottom iterator, index becomes 44
Bottom case: Same result
```

Basically, when an event is deleted, the frame (delimited by the event-index members) stays in place, while the frame iterators move to the previous event. If the top of the frame would move to before the first event, then the frame must shrink.

Top case: If the current iterator is the top (of the frame) iterator, then the top iterator needs to be incremented. The new top event has the same index as the now-gone top event. The index of the bottom event is decremented, since an event before it is now gone. The bottom iterator moves to the next event, which is now at the bottom of the frame. The current event is treated like the top event.

Inside case: If the current iterator is in the middle of the frame, the top iterator and index remain unchanged. The current iterator is incremented, but its index is now the same as the old bottom index. Same for the bottom iterator.

Bottom case: If the current iterator (and bottom iterator) point to the last event in the frame, then both of them need to be decremented. The frame needs to be moved up by one event, so that the current event remains at the bottom (it's just simpler to manage that way).

If there is no event after the bottom of the frame, the iterators that now point to end() must backtrack one event. If the container becomes empty, then everything is invalidated.

Returns

Returns true if the delete was possible. If the container was empty or became empty, then false is returned.

12.12.1.6 bool seq64::eventslots::modify_current_event (const std::string & evtimestamp, const std::string & evname, const std::string & evdata0, const std::string & evdata1) [private]

If the timestamp has changed, however, we can't just modify the event in place. Instead, we finish modifying the event, but tell the caller to delete and reinsert the new event (in its proper new location based on timestamp).

This function always copies the original event, modifiles the copy, deletes the original event, and inserts the "new" event into the editable-event container.

Parameters

evtimestamp	Provides the new event time-stamp as edited by the user.
evname	Provides the event name as edited by the user.
evdata0	Provides the time-stamp as edited by the user.
evtimestamp	Provides the time-stamp as edited by the user.

Returns

Returns true simply if the event-count is greater than 0.

12.12.1.7 bool seq64::eventslots::save_events() [private]

Also sets the dirty flag for the sequence, via the sequence::add_event() function, but this doesn't seem to set the perform dirty flag. So now we pass the modification buck to the parent, who passes it to the perform object.

We added a copy_events() function in the sequence class to replace add_event() for the purpose of reconstructing the events container for the sequence. It is locked by a mutex, and so will not draw until all is done, preventing a nasty segfault (all segfaults are nasty).

We create a new plain event container here, and then passing it to the new locked/threadsafe sequence::copy_ events() function that clears the sequence container and copies the events from the parameter container.

Note that this code will operate event if all events were deleted.

Returns

Returns true if the operations succeeded.

```
12.12.1.8 void seq64::eventslots::select_event ( int event_index = SEQ64_NULL_EVENT_INDEX, bool full_redraw = true ) [private]
```

The event index is provided by converting the y-coordinate of the mouse pointer into a slot number, and then an event index (actually the slot-distance from the m_top_iterator. Confusing, yes no?

Note that, if the event index is negative, then we just queue up a draw operation, which should paint an empty frame – the event container is empty.

Parameters

event_index	Provides the numeric index of the event in the event frame, or SEQ64_NULL_EVENT if there is
	no event to draw.
full_redraw	Defaulting to true, this parameter can be set to false in some case to reduce the flickering of the
	frame under fast movement.

12.12.1.9 void seq64::eventslots::set_text (const std::string & evcategory, const std::string & evtimestamp, const std::string & evdata0, const std::string & evdata1) [private]

Parameters

evtimestamp	The event time-stamp to be set in the parent.
evname	The event name to be set in the parent.
evdata0	The first event data byte to be set in the parent.
evdata1	The second event data byte to be set in the parent.

12.12.1.10 int seq64::eventslots::convert_y (int y) [private]

Parameters

y The y coordinate of the position of the mouse click in the eventslot window/pixmap.

Returns

Returns the index of the event position in the user-interface, which should range from 0 to m_line_count.

```
12.12.1.11 void seq64::eventslots::draw_event ( editable_events::iterator ei, int index ) [private]
```

The slot contains the event details in (so far) one line of text in the box:

| timestamp | event kind | channel | data 0 name + value | data 1 name + value

Currently, this view shows only events that get copied to the sequence's event list. This rules out the following items from the view:

```
    MThd (song header)
    MTrk and Meta TrkEnd (track marker, a sequence has only one track)
    SeqNr (sequence number)
    SeqSpec (but there are three that might appear, see below)
    Meta TrkName
```

The events that are shown in this view are:

```
- One-data-value events:
- Program Change
- Channel Pressure
- Two-data-value events:
- Note Off
- Note On
- Aftertouch
- Control Change
- Pitch Wheel
- Other:
- SysEx events, with partial show of data bytes
- SeqSpec events (TBD):
- Key
- Scale
- Background sequence
```

The index of the event is shown in the editor portion of the eventedit dialog.

```
12.12.1.12 void seq64::eventslots::draw_events( ) [private]
```

It first clears the whole bitmap to white, so that no artifacts from the previous state of the frame are left behind. Need to figure out how to calculate the number of displayable events.

```
m_line_maximum = ???

12.12.1.13 void seq64::eventslots::change_vert( ) [private]
```

Note that m_vadjust is the Gtk::Adjustment object that the eventedit parent passes to the gui_drawingarea_gtk2 constructor.

The top-event and bottom-event indices (and their corresponding editable-event iterators) delimit the part of the event container that is displayed in the eventslots user-interface. The top-event index starts at 0, and the bottom-event is larger (initially, by 42 slots).

When the scroll-bar thumb moves up or down, we need to change both event indices and both event iterators by the corresponding amount. Luckily, the std::multimap iterator is bidirectional.

Note that we may need to reduce the movement of events to a value less than a page; it can be limited backwards by the value of the top index, and forward by the value of the bottom index.

```
12.12.1.14 void seq64::eventslots::page_movement(int new_value) [private]
```

The adjustment is done via movement from the current position.

Do we even need a way to detect excess movement? The scrollbar, if properly set up, should never move the frame too high or too low. Verified by testing.

Parameters

new value 1 lovides the new value of the scrollbal position.	new value	Provides the new value of the scrollbar position.
--	-----------	---

12.12.1.15 void seq64::eventslots::page_topper(editable_events::iterator newcurrent) [private]

The adjustment is done "from scratch". We've found page movement to be an insoluable problem in some editing circumstances. So now we move to the inserted event, and make it the top event.

However, always moving an inserted event to the top is a bit annoying. So now we backtrack so that the inserted event is at the bottom.

Parameters

12.12.1.16 int seq64::eventslots::decrement_top() [private]

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

12.12.1.17 int seq64::eventslots::increment_top() [private]

Also handles the top-event index, so that the GUI can display the proper event numbers.

Returns

Returns the top index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented, or would increment to the end of the container.

12.12.1.18 int seq64::eventslots::decrement_current() [private]

Returns

Returns the decremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

12.12.1.19 int seq64::eventslots::increment_current() [private]

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

```
12.12.1.20 int seq64::eventslots::decrement_bottom( ) [private]
```

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

```
12.12.1.21 int seq64::eventslots::increment_bottom() [private]
```

There is an issue in paging down using the scrollbar where, at the bottom of the scrolling, the bottom iterator ends up bad. Not yet sure how this happens, so for now we backtrack one event if this happens.

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented.

```
12.12.1.22 void seq64::eventslots::on_realize( ) [private]
```

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

```
12.12.1.23 bool seq64::eventslots::on_expose_event ( GdkEventExpose * ev ) [private]
```

It draws all of the sequences.

```
12.12.1.24 bool seq64::eventslots::on_focus_in_event( GdkEventFocus * ev ) [private]
```

See the same function in the perfroll module.

```
12.12.1.25 void seq64::eventslots::on_size_allocate( Gtk::Allocation & a ) [private]
```

It first calls the base-class version of this function.

```
12.12.1.26 void seq64::eventslots::on_move_up() [private]
```

We must scroll up if the event is now before the frame, and should be made the new top event of the frame. Note that this function isn't really an event-response callback. It is called byh eventedit::on_key_press_event().

```
12.12.1.27 void seq64::eventslots::on_move_down( ) [private]
```

We must scroll down if the event is now after the frame. Note that this function isn't really an event-response callback. It is called byh eventedit::on_key_press_event().

12.12.2 Field Documentation

12.12.2.1 int seq64::eventslots::m_slots_chars [private]

Pretty much hardwired to 24 at present.

12.12.2.2 int seq64::eventslots::m_char_w [private]

This value is obtained from a font-renderer accessor function.

12.12.2.3 int seq64::eventslots::m_setbox_w [private]

This used to be hardwired to 6 * 2 (character-width times two).

12.12.2.4 int seq64::eventslots::m_slots_y [private]

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

12.12.2.5 int seq64::eventslots::m_xy_offset [private]

Currently hardwired.

12.12.2.6 int seq64::eventslots::m_top_index [private]

It is used in numbering the events that are shown in the event-slot frame. Do not confuse it with m_current_index, which is relative to the frame, not the container-beginning.

12.12.2.7 int seq64::eventslots::m_current_index [private]

This event will also be pointed to by the m_current_event iterator. Do not confuse it with m_top_index, which is relative to the container-beginning, not the frame.

12.13 seg64::font Class Reference

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

Public Types

Public Member Functions

• font ()

Rote default constructor.

void init (Glib::RefPtr< Gdk::Window > windo)

Initialization function for a window on which fonts will be drawn.

void render_string_on_drawable (Glib::RefPtr< Gdk::GC > m_gc, int x, int y, Glib::RefPtr< Gdk::Drawable > drawable, const char *str, font::Color col) const

Draws a text string.

• int char_width () const

'Getter' function for member m font w

• int char_height () const

'Getter' function for member m_font_h

• int padded_height () const

'Getter' function for member m_padded_h

Private Attributes

· bool m use new font

If true, use the new font, which is a little bit more modern looking.

int m_cell_w

Specifies the cell width of the whole cell.

• int m_cell_h

Specfies the cell height of the whole cell.

int m_font_w

Specifies the exact width of a character cell, in pixels.

• int m font h

Specifies the exact height of a character cell, in pixels.

int m_offset

Provides an ad hoc small horizontal or vertical offset for printing strings.

int m_padded_h

Provides a common constant used by much of the drawing code, but only marginally related to the padded character height.

const Glib::RefPtr< Gdk::Pixmap > * m_pixmap

Points to the current pixmap (m_black_pixmap or m_white_pixmap) to use to render a string.

Glib::RefPtr< Gdk::Pixmap > m black pixmap

The pixmap in the file $src/pixmaps/font_b.xpm$ is loaded into this object.

 $\bullet \ \, Glib::RefPtr < Gdk::Pixmap > m_white_pixmap \\$

The pixmap in the file src/pixmaps/font_w.xpm is loaded into this object.

• Glib::RefPtr< Gdk::Pixmap> m_b_on_y_pixmap

The pixmap in the file src/pixmaps/font_y.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_y_on_b_pixmap

The pixmap in the file src/pixmaps/font_yb.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m b on c pixmap

The pixmap in the file $src/pixmaps/cyan_wenfont_y.xpm$ is loaded into this object.

• Glib::RefPtr< Gdk::Pixmap> m_c_on_b_pixmap

The pixmap in the file src/pixmaps/cyan_wenfont_yb.xpm is loaded into this object.

Glib::RefPtr< Gdk::Bitmap > m_clip_mask

This object is instantiated as a default object.

12.13.1 Member Enumeration Documentation

12.13.1.1 enum seq64::font::Color

Enumerator

BLACK A simple enumeration to describe the basic colors used in writing text. Basically, these two values cause the selection of one or another pixmap (font_b_xpm and font_w_xpm). We've added two more pixmaps to draw black text on a yellow background (font_y.xpm) and yellow text on a black background (font_yb.xpm).

The first supported color. A black font on a white background.

WHITE The second supported color. A white font on a black background.

BLACK_ON_YELLOW A new color, for drawing black text on a yellow background.

YELLOW_ON_BLACK A new color, for drawing yellow text on a black background.

BLACK_ON_CYAN A new color, for drawing black text on a cyan background.

CYAN_ON_BLACK A new color, for drawing cyan text on a black background.

12.13.2 Member Function Documentation

12.13.2.1 void seq64::font::init (Glib::RefPtr < Gdk::Window > wp)

This function loads four pixmaps that contain the characters to be used to draw text strings.

One pixmap has white characters on a black background, one has black characters on a white background, one has yellow characters on a black background, and one has black characters on a yellow background.

12.13.2.2 void seq64::font::render_string_on_drawable (Glib::RefPtr< Gdk::GC $> a_gc$, int x, int y, Glib::RefPtr< Gdk::Drawable $> a_draw$, const char *str, font::Color col) const

This function grabs the proper font bitmap, extracts the current character pixmap from it, and slaps it down where it needs to be to render the character in the string.

Parameters

a_gc	Provides the graphics context for drawing the text using GTK+.
X	The horizontal location of the text.
У	The vertical location of the text.
a_draw	The drawable object on which to draw the text.
str	The string to draw. Should use a constant string reference instead.
col	The font color to use to draw the string. The supported values are font::BLACK, font::WHITE, font::BLACK_ON_YELLOW, font::YELLOW_ON_BLACK. The actual correct colors are provided by selecting one of four font pixmaps, as described in the init() function.

12.13.3 Field Documentation

```
12.13.3.1 int seq64::font::m_font_w [private]
```

Currently defaults to $cf_{text_w} = 6$. Note that a lot of stuff depends on this being 6 at present, even with our new, slightly wider, font.

```
12.13.3.2 int seq64::font::m_font_h [private]
```

Currently defaults to $cf_{text_h} = 10$. Note that a lot of stuff depends on this being 10 at present, even with our new, slightly wider, font. But some of the drawing code doesn't use the character height, but the padded character height.

```
12.13.3.3 const Glib::RefPtr<Gdk::Pixmap>* seq64::font::m_pixmap [mutable], [private]
```

This member used to be an object, but it's probably a bit faster to just use a pointer (or a reference).

```
12.13.3.4 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_black_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is in the resources/pixmaps/wenfont ← _b.xmp pixmap.

```
12.13.3.5 Glib::RefPtr < Gdk::Pixmap > seq64::font::m_white_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is in the resources/pixmaps/wenfont ← _w.xmp pixmap.

```
12.13.3.6 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_y_pixmap [private]
```

It contains a black font on a yellow background. The new-style font, if selected, is in the resources/pixmaps/wenfont ← _y.xmp pixmap.

```
12.13.3.7 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_y_on_b_pixmap [private]
```

It contains a yellow font on a black background. The new-style font, if selected, is resources/pixmaps/wenfont ←
_yb.xmp pixmap.

```
12.13.3.8 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_c_pixmap [private]
```

It contains a black font on a cyan background. It is available only for the new font-style.

```
12.13.3.9 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_c_on_b_pixmap [private]
```

It contains a cyan font on a black background. It is available only for the new font-style.


12.13.3.10 Glib::RefPtr < Gdk::Bitmap > seq64::font::m_clip_mask [private]

All we know is it seems to be a requirement for creating a pixmap object from an XMP file.

12.14 seq64::gui_assistant Class Reference

This class provides an interface for some of the GUI support needed in Sequencer64.

Inheritance diagram for seq64::gui assistant:



Public Member Functions

gui_assistant (keys_perform &kp)

This constructor wires in some externally (for now) created objects.

virtual ~gui_assistant ()

Stock base-class implementation of a virtual destructor.

const keys_perform & keys () const

'Getter' function for member m_keys_perform The const getter.

keys_perform & keys ()

'Getter' function for member m_keys_perform The un-const getter.

Private Attributes

keys_perform & m_keys_perform

Provides a reference to the app-specific GUI-specific keys_perform-derived object that an application is going to use for handling sequence-control keys.

12.14.1 Detailed Description

It also contain a number of helper objects that all kind of go together; only this assistant object will need to be passed around (by non-GUI code).

12.14.2 Constructor & Destructor Documentation

12.14.2.1 seq64::gui_assistant::gui_assistant (keys_perform & kp)


Parameters

kp Provides a set of key codes to be used by the perform object to control patterns and their performance.

12.15 seq64::gui_assistant_gtk2 Class Reference

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

Inheritance diagram for seq64::gui_assistant_gtk2:



Public Member Functions

• gui_assistant_gtk2 ()

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

virtual void quit ()

Calls the Glib Main object's quit() function.

virtual void lash_timeout_connect (lash *lashobject)

Connects the LASH timeout-event callback to the Glib timeout object.

virtual void jack_idle_connect (jack_assistant &jack)

Connects the JACK session-event callback to the Glib idle object.

Static Private Attributes

static keys_perform_gtk2 sm_internal_keys
 Provides a pre-made keys_perform object.

12.15.1 Member Function Documentation

 $\textbf{12.15.1.1} \quad \textbf{void seq64::gui_assistant_gtk2::lash_timeout_connect(\ lash* \textit{lashobject}\)} \quad \texttt{[virtual]}$

The time-out value is set to 250 ms.

Implements seq64::gui_assistant.

12.15.1.2 void seq64::gui_assistant_gtk2::jack_idle_connect(jack_assistant&jack) [virtual]

If JACK session support is not enabled, we might emit a message. This mainly prevents a compiler warning about an unused parameter.

Implements seq64::gui_assistant.

12.15.2 Field Documentation


12.15.2.1 keys_perform_gtk2 seq64::gui_assistant_gtk2::sm_internal_keys [static], [private]

This object is set into the reference provided in the gui assistant base class.

12.16 seq64::gui_drawingarea_gtk2 Class Reference

Implements the basic drawing areas of the application.

Inheritance diagram for seq64::gui_drawingarea_gtk2:



Data Structures

• struct rect

A small helper structure representing a rectangle.

Public Member Functions

gui_drawingarea_gtk2 (perform &p, int window_x=0, int window_y=0)

Perform-only constructor.

• gui_drawingarea_gtk2 (perform &a_perf, Gtk::Adjustment &a_hadjust, Gtk::Adjustment &a_vadjust, int window x=0, int window y=0)

Principal constructor.

~gui_drawingarea_gtk2 ()

Provides a destructor to delete allocated objects.

int window_x () const

'Getter' function for member m_window_x

int window_y () const

'Getter' function for member m window y

int current_x () const

'Getter' function for member m_current_x

int current_y () const

'Getter' function for member m_current_y

int drop_x () const

'Getter' function for member m_drop_x

int drop_y () const

'Getter' function for member m_drop_y

Protected Member Functions

virtual void force_draw ()

Provides a common function for redrawing.

perform & perf ()

'Getter' function for member m_mainperf

void clear_window ()

Clears the main window.

• void set_line (Gdk::LineStyle ls, int width=1)

A small wrapper function for readability in line-drawing.

void draw_line (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window.

void draw_line (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window after setting the given foreground color.

void draw_line_on_pixmap (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap.

void draw_line_on_pixmap (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap after setting the given foreground color.

void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap after setting the given foreground color.

 $\bullet \ \ void \ draw_line \ (Glib::RefPtr < Gdk::Drawable > \&drawable, int \ x1, int \ y1, int \ x2, int \ y2) \\$

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

void draw line (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the drawable after setting the given foreground color.

• void render_string (int x, int y, const std::string &s, font::Color color)

A small wrapper function for readability in string-drawing to the window.

void render_string_on_pixmap (int x, int y, const std::string &s, font::Color color)

A small wrapper function for readability in string-drawing to the pixmap.

void draw_rectangle (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the window.

void draw rectangle (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing.

void draw rectangle (Glib::RefPtr < Gdk::Drawable > &drawable, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "drawable" context, where the foreground color has already been specified.

• void draw_rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any drawable context.

void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "pixmap" context, where the foreground color has already been specified.

• void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any pixmap context.

void draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

void draw_rectangle_on_pixmap (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

void draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

void draw drawable (int xsrc, int ysrc, int xdest, int ydest, int width, int height)

Provides the most common use case for redrawing.

void scroll_adjust (Gtk::Adjustment &adjust, double step)

This function provides optimization for the on_scroll_event() functions, and should provide support for having the seqedit/seqroll/seqtime/seqdata panes follow the scrollbar, in a future upgrade.

• void on_realize ()

For this GTK callback, on realization of window, initialize the shiz.

Protected Attributes

Glib::RefPtr< Gdk::GC > m_gc

The graphics context, which is required for ever drawing and rendering operation.

• Glib::RefPtr< Gdk::Window > m window

Provides the default "window".

• Gtk::Adjustment & m_vadjust

Provides an object for vertical "adjustments".

• Gtk::Adjustment & m_hadjust

Provides an object for horizontal "adjustments".

• Glib::RefPtr< Gdk::Pixmap> m_pixmap

Provides the default "pixmap".

• Glib::RefPtr< Gdk::Pixmap > m_background

Another pixmap, used for backgrounds.

Glib::RefPtr< Gdk::Pixmap > m foreground

Another pixmap, used for foregrounds.

· perform & m mainperf

A frequent hook into the main perform object.

int m_window_x

Window sizes.

int m current x

The x and y value of the current location of the mouse (during dragging?)

int m_drop_x

These values are used when roping and highlighting a bunch of events.

Private Member Functions

void gtk drawarea init ()

Does basic initialization for each of the constructors.

Additional Inherited Members

12.16.1 Detailed Description

Note that this class really "isn't a" gui_pallete_gtk2; it should simply have one. But that base class must be derived from Gtk::DrawingArea. We don't want to waste some space by using a "has-a" relationship, and also put up with having to access the palette indirectly. So, in this case, we tolerate the less strict implementation.

12.16.2 Member Function Documentation

```
12.16.2.1 virtual void seq64::gui_drawingarea_gtk2::force_draw( ) [inline], [protected], [virtual]
```

This function forces a redraw. Some classes extend this function.

Reimplemented in seq64::seqroll, seq64::seqevent, and seq64::seqkeys.

```
12.16.2.2 void seq64::gui_drawingarea_gtk2::clear_window() [inline], [protected]
```

One less need to access m window directly.

```
12.16.2.3 void seq64::gui_drawingarea_gtk2::set_line ( Gdk::LineStyle ls, int width = 1 ) [inline], [protected]
```

Sets the attributes of a line to be drawn.

Is	Provides the Gtk-specific line style.
width	Provides the width of the line to be drawn. It defaults to the most common value, 1.

```
12.16.2.4 void seq64::gui_drawingarea_gtk2::draw_line ( int x1, int y1, int x2, int y2 ) [inline], [protected]
```

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.16.2.5 void seq64::gui_drawingarea_gtk2::draw_line (const Color & c, int x1, int y1, int x2, int y2) [protected]

Parameters

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.16.2.6 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
<i>y</i> 2	The y coordinate of the ending point.

12.16.2.7 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (const Color & c, int x1, int y1, int x2, int y2)

[protected]

Parameters

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.16.2.8 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Pixmap > & pixmap, int x1, int y1, int x2, int y2) [inline], [protected]

pixmap	Provides the Gdk::Pixmap pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.16.2.9 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Pixmap > & pixmap, const Color & c, int x1, int y1, int y2) [protected]

Parameters

pixmap	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.16.2.10 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & drawable, int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.16.2.11 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & drawable, const Color & c, int x1, int x1, int x2, int y2) [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.16.2.12 void seq64::gui_drawingarea_gtk2::render_string (int x, int y, const std::string & s, font::Color color)
[inline], [protected]

Parameters

Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.

12.16.2.13 void seq64::gui_drawingarea_gtk2::render_string_on_pixmap (int x, int y, const std::string & s, font::Color color) [inline], [protected]

Parameters

Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.

12.16.2.14 void seq64::gui_drawingarea_gtk2::draw_rectangle (int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

Parameters

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.16.2.15 void seq64::gui_drawingarea_gtk2::draw_rectangle (const Color & c, int x, int y, int lx, int ly, bool fill = true)

[protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

С	Provides the foreground color to set.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.16.2.16 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & drawable, int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

drawable	le The object on which to draw the rectangle.	
Х	The x-coordinate of the origin.	
У	The y-coordinate of the origin.	
lx	The width of the box.	
ly	The height of the box.	
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).	
	Defaults to true.	

12.16.2.17 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & drawable, const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

Parameters

drawable	The surface on which to draw the box.
С	Provides the foreground color to set.
X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.16.2.18 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr < Gdk::Pixmap > & pixmap, int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

Parameters

pixmap	The object on which to draw the rectangle.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).
	Defaults to true.

12.16.2.19 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr < Gdk::Pixmap > & pixmap, const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

pixmap	The surface on which to draw the box.
С	Provides the foreground color to set.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.16.2.20 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill = true)
[inline], [protected]

Parameters

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.16.2.21 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

С	Provides the foreground color to set.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.16.2.22 void seq64::gui_drawingarea_gtk2::draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill = true) [protected]

It uses Gtk to get the proper background styling for the rectange.

Parameters

Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.16.2.23 void seq64::gui_drawingarea_gtk2::scroll_adjust (Gtk::Adjustment & hadjust, double step) [protected]

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

hadjust	Provides a reference to the adjustment object to be adjusted.
---------	---

Parameters

step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is	
	leftward. If positive, the adjustment is rightward. It can be the value of	
	m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.	

12.16.2.24 void seq64::gui_drawingarea_gtk2::on_realize() [protected]

It allocates any additional resources that weren't initialized in the constructor.

12.16.3 Field Documentation

```
12.16.3.1 Glib::RefPtr<Gdk::Window> seq64::gui_drawingarea_gtk2::m_window [protected]
```

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

```
12.16.3.2 Glib::RefPtr < Gdk::Pixmap > seq64::gui_drawingarea_gtk2::m_pixmap [protected]
```

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

```
12.16.3.3 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_background [protected]
```

Our wrappers still leave this member exposed <giggle>.

```
12.16.3.4 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_foreground [protected]
```

Our wrappers still leave this member exposed.

```
12.16.3.5 perform& seq64::gui_drawingarea_gtk2::m_mainperf [protected]
```

We could move this into yet another base class, since a number of classes don't need it. Probably not worth the effort at this time.

```
12.16.3.6 int seq64::gui_drawingarea_gtk2::m_window_x [protected]
```

Could make this constant, but some windows are resizable.


```
12.16.3.7 int seq64::gui_drawingarea_gtk2::m_drop_x [protected]
```

Provides the x and y value of where the dragging started.

12.17 seq64::gui_palette_gtk2 Class Reference

Implements a stock palette of Gdk::Color elements.

Inheritance diagram for seg64::gui palette gtk2:



Public Member Functions

• gui_palette_gtk2 ()

Principal constructor.

• \sim gui_palette_gtk2 ()

Provides a destructor to delete allocated objects.

• const Color & line_color () const

'Getter' function for member m_line_color Provides an experimental way to change some line colors from black to something else.

• const Color & progress_color () const

'Getter' function for member m_progress_color Provides an experimental way to change the progress line color from black to something else.

· const Color & black () const

'Getter' function for member m_black

· const Color & white () const

'Getter' function for member m_white

· const Color & grey () const

'Getter' function for member m_grey

const Color & dark_grey () const

'Getter' function for member m_dk_grey

· const Color & light grey () const

'Getter' function for member m_lt_grey

const Color & red () const

'Getter' function for member m_red

const Color & orange () const

'Getter' function for member m_orange

· const Color & yellow () const

'Getter' function for member m_yellow

• const Color & green () const

'Getter' function for member m_green

· const Color & blue () const

'Getter' function for member m_blue

· const Color & dark_cyan () const

'Getter' function for member m_dk_cyan

const Color & bg_color () const

'Getter' function for member m_bg_color

void bg_color (const Color &c)

'Setter' function for member m_bg_color

const Color & fg_color () const

'Getter' function for member m_fg_color

void fg_color (const Color &c)

'Setter' function for member m_fg_color

Protected Types

typedef Gdk::Color Color
 Provides a type for the color object.

12.17.1 Detailed Description

Note that this class must be derived from Gtk::DrawingArea (or Gtk::Widget) in order to get access to the get_ default_colormap() function used in the constructor.

12.17.2 Constructor & Destructor Documentation

```
12.17.2.1 seq64::gui_palette_gtk2::gui_palette_gtk2 ( )
```

In the constructor you can only allocate colors; get_window() returns 0 because this window has not be realized.

12.17.3 Member Function Documentation

```
12.17.3.1 const Color& seq64::gui_palette_gtk2::line_color( ) const [inline]
```

Might eventually be selectable from the "user" configuration file


```
12.17.3.2 const Color& seq64::gui_palette_gtk2::progress_color( ) const [inline]
```

Might eventually be selectable from the "user" configuration file

12.18 seq64::gui_window_gtk2 Class Reference

This class supports a basic interface for Gtk::Window-derived objects.

Inheritance diagram for seq64::gui_window_gtk2:



Public Member Functions

• gui window gtk2 (perform &p, int window x=0, int window y=0)

Principal constructor, has a reference to the all-important perform object.

• ~gui_window_gtk2 ()

This rote constructor does nothing.

Protected Member Functions

• perform & perf ()

'Getter' function for member m_mainperf

virtual void quit ()

Provides "quit" functionality that WE HAVE OVERLOOKED!!!

• int redraw_period_ms () const

'Getter' function for member m_redraw_period_ms

void scroll_adjust (Gtk::Adjustment &adjust, double step)

This function provides optimization for the on_scroll_event() functions, and should provide support for having the seqedit/seqroll/seqtime/seqdata panes follow the scrollbar, in a future upgrade.

Private Attributes

• perform & m_mainperf

The master object, sort of a sequence buss.

• int m_window_x

Window sizes.

int m_redraw_period_ms

Provides the timer period for the eventedit timer, used to determine the rate of redrawing.

12.18.1 Constructor & Destructor Documentation

12.18.1.1 seq64::gui_window_gtk2::gui_window_gtk2 (perform & p, int window_x = 0, int window_y = 0)

Note

We've collected the redraw timeouts into a base-class member. Most were valued at c_redraw_ms (40 ms), but mainwnd used 25 ms, so beware. We will eventually make this a user-interface parameter.

Parameters

р	Refers to the main performance object.
window←	The width of the window.
_X	
window←	The height of the window.
_y	

12.18.2 Member Function Documentation

12.18.2.1 void seq64::gui_window_gtk2::scroll_adjust (Gtk::Adjustment & hadjust, double step) [protected]

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

Parameters

hadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is
	leftward. If positive, the adjustment is rightward. It can be the value of
	m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.

12.18.3 Field Documentation

12.18.3.1 int seq64::gui_window_gtk2::m_window_x [private]

Could make this constant, but some windows are resizable.

12.18.3.2 int seq64::gui_window_gtk2::m_redraw_period_ms [private]

This is currently hardwired to 40 ms in Linux, and 20 ms in Windows. Note that mainwind used 25 ms.

12.19 seq64::jack_assistant Class Reference

This class provides the performance mode JACK support.

Public Member Functions

jack_assistant (perform &parent, int bpminute=SEQ64_DEFAULT_BPM, int ppqn=SEQ64_USE_DEFAUL

T_PPQN, int bpm=SEQ64_DEFAULT_BEATS_PER_MEASURE, int beatwidth=SEQ64_DEFAULT_BEAT

_WIDTH)

This constructor initializes a number of member variables, some of them public!

~jack_assistant ()

The destructor doesn't need to do anything yet.

perform & parent ()

'Getter' function for member m_jack_parent Needed for external callbacks.

bool is_running () const

'Getter' function for member m jack running

bool is_master () const

'Getter' function for member m_jack_master

int get_ppqn () const

'Getter' function for member m_ppqn

int get_beat_width () const

'Getter' function for member m_beat_width

void set_beat_width (int bw)

'Setter' function for member m_beat_width

int get_beats_per_measure () const

'Getter' function for member m beats per measure

void set_beats_per_measure (int bpm)

'Setter' function for member m_beats_per_measure

• int get_beats_per_minute () const

 ${\it 'Getter' function for member m_beats_per_minute}$

void set_beats_per_minute (int bpminute)

'Setter' function for member m_beats_per_minute For the future, changing the BPM (beats/minute) internally.

• bool init ()

Initializes JACK support.

• bool deinit ()

Tears down the JACK infrastructure.

bool session_event ()

Writes the MIDI file named "< jack session dir>-file.mid" using a midifile object, quits if told to by JACK, and can free the JACK session event.

void start ()

If JACK is supported, starts the JACK transport.

• void stop ()

If JACK is supported, stops the JACK transport.

void position (bool to_left_tick, bool relocate=false)

If JACK is supported and running, sets the position of the transport to the new frame number, frame 0.

bool output (jack_scratchpad &pad)

Performance output function for JACK, called by the perform function of the same name.

void set_ppqn (int ppqn)

'Setter' function for member m_ppqn For the future, changing the PPQN internally.

double get_jack_tick () const

'Getter' function for member m jack tick

const jack_position_t & get_jack_pos () const

'Getter' function for member m jack pos

Private Member Functions

void set jack running (bool flag)

'Setter' function for member m_jack_running

• jack_client_t * client () const

'Getter' function for member m_jack_client

bool info_message (const std::string &msg)

Common-code for console messages.

bool error message (const std::string &msg)

Common-code for error messages.

jack_client_t * client_open (const std::string &clientname)

A more full-featured initialization for a JACK client, which is meant to be called by the init() function.

void show_statuses (unsigned bits)

Loops through the full set of JACK bits, showing the information for any bits that are set in the given parameter.

void show_position (const jack_position_t &pos) const

Shows a one-line summary of a JACK position structure.

int sync (jack_transport_state_t state=(jack_transport_state_t)(-1))

A helper function for syncing up with JACK parameters.

void set_position (midipulse currenttick)

Provides the code that was effectively commented out in the perform::position_jack() function.

Static Private Attributes

static jack_status_pair_t sm_status_pairs []

Provides a list of JACK status bits, and a brief string to explain the status bit.

Friends

void jack_shutdown_callback (void *arg)

This callback is to shutdown JACK by clearing the jack_assistant::m_jack_running flag.

int jack sync callback (jack transport state t state, jack position t *pos, void *arg)

Global functions for JACK support and JACK sessions.

void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

void jack_session_callback (jack_session_event_t *ev, void *arg)

Set the m_jsession_ev (event) value of the perform object.

12.19.1 Constructor & Destructor Documentation

12.19.1.1 seq64::jack_assistant::jack_assistant (perform & parent, int bpminute = SEQ64_DEFAULT_BPM, int ppqn = SEQ64_USE_DEFAULT_PPQN, int bpm = SEQ64_DEFAULT_BEATS_PER_MEASURE, int beatwidth = SEQ64_DEFAULT_BEAT_WIDTH)

Note that the perform object currently calls jack assistant::init(), but that call could be made here instead.

Parameters

parent Provides a reference to the main perform object that needs to control JACK event.

```
12.19.1.2 seq64::jack_assistant::~jack_assistant()
```

The perform object currently calls jack_assistant::deinit(), but that call could be made here instead.

12.19.2 Member Function Documentation

```
12.19.2.1 void seq64::jack_assistant::set_beats_per_minute(int bpminute) [inline]
```

We should consider adding validation. However, perform::set_beats_per_minute() does validate already.

```
12.19.2.2 bool seq64::jack_assistant::init()
```

Then we become a new client of the JACK server.

A sync callback is needed for polling of slow-sync clients. But seq24/sequencer64 are not slow-sync clients. We don't really need to be a slow-sync client, as far as we can tell. We can't get JACK working exactly the way it does in seq24 without the callback in place. Plus, it does things important to the setup of JACK. So now this setup is permanent.

Jack transport settings:

```
There are three settings: On, Master, and Master Conditional. Currently, they can all be selected in the user-interface's File / Options / JACK/LASH page. We really want only the proper combinations to be set, for clarity (the user-interface now takes care of this. We need to initialize if any of them are set, and the rc_settings::with_jack() function tells us that.
```

jack_set_process_callback() patch:

```
Implemented first patch from freddix/seq24 GitHub project, to fix JACK transport. One line of code. Well, we added some error-checking. :-) Found some old notes on the Web the this patch really only works (to prevent seq24 freeze) if seq24 is set as JACK Master, or if another client application, such as Qtractor, is running as JACK Master (and then seq24 will apparently follow it).
```

Returns

Returns true if JACK is now considered to be running (or if it was already running.)

```
12.19.2.3 bool seq64::jack_assistant::deinit ( )
```

Returns the value of m jack running, which should be false.

```
12.19.2.4 bool seq64::jack_assistant::session_event()
```

ca 2015-07-24 Just a note: The OMA (OpenMandrivaAssociation) patch was already applied to seq24 v.0.9.2. It put quotes around the –file argument. However, the –file option doesn't work, so let's change that line.

```
sequencer64 --file \"${SESSION_DIR}file.mid\" --jack_session_uuid
```

Why are we using a Glib::ustring here? Convenience. But with C++11, we could use a lexical_cast<>. No more ustring, baby! It doesn't really matter; this function can call Gtk::Main::quit(), via the parent's gui().quit() function.

Returns

Always returns false.

```
12.19.2.5 void seq64::jack_assistant::start()
```

This function assumes that m jack client is not null, if m jack running is true.

Found this note in the Hydrogen code:

```
When jack_transport_start() is called, it takes effect from the next processing cycle. The location info from the timebase_master, if there is one, will not be available until the _next_ next cycle. The code must therefore wait one cycle before syncing up with timebase_master.
```

```
12.19.2.6 void seq64::jack_assistant::stop ( )
```

This function assumes that m jack client is not null, if m jack running is true.

```
12.19.2.7 void seq64::jack_assistant::position ( bool to_left_tick, bool relocate = false )
```

This new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

```
http://jackaudio.org/files/docs/html/transport-design.html
```

This position() function is called via perform::position_jack() in the mainwnd, perfedit, perfroll, and seqroll graphical user-interface support objects.

The code that was disabled sets the current tick to 0 or, if state was true, to the leftmost tick (which is probably the position of the L marker). The current tick is then converted to a frame number, and then we locate the transport to that position. We're going to enable this code, but make it dependent on a new boolean parameter that defaults to false, in anticipation of trying it out later.

These repositions reset the progress bars. We don't always want that, it should be an option. TODO.

```
jack transport reposition():
```

Requests a new transport position. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

It's pos parameter provides the requested new transport position. Fill pos->valid to specify which fields should be taken into account. If you mark a set of fields as valid, you are expected to fill them all. Note that "frame" is always assumed, and generally needs to be set:

http://comments.gmane.org/gmane.comp.audio.jackit/18705

Returns 0 if a valid request, EINVAL if the position structure is rejected.

Warning

A lot of this code is effectively disabled by an early return statement.

Parameters

to_left_tick	If true, the current tick is set to the leftmost tick, instead of the 0th tick. Now used, but only if
	relocate is true. One question is, do we want to perform this function if rc().with_jack_transport()
	is true? Seems like we should be able to do it only if m_jack_master is true.
relocate	If true (it defaults to false), then we allow the relocation of the JACK transport to the current_tick or the left tick, rather than to frame 0. EXPERIMENTAL, enables dead code from seq24. Seems to work if set to true when we are the JACK Master. Enabling this code makes "klick -j -P" work, after a fashion. It clicks, but at a way too rapid rate.

12.19.2.8 bool seq64::jack_assistant::output (jack_scratchpad & pad)

This code comes from perform::output_func() from seq24.

Note

Follow up on this note found "out there": "Maybe I'm wrong but if I understood correctly, recent jack1 transport no longer goes into Jack_Transport_Starting state before going to Jack_Transport_Rolling (this was deliberately dropped), but seq24 currently needs this to start off with jack transport." On the other hand, some people have no issues. This may have been due to the lack of m jack pos initialization.

Parameters

pad	Provide a JACK scratchpad for sharing certain items between the perform object and the jack_assistant
	object.

Returns

Returns true if JACK is running.

12.19.2.9 void seq64::jack_assistant::set_ppqn (int ppqn) [inline]

We should consider adding validation. But it is used by perform.

12.19.2.10 bool seq64::jack_assistant::info_message (const std::string & msg) [private]

Adds markers and a newline.

Parameters

msg The message to print, sans the newline.

Returns

Returns true.

12.19.2.11 bool seq64::jack_assistant::error_message(const std::string & msg) [private]

Adds markers, and sets m_jack_running to false.

Parameters

msg The message to print, sans the newline.

Returns

Returns false for convenience/brevity in setting function return values.

12.19.2.12 jack_client_t * seq64::jack_assistant::client_open(const std::string & clientname) [private]

Status bits for jack_status_t return pointer:

JackNameNotUnique means that the client name was not unique. With JackUseExactName, this is fatal. Otherwise, the name was modified by appending a dash and a two-digit number in the range "-01" to "-99". The jack_get_client_name() function returns the exact string used. If the specified client_name plus these extra characters would be too long, the open fails instead.

JackServerStarted means that the JACK server was started as a result of this operation. Otherwise, it was running already. In either case the caller is now connected to jackd, so there is no race condition. When the server shuts down, the client will find out.

Returns

Returns true if JACK has opened the client connection successfully.

12.19.2.13 void seq64::jack_assistant::show_statuses (unsigned bits) [private]

For reference, here are the enumeration values from /usr/include/jack/types.h:

```
= 0 \times 01
JackFailure
JackInvalidOption = 0x02
JackNameNotUnique = 0x04
JackServerStarted = 0x08
JackServerFailed = 0x10
JackServerError
                     = 0x20
JackNoSuchClient
                     = 0 \times 40
                     = 0x80
JackLoadFailure
JackInitFailure
                     = 0 \times 100
JackShmFailure
                     = 0x200
JackVersionError = 0x400
JackBackendError
                     = 0x800
JackClientZombie
                     = 0x1000
```

12.19.2.14 void seq64::jack assistant::show position (const jack position t & pos) const [private]

This function is meant for experimenting and learning.

you want to play with non-Western timings.

The fields of this structure are as follows. Only the fields we care about are shown.

```
jack_nframes_t
                     frame_rate:
                                   current frame rate (per second)
   jack_nframes_t frame:
jack_position_bits_t valid:
                                   frame number, always present
                                  which other fields are valid
JackPositionBBT:
                                  current bar
   int32 t
                    bar:
                                current beat-within-bar
   int32_t
                   beat:
   int32_t
                   tick:
bar_start_tick
                                  current tick-within-beat
   double
                    beats_per_bar: time signature "numerator"
   float
                                  time signature "denominator"
   float.
                   beat_type:
   double
                     ticks_per_beat
   double
                    beats_per_minute
JackBBTFrameOffset:
                   bbt_offset;
                                  frame offset for the BBT fields
   jack_nframes_t
Only the most "important" and time-varying fields are shown. The format
output is brief and inscrutable unless you read this format example:
   nnnnn frame B:B:T N/D TPB BPM BBT
                   1 1
                               | | | | ----- bbt_offset (frame), even if invalid
               | | ----- ticks_per_beat (PPQN * 10?)
                   | ----- beat_type (denominator)
                    -----beats_per_bar (numerator)
                 ----- bar : beat : tick
               ----- frame (number)
      ----- the "valid" bits
The "valid" field is shown as bits in the same bit order as shown here, but
represented as a five-character string, "nnnnn", n = 0 or 1:
   JackVideoFrameOffset = 0x100
   JackAudioVideoRatio = 0x080
   JackBBTFrameOffset
                     = 0 \times 040
   JackPositionTimecode = 0x020
                     = 0x010
   JackPositionBBT
We care most about nnnnn = "00101" in our experiments (the most common
output will be "00001"). And we don't worry about non-integer
measurements... we truncate them to integers. Change the output format if
```

Parameters

```
pos The JACK position structure to dump.
```

```
12.19.2.15 int seq64::jack_assistant::sync( jack_transport_state_t state = (jack_transport_state_t) (-1) )
[private]
```

Sequencer64 is not a slow-sync client, so that callback is not really needed, but we probably need this sub-function here to start out with the right values for interacting with JACK.

Note the call to jack_transport_query(). This call is *not* is seq24, but seems to be needed in sequencer64 because we put m_jack_pos in the initializer list, which sets all its fields to 0. Seq24 accesses m_jack_pos before it ever gets set, but its fields have values. These values are bogus, but are consistent from run to run on my computer, and allow seq24 to follow another JACK Master, on some computers. It explains why people had different experiences with JACK sync.

If we explicity call jack_transport_query() here, without changing the *state* parameter, then sequencer64 also can follow another JACK Master. (CURRENTLY BUGGY!)

Note that we should consider massaging the following jack_position_t members to set them to 0 (or 0.0) if less than 1.0 or 0.5:

```
- bar_start_tick
- ticks_per_beat
- beats_per_minute
- frame_time
- next_time
- audio_frames_per_video_frame
```

Also, why does bbt_offset start at 2128362496?

```
12.19.2.16 void seq64::jack_assistant::set_position ( midipulse currenttick ) [private]
```

We might be able to use it in other functions.

Computing the BBT information from the frame number is relatively simple here, but would become complex if we supported tempo or time signature changes at specific locations in the transport timeline.

```
ticks * 10 = jack ticks;
jack ticks / ticks per beat = num beats;
num beats / beats per minute = num minutes
num minutes * 60 = num seconds
num secords * frame_rate = frame
```

12.19.3 Friends And Related Function Documentation

```
12.19.3.1 void jack shutdown callback (void * arg ) [friend]
```

```
arg Points to the jack_assistant in charge of JACK support for the perform object.
```

12.19.3.2 int jack_sync_callback (jack_transport_state_t state, jack_position_t * pos, void * arg) [friend]

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

Parameters

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

```
12.19.3.3 void jack_timebase_callback ( jack_transport_state_t state, jack_nframes_t nframes, jack_position_t * pos, int new_pos, void * arg ) [friend]
```

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

```
http://essej.net/sooperlooper/
```

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

- -# Calculate the "delta" ticks based on the current frame, the ticks_per_beat, the beats_per_minute, and the frame_rate. The old code saves this in a local, the new code assigns it to pos->tick.
- -# Old code: save this delta as a positive value.
- -# Figure out the settings and modify bar, beat, tick, and bar_start_tick. The old and new code seem to have the same intent, but it seems like the new code is faster and also correct.
 - Old code: Calculations are made by division and mod operations.
 - New code: Calculations are made by increments and decrements in a while loop.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

```
12.19.3.4 void jack_session_callback( jack_session_event_t * ev, void * arg ) [friend]
```

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseq64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

Parameters

ev	The JACK event to be set.
arg	The pointer to the jack_assistant object. Currently not checked for nullity.

12.19.4 Field Documentation

```
12.19.4.1 jack_status_pair_t seq64::jack_assistant::sm_status_pairs [static], [private]
```

Terminated by a 0 value and an empty string.

12.20 seq64::jack_scratchpad Class Reference

Provide a temporary structure for passing data and results between a perform and jack_assistant object.

12.20.1 Detailed Description

The jack_assistant class already has access to the members of perform, but it needs access to and modification of "local" variables in perform::output_func(). This scratchpad is useful even if JACK support is not enabled.

12.21 seq64::keybindentry Class Reference

Class for management of application key-bindings.

Inherits Entry.

Public Member Functions

• keybindentry (type t, unsigned int *location_to_write=nullptr, perform *p=nullptr, long s=0)

This constructor initializes the member with values dependent on the value type provided in the first parameter.

void set (unsigned int val)

Gets the key name from the integer value; if there is one, then it is printed into a temporary buffer, otherwise the value is printed into that buffer as is.

virtual bool on_key_press_event (GdkEventKey *event)

Handles a key press by calling set() with the event's key value.

Private Types

Private Attributes

unsigned int * m_key

Points to the value of the key that is part of this key-binding.

• type m_type

Stores the type of key-binding.

• perform * m_perf

Stores an optional pointer to a perform object.

long m_slot

Provides???

12.21.1 Member Enumeration Documentation

```
12.21.1.1 enum seq64::keybindentry::type [private]
```

Enumerator

location Provides the type of keybindings that can be made. Used for handling a keystroke made while a keyboard-options field is active, for selecting a key via the keyboard, and binding to pattern/sequence boxes, we think. It is used in the options class to associate a key with the binding.

events Used for binding to events.

groups Used for binding to groups.

12.21.2 Constructor & Destructor Documentation

12.21.2.1 seq64::keybindentry::keybindentry (type t, unsigned int * location_to_write = nullptr, perform * p = nullptr, long s = 0)

Usage In options, a pointer to a new key-binding entry is managed by calling keybindentry (keybindentry ∴: location, &perf->keyname).


t	Provides the type of key-binding: location, events, or groups.
location_to_write	The location that holds the value of the key associated with the key-binding. The default value of this parameter is the null pointer.
p	Points to the performance object used with this key-binding. The default value of this parameter is the null pointer.
S	Provides the slot value for this key-binding. The default value of this parameter is zero.

12.21.3	Member Function Documentation
12.21.3.1	void seq64::keybindentry::set (unsigned int <i>val</i>)
Then we	call set_text(buf). The set_width_char() function is then called.
12.21.3.2	<pre>bool seq64::keybindentry::on_key_press_event(GdkEventKey * event) [virtual]</pre>
This valu	e is used to set the event or key depending on the value of m_type.
12.21.4	Field Documentation
12.21.4.1	<pre>unsigned int* seq64::keybindentry::m_key [private]</pre>
Not yet s	ure by the address of this key value is needed. It can be a null pointer, as well.

12.22 seq64::keys_perform Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform:



Public Member Functions

• keys_perform ()

This construction initializes a vast number of member variables, some of them public!

∼keys_perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

void set_keys (const keys_perform_transfer &kpt)

Copies fields from the transfer structure in this object.

void get_keys (keys_perform_transfer &kpt)

Copies fields from this object into the transfer structure.

bool show_ui_sequence_key () const

Accessor m_key_show_ui_sequency_key

· bool show ui sequence number () const

Accessor m_key_show_ui_sequency_number

• virtual std::string key_name (unsigned int key) const

Obtains the name of the key.

virtual void set_all_key_events ()

Provides base class functionality.

virtual void set_all_key_groups ()

Provides base class functionality.

void set_key_event (unsigned int keycode, long sequence_slot)

At construction time, this function sets up one keycode and one event slot.

void set_key_group (unsigned int keycode, long group_slot)

At construction time, this function sets up one keycode and one group slot.

Protected Types

typedef std::map< unsigned int, long > SlotMap

This typedef defines a map in which the key is the keycode, that is, the integer value of a keystroke, and the value is the pattern/sequence number or slot.

typedef std::map< long, unsigned int > RevSlotMap

This typedef is like SlotMap, but used for lookup in the other direction.

Private Attributes

bool m_key_show_ui_sequence_key

If set, shows the shortcut-keys on each filled pattern slot in the main window.

• bool m_key_show_ui_sequence_number

If set, shows the sequence number on each filled pattern and empty pattern slot in the main window.

unsigned int m_key_bpm_up

Provides key assignments for some key sequencer features.

12.22.1 Detailed Description

It provides a way a mapping keystrokes to sequencer actions and song settings.

12.22.2 Constructor & Destructor Documentation

```
12.22.2.1 seq64::keys_perform::~keys_perform()
```

Finally, any active patterns/sequences are deleted.

12.22.3 Member Function Documentation

12.22.3.1 void seq64::keys_perform::set_keys (const keys_perform_transfer & kpt)

This structure holds all of the key settings from the File / Options / Keyboard tab dialog.

Parameters

kpt

The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

12.22.3.2 void seq64::keys_perform::get_keys (keys_perform_transfer & kpt)

Parameters

kpt

The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

12.22.3.3 bool seq64::keys_perform::show_ui_sequence_key()const [inline]

Used in mainwid, options, optionsfile, userfile, and perform.

12.22.3.4 bool seq64::keys_perform::show_ui_sequence_number() const [inline]

Used in mainwid, options, optionsfile, userfile, and perform.

12.22.3.5 std::string seq64::keys_perform::key_name (unsigned int key) const [virtual]

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string.

Parameters

key Provides the numeric value of the keystroke.

Returns

Returns the name of the key, in the format "Key 0xkkkk".

Reimplemented in seq64::keys_perform_gtk2.

12.22.3.6 virtual void seq64::keys_perform::set_all_key_events() [inline], [virtual]

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

12.22.3.7 virtual void seq64::keys_perform::set_all_key_groups() [inline], [virtual]

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

12.22.3.8 void seq64::keys_perform::set_key_event (unsigned int keycode, long sequence_slot)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
sequence_slot	The perform event slot into which the keycode will be assigned.

12.22.3.9 void seq64::keys_perform::set_key_group (unsigned int keycode, long group_slot)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
group_slot	The perform group slot into which the keycode will be assigned.

12.22.4 Field Documentation

12.22.4.1 bool seq64::keys_perform::m_key_show_ui_sequence_number [private]

Also show the sequence number as part of the sequence name in the performance window (song editor).


12.22.4.2 unsigned int seq64::keys_perform::m_key_bpm_up [private]

Used in mainwnd, options, optionsfile, perfedit, seqroll, userfile, and perform.

12.23 seq64::keys_perform_gtk2 Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform_gtk2:



Public Member Functions

• keys_perform_gtk2 ()

This construction initializes a vast number of member variables, some of them public!

virtual ~keys_perform_gtk2 ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

- virtual std::string key_name (unsigned int key) const
 Obtains the name of the key.
- virtual void set_all_key_events ()

Sets up the keys for arming/unmuting events in the Gtk-2 environment.

virtual void set_all_key_groups ()

Sets up the keys for group events in the Gtk-2 environment.

Additional Inherited Members

12.23.1 Detailed Description

It has way too many data members, many of the public. Might be ripe for refactoring.

12.23.2 Constructor & Destructor Documentation

```
12.23.2.1 seq64::keys_perform_gtk2::~keys_perform_gtk2() [virtual]
```

Finally, any active patterns/sequences are deleted.

12.23.3 Member Function Documentation

```
12.23.3.1 std::string seq64::keys_perform_gtk2::key_name ( unsigned int key ) const [virtual]
```

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string.

Reimplemented from seq64::keys_perform.

```
12.23.3.2 void seq64::keys_perform_gtk2::set_all_key_events() [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

```
12.23.3.3 void seq64::keys_perform_gtk2::set_all_key_groups() [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

12.24 seq64::keys_perform_transfer Struct Reference

Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf().

12.25 seq64::keystroke Class Reference

Encapsulates any practical keystroke.

Public Member Functions

• keystroke ()

The default constructor for class keystroke.

The principal constructor.

· keystroke (const keystroke &rhs)

Provides the rote copy constructor.

• keystroke & operator= (const keystroke &rhs)

Provides the rote principal assignment operator.

• bool is_press () const

'Getter' function for member m_is_press

• bool is_letter (int ch=SEQ64_KEYSTROKE_BAD_VALUE) const

'Getter' function for member m_key to test letters, handles ASCII only.

• bool is_delete () const

'Getter' function for member m_key to test for a delete-causing key.

· unsigned int key () const

'Getter' function for member m_key

• seq_modifier_t modifier () const

'Getter' function for member m_modifier

bool mod_control () const

'Getter' function for member m_modifier tested for Ctrl key.

• bool mod_control_shift () const

'Getter' function for member m_{-} modifier tested for Ctrl and Shift key.

• bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

• bool m_is_press

Determines if the key was a press or a release.

unsigned int m_key

The key that was pressed or released.

• seq_modifier_t m_modifier

The optional modifier value.

12.25.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.25.2 Constructor & Destructor Documentation

12.25.2.1 seq64::keystroke::keystroke (unsigned int *key*, bool *press* = SEQ64_KEYSTROKE_PRESS, int *modkey* = int (SEQ64_NO_MASK))

key	The keystroke number of the key that was pressed or released.	
press	If true, the keystroke action was a press, otherwise it was a release.	
modkey	The modifier key combination that was pressed, if any, in the form of a bit-mask, as defined in the gdk_basic_keys module. Common mask values are SEQ64_SHIFT_MASK, SEQ64_CONTROL_MASK, SEQ64_MOD1_MASK, and SEQ64_MOD4_MASK. If no modifier, this value is SEQ64_NO_MASK.	

12.25.2.2 seq64::keystroke::keystroke (const keystroke & rhs)

Parameters

rhs	The object to be copied.
-----	--------------------------

12.25.3 Member Function Documentation

12.25.3.1 keystroke & seq64::keystroke::operator= (const keystroke & rhs)

Parameters

rhs The object to be ass

Returns

Returns the reference to the current object, for use in assignment chains.

12.25.3.2 bool seq64::keystroke::is_letter (int ch = SEQ64_KEYSTROKE_BAD_VALUE) const

Parameters

ch	An optional character to test as an ASCII letter.

Returns

If a character is not provided, true is returned if it is an upper or lower-case letter. Otherwise, true is returned if the m_key value matches the character case-insensitively.

Tricky Code

12.25.4 Field Documentation

12.25.4.1 bool seq64::keystroke::m_is_press [private]

See the SEQ64_KEYSTROKE_PRESS and SEQ64_KEYSTROKE_RELEASE readability macros.

```
12.25.4.2 unsigned int seq64::keystroke::m_key [private]
```

Generally, the extended ASCII range (0 to 255) is supported. However, Gtk-2.x/3.x will generally support the full gamut of characters defined in the gdk_basic_keys.h module. We define minimum and maximum range macros for keystrokes that are a bit generous.

```
12.25.4.3 seg modifier t seg64::keystroke::m_modifier [private]
```

Note that SEQ64 NO MASK is our word for 0, meaning "no modifier".

12.26 seq64::lash Class Reference

This class supports LASH operations, if compiled with LASH support (i.e.

Public Member Functions

• lash (perform &p, int argc, char **argv)

This constructor calls lash_extract(), using the command-line arguments, if SEQ64_LASH_SUPPORT is enabled.

void set_alsa_client_id (int id)

Make ourselves a LASH ALSA client.

• void start ()

Process any LASH events every 250 msec, which is an arbitrarily chosen interval.

bool process_events ()

Process LASH events.

Private Member Functions

· bool init ()

Initializes LASH support, if enabled.

void handle_event (lash_event_t *conf)

Handle a LASH event.

void handle_config (lash_config_t *conf)

Handle a LASH configuration item.

Private Attributes

• perform & m_perform

A hook into the single perform object in the application.

12.26.1 Detailed Description

SEQ64_LASH_SUPPORT is defined). All of the #ifdef skeleton work is done in this class in such a way that any other part of the code can use this class whether or not lash support is actually built in; the functions will just do nothing.

12.26.2 Constructor & Destructor Documentation

```
12.26.2.1 seq64::lash::lash ( perform & p, int argc, char ** argv )
```

We fixed the crazy usage of argc and argv here and in the client code in the seq24 module.

р	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

12.26.3 Member Function Documentation

12.26.3.1 void seq64::lash::set_alsa_client_id (int id)

/param id The ALSA client ID to be set.

12.26.3.2 bool seq64::lash::process_events()

Returns

Always returns true.

12.26.3.3 bool seq64::lash::init() [private]

Returns

Returns true if the LASH subsystem was able to be initialized, and a LASH client representative (m_client) was allocated.

12.26.3.4 void seq64::lash::handle_event(lash_event_t * ev) [private]

Parameters

ev Provides th	e event to be handled.
------------------	------------------------

12.26.3.5 void seq64::lash::handle_config(lash_config_t * conf) [private]

Currently incomplete.


Parameters

conf Provides the configuration item to handle.

12.27 seq64::maintime Class Reference

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

Inheritance diagram for seq64::maintime:



Public Member Functions

• maintime (perform &p, int ppqn=SEQ64_USE_DEFAULT_PPQN)

This constructor sets up the colors black, white, and grey, and then allocates them.

Private Member Functions

int idle_progress (midipulse ticks)

This function clears the window, sets the foreground to black, draws the "time" window's rectangle, and then draws a rectangle for noting the progress of the beat, and the progress for a bar.

· void on_realize ()

Handles realization of the window.

bool on_expose_event (GdkEventExpose *ev)

This function merely idles.

Private Attributes

· const int m beat width

Provides the divisor for ticks to produce a beat value.

const int m_bar_width

Provides the divisor for ticks to produce a bar value.

• const int m_pill_width

Provides the width of the pills, little black squares that show the progress of a beat and a bar (measure).

• const int m_box_width

The width/length of the rectangle to be drawn inside the maintime window.

· const int m box height

The height of the rectangle to be drawn inside the maintime window.

const int m_flash_width

The width/length of the flashing rectangle to be drawn inside the maintime window.

· const int m_flash_height

The height of the flashing rectangle to be drawn inside the maintime window.

const int m_flash_x

The x value at which a flash should occur.

• const int m_box_less_pill

The width/length of the maintime window minus the width of the pill.

midipulse m_tick

Saves the tick value for on_expose_event().

• int m_ppqn

Provides the active PPQN value.

Additional Inherited Members

12.27.1 Detailed Description

We added a lot of members to hold the results of calculations that involve what are essentially constant. This saves CPU time, and maybe a little memory for the code to make those calculations more than once.

12.27.2 Constructor & Destructor Documentation

```
12.27.2.1 seq64::maintime::maintime ( perform & p, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

In the constructor you can only allocate colors; get_window() would return 0 because the windows has not yet been realized.

12.27.3 Member Function Documentation

12.27.3.1 int seq64::maintime::idle_progress (midipulse *ticks*) [private]

Idle hands do the devil's work. We should eventually support some generic coloring for "dark themes". The default coloring is better for "light themes".

ticks Provides the main tick setting. This setting is provided by mainwnd(), in its timer callback.

Returns

Always returns 1 (it used to return "true"!).

```
12.27.3.2 void seq64::maintime::on_realize( ) [private]
```

It performs the base class's on_realize() function. It then allocates some additional resources: a window, a GC (?), and it clears the window. Then it sets the default size of the window, specified by GUI constructor parameters.

```
12.27.3.3 bool seq64::maintime::on_expose_event ( GdkEventExpose * a_e ) [private]
```

We don't need the m_tick member, the function works as well if 0 is passed in. We've removed m_tick permanently.

Actually, it might be useful after all, to avoid flickering under JACK transport. Let's put it back for now. (It doesn't help, but we will leave it in, the overhead is small.)

12.27.4 Field Documentation

```
12.27.4.1 const int seq64::maintime::m_beat_width [private]
```

Currently, this value is hardwired to 4, but will eventually be wired up as usr().midi beat width().

```
12.27.4.2 const int seq64::maintime::m_bar_width [private]
```

Currently, this value is hardwired to 16, but will eventually be wired up as usr().midi_beat_width() * usr().midi_ \leftarrow beats_per_bar().

```
12.27.4.3 const int seq64::maintime::m_box_width [private]
```

This item absolutely depends on the main window being non-resizable.

```
12.27.4.4 const int seq64::maintime::m_box_height [private]
```


This item absolutely depends on the main window being non-resizable.

```
12.27.4.5 const int seq64::maintime::m_flash_width [private]
```

Just a bit smaller than m_box_width.



Inheritance diagram for seq64::mainwid:



Public Member Functions

• mainwid (perform &p)

This constructor sets all of the members.

∼mainwid ()

A rote destructor.

void set_screenset (int ss)

Set the current screen-set.

Private Member Functions

virtual void redraw (int seq)

This virtual function, overridden from the seqmenu base class, draws the the given pattern/sequence again.

· void reset ()

This function redraws everything and queues up a redraw operation.

void draw_marker_on_sequence (int seq, int tick)

Does the actual drawing of one pattern/sequence position marker, a vertical progress bar.

void update_sequences_on_window ()

Updates the image of multiple sequencer/pattern slots.

· void update markers (int ticks)

Draw the cursors (long vertical bars) on each sequence, so that they follow the playing progress of each sequence in the mainwid (Patterns Panel).

bool valid sequence (int seq)

Common-code helper function.

void draw sequence on pixmap (int seq)

This function draws a specific pattern/sequence on the pixmap located in the main window of the application, the Patterns Panel.

void draw_sequences_on_pixmap ()

This function fills the pixmap with sequences.

void fill_background_window ()

This function updates the background window, clearing it.

void draw_pixmap_on_window ()

This function queues the blit of pixmap to window.

void draw_sequence_pixmap_on_window (int seq)

This function draws a sequence pixmap in the Patterns Panel.

int seq_from_xy (int x, int y)

Translates XY coordinates in the Patterns Panel to a sequence number.

• int timeout ()

Provides a stock callback, because some kind of callback is needed.

void calculate_base_sizes (int seq, int &basex, int &basey)

Provides a way to calculate the base x and y size values for the pattern map.

• void on_realize ()

For this GTK callback, on realization of window, initialize the shiz.

• bool on_expose_event (GdkEventExpose *ev)

Implements the GTK expose event callback.

bool on button press event (GdkEventButton *ev)

Handles a press of a mouse button in one of the sequence/pattern slots.

• bool on_button_release_event (GdkEventButton *ev)

Handles a release of a mouse button.

bool on_motion_notify_event (GdkEventMotion *p0)

Handle the motion of the mouse if a mouse button is down and in another sequence and if the current sequence is not in edit mode.

• bool on focus in event (GdkEventFocus *)

Handles an on-focus event.

bool on_focus_out_event (GdkEventFocus *)

Handles an out-of-focus event.

Private Attributes

• sequence m_moving_seq

Holds a partial copy of the sequence we a moving on the patterns panel.

• bool m_button_down

Indicates that the mouse button is still down.

bool m_moving

Indicates that we are still in the middle of a drag-and-drop operation.

• int m_mainwnd_rows

These values are assigned to the values given by the constants of similar names in globals.h, and we will make them parameters or user-interface configuration items later.

· int m screenset slots

Provides a convenience variable for avoiding multiplications.

· int m screenset offset

Provides a convenience variable for avoiding multiplications.

• int m_progress_height

Provides the height of the progress bar, to save calculations and for consistency between drawing and erasing the progress bar.

Additional Inherited Members

12.28.1 Constructor & Destructor Documentation

12.28.1.1 seq64::mainwid::mainwid (perform & p)

And it asks for a size of c_mainwid_x by c_mainwid_y. It adds GDK masks for button presses, releases, motion, key presses, and focus changes.

Parameters

p Provides the reference to the all-important perform object.

12.28.2 Member Function Documentation

12.28.2.1 void seq64::mainwid::set_screenset (int ss)

Parameters

ss Provides the screen-set number to set.

12.28.2.2 void seq64::mainwid::redraw (int seqnum) [private], [virtual]

Parameters

seqnum Provides the number of the sequence to draw.

Implements seq64::segmenu.

12.28.2.3 void seq64::mainwid::draw_marker_on_sequence(int seqnum, int tick) [private]

If the sequence has no events, this function doesn't bother even drawing a position marker.

Note that, when Sequencer64 first comes up, and perform::is_dirty_main() is called, no sequences exist yet. Also, currently the redraw() is hit when seq_edit() is called, but not when seq_event_edit() is called, which makes the latter not paint the in-edit highlight colors (if enabled). Why?

Parameters

seqnum	Provides the number of the sequence to draw.
tick	Provides the location to draw the marker. If pause support is compiled in (i.e. no -disable-pause in
	the configuration), then this parameter is ignored, and is replaced by the sequences' get_lask_tick()
	value. This causes correct stop/pause/play progress-bar behavior in each pattern slot.

12.28.2.4 void seq64::mainwid::update_sequences_on_window() [private]

Used by the friend class mainwnd, but also useful for our EXPERIMENTAL feature to fully highlight the current sequence.

12.28.2.5 void seq64::mainwid::update_markers(int tick) [private]

Parameters

tick Starting point for drawing the markers.

12.28.2.6 bool seq64::mainwid::valid_sequence(int seqnum) [private]

Parameters

seqnum	Provides the number of the sequence to validate.
--------	--

Returns

Returns true if the sequence number is valid for the current m_screenset value.

12.28.2.7 void seq64::mainwid::draw_sequence_on_pixmap(int seqnum) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset).

Also, we now ignore the sequence if it does not exist. :-D

Note

If only the main window is up, then the sequences just play (muted by default) – the progress bars move in each pattern. Gaps in the sequence in the Song (performance) Editor don't change the appearance of the patterns if only the main window is up. But, if the Song Editor window is up, and the song is started using the controls in the Song Editor, then the active patterns are black while playing, and white when gaps in the sequence are encountered. The muting status in the main window is ignored. The muting in the Song (performance) windows is in force. This setup holds for ALSA, but not for JACK transport.

Parameters

seqnum	Provides the number of the sequence slot that needs to be drawn. It is checked for validity before
	usage.

12.28.2.8 void seq64::mainwid::draw_sequences_on_pixmap() [private]

Please note that draw_sequence_on_pixmap() also draws the empty slots of inactive sequences, so we cannot take shortcuts here.

12.28.2.9 void seq64::mainwid::draw_sequence_pixmap_on_window(int segnum) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset. This function is used when dragging a pattern from one pattern-slot to another pattern-slot.

We have to add 1 pixel to the y height in order to avoid leaving behind a line at the bottom of an empty pattern-slot.

Parameters

seqnum	Provides the number of the sequence to draw.

12.28.2.10 int seq64::mainwid::seq_from_xy (int x, int y) [private]

Parameters

a⇔	Provides the x coordinate.
_X	
a⊷	Provides the y coordinate.
_y	

Returns

Returns -1 if the sequence number cannot be calculated.

12.28.2.11 int seq64::mainwid::timeout() [private]

Todo We should use this callback to display the current time in the playback.

Returns

Always returns true.

12.28.2.12 void seq64::mainwid::calculate_base_sizes (int seqnum, int & basex, int & basey) [private]

The values are returned as side-effects.

Parameters

seqnum	Provides the number of the sequence to calculate.
basex	A return parameter for the x coordinate of the base size.
basey	A return parameter for the y coordinate of the base size.

12.28.2.13 void seq64::mainwid::on_realize() [private]

It allocates any additional resources that weren't initialized in the constructor.

This function used to call font::init(), and was the only place where the font::init() function was called. The init() function gets a color-map from the window. We need a more fool-proof was to do this!

12.28.2.14 bool seq64::mainwid::on_expose_event(GdkEventExpose * ev) [private]

Parameters

ev	The expose event.

Returns

Always returns true.

12.28.2.15 bool seq64::mainwid::on_button_press_event (GdkEventButton * p) [private]

If the press is a single left-click, and no Ctrl key is pressed, then this function grabs the focus, calculates the pattern/sequence over which the button press occurred, and sets the m_button_down flag if it is over a pattern. In the release event callback, this then causes the sequence arming/muting to be toggled.

If the press is a single Ctrl-left-click, this function brings up the New or Edit menu. The New menu is brought up if the grid slot is empty, and the Edit menu otherwise. Another way to bring up the same functionality is described in the next paragraph.

If the press is a double-click, it first acts just like two single-clicks (which might confuse the user at first, because it toggles the mute state twice). Then it brings up the Edit menu for the sequence. This new behavior is closer to what users have come to expect from a double-click.

We also try to handle a Ctrl-double-click as a signal to do an event edit, instead of a sequence edit. The event editor provides a way to look at all events in detail, without having to select the type of event to see. However, this doesn't work, the event is treated like a ctrl-single-click. And we use the Alt key to enable window movement or resizing in our window manager, so that's out.

p Provides the parameters of the button event.

Returns

Always returns true.

12.28.2.16 bool seq64::mainwid::on_button_release_event (GdkEventButton * p) [private]

This event is a lot more complex than a press. The left button toggles playback status. The right button brings up a popup menu. If the slot is empty, then a "New" popup is presented, otherwise an "Edit" and selection popup is presented.

Also now implements the new "toggle all other patterns" action, initiated via Shift-Left-Click.

Parameters

p Provides the parameters of the button event.

Returns

Always returns true.

Try disabling the setting of the current sequence; It completely disables drag-n-drop. But leaving it in removes the current-sequence highlighting, which otherwise is fine. So we do it only if moving a pattern (drag-and-drop).

```
12.28.2.17 bool seq64::mainwid::on_motion_notify_event ( GdkEventMotion * p ) [private]
```

This function moves the selected pattern to another pattern slot. The perform::delete_sequence() function sets the perform modification flag.

Parameters

p Provides the parameters of the button event.

Returns

Always returns true.

12.28.2.18 bool seq64::mainwid::on_focus_in_event(GdkEventFocus *) [private]

Just sets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.

```
12.28.2.19 bool seq64::mainwid::on_focus_out_event( GdkEventFocus * ) [private]

Just unsets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.
```

12.28.3 Field Documentation

```
12.28.3.1 sequence seq64::mainwid::m_moving_seq [private]
```

The assignment is made by sequence::partial_copy(), which behaves like the legacy seq24 code.

```
12.28.3.2 bool seq64::mainwid::m_button_down [private]
```

Used in the drag-and-drop functionality.

```
12.28.3.3 int seq64::mainwid::m_screenset_slots [private]
```

It is equal to m_mainwnd_rows * m_mainwnd_cols.


```
12.28.3.4 int seq64::mainwid::m_screenset_offset [private]
```

It is equally to m_screenset_slots * m_screenset.

12.29 seq64::mainwnd Class Reference

This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.

Inheritance diagram for seq64::mainwnd:



Public Member Functions

- mainwnd (perform &a_p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 The constructor the main window of the application.
- ∼mainwnd ()

This destructor must explicitly delete some allocated resources.

void open_file (const std::string &)

Opens and parses (reads) a MIDI file.

• int ppqn () const

'Getter' function for member m_ppqn

• void ppqn (int ppqn)

'Setter' function for member m_ppqn We can't set the PPQN value when the mainwnd is created, we have to do it later, using this function.

Private Member Functions

• void file_import_dialog ()

Presents a file dialog to import a MIDI file.

• void options_dialog ()

Opens the File / Options dialog.

void about_dialog ()

Presents a Help / About dialog.

• void adj callback ss ()

This function is the callback for adjusting the screen-set value.

void adj_callback_bpm ()

This function is the callback for adjusting the BPM value.

void edit callback notepad ()

A callback function for handling an edit to the screen-set notepad.

bool timer callback ()

This function is the GTK timer callback, used to draw our current time and BPM on_events (the main window).

void set_image (bool isrunning)

Changes the image used for the pause/play button.

void start_playing ()

Starts playing of the song.

• void pause_playing ()

Pauses the playing of the song, leaving the progress bar where it stopped.

void stop_playing ()

Stops the playing of the song.

void toggle_playing ()

Reverses the state of playback.

void learn_toggle ()

Toggle the group-learn status.

• void open_performance_edit ()

Opens the Performance Editor (Song Editor).

void open_performance_edit_2 ()

Opens the second Performance Editor (Song Editor).

• void enregister_perfedits ()

This function brings together the two perfedit objects, so that they can tell each other when to queue up a draw operation.

void sequence_key (int seq)

Use the sequence key to toggle the playing of an active pattern in the current screen-set.

void update_window_title ()

Updates the title shown in the title bar of the window.

void toLower (std::string &)

Converts a string to lower-case letters.

• void file new ()

A callback function for the File / New menu entry.

void file_open ()

A callback function for the File / Open menu entry.

· void file save ()

A callback function for the File / Save menu entry.

void file_save_as ()

A callback function for the File / Save As menu entry.

• void file exit ()

A callback function for the File / Exit menu entry.

• void new file ()

Actually does the work of setting up for a new file.

• bool save file ()

Saves the current state in a MIDI file.

void choose_file ()

Creates a file-chooser dialog.

int query_save_changes ()

Queries the user to save the changes made while the application was running.

bool is_save ()

If the data is modified, then the user is queried, and the file is save if okayed.

• bool install signal handlers ()

Installs the signal handlers and pipe code.

bool signal action (Glib::IOCondition condition)

Handles saving or exiting actions when signalled.

• bool on delete event (GdkEventAny *a e)

This callback function handles a delete event from ...?

bool on_key_press_event (GdkEventKey *a_ev)

Handles a key press event.

bool on_key_release_event (GdkEventKey *a_ev)

Handles a key release event.

• virtual void on_grouplearnchange (bool state)

Notification handler for learn mode toggle.

Static Private Member Functions

· static void handle_signal (int sig)

This function is the handler for system signals (SIGUSR1, SIGINT...) It writes a message to the pipe and leaves as soon as possible.

Private Attributes

• Gtk::MenuBar * m menubar

Theses objects support the menu and its sub-menus.

int m_ppqn

Saves the PPQN value obtained from the MIDI file (or the default value, the global ppqn, if SEQ64_USE_DEFAUL← T_PPQN was specified in reading the MIDI file.

mainwid * m_main_wid

The biggest sub-components of mainwnd.

• maintime * m_main_time

Is this the bar at the top that shows moving squares?

perfedit * m_perf_edit

A pointer to the song/performance editor.

perfedit * m_perf_edit_2

A pointer to an optional second song/performance editor.

• options * m_options

A pointer to the program options.

• Gdk::Cursor m_main_cursor

Mouse cursor?

Gtk::Image * m_image_play

Provides a pointer to hold the images for the pause/play button.

• Gtk::Button * m_button_learn

This button is the learn button, otherwise known as the "L" button.

• Gtk::Button * m_button_stop

Implements the red square stop button.

• Gtk::Button * m_button_play

Implements the green triangle play button.

• Gtk::Button * m_button_perfedit

The button for bringing up the Song Editor (Performance Editor).

• Gtk::Adjustment * m_adjust_bpm

The spin/adjustment controls for the BPM (beats-per-minute) value.

• Gtk::Adjustment * m_adjust_ss

The spin/adjustment controls for the screen set value.

Gtk::Adjustment * m adjust load offset

The spin/adjustment controls for the load offset value.

• Gtk::Entry * m_entry_notes

What is this?

· bool m is running

Holds the current status of running, for use in display the play versus pause icon.

sigc::connection m_timeout_connect

Provides a timeout handler.

Static Private Attributes

• static int m_sigpipe [2]

Interesting; what is this used for.

Additional Inherited Members

12.29.1 Constructor & Destructor Documentation

12.29.1.1 seq64::mainwnd::mainwnd(perform & p, bool allowperf2 = true, int ppqn = SEQ64_USE_DEFAULT_PPQN

This constructor is way too large; it would be nicer to provide a number of well-named initialization functions.

Parameters

р	Refers to the main performance object.	
allowperf2	Indicates if a second perfedit window should be created. This is currently a run-time option,	
	selectable in the "user" configuration file.	

Todo Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

View menu items and their hot keys.

View menu items and their hot keys.

Help menu items

Top panel items, including the logo (updated for the new version of this application) and the "timeline" progress bar.

12.29.2 Member Function Documentation

```
12.29.2.1 void seq64::mainwnd::open_file ( const std::string & fn )
```

We leave the ppqn parameter set to the SEQ64_USE_DEFAULT for now, to preserve the legacy behavior of using the global ppqn, and scaling the running time against the PPQN read from the MIDI file. Later, we can provide a value like 0, that will certainly be changed by reading the MIDI file.

We don't need to specify the "oldformat" or "global sequence" parameters of the midifile constructor when reading the MIDI file, since reading handles both the old and new formats, dealing with new constructs only if they are present in the file.

Parameters

fn Provides the file-name for the MIDI file to be opened.

```
12.29.2.2 void seq64::mainwnd::ppqn ( int ppqn ) [inline]
```

m_ppqn = choose_ppqn(ppqn);

12.29.2.3 void seq64::mainwnd::file_import_dialog() [private]

Note that every track of the MIDI file will be imported, even if the track is only a label track (without any MIDI events), or a very long track.

The main difference between the Open operation and the Import operation seems to be that the latter can read MIDI files into a screen-set greater than screen-set 0. No, that's not true, so far. No matter what the current screen-set setting, the import is appended after the current data in screen-set 0. Then, if it overflows that screen-set, the overflow goes into the next screen-set.

It might be nice to have the option of importing a MIDI file into a specific screen-set, for better organization, as well as being able to offset the sequence number.

Also, it is important to note that perf().clear_all() is not called by this routine, as we are merely adding to what might already be there.

```
12.29.2.4 void seq64::mainwnd::about_dialog( ) [private]
```

I (Chris) took the liberty of tacking my name at the end, and hope to eventually have done enough work to warrant having it there.

```
12.29.2.5 void seq64::mainwnd::adj_callback_ss( ) [private]
```

Sets the screen-set value in the Performance/Song window, the Patterns, and something about setting the text based on a screen-set notepad from the Performance/Song window.

Let the perform object keep track of modifications.

Screen-set notepad?

```
12.29.2.6 void seq64::mainwnd::adj_callback_bpm( ) [private]
```

Let the perform object keep track of modifications.

```
12.29.2.7 void seq64::mainwnd::edit_callback_notepad( ) [private]
```

Let the perform object keep track of modifications.

```
12.29.2.8 bool seq64::mainwnd::timer_callback( ) [private]
```

Note

When Sequencer64 first starts up, and no MIDI tune is loaded, the call to mainwid:update_markers() leads to trying to do some work on sequences that don't yet exist. Also, if a sequence is changed by the event editor, we get a crash; need to find out how sequence away with the changes.

Pause:

```
These do not work:
- midipulse tick = perf().get_jack_tick();
- midipulse tick = perf().get_max_tick();
```

12.29.2.9 void seq64::mainwnd::set_image(bool isrunning) [private]

Parameters

isrunning	If true, set the image to the "Pause" icon, since playback is running. Otherwise, set it to the "Play"
	button, since playback is not running.

```
12.29.2.10 void seq64::mainwnd::start_playing() [private]
```

The rc_settings::jack_start_mode() function is used (if jack is running) to determine if the playback mode is "live" (false) or "song" (true). An accessor to perform::start_playing(). This function is actually a callback for the pause/play button.

Note

This overrides the old behavior of playing live mode if the song is started from the main window. So let's go back to the way seq24 handles it. We could also make it dependent on the –legacy option, but that's too much trouble for now.

```
12.29.2.11 void seq64::mainwnd::pause_playing() [private]
```

Currently, it is just the same as stop_playing(), but we will get it to work.

```
12.29.2.12 void seq64::mainwnd::stop_playing( ) [private]
```

An accessor to perform's stop_playing() function. Also calls the mainwid's update_sequences_on_window() function. Not sure that we need this call, since the slots seem to update anyway. But we've noticed that, with this call in place, hitting the Stop button causes a subtle change in the appearance of the first non-empty pattern of the "allofarow.mid" file.

After the Stop button is pushed (in ALSA mode), then the Space key ("start") doesn't work properly. The song starts, then quickly stops. It doesn't matter if update_sequences_on_window() is called or not. This happens even in seq24! This bug has proven incredibly difficult to track down, still working on it.

```
12.29.2.13 void seq64::mainwnd::toggle_playing( ) [private]
```

Meant only to be called when the "Play" button is pressed, if the pause feature has been compiled into the application.

```
12.29.2.14 void seg64::mainwnd::open_performance_edit( ) [private]
```

We will let perform keep track of modifications, and not just set an is-modified flag just because we opened the song editor. We're going to centralize the modification flag in the perform object, and see if it can work.

```
12.29.2.15 void seq64::mainwnd::open_performance_edit_2( ) [private]
```

Experiment: open a second one and see what happens. It works, but one needs to tell the other to redraw if a change is made.

```
12.29.2.16 void seq64::mainwnd::update_window_title( ) [private]
```

Note that the name of the application is obtained by the "(SEQ64_PACKAGE)" construction.

The format of the caption bar is the name of the package/application, followed by the file-specification (shortened if necessary so that the name of the file itself can be seen), ending with the PPQN value in parentheses.

```
12.29.2.17 void seq64::mainwnd::new_file( ) [private]
```

Not sure that we need to clear the modified flag here, especially since it is now centralizeed in the perform object. Let perf().clear_all() handle it now.

```
12.29.2.18 bool seq64::mainwnd::save_file() [private]
```

Here we specify the current value of m_ppqn, which was set when reading the MIDI file. We also let midifile tell the perform that saving worked, so that the "is modified" flag can be cleared. The midifile class is already a friend of perform.

```
12.29.2.19 bool seg64::mainwnd::signal action ( Glib::IOCondition condition ) [private]
```

Returns

Returns true if the signalling was able to be completed, even if it was an unexpected signal.

```
12.29.2.20 bool seq64::mainwnd::on_delete_event( GdkEventAny * a_e ) [private]
```

Any changed data is saved. If the pattern is playing, then it is stopped. We now use is_running(), instead of the global rc().is_pattern_playing() function.

```
12.29.2.21 bool seq64::mainwnd::on_key_press_event( GdkEventKey * ev ) [private]
```

It also handles the control-key and modifier-key combinations matching the entries in its list of if statements.

Todo Test this functionality in old and new application.

```
12.29.2.22 bool seq64::mainwnd::on_key_release_event ( GdkEventKey * ev ) [private]
```

Is this worth turning into a switch statement? Or offloading to a perform member function? The latter.

Todo Test this functionality in old and new application.

Returns

Always returns false.

```
12.29.2.23 void seq64::mainwnd::on_grouplearnchange(bool state) [private], [virtual]
```

This handler responds to a learn-mode change from perf().

Reimplemented from seq64::performcallback.

12.29.3 Field Documentation

```
12.29.3.1 int seq64::mainwnd::m_sigpipe [static], [private]
```

This static member provides a couple of pipes for signalling/messaging.

```
12.29.3.2 int seq64::mainwnd::m_ppqn [private]
```

We need it early here to be able to pass it along to child objects.

```
12.29.3.3 mainwid* seq64::mainwnd::m_main_wid [private]
```

The first is the Patterns Panel.

```
12.29.3.4 Gtk::Button* seq64::mainwnd::m_button_play [private]
```

If configured to support pause, it also supports the pause pixmap and functionality.

```
12.29.3.5 Gtk::Adjustment* seq64::mainwnd::m_adjust_load_offset [private]
```

However, where is this button located? It is handled in the code, but I've never seen the button!

12.30 seq64::mastermidibus Class Reference

The class that "supervises" all of the midibus objects?

Public Member Functions

• mastermidibus (int ppqn=SEQ64_USE_DEFAULT_PPQN, int bpm=c_beats_per_minute)

The mastermidibus default constructor fills the array with our busses.

∼mastermidibus ()

The destructor deletes all of the output busses, clears out the ALSA events, stops and frees the queue, and closes ALSA for this application.

void init (int ppqn)

Initialize the mastermidibus.

snd_seq_t * get_alsa_seq () const

'Getter' function for member m_alsa_seq

• int get_num_out_buses () const

'Getter' function for member m_num_out_buses

int get_num_in_buses () const

'Getter' function for member m_num_in_buses

void set beats per minute (int bpm)

Set the BPM value (beats per minute).

void set_ppqn (int ppqn)

Set the PPQN value (parts per quarter note).

• int get_beats_per_minute () const

'Getter' function for member m_beats_per_minute

• int get ppqn () const

'Getter' function for member m_ppqn

• std::string get_midi_out_bus_name (int a_bus)

Get the MIDI output buss name for the given (legal) buss number.

std::string get_midi_in_bus_name (int a_bus)

Get the MIDI input buss name for the given (legal) buss number.

• void print ()

Print some information about the available MIDI output busses.

· void flush ()

Flushes our local queue events out into ALSA.

• void start ()

Starts all of the configured output busses up to m_num_out_buses.

• void stop ()

Stops each of the output busses.

void clock (midipulse a_tick)

Generates the MIDI clock for each of the output busses.

void continue_from (midipulse a_tick)

Gets the output busses running again, if ALSA support is enabled.

void init_clock (midipulse a_tick)

Initializes the clock of each of the output busses.

• int poll_for_midi ()

Initiate a poll() on the existing poll descriptors.

• bool is_more_input ()

Test the ALSA sequencer to see if any more input is pending.

bool get_midi_event (event *a_in)

Grab a MIDI event.

void set sequence input (bool a state, sequence *a seq)

Set the input sequence object, and set the $m_dumping_input$ value to the given state.

bool is_dumping () const

'Getter' function for member m_dumping_input

sequence * get_sequence () const

'Getter' function for member m seq

void sysex (event *a_event)

Handle the sending of SYSEX events.

void port_start (int a_client, int a_port)

Start the given ALSA MIDI port.

void port_exit (int a_client, int a_port)

Turn off the given port for the given client.

void play (bussbyte bus, event *a e24, midibyte a channel)

Handle the playing of MIDI events on the MIDI buss given by the parameter, as long as it is a legal buss number.

void set_clock (bussbyte bus, clock_e a_clock_type)

Set the clock for the given (legal) buss number.

clock_e get_clock (bussbyte bus)

Gets the clock setting for the given (legal) buss number.

void set_input (bussbyte bus, bool a_inputing)

Set the status of the given input buss, if a legal buss number.

bool get_input (bussbyte bus)

Get the input for the given (legal) buss number.

Private Attributes

```
snd_seq_t * m_alsa_seq
```

The ALSA sequencer client handle.

• int m_num_out_buses

The number of output busses.

int m_num_in_buses

The number of input busses.

midibus * m_buses_out [c_max_busses]

Output MIDI busses.

• midibus * m_buses_in [c_max_busses]

Input MIDI busses.

• midibus * m_bus_announce

MIDI buss announcer?

bool m_buses_out_active [c_max_busses]

Active output MIDI busses.

bool m_buses_in_active [c_max_busses]

Active input MIDI busses.

• bool m_buses_out_init [c_max_busses]

Output MIDI buss initialization.

bool m_buses_in_init [c_max_busses]

Input MIDI buss initialization.

clock_e m_init_clock [c_max_busses]

Clock initialization.

bool m_init_input [c_max_busses]

Input initialization?

• int m queue

The ID of the MIDI queue.

• int m_ppqn

Resolution in parts per quarter note.

int m_beats_per_minute

BPM (beats per minute).

• int m_num_poll_descriptors

The number of descriptors for polling.

struct pollfd * m_poll_descriptors

Points to the list of descriptors for polling.

• bool m_dumping_input

For dumping MIDI input to a sequence for recording.

sequence * m_seq

Points to the sequence object.

• mutex m_mutex

The locking mutex.

12.30.1 Constructor & Destructor Documentation

```
12.30.1.1 seq64::mastermidibus::mastermidibus ( int ppqn = SEQ64_USE_DEFAULT_PPQN, int bpm = c_beats_per_minute )
```

ppqn	Provides the PPQN value for this object. However, in most cases, the default,
	SEQ64_USE_DEFAULT_PPQN should be specified. Then the caller of this constructor should call
	mastermidibus::set_ppqn() to set up the proper PPQN value.
bpm	Provides the beats per minute value, which defaults to c_beats_per_minute.

```
12.30.1.2 seq64::mastermidibus::~mastermidibus()
```

Valgrind indicates we might have issues caused by the following functions:

```
- snd_config_hook_load()
- snd_config_update_r() via snd_seq_open()
- _dl_init() and other GNU function
- init_gtkmm_internals() [version 2.4]
```

12.30.2 Member Function Documentation

```
12.30.2.1 void seq64::mastermidibus::init ( int ppqn )
```

It initializes 16 MIDI output busses, a hardwired constant, 16. Only one MIDI input buss is initialized.

```
12.30.2.2 void seq64::mastermidibus::set_beats_per_minute ( int bpm )
```

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information.

We fill the ALSA tempo structure (snd_seq_queue_tempo_t) with the current tempo information, set the BPM value, put it in the tempo structure, and give the tempo value to the ALSA queue.

Threadsafe

Parameters

bpm Provides the beats-per-minute value to set.

12.30.2.3 void seq64::mastermidibus::set_ppqn (int ppqn)

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information. Fills the tempo structure with the current tempo information. Then sets the ppqn value. Finally, gives the tempo structure to the ALSA queue.

Threadsafe

Parameters

ppqn	The PPQN value to be set.
------	---------------------------

12.30.2.4 std::string seq64::mastermidibus::get_midi_out_bus_name (int bus)

Parameters

bus Provides the output bus	number.
-----------------------------	---------

Returns

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected.

12.30.2.5 std::string seq64::mastermidibus::get_midi_in_bus_name (int bus)

Parameters

bus Provides the input buss number.

Returns

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected.

12.30.2.6 void seq64::mastermidibus::flush ()

Threadsafe

12.30.2.7 void seq64::mastermidibus::start ()

Threadsafe

12.30.2.8 void seq64::mastermidibus::stop()

If ALSA support is enable, also drains the output, synchronizes the output queue, and then stop the queue.

Threadsafe

12.30.2.9 void seq64::mastermidibus::clock (midipulse tick)

Threadsafe

Parameters

tick Provides the tick value with which to set the buss clock.

12.30.2.10 void seq64::mastermidibus::continue_from (midipulse tick) Threadsafe **Parameters** Provides the tick value to continue from. 12.30.2.11 void seq64::mastermidibus::init_clock (midipulse tick) Threadsafe **Parameters** Provides the tick value with which to initialize the buss clock. 12.30.2.12 int seq64::mastermidibus::poll_for_midi() Returns Returns the result of the poll, or 0 if ALSA is not supported. 12.30.2.13 bool seq64::mastermidibus::is_more_input() Threadsafe Returns Returns true if ALSA is supported, and the returned size is greater than 0, or false otherwise. 12.30.2.14 bool seq64::mastermidibus::get_midi_event (event * inev) Threadsafe **Parameters** The event to be set based on the found input event. 12.30.2.15 void seq64::mastermidibus::set_sequence_input (bool state, sequence * seq) Threadsafe

state Provides the dumping-input state to be set.]
seq	Provides the sequence object to be logged as the mastermidibus's sequence. Can also be used to set]
	a null pointer, to disable the sequence setting.	

12.30.2.16 void seq64::mastermidibus::sysex (event * ev)

Threadsafe

Parameters

ev	Provides the event pointer to be set.
----	---------------------------------------

12.30.2.17 void seq64::mastermidibus::port_start (int client, int port)

Threadsafe Quite a lot is done during the lock!

Parameters

client	Provides the ALSA client number.
port	Provides the ALSA client port.

12.30.2.18 void seq64::mastermidibus::port_exit (int client, int port)

Both the input and output busses for the given client are stopped, and set to inactive.

Threadsafe

Parameters

client	The client to be matched and acted on.
port	The port to be acted on. Both parameter must be match before the buss is made inactive.

12.30.2.19 void seq64::mastermidibus::play (bussbyte bus, event * e24, midibyte channel)

Threadsafe

Parameters

bus	The buss to start play on.
e24	The seq24 event to play on the buss.
channel The channel on which to play the e	

12.30.2.20 void seq64::mastermidibus::set_clock (bussbyte bus, clock_e clocktype)

The legality checks are a little loose, however.

Threadsafe

Parameters

bus	The buss to start play on.
clocktype	The type of clock to be set, either "off", "pos", or "mod", as noted in the midibus_common module.

12.30.2.21 clock_e seq64::mastermidibus::get_clock (bussbyte bus)

Parameters

bus	Provides the buss number to read.
-----	-----------------------------------

Returns

If the buss number is legal, and the buss is active, then its clock setting is returned. Otherwise, e_clock_off is returned.

12.30.2.22 void seq64::mastermidibus::set_input (bussbyte bus, bool inputing)

Why is another buss-count constant, and a global one at that, being used? And I thought there was only one input buss anyway!

Threadsafe

Parameters

<i>bus</i> Pr	ovides the buss number.
---------------	-------------------------

12.30.2.23 bool seq64::mastermidibus::get_input (bussbyte bus)

Parameters

bus	Provides the buss number.

Returns

Always returns false.

12.30.3 Field Documentation


12.30.3.1 int seq64::mastermidibus::m_beats_per_minute [private]

We had to lengthen this name; way too easy to confuse it with "bpm" for "beats per measure".

12.31 seq64::midi_container Class Reference

This class is the abstract base class for a container of MIDI track information.

Inheritance diagram for seq64::midi container:



Public Member Functions

• midi_container (sequence &seq)

Fills in the few members of this class.

virtual ∼midi_container ()

A rote constructor needed for a base class.

void fill (int tracknumber)

This function fills the given track (sequence) with MIDI data from the current sequence, preparatory to writing it to a file.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

• virtual bool done () const

Instead of checking for the size of the container when "emptying" it [see the midifile::write() function], use this function, which is overridden to match the type of container being used.

• virtual void put (midibyte b)=0

Provides a way to add a MIDI byte into the container.

• virtual midibyte get ()=0

Provide a way to get the next byte from the container.

Protected Member Functions

• unsigned int position () const

Returns the current position.

Private Member Functions

void add variable (midipulse v)

This function masks off the lower 8 bits of the long parameter, then shifts it right 7, and, if there are still set bits, it encodes it into the buffer in reverse order.

void add_long (midipulse x)

What is the difference between this function and add_list_var()?

Private Attributes

• sequence & m sequence

Provide a hook into a sequence so that we can exchange data with a sequence object.

unsigned int m_position_for_get

Provides the position in the container when making a series of get() calls on the container.

12.31.1 Member Function Documentation

```
12.31.1.1 void seq64::midi_container::fill ( int tracknumber )
```

Note that some of the events might not come out in the same order they were stored in (we see that with program-change events).

This function replaces sequence::fill_container().

Now, for sequence 0, an alternate format for writing the sequencer number chunk is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assume to increment. This application doesn't use with that shortcut.

Triggers:

```
Triggers are added by first calling add_variable(0), which is needed because why? Then 0xFF 0x7F is written, followed by the length value, which is the number of triggers at 3 long integers per trigger, plus the 4-byte code for triggers, c_triggers_new = 0x24240008.
```

Not threadsafe The sequence object bound to this container needs to provide the locking mechanism when calling this function.

tracknumber Provides the track number. This number is masked into the track information.	tracknumber	Provides the track number. This number is masked into the track information.
--	-------------	--

```
12.31.1.2 virtual void seq64::midi_container::put( midibyte b ) [pure virtual]
```

The original seq24 container used an std::list and a push_front operation.

Implemented in seq64::midi_list, and seq64::midi_vector.

```
12.31.1.3 virtual midibyte seq64::midi_container::get() [pure virtual]
```

It also increments m_position_for_get.

Implemented in seq64::midi_list, and seq64::midi_vector.

```
12.31.1.4 unsigned int seq64::midi_container::position() const [inline], [protected]
```

Before the return, the position counter is incremented to the next position.

```
12.31.1.5 void seq64::midi_container::add_variable ( midipulse v ) [private]
```

This function "replaces" sequence::add_list_var().

12.31.1.6 void seq64::midi_container::add_long (midipulse x) [private]


This function "replaces" sequence::add_long_list().

This was a *global* internal function called addLongList(). Let's at least make it a private member now, and hew to the naming conventions of this class.

12.32 seq64::midi_list Class Reference

This class is the std::list implementation of the midi_container.

Inheritance diagram for seq64::midi_list:



Public Member Functions

midi_list (sequence &seq)

This constructor fills in the members.

virtual ~midi_list ()

A rote constructor needed for a base class.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

· virtual bool done () const

For popping data from the MIDI list, we are done when the container is empty.

virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

• virtual midibyte get ()

Provide a way to get the next byte from the container.

Private Types

typedef std::list< midibyte > CharList
 Provides the type of this container.

Private Attributes

· CharList m_char_list

The container itself.

Additional Inherited Members

12.32.1 Member Typedef Documentation

```
12.32.1.1 typedef std::list<midibyte> seq64::midi_list::CharList [private]
```

This type is basically the same as the container used in the midifile module, and almost identical to the CharList type defined in the sequence module.

12.32.2 Member Function Documentation

```
12.32.2.1 virtual void seq64::midi_list::put( midibyte b ) [inline], [virtual]
```

The original seq24 list used an std::list and a push_front operation.

Implements seq64::midi_container.

```
12.32.2.2 virtual midibyte seq64::midi_list::get( ) [inline], [virtual]
```

In this implementation, m_position_for_get is not used. The elements of the container are popped off backward!

Implements seq64::midi_container.

12.33 seq64::midi_measures Class Reference

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b ← :d").

Public Member Functions

• midi_measures ()

Default constructor for midi_measures.

midi_measures (int measures, int beats, int divisions)

Principal constructor for midi_measures.

• int measures () const

'Getter' function for member m_measures

• void measures (int m)

'Setter' function for member m_measures We can add validation later.

· int beats () const

'Getter' function for member m_beats

· void beats (int b)

'Setter' function for member m_beats We can add validation later.

· int divisions () const

'Getter' function for member m divisions

void divisions (int d)

'Setter' function for member m_divisions We can add validation later.

Private Attributes

• int m_measures

The integral number of measures in the measures-based time.

• int m_beats

The integral number of beats in the measures-based time.

• int m_divisions

The integral number of divisions/pulses in the measures-based time.

12.33.1 Detailed Description

More commonly known as "bars:beats:ticks", or "BBT".

12.33.2 Field Documentation

12.33.2.1 int seq64::midi_measures::m_divisions [private]

There are two possible translations of the two bytes of a division. If the top bit of the 16 bits is 0, then the time division is in "ticks per beat" (or "pulses per quarter note"). If the top bit is 1, then the time division is in "frames per second". This function deals only with the ticks/beat definition.

12.34 seq64::midi_splitter Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

midi splitter (int ppqn=SEQ64 USE DEFAULT PPQN)

Principal constructor.

~midi_splitter ()

A rote destructor.

• bool log main sequence (sequence &seq, int seqnum)

Logs the main sequence (an SMF 0 track) for later usage in splitting the track.

· void initialize ()

Resets the SMF 0 support variables in preparation for parsing a new MIDI file.

void increment (int channel)

Processes a channel number by raising its flag in the m_smf0_channels[] array.

bool split (perform &p, int screenset)

This function splits an SMF 0, splitting all of the channels in the sequence out into separate sequences, and adding each to the perform object.

• int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

· int count () const

'Getter' function for member m_smf0_channels_count

Private Member Functions

• bool split channel (const sequence &main seq, sequence *seq, int channel)

This function splits the given sequence into new sequences, one for each channel found in the SMF 0 track.

Private Attributes

int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.

· bool m_use_default_ppqn

Indicates that the default PPQN is in force.

• int m_smf0_channels_count

Provides support for SMF 0, indicates how many channels were found in the file in a single sequence.

• bool m_smf0_channels [16]

Provides support for SMF 0, holds a bool value that indicates the occurrence of a given channel.

• sequence * m smf0 main sequence

Provides support for SMF 0, points to the initial SMF 0 sequence, from which the single-channel sequences will be created.

• int m_smf0_seq_number

Provides support for SMF 0, holds the prospective sequence number of the main (SMF 0) sequence.

12.34.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.34.2 Constructor & Destructor Documentation

12.34.2.1 seq64::midi_splitter::midi_splitter(int ppqn = SEQ64_USE_DEFAULT_PPQN)

Parameters

ppqn

Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file.

- · Reading.
 - If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The
 m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the
 MIDI file, ppqn, is then use to scale the running-time of the sequence relative to
 DEFAULT_PPQN.
 - Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the
 value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
- Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller
 must query for the PPQN set during parsing, and pass it to the constructor when preparing to
 write the file. See how it is done in the mainwand class.

12.34.3 Member Function Documentation

12.34.3.1 void seq64::midi_splitter::increment (int channel)

If it is the first entry for that channel, m_smf0_channels_count is incremented. We won't check the channel number, to save time, until someday we segfault :-D

12.34.3.2 bool seq64::midi_splitter::split (perform & p, int screenset)

Lastly, it adds the SMF 0 track as the last track; the user can then examine it before removing it. Is this worth the effort?

There is a little oddity, in that, if the SMF 0 track has events for only one channel, this code will still create a new sequence, as well as the main sequence. Not sure if this is worth extra code to just change the channels on the main sequence and put it into the correct track for the one channel it contains.

Parameters

p	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded. Returns false if no SMF 0 main sequence was logged.

12.34.3.3 int seq64::midi_splitter::ppqn() const [inline]

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midi_splitter constructor.

12.34.3.4 bool seq64::midi_splitter::split_channel (const sequence & main_seq, sequence * s, int channel)

[private]

Note that the events that are read from the MIDI file have delta times. Sequencer64 converts these delta times to cumulative times. We need to preserve that here. Conversion back to delta times is needed only when saving the sequences to a file. This is done in midi_container::fill().

We have to accumulate the delta times in order to be able to set the length of the sequence in pulses.

Luckily, we don't have to worry about copying triggers, since the imported SMF 0 track won't have any Seq24/← Sequencer24 triggers.

It doesn't set the sequence number of the sequence; that is set when the sequence is added to the perform object.

Parameters

main_seq	This parameter is the whole SMF 0 track that was read from the MIDI file. It contains all of the channel data that needs to be split into separate sequences.
s	Provides the new sequence that needs to have its settings made, and all of the selected channel events added to it.
channel	Provides the MIDI channel number (re 0) that marks the channel data the needs to be extracted and added to the new sequence.

Returns

Returns true if at least one event got added. If none were added, the caller should delete the sequence object represented by parameter *s*.

12.34.4 Field Documentation

12.34.4.1 int seq64::midi_splitter::m_smf0_channels_count [private]

SMF 1 file parsing will only warn about more than one channel found in a given sequence.

12.34.4.2 bool seq64::midi_splitter::m_smf0_channels[16] [private]

Obviously, we don't have to worry about multiple MIDI busses.

12.34.4.3 int seq64::midi_splitter::m_smf0_seq_number [private]

We want to be able to add that sequence last, for easier and cleaner removal of that sequence by the user.

12.35 seq64::midi_timing Class Reference

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

Public Member Functions

• midi_timing ()

Defaults constructor for midi_timing.

midi timing (int bpminute, int bpmeasure, int beatwidth, int ppqn)

Principal constructor for midi_timing.

• int beats_per_minute () const

'Getter' function for member m_beats_per_minute

void beats_per_minute (int b)

'Setter' function for member m_beats_per_minute We can add validation later.

• int beats_per_measure () const

'Getter' function for member m_beats_per_measure

void beats_per_measure (int b)

'Setter' function for member m_beats_per_measure We can add validation later.

int beat_width () const

'Getter' function for member m_beats_per_beat_width

void beat width (int bw)

'Setter' function for member m_beats_per_beat_width We can add validation later.

• int ppqn () const

'Getter' function for member m_ppqn

void ppqn (int p)

'Setter' function for member m_ppqn We can add validation later.

Private Attributes

• int m_beats_per_minute

This value should match the BPM value selected when editing the song.

int m_beats_per_measure

This value should match the numerator value selected when editing the sequence.

· int m beat width

This value should match the denominator value selected when editing the sequence.

• int m_ppqn

This value provides the precision of the MIDI song.

12.35.1 Detailed Description

Although Seq24/Sequencer64 currently are heavily dependent on hard-wired values, that will be rectified eventually, so let us get ready for it.

12.35.2 Field Documentation

12.35.2.1 int seq64::midi_timing::m_beats_per_minute [private]

This value is most commonly set to 120, but is also read from the MIDI file. This value is needed if one want to calculate durations in true time units such as seconds, but is not needed to calculate the number of pulses/ticks/divisions.

12.35.2.2 int seq64::midi_timing::m_beats_per_measure [private]

This value is most commonly set to 4.

12.35.2.3 int seq64::midi_timing::m_beat_width [private]

This value is most commonly set to 4, meaning that the fundamental beat unit is the quarter note.


12.35.2.4 int seq64::midi_timing::m_ppqn [private]

This value is most commonly set to 192, but is also read from the MIDI file. We are still working getting "non-standard" values to work.

12.36 seq64::midi_vector Class Reference

This class is the std::vector implementation of the midi_container.

Inheritance diagram for seq64::midi_vector:



Public Member Functions

• midi_vector (sequence &seq)

This constructor fills in the members.

virtual ~midi_vector ()

A rote constructor needed for a base class.

virtual std::size_t size () const

Returns the size of the container, in midibytes.

· virtual bool done () const

For iterating through the data in the MIDI vector, we are done when we've gotten the last element of the container.

virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

• virtual midibyte get ()

Provide a way to get the next byte from the container.

Private Types

typedef std::vector< midibyte > CharVector

Provides the type of this container.

Private Attributes

CharVector m_char_vector

The container itself.

Additional Inherited Members

12.36.1 Member Function Documentation

```
12.36.1.1 virtual void seq64::midi_vector::put( midibyte b) [inline], [virtual]
```

The original seq24 list used an std::list and a push_front operation.

Implements seq64::midi_container.

```
12.36.1.2 virtual midibyte seq64::midi_vector::get( ) [inline], [virtual]
```

In this implementation, m_position_for_get is used.

Implements seq64::midi container.

12.37 seg64::midibus Class Reference

Provides a class for handling the MIDI buss on Linux.

Public Member Functions

 midibus (int localclient, int destclient, int destport, snd_seq_t *seq, const char *client_name, const char *port name, int id, int queue, int ppqn=SEQ64 USE DEFAULT PPQN)

Provides a constructor with client number, port number, ALSA sequencer support, name of client, name of port.

• midibus (int localclient, snd_seq_t *seq, int id, int queue, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Secondary constructor.

• ∼midibus ()

A rote empty destructor.

· bool init_out ()

Initialize the MIDI output port.

bool init_in ()

Initialize the MIDI input port.

bool deinit_in ()

Deinitialize the MIDI input?

• bool init out sub ()

Initialize the output in a different way?

bool init_in_sub ()

Initialize the output in a different way?

void print ()

Prints m_name.

const std::string & get_name () const

'Getter' function for member n_name

int get_id () const

'Getter' function for member m_id

void play (event *e24, midibyte channel)

This play() function takes a native event, encodes it to an ALSA event, and puts it in the queue.

void sysex (event *e24)

Takes a native SYSEX event, encodes it to an ALSA event, and then puts it in the queue.

void start ()

This function gets the MIDI clock a-runnin', if the clock type is not e_clock_off.

• void stop ()

Stop the MIDI buss.

void clock (midipulse tick)

Generates the MIDI clock, starting at the given tick value.

void continue_from (midipulse tick)

Continue from the given tick.

· void init_clock (midipulse tick)

Initialize the clock, continuing from the given tick.

void set_clock (clock_e clocktype)

'Setter' function for member m_clock_type

clock_e get_clock () const

'Getter' function for member m_clock_type

void set_input (bool inputing)

Input functions.

bool get_input () const

'Getter' function for member m_inputing

· void flush ()

Flushes our local queue events out into ALSA.

• int get client () const

'Getter' function for member m_dest_addr_client The address of client.

• int get_port () const

'Getter' function for member m_dest_addr_port

Static Public Member Functions

static void set clock mod (int clockmod)

Set the clock mod to the given value, if legal.

static int get_clock_mod ()

Get the clock mod.

Private Attributes

• int m id

The ID of the midibus object.

clock_e m_clock_type

The type of clock to use.

bool m inputing

TBC

int m_ppqn

Provides the PPQN value in force, currently a constant.

• snd seq t *const m seq

ALSA sequencer client handle.

· const int m_dest_addr_client

Destination address of client.

· const int m dest addr port

Destination port of client.

• const int m_local_addr_client

Local address of client.

• int m_local_addr_port

Local port of client.

• int m_queue

Another ID of the MIDI queue?

• std::string m_name

The name of the MIDI buss.

• midipulse m_lasttick

The last (most recent? final?) tick.

• mutex m_mutex

Locking mutex.

Static Private Attributes

• static int m_clock_mod

This is another name for "16 * 4".

Friends

· class mastermidibus

The master MIDI bus sets up the buss.

12.37.1 Constructor & Destructor Documentation

12.37.1.1 seq64::midibus::midibus (int *localclient*, int *destclient*, int *destport*, snd_seq_t * seq, const char * client_name, const char * port_name, int id, int queue, int ppqn = SEQ64_USE_DEFAULT_PPQN)

Parameters

localclient	Provides the local-client number.
destclient	Provides the destination-client number.
destport	Provides the destination-client port.
seq	Provides the sequence that will work with this buss.
client_name	Provides the client name, but this parameter is unused.
port_name	Provides the port name.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used in the constructed human-readable buss name.
queue	Provides the queue ID.

```
12.37.1.2 seq64::midibus::midibus ( int localclient, snd_seq_t * seq, int id, int queue, int ppqn = SEQ64\_USE\_DEFAULT\_PPQN )
```

Similar to the principal constructor, but labels the buss by number more than by name.

Parameters

localclient	Provides the local-client number.
seq	Provides the sequence that will work with this buss.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used
	in the constructed human-readable buss name.
queue	Provides the queue ID.

12.37.2 Member Function Documentation

12.37.2.1 bool seq64::midibus::init_out()

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.37.2.2 bool seq64::midibus::init_in()

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.37.2.3 bool seq64::midibus::deinit_in()

Returns

Returns true, unless an error occurs.

12.37.2.4 bool seq64::midibus::init_out_sub()

Returns

Returns true unless setting up the ALSA port failed in some way.

12.37.2.5 bool seq64::midibus::init_in_sub()

Returns

Returns true unless setting up the ALSA port failed in some way.

12.37.2.6 void seq64::midibus::play (event * e24, midibyte channel)

Threadsafe

Parameters

e24	The event to be played on this bus.
channel	The channel of the playback.

12.37.2.7 void seq64::midibus::sysex (event * e24)

Parameters

e24 The eve	nt to be handled.
-------------	-------------------

12.37.2.8 void seq64::midibus::clock (midipulse tick)

Parameters

tick Provides the starting tick.

12.37.2.9 void seq64::midibus::continue_from (midipulse tick)

Parameters

tick The continuing tick.

12.37.2.10 void seq64::midibus::init_clock (midipulse tick)

Parameters

tick The starting tick.

12.37.2.11 void seq64::midibus::set_input (bool inputing)

Set status to of "inputting" to the given value.

If the parameter is true, then init_in() is called; otherwise, deinit_in() is called.

Parameters

inputing	The inputing value to set.
----------	----------------------------

12.37.3 Field Documentation

```
12.37.3.1 int seq64::midibus::m_clock_mod [static], [private]
```

Initialize this static member.

12.38 seq64::midifile Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

 midifile (const std::string &name, int ppqn=SEQ64_USE_DEFAULT_PPQN, bool oldformat=false, bool globalbgs=true)

Principal constructor.

• ∼midifile ()

A rote destructor.

• bool parse (perform &a_perf, int a_screen_set=0)

This function opens a binary MIDI file and parses it into sequences and other application objects.

bool write (perform &a_perf)

Write the whole MIDI data and Seq24 information out to the file.

• const std::string & error_message () const

'Getter' function for member m_error_message

• bool error_is_fatal () const

'Getter' function for member m_error_is_fatal

• int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

Private Member Functions

bool parse_smf_0 (perform &p, int screenset)

This function parses an SMF 0 binary MIDI file as if it were an SMF 1 file, then, if more than one MIDI channel was encountered in the sequence, splits all of the channels in the sequence out into separate sequences.

bool parse_smf_1 (perform &p, int screenset, bool is_smf0=false)

This function parses an SMF 1 binary MIDI file; it is basically the original seq25 midifile::parse() function.

midilong parse_prop_header (int file_size)

Parse the proprietary header, figuring out if it is the new format, or the legacy format, for sequencer-specific data.

bool parse_proprietary_track (perform &a_perf, int file_size)

After all of the conventional MIDI tracks are read, we're now at the "proprietary" Seq24 data section, which describes the various features that Seq24 supports.

• int pow2 (int logbase2)

Internal function for simple calculation of a power of 2 without a lot of math.

• bool checklen (midilong len, midibyte type)

Internal function to check for and report a bad length value.

void add_trigger (sequence &seq, midishort ppqn)

Internal function to make the parser easier to read.

midilong read_long ()

Reads 4 bytes of data using read_byte().

• midishort read short ()

Reads 2 bytes of data using read_byte().

midibyte read_byte ()

Reads 1 byte of data directly from the m_data vector, incrementing m_pos after doing so.

• midilong read varinum ()

Read a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

• void write_long (midilong value)

Writes 4 bytes, using the write_byte() function.

void write_short (midishort value)

Writes 2 bytes, using the write_byte() function.

• void read_byte_array (midibyte *b, int len)

A helper function to simplify reading midi_control data from the MIDI file.

void write_byte (midibyte c)

Writes 1 byte.

void write varinum (midilong)

Writes a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

void write track name (const std::string &trackname)

Writes out a track name.

std::string read_track_name ()

Reads the track name.

void write_seq_number (midishort seqnum)

Writes out a sequence number.

int read_seq_number ()

Reads the sequence number.

void write track end ()

Writes out the end-of-track marker.

void write_prop_header (midilong tag, long len)

We want to write:

bool write_proprietary_track (perform &a_perf)

Writes out the proprietary/SeqSpec section, using the new format if the legacy format is not in force.

long varinum_size (long len) const

Calculates the length of a variable length value.

long prop_item_size (long datalen) const

Calculates the size of a proprietary item, as written by the write_prop_header() function, plus whatever is called to write the data.

long track_name_size (const std::string &trackname) const

Calculates the size of a trackname and the meta event that specifies it.

void errdump (const std::string &msg)

Helper function to emit more useful error messages.

void errdump (const std::string &msg, unsigned long p)

Helper function to emit more useful error messages for erroneous long values.

long seq_number_size () const

Returns the size of a sequence-number event, which is always 5 bytes, plus one byte for the delta time that precedes it

· long track end size () const

Returns the size of a track-end event, which is always 3 bytes.

bool is_sysex_special_id (midibyte ch)

Check for special SysEx ID byte.

Private Attributes

• int m_file_size

Holds the size of the MIDI file.

• std::string m_error_message

Holds the last error message, useful for trouble-shooting without having Sequencer64 running in a console window.

bool m_error_is_fatal

Indicates if the error should be considered fatal.

bool m_disable_reported

Indicates that file reading has already been disabled (due to serious errors), so don't complain about it anymore.

• int m pos

Holds the position in the MIDI file.

• const std::string m_name

The unchanging name of the MIDI file.

• std::vector< midibyte > m_data

This vector of characters holds our MIDI data.

std::list< midibyte > m_char_list

Provides a list of characters.

bool m_new_format

Use the new format for the proprietary footer section of the Seq24 MIDI file.

• bool m_global_bgsequence

Indicates to store the new key, scale, and background sequence in the global, "proprietary" section of the MIDI song.

• int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.

bool m_use_default_ppqn

Indicates that the default PPQN is in force.

• midi_splitter m_smf0_splitter

Provides support for SMF 0.

12.38.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.38.2 Constructor & Destructor Documentation

12.38.2.1 seq64::midifile::midifile (const std::string & name, int ppqn = SEQ64_USE_DEFAULT_PPQN, bool oldformat = false, bool globalbgs = true)

Parameters

name	Provides the name of the MIDI file to be read or written.
ppqn	Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file.
	Reading.
	 If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the MIDI file, ppqn, is then use to scale the running-time of the sequence relative to DEFAULT_PPQN.
	 Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
	 Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller must query for the PPQN set during parsing, and pass it to the constructor when preparing to write the file. See how it is done in the mainwand class.
oldformat	If true, write out the MIDI file using the old Seq24 format, instead of the new MIDI-compliant sequencer-specific format, for the seq24-specific SeqSpec tags defined in the globals module. This option is false by default. Note that this option is only used in writing; reading can handle either format transparently.
globalbgs	If true, write any non-default values of the key, scale, and background sequence to the global "proprietary" section of the MIDI file, instead of to each sequence. Note that this option is only used in writing; reading can handle either format transparently.

12.38.3 Member Function Documentation

MIDI channel:

12.38.3.1 bool seq64::midifile::parse (perform & p, int screenset = 0)

In addition to the standard MIDI track data in a normal track, Seq24/Sequencer64 adds four sequencer-specific events just before the end of the track:

```
c_triggers_new: SeqSpec FF 7F 1C 24 24 00 08 00 00 ...
c_midibus: SeqSpec FF 7F 05 24 24 00 01 00
c_timesig: SeqSpec FF 7F 06 24 24 00 06 04 04
c_midich: SeqSpec FF 7F 05 24 24 00 02 06

Note that only Sequencer64 adds "FF 7F len" to the SeqSpec data.

Standard MIDI provides for port and channel specification meta events, but they are apparently considered obsolete:

Obsolete meta-event: Replacement:

MIDI port (buss): FF 21 01 po Device (port) name: FF 09 len text
```

FF 20 01 ch

What do other applications use for specifying port/channel?

Note on the is-modified flag: We now assume that the perform object is starting from scratch when parsing. But we let mainwnd tell the perform object when to clear everything with perform::clear_all(). The mainwnd does this for a new file, opening a file, but not for a file import, which might be done simply to add more MIDI tracks to the current composition. So, if parsing succeeds, all we want to do is make sure the flag is set.

Parsing a file successfully is not always a modification of the setup. For instance, the first read of a MIDI file should start clean, not dirty.

SysEx notes:

Some files (e.g. Dixie04.mid) do not always encode System Exclusive messages properly for a MIDI file. Instead of a varinum length value, they are followed by extended IDs (0x7D, 0x7E, or 0x7F).

We've covered some of those cases by disabling access to m_data if the position passes the size of the file, but we want try to bypass these odd cases properly. So we look ahead for one of these special values.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file. This value ranges from -31 to 0 to +31 (32 is the maximum screen-set available in Seq24). This offset is added to the sequence number read in for the sequence, to place it elsewhere in the imported tune, and locate it in a specific screen-set. If this parameter is non-zero, then we will assume that the perform data is dirty.

Returns

Returns true if the parsing succeeded. Note that the error status is saved in m_error_is_fatal, and a message (to display later) is saved in m_error_message.

12.38.3.2 bool seq64::midifile::write (perform & p)

Parameters

p Provides the object that will contain and manage the entire performance.

Returns

Returns true if the write operations succeeded.

Note

Seq24 reverses the order of some events, due to popping from its container. Not an issue here.

12.38.3.3 int seq64::midifile::ppqn() const [inline]

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midifile constructor.

12.38.3.4 bool seq64::midifile::parse_smf_0 (perform & p, int screenset) [private]

The original sequence remains in place, in sequence slot 16 (the 17th slot). The user is responsible for deleting it if it is not needed.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded.

12.38.3.5 bool seq64::midifile::parse_smf_1 (perform & p, int screenset, bool is_smf0 = false) [private]

It assumes the file-data has already been read into memory. It also assumes that the ID, track-length, and format have already been read.

Parameters

p	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded.

12.38.3.6 midilong seq64::midifile::parse_prop_header(int file_size) [private]

The new format creates a final track chunk, starting with "MTrk". Then comes the delta-time (here, 0), and the event. An event is a MIDI event, a SysEx event, or a Meta event.

A MIDI Sequencer Specific meta message includes either a delta time or absolute time, and the MIDI Sequencer Specific event encoded as follows:

0x00 0xFF 0x7F length data

For convenience, this function first checks the amount of file data left. If enough, then it reads a long value. If the value starts with 0×00 0xFF 0x7F, then that is a SeqSpec event, which signals usage of the new Sequencer64 "proprietary" format. Otherwise, it is probably the old format, and the long value is a control tag $(0 \times 242400 \text{nn})$, which can be returned immedidately.

If it is the new format, we back up to the FF, then get the next byte, which should be a 7F. If so, then we read the length (a variable length value) of the data, and then read the long value, which should be the control tag, which, again, is returned by this function.

Note

Most sequencers seem to be tolerant of both the lack of an "MTrk" marker and of the presence of an unwrapped control tag, and so can handle both the old and new formats of the final proprietary track.

Parameters

file_size	The size of the data file. This value is compared against the member m_pos (the position inside
	m_data[]), to make sure there is enough data left to process.

Returns

Returns the control-tag value found. These are the values, such as c_midich, found in the globals module, that indicate the type of sequencer-specific data that comes next. If there is not enough data to process, then 0 is returned.

12.38.3.7 bool seq64::midifile::parse_proprietary_track(perform & p, int file_size) [private]

It consists of series of tags:

```
c_midictrl
c_midiclocks
c_notes
c_bpmtag (beats per minute)
c_mutegroups
c_musickey (new, added if usr() global_seq_feature() is true)
c_musicscale (ditto)
c_backsequence (ditto)
```

(There are more tags defined in the globals module, but they are not used in this function. This doesn't quite make sense, as there are also some "triggers" values, and we're pretty sure the application uses them. Oh, it turns out that they are set up by actions performed on each sequence, and are stored as sequencer-specific ("SeqSpec") data with each track's data as held in the MIDI container for the track. See the midi_container module for more information.)

The format is (1) tag ID; (2) length of data; (3) the data.

First, we separate out this function for a little more clarity. Then we added code to handle reading both the legacy Seq24 format and the new, MIDI-compliant format. Note that even the new format is not quite correct, since it doesn't handle a MIDI manufacturer's ID, making it a single byte that is part of the data. But it does have the "MTrk" marker and track name, so that must be processed for the new format.

Now, in our "midicvt" project, we have a test MIDI file, b4uacuse-non-mtrk.midi that is good, except for having a tag "MUnk" instead of "MTrk". We should consider being more permissive, if possible. Otherwise, though, the only penality is that the "proprietary" chunk is completely skipped.

Parameters

p	The performance object that is being set via the incoming MIDI file.
file_size	The file size as determined in the parse() function.

There are also implicit parameters, with the m_pos and m_new_format member variables.

12.38.3.8 int seq64::midifile::pow2 (int logbase2) [private]

Use for calculating the denominator of a time signature.

Parameters

logbase2	Provides the power to which 2 is to be raised. This integer is probably only rarely greater than 4
	(which represents a denominator of 16).

Returns

Returns 2 raised to the logbase2 power.

12.38.3.9 bool seq64::midifile::checklen (midilong len, midibyte type) [private]

Parameters

len	The length value to be checked, and it should be greater than 0.
type	The type of meta event. Used for displaying an error.

Returns

Returns true if the length parameter is valid.

12.38.3.10 void seq64::midifile::add_trigger(sequence & seq, midishort ppqn) [private]

Handles only c_triggers_new values, not the old c_triggers value. If m_ppqn isn't set to the default value, then we must scale these triggers accordingly, just as is done for the MIDI events.

Parameters

seq	Provides the sequence to which the trigger is to be added.
ppqn	Provides the ppqn value to use to scale the tick values if m_use_default_ppqn is true. If 0, the ppqn value is not used.

12.38.3.11 midilong seq64::midifile::read_long() [private]

Warning

This code looks endian-dependent and integer-size dependent.

12.38.3.12 midilong seq64::midifile::read_varinum() [private]

This function reads the bytes while bit 7 is set in each byte. Bit 7 is a continuation bit. See write_varinum() for more information.

12.38.3.13 void seq64::midifile::write_long(midilong x) [private]

Warning

This code looks endian-dependent.

12.38.3.14 void seq64::midifile::write_short(midishort x) [private]

Warning

This code looks endian-dependent.

12.38.3.15 void seq64::midifile::read_byte_array(midibyte * b, int len) [inline], [private]

Parameters

b	The byte array to receive the data.
len	The number of bytes in the array, and to be read.

12.38.3.16 void seq64::midifile::write_byte (midibyte c) [inline], [private]

The byte is written to the m_char_list member, using a call to push_back().

12.38.3.17 void seq64::midifile::write_varinum (midilong value) [private]

A MIDI file Variable Length Value is stored in bytes. Each byte has two parts: 7 bits of data and 1 continuation bit. The highest-order bit is set to 1 if there is another byte of the number to follow. The highest-order bit is set to 0 if this byte is the last byte in the VLV.

To recreate a number represented by a VLV, first you remove the continuation bit and then concatenate the leftover bits into a single number.

To generate a VLV from a given number, break the number up into 7 bit units and then apply the correct continuation bit to each byte.

In theory, you could have a very long VLV number which was quite large; however, in the standard MIDI file specification, the maximum length of a VLV value is 5 bytes, and the number it represents can not be larger than 4 bytes.

Here are some common cases:

```
Numbers between 0 and 127 (0x7F) are represented by a single byte.
0x80 is represented as "0x81 0x00".
0x0FFFFFFFF (the largest number) is represented as "0xFF 0xFF
```

Also see the varinum_size() function.

0xFF 0x7F".

12.38.3.18 void seq64::midifile::write_track_name(const std::string & trackname) [private]

Note that we have to precede this "event" with a delta time value, set to 0.

```
12.38.3.19 std::string seq64::midifile::read_track_name( ) [private]
```

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the track name, or an empty string if there was a problem.

```
12.38.3.20 void seq64::midifile::write_seq_number( midishort seqnum ) [private]
```

The format is "00 FF 00 02 ss ss", where "02" is actually the constant length of the data. We have to precede these values with a 0 delta time, of course.

Now, for sequence 0, an alternate format is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assumed to increment. Our application doesn't bother with that shortcut.

```
12.38.3.21 int seq64::midifile::read_seq_number( ) [private]
```

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the sequence number found, or -1 if it was not found.

12.38.3.22 void seq64::midifile::write_prop_header(midilong control_tag, long data_length) [private]

- 0x4D54726B. The track tag "MTrk". The MIDI spec requires that software can skip over non-standard chunks. "Prop"? Would require a fix to midicvt.
- 0xaabbccdd. The length of the track. This needs to be calculated somehow.
- 0x00. A zero delta time.
- 0x7f7f. Sequence number, a special value, well out of normal range.
- The name of the track:
 - "Seq24-Spec"
 - "Sequencer64-S"

Then follows the proprietary/SeqSpec data, written in the normal manner. Finally, tack on the track-end meta-event.

Components of final track size:

```
-# Delta time. 1 byte, always 0x00.
-# Sequence number. 5 bytes. OPTIONAL. We won't write it.
-# Track name. 3 + 10 or 3 + 15
-# Series of proprietary/SeqSpec specs:
    -# Prop header:
    -# If legacy format, 4 bytes.
    -# Otherwise, 2 bytes + varinum_size(length) + 4 bytes.
    -# Length of the prop data.
-# Track End. 3 bytes.
```

Writes a "proprietary" (SeqSpec) Seq24 footer header in either the new MIDI-compliant format, or the legacy Seq24 format. This function does not write the data. It replaces calls such as "write_long(c_midich)" in the proprietary secton of write().

The legacy format just writes the control tag (0x242400xx). The new format writes 0x00 0xFF 0x7F len 0x242400xx; the first 0x00 is the delta time.

In the new format, the 0x24 is a kind of "manufacturer ID". At http://www.midi.org/techspecs/manid. php we see that most manufacturer IDs start with 0x00, and are thus three bytes long, or start with codes at 0x40 and above. Similary, this site shows that no manufacturer uses 0x24:

http://sequence15.blogspot.com/2008/12/midi-manufacturer-ids.html

Warning

Currently, the manufacturer ID is not handled; it is part of the data, which can be misleading in programs that analyze MIDI files.

Parameters

control_tag	Determines the type of sequencer-specific section to be written. It should be one of the value in the globals module, such as c_midibus or c_mutegroups.
data_length	The amount of data that will be written. This parameter does not count the length of the header itself.

```
12.38.3.23 bool seq64::midifile::write_proprietary_track( perform & p ) [private]
```

The first thing to do, for the new format only, is calculate the length of this big section of data. This was quite tricky; we tweaked and adjusted until the midicvt program handled the whole new-format file without emitting any errors.

Here's the basics of what Seq24 did for writing the data in this part of the file:

```
-# Write the c_midictrl value, then write a 0. To us, this looks like
no one wrote any code to write this data. And yet, the parsing
code can handles a non-zero value, which is the number of sequences
as a long value, not a byte. So shouldn't we write 4 bytes, not
one? Yes, indeed, we made a mistake. However, we should be
writing out the full data set as well. But not even Seq24 does
that! Perhaps they decided it was best kept in the "rc"
configuration file.
-# MORE TO COME.
```

```
12.38.3.24 long seq64::midifile::varinum_size ( long len ) const [private]
```

This function is needed when calculating the length of a track. Note that it handles only the following situations:

https://en.wikipedia.org/wiki/Variable-length_quantity

```
1 byte: 0x00 to 0x7F
2 bytes: 0x80 to 0x3FFF
3 bytes: 0x4000 to 0x001FFFFF
4 bytes: 0x200000 to 0x0FFFFFFF
```

Returns

Returns values as noted above. Anything beyond that range returns 0.

```
12.38.3.25 long seq64::midifile::prop_item_size ( long data_length ) const [private]
```

If using the new format, the length includes the sum of sequencer-specific tag (0xFF 0x7F) and the size of the variable-length value. Then, for legacy and new format, 4 bytes are added for the Seq24 MIDI control value, and then the data length is added.

```
12.38.3.26 void seq64::midifile::errdump(const std::string & msg) [private]
```

It adds the file offset to the message.

Parameters

msg	The main error message string, without an ending newline character.
-----	---

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

12.38.3.27 void seq64::midifile::errdump (const std::string & msg, unsigned long value) [private]

It adds the file offset to the message.

Parameters

	msg	The main error message string, without an ending newline character.
ĺ	value	The long value to show as part of the message.

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

12.38.3.28 bool seq64::midifile::is_sysex_special_id (midibyte ch) [inline], [private]

Parameters

ch | Provides the byte to be checked against 0x7D through 0x7F.

Returns

Returns true if the byte is SysEx special ID.

12.38.4 Field Documentation

```
12.38.4.1 int seq64::midifile::m_file_size [private]
```

This variable was added when loading a file that caused an attempt to load data well beyond the file-size of the midicvt test file Dixie04.mid.

```
12.38.4.2 std::string seq64::midifile::m_error_message [private]
```

If empty, there's no pending error. Currently most useful in the parse() function.

```
12.38.4.3 bool seq64::midifile::m_error_is_fatal [private]
```

The caller can query for this value after getting the return value from parse().

```
12.38.4.4 bool seq64::midifile::m_disable_reported [private]
```

Once is enough.

```
12.38.4.5 int seq64::midifile::m_pos [private]
```

This is at least a 31-bit value in the recent architectures running Linux and Windows, so it will handle up to 2 Gb of data. This member is used as the offset into the m data vector.

```
12.38.4.6 std::vector<midibyte> seq64::midifile::m_data [private]
```

We could also use a string of characters, unsigned. This member is resized to the putative size of the MIDI file, in the parse() function. Then the whole file is read into it, as if it were an array. This member is an input buffer.

```
12.38.4.7 std::list<midibyte> seq64::midifile::m_char_list [private]
```

The class pushes each MIDI byte into this list using the write_byte() function. Also note that the write() function calls sequence::fill_list() to fill a temporary std::list<char> (!) buffer, then writes that data backwards to this member. This member is an output buffer.

```
12.38.4.8 bool seq64::midifile::m_new_format [private]
```

In the new format, each sequencer-specfic value (0x242400xx, as defined in the globals module) is preceded by the sequencer-specific prefix, 0xFF 0x7F len id/date). By default, the new format is used, but the user can specify the —legacy (-I) option, or make a soft link to the sequence24 binary called "seq24", to write the data in the old format. [We will eventually add the —legacy option to the "rc" configuration file.] Note that reading can handle either format transparently.


```
12.38.4.9 midi_splitter seq64::midifile::m_smf0_splitter [private]
```

This object holds all of the information needed to split a multi-channel sequence.

12.39 seq64::mutex Class Reference

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.

Inheritance diagram for seq64::mutex:



Public Member Functions

• mutex ()

The constructor assigns the recursive mutex to the local locking mutex.

· void lock () const

Lock the mutex.

· void unlock () const

Unlock the mutex.

Protected Attributes

pthread_mutex_t m_mutex_lock

Provides a mutex lock usable by a single module or class.

Static Private Attributes

· static const pthread mutex t sm recursive mutex

Provides a way to disable the locking.

12.39.1 Field Documentation

```
12.39.1.1 const pthread_mutex_t seq64::mutex::sm_recursive_mutex [static], [private]
```

Define the static recursive mutex and its condition variable.

Mostly experimental, we want to disable locking to see if we can speed up MIDI file reading when the application is compiled for debugging. It takes about 8 seconds to read our sample MIDI files. This does not solve the problem of the long MIDI-file parsing, however.

```
static bool sm_mutex_enabled;
```

Provides a recursive mutex that can be used by the whole application, apparently.

12.40 seq64::options Class Reference

This class supports a full tabbed options dialog.

Inherits Dialog.

Private Types

Private Attributes

· perform & m_mainperf

The performance object to which some of these options apply.

• Gtk::Button * m_button_ok

The famous "OK" button's pointer.

Gtk::CheckButton * m_button_jack_transport

Main JACK transport selection.

• Gtk::CheckButton * m button jack master

Main JACK transport master selection.

• Gtk::CheckButton * m_button_jack_master_cond

Main JACK transport master-conditional selection.

Gtk::Button * m_button_jack_connect

JACK Connect button, which we need to enable/disable for clarity and some additional safety.

Gtk::Button * m_button_jack_disconnect

JACK Disonnect button, which we need to enable/disable for clarity and some additional safety.

Gtk::Notebook * m_notebook

Not sure yet what this notebook is for.

12.40.1 Member Enumeration Documentation

12.40.1.1 enum seq64::options::button [private]

Enumerator

e_jack_transport Defines buttons indices or IDs for some controls related to JACK. These values are handled in options::transport_callback(). Some of them set JACK-related values in the rc_settings object, while the others set up or tear down the JACK support of sequencer64.

The JACK Transport settings are a little messy. They should be radio buttons, and control each other's settings. Currently, if the user wants to set up for JACK Master, the JACK Transport button must also be checked.

```
Turns on the "with JACK Transport" option,
rc_settings::with_jack_transport().
```

- e_jack_master Turns on the "with JACK Master" option, rc_settings::with_jack_master(). If another application is already JACK Master, this will fail.
- e_jack_master_cond Turns on the "with JACK Master" option rc_settings::with_jack_master_cond(). This option makes sequencer64 the JACK Master conditionally, that is, if no other application has claimed that role.
- **e_jack_start_mode_live** Doesn't directly do anything; the live mode versus song mode is set by the e_
 jack_start_mode_song value.
- e_jack_connect Causes the perform object's JACK initialization function, perform::init_jack(), to be called.
- e_jack_disconnect Causes the perform object's JACK deinitialization function, perform::deinit_jack(), to be called.

12.40.2 Field Documentation


12.40.2.1 Gtk::Notebook* seq64::options::m_notebook [private]

Must be a GTK thang.

12.41 seq64::optionsfile Class Reference

Provides a file for reading and writing the application' main configuration file.

Inheritance diagram for seq64::optionsfile:



Public Member Functions

• optionsfile (const std::string &name)

Principal constructor.

∼optionsfile ()

A rote destructor.

• bool parse (perform &perf)

Parse the \sim /.seq24rc or \sim /.config/sequencer64/sequencer64.rc file.

• bool write (const perform &perf)

This options-writing function is just about as complex as the options-reading function.

Additional Inherited Members

12.41.1 Detailed Description

The settings that are passed around are provided or used by the perform class.

12.41.2 Member Function Documentation

```
12.41.2.1 bool seq64::optionsfile::parse(perform & p) [virtual]
```

[midi-control]

Get the number of sequence definitions provided in the [midi-control] section. Ranges from 32 on up. Then read in all of the sequence lines. The first 32 apply to the first screen set. There can also be a comment line "# mute in group" followed by 32 more lines. Then there are addditional comments and single lines for BPM up, BPM down, Screen Set Up, Screen Set Down, Mod Replace, Mod Snapshot, Mod Queue, Mod Gmute, Mod Glearn, and Screen Set Play. These are all forms of MIDI automation useful to control the playback while not sitting near the computer.

[mute-group]

The mute-group starts with a line that indicates up to 32 mute-groups are defined. A common value is 1024, which means there are 32 groups times 32 keys. But this value is currently thrown away. This value is followed by 32 lines of data, each contained 4 sets of 8 settings. See the seq24-doc project on GitHub for a much more detailed description of this section.

[midi-clock]

The MIDI-clock section defines the clocking value for up to 16 output busses. The first number, 16, indicates how many busses are specified. Generally, these busses are shown to the user with names such as "[1] seq24 1".

[keyboard-control]

The keyboard control defines the keys that will toggle the stage of each of up to 32 patterns in a pattern/sequence box. These keys are displayed in each box as a reminder. The first number specifies the Key number, and the second number specifies the Sequence number.

[keyboard-group]

The keyboard group specifies more automation for the application. The first number specifies the Key number, and the second number specifies the Group number. This section should be better described in the seq24-doc project on GitHub.

[jack-transport]

This section covers various JACK settings, one setting per line. In order, the following numbers are specfied:

```
    jack_transport - Enable sync with JACK Transport.
    jack_master - Seq24 will attempt to serve as JACK Master.
    jack_master_cond - Seq24 will fail to be Master if there is already a Master set.
    jack_start_mode:

            0 = Playback will be in Live mode. Use this to allow muting and unmuting of loops.
            1 = Playback will use the Song Editor's data.
```

[midi-input]

This section covers the MIDI input busses, and has a format similar to "[midi-clock]". Generally, these busses are shown to the user with names such as "[1] seq24 1", and currently there is only one input buss. The first field is the port number, and the second number indicates whether it is disabled (0), or enabled (1).

[midi-clock-mod-ticks]

This section covers.... One common value is 64.

[manual-alsa-ports]

This section covers.... Set to 1 if you want seq24 to create its own ALSA ports and not connect to other clients.

[last-used-dir]

This section simply holds the last path-name that was used to read or write a MIDI file. We still need to add a check for a valid path, and currently the path must start with a "/", so it is not suitable for Windows.

[interaction-method]

This section specified the kind of mouse interaction.

- 0 = 'seq24' (original Seq24 method).
- 1 = 'fruity' (similar to a certain fruity sequencer we like).

The second data line is set to "1" if Mod4 can be used to keep seq24 in note-adding mode even after the right-click is released, and "0" otherwise.

Implements seq64::configfile.

12.41.2.2 bool seq64::optionsfile::write (const perform & p) [virtual]

Parameters

p Provides a const reference to the main perform object. However, we have to cast away the constness, because too many of the perform getter functions are used in non-const contexts.

Returns

Returns true if the write operations all succeeded.


New boolean to show sequence numbers; ignored in legacy mode.

Implements seq64::configfile.

12.42 seq64::perfedit Class Reference

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

Inheritance diagram for seq64::perfedit:



Public Member Functions

- perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAULT_PPQN)

 Principal constructor, has a reference to a perform object.
- ∼perfedit ()

This rote constructor does nothing.

• void init_before_show ()

This function forwards its call to the perfroll function of the same name.

• void enqueue_draw (bool forward=true)

Helper wrapper for calling perfroll::queue_draw() for one or both perfedits.

• void set_zoom (int z)

Implements the horizontal zoom feature.

• void enregister_peer (perfedit *peer)

Register the peer perfedit object.

Static Public Member Functions

static bool zoom_check (int z)

Checks zoom values for the z/Z keystrokes used in perfroll and perftime.

Private Member Functions

void set_beats_per_bar (int bpm)

Sets the beats-per-measure text and value to the given value, and then calls set_guides().

void set beat width (int bw)

Sets the BW (beat width, or the denominator in the time signature) text and values to the given value, and then calls set_guides().

• void set_snap (int snap)

Sets the snap text and values to the given value, and then calls set_guides().

• void set_guides ()

Sets the guides, which are the L and R user-interface elements.

• void grow ()

Increments the size of the perfroll and perftime objects.

void set_looped ()

Set the looping in the perform object.

• void expand ()

Implement the expand action.

• void collapse ()

Implement the collapse action.

• void copy ()

Implement the copy (actually, expand-and-copy) action.

• void undo ()

Implement the undo feature (Ctrl-Z).

• void popup_menu (Gtk::Menu *menu)

Opens the given popup menu.

• bool timeout ()

Handles a drawing timeout.

void set_image (bool isrunning)

Changes the image used for the pause/play button.

void start_playing ()

Implement the playing.

void pause_playing ()

Pauses the playing of the song, leaving the progress bar where it stopped.

void stop_playing ()

Stop the playing.

void toggle_playing ()

Reverses the state of playback.

• void on_realize ()

This callback function calls the base-class on_realize() function, and then connects the perfedit::timeout() function to the Glib signal-timeout, with a redraw timeout of redraw_period_ms().

• bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on_delete_event (GdkEventAny *)

All this callback function does is return false.

Private Attributes

• perfedit * m_peer_perfedit

The partner instance of perfedit.

• Gtk::Table * m_table

A whole horde of GUI elements.

• Gtk::Button * m button play

Implements the yellow two-bar pause button.

• Gtk::Menu * m_menu_bpm

Menus for time signature, beats per measure, beat width.

int m_snap

Set snap-to in "pulses".

• int m_bpm

The current "beats per measure" value.

• int m bw

The current "beat width" value.

• int m ppqn

The current "parts per quarter note" value.

bool m_is_running

Holds the current status of running, for use in display the play versus pause icon.

• int m standard bpm

The standard "beats per measure" of Sequencer64, which here matches the beats-per-measure displayed in the perfroll (piano roll).

Additional Inherited Members

12.42.1 Detailed Description

It has a seqroll and piano roll? No, it has a perform, a perfnames, a perfroll, and a perftime.

12.42.2 Constructor & Destructor Documentation

```
12.42.2.1 seq64::perfedit::perfedit ( perform & p, bool second_perfedit = false, int ppqn = SEQ64 USE DEFAULT PPQN )
```

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Parameters

p Refers to the main performance object.

Todo Offload most of the work into an initialization function like options does.

```
12.42.2.2 seq64::perfedit::~perfedit()
```

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.42.3 Member Function Documentation

```
12.42.3.1 void seq64::perfedit::init_before_show()
```

It does not seem to need to also forward to the perftime function of the same name.

12.42.3.2 void seq64::perfedit::enqueue_draw (bool forward = true)

Parameters

forward	If true (the default), pass the call to the peer. When passing this call to the peer, this parameter is set
	to false to prevent an infinite loop and the resultant stack overflow.

```
12.42.3.3 static bool seq64::perfedit::zoom_check(int z) [inline], [static]
```

It has to range from greater than 1 (the highest zoom-in causes an unexplained drawing artifact at this time), and not greater than four times the c_perf_scale_x value, at which point we have zoomed out so far that the measure numbers are almost completely obscured.

```
12.42.3.4 void seq64::perfedit::enregister_peer ( perfedit * peer ) [inline]
```

This function is meant to be called by mainwnd, which creates the perfedits and then makes sure they get along.

```
12.42.3.5 void seq64::perfedit::set_beats_per_bar(int bpm) [private]
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

Parameters

bpm	Provides the beats/measure or beats/bar value to be set. This value is basically the numerator of the time
	signature.

```
12.42.3.6 void seq64::perfedit::set_beat_width(int bw) [private]
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

Parameters

bw | Provides the beat width to be set. The beat width is basically the denominator of the time signature.

12.42.3.7 void seq64::perfedit::set_snap (int snap) [private]

Parameters

snap | Provide the snap value to be set. This value is basically the numerator of the expression "1 / snap".

12.42.3.8 void seq64::perfedit::set_guides() [private]

See the set_snap() function.

It's a little confusing; I assigned the label "m_standard_bpm" to the value 4 in "measure_pulse = $192 * 4 * m_bpm / m_bw$ ", but I am not sure I understand this equation... why the extra factor of 4? That 4 appears in "c_ppqn * 4" a lot in the original code.

```
12.42.3.9 void seq64::perfedit::grow( ) [private]
```

Make sure that setting the modified flag makes sense for this operation. It doesn't seem to modify members.

```
12.42.3.10 void seq64::perfedit::expand() [private]
```

This action opens up a space of events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, moving its triggers, and telling the perfroll to redraw.

```
12.42.3.11 void seq64::perfedit::collapse( ) [private]
```

This action removes all events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, not moving its triggers (they go away), and telling the perfoll to redraw.

```
12.42.3.12 void seq64::perfedit::copy( ) [private]
```

This action opens up a space of events between the L and R (left and right) markers, and copies the information from the same amount of events that follow the R marker. This action is preceded by pushing an Undo operation in the perform object, copying its triggers, and telling the perfroll to redraw.

```
12.42.3.13 void seq64::perfedit::undo() [private]
```

We pop an Undo trigger, and then ask the perfroll to queue up a (re)drawing action.

```
12.42.3.14 bool seq64::perfedit::timeout( ) [private]
```

It redraws "dirty" sequences in the perfroll and the perfnames objects, and shows draw progress on the perfroll. This function is called frequently and continuously. It will work for both perfedit windows, if both are up.

```
12.42.3.15 void seq64::perfedit::start_playing() [private]
```

JACK will be used if it is present and, in the application, enabled and working.

```
12.42.3.16 void seq64::perfedit::pause_playing() [private]
```

Currently, it is just the same as stop_playing(), but we will get it to work. Keeps the stop button enabled as a kind of rewind for ALSA.

```
12.42.3.17 void seq64::perfedit::toggle_playing() [inline], [private]
```

Meant only to be called when the "Play" button is pressed. Currently, the GUI does not change. This function will ultimately act like a Pause/Play button, but currently the pause functionality on works (partially) for JACK transport. Currently not used.

12.42.4 Field Documentation

```
12.42.4.1 int seq64::perfedit::m_bpm [private]
```

Do not confuse it with BPM (beats per minute). The numerator of the time signature.


```
12.42.4.2 int seq64::perfedit::m_bw [private]
```

The denominator of the time signature.

12.43 seq64::perfnames Class Reference

This class implements the left-side keyboard in the patterns window.

Inheritance diagram for seq64::perfnames:



Public Member Functions

• perfnames (perform &p, perfedit &parent, Gtk::Adjustment &vadjust)

Principal constructor for this user-interface object.

void redraw_dirty_sequences ()

Redraws sequences that have been modified.

Private Member Functions

• void enqueue draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

int convert y (int y)

Converts a y-value into a sequence number and returns it.

void draw_sequence (int sequence)

Draw the given sequence.

· void change_vert ()

Change the vertial offset of a sequence/pattern.

void update pixmap ()

This function does nothing.

· void draw_area ()

This function does nothing.

void redraw (int sequence)

Redraw the given sequence.

void on_realize ()

Handles the callback when the window is realized.

• bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button.

bool on_button_release_event (GdkEventButton *ev)

Handles a button-release for the right button, bringing up a popup menu.

• void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

• bool on_scroll_event (GdkEventScroll *ev)

Handle the scrolling of the window.

Private Attributes

· perfedit & m parent

Provides a link to the perfedit that created this object.

• int m names chars

Provides the number of the characters in the name box.

int m_char_w

Provides the "real" width of a character.

int m_setbox_w

Provides the width of the "set number" box.

• int m_namebox_w

Provides the width of the "name" box.

int m_names_x

Provides the width of the names box, which is the width of a character for 24 characters.

· int m names y

Provides the height of the names box, which is hardwired to 24 pixels.

· int m_xy_offset

Provides the horizontal and vertical offsets of the text relative to the names box.

Additional Inherited Members

12.43.1 Detailed Description

Obsolete Note the usage of virtual base classes. Since these can add some extra overhead, we should determine if we can do without the virtuality (and indeed it doesn't seem to be needed).

12.43.2 Constructor & Destructor Documentation

```
12.43.2.1 seq64::perfnames::perfnames ( perform & p, perfedit & parent, Gtk::Adjustment & vadjust )
```

Weird is that the window (x,y) are set to (c_names_x, 100), when c_names_y is 22 (now 24) in globals.h.

12.43.3 Member Function Documentation

```
12.43.3.1 void seq64::perfnames::enqueue_draw() [private]
```

The parent perfedit will call perfnames::queue_draw() on behalf of this object, and it will pass a perfnames.::enqueue_draw() to the peer perfedit's perfnames, if the peer exists.

```
12.43.3.2 void seq64::perfnames::draw_sequence(int seqnum) [private]
```

This function has to be prepared to handle an almost endless list of sequences, including unused ones, to draw them all with compatible styles. The sequences are grouped by set-number. The set-number occurs every 32 sequences in the leftmost column of the window.

```
12.43.3.3 void seq64::perfnames::on_realize( ) [private]
```

It first calls the base-class version of on realize(). Then it allocates any additional resources needed.

```
12.43.3.4 bool seq64::perfnames::on_expose_event( GdkEventExpose * ev ) [private]
```

It draws all of the sequences.

```
12.43.3.5 void seq64::perfnames::on_size_allocate ( Gtk::Allocation & a ) [private]
```

It first calls the base-class version of this function.

12.43.4 Field Documentation

```
12.43.4.1 perfedit& seq64::perfnames::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

12.43.4.2 int seq64::perfnames::m_names_chars [private]

Pretty much hardwired to 24 at present.

12.43.4.3 int seq64::perfnames::m_char_w [private]

This value is obtained from a font-renderer accessor function.

12.43.4.4 int seq64::perfnames::m_setbox_w [private]

This used to be hardwired to 6 * 2 (character-width times two).

12.43.4.5 int seq64::perfnames::m_namebox_w [private]

This used to be a weird calculation based on character width.

12.43.4.6 int seq64::perfnames::m_names_y [private]

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

12.43.4.7 int seq64::perfnames::m_xy_offset [private]

Currently hardwired.

12.44 seq64::perform Class Reference

This class supports the performance mode.

Public Member Functions

• perform (gui_assistant &mygui, int ppqn=SEQ64_USE_DEFAULT_PPQN)

This construction initializes a vast number of member variables, some of them public (but we're working on that)!

∼perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

bool is_modified () const

'Getter' function for member m_is_modfied

• void modify ()

'Setter' function for member m_is_modified This setter only sets the modified-flag to true.

• int sequence_count () const

'Getter' function for member m_sequence_count It is better to call this getter before bothering to even try to use a sequence.

int sequence_max () const

'Getter' function for member m_sequence_max

int get_beats_per_bar () const

'Getter' function for member m_beats_per_bar

void set_beats_per_bar (int bpm)

'Setter' function for member m_beats_per_bar

• int get_beat_width () const

'Getter' function for member m_beat_width

· void set beat width (int bw)

'Setter' function for member m_beat_width

· const gui_assistant & gui () const

'Getter' function for member m_gui_support The const getter.

• gui_assistant & gui ()

'Getter' function for member m_gui_support The un-const getter.

• const keys_perform & keys () const

'Getter' function for member m gui support.keys() The const getter.

• keys_perform & keys ()

'Getter' function for member m_gui_support.keys() The un-const getter.

mastermidibus & master bus ()

'Getter' function for member m_master_bus

bool is_running () const

'Getter' function for member m_running

· bool is jack running () const

'Getter' function for member m_jack_asst.is_running() This function is useful for announcing the status of JACK in user-interface items that only have access to the perform object.

bool is_paused () const

'Getter' function for member m is paused

• bool is pausable () const

'Getter' function for member m_is_paused and ! m_jack_asst.is_running() We might just make this internal.

bool is_learn_mode () const

 ${\it 'Getter' function for member m_mode_group_learn}$

void enregister (performcallback *pfcb)

Adds a pointer to an object to be notified by this perform object.

void clear_all ()

Clears all of the patterns/sequences.

• void launch (int ppqn)

Calls the MIDI buss and JACK initialization functions and the input/output thread-launching functions.

• void new_sequence (int seq)

Creates a new pattern/sequence for the given slot, and sets the new pattern's master MIDI bus address.

void add_sequence (sequence *seq, int perf)

Adds a pattern/sequence pointer to the list of patterns.

• void delete sequence (int seq)

Deletes a pattern/sequence by number.

bool is_sequence_in_edit (int seq)

Check if the pattern/sequence, given by number, has an edit in progress.

• void clear sequence triggers (int seq)

Clears the patterns/sequence for the given sequence, if it is active.

void print_triggers () const

Shows all the triggers of all the sequences.

· void finish ()

The rough opposite of launch(); it doesn't stop the threads.

• midipulse get_tick () const

'Getter' function for member m_tick

midipulse get_jack_tick () const

'Getter' function for member m_jack_tick

void set_jack_tick (midipulse tick)

'Setter' function for member m_jack_tick

void set_left_tick (midipulse tick, bool setstart=true)

Set the left marker at the given tick.

• midipulse get_left_tick () const

'Getter' function for member m_left_tick

void set_start_tick (midipulse tick)

'Setter' function for member m_starting_tick

midipulse get_max_tick () const

Gets the max-tick value of all active sequences.

void set_right_tick (midipulse tick, bool setstart=true)

Set the right marker at the given tick.

· midipulse get_right_tick () const

'Getter' function for member m_right_tick

void move triggers (bool direction)

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are moved by the difference between the right and left in the specified direction.

void copy_triggers ()

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are copied, offset by the difference between the right and left.

void push trigger undo ()

For every active sequence, call that sequence's push_trigger_undo() function.

void pop trigger undo ()

For every active sequence, call that sequence's pop_trigger_undo() function.

void split_trigger (int seqnum, midipulse tick)

Convenience function for perfroll's split-trigger functionality.

midipulse get_max_trigger ()

Locates the largest trigger value among the active sequences.

void collapse ()

Convenience function for perfedit's collapse functionality.

void copy ()

Convenience function for perfedit's copy functionality.

• void expand ()

Convenience function for perfedit's expand functionality.

midi_control & midi_control_toggle (int seq)

Retrieves a reference to a value from m midi cc toggle[].

• midi_control & midi_control_on (int seq)

Retrieves a reference to a value from m_midi_cc_on[].

midi_control & midi_control_off (int seq)

Retrieves a reference to a value from m_midi_cc_off[].

• void handle_midi_control (int control, bool state)

Handle the MIDI Control values that provide some automation for the application.

• const std::string & get_screen_set_notepad (int screen_set) const

 $Retrieves \ the \ given \ string \ from \ m_screen_set_notepad[].$

const std::string & current_screen_set_notepad () const

Returns the notepad text for the current screen-set.

• void set_screen_set_notepad (int screenset, const std::string ¬e)

Copies the given string into m_screen_set_notepad[].

void set_screen_set_notepad (const std::string ¬e)

Sets the notepad text for the current screen-set.

· void set screenset (int ss)

Sets the m screenset value (the index or ID of the current screen set).

int get_screenset () const

'Getter' function for member m_screenset

void set_playing_screenset ()

Sets the screen set that is active, based on the value of m_playing_screen.

int get_playing_screenset () const

'Getter' function for member m_playing_screen

void mute_group_tracks ()

Will need to study this one more closely.

void select_and_mute_group (int g_group)

Select a mute group and then mutes the track in the group.

void set_mode_group_mute ()

'Setter' function for member m_mode_group

void unset_mode_group_mute ()

'Setter' function for member m_mode_group Unsets this member.

void select_group_mute (int g_mute)

Makes some checks on all of the active sequences, and sets the group mute flag, m_mute_group_selected, to the clamped g-mute value.

• void set mode group learn ()

Sets the group-mute mode, then the group-learn mode, then notifies all of the notification subscribers.

void unset_mode_group_learn ()

Notifies all of the notification subscribers that group-learn is being turned off.

void select_mute_group (int group)

Makes some checks and sets the group mute flag, m_mute_group_selected, to the clamped g-mute value, if all goes well (no null sequences are encountered).

• void start (bool state)

If JACK is not running, call inner_start() with the given state.

• void stop ()

If JACK is not running, call inner_stop().

void start_jack ()

If JACK is supported, starts the JACK transport.

void stop_jack ()

If JACK is supported, stops the JACK transport.

• void position_jack (bool state)

If JACK is supported and running, sets the position of the transport.

void off_sequences ()

For all active patterns/sequences, set the playing state to false.

void all_notes_off ()

For all active patterns/sequences, turn off its playing notes.

• void set_active (int seq, bool active)

Sets or unsets the active state of the given pattern/sequence number.

void set_was_active (int seq)

Sets was-active flags: main, edit, perf, and names.

bool is_dirty_main (int seq)

Checks the pattern/sequence for main-dirtiness.

• bool is_dirty_edit (int seq)

Checks the pattern/sequence for edit-dirtiness.

• bool is_dirty_perf (int seq)

Checks the pattern/sequence for perf-dirtiness.

bool is_dirty_names (int seq)

Checks the pattern/sequence for names-dirtiness.

· bool is active (int seq) const

Checks the pattern/sequence for activity.

• sequence * get_sequence (int seq)

Retrieves the actual sequence, based on the pattern/sequence number.

void reset sequences (bool pause=false)

For all active patterns/sequences, get its playing state, turn off the playing notes, set playing to false, zero the markers, and, if not in playback mode, restore the playing state.

void play (midipulse tick)

Plays all notes to the current tick.

void set_orig_ticks (midipulse tick)

For every pattern/sequence that is active, sets the "original tick" value for the pattern.

void set_beats_per_minute (int bpm)

Sets the value of the BPM into the master MIDI buss, after making sure it is squelched to be between 20 and 500.

int get_beats_per_minute ()

Retrieves the BPM setting of the master MIDI buss.

void set_looping (bool looping)

'Setter' function for member m looping

void set_sequence_control_status (int status)

If the given status is present in the c_status_snapshot, the playing state is saved.

void unset_sequence_control_status (int status)

If the given status is present in the c_status_snapshot, the playing state is restored.

void sequence_playing_on (int seq)

Turn off the playing of a sequence, if it is active.

void sequence playing off (int seq)

Turn off the playing of a sequence, if it is active.

void set_group_mute_state (int g_track, bool mute_state)

This function sets the mute state of an element in the m mute group array.

bool get_group_mute_state (int g_track)

The "inverse" of set_group_mute_state(), it gets the value of the desired track.

void mute_all_tracks ()

Mutes all tracks in the current set of active patterns/sequences.

void output func ()

Performance output function.

void input_func ()

This function is called by input_thread_func().

void set_offset (int offset)

Calculates the offset into the screen sets.

void save_playing_state ()

For all active patterns/sequences, this function gets the playing status and saves it in m_sequence_state[i].

void restore_playing_state ()

For all active patterns/sequences, this function gets the playing status from m_sequence_state[i] and sets it for the sequence.

std::string key_name (unsigned int k) const

Here follows a few forwarding functions for the keys_perform-derived classes.

· bool show ui sequence key () const

Accessor m_show_ui_sequency_key Provides access to keys().show_ui_sequence_key().

· bool show ui sequence number () const

Accessor m_show_ui_sequency_number Provides access to keys().show_ui_sequence_number().

unsigned int lookup_keyevent_key (long seqnum)

Getters of keyboard mapping for sequence and groups.

void start_playing (bool songmode=false)

'Getter' function for member rc().is_pattern_playing() Provide a convenience function so that clients don't have to mess with a global variable when they're dealing with a perform object.

void pause playing ()

Pause playback, so that progress bars stay where they are, and playback always resumes where it left off, even in ALSA mode.

void stop_playing ()

Encapsulates a series of calls used in mainwnd.

void start_key (bool songmode=false)

Invoke the start key functionality.

void pause_key (bool songmode=false)

Invoke the pause key functionality.

void stop_key ()

Invoke the stop key functionality.

void learn_toggle ()

Encapsulates some calls used in mainwnd.

int decrement_beats_per_minute ()

Encapsulates some calls used in mainwnd.

int increment_beats_per_minute ()

Encapsulates some calls used in mainwnd.

int decrement_screenset ()

Encapsulates some calls used in mainwnd.

• int increment_screenset ()

Encapsulates some calls used in mainwnd.

· bool highlight (const sequence &seq) const

True if a sequence is empty and should be highlighted.

bool is_smf_0 (const sequence &seq) const

True if the sequence is an SMF 0 sequence.

• void sequence_key (int seq)

Handle a sequence key to toggle the playing of an active pattern in the selected screen-set.

• std::string sequence_label (const sequence &seq)

Provides a way to format the sequence parameters string for display in the mainwid or perfnames modules.

void set input bus (int bus, bool input active)

Sets the input bus, and handles the special "key labels on sequence" and "sequence numbers on sequence" functionality.

bool mainwnd_key_event (const keystroke &k)

Provided for mainwnd::on_key_press_event() and mainwnd::on_key_release_event() to call.

bool perfroll_key_event (const keystroke &k, int drop_sequence)

Provided for perfroll::on_key_press_event() and perfroll::on_key_release_event() to call.

• bool playback_key_event (const keystroke &k, bool songmode=false)

New function provided to unify the stop/start (space/escape) behavior of the various windows where playback can be started, paused, or stopped.

Private Member Functions

void launch_input_thread ()

Creates the input thread using input_thread_func().

void launch output thread ()

Creates the output thread using output_thread_func().

• bool init jack ()

Initializes JACK support, if SEQ64_JACK_SUPPORT is defined.

• bool deinit jack ()

Tears down the JACK infrastructure.

bool seg in playing screen (int seg)

A helper function for determining if the mode group is in force, the playing screenset is the same as the current screenset, and the sequence is in the range of the playing screenset.

• void is_modified (bool flag)

'Setter' function for member m_is_modified

bool is_midi_control_valid (int seq) const

Checks the parameter against c_midi_controls.

bool is_screenset_valid (int screenset) const

Checks the screenset against m_max_sets.

void set_running (bool running)

'Setter' function for member m running

void set_playback_mode (bool playbackmode)

'Setter' function for member m_playback_mode

int mute_group_offset (int track)

A helper function to calculate the index into the mute-group array, based on the desired track.

• bool is_seq_valid (int seq) const

Provides common code to check for the bounds of a sequence number.

• bool is_mseq_valid (int seq) const

Validates the sequence number, which is important since they're currently used as array indices.

• bool install_sequence (sequence *seq, int seqnum)

A private helper function for add_sequence() and new_sequence().

void inner_start (bool state)

Locks on m_condition_var.

void inner_stop ()

Unconditionally, and without locking, clears the running status, resets the sequences, and sets m_usemidiclock false.

· int clamp_track (int track) const

Provides common code to keep the track value valid.

void set_all_key_events ()

Pass-along function for keys().set_all_key_events.

• void set_all_key_groups ()

Pass-along function for keys().set_all_key_events.

void set_key_event (unsigned int keycode, long sequence_slot)

At construction time, this function sets up one keycode and one event slot.

· void set_key_group (unsigned int keycode, long group_slot)

At construction time, this function sets up one keycode and one group slot.

Private Attributes

• gui_assistant & m_gui_support

Support for a wide range of GUI-related operations.

bool m_mute_group [c_gmute_tracks]

Mute group support.

• int m_playing_screen

Playing screen support.

· int m_playscreen_offset

Playing screen sequence number offset.

• sequence * m_seqs [c_max_sequence]

Provides a "vector" of patterns/sequences.

• mastermidibus m_master_bus

Provides our MIDI buss.

pthread_t m_out_thread

Provides information for managing pthreads.

bool m_playback_mode

Specifies the playback mode.

• int m_ppqn

Holds the current PPQN for usage in various actions.

• int m_beats_per_bar

Holds the beats/bar value as obtained from the MIDI file.

· int m beat width

Holds the beat width value as obtained from the MIDI file.

midipulse m_one_measure

Holds the "one measure's worth" of pulses (ticks), which is normally m_ppqn * 4.

midipulse m_left_tick

Holds the position of the left (L) marker, and it is first defined as 0.

midipulse m_right_tick

Holds the position of the right (R) marker, and it is first defined as the end of the fourth measure.

· midipulse m starting tick

Holds the starting tick for playing.

• midipulse m_tick

MIDI Clock support.

midipulse m_jack_tick

Let's try to save the last JACK pad structure tick for re-use with resume after pausing.

• bool m_usemidiclock

More MIDI clock support.

• bool m_midiclockrunning

More MIDI clock support.

· int m midiclocktick

More MIDI clock support.

int m_midiclockpos

More MIDI clock support.

· bool m is paused

Support for pause, which does not reset the "last tick" when playback stops/starts.

int m_seqs_in_set

We will eventually replace c_seqs_in_set with this member, which defaults to the value of c_seqs_in_set.

· int m max sets

A replacement for the c_max_sets constant.

• int m_sequence_count

Keeps track of created sequences, whether or not they are active.

• int m_sequence_max

A replacement for the c_max_sequence constant.

· bool m is modified

It may be a good idea to eventually centralize all of the dirtiness of a performance here.

• condition_var m_condition_var

A condition variable to protect...

jack_assistant m_jack_asst

A wrapper object for the JACK support of this application.

Static Private Attributes

• static midi_control sm_mc_dummy

Provides a dummy, inactive midi_control object to handle out-of-range midi_control indicies.

Friends

int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)
 Global functions for JACK support and JACK sessions.

12.44.1 Detailed Description

It has way too many data members, one of them public. Might be ripe for refactoring. That has its own dangers, of course.

12.44.2 Constructor & Destructor Documentation

12.44.2.1 seq64::perform::perform (gui_assistant & mygui, int ppqn = SEQ64_USE_DEFAULT_PPQN)

Also note that we have a little issue with the fact that various sequences (patterns) can potentially have different beats/measure and beat-width values.

Currently, when reading the MIDI file, the beats/minute value is obtained from the MIDI file, if present, and this value is passed to perform::set_beats_per_minute(), which forwards it to the master MIDI buss and JACK assistant objects. This Tempo setting comes from both the Tempo meta event in track 0, and from the Seq24's c_bpm SeqSpec section! This setting is now also made for the two Time Signature values.

Parameters

mygui	Provides access to the GUI assistant that holds many things, including the containers of keys and the "events" they provide. This is a base-class reference; for a real class, see the gui_assistant_gtk2 class in the seq_gtkmm2 GUI-specific library. Note that we access the m_gui_support member using the gui() accessor function.
ppqn	The default, choosable, or actual PPQN value.

```
12.44.2.2 seq64::perform::~perform()
```

Finally, any active or inactive (but allocated) patterns/sequences are deleted, and their pointers nullified.

12.44.3 Member Function Documentation

```
12.44.3.1 void seq64::perform::modify() [inline]
```

The setter that will, is modified(), is private. No one but perfrom and its friends should falsify this flag.

```
12.44.3.2 int seq64::perform::sequence_count() const [inline]
```

In many cases at startup, or when loading a file, there are no sequences yet, and still the code calls functions that try to access them.

```
12.44.3.3 void seq64::perform::clear_all()
```

The mainwind module calls this function. Note that perform now handles the "is modified" flag on behalf of all external objects, to centralize and simplify the dirtying of a MIDI tune.

Anything else to clear? What about all the other sequence flags? We can beef up delete_sequence() for them, at some point.

```
12.44.3.4 void seq64::perform::launch ( int ppqn )
```

This function is called in main(). We collected all the calls here as a simplification, and renamed it because it is more than just initialization. This function must be called after the perform constructor and after the configuration file and command-line configuration overrides.

Parameters

ppqn	Provides the PPQN value, which is either the default value (192) or is read from the "user" configuration
	file.

12.44.3.5 void seq64::perform::new_sequence (int seq)

Then it activates the pattern [this is done in the install sequence() function]. It doesn't deal with thrown exceptions.

This function is called by the seqmenu and mainwid objects to create a new sequence. We now pass this sequence to install_sequence() to better handle potential memory leakage, and to make sure the sequence gets counted. Also, adding a new sequence from the user-interface is a significant modification, so the "is modified" flag gtes set.

Parameters

seq	The prospective sequence number of the new sequence.
-----	--

12.44.3.6 void seq64::perform::add_sequence (sequence * seq, int prefnum)

No check is made for a null pointer, but the install_sequence() call will make sure such a pointer is officially logged.

This function checks for the preferred sequence number. This is the number that was specified by the Sequence Number meta-event for the current track. If the preferred sequence number is in the valid range (0 to m_sequence — max) and it is not active, add it and activate it. Otherwise, iterate through all patterns from prefnum to m_ sequence max and add and activate the first one that is not active, and then finish.

Finally, note that this function is used only by midifile, when reading in a MIDI song. Therefore, the "is modified" flag is *not* set by this function; loading a sequence from a file is not a modification that should lead to a prompt for saving the file later.

Todo Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Warning

The logic of the if-statement in this function was such that *prefnum* could be out-of-bounds in the else-clause. We reworked the logic to be airtight. This bug was caught by gcc 4.8.3 on CentOS, but not on gcc 4.9.3 on Debian Sid!

Parameters

seq	The pointer to the pattern/sequence to add.
prefnum	The preferred sequence number of the pattern, as explained above. If this value is out-of-range,
	then it is basically ignored.

12.44.3.7 void seq64::perform::delete_sequence (int seq)

We now also solidify the deletion by setting the pointer to null after deletion, so it will blow up if accidentally accessed. The final act is to raise the "is modified" flag, since deleting an existing sequence is always a significant modification.

Now, this function obviously sets the "active" flag for the sequence to false. But there are a few other flags that are not modified; shouldn't we also falsify them here?

12.44.3.8 void seq64::perform::clear_sequence_triggers (int seq)

Parameters

seq Provides the desired sequence. Hopefull, the is_active() function validates this value.

12.44.3.9 void seq64::perform::finish() [inline]

A minor simplification for the main() routine, hides the JACK support macro.

12.44.3.10 void seq64::perform::set_left_tick (midipulse tick, bool setstart = true)

We let the caller determine if this setting is a modification. If the left tick is later than the right tick, the right tick is move to one measure past the left tick.

Todo The perform::m_one_measure member is currently hardwired to PPQN * 4.

Parameters

tick	The tick (MIDI pulse) at which to place the left tick. If the left tick is greater than or equal to the right tick, then the right ticked is moved forward by one "measure's length" ($m_ppqn * 4$) past the left tick.
setstart	If true (the default, and longstanding implicit setting), then the starting tick is also set to the left tick.

12.44.3.11 midipulse seq64::perform::get_max_tick() const

We can't seem to find a way to get a good value from the perform object itself, so we get it from the sequences. This approach kind of works, but the result is slow. We could optimize it a little by saving the indices of the first and last active sequence.

Returns

If no active sequence is found, 0 is returned. Otherwise, the maximum get_last_tick() value of the active sequences is returned.

12.44.3.12 void seq64::perform::set_right_tick (midipulse tick, bool setstart = true)

This setting is made only if the tick parameter is at or beyond the first measure. We let the caller determine is this setting is a modification.

Parameters

tick	The tick (MIDI pulse) at which to place the right tick. If less than or equal to the left tick setting, then the left tick is backed up by one "measure's worth" (m_ppqn * 4) worth of ticks from the new right tick.
setstart	If true (the default, and longstanding implicit setting), then the starting tick is also set to the left tick, if that got changed.

12.44.3.13 void seq64::perform::move_triggers (bool direction)

Parameters

direction	Specifies the desired direction; false = left, true = right.
-----------	--

12.44.3.14 void seq64::perform::copy_triggers ()

This copies the triggers between the L marker and R marker to the R marker.

12.44.3.15 void seq64::perform::push_trigger_undo()

Too bad we cannot yet keep track of all the undoes for the sake of properly handling the "is modified" flag.

12.44.3.16 midipulse seq64::perform::get_max_trigger()

Returns

Returns the highest trigger value, or zero. It is not clear why this function doesn't return a "no trigger found" value. Is there always at least one trigger, at 0?

12.44.3.17 midi_control & seq64::perform::midi_control_toggle (int seq)

Parameters

seq Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object. Note that this value is unsigned simply to make the legality check of the parameter easier.

12.44.3.18 midi_control & seq64::perform::midi_control_on (int seq)

Parameters

seq Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object.

12.44.3.19 midi_control & seq64::perform::midi_control_off (int seq)

Parameters

seq Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object.

12.44.3.20 void seq64::perform::handle_midi_control (int ctrl, bool state)

Parameters

ctrl	The MIDI control value to use to perform an operation.
state	The state of the control, used with the following
	values:

c_midi_control_mod_replace
c_midi_control_mod_snapshot
c_midi_control_mod_queue
c_midi_control_mod_gmute
c_midi_control_mod_glearn

12.44.3.21 const std::string & seq64::perform::get_screen_set_notepad (int screenset) const

screenset	The ID number of the string set, an index into the m_screen_set_notepad[] array. This value is
	validated.

Returns

Returns a reference to the desired string, or to an empty string if the screen-set number is invalid.

12.44.3.22 void seq64::perform::set_screen_set_notepad (int screenset, const std::string & notepad)

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_xxx[] arrays.
notepad	Provides the string date to copy into the notepad. Not sure why a pointer is used, instead of nice
	"const std::string &" parameter. And this pointer isn't checked.

12.44.3.23 void seq64::perform::set_screenset (int ss)

It's not clear that we need to set the "is modified" flag just because we changed the screen set, so we don't.

Parameters

ss	The index of the desired string set. It is forced to range from 0 to m_max_sets - 1.
----	--

12.44.3.24 void seq64::perform::set_playing_screenset ()

For each value up to m_seqs_in_set (32), the index of the current sequence in the currently screen set (m_playing _ _screen) is obtained. If it is active and the sequence actually exists. Null sequences are no longer flagged as an error, they are just ignored.

Modifies m_playing_screen, and mutes the group tracks.

12.44.3.25 void seq64::perform::select_group_mute (int a_g_mute)

Null sequences are no longer flagged as an error, they are just ignored.

Parameters

a_g_mute	The number of the mute group, clamped to be between 0 and m_seqs_in_set-1.

12.44.3.26 void seq64::perform::unset_mode_group_learn()

Then unsets the group-learn mode flag.

12.44.3.27 void seq64::perform::select_mute_group (int a_group)

Null sequences are no longer flagged as an error, they are just ignored.

Will need to study this one more closely.

Parameters

a_group	Provides the group to mute. Note that this parameter is essentially a track or sequence number.
---------	---

12.44.3.28 void seq64::perform::start (bool state)

Parameters

state	What does this state mean?
-------	----------------------------

12.44.3.29 void seq64::perform::stop ()

The logic seems backward here, in that we call inner_stop() if JACK is not running. Or perhaps we misunderstand the meaning of m_jack_running?

12.44.3.30 void seq64::perform::position_jack (bool state)

If we run "klick -j -P" and then start Sequencer64, we get:

```
klick: src/metronome_jack.cc:52: virtual void
MetronomeJack::process_callback(sample_t*, nframes_t): Assertion
'pos.beat > 0 && pos.beat <= pos.beats_per_bar' failed.</pre>
```

Let's try enabling the relocate parameter if we're JACK Master. This removes the error from klick, but it clicks at an extremely fast rate!

12.44.3.31 void seq64::perform::all_notes_off()

Then flush the MIDI buss.

12.44.3.32 void seq64::perform::set_active (int seq, bool active)

If setting it active, the sequence::number() setter is called. It won't modify the sequence's internal copy of the sequence number if it has already been set.

Parameters

seq	Provides the prospective sequence number.
active	True if the sequence is to be set to the active state.

12.44.3.33 void seq64::perform::set_was_active (int seq)

Why do we need this routine?

Parameters

	seq	The pattern number.	It is checked for invalidity.
--	-----	---------------------	-------------------------------

12.44.3.34 bool seq64::perform::is_dirty_main (int seq)

See the sequence::is_dirty_main() function.

Parameters

seq The pattern number. It is checked for invalidity.

Returns

Returns the was-active-main flag value, before setting it to false. Returns false if the pattern was invalid.

12.44.3.35 bool seq64::perform::is_dirty_edit (int seq)

Parameters

Returns

Returns the was-active-edit flag value, before setting it to false. Returns false if the pattern was invalid.

12.44.3.36 bool seq64::perform::is_dirty_perf (int seq)

Parameters

seq The pattern number. It is checked for invalidity.

Returns

Returns the was-active-perf flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.44.3.37 bool seq64::perform::is_dirty_names (int seq)

seq The pattern number. It is checked for invalidity.

Returns

Returns the was-active-names flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.44.3.38 bool seq64::perform::is_active (int seq) const [inline]

Todo We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Parameters

seq

The pattern number. It is checked for invalidity. This can lead to "too many" (i.e. redundant) checks, but we're trying to centralize such checks in this function.

Returns

Returns the value of the active-flag, or false if the sequence was invalid or null.

12.44.3.39 sequence * seq64::perform::get_sequence(int seq) [inline]

Parameters

seq The prospective sequence number.

Returns

Returns the value of m_seqs[seq] if seq is valid. Otherwise, a null pointer is returned.

12.44.3.40 void seq64::perform::reset_sequences (bool pause = false)

Note that these calls could be folded into one member function of the sequence class. [Done!]

Finally, flush the MIDI buss.

12.44.3.41 void seq64::perform::play (midipulse tick)

Starts the playing of all the patterns/sequences.

This function just runs down the list of sequences and has them dump their events.

tick Provides the tick at which to start playing.

12.44.3.42 void seq64::perform::set_orig_ticks (midipulse tick)

This is really the "last tick" value, so we renamed sequence::set_orig_tick() to sequence::set_last_tick().

Parameters

tick | Provides the last-tick value to be set for each sequence that is active.

12.44.3.43 void seq64::perform::set_beats_per_minute (int bpm)

Replaces perform::set bpm() from seg24.

The value is set only if neither JACK nor this performance object are running.

It's not clear that we need to set the "is modified" flag just because we changed the beats per minute. This setting does get saved to the MIDI file, with the c_bpmtag.

12.44.3.44 void seq64::perform::set_sequence_control_status (int status)

Then the given status is OR'd into the m_control_status.

12.44.3.45 void seq64::perform::unset_sequence_control_status (int status)

Then the given status is reversed in m_control_status.

12.44.3.46 void seq64::perform::sequence_playing_on (int seq)

Parameters

seq The number of the sequence to be turned on.

12.44.3.47 void seq64::perform::sequence_playing_off (int seq)

Parameters

seq The number of the sequence to be turned off.

12.44.3.48 void seq64::perform::set_group_mute_state (int gtrack, bool muted)

The index value is the track number offset by the number of the selected mute group (which seems equivalent to a set number) times the number of sequences in a set.

Parameters

gtrack	The number of the track to be muted/unmuted.
muted	This boolean indicates the state to which the track should be set.

12.44.3.49 bool seq64::perform::get_group_mute_state (int gtrack)

Parameters

gtrack	The number of the track for which the state is to be obtained. Like set_group_mute_state(), this value
	is offset by adding m_mute_group_selected * m_seqs_in_set.

Returns

Returns the value of m_mute_group[gtrack + set offset]

12.44.3.50 void seq64::perform::output_func()

This function is called by the free function output_thread_func(). Here's how it works:

```
It runs while m_outputing is true.MORE TO COME
```

Change Note ca 2016-01-26 Hurray, seq24 is coming back to life! We see that there is a fix for clock tick drift here, which relies on using long and long long values. See the Changelog for seq24 0.9.3.

- 1. Get delta time (current last).
- 2. Get delta ticks from time.
- 3. Add to current_ticks.
- 4. Compute prebuffer ticks.
- 5. Play from current tick to prebuffer.

Figure out how much time we need to sleep, and do it.

```
12.44.3.51 void seq64::perform::set_offset(int offset) [inline]
```

Sets m_offset = offset * c_mainwnd_rows * c_mainwnd_cols;

```
offset The desired offset.
```

```
12.44.3.52 void seq64::perform::save_playing_state ( )
```

Inactive patterns get the value set to false.

```
12.44.3.53 bool seq64::perform::show_ui_sequence_key( )const [inline]
```

Used in mainwid, options, optionsfile, userfile, and perform.

```
12.44.3.54 bool seq64::perform::show_ui_sequence_number() const [inline]
```

Used in mainwid, optionsfile, and perform.

```
12.44.3.55 unsigned int seq64::perform::lookup_keyevent_key ( long seqnum ) [inline]
```

If not found, returns something "safe" [so use get_key()->count() to see if it's there first]

```
12.44.3.56 void seq64::perform::start_playing ( bool songmode = false )
```

Encapsulates a series of calls used in mainwnd.

Actually, we can use the m_running variable.

```
bool is_playing () const { return rc().is_pattern_playing(); // Change Note ca 2016-03-19 return m_running; }
```

We've reversed the start() and start_jack() calls so that JACK is started first, to match all of the other use-cases for playing that we've found in the code.

Note that the complementary function, stop_playing(), is an inline function defined in the header file.

Note

It would be nice to know why the following code snippet disables the mute/unmute functionality of the performance/song editor:

```
position_jack(false);
start_jack();
start(false);

The jack_assistant::position() function doesn't use the boolean
parameter at present; that code is effectively disabled.

Okay, now it does, if the "relocate" parameter is true. See
perform::position_jack() and jack_assistant::position(). This
parameter, when true, allows the "klick" application to get
proper position data.

The perform::start() function passes its boolean flag to
perform::inner_start(), which sets the playback mode to that flag; if
that flag is false, that turns off "song" mode. So that explains why
mute/unmute is disabled.

seqroll and mainwnd: position_jack(false); start(false); start_jack().
perfedit: position_jack(true); start_jack(); start(true).
```

Indicates if the caller wants to start the playback in JACK mode. In the seq42 (yes, "42", not "24") code at GitHub, this flag was identical to the "global_jack_start_mode" flag, which is true for Song mode, and false for Live mode. False disables Song mode, and is the default, which matches seq24. If the previous state was "paused", then we start it in Live mode, which works because Song mode has already turned on the sequences. This method is not quite intuitive, because it is really following Live mode.

12.44.3.57 void seq64::perform::pause_playing ()

Currently almost the same as stop_playing(), but expanded as noted in the comments so that we ultimately have more granular control over what happens. We're researching the whole sequence of stopping and starting, and it can be tricky to make correct changes.

We still need to make restarting pick up at the same place in ALSA mode; in JACK mode, JACK transport takes care of that feature.

12.44.3.58 void seq64::perform::stop_playing ()

Stops playback, turns off the (new) m_is_paused flag, and set the "is-pattern-playing" flag to false. Do we need to reset the m_running flag here?

12.44.3.59 void seq64::perform::start_key (bool songmode = false)

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

,	T 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1
sonamode	The live/play mode parameter to be passed along to the key processor.
conginicae	The interplay mode parameter to be passed along to the key processes.

12.44.3.60 void seq64::perform::pause_key (bool songmode = false)

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

songmode	The live/play mode parameter to be passed along to the key processor, when starting playback.
----------	---

12.44.3.61 void seq64::perform::stop_key ()

Meant to be used by GUIs to unify the treatment of keys versus buttons.

```
12.44.3.62 int seq64::perform::decrement_beats_per_minute() [inline]
```

Actually does a lot of work in those function calls.

```
12.44.3.63 int seq64::perform::increment_beats_per_minute( ) [inline]
```

Actually does a lot of work in those function calls.

```
12.44.3.64 bool seq64::perform::highlight ( const sequence & seq ) const [inline]
```

This setting is currently a build-time option, but could be made a run-time option later.

```
12.44.3.65 std::string seq64::perform::sequence_label ( const sequence & seq )
```

This string goes on the bottom-left of those user-interface elements.

The format of this string is something like the following example, depending on the "show sequence numbers" option. The values shown are, in this order, sequence number (if allowed), buss number, channel number, beats per bar, and beat width.

```
No sequence number: 31-16 4/4
Sequence number: 9 31-16 4/4
```

```
The sequence number and buss number are re 0, while the channel number is displayed re 1, unless it is an SMF 0 null channel (0xFF), in which case it is 0.
```

Note

Later, we could add the sequence hot-key to this string, though showing that is not much use in perfnames. Also, this function is a stilted mix of direct access and access through sequence number.

Parameters

seq	Provides the reference to the sequence, use for getting the sequence parameters to be written to the
	label string.

Returns

Returns the filled in label if the sequence is active. Otherwise, an empty string is returned.

```
12.44.3.66 void seq64::perform::set_input_bus ( int bus, bool active )
```

This function is called by options::input_callback().

Tricky Code See the bus parameter. We should provide two separate functions for this feature, but it is already combined into one input-callback function with a lot of other functionality in the options module.

bus	If this value is greater than SEQ64_DEFAULT_BUSS_MAX (32), then it is treated as a user-interface flag (PERFORM_KEY_LABELS_ON_SEQUENCE or PERFORM_NUM_LABELS_ON_SEQUENCE)
	that causes all the sequences to be dirtied, and thus get redrawn with the new user-interface setting.
active	Indicates whether the buss or the user-interface feature is active or inactive.

12.44.3.67 bool seq64::perform::mainwnd_key_event (const keystroke & k)

Returns

Returns true if the key was handled.

12.44.3.68 bool seq64::perform::perfroll_key_event (const keystroke & k, int drop_sequence)

The "is modified" flag is raised if something is deleted, but we cannot yet handle the case where we undo all the changes. So, for now, we play it safe with the user, even if the user gets annoyed because he knows that he undid all the changes.

Returns

Returns true if the key was handled.

12.44.3.69 bool seq64::perform::playback_key_event (const keystroke & k, bool songmode = false)

To be used in mainwnd, perfedit, and seqroll.

The start/end key may be the same key (e.g. Space) to allow toggling when the same key is mapped to both triggers.

Checking is_running() may not work completely in JACK.

Parameters

k	Provides the encapsulated keystroke to check.
songmode	Provides the "jack flag" needed by the mainwnd, seqroll, and perfedit windows. Defaults to false,
	which disables Song mode, and enables Live mode.

Returns

Returns true if the keystroke matched the start, stop, or (new) pause keystrokes.

12.44.3.70 void seq64::perform::launch_input_thread() [private]

This might be a good candidate for a small thread class derived from a small base class.

```
12.44.3.71 void seq64::perform::launch_output_thread( ) [private]
```

This might be a good candidate for a small thread class derived from a small base class.

```
12.44.3.72 bool seq64::perform::init_jack( ) [inline], [private]
```

Who calls this routine? The main() routine of the application [via launch()], and the options module, when the Connect button is pressed.

Returns

Returns the result of the init() call; true if JACK sync is now running. If JACK support is not built into the application, then this function returns false, to indicate that JACK is (definitely) not running.

```
12.44.3.73 bool seq64::perform::deinit_jack( ) [inline], [private]
```

Called by launch() and in the options module, when the Disconnect button is pressed.

Returns

Returns the result of the init() call; false if JACK sync is now no longer running. If JACK support is not built into the application, then this function returns true, to indicate that JACK is (definitely) not running.

```
12.44.3.74 bool seq64::perform::seq_in_playing_screen( int seq ) [private]
```

Parameters

Se	eq	Provides the index of the desired sequence.	
----	----	---	--

Returns

Returns true if the sequence adheres to the conditions noted above.

```
12.44.3.75 bool seq64::perform::is_midi_control_valid (int seq ) const [inline], [private]
```

Parameters

```
seq The value that should be in the c_midi_controls range.
```

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

12.44.3.76 bool seq64::perform::is_screenset_valid(int screenset) const [inline], [private]

screenset	The prospective screenset value.
screenset	The prospective screenset value.

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

12.44.3.77 bool seq64::perform::is_seq_valid (int seq) const [private]

Also see the function is mseq valid(), which also checks the pointer stored in the m seq[] array.

We considered checking the *seq* param against sequence_count(), but this function is called while creating sequences that add to that count, so we continue checking against the "container" size. Also, it is possible to have holes in the array representing inactive sequences, so that sequencer count() would be too limiting.

Parameters

seq The sequencer number, in interval [0, m_sequence_max).

Returns

Returns true if the sequence number is valid.

12.44.3.78 bool seq64::perform::is_mseq_valid (int seq) const [private]

It also evaluates the m_seq[seq] pointer value.

Note

Since we can have holes in the sequence array, where there are inactive sequences, we check if the sequence is even active before emitting a message about a null pointer for the sequence. We only want to see messages that indicate actual problems.

Parameters

seq

Provides the sequence number to be checked. It is checked for validity. We cannot compare the sequence number versus the sequence_count(), because the current implementation can have inactive holes (with null pointers) interspersed with active pointers.

Returns

Returns true if the sequence number is valid as per is seq valid(), and the sequence pointer is not null.

12.44.3.79 bool seq64::perform::install_sequence (sequence * seq, int seqnum) [private]

It is common code and using it prevents inconsistences. It assumes values have already been checked. It does not set the "is modified" flag, since adding a sequence by loading a MIDI file should not set it. Compare new_\circ sequence(), used by mainwid and seqmenu, with add_sequence(), used by midifile.

seq	The pointer to the pattern/sequence to add.
seqnum	The sequence number of the pattern to be added.

Returns

Returns true if a sequence was removed, or the sequence was successfully added. In other words, if a real change in sequence pointers occurred. It is up to the caller to decide if the change warrants setting the "is modified" flag.

12.44.3.80 void seq64::perform::inner_start (bool state) [private]

Then, if not is_running(), the playback mode is set to the given state. If that state is true, call off_sequences(). Set the running status, and signal the condition. Then unlock.

Minor issue:

In ALSA mode, restarting the sequence moves the progress bar to the beginning of the sequence, even if just pausing.

Parameters

state	Sets the playback mode, and, if true, turns off all of the sequences.
-------	---

12.44.3.81 void seq64::perform::inner_stop() [private]

Note that we do need to set the running flag to false here, even when JACK is running. Otherwise, JACK starts ping-ponging back and forth between positions under some circumstances.

However, if JACK is running, we do not want to reset the sequences... this causes the progress bar for each sequence to remove to near the end of the sequence.

12.44.3.82 int seq64::perform::clamp_track(int track) const [inline], [private]

Note the bug we found, where we checked for track > m_seqs_in_set, but set it to m_seqs_in_set - 1 in that case!

12.44.3.83 void seq64::perform::set_key_event (unsigned int keycode, long sequence_slot) [inline], [private]

It is called 32 times, corresponding to the pattern/sequence slots in the Patterns window. It first removes the given key-code from the regular and reverse slot-maps. Then it removes the sequence-slot from the regular and reverse slot-maps. Finally, it adds the sequence-slot with a key value of key-code, and adds the key-code with a value of sequence-slot.

12.44.3.84 void seq64::perform::set_key_group (unsigned int keycode, long group_slot) [inline], [private]

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window. Compare it to the set_key ← _events() function.

12.44.4 Friends And Related Function Documentation

```
12.44.4.1 int jack_sync_callback ( jack_transport_state_t state, jack_position_t * pos, void * arg ) [friend]
```

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

Parameters

state	The JACK Transport state.	
pos	The JACK position value.	
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.	

Returns

Returns 1 if the function works, and 0 if something was wrong.

12.44.5 Field Documentation

```
12.44.5.1 midi_control seq64::perform::sm_mc_dummy [static], [private]
```

Instantiate the dummy midi control object, which is used in lieu of a null pointer.

We're taking code that basically works already, in the sense that it never seems to access a null pointer. So we're not even risking data transfers between this dummy object and the ones we really want to use.

```
12.44.5.2 int seq64::perform::m_playscreen_offset [private]
```

Saves some multiplications, should make the code easier to grok, and centralizes the use of c_seqs_in_set, which we want to be able to change at run-time, as a future enhancement.

```
12.44.5.3 sequence* seq64::perform::m_seqs[c_max_sequence] [private]
```

Todo First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

```
12.44.5.4 bool seq64::perform::m_playback_mode [private]
```

There are two, "live" and "song", indicated by the following values:

```
m_playback_mode == false: live mode
m_playback_mode == true: playback/song mode
```

```
12.44.5.5 int seq64::perform::m_beats_per_bar [private]
```

The default value is SEQ64_DEFAULT_BEATS_PER_MEASURE (4).

```
12.44.5.6 int seq64::perform::m_beat_width [private]
```

The default value is SEQ64 DEFAULT BEAT WIDTH (4).

```
12.44.5.7 midipulse seq64::perform::m_one_measure [private]
```

We can save some multiplications, and, more importantly, later define a more flexible definition of "one measure's worth" than simply four quarter notes.

```
12.44.5.8 midipulse seq64::perform::m_left_tick [private]
```

Note that "tick" is actually "pulses".

```
12.44.5.9 midipulse seq64::perform::m_right_tick [private]
```

Note that "tick" is actually "pulses".

```
12.44.5.10 midipulse seq64::perform::m_starting_tick [private]
```

By default, this value is always reset to the value of the "left tick". We want to eventually be able to leave it at the last playing tick, to support a "pause" functionality. Note that "tick" is actually "pulses".

```
12.44.5.11 midipulse seq64::perform::m_tick [mutable], [private]
```

The m_tick member holds the tick to be used in displaying the progress bars and the maintime pill. It is mutable because sometimes we want to adjust it in a const function for pause functionality.

```
12.44.5.12 int seq64::perform::m_seqs_in_set [private]
```

This change will require some arrays to be dynamically allocated (vectors).

12.44.5.13 int seq64::perform::m_max_sets [private]

Again, currently set to the old value, which is used in hard-wired array sizes. To make it variable will require a move from arrays to vectors.

12.44.5.14 int seq64::perform::m_sequence_count [private]

Used by the install_sequence() function. Note that this value is not a suitable replacement for c_max_sequence/m← _sequence_max, because there can be inactive sequences amidst the active sequences.

12.44.5.15 int seq64::perform::m_sequence_max [private]

However, this value is already 32 * 32 = 1024, and is probably enough for any usage. Famous last words?


12.44.5.16 bool seq64::perform::m_is_modified [private]

All the GUIs seem to use a perform object. IN PROGRESS.

12.45 seq64::performcallback Struct Reference

Provides for notification of events.

Inheritance diagram for seq64::performcallback:



12.45.1 Detailed Description

Provide a response to a group-learn change event.

12.46 seq64::perfroll Class Reference

This class implements the performance roll user interface.

Inheritance diagram for seq64::perfroll:



Public Member Functions

perfroll (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=S←
 EQ64_USE_DEFAULT_PPQN)

Principal constructor.

∼perfroll ()

This destructor deletes the interaction object.

• void set_guides (int snap, int measure, int beat)

This function sets the m_snap, m_measure_length, and m_beat_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

· void update sizes ()

Updates the sizes of various items.

void init_before_show ()

Sets the roll-lengths ticks member.

void fill_background_pixmap ()

This function updates the background of the piano roll.

void increment_size ()

Increments the value of m_roll_length_ticks by the PPQN * 512, then calls update_sizes().

• void draw all ()

Provides a very common sequence of calls used in perfroll_input.

• void redraw_progress ()

Helper function to simplify the client call.

Private Member Functions

void draw_progress ()

Draws the progress line that shows where we are in the performance.

void redraw_dirty_sequences ()

Redraws patterns/sequences that have been modified.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

void convert_xy (int x, int y, midipulse &ticks, int &seq)

Converts (x, y) coordinates on the piano roll to tick (pulse) and sequence numbers.

void convert_x (int x, midipulse &ticks)

Converts a tick-offset on the x coordinate.

void snap_x (int &x)

This function performs a 'snap' action on x.

void draw_sequence_on (int seqnum)

Draws the given pattern/sequence on the given drawable area.

void draw_background_on (int seqnum)

Draws the given pattern/sequence background on the given drawable area.

void draw_drawable_row (long y)

Not quite sure what this draws yet.

· void change horz ()

Changes the 4-bar horizontal offset member and queues up a draw operation.

void change_vert ()

Changes the 4-bar vertical offset member and queues up a draw operation.

void split_trigger (int sequence, midipulse tick)

Splits a trigger, whatever that means.

• void enqueue_draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

void set_zoom (int z)

Implements the horizontal zoom feature.

void on_realize ()

Provides the on-realization callback.

bool on_expose_event (GdkEventExpose *ev)

Handles the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

This callback function handles a button press by forwarding it to the interaction object's button-press function.

bool on button release event (GdkEventButton *ev)

This callback function handles a button release by forwarding it to the interaction object's button-release function.

bool on_motion_notify_event (GdkEventMotion *ev)

Handles motion notification by forwarding it to the interaction object's motion-notification callback function.

bool on_scroll_event (GdkEventScroll *ev)

Handles horizontal and vertical scrolling.

bool on_focus_in_event (GdkEventFocus *ev)

This callback handles an in-focus event by setting the flag to HAS_FOCUS.

bool on focus out event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

• void on_size_allocate (Gtk::Allocation &al)

Upon a size allocation event, this callback calls the base-class version of this function, then sets m_window_x and m window y, and calls update sizes().

bool on_key_press_event (GdkEventKey *ev)

This callback function handles a key-press event.

void on_size_request (GtkRequisition *)

This do-nothing callback effectively throws away a size request.

Private Attributes

· perfedit & m parent

Provides a link to the perfedit that created this object.

• int m_h_page_increment

Provides the horizontal page increment for the horizontal scrollbar.

int m_v_page_increment

Provides the vertical page increment for the vertical scrollbar.

• int m_zoom

New value to attempt a rudimentary time-zoom feature.

· FruityPerfInput m_fruity_interaction

We need both styles of interaction object present.

• Seq24PerfInput m_seq24_interaction

Provides support for standard Seq24 mouse handling, plus the keystroke handlers.

Friends

· class FruityPerfInput

These friend implement interaction-specific behavior, although only the Seq24 interactions support keyboard processing, except for some common functionality provided by perform::perfroll_key_event().

Additional Inherited Members

12.46.1 Constructor & Destructor Documentation

12.46.1.1 seq64::perfroll::~perfroll()

Well, now there are two objects, so no explicit deletion necessary.

12.46.2 Member Function Documentation

12.46.2.1 void seq64::perfroll::set_guides (int snap, int measure, int beat)

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set_guides (). This is actually equal to the measure-pulses divided by the snap value in perfedit; the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set_guides().
beat	Provides the number of beat-pulses (pulses per beat) as calculated in perfedit::set_guides().

12.46.2.2 void seq64::perfroll::update_sizes ()

Note

Trying to figure out what the 16 is. So take the "bars-visible" calculation, the c_perf_scale_x value, assume that "ticks" is another name for "pulses", and assume that "beats" is a quarter note. Ignoring the numbers, the units come out to:

```
pixels * ticks / pixel
bars = ------
ticks / beat * beats / bar
```

Thus, the 16 is a "beats per bar" or "beats per measure" value. This doesn't quite make sense, but there are 16 divisions per beat on the perfroll user-interface. So for now we'll call it the latter, and make a variable called "m_divs_per_beat", see its definition in the class initializer list.

12.46.2.3 void seq64::perfroll::init_before_show()

First, it gets the largest trigger value among the active sequences. Then it truncates this value to the nearest PPQN * 16 ticks. Then it adds PPQN * 4096 ticks.

12.46.2.4 void seq64::perfroll::fill_background_pixmap()

The first thing done is to clear the background by painting it with a filled white rectangle.

This function is called whenever something occurs (e.g. zoom) that can affect how the piano roll is drawn.

```
12.46.2.5 void seq64::perfroll::draw_progress() [private]
```

We would like to be able to leave the line there when the progress is paused while running off of JACK transport. How? The perf().get_tick() call always returns 0 when stop is in force.

If we comment out the erasure of the old line, we see that the progress bar is also erased when a pattern boundary is hit (triggers), and when the sequence is stopped by the user.

In order to support true pause in the song editor, we tried to replace perform::get_tick() with perform::get_start_tick() and perform::get_last_tick() [a new experimental function]. But those replacements here always return 0, even as perform::get_tick() increases. Now were are trying a newer function, perform::get_max_tick(), which seems to do the trick for resuming (instead of rewinding) the progress bar. It's still a tiny bit laggy, so we have to find a faster way to get the maximum. (Note that the draw_progress function is called at every timeout, that is, constantly.)

```
12.46.2.6 void seq64::perfroll::set_ppqn ( int ppqn ) [private]
```

The m_ticks_per_bar member replaces the global ppqn times 16. This construct is parts-per-quarter-note times 4 quarter notes times 4 sixteenth notes in a bar. (We think...)

The m_perf_scale_x member starts out at c_perf_scale_x, which is 32 ticks per pixel at the default tick rate of 192 PPQN. We adjust this now. But note that this calculation still involves the c_perf_scale_x constant.

```
12.46.2.7 void seq64::perfroll::convert_xy ( int x, int y, midipulse & d_tick, int & d_seq ) [private]
```

The results are returned via the d_tick and d_seq parameters. The sequence number is clipped to a legal value (0 to m_sequence_max).

Parameters

	X	The x coordinate of the mouse pointer.
	У	The y coordinate of the mouse pointer.
out	d_tick	Holds the calculated tick value.
out	d_seq	Holds the calculated sequence-number value.

```
12.46.2.8 void seq64::perfroll::convert_x ( int x, midipulse & tick ) [private]
```

The result is returned via the tick parameter.

```
12.46.2.9 void seq64::perfroll::snap_x ( int & x ) [private]
```

- m_snap = number pulses to snap to
- m perf scale x = number of pulses per pixel

Therefore $mod = m_snap/m_perf_scale_x$ equals the number pixels to snap to.

```
12.46.2.10 void seq64::perfroll::draw_sequence_on(int seqnum) [private]
```

Statement nesting from hell!

```
12.46.2.11 void seq64::perfroll::draw_drawable_row(long y) [private]
```

It is involved in the drawing of a greyed (selected) row.

What's weird is that we divide y by m_names_y, then multiply it by m_names_y, before passing the result to draw—drawable(). However, if we just as y casted to an int, then the drawing of the row is only partial, vertically.

```
12.46.2.12 void seq64::perfroll::enqueue_draw( ) [private]
```

The parent perfedit will call perfroll::queue_draw() on behalf of this object, and it will pass a perfroll::enqueue_draw() to the peer perfedit's perfroll, if the peer exists.

```
12.46.2.13 void seq64::perfroll::set_zoom(int z) [private]
```

ca 2016-04-05 The initial zoom value is c_perf_scale_x (32). We allow it to range from 1 to 128, for now. Smaller values zoom in.

```
12.46.2.14 void seq64::perfroll::on_realize( ) [private]
```

Calls the base-class version first.

Then it allocates the additional resources need, that couldn't be initialized in the constructor, and makes some connections.

```
12.46.2.15 bool seq64::perfroll::on_expose_event( GdkEventExpose * ev ) [private]
```

Returns

Always returns true.

```
12.46.2.16 bool seq64::perfroll::on_button_press_event ( GdkEventButton * ev ) [private]
```

This gives us Seq24 versus Fruity behavior.

One minor issue: Fruity behavior doesn't yet provide the keystroke behavior we now handle for the Seq24 mode of operation.

```
12.46.2.17 bool seq64::perfroll::on_button_release_event ( GdkEventButton * ev ) [private]
```

This gives us Seq24 versus Fruity behavior.

```
12.46.2.18 bool seq64::perfroll::on_key_press_event( GdkEventKey * ev ) [private]
```

If we don't check the event type first, then the ev->keyval value is something weird like 65507. Note that we pass the functionality on to the perform::perfroll_key_event() function for the handling of delete, cut, copy, paste, and undo operations. If the keystroke is not handled by that function, then we handle it here.

Note that only the Seq24 input interaction object handles additional keystrokes not handled by the perfroll_key_ event() function. The perfroll_key_event() call handles Del, Ctrl-X, Ctrl-C, Ctrl-V, and Ctrl-Z (which does nothing at present).

Note that, even though we filter out the Ctrl key here, it still works for Ctrl-X (cut) and Ctrl-V (paste). For undo, the Undo button can be used, Ctrl-Z never worked in this view anyway.

12.46.3 Friends And Related Function Documentation

```
12.46.3.1 friend class FruityPerfInput [friend]
```

The perfedit class needs access to the private enqueue draw() function.

12.46.4 Field Documentation

```
12.46.4.1 perfedit& seq64::perfroll::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
12.46.4.2 int seq64::perfroll::m_h_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 4, for now. Might be a useful "user" configuration option.

```
12.46.4.3 int seq64::perfroll::m_v_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 8, for now. Might be a useful "user" configuration option.

```
12.46.4.4 FruityPerfInput seq64::perfroll::m_fruity_interaction [private]
```

Even if the user specifies the fruity interaction, the Seq24 interaction is still needed to handle our new keystroke support for the perfroll. We need both objects to exist all the time, similar to the Fruity/Seq24 roles in the seqroll object.

Obsolete AbstractPerfInput * m_interaction

12.47 seq64::perftime Class Reference

This class implements drawing the piano time at the top of the "performance window" (the "song editor"). Inheritance diagram for seq64::perftime:



Public Member Functions

• perftime (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_P ← PQN)

Principal constructor.

• void set_guides (int snap, int measure)

Sets the m_snap value and the m_measure_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

void increment_size ()

This function does nothing.

Private Member Functions

void enqueue_draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

• void set zoom (int z)

Implements the horizontal zoom feature.

void draw_background ()

Separated out the drawing done in on_expose_event(), so that it can be redone when the zoom changes.

· void change_horz ()

Change the m_4bar_offset and queue a draw operation.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

• long tick_to_pixel (midipulse tick)

Common calculation to convert a pulse/tick value to a perftime x value.

· midipulse pixel_to_tick (long pixel)

The inverse of tick_to_pixel().

void update_sizes ()

This function does nothing.

• int idle_progress ()

This function just returns true.

void update_pixmap ()

This function does nothing.

void draw_pixmap_on_window ()

This function does nothing.

void on_realize ()

Implements the on-realization event, then allocates some resources the could not be allocated in the constructor.

• bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Implement the button-press event.

• void on_size_allocate (Gtk::Allocation &r)

Implements a size-allocation event.

bool on_button_release_event (GdkEventButton *)

This button-release handler does nothing.

• bool key_press_event (GdkEventKey *ev)

This callback function handles a key-press event.

Private Attributes

perfedit & m_parent

Provides a link to the perfedit that created this object.

• int m_4bar_offset

Not yet sure exactly what this member represents.

• int m_tick_offset

This member is m_4bar_offset times 16 times the current PPQN, to save some calculations and centralize this value.

• int m_ppqn

The current value of PPQN, which we are trying to get to work everywhere, when PPQN is changed from the global ppqn = 192.

• int m_snap

Snap value, starts out very small, equal to m_ppqn.

int m_measure_length

Provides the length of a measure in pulses or ticks.

int m_left_marker_tick

Holds the current location of the left (L) marker when arrow movement is in force.

int m_right_marker_tick

Holds the current location of the right (R) marker when arrow movement is in force.

• int m perf scale x

A class version of the global c_perf_scale_x factor.

· int m_timearea_y

A class version of the global c_timerarea_y factor.

Additional Inherited Members

12.47.1 Constructor & Destructor Documentation

```
12.47.1.1 seq64::perftime::perftime ( perform & p, perfedit & parent, Gtk::Adjustment & hadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

In the constructor you can only allocate colors; get window() returns 0 because we have not been realized.

Note

Note that we still have to use a global constant in the base-class constructor; we cannot assign it to the corresponding member beforehand.

12.47.2 Member Function Documentation

12.47.2.1 void seq64::perftime::set_guides (int snap, int measure)

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set_guides(). This is actually equal to the measure-pulses divided by the snap value in perfedit; the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in
	perfedit::set_guides(). Generated by Doxygen

```
12.47.2.2 void seq64::perftime::enqueue_draw() [private]
```

The parent perfedit will call perftime::queue_draw() on behalf of this object, and it will pass a perftime::enqueue_draw() to the peer perfedit's perftime, if the peer exists.

```
12.47.2.3 void seq64::perftime::on_realize( ) [private]
```

It is important to call the base-class version of this function.

Done in base-class's on realize() and in its constructor now.

```
m_window = get_window();
m_gc = Gdk::GC::create(m_window);
m_window->clear();
set_size_request(10, m_timearea_y);
```

```
12.47.2.4 bool seg64::perftime::on_expose_event( GdkEventExpose * ev ) [private]
```

Note

The perfedit object is created early on. When brought on-screen from mainwand (the main window), first, perftime::on_realize() is called, then this event is called.

```
12.47.2.5 bool seq64::perftime::key_press_event ( GdkEventKey * ev ) [private]
```

Can't get the keystroke events to be seen by perfroll or perftime here using the normal callback function for keystrokes, and not sure why. The perfedit object can call this function, and that call works, so the perfedit class, which does get keystrokes, calls this function to do the work.

This function uses the "I" key to activate the movement of the "L" marker with the arrow keys, by the interval of on snap value for each press. It also uses the "r" key to activate the movement of the "R" marker, and the "x" to deactivate either movement move.

Be aware that there is no visual feedback, as yet, that one is in the movement mode.

Also be aware the changing the name of this function from "key_press_event()" to "on_key_press_event()" will disrupt the process, causing keystrokes to not get here. Too tricky.

12.47.3 Field Documentation

```
12.47.3.1 perfedit& seq64::perftime::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
12.47.3.2 int seq64::perftime::m_measure_length [private]
```

This value is $m_{ppqn} * 4$, though eventually we want to employ a more flexible representation of measure length. Supports perftime's keystroke processing.

12.47.3.3 int seq64::perftime::m_left_marker_tick [private]

Otherwise it is -1. Supports perftime's keystroke processing.

12.47.3.4 int seq64::perftime::m_right_marker_tick [private]

Otherwise it is -1. Supports perftime's keystroke processing.

12.48 seq64::rc_settings Class Reference

This class contains the options formerly named "global_xxxxxxx".

Public Member Functions

• rc settings ()

Default constructor.

· rc settings (const rc settings &rhs)

Copy constructor.

rc_settings & operator= (const rc_settings &rhs)

Principal assignment operator.

• std::string config_filespec () const

Constructs the full path and file specification for the "rc" file based on whether or not the legacy Seq24 filenames are being used.

• std::string user_filespec () const

Constructs the full path and file specification for the "user" file based on whether or not the legacy Seq24 filenames are being used.

· void set_defaults ()

Sets the default values.

• bool auto_option_save () const

Accessor m_auto_option_save

• bool legacy_format () const

Accessor m_legacy_format

bool lash_support () const

Accessor m_lash_support

• bool allow_mod4_mode () const

Accessor m_allow_mod4_mode

· bool show_midi () const

Accessor m_show_midi

• bool priority () const

Accessor m_priority

• bool stats () const

Accessor m stats

• bool pass_sysex () const

Accessor m_pass_sysex

· bool with jack transport () const

Accessor m with jack transport

• bool with_jack_master () const

Accessor m_with_jack_master

• bool with_jack_master_cond () const

Accessor m_with_jack_master_cond

bool with_jack () const

Accessor m_with_jack_transport m_with_jack_master, and m_with_jack_master_cond, to save client code some trouble.

bool jack_start_mode () const

Accessor m_jack_start_mode,

bool manual_alsa_ports () const

Accessor m_manual_alsa_ports

bool reveal_alsa_ports () const

Accessor m_reveal_alsa_ports

bool is_pattern_playing () const

Accessor m_is_pattern_playing

• bool print_keys () const

Accessor m_print_keys

· bool device_ignore () const

Accessor m_device_ignore

• int device ignore num () const

'Getter' function for member m_device_ignore_num

interaction_method_t interaction_method () const

'Getter' function for member m_interaction_method

· const std::string & filename () const

'Getter' function for member m_filename

· const std::string & jack_session_uuid () const

'Getter' function for member m_jack_session_uuid

· const std::string & last_used_dir () const

'Getter' function for member m_last_used_dir

const std::string & config_directory () const

'Getter' function for member m_config_directory

const std::string & config_filename () const

'Getter' function for member m_config_filename
• const std::string & user_filename () const

'Getter' function for member m_user_filename

const std::string & config_filename_alt () const

'Getter' function for member m config filename alt;

• const std::string & user_filename_alt () const

'Getter' function for member m_user_filename_alt

void device_ignore_num (int value)

'Setter' function for member m_device_ignore_num However, please note that this value, while set in the options processing of the main module, does not appear to be used anywhere in the code in seq24, Sequencer24, and this application.

void interaction_method (interaction_method_t value)

'Setter' function for member m_interaction_method

void filename (const std::string &value)

'Setter' function for member m filename

void jack_session_uuid (const std::string &value)

'Setter' function for member m_jack_session_uuid

void last_used_dir (const std::string &value)

'Setter' function for member m last used dir

void config_directory (const std::string &value)

'Setter' function for member m_config_directory

void config_filename (const std::string &value)

'Setter' function for member m_config_filename

void user_filename (const std::string &value)

'Setter' function for member m_user_filename

void config_filename_alt (const std::string &value)

'Setter' function for member m_config_filename_alt;

void user_filename_alt (const std::string &value)

'Setter' function for member m_user_filename_alt

Private Member Functions

• std::string home_config_directory () const

Provides the directory for the configuration file, and also creates the directory if necessary.

Private Attributes

std::string m filename

Provides the name of current MIDI file.

12.48.1 Member Function Documentation

12.48.1.1 std::string seq64::rc_settings::home_config_directory()const [private]

If the legacy format is in force, then the home directory for the configuration is (in Linux) "/home/username", and the configuration file is ".seq24rc".

If the new format is in force, then the home directory is (in Linux) "/home/username/.config/sequencer64", and the configuration file is "sequencer64.rc".

Returns

Returns the selection home configuration directory. If it does not exist or could not be created, then an empty string is returned.

12.49 seg64::rect Class Reference

A small helper class representing a rectangle.


12.50 seq64::gui_drawingarea_gtk2::rect Struct Reference

A small helper structure representing a rectangle.

12.51 seq64::Seq24PerfInput Class Reference

Implements the default (Seq24) performance input characteristics of this application.

Inheritance diagram for seq64::Seq24PerfInput:



Public Member Functions

- bool on_button_press_event (GdkEventButton *a_ev, perfroll &roll)

 Handles the normal variety of button-press event.
- $\bullet \ \ bool\ on_button_release_event\ (GdkEventButton\ *a_ev,\ perfroll\ \&roll)\\$

Handles various button-release events.

• bool on_motion_notify_event (GdkEventMotion *a_ev, perfroll &roll)

Handles the normal motion-notify event.

Private Member Functions

• void set_adding (bool a_adding, perfroll &roll)

A popup menu (which one?) calls this.

bool handle_motion_key (bool is_left, perfroll &roll)

Handles the keystroke motion-notify event for moving a pattern back and forth in the performance.

• bool is_adding () const

'Getter' function for member m_adding

Private Attributes

· bool m_adding

Indicates we are in the middle of adding a sequence segment to the performance.

midipulse m_effective_tick

The current tick for the current segment?

12.51.1 Member Function Documentation

12.51.1.1 bool seq64::Seq24Perfinput::on_button_press_event (GdkEventButton * ev, perfroll & roll) [virtual]

Is there any easy way to use ctrl-left-click as the middle button here?

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

```
12.51.1.2 bool seq64::Seq24Perfinput::on_button_release_event ( GdkEventButton * ev, perfroll & roll ) [virtual]
```

Any use for the middle-button or ctrl-left-click we can add?

Returns

Returns true if any modification occurred.

Implements seq64::AbstractPerfInput.

```
12.51.1.3 bool seq64::Seq24PerfInput::on_motion_notify_event( GdkEventMotion * ev, perfroll & roll ) [virtual]
```

Returns

Returns true if a modification occurs. This function used to always return true.

Implements seq64::AbstractPerfInput.

```
12.51.1.4 void seq64::Seq24PerfInput::set_adding ( bool adding, perfroll & roll ) [private]
```

What does it mean?

```
12.51.1.5 bool seq64::Seq24PerfInput::handle_motion_key( bool is_left, perfroll & roll) [private]
```

What happens when the mouse is used to drag the pattern is that, first, roll.m_drop_tick is set by left-clicking into the pattern to select it. As the pattern is dragged, the drop-tick value does not change, but the tick (converted from the moving x value) does.

Then the button-handler sets roll.m_moving = true, and calculates roll.m_drop_tick_trigger_offset = roll.m_drop_tick - p.get_sequence(dropseq)->selected_trigger_start();

The motion handler sees that roll.m_moving is true, gets the new tick value from the new x value, offsets it, and calls p.get_sequence(dropseq)->move_selected_triggers_to(tick, true).

When the user releases the left button, then roll.m_growing is turned of and the roll draw_all()'s.

Parameters

is_left	False denotes the right arrow key, and true denotes the left arrow key.]
roll	Provides a reference to the parent roll, which keeps track of most of the information about the status of]
	the window.	

Returns

Returns true if there was some action able to happen that would necessitate a window update. We've updated triggers::move_selected() [called indirectly near the end of this routine] to return false if no more movement could be made. This prevents this routine from moving way ahead after movement of the selected (in the user-interface) trigger stops.

12.52 seq64::Seq24SeqEventInput Struct Reference

This structure implement the normal interaction methods for Seq24.

Public Member Functions

• Seq24SeqEventInput ()

Default constructor.

void set_adding (bool a_adding, seqevent &ths)

Changes the mouse cursor to a pencil or a left pointer in the given seqevent aobject, depending on the first parameter.

bool on_button_press_event (GdkEventButton *a_ev, seqevent &ths)

Implements the on-button-press event callback.

bool on_button_release_event (GdkEventButton *a_ev, seqevent &ths)

Implements the on-button-release callback.

bool on_motion_notify_event (GdkEventMotion *a_ev, seqevent &ths)

Implements the on-motion-notify event.

12.52.1 Member Function Documentation

12.52.1.1 void seq64::Seq24SeqEventInput::set_adding (bool adding, seqevent & seqev)

Modifies m_adding as well.

12.52.1.2 bool seq64::Seq24SeqEventInput::on_button_press_event (GdkEventButton * a_ev, seqevent & seqev)

Set values for dragging, then reset the box that holds dirty redraw spot. Then do the rest.

Returns

Returns true if a likely modification was made. This function used to return true all the time.

Needs update. seqev.m_seq.unselect(); ???????

12.52.1.3 bool seq64::Seq24SeqEventInput::on_button_release_event (GdkEventButton * a_ev, seqevent & seqev)

Returns

Returns true if a likely modification was made. This function used to return true all the time.

12.52.1.4 bool seq64::Seq24SeqEventInput::on_motion_notify_event (GdkEventMotion * a_ev, seqevent & seqev)

Returns

Returns true if a likely modification was made. This function used to return true all the time.

12.53 seq64::Seq24SeqRollInput Class Reference

Implements the Seq24 mouse interaction paradigm for the seqroll.

Public Member Functions

Seq24SeqRollInput ()

Default constructor.

void set_adding (bool a_adding, seqroll &ths)

Changes the mouse cursor pixmap according to whether a note is being added or not.

• bool on_button_press_event (GdkEventButton *a_ev, seqroll &ths)

Implements the on-button-press event handling for the Seq24 style of mouse interaction.

bool on_button_release_event (GdkEventButton *a_ev, seqroll &ths)

Implements the on-button-release event handling for the Seq24 style of mouse interaction.

• bool on_motion_notify_event (GdkEventMotion *a_ev, seqroll &ths)

Seq24-style on-motion mouse interaction.

12.53.1 Member Function Documentation

12.53.1.1 void seq64::Seq24SeqRollInput::set_adding (bool adding, seqroll & sroll)

What calls this? It is actually a right click.

12.53.1.2 bool seq64::Seq24SeqRollInput::on_button_press_event (GdkEventButton * ev, seqroll & sroll)

This function now uses the needs_update flag to determine if the perform object should modify().

Returns

Returns the value of needs_update. It used to return only true.

12.53.1.3 bool seq64::Seq24SeqRollInput::on_button_release_event (GdkEventButton * ev, seqroll & sroll)
This function now uses the needs_update flag to determine if the perform object should modify().
Returns the value of needs_update. It used to return only true.
12.54 seq64::seqdata Class Reference
This class supports drawing piano-roll eventis on a window.

Inheritance diagram for seq64::seqdata:



Public Member Functions

- seqdata (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust)

 Principal constructor.
- void reset ()

This function calls update_size().

• void redraw ()

Updates the pixmap and queues up a redraw operation.

void set_zoom (int a_zoom)

Sets the zoom to the given value and resets the view via the reset function.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given value, and the control to the optional given value, which defaults to 0, then calls redraw().

Private Member Functions

• int idle_redraw ()

Draws events on this object's built-in window and pixmap.

· void update sizes ()

Updates the sizes in the pixmap if the view is realized, and queues up a draw operation.

void update_pixmap ()

Simply calls draw_events_on_pixmap().

void draw_line_on_window ()

Draws on vertical line on the data window.

void xy_to_rect (int x1, int y1, int x2, int y2, int &rx, int &ry, int &rw, int &rh)

This function takes two points, and returns an Xwin rectangle, returned via the last four parameters.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > drawable)

Draws events on the given drawable object.

• void change_horz ()

Change the scrolling offset on the x-axis, and redraw.

void convert_x (int x, midipulse &tick)

This function takes screen coordinates, and gives the horizontaol tick value based on the current zoom, returned via the second parameter.

• void render_number (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, const char *const num)

Convenience function for rendering numbers.

void draw_events_on_pixmap ()

Simply calls draw_events_on() for this object's built-in pixmap.

void draw_pixmap_on_window ()

Simply queues up a draw operation.

void on_realize ()

Implements the on-realization event, by calling the base-class version and then allocating the resources that could not be allocated in the constructor.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Implement a button-press event.

• bool on_button_release_event (GdkEventButton *ev)

Implement a button-release event.

• bool on_motion_notify_event (GdkEventMotion *ev)

Handles a motion-notify event.

bool on_leave_notify_event (GdkEventCrossing *ev)

Handles an on-leave notification event.

bool on_scroll_event (GdkEventScroll *ev)

Implements the on-scroll event.

void on_size_allocate (Gtk::Allocation &)

Handle a size-allocation event.

Private Attributes

• int m zoom

one pixel == m_zoom ticks

int m_number_w

The adjusted width of a digit in a data number.

int m_number_h

The adjusted height of all digits in a data number.

int m_number_offset_y

A new value to make it easier to adapt the vertical number drawing of a data item's numeric value to a different font.

midibyte m_status

What is the data window currently editing?

Additional Inherited Members

12.54.1 Constructor & Destructor Documentation

```
12.54.1.1 seq64::seqdata::seqdata ( sequence & seq, perform & p, int zoom, Gtk::Adjustment & hadjust )
```

In the constructor you can only allocate colors, get_window() returns 0 because we have not been realized.

12.54.2 Member Function Documentation

```
12.54.2.1 void seq64::seqdata::reset ( )
```

Then, regardless of whether the view is realized, updates the pixmap and queues up a draw operation.

Note

If it weren't for the is_realized() condition, we could just call update_sizes(), which does all this anyway.

```
12.54.2.2 void seq64::seqdata::set_data_type ( midibyte status, midibyte control )
```

Perhaps we should check that at least one of the parameters causes a change.

```
12.54.2.3 int seq64::seqdata::idle_redraw() [private]
```

This drawing is done only if there is no dragging in progress, to guarantee no flicker.

```
12.54.2.4 void seq64::seqdata::update_sizes( ) [private]
```

It creates a pixmap with window dimensions given by m window x and m window y.

12.54.2.5 void seq64::seqdata::xy_to_rect(int x1, int y1, int x2, int y2, int & rx, int & ry, int & rw, int & rh) [private]

It checks the mins/maxes, then fills in x, y, and width, height.

```
12.54.2.6 void seq64::seqdata::draw_events_on( Glib::RefPtr< Gdk::Drawable > drawable) [private]
```

Very similar to seqevent::draw_events_on(). And yet it doesn't handle zooming as well, must fix! ca 2016-04-13 We now draw the data line for selected event in orange, instead of black.

Parameters

drawable	The given drawable object.
----------	----------------------------

```
12.54.2.7 void seq64::seqdata::change_horz( ) [private]
```

Basically identical to sequent::change horz().

```
12.54.2.8 void seq64::seqdata::on_realize( ) [private]
```

It also connects up the change_horz() function.

Note that this function creates a small pixmap for every possible y-value, where y ranges from 0 to MIDI_COUNT ← _MAX-1 = 127. It then fills each pixmap with a numeric representation of that y value, up to three digits (left-padded with spaces).

```
12.54.2.9 bool seq64::seqdata::on expose event ( GdkEventExpose * a e ) [private]
```

Returns

Always returns true.

```
12.54.2.10 bool seq64::seqdata::on_button_press_event( GdkEventButton * ev ) [private]
```

Returns

Always returns true.

```
12.54.2.11 bool seq64::seqdata::on_button_release_event( GdkEventButton * ev ) [private]
```

Returns

Returns true if a modification occurred, and in that case also sets the perform modification flag.

```
12.54.2.12 bool seq64::seqdata::on_motion_notify_event ( GdkEventMotion * ev ) [private]
```

It converts the x,y of the mouse to ticks, then sets the events in the event-data-range, updates the pixmap, draws events in the window, and draws a line on the window.

Returns

Returns true if a change in event data occurred. If true, then the perform modification flag is set.

```
12.54.2.13 bool seq64::seqdata::on_scroll_event( GdkEventScroll * a_ev ) [private]
```

This scroll event only handles basic scrolling, without any modifier keys such as SEQ64_CONTROL_MASK or SEQ64K_SHIFT_MASK.

If there is a note (seqroll pane) or event (seqevent pane) selected, and mouse hovers over the data area (seqdata pane), then this scrolling action will increase or decrease the value of the data item, which lengthens of shortens the line drawn.

Todo DOCUMENT the sequata scrolling behavior in the documentation projects.

Returns

Always returns true.

12.54.3 Field Documentation

```
12.54.3.1 int seq64::seqdata::m_number_w [private]
```

By "adjusted", well this is just a minor tweak for appearances.

```
12.54.3.2 int seq64::seqdata::m_number_h [private]
```

Basically, the character height times 3. By "adjusted", well this is just a minor tweak for appearances.


```
12.54.3.3 int seq64::seqdata::m_number_offset_y [private]
```

This value was hardwired as 8, for a character height of 10.

12.55 seq64::seqedit Class Reference

Implements the Pattern Editor, which has references to:

Inheritance diagram for seq64::seqedit:



Public Member Functions

- seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 Principal constructor.
- ∼seqedit ()

A rote destructor.

Private Member Functions

void set_zoom (int zoom)

Selects the given zoom value.

void set_snap (int snap)

Selects the given snap value, which is the number of ticks in a snap-sized interval.

• void set_note_length (int note_length)

Selects the given note-length value.

· void set beats per bar (int bpm)

Set the bpm (beats per measure) value, using the given parameter, and some internal values passed to apply_\leftarrow length().

void set_beat_width (int bw)

Set the bw (beat width) value, using the given parameter, and some internal values passed to apply_length().

void set_rec_vol (int recvol)

Passes the given parameter to sequence::set_rec_vol().

void horizontal_adjust (double step)

This function provides optimization for the on scroll event() function.

void set_measures (int lim)

Set the measures value, using the given parameter, and some internal values passed to apply_length().

void apply length (int bpm, int bw, int measures)

Sets the sequence length based on the three given parameters.

long get_measures ()

Calculates the measures value based on the bpm (beats per measure), ppqn (parts per quarter note), and bw (beat width) values, and returns the resultant measures value.

void set midi channel (int midichannel)

Selects the given MIDI channel parameter in the main sequence object, so that it will use that channel.

void set_midi_bus (int midibus)

Selects the given MIDI buss parameter in the main sequence object, so that it will use that buss.

void set scale (int scale)

Selects the given scale value.

void set_key (int note)

Selects the given key (signature) value.

void set_background_sequence (int seq)

Draws the given background sequence on the Pattern editor so that the musician has something to see that can be played against.

• void name_change_callback ()

Set the name for the main sequence to this object's entry name.

· void play_change_callback ()

Passes the play status to the sequence object.

void record_change_callback ()

Passes the recording status to the sequence object.

void q_rec_change_callback ()

Passes the quantized-recording status to the sequence object.

• void thru_change_callback ()

Passes the MIDI Thru status to the sequence object.

void undo_callback ()

Pops an undo operation from the sequence object, and then tells the segroll, seqtime, seqdata, and seqevent objects to redraw.

• void redo_callback ()

Pops a redo operation from the sequence object, and then tell the segroll, seqtime, seqdata, and seqevent objects to redraw.

• void set_data_type (midibyte status, midibyte control=0)

Sets the data type based on the given parameters.

void fill_top_bar ()

This function inserts the user-interface items into the top bar or panel of the pattern editor; this bar has two rows of user interface elements.

· void create menus ()

Creates the various menus by pushing menu elements into the menus.

void popup_menu (Gtk::Menu *menu)

Pops up the given pop-up menu.

void popup_event_menu ()

Populates the event-selection menu that drops from the "Event" button in the bottom row of the Pattern editor.

• void popup_midibus_menu ()

Populates the MIDI Output buss pop-up menu.

• void popup_sequence_menu ()

Populates the "set background sequence" menu (drops from the button that has some note-bars on it at the right of the second row of the top bar).

void popup_tool_menu ()

Sets up the pop-up menus that are brought up by pressing the Tools button, which shows a hammer image.

· void popup midich menu ()

Populates the MIDI Channel pop-up menu.

Gtk::Image * create_menu_image (bool state=false)

Sets the manu pixmap depending on the given state, where true is a full menu (black backgroun), and empty menu (gray background).

• bool timeout ()

Update the window after a time out, based on dirtiness and on playback progress.

void do_action (int action, int var)

Implements the actions brought forth from the Tools (hammer) button.

void on_realize ()

On realization, calls the base-class version, and connects the redraw timeout signal, timed at redraw_period_ms().

bool on_delete_event (GdkEventAny *event)

Handles an on-delete event.

• bool on scroll event (GdkEventScroll *ev)

Handles an on-scroll event.

bool on_key_press_event (GdkEventKey *ev)

Handles a key-press event.

Private Attributes

int m_zoom

Provides the zoom values: 1 2 3 4, and 1, 2, 4, 8, 16.

• int m_snap

Used in setting the snap-to value in pulses, off = 1.

int m_note_length

The default length of a note to be inserted by a right-left-click operation.

• int m_scale

Settings for the music scale, key, and background sequence.

· long m_measures

Provides the length of the sequence in measures.

int m_ppqn

Holds a copy of the current PPQN for the sequence (and the entire MIDI file).

· sequence & m_seq

Holds a reference to the sequence that this window represents.

• Gtk::MenuBar * m_menubar

A number of user-interface objects.

• Gtk::Menu * m menu length

Provides the length in measures.

• Gtk::Menu * m_menu_bpm

These member provife the time signature, beats per measure, and beat width menus.

• int m_pos

Basically the sequence number.

• Gtk::Adjustment * m vadjust

Scrollbar and adjustment objects for horizontal and vertical panning.

• seqkeys * m_seqkeys_wid

Handles the piano-keys part of the user-interface.

• seqtime * m_seqtime_wid

Handles the time-line (bar or measures) part of the user-interface.

• seqdata * m_seqdata_wid

Handles the event-data part of the user-interface.

seqevent * m_seqevent_wid

Handles the small event part of the user-interface, where events can be moved and added.

• seqroll * m_seqroll_wid

Handles the piano-roll part of the user-interface.

• Gtk::Table * m_table

More user-interface elements.

midibyte m_editing_status

Indicates what is the data window currently editing?

Static Private Attributes

• static int m_initial_snap

Static data members.

Additional Inherited Members

12.55.1 Detailed Description

- perform
- · seqroll
- · seqkeys
- · seqdata
- · seqtime
- · seqevent
- sequence

This class has a metric ton of user-interface objects and other members.

12.55.2 Constructor & Destructor Documentation

```
12.55.2.1 seq64::seqedit::seqedit( perform & p, sequence & seq, int pos, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

If provided, override the scale, key, and background-sequence with the values stored in the file with the sequence, if they are set to non-default values. This is a new feature.

Todo Offload most of the work into an initialization function like options does.

Horizontal Gtk::Adjustment constructor: The initial value was 0 on a range from 0 to 1, with step and page increments of 1, and a page_size of 1. We can fix these values here, or create an h_adjustment() function similar to eventedit ::v adjustment(), which first gets called in on realize().

12.55.3 Member Function Documentation

```
12.55.3.1 void seq64::seqedit::set_zoom(int z) [private]
```

It is passed to the segroll, segtime, segdata, and segevent objects, as well.

The notation is in pixels:ticks, but I would prefer to use pulses/pixel (pulses per pixel). Oh well.

Finally, note that this value of zoom is saved to the "user" configuration file when Sequencer64 exit.

```
12.55.3.2 void seq64::seqedit::set_snap ( int snap ) [private]
```

It is passed to the seqroll, seqevent, and sequence objects, as well.

The default initial snap is the default PPQN divided by 4, or the equivalent of a 16th note (48 ticks). The snap divisor is 192 * 4 / 48 or 16.

```
12.55.3.3 void seq64::seqedit::set_note_length ( int notelength ) [private]
```

It is passed to the seqroll object, as well.

Warning

Currently, we don't handle changes in the global PPQN after the creation of the menu. The creation of the menu hard-wires the values of note-length. To adjust for a new global PQN, we will need to store the original PPQN (m_original_ppqn = m_ppqn), and then adjust the notelength based on the new PPQN. For example if the new PPQN is twice as high as 192, then the notelength should double, though the text displayed in the "Note length" field should remain the same. However, we do adjust for a non-default PPQN at startup time.

Parameters

notelength Prov	ides the note length in units of MIDI pulses.
-----------------	---

```
12.55.3.4 void seq64::seqedit::horizontal_adjust(double step) [inline], [private]
```

A duplicate of the one in segroll.

Parameters

st	ер	Provides the step value to use for adjusting the horizontal scrollbar. See
		gui_drawingarea_gtk2::scroll_adjust() for more information.

12.55.3.5 void seq64::seqedit::set_measures (int lim) [private]

Parameters

lim Provides the sequence length, in measures.

12.55.3.6 void seq64::seqedit::apply_length (int bpm, int bw, int measures) [private]

There's an implicit "adjust-triggers = true" parameter used in sequence::set length().

Then the seqroll, seqtime, seqdata, and seqevent objects are reset().

12.55.3.7 long seq64::seqedit::get_measures() [private]

Todo Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

12.55.3.8 void seq64::seqedit::set_midi_channel(int midichannel) [private]

Should this change set the is-modified flag?

12.55.3.9 void seq64::seqedit::set_midi_bus(int bus) [private]

Should this change set the is-modified flag?

12.55.3.10 void seq64::seqedit::set_scale (int scale) [private]

It is passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

```
12.55.3.11 void seq64::seqedit::set_key(int key) [private]
```

It is passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global seq feature().

```
12.55.3.12 void seq64::seqedit::set_background_sequence(int seqnum) [private]
```

As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data, but only if less or equal to the maximum single-byte MIDI value, 127.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

Todo Make the sequence pointer a reference.

```
12.55.3.13 void seq64::seqedit::name_change_callback( ) [private]
```

That name is the name the user has given to the sequence being edited.

```
12.55.3.14 void seq64::seqedit::set_data_type ( midibyte status, midibyte control = 0 ) [private]
```

This function uses the hardwired array c controller names.

Parameters

stati	us	The current editing status.
cont	trol	The control value. However, we really need to validate it!

```
12.55.3.15 void seg64::segedit::fill_top_bar( ) [private]
```

Note that, if a non-default title for the sequence is in force, then we immediately force the focus to the sequol "widget", so that the space bar can be used to control playback, instead of immediately erasing the name of the sequence.

```
12.55.3.16 void seq64::seqedit::create_menus() [private]
```

The first menu is the Zoom menu, represented in the pattern/sequence editor by a button with a magnifying glass. The values are "pixels to ticks", where "ticks" are actually the "pulses" of "pulses per quarter note". We would prefer the notation "n" instead of "1:n", as in "n pulses per pixel".

Note that many of the setups here could be loops through data structures. The Snap menu is actually the Grid Snap button, which shows two arrows pointing to a central bar.

The note-length menu is on the button that shows four notes.

This menu lets one set the key of the sequence, and is brought up by the button with the "golden key" image on it.

This button shows a down around for the bottom half of the time signature. It's tooltip is "Time signature. Length of beat." But it is called bw, or beat width, in the code.

This menu is shown when pressing the button at the bottom of the window that has "Vol" as its label. Let's show the numbers as well to help the user. And we'll have to document this change.

This menu sets the scale to show on the panel, and the button shows a "staircase" image. See the c_music_scales enumeration defined in the globals module.

This section sets up two different menus. The first is m_menu_length. This menu lets one set the sequence length in bars. The second menu is the m_menu_bpm, or BPM, which here means "beats per measure" (not "beats per minute").

```
12.55.3.17 void seq64::seqedit::popup_event_menu() [private]
```

This menu has a large number of items. I think they are filled in in code, but can also be loaded from \sim /.seq24usr. To be determined. Create the 8 sub-menus for the various ranges of controller changes, shown 16 per sub-menu.

```
12.55.3.18 void seq64::seqedit::popup_midibus_menu() [private]
```

The MIDI busses are obtained by getting the mastermidibus object, and iterating through the busses that it contains.

```
12.55.3.19 void seq64::seqedit::popup_sequence_menu() [private]
```

It is populated with an "Off" menu entry, and a second "[0]" menu entry that pulls up a drop-down menu of all of the patterns/sequences that are present in the MIDI file for screen-set 0. If more screensets have active sequences, then their screen-set number appears in the screen-set section of the menu.

Now, at present, we can only save background sequence numbers that are less than 128, which means the sequences from 0 to 127, or the first four screen sets. Higher sequences can be selected, but, right now, they cannot be saved. We'll probably fix that at some point, low priority.

```
12.55.3.20 void seq64::seqedit::popup_tool_menu( ) [private]
```

This button shows three sub-menus that need to be filled in by this function. All the functions accessed here seem to be implemented by the do_action() function.

```
12.55.3.21 bool seq64::seqedit::timeout( ) [private]
```

Note the new call to seqroll::follow_progress(). This allows the seqroll to pop to the next frame of events to continue to show the moving progress bar. Does this need to be an option? It only affects patterns longer than a measure or two, whatever the width of the seqroll window is. This is a new feature that is not in seq24.

What about seqtime? That doesn't change.

```
12.55.3.22 void seq64::seqedit::do_action (int action, int var) [private]
```

Note that the push_undo() calls push all of the current events (in sequence::m_events) onto the stack (as a single entry).

```
12.55.3.23 bool seq64::seqedit::on_delete_event ( GdkEventAny * event ) [private]
```

It tells the sequence to stop recording, tells the perform object's mastermidibus to stop processing input, and sets the sequence object's editing flag to false.

Warning

This function also calls "delete this"!

Returns

Always returns false.

```
12.55.3.24 bool seq64::seqedit::on_scroll_event( GdkEventScroll * ev ) [private]
```

This handles moving the scroll wheel on a mouse or do a two-fingered scrolling action on a touchpad. If no modifier key is pressed, this moves the view up or down on the "notes" coordinate, showing different piano keys. This behavior is implemented in seqkeys::on_scroll_event(), and is called into play by returning false here.

If the Ctrl key is pressed, then the scrolling action causes the view to zoom in or out. This behavior is implemented here.

If the Shift key is pressed, then the scrolling action moves the view horizontally on the time-line (measures-line) of the piano roll. This behavior is implemented here.

```
12.55.3.25 bool seq64::seqedit::on_key_press_event( GdkEventKey * ev ) [private]
```

In particular, the Ctrl-W keypress. This keypress closes the sequence/pattern editor window by way of calling on—
_delete_event(). We should consider applying this convention to all the other windows. Also handled are the new z0Z zoom keys.

12.55.4 Field Documentation

```
12.55.4.1 int seq64::seqedit::m_initial_snap [static], [private]
```

These items apply to all of the instances of seqedit, and are passed on to the following constructors:

- · seqdata
- · seqevent
- · segroll
- · seqtime

The snap and note-length defaults would be good to write to the "user" configuration file. The scale and key would be nice to write to the proprietary section of the MIDI song. Or, even more flexibly, to each sequence, if that makes sense to do, since all tracks would generally be in the same key. Right, Charles Ives?

Note that, currently, that some of these "initial values" are modified, so that they are "contagious". That is, the next sequence to be opened in the sequence editor will adopt these values. This is a long-standing feature of Seq24, but strikes us as a bit surprising.

ca 2016-04-10 If we just double the PPQN, then the snap divisor becomes 32, and the snap interval is a 32nd note. We would like to keep it at a 16th note. We correct the snap ticks to the actual PPQN ratio.

```
12.55.4.2 int seq64::seqedit::m_zoom [private]
```

The value of zoom is the same as the number of pixels per tick on the piano roll.

```
12.55.4.3 int seq64::seqedit::m_pos [private]
```

We will eventually remove this member, as we can get it via sequence::number() now.

```
12.55.4.4 seqkeys* seq64::seqedit::m_seqkeys_wid [private]
```

This item draws the piano-keys at the left of the seqedit window.

```
12.55.4.5 seqtime* seq64::seqedit::m_seqtime_wid [private]
```

This is the location where the measure numbers and the END marker are shown.

```
12.55.4.6 seqdata* seq64::seqedit::m_seqdata_wid [private]
```

This is the area at the bottom of the window that shows value lines for the selected kinds of events.

```
12.55.4.7 Gtk::Table* seq64::seqedit::m_table [private]
```

These items provide a number of buttons and text-entry fields, as well as their layout.

12.56 seq64::seqevent Class Reference

Implements the piano event drawing area.

Inheritance diagram for seq64::seqevent:



Public Member Functions

• seqevent (perform &p, sequence &seq, int zoom, int snap, seqdata &seqdata_wid, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

• void reset ()

This function basically resets the whole widget as if it was realized again.

· void redraw ()

Adjusts the scrolling offset for ticks, updates the pixmap, and draws it on the window.

· void set zoom (int a zoom)

Sets zoom to the given value, and resets if the value ended up being changed.

void set_snap (int a_snap)

'Setter' function for member m_snap

void set_data_type (midibyte a_status, midibyte a_control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

void update_sizes ()

If the window is realized, this function creates a pixmap with window dimensions, the updates the pixmap, and queues up a redraw.

void draw background ()

This function updates the background.

void draw_events_on_pixmap ()

This function fills the main pixmap with events.

· void draw pixmap on window ()

This function currently just queues up a draw operation for the pixmap.

void draw_selection_on_window ()

Draw the selected events on the window.

void update_pixmap ()

Redraws the background pixmap on the main pixmap, then puts the events on.

Private Member Functions

virtual void force_draw ()

Forces a draw on the current drawable area of the window.

int idle_redraw ()

Implements redraw while idling.

void x_to_w (int a_x1, int a_x2, int &a_x, int &a_w)

This function checks the mins / maxes.

void drop_event (midipulse a_tick)

Drops (adds) an event at the given tick.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > a_draw)

Draws events on the given drawable object.

• void start_paste ()

Starts a paste operation.

void change_horz ()

Changes the horizontal scrolling offset for ticks, then updates the pixmap and forces a redraw.

• void convert_x (int x, midipulse &tick)

Takes the screen x coordinate, multiplies it by the current zoom, and returns the tick value in the given parameter.

• void convert_t (midipulse ticks, int &x)

Converts the given tick value to an x corrdinate, based on the zoom, and returns it via the second parameter.

void snap_y (int &y)

This function performs a 'snap' on y.

void snap_x (int &a_x)

This function performs a 'snap' on x.

• void on realize ()

Implements the on-realize callback.

bool on_expose_event (GdkEventExpose *a_ev)

Implements the on-expose event callback.

```
• bool on_button_press_event (GdkEventButton *a_ev)

Implements the on-button-press event callback.
```

bool on_button_release_event (GdkEventButton *a_ev)

Implements the on-button-release event callback.

bool on_motion_notify_event (GdkEventMotion *a_ev)

Implements the on-motion-notify event callback.

bool on_focus_in_event (GdkEventFocus *)

Responds to a focus event by setting the HAS_FOCUS flag.

bool on_focus_out_event (GdkEventFocus *)

Responds to a unfocus event by resetting the HAS_FOCUS flag.

bool on_key_press_event (GdkEventKey *a_p0)

Implements the key-press event callback function.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event callback.

Private Attributes

• FruitySeqEventInput m_fruity_interaction

Why should we need both at the same time? Just load the one that is specified in the configuration.

int m_zoom

Zoom setting, means that one pixel == m_zoom ticks.

· bool m_selecting

Used when highlighting a bunch of events.

midibyte m_status

Indicates what is the data window currently editing?

Additional Inherited Members

```
12.56.1 Member Function Documentation
```

```
Basically identical to seqtime::reset().

12.56.1.2 void seq64::seqevent::redraw()

Somewhat similar to seqroll::redraw().
```

12.56.1.1 void seq64::seqevent::reset ()

```
12.56.1.3 void seq64::seqevent::set_snap ( int a_snap ) [inline]
```

Simply sets the snap member.

12.56.1.4 void seq64::seqevent::set_data_type (midibyte status, midibyte control = 0)

Then redraws.

```
12.56.1.5 void seq64::seqevent::update_sizes ( )
```

This ends up filling the background with dotted lines, etc.

```
12.56.1.6 void seq64::seqevent::draw_background()
```

It sets the foreground to white, draws the rectangle, in order to clear the pixmap.

```
12.56.1.7 void seq64::seqevent::draw_pixmap_on_window( )
```

Old comments:

```
It then tells event to do the same. We changed something on this window, and chances are we need to update the event widget as well and update our velocity window.
```

```
12.56.1.8 int seq64::seqevent::idle_redraw( ) [private]
```

Who calls this routine?

```
12.56.1.9 void seq64::seqevent::x_to_w ( int a_x1, int a_x2, int & a_x, int & a_w ) [private]
```

Then it fills in x and the width.

```
12.56.1.10 void seq64::seqevent::drop_event( midipulse a_tick) [private]
```

It sets the first byte properly for after-touch, program-change, channel-pressure, and pitch-wheel. The type of event is determined by m_status.

```
12.56.1.11 void seq64::seqevent::draw_events_on( Glib::RefPtr< Gdk::Drawable > drawable ) [private]
```

Very similar to seqdata::draw_events_on().

Parameters

drawable The given drawable objec

```
12.56.1.12 void seq64::seqevent::start_paste( ) [private]
```

It gets the clipboard box that selected elements are in, makes a coordinate conversion, and then, sets the m_\circ} selected rectangle to hold the (x,y,w,h) of the selected events.

```
12.56.1.13 void seq64::seqevent::change_horz() [private]
```

Very similar to seqroll::change_horz(). Basically identical to seqdata::change_horz().

```
12.56.1.14 void seq64::seqevent::convert_x (int x, midipulse & tick ) [inline], [private]
```

Why not just return it normally?

```
12.56.1.15 void seq64::seqevent::convert_t( midipulse ticks, int & x ) [inline], [private]
```

Why not just return it normally?

```
12.56.1.16 void seq64::seqevent::snap_x ( int & x ) [private]
```

- snap = number pulses to snap to
- m zoom = number of pulses per pixel
- Therefore snap / m_zoom = number of pixels to snap to.

```
12.56.1.17 void seq64::seqevent::on_realize( ) [private]
```

It calls the base-class version, and then allocates additional resource not allocated in the constructor. Finally, it connects up the change horz function.

```
12.56.1.18 bool seq64::seqevent::on_button_press_event( GdkEventButton * a_ev ) [private]
```

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. In the legacy code, each case fell through to the next case to the "default" case! We will assume for now that this is incorrect.

Note that returning "true" from a Gtkmm event-handler stops the propagation of the event to higher-level widgets. The Fruity and Seq24 event handlers return true, always. In the legacy code, though, the fall-through code caused false to be returned, always. Not sure what effect this had. Added some fixes, but then commented them out until better testing can be done.

```
12.56.1.19 bool seg64::segevent::on_button_release_event( GdkEventButton * a_ev ) [private]
```

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

12.56.1.20 bool seq64::seqevent::on_motion_notify_event (GdkEventMotion * a_ev) [private]

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

12.56.1.21 bool seq64::seqevent::on_key_press_event (GdkEventKey * ev) [private]

It handles deleted a selection via the Backspace or Delete keys, cut via Ctrl-X, copy via Ctrl-C, paste via Ctrl-V, and undo via Ctrl-Z.

Would be nice to provide redo functionality via Ctrl-Y. :-)


Returns

Returns true if an event was handled. Only some of the handled events also cause the perform modification flag to be set as a side-effect.

12.57 seq64::seqkeys Class Reference

This class implements the left side piano of the pattern/sequence editor.

Inheritance diagram for seq64::seqkeys:



Public Member Functions

- seqkeys (sequence &seq, perform &p, Gtk::Adjustment &vadjust)
- Principal constructor.void set_scale (int a_scale)

Sets the musical scale, then resets.

void set_key (int a_key)

Sets the musical key, then resets.

void set_hint_key (int a_key)

Sets a key to grey so that it can serve as a scale hint.

• void set hint state (bool a state)

Sets the hint state to the given value.

Private Member Functions

virtual void force_draw ()

Forces a draw operation on the whole window.

· void draw_area ()

Draws the updated pixmap on the drawable area of the window where the keys' location is hardwired.

void update pixmap ()

Updates the pixmaps to prepare it for the next draw operation.

void convert_y (int a_y, int &a_note)

Takes the screen y coordinate, and returns the note value in the second parameter.

void draw_key (int a_key, bool a_state)

Draws the given key according to the given state.

void change_vert ()

Changes the y offset of the scrolling, and the forces a draw.

· void reset ()

Resetting the keys view updates the pixmap and queues up a draw operation.

• bool is black key (int key) const

Detects a black key.

• void on_realize ()

Implements the on-realize event.

bool on expose event (GdkEventExpose *a ev)

Implements the on-expose event, by drawing on the window.

• bool on button press event (GdkEventButton *a ev)

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *a_ev)

Implements the on-button-release event callback.

bool on_motion_notify_event (GdkEventMotion *a_p0)

Implements the on-motion-notify event handler.

bool on_enter_notify_event (GdkEventCrossing *p0)

Implements the on-enter notification event handler.

bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave notification event handler.

• bool on scroll event (GdkEventScroll *a ev)

Implements the on-scroll-event notification event handler.

• void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocation notification event handler.

Private Attributes

bool m keying

What is this?

Additional Inherited Members

12.57.1 Member Function Documentation

12.57.1.1 void seg64::segkeys::set_hint_state (bool state)

Parameters

state	Provides the value for hinting, where true == on, false == off.
-------	---

```
12.57.1.2 void seq64::seqkeys::force_draw() [private], [virtual]
```

Unlike most other overridden versions of force_draw(), this one does not call the base-class version.

Reimplemented from seq64::gui_drawingarea_gtk2.

```
12.57.1.3 void seq64::seqkeys::draw_key ( int key, bool state ) [private]
```

It accounts for the black keys and the white keys, and for the highlighting of the active key.

Parameters

key	The key to be drawn.
state	How the key is to be drawn, where false == normal, true == grayed. A key is greyed when the mouse
	cursor is at the same vertical location on the piano as the key.

```
12.57.1.4 void seq64::seqkeys::on_realize( ) [private]
```

Call the base-class version and then allocates resources that could not be allocated in the constructor. It connects the change_vert() function and then calls it.

```
12.57.1.5 bool seq64::seqkeys::on_button_press_event( GdkEventButton * ev ) [private]
```

It currently handles only the left button. This button, pressed on the piano keyboard, causes m_keying to be set to true, and the given note to play.

Returns

Always returns true.

```
12.57.1.6 bool seq64::seqkeys::on_button_release_event ( GdkEventButton * ev ) [private]
```

It currently handles only the left button, and only if m_keying is true.

This function is used after pressing on one of the keys on the left-side

Returns

Always returns true. piano keyboard, to make it play, and turns off the playing of the note. Always returns true.

```
12.57.1.7 bool seq64::seqkeys::on_motion_notify_event ( GdkEventMotion * a_p0 ) [private]
```

This allows rolling down the keyboard, playing the notes one-by-one.

Returns

Always returns false.

```
12.57.1.8 bool seq64::seqkeys::on_enter_notify_event( GdkEventCrossing * p0 ) [private]
```

I think this greys the current key.

```
12.57.1.9 bool seq64::seqkeys::on_leave_notify_event( GdkEventCrossing * p0 ) [private]
```

I think this un-greys the current key.

```
12.57.1.10 bool seq64::seqkeys::on_scroll_event( GdkEventScroll * ev ) [private]
```

Note that there is no usage of the modifier keys (e.g. Shift or Ctrl). Compare this function to seqedit::on_scroll_← event().

Parameters

```
ev Provides the direction of the scroll event.
```

Returns

Always returns true.

```
12.57.1.11 void seq64::seqkeys::on_size_allocate ( Gtk::Allocation & all ) [private]
```


Parameters

all Provies the allocation and its width and height.

12.58 seq64::seqmenu Class Reference

This class handles the right-click menu of the sequence slots in the pattern window.

Inheritance diagram for seq64::seqmenu:



Public Member Functions

seqmenu (perform &a_p)

Principal constructor.

virtual ∼segmenu ()

Provides a rote base-class destructor.

int current_seq () const

'Getter' function for member m_current_seq We're changing the name, so that "seq" indicates an integer by (an imperfect) convention.

bool is_modified () const

'Getter' function for member m_modified

Protected Member Functions

• void current_seq (int seq)

'Setter' function for member m_current_seq

void edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence Pass in -1 to disable the edit-sequence number.

• bool is_edit_sequence (int seqnum) const

'Getter' function for member m_edit_sequence Tests the parameter against m_edit_sequence.

void is modified (bool flag)

'Setter' function for member m_modified

sequence * get current sequence () const

'Getter' function for member m_mainperf.get_sequence(current_seq()) This call is used many, many times, and well worth wrapping.

• sequence * get_sequence (int seqnum) const

Forwards the get-sequence call to the perform object.

• bool is_current_seq_active () const

Forwards the is-sequence-active check to the perform object.

bool is_current_seq_in_edit () const

Forwards the is-sequence-in-edit check to the perform object.

void new_current_sequence ()

Forwards the new-current-sequence call to the perform object.

void new_sequence (int seqnum)

Forwards the new-sequence call to the perform object.

• void delete_current_sequence ()

Forwards the delete-sequence call to the perform object.

void toggle_current_sequence ()

Forwards the sequence-playing-toggle call to the perform object.

void popup_menu ()

This function sets up the File menu entries.

void seq_edit ()

This menu callback launches the sequence-editor (pattern editor) window.

void seq_event_edit ()

This menu callback launches the new event editor window.

Private Member Functions

void seq_new ()

This function sets the new sequence into the perform object, a bit prematurely, though.

• void seq_copy ()

Copies the selected (current) sequence to the clipboard sequence.

void seq_cut ()

Deletes the selected (current) sequence and copies it to the clipboard sequence, if it is not in edit mode.

void seq paste ()

Pastes the sequence clipboard into the current sequence, if the current sequence slot is not active.

void seq_clear_perf ()

If the current sequence is active, this function pushes a trigger undo in the main perform object, clears its sequence triggers for the current sequence, and sets the dirty flag of the sequence.

void set_bus_and_midi_channel (int a_bus, int a_ch)

Sets up the bus, MIDI channel, and dirtiness flag of the current sequence in the main perform object, as per the give parameters.

void mute_all_tracks ()

Mutes all tracks in the main perform object.

Private Attributes

perform & m_mainperf

Provides a reference to the central object involved in managing a song and performance.

· sequence m clipboard

Holds a copy of data concerning a sequence, which can then be pasted into another pattern slot.

seqedit * m_seqedit

Points to the latest segedit object, if created.

· eventedit * m eventedit

Points to the latest eventedit object, if created.

· int m current seq

References the current sequence by sequence number.

• int m_edit_sequence

Hold the number of the currently-in-edit sequence.

bool m_modified

Indicates if a sequence has been created.

12.58.1 Detailed Description

It is an abstract base class.

12.58.2 Constructor & Destructor Documentation

```
12.58.2.1 seq64::seqmenu::seqmenu ( perform & p )
```

Apart from filling in some of the members, this function initializes the clipboard, so that we don't get a crash on a paste with no previous copy.

```
12.58.2.2 seq64::seqmenu::~seqmenu() [virtual]
```

A rote destructor.

This is necessary in an abstraction base class.

If we determine that we need to delete the m_sequedit pointer, we can do it here. But that is not likely, because we can have many new sequedit objects in play, because we can edit many at once.

12.58.3 Member Function Documentation

```
12.58.3.1 bool seq64::seqmenu::is_edit_sequence ( int seqnum ) const [inline], [protected]
```

Returns true if that member is not -1, and the parameter matches it.

```
12.58.3.2 void seq64::seqmenu::popup_menu( ) [protected]
```

It also sets up the pattern popup menu entries that are used in mainwid. Note that, for the selected sequence, the "Edit" and "Event Edit" menu entries are not included if a pattern editor or event editor is already running. The new event editor seems to create far-reaching problems that we do not yet understand, so it is now possible to disable it at build time. We have mitigated most of those problems by not allowing both a seq_edit() and a seq_event_edit() at the same time.

```
12.58.3.3 void seq64::seqmenu::seq_edit() [protected]
```

If it is already open for that sequence, this function just raises it.

Note that the m_seqedit member to which we save the new pointer is currently there just to avoid a compiler warning.

Also, if a new sequences is created, we set the m_modified flag to true, even though the sequence might later be deleted. Too much modification to keep track of!

An oddity is that calling show all() here does not work unless the seqedit() constructor makes its show all() call.

```
12.58.3.4 void seq64::seqmenu::seq_event_edit( ) [protected]
```

If it is already open for that sequence, this function just raises it.

Note that the m_eventedit member to which we save the new pointer is currently there just to avoid a compiler warning.

This menu entry is available only if the selected sequence is active. That is, if the sequence has already been created.

An oddity is that we need the show_all() call here in order to see the dialog. A situation different from that for sequent! However, now it doesn't seem to be needed, and we have put it back into the eventedit constructor.

```
12.58.3.5 void seq64::seqmenu::seq_new( ) [private]
```

For one thing, if current_seq() is either a -1 or is greater than the maximum allowed sequence number, perform ::is_active() will return false, and we have no idea whether the sequence is not active or the sequence number is just invalid. So we need to check the pointer we got before trying to use it.

```
12.58.3.6 void seq64::seqmenu::seq_copy( ) [private]
```

We use a more appropriate function than operator =() here: sequence::partial_assign().

Todo Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

```
12.58.3.7 void seq64::seqmenu::seq_cut( ) [private]
```

Todo A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

```
12.58.3.8 void seq64::seqmenu::seq_paste( ) [private]
```

Then it sets the dirty flag for the destination sequence.

Todo All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

```
12.58.3.9 void seq64::seqmenu::seq_clear_perf( ) [private]
```

Todo All of seq_paste() can be offloaded to a (new) perform member function.

12.58.4 Field Documentation

```
12.58.4.1 seqedit* seq64::seqmenu::m_seqedit [private]
```

Change Note Added by Chris on 2015-08-02 based on compiler warnings and a comment warning in the seq_edit() function. We'll save the result of that function here, and will let valgrind tell us later if Gtkmm takes care of it.


```
12.58.4.2 bool seq64::seqmenu::m_modified [private]
```

Todo We need to make sure that the perform object is in control of the modification flag.

12.59 seq64::seqroll Class Reference

Implements the piano roll section of the pattern editor.

Inheritance diagram for seq64::seqroll:



Public Member Functions

• seqroll (perform &perf, sequence &seq, int zoom, int snap, seqkeys &seqkeys_wid, int pos, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

∼seqroll ()

Provides a destructor to delete allocated objects.

void set_snap (int snap)

Sets the snap to the given value, and then resets the view.

void set_zoom (int zoom)

Sets the zoom to the given value, and then resets the view.

void set note length (int note length)

'Setter' function for member m_note_length

void set_ignore_redraw (bool ignore)

'Setter' function for member m_ignore_redraw

void set_key (int key)

Sets the music key to the given value, and then resets the view.

void set_scale (int scale)

Sets the music scale to the given value, and then resets the view.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

void set_background_sequence (bool state, int seq)

This function sets the given sequence onto the piano roll of the pattern editor, so that the musician can have another pattern to play against.

void update_pixmap ()

This function draws the background pixmap on the main pixmap, and then draws the events on it.

void update_sizes ()

Update the sizes of items based on zoom, PPQN, BPM, BW (beat width) and more.

void update_background ()

Updates the background of this window.

void draw_background_on_pixmap ()

Draws the main pixmap.

void draw_events_on_pixmap ()

Fills the main pixmap with events.

void draw_selection_on_window ()

Draws the current selecton on the main window.

void draw_progress_on_window ()

Draw a progress line on the window.

void reset ()

This function basically resets the whole widget as if it were realized again.

• void update_and_draw (int force=false)

Wraps up some common code.

• void redraw ()

Redraws unless m_ignore_redraw is true.

• void redraw_events ()

Redraws events unless m_ignore_redraw is true.

void start paste ()

Starts a paste operation.

void follow_progress ()

Checks the position of the tick, and, if it is in a different piano-roll "page" than the last page, moves the page to the next page.

Private Member Functions

• virtual void force draw ()

Set the pixmap into the window and then draws the selection on it.

void horizontal_adjust (double step)

This function provides optimization for the on scroll event() function.

void snap_y (int &y)

Snaps the y value to the piano-key "height".

void snap_x (int &x)

Performs a 'snap' operation on the x coordinate.

void convert_tn (midipulse ticks, int note, int &x, int &y)

This function takes the given note and tick, and returns the screen coordinates via the pointer parameters.

void xy to rect (int x1, int y1, int x2, int y2, int &x, int &y, int &w, int &h)

Converts rectangle corner coordinates to a starting coordinate, plus a width and height.

• void convert_tn_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l, int &x, int &y, int &w, int &h)

Converts a tick/note box to an x/y rectangle.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

Draws events on the given drawable area.

• int idle redraw ()

Draw the events on the main window and on the pixmap.

• void change_horz ()

Change the horizontal scrolling offset and redraw.

void change_vert ()

Change the vertical scrolling offset and redraw.

· void on realize ()

Implements the on-realize event handling.

• bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event handling.

bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event handling.

bool on_button_release_event (GdkEventButton *ev)

Implements the on-button-release event handling.

bool on_motion_notify_event (GdkEventMotion *ev)

Implements the on-motion-notify event handling.

bool on_focus_in_event (GdkEventFocus *)

Implements the on-focus event handling.

bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

bool on_key_press_event (GdkEventKey *ev)

Implements the on-key-press event handling.

• bool on_scroll_event (GdkEventScroll *a_ev)

Implements the on-scroll event handling.

• void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event handling.

bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave-notify event handling.

bool on_enter_notify_event (GdkEventCrossing *p0)

Implements the on-enter-notify event handling.

Private Attributes

• Gtk::Adjustment & m_horizontal_adjust

We need direct access to the horizontal scrollbar if we want to be able to make it follow the progress bar.

FruitySeqRollInput m_fruity_interaction

Provides a fruity input object, whether it is needed or not.

• Seq24SeqRollInput m_seq24_interaction

Provides a normal seq24 input object, which is always needed to handle, for example, keystroke input.

• int m_pos

A position value.

• int m_zoom

one pixel == m_zoom ticks*

• midibyte m_status

Indicates what is the data window currently editing.

· bool m_selecting

When highlighting a bunch of events.

int m_move_delta_x

Tells where the dragging started.

• int m_scroll_page

Provides the current scroll page in which the progress bar resides.

Friends

· class FruitySeqRollInput

These friend implement interaction-specific behavior, although only the Seq24 interactions support keyboard processing.

Additional Inherited Members

12.59.1 Constructor & Destructor Documentation

12.59.1.1 seq64::seqroll::seqroll (perform & p, sequence & seq, int zoom, int snap, seqkeys & seqkeys_wid, int pos, Gtk::Adjustment & hadjust, Gtk::Adjustment & vadjust, int ppqn = SEQ64 USE DEFAULT PPQN)

Parameters

р	The performance object that helps control this piano roll. Note that we can get the perform object from the sequence, and save a parameter. Low priority change.	
seq	seq The sequence object represented by this piano roll.	
zoom	The initial zoom of this piano roll.	
snap	The initial grid snap of this piano roll.	
seqkeys_wid	A reference to the piano keys window that is shown to the left of this piano roll.	
pos	A position parameter. See the description of seqroll::m_pos . This is actually the sequence number, and is currently unused. However, we're sure we can find a use for it sometime.	
hadjust	Represents the horizontal scrollbar of this window. It is actually created by the "parent" sequential object.	
vadjust	Represents the vertical scrollbar of this window. It is actually created by the "parent" sequential object.	
ppqn	The initial value of the PPQN for this sequence. Useful in scale calculations.	

12.59.1.2 seq64::seqroll::∼seqroll ()

The only thing to delete here is the clipboard.

12.59.2 Member Function Documentation

12.59.2.1 void seq64::seqroll::set_zoom (int zoom)

Parameters

12.59.2.2 void seq64::seqroll::set_key (int key)

Parameters

key	The desired key value.
-----	------------------------

12.59.2.3 void seq64::seqroll::set_scale (int scale)

Parameters

scale The desired sc	ale value.
----------------------	------------

12.59.2.4 void seq64::seqroll::set_data_type (midibyte status, midibyte control)

Unlike the same function in seqevent, this version does not redraw.

12.59.2.5 void seq64::seqroll::set_background_sequence (bool state, int seq)

The state parameter sets the boolean m_drawing_background_seq.

Parameters

state	If true, the background sequence will be drawn.
seq	Provides the sequence number, which is checked against the SEQ64_IS_LEGAL_SEQUENCE() macro before being used. This macro allows the value SEQ64_SEQUENCE_LIMIT, which disables the
	background sequence.

12.59.2.6 void seq64::seqroll::update_sizes ()

It brings the scrollbar back to the beginning, resets the upper limit to the number of ticks in the sequence, sets the page-size based on the window size and the zoom factor.

The horizontal step increment is 1 semiquaver (1/16) note per zoom level. The horizontal page increment is currently always one bar. We may want to make that larger for scrolling after the progress bar.

Tha maximum value set for the scrollbar brings it to the last "page" of the piano roll.

The vertical size are also adjusted. More on the story later.

```
12.59.2.7 void seq64::seqroll::update_background()
```

The first thing done is to clear the background, painting it white.

```
12.59.2.8 void seq64::seqroll::draw_events_on_pixmap( )
```

Just calls draw events on().

```
12.59.2.9 void seq64::seqroll::draw_progress_on_window()
```

This is done by first blanking out the line with the background, which contains white space and grey lines, using the the draw_drawable function. Remember that we wrap the draw_drawable() function so it's parameters are xsrc, ysrc, xdest, ydest, width, and height.

Note that the progress-bar position is based on the sequence::get_last_tick() value, the current zoom, and the current scroll-offset x value.

```
12.59.2.10 void seq64::seqroll::reset ( )
```

It's almost identical to the change horz() function, just calling update sizes() before update and draw().

```
12.59.2.11 void seq64::seqroll::update_and_draw ( int force = false )
```

Parameters

force If true, force an immediate draw, otherwise just queue up a draw.

```
12.59.2.12 void seq64::seqroll::redraw ( )
```

Somewhat similar to seqevent::redraw().

```
12.59.2.13 void seq64::seqroll::follow_progress ( )
```

We don't want to do any of this if the length of the sequence fits in the window, but for now it doesn't hurt; the progress bar just never meets the criterion for moving to the next page.

Todo

- If playback is disabled (such as by a trigger), then do not update the page;
- When it comes back, make sure we're on the correct page;
- · When it stops, put the window back to the beginning, even if the beginning is not defined as "0".

12.59.2.14 void seq64::seqroll::horizontal_adjust(double step) [inline], [private]

A duplicate of the one in seqedit.

Parameters

step Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_adjust() for more information.

12.59.2.15 void seq64::seqroll::snap_y(int & y) [inline],[private]

Parameters

```
y The y-value to be snapped.
```

12.59.2.16 void seq64::seqroll::snap_x (int & x) [private]

This function is similar to snap_y(), but it calculates a modulo value from the snap and zoom settings.

```
- m_snap = number pulses to snap to
- m_zoom = number of pulses per pixel
```

Therefore, m_snap / m_zoom = number pixels to snap to.

12.59.2.17 void seq64::seqroll::convert_tn(midipulse ticks, int note, int & x, int & y) [private]

This function is the "inverse" of convert_xy().

Parameters

tick Provides the horizontal value in MIDI pulses.		
note	Provides the vertical value, a note value.	
Х	x Provides the destination x value of the coordinate.	
У	Provides the destination y value of the coordinate.	

12.59.2.18 void seq64::seqroll::xy_to_rect(int x1, int y1, int x2, int & x, int & y, int & w, int & h) [private]

This function checks the mins / maxes, and then fills in the x, y, width, and height values.

12.59.2.19 void seq64::seqroll::draw_events_on(Glib::RefPtr< Gdk::Drawable > draw) [private]

"Method 0" seems be the one that draws the background sequence, if active. "Method 1" draws the sequence itself.

```
12.59.2.20 void seq64::seqroll::change_horz( ) [private]
```

Roughly similar to seqevent::change_horz().

```
12.59.2.21 bool seq64::seqroll::on_key_press_event ( GdkEventKey * ev ) [private]
```

The start/end key may be the same key (i.e. SPACEBAR). Allow toggling when the same key is mapped to both triggers (i.e. SPACEBAR).

Concerning the usage of the arrow keys in this function: This code is reached, but has no visible effect. Why? I think they were meant to move the point for playback. We may HAVE A BUG with our new handling of triggers, or maybe these depend upon the proper playback mode. In any case, the old functionality is preserved. However, if there are notes selected, then these keys support selection movement.

```
12.59.2.22 bool seq64::seqroll::on_scroll_event( GdkEventScroll * ev ) [private]
```

This scroll event only handles basic scrolling without any modifier keys such as SEQ64_CONTROL_MASK or S← EQ64_SHIFT_MASK. The seqedit class handles that fun stuff.

Note that this function seems to duplicate the functionality of seqkeys::on_scroll_event(). Do we really need both?
Which one do we need?

12.59.3 Field Documentation

```
12.59.3.1 int seq64::seqroll::m_pos [private]
```

Need to clarify what exactly this member is used for.

12.60 seg64::segtime Class Reference

This class implements the piano time, whatever that is.

Inheritance diagram for seq64::seqtime:



Public Member Functions

seqtime (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFA
 ULT_PPQN)

Principal constructor.

• void reset ()

Sets the scroll offset tick and x values, updates the sizes and the pixmap, and resets the window.

```
    void redraw ()
```

Very similar to the reset() function, except it doesn't update the sizes.

void set zoom (int zoom)

Sets the zoom to the given value and resets the window.

Private Member Functions

• void draw_pixmap_on_window ()

Draws the pixmap on the window.

void update_pixmap ()

Updates the pixmap.

void change_horz ()

Changes the scrolling horizontal offset, updates the pixmap, and forces a redraw.

void update_sizes ()

Updates the pixmap to a new size and queues up a draw operation.

• bool idle_progress ()

Simply returns true.

• void on_realize ()

Called when the window is drawn.

bool on_expose_event (GdkEventExpose *a_ev)

Implements the on-expose event handler.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event handler.

bool on_button_press_event (GdkEventButton *)

Implements the on-button-press event handler.

bool on_button_release_event (GdkEventButton *)

Implements the on-button-release event handler.

Private Attributes

```
int m_zoomone pixel == m_zoom ticks
```

Additional Inherited Members

12.60.1 Constructor & Destructor Documentation

```
12.60.1.1 seq64::seqtime::seqtime ( sequence & seq, perform & p, int zoom, Gtk::Adjustment & hadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

In the constructor you can only allocate colors; get_window() returns 0 because the window is not yet realized>

12.60.2 Member Function Documentation

```
12.60.2.1 void seq64::seqtime::reset ( )
```

Basically identical to seqevent::reset().

```
12.60.2.2 void seq64::seqtime::update_pixmap( ) [private]
```

When the zoom is at 32 ticks per pixel, there is a thick bar for every measure, and a measure number and major time division every 4 measures.at the default PPQN of 192.

A major line is a line that has a measure number in the timeline. The number of measures in a major line is 1 for zooms from 1:1 to 1:8; 2 for zoom 1:16; 4 for zoom 1:32; 8 for zoom 1:64 (new); and 16 for zoom 1:128. Zooms 1:64 and above look good only for high PPQN values.

We calculate the measure length in 32nd notes. This value is, of course, 32, when the time signature is 4/4. Then calculate measures/line. "measures_per_major" is more like "measures per major line". With a higher zoom than 32, this calculation yields a floating-point exception if m_zoom

32, so we rearrange the calculation and hope that it still works out the

same for smaller values.

Todo Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

```
12.60.2.3 void seq64::seqtime::on_realize( ) [private]
```

Call the base-class version of this function first. Then addition resources are allocated.

```
12.60.2.4 bool seq64::seqtime::on_button_press_event ( GdkEventButton * ) [inline], [private]
```

Simply returns false.

```
12.60.2.5 bool seq64::seqtime::on_button_release_event( GdkEventButton * ) [inline], [private]
```

Simply returns false.

12.61 seq64::sequence Class Reference

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

Public Types

Public Member Functions

sequence (int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

∼sequence ()

A rote destructor.

void partial_assign (const sequence &rhs)

A cut-down version of principal assignment operator.

event list & events ()

'Getter' function for member m_events

• const event_list & events () const

'Getter' function for member m events

· bool any selected notes () const

'Getter' function for member m_events.any_selected_notes()

triggers::List & triggerlist ()

'Getter' function for member m_triggers

• int number () const

'Getter' function for member m_seq_number

void number (int segnum)

'Setter' function for member m_seq_number This setter will set the sequence number only if it has not already been set

• int event_count () const

Returns the number of events stored in m_events.

• void push undo ()

Pushes the event-list into the undo-list.

• void pop_undo ()

If there are items on the undo list, this function pushes the event-list into the redo-list, puts the top of the undo-list into the event-list, pops from the undo-list, calls verify_and_link(), and then calls unselect.

void pop_redo ()

If there are items on the redo list, this function pushes the event-list into the undo-list, puts the top of the redo-list into the event-list, pops from the redo-list, calls verify_and_link(), and then calls unselect.

void push_trigger_undo ()

Calls triggers::push_undo() with locking.

void pop_trigger_undo ()

Calls triggers::pop_undo() with locking.

void set_name (const std::string &name)

Sets the sequence name member, m_name.

void set_name (char *name)

Sets the sequence name member, m_name.

int get_ppqn () const

'Getter' function for member m_ppqn Provided as a convenience for the editable_events class.

void set_beats_per_bar (int beatspermeasure)

'Setter' function for member m_time_beats_per_measure

• int get_beats_per_bar () const

'Getter' function for member m_time_beats_per_measure

void set_beat_width (int beatwidth)

'Setter' function for member m_time_beat_width

int get_beat_width () const

'Getter' function for member m_time_beat_width

void clocks_per_metronome (int cpm)

'Setter' function for member m_clocks_per_metronome

• int clocks_per_metronome () const

'Getter' function for member m_clocks_per_metronome

void set_32nds_per_quarter (int tpq)

'Setter' function for member m_32nds_per_quarter

• int get_32nds_per_quarter () const

'Getter' function for member m_32nds_per_quarter

void us_per_quarter_note (int upqn)

'Setter' function for member m_us_per_quarter_note

• int us_per_quarter_note () const

'Getter' function for member m_us_per_quarter_note

void set_rec_vol (int rec_vol)

'Setter' function for member m_rec_vol

void set_song_mute (bool mute)

'Setter' function for member m_song_mute

• bool get_song_mute () const

'Getter' function for member m_song_mute

• const char * get_name () const

'Getter' function for member m_name pointer

· const std::string & name () const

'Getter' function for member m name

void set_editing (bool edit)

'Setter' function for member m_editing

bool get_editing () const

'Getter' function for member m_editing

void set_raise (bool edit)

'Setter' function for member m_raise

· bool get_raise (void) const

'Getter' function for member m_raise

void set_length (midipulse len, bool adjust_triggers=true)

Sets the length (m length) and adjusts triggers for it, if desired.

· midipulse get_length () const

'Getter' function for member m_length

midipulse get_last_tick ()

Returns the last tick played, and is used by the editor's idle function.

void set_last_tick (midipulse tick)

'Setter' function for member m_last_tick This function used to be called "set_orig_tick()", now renamed to match up with get_last_tick().

midipulse mod_last_tick ()

Some MIDI file errors and other things can lead to an m_length of 0, which causes arithmetic errors when m_last_tick is modded against it.

void set_playing (bool)

Sets the playing state of this sequence.

• bool get_playing () const

'Getter' function for member m_playing

void toggle_playing ()

Toggles the playing status of this sequence.

• void toggle queued ()

'Setter' function for member m_queued and m_queued_tick

• void off_queued ()

'Setter' function for member m_queued

bool get_queued () const

'Getter' function for member m_queued

· midipulse get queued tick () const

'Getter' function for member m_queued_tick

bool check_queued_tick (midipulse tick) const

Helper function for perform.

void set recording (bool)

'Setter' function for member m_recording and m_notes_on

• bool get_recording () const

'Getter' function for member m recording

void set_snap_tick (int st)

'Setter' function for member m_snap_tick

void set_quantized_rec (bool qr)

'Setter' function for member m_quantized_rec

bool get_quantized_rec () const

'Getter' function for member m_quantized_rec

void set_thru (bool)

'Setter' function for member m_thru

• bool get thru () const

'Getter' function for member m_thru

bool is_dirty_main ()

Returns the value of the dirty main flag, and sets that flag to false (i.e.

bool is_dirty_edit ()

Returns the value of the dirty edit flag, and sets that flag to false.

bool is_dirty_perf ()

Returns the value of the dirty performance flag, and sets that flag to false.

bool is_dirty_names ()

Returns the value of the dirty names (heh heh) flag, and sets that flag to false.

void set dirty mp ()

Sets the dirty flags for names, main, and performance.

• void set dirty ()

Call set_dirty_mp() and then sets the dirty flag for editing.

• midibyte get_midi_channel () const

 ${\it 'Getter' function for member m_midi_channel}$

bool is_smf_0 () const

Returns true if this sequence is an SMF 0 sequence.

void set_midi_channel (midibyte ch)

Sets the m_midi_channel number.

void print () const

Prints a list of the currently-held events.

• void print_triggers () const

Prints a list of the currently-held triggers.

void play (midipulse tick, bool playback_mode)

The play() function dumps notes starting from the given tick, and it pre-buffers ahead.

bool add_event (const event &er)

Adds an event to the internal event list in a sorted manner.

• void add_trigger (midipulse tick, midipulse len, midipulse offset=0, bool adjust_offset=true)

Adds a trigger.

void split_trigger (midipulse tick)

Splits a trigger.

void grow_trigger (midipulse tick_from, midipulse tick_to, midipulse len)

Grows a trigger.

void del trigger (midipulse tick)

Deletes a trigger, that brackets the given tick, from the trigger-list.

bool get_trigger_state (midipulse tick)

Checks the list of triggers against the given tick.

bool select trigger (midipulse tick)

Checks the list of triggers against the given tick.

• bool unselect_triggers ()

Unselects all triggers.

bool intersect triggers (midipulse position, midipulse &start, midipulse &ender)

This function examines each trigger in the trigger list.

bool intersect_notes (midipulse position, midipulse position_note, midipulse &start, midipulse &ender, int ¬e)

This function examines each note in the event list.

• bool intersect_events (midipulse posstart, midipulse posend, midibyte status, midipulse &start)

This function examines each non-note event in the event list.

void del_selected_trigger ()

Deletes the first selected trigger that is found.

void cut_selected_trigger ()

Copies and deletes the first selected trigger that is found.

• void copy_selected_trigger ()

Copies the first selected trigger that is found.

void paste trigger ()

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

• bool move_selected_triggers_to (midipulse tick, bool adjust_offset, int which=2)

Moves selected triggers as per the given parameters.

• midipulse selected_trigger_start ()

Gets the last-selected trigger's start tick.

midipulse selected_trigger_end ()

Gets the selected trigger's end tick.

midipulse get_max_trigger ()

Get the ending value of the last trigger in the trigger-list.

· void move_triggers (midipulse start_tick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

void copy_triggers (midipulse start_tick, midipulse distance)

Copies triggers to...

• void clear triggers ()

Clears the whole list of triggers.

midipulse get_trigger_offset () const

'Getter' function for member m_trigger_offset

void set midi bus (char mb)

Sets the midibus number to dump to.

· char get_midi_bus () const

'Getter' function for member m_bus

void set_master_midi_bus (mastermidibus *mmb)

'Setter' function for member m_masterbus

• int select note events (midipulse tick s, int note h, midipulse tick f, int note l, select action e action)

This function selects events in range of tick start, note high, tick end, and note low.

• int select events (midipulse tick s, midipulse tick f, midibyte status, midibyte cc, select action e action)

Select all events in the given range, and returns the number selected.

• int select_events (midibyte status, midibyte cc, bool inverse=false)

Select all events with the given status, and returns the number selected.

• int get num selected notes () const

Counts the selected notes in the event list.

int get_num_selected_events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

• void select all ()

Selects all events, unconditionally.

void copy_selected ()

Copies the selected events.

void cut selected (bool copyevents=true)

Cuts the selected events.

void paste_selected (midipulse tick, int note)

Pastes the selected notes (and only note events) at the given tick and the given note value.

void get_selected_box (midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)

Returns the 'box' of the selected items.

void get_clipboard_box (midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)

Returns the 'box' of the clipboard items.

void move selected notes (midipulse deltatick, int deltanote)

Removes and adds reads selected in position.

void add note (midipulse tick, midipulse len, int note, bool paint=false)

Adds a note of a given length and note value, at a given tick location.

• void add event (midipulse tick, midibyte status, midibyte d0, midibyte d1, bool paint=false)

Adds a event of a given status value and data values, at a given tick location.

void stream_event (event &ev)

Streams the given event.

• bool change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int d_s, int d f)

Changes the event data range.

void increment_selected (midibyte status, midibyte control)

Increments events the match the given status and control values.

void decrement_selected (midibyte status, midibyte control)

Decrements events the match the given status and control values.

void grow_selected (midipulse deltatick)

Moves note off event.

void stretch_selected (midipulse deltatick)

Performs a stretch operation on the selected events.

· void remove marked ()

Removes marked events.

void mark_selected ()

Marks the selected events.

void unpaint all ()

Unpaints all events in the event-list.

• void unselect ()

Deselects all events, unconditionally.

void verify_and_link ()

This function verifies state: all note-ons have an off, and it links note-offs with their note-ons.

• void link new ()

Links a new event.

• void zero markers ()

Resets everything to zero.

void play_note_on (int note)

Plays a note from the piano roll on the main bus on the master MIDI buss.

void play_note_off (int note)

Turns off a note from the piano roll on the main bus on the master MIDI buss.

void off_playing_notes ()

Sends a note-off event for all active notes.

• void pause ()

EXPERIMENTAL.

· void reset (bool live mode)

Provides a helper function simplify and speed up perform::reset_sequences().

void reset draw marker ()

This refreshes the play marker to the last tick.

· void reset_draw_trigger_marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

draw_type get_next_note_event (midipulse *tick_s, midipulse *tick_f, int *note, bool *selected, int *velocity)

Each call to seqdata() fills the passed references with a events elements, and returns true.

• bool get minmax note events (int &lowest, int &highest)

A new function provided so that we can find the minimum and maximum notes with only one (not two) traversal of the event list.

bool get_next_event (midibyte status, midibyte cc, midipulse *tick, midibyte *d0, midibyte *d1, bool *selected)

Get the next event in the event list that matches the given status and control character.

bool get_next_event (midibyte *status, midibyte *cc)

Get the next event in the event list.

bool get next trigger (midipulse *tick on, midipulse *tick off, bool *selected, midipulse *tick offset)

Get the next trigger in the trigger list, and set the parameters based on that trigger.

void fill_container (midi_container &c, int tracknumber)

This function fills the given character list with MIDI data from the current sequence, preparatory to writing it to a file.

void quantize events (midibyte status, midibyte cc, midipulse snap tick, int divide, bool linked=false)

Not deleting the ends, not selected.

• void transpose_notes (int steps, int scale)

Transposes notes by the given steps, in accordance with the given scale.

• midibyte musical_key () const

'Getter' function for member m_musical_key

void musical_key (int key)

'Setter' function for member m_musical_key

• midibyte musical_scale () const

'Getter' function for member m_musical_scale

· void musical scale (int scale)

'Setter' function for member m_musical_scale

• int background_sequence () const

'Getter' function for member m_background_sequence

· void background sequence (int bs)

'Setter' function for member m_background_sequence Only partial validation at present, we do not want the upper limit to be hard-wired at this time.

void show_events () const

A member function to dump a summary of events stored in the event-list of a sequence.

void copy_events (const event_list &newevents)

Copies an external container of events into the current container, effectively replacing all of its events.

Private Member Functions

void set_parent (perform *p)

'Setter' function for member m_parent Sets the "parent" of this sequence, so that it can get some extra information about the performance.

void put event on bus (event &ev)

Takes an event that this sequence is holding, and places it on the MIDI buss.

void set_trigger_offset (midipulse trigger_offset)

Sets m trigger offset and wraps it to m length.

void split_trigger (trigger &trig, midipulse splittick)

Splits the trigger given by the parameter into two triggers.

void adjust_trigger_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length of ???, for all triggers, and undo triggers.

void remove (event list::iterator i)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

· void remove (event &e)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

· void remove all ()

Clears all events from the event container.

Private Attributes

perform * m_parent

For pause support, we need a way for the sequence to find out if JACK transport is active.

event_list m_events

This list holds the current pattern/sequence events.

midibyte m_midi_channel

Contains the proper MIDI channel for this sequence.

• midibyte m_bus

Contains the proper MIDI bus number for this sequence.

· bool m_song_mute

Provides a flag for the song playback mode muting.

• int m_notes_on

Provides a member to hold the polyphonic step-edit note counter.

mastermidibus * m_masterbus

Provides the master MIDI buss which handles the output of the sequence to the proper buss and MIDI channel.

• int m_playing_notes [SEQ64_MIDI_NOTES_MAX]

Provides a "map" for Note On events.

bool m_was_playing

Indicates if the sequence was playing.

· bool m_playing

True if sequence playback currently is in progress for this sequence.

bool m_recording

True if sequence recording currently is in progress for this sequence.

bool m_dirty_main

These flags indicate that the content of the sequence has changed due to recording, editing, performance management, or even (?) a name change.

bool m_editing

Indicates that the sequence is currently being edited.

bool m raise

Used in seqmenu and seqedit.

· std::string m_name

Provides the name/title for the sequence.

· midipulse m last tick

These members manage where we are in the playing of this sequence, including triggering.

• const int m_maxbeats

This constant provides ...?

• int m_ppqn

Holds the PPQN value for this sequence, so that we don't have to rely on a global constant value.

• int m_seq_number

A new member so that the sequence number is carried along with the sequence.

• midipulse m_length

Holds the length of the sequence in pulses (ticks).

• midipulse m_snap_tick

The size of snap in units of pulses (ticks).

· int m time beats per measure

Provides the number of beats per bar used in this sequence.

• int m_time_beat_width

Provides with width of a beat.

· int m_clocks_per_metronome

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

int m_32nds_per_quarter

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

• int m_us_per_quarter_note

Augments the beats/bar and beat-width with the additional values included in a Tempo meta event.

• int m_rec_vol

The volume to be used when recording.

midibyte m_musical_key

Holds a copy of the musical key for this sequence, which we now support writing to this sequence.

• midibyte m_musical_scale

Holds a copy of the musical scale for this sequence, which we now support writing to this sequence.

int m_background_sequence

Holds a copy of the background sequence number for this sequence, which we now support writing to this sequence.

• mutex m_mutex

Provides locking for the sequence.

Static Private Attributes

• static event_list m_events_clipboard

A static clipboard for holding pattern/sequence events.

12.61.1 Detailed Description

More members than you can shake a stick at.

12.61.2 Member Enumeration Documentation

12.61.2.1 enum seq64::sequence::select_action_e

Enumerator

e_select This enumeration is used in selecting events and note. Se the select_note_events() and select_← events() functions.

```
To select ...
```

- e_select_one To select ...
- e_is_selected The events are selected ...
- e_would_select The events would be selected ...
- e_deselect To deselect the event under the cursor.
- **e_toggle_selection** To toggle the selection of the event under the cursor.
- e_remove_one To remove one note under the cursor.

12.61.3 Member Function Documentation

12.61.3.1 void seq64::sequence::partial_assign (const sequence & rhs)

We're replacing that incomplete function (many members are not assigned) with the more accurately-named partial_assign() function.

It did not assign them all, so we created this partial_assign() function to do this work, and replaced operator =() with this function in client code.

Threadsafe

```
12.61.3.2 int seq64::sequence::event_count() const

Threadsafe

12.61.3.3 void seq64::sequence::push_undo()

Threadsafe

12.61.3.4 void seq64::sequence::pop_undo()

Threadsafe

12.61.3.5 void seq64::sequence::pop_redo()

Threadsafe

12.61.3.6 void seq64::sequence::push_trigger_undo()

Threadsafe

12.61.3.7 void seq64::sequence::push_trigger_undo()
```

Threadsafe

Parameters

beatspermeasure	The new setting of the beats-per-bar value.	
Dodiepooaca.c	indicate detailing or and beaute per bar value.	ı

12.61.3.8 void seq64::sequence::set_beat_width (int beatwidth)

Threadsafe

Parameters

beatwidth The new setting of the beat width value.

```
12.61.3.9 int seq64::sequence::get_beat_width()const [inline]
```

Threadsafe

```
12.61.3.10 void seq64::sequence::set_rec_vol ( int recvol )
```

Threadsafe

Parameters

```
recvol The new setting of the recording volume setting.
```

```
12.61.3.11 const char* seq64::sequence::get_name( ) const [inline]
```

Deprecated

```
12.61.3.12 void seq64::sequence::set_length ( midipulse len, bool adjust_triggers = true )
```

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks:

```
L = M x B x 4 x P / W
L == length (ticks or pulses)
M == number of measures
B == beats per measure
P == pulses per quarter-note
W == beat width in beats per measure

For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4,
P can be 192 (but we want to support higher values), and W is 4.
So L = 100 * 4 * 4 * 192 / 4 = 76800 ticks. Seems small.
```

Threadsafe

```
12.61.3.13 midipulse seq64::sequence::get_last_tick ( )

If m_length is 0, this function returns m_last_tick - m_trigger_offset, to avoid an arithmetic exception. Should we return 0 instead?

Note that seqroll calls this function to help get the location of the progress bar. What does perfedit do?
```

```
12.61.3.14 void seq64::sequence::set_last_tick ( midipulse tick )
```

Threadsafe

```
12.61.3.15 midipulse seq64::sequence::mod_last_tick( ) [inline]
```

This function replaces the "m_last_tick % m_length", returning m_last_tick if m_length is 0 or 1.

```
12.61.3.16 void seq64::sequence::set_playing (bool p)
```

When playing, and the sequencer is running, notes get dumped to the ALSA buffers.

Parameters

p Provides the playing status to set. True means to turn on the playing, false means to turn it off, and turn off any notes still playing.

```
12.61.3.17 void seq64::sequence::toggle_queued( )
```

Toggles the queued flag and sets the dirty-mp flag. Also calculates the queued tick based on m_last_tick.

Threadsafe

```
12.61.3.18 void seq64::sequence::off_queued()
```

Toggles the queued flag and sets the dirty-mp flag.

Threadsafe

12.61.3.19 void seq64::sequence::set_recording (bool r)

Threadsafe

12.61.3.20 void seq64::sequence::set_snap_tick (int st)

Threadsafe

```
12.61.3.21 void seq64::sequence::set_quantized_rec ( bool qr )
Threadsafe
12.61.3.22 void seq64::sequence::set_thru (bool r)
Threadsafe
12.61.3.23 bool seq64::sequence::is_dirty_main()
resets it). This flag signals that a redraw is needed from recording.
Threadsafe
12.61.3.24 bool seq64::sequence::is_dirty_edit()
Threadsafe
12.61.3.25 bool seq64::sequence::is_dirty_perf()
Threadsafe
12.61.3.26 bool seq64::sequence::is_dirty_names ( )
Threadsafe
12.61.3.27 void seq64::sequence::set_dirty_mp ( )
Not threadsafe
12.61.3.28 void seq64::sequence::set_dirty()
Threadsafe
12.61.3.29 void seq64::sequence::set_midi_channel ( midibyte ch )
Threadsafe
12.61.3.30 void seq64::sequence::print ( ) const
Not threadsafe
```

12.61.3.31 void seq64::sequence::print_triggers () const

Not threadsafe

12.61.3.32 void seq64::sequence::play (midipulse tick, bool playback_mode)

This function is called by the sequencer thread, performance. The tick comes in as global tick.

It turns the sequence off after we play in this frame.

Note

With pause support, the progress bar for the pattern/sequence editor does what we want: pause with the pause button, and rewind with the stop button. Works with JACK, with issues, but we'd like to have the stop button do a rewind in JACK, too.

Parameters

tick	Provides the current end-tick value.
playback_mode	Provides how playback is managed. True indicates that it is performance/song-editor playback, controlled by the set of patterns and triggers set up in that editor, and saved with the song in seq24 format. False indicates that the playback is controlled by the main windows, in live mode.

Threadsafe

12.61.3.33 bool seq64::sequence::add_event (const event & er)

Then it reset the draw-marker and sets the dirty flag.

Currently, when reading a MIDI file [see the midifile::parse() function], only the main events (notes, after-touch, pitch, program changes, etc.) are added with this function. So, we can rely on reading only playable events into a sequence. Well, actually, certain meta-events are also read, to obtain channel, buss, and more settings. Also read for a sequence, if the global-sequence flag is not set, are the new key, scale, and background sequence parameters.

This module (sequencer) adds all of those events as well, but it can surely add other events. We should assume that any events added by sequencer are playable/usable.

Threadsafe

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. Actually, this is true only in Seq24, we've fixed that behavior for Sequencer64.

Parameters

er Provide a reference to the event to be added; the event is copied into the events container.

12.61.3.34 void seq64::sequence::add_trigger (midipulse *tick*, midipulse *len*, midipulse *offset* = 0, bool *fixoffset* = true)

A pass-through function that calls triggers::add().

12.61.3.35 void seq64::sequence::split_trigger (midipulse splittick)

This is the public overload of split_trigger.

Threadsafe

12.61.3.36 void seq64::sequence::grow_trigger (midipulse tickfrom, midipulse tickto, midipulse len)

Parameters

tickfrom	The desired from-value back which to expand the trigger, if necessary.	
tickto	The desired to-value towards which to expand the trigger, if necessary	
len	The additional length to append to tickto for the check.	

Threadsafe

12.61.3.37 void seq64::sequence::del_trigger (midipulse tick)

Threadsafe

12.61.3.38 bool seq64::sequence::get_trigger_state (midipulse tick)

If any trigger is found to bracket that tick, then true is returned.

Parameters

rovides the tick of interest.	tick
-------------------------------	------

Returns

Returns true if a trigger is found that brackets the given tick.

12.61.3.39 bool seq64::sequence::select_trigger (midipulse tick)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

Returns

Returns true if a trigger is found that brackets the given tick.

12.61.3.40 bool seq64::sequence::unselect_triggers ()

Returns

Always returns false.

12.61.3.41 bool seq64::sequence::intersect_triggers (midipulse position, midipulse & start, midipulse & ender)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit.

Threadsafe

Parameters

position	The position to examine.
start	The destination for the starting tick of the matching trigger.
ender	The destination for the ending tick of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.61.3.42 bool seq64::sequence::intersect_notes (midipulse position, midipulse position_note, midipulse & start, midipulse & ender, int & note)

If the given position is between the current notes on and off time values, values, the these values are copied to the start and end parameters, respectively, the note value is copied to the note parameter, and then we exit.

Threadsafe

Parameters

position	The position to examine.
position_note	I think this is the note value we might be looking for ???
start	The destination for the starting timestamp of the matching note.
ender	The destination for the ending timestamp of the matching note.
note	The destination for the note of the matching event. Why is this an int value???

Returns

Returns true if a event was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.61.3.43 bool seq64::sequence::intersect_events (midipulse *posstart*, midipulse *posend*, midibyte *status*, midipulse & *start*)

If the given position is between the current notes's timestamp-start and timestamp-end values, the these values are copied to the posstart and posend parameters, respectively, and then we exit.

Threadsafe

Parameters

posstart	The starting position to examine.
posend	The ending position to examine.
status	The desired status value.
start	The destination for the starting timestamp of the matching trigger.

Returns

Returns true if a event was found whose start/end timestamps contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

```
12.61.3.44 void seq64::sequence::paste_trigger ( )
```

Why isn't this protected by a mutex? We will eventually enable this if anything bad happens, such as a deadlock, or corruption.

12.61.3.45 bool seq64::sequence::move_selected_triggers_to (midipulse tick, bool adjustoffset, int which = 2)

```
min_tick][0 1][max_tick
```

The \a which parameter has three possible values:

```
-# If we are moving the 0, use first as offset.
-# If we are moving the 1, use the last as the offset.
-# If we are moving both (2), use first as offset.
```

Threadsafe

Parameters

tick	The tick at which the trigger starts.
adjustoffset	Set to true if the offset is to be adjusted.
which	Selects which movement will be done, as discussed above.

Returns

Returns the value of triggers::move_selected(), which indicate that the movement could be made. Used in Seq24PerfInput::handle_motion_key().

```
12.61.3.46 midipulse seq64::sequence::selected_trigger_start( )
Threadsafe
Returns
      Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then -1 is returned.
12.61.3.47 midipulse seq64::sequence::selected_trigger_end()
Threadsafe
12.61.3.48 midipulse seq64::sequence::get_max_trigger()
Threadsafe
12.61.3.49 void seq64::sequence::move_triggers ( midipulse starttick, midipulse distance, bool direction )
Note the dependence on the m_length member being kept in sync with the parent's value of m_length.
Threadsafe
12.61.3.50 void seq64::sequence::copy_triggers ( midipulse starttick, midipulse distance )
Threadsafe
12.61.3.51 void seq64::sequence::clear_triggers ( )
Threadsafe
12.61.3.52 void seq64::sequence::set_midi_bus ( char mb )
Threadsafe
12.61.3.53 void seq64::sequence::set_master_midi_bus ( mastermidibus * mmb )
Threadsafe
Parameters
 mmb
          Provides a pointer to the master MIDI buss for this sequence. This should be a reference.
```

12.61.3.54 int seq64::sequence::select_note_events (midipulse a_tick_s, int a_note_h, midipulse a_tick_f, int a_note_l, select_action_e a_action)

Returns the number selected.

Threadsafe

12.61.3.55 int seq64::sequence::select_events (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)

Note that there is also an overloaded version of this function.

Threadsafe

12.61.3.56 int seq64::sequence::select_events (midibyte status, midibyte cc, bool inverse = false)

Note that there is also an overloaded version of this function.

Threadsafe

Warning

This used to be a void function, so it just returns 0 for now.

Parameters

status	Provides the status value to be selected.
СС	If the status is EVENT_CONTROL_CHANGE, then data byte 0 must match this value.
inverse	If true, invert the selection.

Returns

Always returns 0.

12.61.3.57 int seq64::sequence::get_num_selected_notes () const

Threadsafe

12.61.3.58 int seq64::sequence::get_num_selected_events (midibyte status, midibyte cc) const

If the event is a control change (CC), then it must also match the given CC value.

Threadsafe

12.61.3.59 void seq64::sequence::select_all()

Threadsafe

12.61.3.60 void seq64::sequence::copy_selected()

Threadsafe

12.61.3.61 void seq64::sequence::cut_selected (bool copyevents = true)

Threadsafe

12.61.3.62 void seq64::sequence::paste_selected (midipulse tick, int note)

I wonder if we can get away with just getting a reference to m_events_clipboard, rather than copying the whole thing, for speed.

Threadsafe

12.61.3.63 void seq64::sequence::get_selected_box (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l)

Note the common-code betweem this function and get_clipboard_box().

Threadsafe

12.61.3.64 void seq64::sequence::get_clipboard_box (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l)

Note the common-code betweem this function and get_selected_box().

Threadsafe

12.61.3.65 void seq64::sequence::move_selected_notes (midipulse delta_tick, int delta_note)

Parameters

delta_ticl	(Provides the amount of time to move the selected notes.
delta_no	e	Provides the amount of pitch to move the selected notes.

12.61.3.66 void seq64::sequence::add_note (midipulse tick, midipulse length, int note, bool paint = false)

It adds a single note-on / note-off pair.

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Threadsafe

12.61.3.67 void seq64::sequence::add_event (midipulse *tick*, midibyte *status*, midibyte *d0*, midibyte *d1*, bool *paint* = false)

The a_paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Threadsafe

12.61.3.68 void seq64::sequence::stream_event (event & ev)

Threadsafe

12.61.3.69 bool seq64::sequence::change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int data_s, int data_f)

Changes only selected events, if any.

Threadsafe

Let t == the current tick value; t == tick start value; t == tick finish value; t == tic

Then

If this were an interpolation formula it would be:

Something is not quite right; to be investigated.

Parameters

tick⇔	Provides the starting tick value.
_s	
tick⊷	Provides the ending tick value.
_f	
status	Provides the event status that is to be changed.
СС	Provides the event control value.
data⊷	Provides the starting data value.
_s	
data⊷	Provides the finishing data value.
_f	

Returns

Returns true if the data was changed.

12.61.3.70 void seq64::sequence::increment_selected (midibyte astat, midibyte control)

The supported statuses are:

- EVENT_NOTE_ON
- EVENT_NOTE_OFF
- EVENT_AFTERTOUCH
- EVENT_CONTROL_CHANGE EVENT_PITCH_WHEEL
- EVENT_PROGRAM_CHANGE
- EVENT_CHANNEL_PRESSURE

Threadsafe

12.61.3.71 void seq64::sequence::decrement_selected (midibyte astat, midibyte control)

The supported statuses are:

- · One-byte messages
 - EVENT_PROGRAM_CHANGE
 - EVENT_CHANNEL_PRESSURE
- · Two-byte messages
 - EVENT_NOTE_ON
 - EVENT_NOTE_OFF
 - EVENT_AFTERTOUCH
 - EVENT CONTROL CHANGE
 - EVENT_PITCH_WHEEL

Threadsafe

12.61.3.72 void seq64::sequence::grow_selected (midipulse delta_tick)

If an event is not linked, this function now ignores the event's timestamp, rather than risk a segfault on a null pointer.

Threadsafe

Parameters

delta_tick An offset for each linked event's timestamp.

```
12.61.3.73 void seq64::sequence::stretch_selected ( midipulse delta_tick )
```

This should move a note off event, according to old comments, but it doesn't seem to do that. See the grow_\circ selected() function.

Threadsafe

```
12.61.3.74 void seq64::sequence::remove_marked ( )
```

Note how this function handles removing a value to avoid incrementing a now-invalid iterator.

Threadsafe

```
12.61.3.75 void seq64::sequence::mark_selected ( )
```

Threadsafe

```
12.61.3.76 void seq64::sequence::unpaint_all()
```

Threadsafe

```
12.61.3.77 void seq64::sequence::unselect ( )
```

Threadsafe

```
12.61.3.78 void seq64::sequence::verify_and_link( )
```

Threadsafe

```
12.61.3.79 void seq64::sequence::link_new( )
```

Threadsafe

```
12.61.3.80 void seq64::sequence::zero_markers() [inline]
```

This function is used when the sequencer stops. This function currently sets $m_{act} = 0$, but we would like to avoid that if doing a pause, rather than a stop, of playback. However, commenting out this setting doesn't have any effect that we can see with a quick look at the user-interface.

Parameters

tick Provides the optional tick value to set as "0". It defaults to 0.

```
12.61.3.81 void seq64::sequence::play_note_on ( int a_note )
```

It flushes a note to the midibus to preview its sound, used by the virtual piano.

Threadsafe

```
12.61.3.82 void seq64::sequence::play_note_off ( int a_note )
```

Threadsafe

```
12.61.3.83 void seq64::sequence::off_playing_notes ( )
```

This function does not bother checking if m_masterbus is a null pointer.

Threadsafe

```
12.61.3.84 void seq64::sequence::pause ( )
```

A pause version of reset(). The reset() function is currently not called when pausing, but we still need the note-shutoff capability to prevent notes from lingering. Not that we do not call set_playing(false)... it disarms the sequence, which we do not want upon pausing.

```
12.61.3.85 void seq64::sequence::reset ( bool live_mode )
```

Note that, in live mode, the user controls playback, while otherwise JACK or the performance/song editor controls playback. (We're still a bit confounded about these modes, alas.)

Parameters

```
live_mode True if live mode is on. This means that JACK transport is not in control of playback.
```

```
12.61.3.86 void seq64::sequence::reset_draw_marker()
```

It resets the draw marker so that calls to get_next_note_event() will start from the first event.

Threadsafe

```
12.61.3.87 void seg64::sequence::reset_draw_trigger_marker()
```

Threadsafe

```
12.61.3.88 draw_type seq64::sequence::get_next_note_event ( midipulse * a_tick_s, midipulse * a_tick_f, int * a_note, bool * a_selected, int * a_velocity )
```

When it has no more events, returns a false.

12.61.3.89 bool seq64::sequence::get_minmax_note_events (int & lowest, int & highest)

Todo For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

Threadsafe

Parameters

lowest	A reference parameter to return the note with the lowest value. if there are no notes, then it is set to SEQ64_MIDI_COUNT_MAX-1.
highest	A reference parameter to return the note with the highest value. if there are no notes, then it is set to -1.

Returns

If there are no notes in the list, then false is returned, and the results should be disregarded.

12.61.3.90 bool seq64::sequence::get_next_event (midibyte status, midibyte cc, midipulse * tick, midibyte * d0, midibyte * d1, bool * selected)

Then set the rest of the parameters parameters using that event. If the status is the new value EVENT_ANY, then any event will be obtained.

Note the usage of event::is_desired_cc_or_not_cc(status, cc, *d0); Either we have a control change with the right CC or it's a different type of event.

Parameters

status	The type of event to be obtained. The special value EVENT_ANY can be provided so that no event statuses are filtered.
СС	The continuous controller value that might be desired.
tick	A pointer return value for the tick value of the next event found.
d0	A pointer return value for the first data value of the event.
d1	A pointer return value for the second data value of the event.
selected	A pointer return value for the is-selected status of the event.

12.61.3.91 bool seq64::sequence::get_next_event (midibyte * a_status, midibyte * a_cc)

Then set the status and control character parameters using that event.

12.61.3.92 void seq64::sequence::fill_container (midi_container & c, int tracknumber)

Note that some of the events might not come out in the same order they were stored in (we see that with program-change events.

С	Provides the std::list object to push events to the front, which thus inserts them in backwards
	order. (These events are then popped back, which restores the order, with some exceptions).
tracknumber	Provides the track number. This number is masked into the track information.

12.61.3.93 void seq64::sequence::transpose_notes (int steps, int scale)

If the scale value is 0, this is "no scale", which is the chromatic scale, where all 12 notes, including sharps and flats, are part of the scale.

12.61.3.94 void seq64::sequence::background_sequence(int bs) [inline]

Disabling the sequence number (setting it to SEQ64_SEQUENCE_LIMIT) is valid.

12.61.3.95 void seq64::sequence::copy_events (const event_list & newevents)

Compare this function to the remove_all() function. Copying the container is a lot of work, but fairly fast, even with an std::multimap as the container.

Threadsafe Note that we had to consolidate the replacement of all the events in the container in order to prevent the "Save to Sequence" button in the eventedit object from causing the application to segfault. It would segfault when the mainwand timer callback would fire, causing updates to the sequence's slot pixmap, which would then try to access deleted events. Part of the issue was that note links were dropped when copying the events, so now we call verify_and_link() to hopefully reconstitute the links.

Parameters

newevents	Provides the container of MIDI events that will completely replace the current container. Normally
	this container is supplied by the event editor, via the eventslots class.

12.61.3.96 void seq64::sequence::set_parent(perform * **p**) [private]

Remember that m_parent is not at all owned by the sequence. We just don't want to do all the work necessary to make it a reference, at this time.

12.61.3.97 void seq64::sequence::put_event_on_bus(event & ev) [private]

This function does not bother checking if m masterbus is a null pointer.

Parameters

ev	The event to put on the buss.

Threadsafe

12.61.3.98 void seq64::sequence::set_trigger_offset (midipulse trigger_offset) [private]

If m_length is 0, then m_trigger_offset is simply set to the parameter.

Threadsafe

Parameters

trigger_offset	The full trigger offset to set.
----------------	---------------------------------

12.61.3.99 void seq64::sequence::split_trigger (trigger & trig, midipulse splittick) [private]

This is the private overload of split trigger.

Threadsafe

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is shortened.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

12.61.3.100 void seq64::sequence::adjust_trigger_offsets_to_length (midipulse newlength) [private]

Threadsafe

Might can get rid of this function?

12.61.3.101 void seq64::sequence::remove(event_list::iterator i) [private]

(And we no longer bother checking the pointer. If it is now, all hope is lost.) If it's a note off, and that note is currently playing, then send a note off. Do we need a flush() call as well?

Not threadsafe

12.61.3.102 void seq64::sequence::remove(event & e) [private]

Finds the given event in m_events, and removes the first iterator matching that.

Not threadsafe

Todo Use find instead in sequence::remove()!

12.61.3.103 void seq64::sequence::remove_all() [private]

Unsets the modified flag. Also see the new copy_events() function.

12.61.4 Field Documentation

```
12.61.4.1 perform* seq64::sequence::m_parent [private]
```

We can use the rc_settings flag(s), but JACK could be disconnected. We could use a reference here, but, to avoid modifying the midifile class as well, we use a pointer. It is set in perform::add_sequence().

```
12.61.4.2 midibyte seq64::sequence::m_midi_channel [private]
```

However, if this value is EVENT_NULL_CHANNEL (0xFF), then this sequence is an SMF 0 track, and has no single channel.

```
12.61.4.3 int seq64::sequence::m_playing_notes[SEQ64_MIDI_NOTES_MAX] [private]
```

It is used when muting, to shut off the notes that are playing.

```
12.61.4.4 bool seq64::sequence::m_raise [private]
```

It allows a sequence editor window to pop up if not already raised, in seqedit::timeout().

```
12.61.4.5 int seq64::sequence::m_seq_number [private]
```

This number is set in the perform::install_sequence() function.

```
12.61.4.6 midipulse seq64::sequence::m_length [private]
```

This value should be a power of two when used as a bar unit.

```
12.61.4.7 midipulse seq64::sequence::m_snap_tick [private]
```

It starts out as the value m ppqn / 4.

```
12.61.4.8 int seq64::sequence::m_time_beats_per_measure [private]
```

Defaults to 4. Used by the sequence editor to mark things in correct time on the user-interface.

```
12.61.4.9 int seq64::sequence::m_time_beat_width [private]
```

Defaults to 4, which means the beat is a quarter note. A value of 8 would mean it is an eighth note. Used by the sequence editor to mark things in correct time on the user-interface.

```
12.61.4.10 int seq64::sequence::m_clocks_per_metronome [private]
```

This value provides the number of MIDI clocks between metronome clicks. The default value of this item is 24. It can also be read from some SMF 1 files, such as our hymne.mid example.

```
12.61.4.11 int seq64::sequence::m_32nds_per_quarter [private]
```

This value provides the number of notated 32nd notes in a MIDI quarter note (24 MIDI clocks). The usual (and default) value of this parameter is 8; some sequencers allow this to be changed.

```
12.61.4.12 int seq64::sequence::m_us_per_quarter_note [private]
```

This value can be extracted from the beats-per-minute value (mastermidibus::m_beats_per_minute), but here we set it to 0 by default, indicating that we don't want to write it. Otherwise, it can be read from a MIDI file, and saved here to be restored later.

```
12.61.4.13 midibyte seq64::sequence::m_musical_key [private]
```

If the value is SEQ64_KEY_OF_C, then there is no musical key to be set.

```
12.61.4.14 midibyte seq64::sequence::m_musical_scale [private]
```

If the value is the enumeration value c_scale_off, then there is no musical scale to be set.

```
12.61.4.15 int seq64::sequence::m_background_sequence [private]
```

If the value is greater than max_sequence(), then there is no background sequence to be set.

```
12.61.4.16 mutex seq64::sequence::m_mutex [mutable], [private]
```

Made mutable for use in certain locked getter functions.

12.62 seq64::trigger Class Reference

This class hold a single trigger for a sequence object.

Public Member Functions

• trigger ()

Initializes the trigger structure.

bool operator< (const trigger &rhs)

This operator compares only the m_tick_start members.

• midipulse tick_start () const

'Getter' function for member m_tick_start

void tick_start (midipulse s)

'Setter' function for member m_tick_start

void increment_tick_start (midipulse s)

'Setter' function for member m_tick_start

void decrement_tick_start (midipulse s)

'Setter' function for member m_tick_start

· midipulse tick end () const

'Getter' function for member m_tick_end

void tick_end (midipulse e)

'Setter' function for member m_tick_end

void increment_tick_end (midipulse s)

'Setter' function for member m_tick_end

void decrement_tick_end (midipulse s)

'Setter' function for member m_tick_end

• midipulse offset () const

'Getter' function for member m_offset

void offset (midipulse o)

'Setter' function for member m_offset

void increment_offset (midipulse s)

'Setter' function for member m_offset

void decrement_offset (midipulse s)

'Setter' function for member m_offset

• bool selected () const

'Getter' function for member m selected

void selected (bool s)

'Setter' function for member m_selected

Private Attributes

• midipulse m_tick_start

Provides the starting tick for this trigger.

• midipulse m_tick_end

Provides the ending tick for this trigger.

midipulse m_offset

Provides the offset for this trigger.

bool m_selected

Indicates that the trigger is part of a selection.

12.62.1 Detailed Description

This class is used in playback, and is contained in the triggers class.

12.62.2 Member Function Documentation

12.62.2.1 bool seq64::trigger::operator< (const trigger & rhs) [inline]

rhs The "right-hand side" of the less-than operation.

Returns

Returns true if m_tick_start is less than rhs's.

12.63 seq64::triggers Class Reference

The triggers class is a receptable the triggers that can be used with a sequence object.

Public Types

typedef std::list< trigger > List

Exposes the triggers type, currently needed for midi_container only.

Public Member Functions

· triggers (sequence &parent)

Principal constructor.

• \sim triggers ()

A rote destructor.

• triggers & operator= (const triggers &rhs)

Principal assignment operator.

void set ppqn (int ppqn)

'Setter' function for member m_ppqn We have to set this value after construction for best safety.

void set_length (int len)

'Setter' function for member m_length We have to set this value after construction for best safety.

• List & triggerlist ()

'Getter' function for member m_triggers

• void push_undo ()

Pushes the list-trigger into the trigger undo-list, then flags each item in the undo-list as unselected.

void pop_undo ()

If the trigger undo-list has any items, the list-trigger is pushed into the redo list, the top of the undo-list is coped into the list-trigger, and then pops from the undo-list.

· void print (const std::string &seqname) const

Prints a list of the currently-held triggers.

bool play (midipulse &starttick, midipulse &endtick)

If playback-mode (song mode) is in force, that is, if using in-triggers and on/off triggers, this function handles that kind of playback.

void add (midipulse tick, midipulse len, midipulse offset=0, bool adjustoffset=true)

Adds a trigger.

void adjust_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length of ???, for all triggers, and undo triggers.

· void split (midipulse tick)

Splits the first trigger that brackets the splittick parameter.

void split (trigger &trig, midipulse splittick)

Splits the trigger given by the parameter into two triggers.

· void grow (midipulse tickfrom, midipulse tickto, midipulse length)

Grows a trigger.

· void remove (midipulse tick)

Deletes the first trigger that brackets the given tick from the trigger-list.

bool get_state (midipulse tick)

Checks the list of triggers against the given tick.

bool select (midipulse tick)

Checks the list of triggers against the given tick.

• bool unselect ()

Unselects all triggers.

· bool intersect (midipulse position, midipulse &start, midipulse &end)

This function examines each trigger in the trigger list.

• void remove_selected ()

Deletes the first selected trigger that is found.

void copy_selected ()

Copies the first selected trigger that is found.

· void paste ()

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

• bool move_selected (midipulse tick, bool adjustoffset, int which=2)

Moves selected triggers as per the given parameters.

• midipulse get_selected_start ()

Gets the selected trigger's start tick.

midipulse get_selected_end ()

Gets the selected trigger's end tick.

• midipulse get_maximum ()

Get the ending value of the last trigger in the trigger-list.

void move (midipulse starttick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

· void copy (midipulse starttick, midipulse distance)

Not sure what these diagrams are for yet.

• void clear ()

Clears the whole list of triggers.

bool next (midipulse *tick on, midipulse *tick off, bool *selected, midipulse *tick offset)

Get the next trigger in the trigger list, and set the parameters based on that trigger.

trigger next_trigger ()

Get the next trigger in the trigger list.

void reset_draw_trigger_marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

Private Member Functions

· midipulse adjust offset (midipulse offset)

Adjusts the given offset by mod'ing it with m_length and adding m_length if needed, and returning the result.

Private Attributes

• sequence & m_parent

Holds a reference to the parent sequence object that owns this trigger object.

List m_triggers

This list holds the current pattern/triggers events.

• trigger m_clipboard

This item holds a single copied trigger, to be pasted later.

Stack m_undo_stack

Handles the undo list for a series of operations on triggers.

Stack m_redo_stack

Handles the redo list for a series of operations on triggers.

• List::iterator m_iterator_play_trigger

An iterator for cycling through the triggers during playback.

· List::iterator m_iterator_draw_trigger

An iterator for cycling through the triggers during drawing.

· bool m_trigger_copied

Set to true if there is an active trigger in the trigger clipboard.

• int m_ppqn

Holds the value of the PPQN from the parent sequence, for easy access.

· int m_length

Holds the value of the length from the parent sequence, for easy access.

12.63.1 Constructor & Destructor Documentation

12.63.1.1 seq64::triggers::triggers (sequence & parent)

Parameters

parent The triggers object often needs to tell its parent sequence object what to do (such as stop playing).

12.63.2 Member Function Documentation

12.63.2.1 triggers & seq64::triggers::operator= (const triggers & rhs)

Follows the stock rules for such an operator, but does a little more then just assign member values.

FIXED, BEWARE: Currently, it does not assign them all, so we should create a partial_copy() function to do this work, and use it where it is needed.

Parameters

rhs Provides the "right-hand side" of the assignment operation.

Returns

Returns a reference to self, for use in concatenated assignment operations.

```
12.63.2.2 void seq64::triggers::set_length ( int len ) [inline]
```

Also, there a chance that the length of the parent might change from time to time. Currently, only the sequence constructor and midifile call this function.

12.63.2.3 void seq64::triggers::print (const std::string & seqname) const

Parameters

segname A tag name to accompany the print-out, for the human to	read.
---	-------

12.63.2.4 bool seq64::triggers::play (midipulse & start_tick, midipulse & end_tick)

This is a new function for sequence::play() to call.

The for-loop goes through all the triggers, determining if there is are trigger start/end values before the *end_tick*. If so, then the trigger state is set to true (start only within the tick range) or false (end is within the tick range), and the trigger tick is set to start or end. The first start or end trigger that is past the end tick cause the search to end.

If the trigger state has changed, then the start/end ticks are passed back to the sequence, and the trigger offset is adjusted.

Parameters

start_tick	Provides the starting tick value, and returns the modified value as a side-effect.
end_tick	Provides the ending tick value, and returns the modified value as a side-effect.

Returns

Returns true if we're through playing the frame (trigger turning off), and the caller should stop the playback.

12.63.2.5 void seq64::triggers::add (midipulse tick, midipulse len, midipulse offset = 0, bool fixoffset = true)

What is this?

tick	Provides the tick (pulse) time at which the trigger goes on.
len	Provides the length of the trigger. This value is actually calculated from the "on" value minus the "off" value read from the MIDI file.
offset	This value specifies the offset of the trigger. It is a feature of the c_triggers_new that c_triggers doesn't have. It is the third value in the trigger specification of the Sequencer64 MIDI file.
fixoffset	If true, the offset parameter is modified by adjust_offset() first. We think that basically makes sure it is positive.

12.63.2.6 void seq64::triggers::adjust_offsets_to_length (midipulse newlength)

Parameters

newlength	Provides the length to which to adjust the offsets.

COMMON CODE?

COMMON CODE?

12.63.2.7 void seq64::triggers::split (midipulse splittick)

This is the first trigger where splittick is greater than L and less than R.

Parameters

splittick	Provides the tick that must be bracketed for the split to be made.
-----------	--

12.63.2.8 void seq64::triggers::split (trigger & trig, midipulse splittick)

The original trigger ends 1 tick before the splittick parameter, and the new trigger starts at splittick and ends where the original trigger ended.

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is shortened, as a
	side-effect.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

12.63.2.9 void seq64::triggers::grow (midipulse tickfrom, midipulse tickto, midipulse len)

This function looks for the first trigger where the tickfrom parameter is between the trigger's tick-start and tick-end values. If found then the trigger's start is moved back to tickto, if necessary, or the trigger's end is moved to tickto plus the length parameter, if necessary.

Then this new trigger is added, and the function breaks from the search loop.

tickfrom	The desired from-value back which to expand the trigger, if necessary.
tickto	The desired to-value towards which to expand the trigger, if necessary.
len	The additional length to append to tickto for the check.

12.63.2.10 void seq64::triggers::remove (midipulse tick)

Parameters

_		
ſ	tick	Provides the tick to be examined.

12.63.2.11 bool seq64::triggers::get_state (midipulse tick)

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick Provides the tick of interest

Returns

Returns true if a trigger is found that brackets the given tick.

12.63.2.12 bool seq64::triggers::select (midipulse tick)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick	Provides the tick of interest.
------	--------------------------------

Returns

Returns true if a trigger is found that brackets the given tick.

12.63.2.13 bool seq64::triggers::unselect ()

Returns

Always returns false.

12.63.2.14 bool seq64::triggers::intersect (midipulse position, midipulse & start, midipulse & ender)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit.

position	The position to examine.
start	The destination for the starting tick (m_tick_start) of the matching trigger.
ender	The destination for the ending tick (m_tick_end) of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

```
12.63.2.15 void seq64::triggers::paste ( )
```

It pastes at the copy end.

12.63.2.16 bool seq64::triggers::move_selected (midipulse tick, bool fixoffset, int which = 2)

```
mintick][0 1][maxtick
```

The \a which parameter has three possible values:

- -# If we are moving the O, use first as offset.
- -# If we are moving the 1, use the last as the offset.
- -# If we are moving both (2), use first as offset.

Parameters

tick	The tick at which the trigger starts.	
fixoffset	Set to true if the offset is to be adjusted.	
which	Selects which movement will be done, as discussed above.	

Returns

Returns true if there was room to move. Otherwise, false is returned. We need this feature to support keystoke movement of a selected trigger in the perfroll window, and keep it from continually incrementing when there can be no more movement. This causes moving the other direction to be delayed while the accumulating movement counter is used up. However, right now we can't rely on this result, and ignore it. There may be no way around this minor issue.

```
12.63.2.17 midipulse seq64::triggers::get_selected_start()
```

We guess this ends up selecting only one trigger, otherwise only the last selected one would effectively set the result.

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

12.63.2.18 midipulse seq64::triggers::get_selected_end()

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

```
12.63.2.19 midipulse seq64::triggers::get_maximum ( )
```

Returns

Returns the tick-end for the last trigger, if available. Otherwise, 0 is returned.

```
12.63.2.20 void seq64::triggers::move ( midipulse starttick, midipulse distance, bool direction )
```

There's no way to optimize this by saving tick values, as they are potentially modified at each step.

Parameters

starttick	The current location of the triggers.
distance	The distance away from the current location to which to move the triggers.
direction	If true, the triggers are moved forward. If false, the triggers are moved backward.

12.63.2.21 void seq64::triggers::copy (midipulse starttick, midipulse distance)

```
]
    ] [
[
... a
5
 7 play
     offset
 10 play
] [ ] [] orig
[
     [ ] [ ][] split on the R marker, shift first [ ]
     delete middle
     move ticks
        ][ ] [ ] [] split on L
                 ]
              [ ] [] increase all after L
```

Copies triggers to a point distant from a given tick.

starttick	The current location of the triggers.	
distance	The distance away from the current location to which to copy the triggers.	

12.63.2.22 bool seq64::triggers::next (midipulse * tick_on, midipulse * tick_off, bool * selected, midipulse * offset)

Todo It would be a bit simpler to simply return a trigger object, wouldn't it?

Parameters

tick_on	Return value for the retrieval of the starting tick for the trigger.
tick_off	Return value for the retrieval of the ending tick for the trigger.
selected	Return value for the retrieval of the is-selected flag for the trigger.
offset	Return value for the retrieval of the offset for the trigger.

Returns

Returns true if a trigger was found. If false, the caller cannot rely on the values returned through the return parameters.

Side-effect(s) The value of the m_iterator_draw_trigger member will be altered by this call, unless pointing to the end of the triggerlist, or if there are no triggers.

12.63.2.23 trigger seq64::triggers::next_trigger()

Returns

Returns the next trigger. If there is none, a default trigger object is returned.

12.63.2.24 midipulse seq64::triggers::adjust_offset (midipulse offset) [private]

Parameters

offse	t Provides	the offset, n	mod'ed against m	_length, u	sed to adjust the offset.

Returns

Returns the new offset. However, if m_length is 0, no change is made, and the original offset is returned.

12.63.3 Field Documentation

12.63.3.1 int seq64::triggers::m_ppqn [private]

This should not change, but we have to set it after construction, and so we provide a setter for it, set_ppqn(), called by the sequence constructor.

12.63.3.2 int seq64::triggers::m_length [private]

This might change, we're not yet sure.

12.64 seq64::user_instrument Class Reference

Provides data about the MIDI instruments, readable from the "user" configuration file.

Public Member Functions

user instrument (const std::string &name="")

Default constructor.

user_instrument (const user_instrument &rhs)

Copy constructor.

user_instrument & operator= (const user_instrument &rhs)

Principal assignment operator.

• bool is_valid () const

'Getter' function for member m_is_valid

· void set_defaults ()

Sets the default values.

const std::string & name () const

'Getter' function for member m_instrument_def.instrument (name of instrument)

· int controller count () const

'Getter' function for member m_controller_count This function returns the number of active controllers.

• int controller max () const

'Getter' function for member MIDI_CONTROLLER_MAX This function returns the maximum number of controllers, active or inactive.

const std::string & controller_name (int c) const

'Getter' function for member m_instrument_def.controllers[c]

bool controller_active (int c) const

'Getter' function for member m_instrument_def.controllers_active[c]

• void set_controller (int c, const std::string &cname, bool isactive)

'Setter' function for member m_instrument_def.controllers[c] and .controllers_active[c] Only sets the controller values if the object is already valid.

Private Member Functions

void set name (const std::string &instname)

'Setter' function for member m_instrument_def.instrument

void copy_definitions (const user_instrument &rhs)

Copies the array members from one instance of user_instrument to this one.

Private Attributes

• bool m is valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

· int m controller count

Provides the actual number of non-default controllers actually set.

user_instrument_t m_instrument_def

The instance of the structure that this class wraps.

12.64.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.64.2 Member Function Documentation

```
12.64.2.1 void seq64::user_instrument::set_defaults ( )
```

Also invalidates the object.

```
12.64.2.2 int seq64::user_instrument::controller_max( ) const [inline]
```

Remember that the controller numbers for each MIDI instrument range from 0 to 127 (MIDI_CONTROLLER_MAX-1).

12.64.2.3 const std::string & seq64::user_instrument::controller_name (int c) const

Parameters

c The index of the desired of	controller.
-------------------------------	-------------

Returns

The name of the desired controller has is returned. If the index c is out of range, or the object is not valid, then a reference to an internal, empty string is returned.

12.64.2.4 bool seq64::user_instrument::controller_active (int c) const

Parameters

	The index of the desired controller.
C	i The index of the desired controller.

Returns

The status of the desired controller has is returned. If the index c is out of range, or the object is not valid, then false is returned.

12.64.2.5 void seq64::user_instrument::set_controller (int c, const std::string & cname, bool isactive)

Parameters

С	The index of the desired controller.	
cname	The name of the controller to be set as the controller name.	
isactive	A flag that indicates if the desired controller is active.	

12.64.2.6 void seq64::user_instrument::set_name (const std::string & instname) [private]

If the name parameter is not empty, the validity flag is set to true, otherwise it is set to false. Too tricky?

12.64.2.7 void seq64::user_instrument::copy_definitions (const user_instrument & rhs) [private]

Does not include the validity flag.

12.64.3 Field Documentation

12.64.3.1 bool seq64::user_instrument::m_is_valid [private]

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call. However, setting an empty name for the instrument member will render the object invalid.

12.64.3.2 int seq64::user_instrument::m_controller_count [private]

Often, the "user" configuration file has only a few out of the 128 assigned explicitly.

12.65 seq64::user_instrument_t Struct Reference

This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/susr file.

Data Fields

· std::string instrument

Provides the name of the "instrument" being supported.

std::string controllers [SEQ64 MIDI CONTROLLER MAX]

Provides a list of up to 128 controllers (e.g.

bool controllers_active [SEQ64_MIDI_CONTROLLER_MAX]

Provides a flag that indicates if each of up to 128 controller is active and supported.

12.65.1 Field Documentation

12.65.1.1 std::string seq64::user_instrument_t::instrument

Do not confuse "instrument" with "program" here. An "instrument" is most likely a hardware MIDI sound-box (though it could be a software synthesizer as well.

12.65.1.2 std::string seq64::user_instrument_t::controllers[SEQ64_MIDI_CONTROLLER_MAX]

"Modulation"). If a controller isn't present, or if General MIDI is in force, this name might be empty.

12.65.1.3 bool seq64::user_instrument_t::controllers_active[SEQ64_MIDI_CONTROLLER_MAX]

If false, it might be an unsupported controller or a General MIDI device.

12.66 seq64::user_midi_bus Class Reference

Provides data about the MIDI busses, readable from the "user" configuration file.

Public Member Functions

• user midi bus (const std::string &name="")

Default constructor.

• user midi bus (const user midi bus &rhs)

Copy constructor.

user_midi_bus & operator= (const user_midi_bus &rhs)

Principal assignment operator.

• bool is_valid () const

'Getter' function for member m_is_valid

· void set_defaults ()

Sets the default values.

• const std::string & name () const

'Getter' function for member m_midi_bus_def.alias (name of alias)

int channel_count () const

'Getter' function for member m_channel_count

• int channel_max () const

'Getter' function for member SEQ64_MIDI_BUS_CHANNEL_MAX

· int instrument (int channel) const

'Getter' function for member m_midi_bus_def.instrument[channel]

· void set instrument (int channel, int instrum)

'Getter' function for member m_midi_bus_def.instrument[channel]

Private Member Functions

• void set_name (const std::string &name)

'Setter' function for member m_midi_bus_def.alias (name of alias) Also sets the validity flag according to the emptiness of the name parameter.

void copy definitions (const user midi bus &rhs)

Copies the member fields from one instance of user_midi_bus to this one.

Private Attributes

· bool m is valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

int m_channel_count

Provides the actual number of non-default buss channels actually set.

user_midi_bus_t m_midi_bus_def

The instance of the structure that this class wraps.

12.66.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.66.2 Member Function Documentation

```
12.66.2.1 void seq64::user_midi_bus::set_defaults ( )
```

Also invalidates the object. All 16 of the channels are set to SEQ64 GM INSTRUMENT FLAG (-1).

```
12.66.2.2 int seq64::user_midi_bus::channel_count( ) const [inline]
```

Returns

This function returns the number of channels. Basically this value is always the same as that returned by channel_max(), but this pair of functions is consistent with the count functions in the user_instrument class.

```
12.66.2.3 int seq64::user_midi_bus::channel_max() const [inline]
```

Returns

Returns the maximum number of MIDI buss channels. Remember that the instrument channels for each MIDI buss range from 0 to 15 (MIDI BUS CHANNEL MAX-1).

12.66.2.4 int seq64::user_midi_bus::instrument (int channel) const

Parameters

channel	Provides the desired buss channel number.

Returns

The instrument number of the desired buss channel is returned. If the channel number is out of range, or the object is not valid, then SEQ64_GM_INSTRUMENT_FLAG (-1) is returned.

12.66.2.5 void seq64::user_midi_bus::set_instrument (int channel, int instrum)

Does not alter the validity flag, just checks it.

Parameters

channel	Provides the desired buss channel number.
instrum	Provides the instrument number to set that channel to.

12.66.2.6 void seq64::user_midi_bus::copy_definitions (const user_midi_bus & rhs) [private]

Does not include the validity flag.

12.66.3 Field Documentation

```
12.66.3.1 bool seq64::user_midi_bus::m_is_valid [private]
```

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call.

```
12.66.3.2 int seq64::user_midi_bus::m_channel_count [private]
```

Often, the "user" configuration file has only a few out of the 16 assigned explicitly.

12.67 seq64::user_midi_bus_t Struct Reference

This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the application).

Data Fields

std::string alias

Provides the user's desired name for the MIDI bus.

int instrument [SEQ64_MIDI_BUS_CHANNEL_MAX]

Provides an implicit list of MIDI channels from 0 to 15 (1 to 16) and the "instrument" number assigned to each channel.

12.67.1 Field Documentation

12.67.1.1 std::string seq64::user_midi_bus_t::alias

For example, "2x2 A" for some kind of MIDI card or USB MIDI cable. If manual-alsa-ports is enabled, this could be something like "[0] seq24 0", and that is what should be shown in that case.

12.67.1.2 int seq64::user_midi_bus_t::instrument[SEQ64_MIDI_BUS_CHANNEL_MAX]

Note that the "instrument" is not a MIDI program number. Instead, it is the number associated with a "user-instrument" section in the "user" configuration file.

12.68 seq64::user_settings Class Reference

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

Public Member Functions

user_settings ()

Default constructor.

· user settings (const user settings &rhs)

Copy constructor.

user_settings & operator= (const user_settings &rhs)

Principal assignment operator.

void set defaults ()

Sets the default values.

• void normalize ()

Calculate the derived values from the already-set values.

bool add bus (const std::string &alias)

Adds a user buss to the container, but only does so if the name parameter is not empty.

bool add instrument (const std::string &instname)

Adds a user instrument to the container, but only does so if the name parameter is not empty.

const user midi bus & bus (int index)

'Getter' function for member Unlike the non-const version this function is public.

const user_instrument & instrument (int index)

'Getter' function for member Unlike the non-const version this function is public.

• int bus_count () const

'Getter' function for member m_midi_buses.size()

void set bus instrument (int index, int channel, int instrum)

'Getter' function for member m_midi_buses[index].instrument[channel] Currently this function is used, in the userfile ::parse() function.

• int bus_instrument (int buss, int channel)

'Getter' function for member m_midi_buses[buss].instrument[channel]

• const std::string & bus_name (int buss)

'Getter' function for member m_midi_buses[buss].name

· int instrument count () const

 ${\it 'Getter' function for member m_instruments.size()}$

· void set instrument controllers (int index, int cc, const std::string &ccname, bool isactive)

'Setter' function for member m_midi_instrument_defs[index].controllers, controllers_active

const std::string & instrument_name (int instrum)

'Getter' function for member m_instruments[instrument].instrument (name of instrument)

• const std::string & instrument_name (int buss, int channel)

Gets the correct instrument number from the buss and channel, and then looks up the name of the instrument.

bool instrument_controller_active (int instrum, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller]

bool controller_active (int buss, int channel, int cc)

A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

const std::string & instrument_controller_name (int instrum, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller]

• const std::string & controller name (int buss, int channel, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller] A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

int grid_style () const

'Getter' function for member m_grid_style Checks for normal style.

· bool grid is normal () const

'Getter' function for member m_grid_style Checks for normal style.

· bool grid is white () const

'Getter' function for member m_grid_style Checks for the white style.

bool grid_is_black () const

'Getter' function for member m_grid_style Checks for the black style.

• int grid brackets () const

'Getter' function for member m_grid_brackets

• int mainwnd_rows () const

'Getter' function for member m_mainwnd_rows

• int mainwnd_cols () const

'Getter' function for member m_mainwnd_cols

• int seqs_in_set () const

'Getter' function for member m_seqs_in_set, dependent member

int gmute_tracks () const

'Getter' function for member m_gmute_tracks, dependent member

• int max_sets () const

'Getter' function for member m_max_sets

int max_sequence () const

'Getter' function for member m_max_sequence, dependent member

int text_x () const

'Getter' function for member m_text_x, not user modifiable, not saved

int text_y () const

'Getter' function for member m_text_y, not user modifiable, not saved

int seqchars_x () const

'Getter' function for member m_seqchars_x, not user modifiable, not saved

int seqchars_y () const

'Getter' function for member m_seqchars_y, not user modifiable, not saved

• int seqarea_x () const

'Getter' function for member m_seqarea_x, not user modifiable, not saved

int seqarea_y () const

'Getter' function for member m_seqarea_y, not user modifiable, not saved

• int seqarea_seq_x () const

'Getter' function for member m_seqarea_seq_x, not user modifiable, not saved

• int seqarea_seq_y () const

'Getter' function for member m_seqarea_seq_y, not user modifiable, not saved

int mainwid_border () const

'Getter' function for member m_mainwid_border

• int mainwid_spacing () const

'Getter' function for member m_mainwid_spacing

• int mainwid_x () const

'Getter' function for member m_mainwid_x, dependent member

int mainwid_y () const

'Getter' function for member m_mainwid_y, dependent member

• int control_height () const

'Getter' function for member m_control_height

• int zoom () const

 ${\it 'Getter' function for member m_current_zoom}$

void zoom (int value)

'Setter' function for member m_current_zoom This value is not modified unless the value parameter is between 1 and 512, inclusive.

· bool global seq feature () const

'Getter' function for member m_global_seq_feature_save

void global_seq_feature (bool flag)

'Setter' function for member m_global_seq_feature_save

int seqedit_scale () const

'Getter' function for member m segedit scale

· void segedit scale (int scale)

'Setter' function for member m_seqedit_scale

• int seqedit_key () const

'Getter' function for member m_seqedit_key

void seqedit_key (int key)

'Setter' function for member m_seqedit_key

• int seqedit_bgsequence () const

'Getter' function for member m_seqedit_bgsequence

void seqedit_bgsequence (int seqnum)

'Setter' function for member m_seqedit_bgsequence Note that SEQ64_IS_LEGAL_SEQUENCE() allows the SE← Q64_SEQUENCE_LIMIT (0x800 = 2048) value, to turn off the use of a background sequence.

bool use_new_font () const

'Getter' function for member m_use_new_font

bool allow_two_perfedits () const

'Getter' function for member m_allow_two_perfedits

• int perf_h_page_increment () const

'Getter' function for member m_h_perf_page_increment

int perf_v_page_increment () const

'Getter' function for member m_v_perf_page_increment

· bool progress_bar_colored () const

'Getter' function for member m_progress_bar_colored

· bool progress_bar_thick () const

'Getter' function for member m_progress_bar_thick

• int window redraw rate () const

'Getter' function for member m_window_redraw_rate_ms

bool save_user_config () const

'Getter' function for member m save user config

void save_user_config (bool flag)

'Setter' function for member m_save_user_config

int midi_ppqn () const

'Getter' function for member m_midi_ppqn

int midi_beats_per_bar () const

 ${\it 'Getter' function for member m_midi_beats_per_measure}$

• int midi_beats_per_minute () const

'Getter' function for member m_midi_beats_per_minute

int midi_beat_width () const

'Getter' function for member m_midi_beat_width

· char midi buss override () const

'Getter' function for member m_midi_buss_override

• int min_zoom () const

 ${\it 'Getter' function for member mc_min_zoom}$

• int max_zoom () const

'Getter' function for member mc_max_zoom

int baseline_ppqn () const

'Getter' function for member mc_baseline_ppqn

· void use new font (bool flag)

'Setter' function for member m_use_new_font

void allow_two_perfedits (bool flag)

Sets the value of allowing two perfedits to be created and shown to the user.

void perf_h_page_increment (int inc)

Sets the horizontal page increment size for the horizontal scrollbar of a perfedit window.

void perf v page increment (int inc)

Sets the vertical page increment size for the vertical scrollbar of a perfedit window.

void progress bar colored (bool flag)

'Setter' function for member m progress bar colored

· void progress_bar_thick (bool flag)

'Setter' function for member m progress bar thick

void window_redraw_rate (int ms)

'Setter' function for member m_window_redraw_rate_ms

void midi_ppqn (int ppqn)

'Setter' function for member m_midi_ppqn This value can be set from 96 to 19200 (this upper limit will be determined by what Sequencer64 can actually handle).

· void midi buss override (char buss)

'Setter' function for member m midi buss override This value can be set from 0 to 31.

Protected Member Functions

· void grid brackets (int thickness)

'Getter' function for member m_grid_brackets

void grid_style (int gridstyle)

'Setter' function for member m_grid_style

void mainwnd_rows (int value)

'Setter' function for member m_mainwnd_rows This value is not modified unless the value parameter is between 4 and 8, inclusive.

void mainwnd_cols (int value)

'Setter' function for member m_mainwnd_cols This value is not modified unless the value parameter is between 8 and

• void max sets (int value)

'Setter' function for member m_max_sets This value is not modified unless the value parameter is between 32 and 64. inclusive.

void text_x (int value)

'Setter' function for member m_text_x This value is not modified unless the value parameter is between 6 and 6, inclusive.

void text_y (int value)

'Setter' function for member m_text_y This value is not modified unless the value parameter is between 12 and 12, inclusive.

• void seqchars_x (int value)

'Setter' function for member m_seqchars_x This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 15.

void seqchars_y (int value)

'Setter' function for member m_seqchars_y This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 5.

void seqarea_x (int value)

'Setter' function for member m segarea x

void seqarea_y (int value)

'Setter' function for member m_seqarea_y

void seqarea_seq_x (int value)

'Setter' function for member m_segarea_seg_x

void seqarea_seq_y (int value)

'Setter' function for member m_seqarea_seq_y

void mainwid_border (int value)

'Setter' function for member m_mainwid_border This value is not modified unless the value parameter is between 0 and 3, inclusive.

void mainwid spacing (int value)

'Setter' function for member m_mainwid_spacing This value is not modified unless the value parameter is between 2 and 6, inclusive.

void control height (int value)

'Setter' function for member m_control_height This value is not modified unless the value parameter is between 0 and 4, inclusive.

void dump summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

void midi_beats_per_bar (int beatsperbar)

'Setter' function for member m_midi_beats_per_measure This value can be set from 1 to 16.

void midi beats per minute (int beatsperminute)

'Setter' function for member m_midi_beats_minute This value can be set from 20 to 500.

void midi_beat_width (int beatwidth)

'Setter' function for member m_midi_beatwidth This value can be set to any power of 2 in the range from 1 to 16.

Private Types

typedef std::vector< user midi bus > Busses

[user-midi-bus-definitions]

typedef std::vector< user_instrument > Instruments

[user-instrument-definitions]

Private Member Functions

· user midi bus & private bus (int buss)

'Getter' function for member m_midi_buses[index] (internal function) If the index is out of range, then an invalid object is returned.

user_instrument & private_instrument (int instrum)

'Getter' function for member m_instruments[index] If the index is out of range, then a invalid object is returned.

Private Attributes

Busses m_midi_buses

Provides data about the MIDI busses, readable from the "user" configuration file.

· Instruments m instruments

Provides data about the MIDI instruments, readable from the "user" configuration file.

mainwid_grid_style_t m_grid_style

[user-interface-settings]

· int m grid brackets

Specify drawing brackets (like the old Seq24) or a solid box.

int m_mainwnd_rows

Number of rows in the Patterns Panel.

· int m mainwnd cols

Number of columns in the Patterns Panel.

int m_max_sets

Maximum number of screen sets that can be supported.

• int m_mainwid_border

These control sizes.

· int m_control_height

This constants seems to be created for a future purpose, perhaps to reserve space for a new bar on the mainwid pane.

int m_current_zoom

Provides the initial zoom value, in units of ticks per pixel.

bool m_global_seq_feature_save

If true, this value provide a bit of backward-compatibility with the global key/scale/background-sequence persistence feature.

· int m_seqedit_scale

Replaces sequelit::m_initial_scale as the repository for the scale to apply when a sequence is loaded into the sequence editor.

· int m segedit key

Replaces seqedit::m_initial_key as the repository for the key to apply when a sequence is loaded into the sequence editor.

• int m_seqedit_bgsequence

Replaces sequent::m_initial_sequence as the repository for the background sequence to apply when a sequence is loaded into the sequence editor.

bool m_use_new_font

Sets the usage of the font.

bool m_allow_two_perfedits

Enables the usage of two perfedit windows, for added convenience in editing multi-set songs.

int m_h_perf_page_increment

Allows a changed to the page size for the horizontal scroll bar.

• int m_v_perf_page_increment

Allows a changed to the page size for the vertical scroll bar.

bool m_progress_bar_colored

If set, makes progress bars have the "progress_color()", instead of black.

bool m_progress_bar_thick

If set, makes progress bars thicker than 1 pixel...

int m_window_redraw_rate_ms

Provides the global setting for redraw rate of windows.

int m_text_x

Constants for the mainwid class.

int m_seqchars_x

Constants for the mainwid class.

• int m_midi_ppqn

Provides the universal PPQN setting for the duration of this setting.

int m_midi_beats_per_measure

Provides the universal and unambiguous MIDI value for beats per measure, also called "beats per bar" (BPB).

int m_midi_beats_per_minute

Provides the universal and unambiguous MIDI value for beats per minute (BPM).

int m_midi_beat_width

Provides the universal MIDI value for beats width (BW).

• char m_midi_buss_override

Provides a universal override of the buss number for all sequences, for the purpose of convenience of of testing.

• int m_seqs_in_set

Number of patterns/sequences in the Patterns Panel, also known as a "set" or "screen set".

int m_gmute_tracks

Number of group-mute tracks that can be supported, which is m_seqs_in_set squared, or 1024.

• int m_max_sequence

The maximum number of patterns supported is given by the number of patterns supported in the panel (32) times the maximum number of sets (32), or 1024 patterns.

• int m segarea x

The m_seqarea_x and m_seqarea_y constants are derived from the width and heights of the default character set, and the number of characters in width, and the number of lines, in a pattern/sequence box.

• int m segarea seg x

Area of what? Doesn't look at all like it is based on the size of characters.

· int m_mainwid_x

The width of the main pattern/sequence grid, in pixels.

· bool m save user config

Provides a temporary variable that can be set from the command line to cause the "user" state to be saved into the "user" configuration file.

const int mc_min_zoom

Provides the minimum zoom value, currently a constant.

· const int mc max zoom

Provides the maximum zoom value, currently a constant.

const int mc_baseline_ppqn

Permanent storage for the baseline, default PPQN used by Seq24.

12.68.1 Detailed Description

These settings will eventually be made part of the "user" settings file.

12.68.2 Member Typedef Documentation

```
12.68.2.1 typedef std::vector<user_midi_bus> seq64::user_settings::Busses [private]
```

Internal type for the container of user_midi_bus objects. Sorry about the "confusion" about "bus" versus "buss". See Google for arguments about it.

```
12.68.2.2 typedef std::vector<user_instrument> seq64::user_settings::Instruments [private]
```

Internal type for the container of user_instrument objects.

12.68.3 Member Enumeration Documentation

```
12.68.3.1 enum seq64::user_settings::mainwid_grid_style_t [private]
```

Enumerator

grid_style_normal Provides a setting to control the overall style of grid-drawing for the pattern slots in mainwid. These values can be specified in the [user-interface-settings] section of the "user" configuration file.

```
The grid background color is the normal background color for the current GTK theme. The box is drawn with brackets on either side.
```

grid_style_white The grid background color is white. This style better fits displaying the white-on-black sequence numbers. The box is drawn with brackets on either side.

grid_style_black The grid background color is black.

grid_style_max Marks the end of the list, and is an illegal value.

12.68.4 Member Function Documentation

```
12.68.4.1 void seq64::user_settings::set_defaults ( )
```

For the m_midi_buses and m_instruments members, this function can only iterate over the current size of the vectors. But the default size is zero!

```
12.68.4.2 const user_midi_bus& seq64::user_settings::bus(int index) [inline]
```

Cannot append the const specifier.

```
12.68.4.3 const user_instrument& seq64::user_settings::instrument(int index) [inline]
```

Cannot append the const specifier.

```
12.68.4.4 bool seq64::user settings::controller active (int buss, int channel, int cc) [inline]
```

It also has a shorter name.

```
12.68.4.5 const std::string& seq64::user_settings::controller_name( int buss, int channel, int cc ) [inline]
```

It also has a shorter name.

```
12.68.4.6 void seq64::user_settings::zoom ( int value )
```

The default value is 2. Note that 0 is allowed as a special case, which allows the default zoom to be adjusted when the PPQN value is different from the default.

```
12.68.4.7 void seq64::user_settings::mainwnd_rows ( int value ) [protected]
```

The default value is 4. Dependent values are recalculated after the assignment.

```
12.68.4.8 void seq64::user_settings::mainwnd_cols(int value) [protected]
```

The default value is 8. Dependent values are recalculated after the assignment.

```
12.68.4.9 void seq64::user_settings::max_sets (int value) [protected]
```

The default value is 32. Dependent values are recalculated after the assignment.

```
12.68.4.10 void seq64::user_settings::text_x ( int value ) [protected]
```

The default value is 6. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

```
12.68.4.11 void seq64::user_settings::text_y ( int value ) [protected]
```

The default value is 12. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

```
12.68.4.12 void seq64::user_settings::mainwid_border( int value ) [protected]
```

The default value is 0. Dependent values are recalculated after the assignment.

```
12.68.4.13 void seq64::user_settings::mainwid_spacing (int value) [protected]
```

The default value is 2. Dependent values are recalculated after the assignment.

```
12.68.4.14 void seq64::user_settings::control_height(int value) [protected]
```

The default value is 0. Dependent values are recalculated after the assignment.

```
12.68.4.15 void seq64::user_settings::dump_summary( ) [protected]
```

Does its work only if PLATFORM_DEBUG and SEQ64_USE_DEBUG_OUTPUT are defined. Only enabled in emergencies :-D.

```
12.68.4.16 void seq64::user_settings::perf_h_page_increment ( int inc )
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 6 (which is 24 measures, the same as the typical width of the perfroll)

```
12.68.4.17 void seq64::user_settings::perf_v_page_increment ( int inc )
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 18 (which is 18 tracks, slightly more than the typical height of the perfroll)

```
12.68.4.18 void seq64::user_settings::midi_ppqn ( int value )
```

The default value is 192.

```
12.68.4.19 void seq64::user_settings::midi_buss_override ( char buss )
```

The default value is -1, which means that there is no buss override. It provides a way to override the buss number for smallish MIDI files. It replaces the buss-number read from the file. This option is turned on by the —bus option, and is merely a convenience feature for the quick previewing of a tune. (It's called "developer laziness".)

```
12.68.4.20 void seq64::user_settings::midi_beats_per_bar( int value ) [protected]
```

The default value is 4.

```
12.68.4.21 void seq64::user_settings::midi_beats_per_minute( int value ) [protected]
```

The default value is 120.

```
12.68.4.22 void seq64::user_settings::midi_beat_width(int bw) [protected]
```

The default value is 4.

```
12.68.4.23 user_midi_bus & seq64::user_settings::private_bus(int index) [private]
```

This invalid object has an empty alias, and all the instrument numbers are -1.

```
12.68.4.24 user_instrument & seq64::user_settings::private_instrument(int index) [private]
```

This invalid object has an empty(), instrument name, false for all controllers_active[] values, and empty controllers[] string values.

12.68.5 Field Documentation

```
12.68.5.1 Busses seq64::user_settings::m_midi_buses [private]
```

Since this object is a vector, its size is adjustable.

12.68.5.2 Instruments seq64::user_settings::m_instruments [private]

The size is adjustable, and grows as objects are added.

```
12.68.5.3 mainwid_grid_style_t seq64::user_settings::m_grid_style [private]
```

These are not labelled, but are present in the "user" configuration file in the following order:

```
-# grid-style
-# grid-brackets
   mainwnd-rows
   mainwnd-cols
-# max-set
-# mainwid-border
-#
   control-height
-# global-seq-feature
-# use-new-font
-# allow-two-perfedits
-# perf-h-page-increment
-#
   perf-v-page-increment
-# progress-bar-colored (new)
-# progress-bar-thick (new)
   window-redraw-rate-ms (new)
```

Specifies the current grid style.

```
12.68.5.4 int seq64::user_settings::m_grid_brackets [private]
```

0 = no brackets, 1 and above is the thickness of the brakcets. 1 is the normal thickness of the brackets, 2 is a two-pixel thickness, and so on.

```
12.68.5.5 int seq64::user_settings::m_mainwnd_rows [private]
```

The current value is 4, and if changed, many other values depend on it. Together with m_mainwnd_cols, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set". We would like to be able to change this value from 4 to 8, and maybe allow the values of 5, 6, and 7 as well. But if we could just get 8 working, then well would Sequencer64 deserve the 64 in its name.

```
12.68.5.6 int seq64::user_settings::m_mainwnd_cols [private]
```

The current value is 4, and probably won't change, since other values depend on it. Together with m_mainwnd_rows, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set".

```
12.68.5.7 int seq64::user_settings::m_max_sets [private]
```

Basically, that the number of times the Patterns Panel can be filled. 32 sets can be created. Although this value is part of the "user" configuration file, it is likely that it will never change. Rather, the number of sequences per set would change. We'll see.

```
12.68.5.8 int seq64::user_settings::m_mainwid_border [private]
```

We'll try changing them and see what happens. Increasing these value spreads out the pattern grids a little bit and makes the Patterns panel slightly bigger. Seems like it would be useful to make these values user-configurable.

```
12.68.5.9 int seq64::user_settings::m_control_height [private]
```

But it is used only in this header file, to define m_mainwid_y, but doesn't add anything to that value.

```
12.68.5.10 int seq64::user_settings::m_current_zoom [private]
```

The original default value was 32 ticks per pixel, but larger PPQN values need higher values, and we will have to adapt the default zoom to the PPQN value.

```
12.68.5.11 bool seq64::user_settings::m_global_seq_feature_save [private]
```

In this feature, applying one of these three changes to a sequence causes them to also be applied to sequences that are subsequently opened for editing. However, we improve on this feature by allowing the changes to be saved in the global, proprietary part of the saved MIDI file.

If false, the user can still save the key/scale/background-sequence values with each individual sequence, so they can be different.

This value will be true by default, unless changed in the "user" configuration file.

```
12.68.5.12 int seq64::user_settings::m_seqedit_scale [private]
```

Its default value is c_scale_off. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musicscale, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musicscale.

```
12.68.5.13 int seq64::user_settings::m_seqedit_key [private]
```

Its default value is SEQ64_KEY_OF_C. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musickey, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musickey.

```
12.68.5.14 int seq64::user_settings::m_seqedit_bgsequence [private]
```

Its default value is SEQ64_SEQUENCE_LIMIT. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored, if it has a valid (but not "legal") value, in the "proprietary" track at the end of the file, under the control tag c_backsequence, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_backsequence.

```
12.68.5.15 bool seq64::user_settings::m_use_new_font [private]
```

By default, in normal mode, the new font is used. In legacy mode, the old font is used.

12.68.5.16 bool seq64::user_settings::m_allow_two_perfedits [private]

Defaults to true.

```
12.68.5.17 int seq64::user_settings::m_h_perf_page_increment [private]
```

The value used to be hardwired to 1 (in four-measure units), now it defaults to 4 (16 measures at a time). The value of 1 is already covered by the scrollbar arrows.

```
12.68.5.18 int seq64::user_settings::m_v_perf_page_increment [private]
```

The value used to be hardwired to 1 (in single-track units), now it defaults to 8. The value of 1 is already covered by the scrollbar arrows.

```
12.68.5.19 bool seq64::user_settings::m_progress_bar_colored [private]
```

This value is hardwired in the gui_palette_gtk2 module, to red. Really, that is the only color that stands out as well as black.

```
12.68.5.20 bool seq64::user_settings::m_progress_bar_thick [private]
```

2 pixels. It isn't useful to support anything thicker.

```
12.68.5.21 int seq64::user_settings::m_window_redraw_rate_ms [private]
```

Not all windows use this yet. The default is 40 ms (c_redraw_ms, which is 20 ms in Windows builds)), but some windows originally used 25 ms, so beware of side-effects.

```
12.68.5.22 int seq64::user_settings::m_text_x [private]
```

The m_text_x and m_text_y constants help define the "seqarea" size. It looks like these two values are the character width (x) and height (y) in pixels. Thus, these values would be dependent on the font chosen. But that, currently, is hard-wired. See the m_font_6_12[] array for the default font specification.

However, please not that font files are not used. Instead, the fonts are provided by two pixmaps in the src/pixmap directory: $font_b.xpm$ (black lettering on a white background) and $font_w.xpm$ (white lettering on a black background).

We have added black-on-yellow and yellow-on-black versions of the fonts, to support the highlighting of pattern boxes if they are empty of actual MIDI events.

We have also added a set of four new font files that are roughly the same size, and are treated as the same size, but look smooth and less like a DOS-era font.

The font module does not use these values directly, but does define some similar variables that differ slightly between the two styles of font. There are a lot of tricks and hard-wired places to fix before further work can be done with fonts in Sequencer64.

```
12.68.5.23 int seq64::user_settings::m_seqchars_x [private]
```

The m_seqchars_x and m_seqchars_y constants help define the "seqarea" size. These look like the number of characters per line and the number of lines of characters, in a pattern/sequence box.

```
12.68.5.24 int seq64::user_settings::m_midi_ppqn [private]
```

This variable replaces the global ppqn. The default value of this setting is 192 parts-per-quarter-note (PPQN). There is still a lot of work to get a different PPQN to work properly in speed of playback, scaling of the user interface, and other issues. Note that this value can be changed by the still-experimental –ppqn option. There is one remaining trace of the global, though: DEFAULT PPQN.

```
12.68.5.25 int seq64::user_settings::m_midi_beats_per_measure [private]
```

This variable will replace the global beats per measure. The default value of this variable is SEQ64_DEFAULT_← BEATS_PER_MEASURE (4). For external access, we will call this value "beats per bar", abbreviate it "BPB", and use "bpb" in any accessor function names. Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BPB value, either for MIDI purposes or for drawing the piano-roll grids. So we might need a couple different versions of this variable.

```
12.68.5.26 int seq64::user_settings::m_midi_beats_per_minute [private]
```

This variable will replace the global beats per minute. The default value of this variable is DEFAULT_BPM (120). This variable should apply to the whole session; there's probably no way to support a diffent tempo for each sequence. But we shall see. For external access, we will call this value "beats per minute", abbreviate it "BPM", and use "bpm" in any accessor function names.

```
12.68.5.27 int seq64::user_settings::m_midi_beat_width [private]
```

This variable will replace the global beat_width. The default value of this variable is DEFAULT_BEAT_WIDTH (4). Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BW value, either for MIDI purposes or for drawing the user-interface. So we might need a couple different versions of this variable. For external access, we will call this value "beat width", abbreviate it "BW", and use "bw" in any accessor function names.

```
12.68.5.28 char seq64::user_settings::m_midi_buss_override [private]
```

This variable replaces the global buss-override variable, and is set via the command-line option -bus.

```
12.68.5.29 int seq64::user_settings::m_seqs_in_set [private]
```

This value is $4 \times 8 = 32$ by default.

Warning

Currently implicit/explicit in a number of the "rc" file and rc_settings. Would probably want the left 32 or the first 32 items in the main window only to be subject to keystroke control. This value is calculated by the normalize() function, and is *not* part of the "user" configuration file.

```
12.68.5.30 int seq64::user_settings::m_gmute_tracks [private]
```

This value is *not* part of the "user" configuration file; it is calculated by the normalize() function.

```
12.68.5.31 int seq64::user_settings::m_max_sequence [private]
```

It is a derived value, and not stored in the "user" file.

```
m_max_sequence = m_seqs_in_set * m_max_sets;
```

```
12.68.5.32 int seq64::user_settings::m_seqarea_x [private]
```

Compare these two constants to m_seqarea_seq_x(y), which was in mainwid.h, but is now in this file.

```
12.68.5.33 int seq64::user_settings::m_seqarea_seq_x [private]
```

These are used only in the mainwid module.

```
12.68.5.34 int seq64::user_settings::m_mainwid_x [private]
```

Affected by the m_mainwid_border and m_mainwid_spacing values.

```
12.68.5.35 bool seq64::user_settings::m_save_user_config [private]
```

Normally, this state is not saved. It is not saved because there is currently no user-interface for editing it, and because it can pick up some command-line options, and it is not right to have them written to the "user" configuration file

(The "rc" configuration file is a different case, having historically always been saved, and having a number of command-line options, such as JACK settings that should generally be permanent on a given system.)

Anyway, this flag can be set by the –user-save option. This setting is never saved. But note that, if no "user" configuration file is found, it is then saved anyway.

```
12.68.5.36 const int seq64::user_settings::mc_min_zoom [private]
```

It's value is 1.

```
12.68.5.37 const int seq64::user_settings::mc_max_zoom [private]
```

It's value was 32, but is now 512, to allow for better presentation of high PPQN valued sequences.


```
12.68.5.38 const int seq64::user_settings::mc_baseline_ppqn [private]
```

This value is necessary in order to keep user-interface elements stable when different PPQNs are used. It is set to DEFAULT_PPQN.

12.69 seq64::userfile Class Reference

Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24usr configuration file.

Inheritance diagram for seq64::userfile:



Public Member Functions

• userfile (const std::string &a_name)

Principal constructor.

• ∼userfile ()

A rote destructor needed for a derived class.

• bool parse (perform &a_perf)

Parses a "usr" file, filling in the given perform object.

bool write (const perform &a_perf)

This function just returns false, as there is no "perform" information in the user-file yet.

Private Member Functions

• void dump_setting_summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

Additional Inherited Members

12.69.1 Member Function Documentation

```
12.69.1.1 bool seq64::userfile::parse ( perform & a_perf ) [virtual]
```

This function opens the file as a text file (line-oriented).

Parameters

a_perf The performance object, currently unuse	d.
---	----

Implements seq64::configfile.

```
12.69.1.2 bool seq64::userfile::write ( const perform & a_perf ) [virtual]
```

Parameters

a perf	The performance object, currently unused.

Implements seq64::configfile.

```
12.69.1.3 void seq64::userfile::dump_setting_summary() [private]
```

Does work only if PLATFORM_DEBUG is defined; see the user_settings class.

Index

\sim event	adjust_trigger_offsets_to_length
seq64::event, 96	seq64::sequence, 358
\sim eventedit	adjustment_dummy
seq64::eventedit, 112	seq64, 66
\sim jack_assistant	alias
seq64::jack_assistant, 150	seq64::user_midi_bus_t, 376
~keys_perform	all_notes_off
seq64::keys_perform, 161	seq64::perform, 257
~keys_perform_gtk2	analyze
seq64::keys_perform_gtk2, 165	seq64::editable_event, 85
\sim mastermidibus	any_selected_notes
seq64::mastermidibus, 194	seq64::event_list, 108
\sim perfedit	append_sysex
seq64::perfedit, 237	seq64::event, 100
\sim perform	apply_length
seq64::perform, 251	seq64::seqedit, 302
\sim perfroll	
seq64::perfroll, 275	BLACK_ON_CYAN
\sim seqmenu	seq64::font, 129
seq64::seqmenu, 319	BLACK_ON_YELLOW
~seqroll	seq64::font, 129
seq64::seqroll, 326	BLACK
	seq64::font, 129
about_dialog	background_sequence
seq64::mainwnd, 187	seq64::sequence, 357
add	beats_per_minute_from_tempo
seq64::editable_events, 90	seq64, 55
seq64::event_list, 105	bus
seq64::triggers, 365	seq64::user_settings, 384
add_event	Busses
seq64::sequence, 345, 351	seq64::user_settings, 383
add_long	button
seq64::midi_container, 201	seq64::options, 230
add_note	
seq64::sequence, 351	c_chord_text
add_sequence	seq64, 69
seq64::perform, 253	c_controller_names
add_trigger	seq64, 66
seq64::midifile, 222	c_mainwid_x
seq64::sequence, 345	seq64, 69
add_variable	c_max_instruments
seq64::midi_container, 201	seq64, 69
adj_callback_bpm	c_midi_track_ctrl
seq64::mainwnd, 188	seq64, 67
adj_callback_ss	c_midibus
seq64::mainwnd, 188	seq64, 67
adjust_offset	c_midibus_output_size
seq64::triggers, 370	seq64, 66
adjust_offsets_to_length	c_music_scales
seq64::triggers, 366	seq64, 49

c_scales_policy	click
seq64, 67	seq64::click, 73, 74
c_scales_transpose_dn_neg	client_open
seq64, 68	seq64::jack_assistant, 153
c_scales_transpose_up	clock
seq64, 68	seq64::mastermidibus, 195
c_select_all_notes	seq64::midibus, 214
seq64, 69	clock_e
CYAN_ON_BLACK	seq64, 49
seq64::font, 129	clock_tick_duration_bogus
calculate_base_sizes	seq64, 57
seq64::mainwid, 180	clock_ticks_from_ppqn
category	seq64, 57
seq64::editable_event, 84	collapse
category_channel_message	seq64::perfedit, 238
seq64::editable_event, 82	Color
category_meta_event	seq64::font, 129
seq64::editable_event, 82	cond
category_name	seq64::condition_var, 76
seq64::editable_event, 82	configfile
category_prop_event	seq64::configfile, 77
seq64::editable_event, 82	continue_from
category_system_message	seq64::mastermidibus, 195
seq64::editable_event, 82	seq64::midibus, 214
category_t	control_height
seq64::editable_event, 82	seq64::user_settings, 385
change_event_data_range	controller_active
seq64::sequence, 352	seq64::user_instrument, 372
change_horz	seq64::user_settings, 384
seq64::seqdata, 295	controller_max
seq64::seqevent, 310	seq64::user_instrument, 372
seq64::seqroll, 328	controller_name
change_vert	seq64::user_instrument, 372
seq64::eventslots, 124	seq64::user_settings, 384
channel_count	controllers
seq64::user_midi_bus, 375	seq64::user_instrument_t, 373
channel_max	controllers_active
seq64::user_midi_bus, 375	seq64::user_instrument_t, 373
CharList	convert_t
seq64::midi_list, 203	seq64::seqevent, 311
check_channel	convert_tn
seq64::event, 97	seq64::seqroll, 328
checklen	convert_x
seq64::midifile, 222	seq64::perfroll, 277
choose_ppqn	seq64::seqevent, 311
seq64, 62	convert_xy
clamp_track	seq64::perfroll, 277
seq64::perform, 268	convert_y
clear	seq64::eventslots, 123
seq64::event_list, 106	copy
clear_all	seq64::perfedit, 238
seq64::perform, 252	seq64::triggers, 369
clear_sequence_triggers	copy_definitions
seq64::perform, 253	seq64::user_instrument, 373
clear_triggers	seq64::user_midi_bus, 375
seq64::sequence, 349	copy_events
clear_window	seq64::sequence, 357
seq64::gui_drawingarea_gtk2, 137	copy_selected

coa64::coauoneo 250	seq64::seqroll, 328
seq64::sequence, 350 copy_triggers	draw_events_on_pixmap
seq64::perform, 254	seq64::seqroll, 327
seq64::sequence, 349	draw_key
count	seq64::seqkeys, 315
seq64::editable_events, 90	draw line
seq64::event_list, 105	seq64::gui_drawingarea_gtk2, 137–139
count_selected_events	
seq64::event list, 108	draw_line_on_pixmap seq64::gui_drawingarea_gtk2, 138
create_lash_driver	draw marker on sequence
seq64, 64	seq64::mainwid, 178
create_menus	draw_normal_rectangle_on_pixmap
seq64::seqedit, 303	seq64::gui_drawingarea_gtk2, 142
cut_selected	draw_pixmap_on_window
seq64::sequence, 351	seq64::seqevent, 310
36q0436quence, 331	draw_progress
DRAW_FIN	seq64::perfroll, 276
seq64, 49	draw progress on window
decrement_beats_per_minute	seq64::seqroll, 327
seq64::perform, 263	draw_rectangle
decrement_bottom	seq64::gui_drawingarea_gtk2, 140, 141
seq64::eventslots, 125	draw_rectangle_on_pixmap
decrement_current	seq64::gui drawingarea gtk2, 142
seq64::eventslots, 125	draw_sequence
decrement_selected	seq64::perfnames, 242
seq64::sequence, 353	draw_sequence_on
decrement_top	seq64::perfroll, 277
seq64::eventslots, 125	draw_sequence_on_pixmap
deinit	seq64::mainwid, 178
seq64::jack_assistant, 150	draw_sequence_pixmap_on_window
deinit in	seq64::mainwid, 179
seq64::midibus, 213	draw_sequences_on_pixmap
deinit jack	seq64::mainwid, 179
seq64::perform, 266	draw type
del_trigger	seq64, 49
seq64::sequence, 346	drop event
delete_current_event	seq64::seqevent, 310
seq64::eventslots, 121	dump_setting_summary
delete_lash_driver	seq64::userfile, 393
seq64, 65	dump_summary
delete_sequence	seq64::user settings, 385
seq64::perform, 253	30404u301_30ttilig3, 000
delta_time_us_to_ticks	e_clock_mod
seq64, 56	seq64, 49
do_action	e_clock_off
seq64::seqedit, 304	seq64, 49
double ticks from ppqn	e clock pos
seq64, 58	seq64, 49
draw_background	e deselect
seq64::seqevent, 310	seq64::sequence, 341
draw_drawable_row	e_is_selected
seq64::perfroll, 278	seq64::sequence, 341
draw_event	e_jack_connect
seq64::eventslots, 123	seq64::options, 230
draw_events	e_jack_disconnect
seq64::eventslots, 124	seq64::options, 230
draw_events_on	e_jack_master
seq64::seqdata, 294	seq64::options, 230
seq64::seqevent, 310	e_jack_master_cond
in the second of	→ = ····· -··· ·

04 11 000	et
seq64::options, 230	file_executable
e_jack_start_mode_live	seq64, 61
seq64::options, 230	file_exists
e_jack_start_mode_song	seq64, 60
seq64::options, 230	file_import_dialog
e_jack_transport	seq64::mainwnd, 187
seq64::options, 230	file_is_directory
e_remove_one	seq64, 61
seq64::sequence, 341	file_readable
e_select	seq64, 60
seq64::sequence, 341	file_writable
e_select_one	seq64, 61
seq64::sequence, 341	fill
e_toggle_selection	seq64::midi_container, 200
seq64::sequence, 341	fill_background_pixmap
e_would_select	seq64::perfroll, 276
seq64::sequence, 341	fill_container
EVENT_ANY	seq64::sequence, 356
seq64, 66	fill_top_bar
EVENT_MIDI_SYSEX	seq64::seqedit, 303
seq64, 66	finish
EVENT_NULL_CHANNEL	seq64::perform, 253
seq64, 66	flush
edit_callback_notepad	seq64::mastermidibus, 195
seq64::mainwnd, 188	follow_progress
editable_event	seq64::seqroll, 327
seq64::editable_event, 83	font_render
editable_events	seq64, 65
seq64::editable_events, 89	force_draw
enqueue_draw	seq64::gui_drawingarea_gtk2, 137
seq64::perfedit, 237	seq64::seqkeys, 315
seq64::perfnames, 242	format_timestamp
seq64::perfroll, 278	seq64::editable_event, 85
seq64::perftime, 283	FruityPerfInput
enregister_peer	seq64::perfroll, 279
seq64::perfedit, 237	
errdump	get
seq64::midifile, 226	seq64::midi_container, 201
error message	seq64::midi_list, 203
seq64::jack_assistant, 153	seq64::midi_vector, 210
event	get_beat_width
seq64::event, 96	seq64::sequence, 342
event count	get_clipboard_box
seq64::sequence, 341	seq64::sequence, 351
event_key	get_clock
seq64::event_list::event_key, 102	seq64::mastermidibus, 198
event list	get_data
seq64::event_list, 105	seq64::event, 100
eventedit	get_group_mute_state
seq64::eventedit, 111	seq64::perform, 261
events	get_input
seq64::keybindentry, 158	seq64::mastermidibus, 198
expand	get_keys
seq64::perfedit, 238	seq64::keys_perform, 162
extract_timing_numbers	get_last_tick
seq64, 50	seq64::sequence, 342
30q0+, 00	get_max_tick
file accessible	seq64::perform, 254
seq64, 61	get_max_trigger
•	

seq64::perform, 255	seq64::gui_assistant, 132
seq64::sequence, 349	gui_palette_gtk2
get_maximum	seq64::gui_palette_gtk2, 145
seq64::triggers, 369	gui_window_gtk2
get_measures	seq64::gui_window_gtk2, 147
seq64::seqedit, 302	handla config
get_midi_event	handle_config
seq64::mastermidibus, 196	seq64::lash, 169
get_midi_in_bus_name	handle_event
seq64::mastermidibus, 195	seq64::lash, 169
get_midi_out_bus_name	handle_insert
seq64::mastermidibus, 194	seq64::eventedit, 114
get_minmax_note_events	handle_midi_control
seq64::sequence, 355	seq64::perform, 255 handle_modify
get_name	seq64::eventedit, 114
seq64::sequence, 342	handle_motion_key
get_next_event	-
seq64::sequence, 356	seq64::Seq24PerfInput, 288 handle save
get_next_note_event	seq64::eventedit, 114
seq64::sequence, 355	help check
get_num_selected_events	· -
seq64::sequence, 350	seq64, 59
get_num_selected_notes	highlight
seq64::sequence, 350	seq64::perform, 264
get_rank	home_config_directory
seq64::event, 101	seq64::rc_settings, 286 horizontal_adjust
get_screen_set_notepad	seq64::seqedit, 301
seq64::perform, 255	seq64::seqroll, 327
	5eq045eq1011, 521
get_selected_box	
get_selected_box seq64::sequence, 351	idle progress
-	idle_progress
seq64::sequence, 351	seq64::maintime, 172
seq64::sequence, 351 get_selected_end	seq64::maintime, 172 idle_redraw
seq64::sequence, 351 get_selected_end seq64::triggers, 368	seq64::maintime, 172 idle_redraw seq64::seqdata, 294
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 groups	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white seq64::user_settings, 383	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 groups seq64::keybindentry, 158 grow	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129 seq64::jack_assistant, 150
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 groups seq64::keybindentry, 158 grow seq64::perfedit, 238	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129 seq64::lash, 169
seq64::sequence, 351 get_selected_end	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129 seq64::jack_assistant, 150 seq64::lash, 169 seq64::mastermidibus, 194
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 groups seq64::keybindentry, 158 grow seq64::perfedit, 238 seq64::triggers, 366 grow_selected	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129 seq64::jack_assistant, 150 seq64::lash, 169 seq64::mastermidibus, 194 init_before_show
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 groups seq64::keybindentry, 158 grow seq64::perfedit, 238 seq64::triggers, 366 grow_selected seq64::sequence, 353	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129 seq64::jack_assistant, 150 seq64::lash, 169 seq64::mastermidibus, 194 init_before_show seq64::perfedit, 237
seq64::sequence, 351 get_selected_end	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129 seq64::font, 129 seq64::lash, 169 seq64::mastermidibus, 194 init_before_show seq64::perfedit, 237 seq64::perfroll, 276
seq64::sequence, 351 get_selected_end seq64::triggers, 368 get_selected_start seq64::triggers, 368 get_sequence seq64::perform, 259 get_state seq64::triggers, 367 get_trigger_state seq64::sequence, 346 grid_style_black seq64::user_settings, 383 grid_style_max seq64::user_settings, 383 grid_style_normal seq64::user_settings, 383 grid_style_white seq64::user_settings, 383 groups seq64::keybindentry, 158 grow seq64::perfedit, 238 seq64::triggers, 366 grow_selected seq64::sequence, 353	seq64::maintime, 172 idle_redraw seq64::seqdata, 294 seq64::seqevent, 310 increment seq64::midi_splitter, 206 increment_beats_per_minute seq64::perform, 264 increment_bottom seq64::eventslots, 126 increment_current seq64::eventslots, 125 increment_selected seq64::sequence, 353 increment_top seq64::eventslots, 125 info_message seq64::jack_assistant, 152 init seq64::font, 129 seq64::jack_assistant, 150 seq64::lash, 169 seq64::mastermidibus, 194 init_before_show seq64::perfedit, 237

seq64::midibus, 214	is_midi_control_valid
init_in	seq64::perform, 266
seq64::midibus, 213	is_more_input
init_in_sub	seq64::mastermidibus, 196
seq64::midibus, 214	is_mseq_valid
init_jack	seq64::perform, 267
seq64::perform, 266	is_note_msg
init_out	seq64::event, 98
seq64::midibus, 213	is_one_byte_msg
init_out_sub	seq64::event, 98
seq64::midibus, 213	is_screenset_valid
inner_start	seq64::perform, 266
seq64::perform, 268	is_seq_valid
	seq64::perform, 267
inner_stop	is_sysex_special_id
seq64::perform, 268	seq64::midifile, 226
insert_event	is_two_byte_msg
seq64::eventslots, 120, 121	seq64::event, 98
install_sequence	Sequ4event, 90
seq64::perform, 267	jack assistant
instrument	seq64::jack_assistant, 150
seq64::user_instrument_t, 373	jack_idle_connect
seq64::user_midi_bus, 375	
seq64::user_midi_bus_t, 376	seq64::gui_assistant_gtk2, 133 jack_session_callback
seq64::user_settings, 384	
Instruments	seq64, 64
seq64::user_settings, 383	seq64::jack_assistant, 157
interaction_method_t	jack_shutdown_callback
seq64, 49	seq64, 63
intersect	seq64::jack_assistant, 155
seq64::triggers, 367	jack_sync_callback
intersect_events	seq64, 63
seq64::sequence, 347	seq64::jack_assistant, 156
intersect_notes	seq64::perform, 269
seq64::sequence, 347	jack_timebase_callback
intersect triggers	seq64, 63
seq64::sequence, 347	seq64::jack_assistant, 156
is_active	14
seq64::perform, 259	Key
is_channel_msg	seq64::editable_events, 89
seq64::event, 97	key_name
is_desired_cc_or_not_cc	seq64::keys_perform, 162
	seq64::keys_perform_gtk2, 165
seq64::event, 98	seq64::keys_perform_gtk2, 165 key_press_event
seq64::event, 98 is_dirty_edit	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283
seq64::event, 98 is_dirty_edit seq64::perform, 258	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344 is_dirty_perf	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168 lash_driver seq64, 65
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168 lash_driver
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344 is_dirty_perf	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168 lash_driver seq64, 65
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344 is_dirty_perf seq64::perform, 258	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168 lash_driver seq64, 65 lash_timeout_connect
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344 is_dirty_perf seq64::perform, 258 seq64::sequence, 344	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168 lash_driver seq64, 65 lash_timeout_connect seq64::gui_assistant_gtk2, 133
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344 is_dirty_perf seq64::perform, 258 seq64::sequence, 344 is_dirty_perf seq64::perform, 258 seq64::sequence, 344	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168 lash_driver seq64, 65 lash_timeout_connect seq64::gui_assistant_gtk2, 133 launch
seq64::event, 98 is_dirty_edit seq64::perform, 258 seq64::sequence, 344 is_dirty_main seq64::perform, 258 seq64::sequence, 344 is_dirty_names seq64::perform, 258 seq64::sequence, 344 is_dirty_perf seq64::sequence, 344 is_dirty_perf seq64::sequence, 344 is_edit_sequence seq64::sequence seq64::seqmenu, 320	seq64::keys_perform_gtk2, 165 key_press_event seq64::perftime, 283 keybindentry seq64::keybindentry, 158 keystroke seq64::keystroke, 166, 167 lash seq64::lash, 168 lash_driver seq64, 65 lash_timeout_connect seq64::gui_assistant_gtk2, 133 launch seq64::perform, 252

launch_output_thread	seq64::mainwid, 182
seq64::perform, 265	m_button_play
line_after	seq64::mainwnd, 191
seq64::configfile, 78	m_bw
line_color	seq64::perfedit, 239
seq64::gui_palette_gtk2, 145	m_c_on_b_pixmap
link_new	seq64::font, 130
seq64::event_list, 107	m_category
seq64::sequence, 354	seq64::editable_event, 87
load_events	m_channel
seq64::editable_events, 89	seq64::event, 101
seq64::eventslots, 120	m_channel_count
location	seq64::user_midi_bus, 376
seq64::keybindentry, 158	m_char_list
log2_time_sig_value	seq64::midifile, 227
seq64, 54	m_char_w
long_options	seq64::eventslots, 127
seq64, 69	seq64::perfnames, 243
lookup_keyevent_key	m_clip_mask
seq64::perform, 262	seq64::font, 130
	m_clock_mod
m_32nds_per_quarter	seq64::midibus, 215
seq64::sequence, 360	m_clocks_per_metronome
m_adjust_load_offset	seq64::sequence, 359
seq64::mainwnd, 191	m_control_height
m_allow_two_perfedits	seq64::user_settings, 387
seq64::user_settings, 388	
m_b_on_c_pixmap	m_controller_count
seq64::font, 130	seq64::user_instrument, 373
m_b_on_y_pixmap	m_current_event
seq64::font, 130	seq64::editable_events, 91
m_background	m_current_index
seq64::gui_drawingarea_gtk2, 143	seq64::eventslots, 127
m_background_sequence	m_current_zoom
seq64::sequence, 360	seq64::user_settings, 388
30q0+1.30qu01100, 000	m_data
m_bar_width	
	seq64::event, 101
m_bar_width	seq64::midifile, 227
m_bar_width seq64::maintime, 173 m_beat_width	seq64::midifile, 227 m_disable_reported
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173	seq64::midifile, 227
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209	seq64::midifile, 227 m_disable_reported
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270	seq64::midifile, 227 m_disable_reported seq64::midifile, 227
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height seq64::maintime, 173	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height seq64::maintime, 173
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height seq64::maintime, 173 m_box_width	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height seq64::maintime, 173 m_flash_width
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height seq64::maintime, 173 m_box_width seq64::maintime, 173	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height seq64::maintime, 173 m_flash_width seq64::maintime, 173
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height seq64::maintime, 173 m_box_width seq64::maintime, 173 m_bpm	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height seq64::maintime, 173 m_flash_width seq64::maintime, 173 m_font_h
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height seq64::maintime, 173 m_box_width seq64::maintime, 173 m_bpm seq64::perfedit, 239	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height seq64::maintime, 173 m_flash_width seq64::maintime, 173 m_font_h seq64::font, 130
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height seq64::maintime, 173 m_box_width seq64::maintime, 173 m_bpm seq64::perfedit, 239 m_button	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height seq64::maintime, 173 m_flash_width seq64::maintime, 173 m_font_h seq64::font, 130 m_font_w
m_bar_width seq64::maintime, 173 m_beat_width seq64::maintime, 173 seq64::midi_timing, 209 seq64::perform, 270 m_beats_per_bar seq64::perform, 270 m_beats_per_measure seq64::midi_timing, 208 m_beats_per_minute seq64::mastermidibus, 198 seq64::midi_timing, 208 m_black_pixmap seq64::font, 130 m_box_height seq64::maintime, 173 m_box_width seq64::maintime, 173 m_bpm seq64::perfedit, 239	seq64::midifile, 227 m_disable_reported seq64::midifile, 227 m_divisions seq64::midi_measures, 204 m_drop_x seq64::gui_drawingarea_gtk2, 143 m_error_is_fatal seq64::midifile, 227 m_error_message seq64::midifile, 227 m_file_size seq64::midifile, 227 m_flash_height seq64::maintime, 173 m_flash_width seq64::maintime, 173 m_font_h seq64::font, 130

seq64::user_settings, 387
m_max_sequence
seq64::user_settings, 391
m_max_sets
seq64::perform, 270
seq64::user_settings, 387
m_measure_length
seq64::perftime, 283
m_midi_beat_width
seq64::user_settings, 390
m_midi_beats_per_measure
seq64::user_settings, 390
m_midi_beats_per_minute
seq64::user_settings, 390
m_midi_buses
seq64::user_settings, 386
m_midi_buss_override
seq64::user_settings, 390
m_midi_channel
seq64::sequence, 359
m_midi_parameters
seq64::editable events, 91
m_midi_ppqn
seq64::user_settings, 390
m_modified
seq64::seqmenu, 321
m_modifier
seq64::click, 74
seq64::keystroke, 168
m_moving_seq
seq64::mainwid, 182
m_musical_key
seq64::sequence, 360
m musical scale
seq64::sequence, 360
m_mutex
seq64::sequence, 360
seq64::sequence, 360 m_name_meta
seq64::sequence, 360 m_name_meta seq64::editable_event, 87
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook seq64::options, 230
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook seq64::options, 230 m_number_h
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook seq64::options, 230 m_number_h seq64::seqdata, 296
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook seq64::options, 230 m_number_h seq64::seqdata, 296 m_number_offset_y
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook seq64::options, 230 m_number_h seq64::seqdata, 296 m_number_offset_y seq64::seqdata, 296
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook seq64::options, 230 m_number_h seq64::seqdata, 296 m_number_offset_y
seq64::sequence, 360 m_name_meta seq64::editable_event, 87 m_name_status seq64::editable_event, 87 m_namebox_w seq64::perfnames, 243 m_names_chars seq64::perfnames, 242 m_names_y seq64::perfnames, 243 m_new_format seq64::midifile, 227 m_notebook seq64::options, 230 m_number_h seq64::seqdata, 296 m_number_offset_y seq64::seqdata, 296

0.4	
seq64::perform, 270	seq64::user_settings, 388
m_parent	m_seqedit_key
seq64::editable_event, 86	seq64::user_settings, 388
seq64::perfnames, 242	m_seqedit_scale
seq64::perfroll, 279	seq64::user_settings, 388
seq64::perftime, 283	m_seqkeys_wid
seq64::sequence, 359	seq64::seqedit, 306
m_pixmap	m_seqs
seq64::font, 130	seq64::perform, 269
seq64::gui_drawingarea_gtk2, 143	m_seqs_in_set
m_playback_mode	seq64::perform, 270
seq64::perform, 269	seq64::user_settings, 390
m_playing_notes	m_seqtime_wid
seq64::sequence, 359	seq64::seqedit, 306
m_playscreen_offset	m_sequence
seq64::perform, 269	seq64::editable_events, 91
m_pos	m_sequence_count
seq64::midifile, 227	seq64::perform, 271
seq64::seqedit, 306	m_sequence_max
seq64::seqroll, 329	seq64::perform, 271
m_ppqn	m_setbox_w
seg64::maintime, 174	seq64::eventslots, 127
seq64::mainwnd, 191	seq64::perfnames, 243
seq64::midi_timing, 209	m_sigpipe
seq64::triggers, 370	seq64::mainwnd, 191
m_progress_bar_colored	m_slots_chars
seq64::user_settings, 389	seq64::eventslots, 127
m_progress_bar_thick	m_slots_y
seq64::user_settings, 389	seq64::eventslots, 127
	m_smf0_channels
m_raise	
seq64::sequence, 359	seq64::midi_splitter, 207
m_rank	m_smf0_channels_count
seq64::event_list::event_key, 103	seq64::midi_splitter, 207
m_redraw_period_ms	m_smf0_seq_number
seq64::gui_window_gtk2, 147	seq64::midi_splitter, 207
m_right_marker_tick	m_smf0_splitter
seq64::perftime, 284	seq64::midifile, 228
m_right_tick	m_snap_tick
seq64::perform, 270	seq64::sequence, 359
m_save_user_config	m_starting_tick
seq64::user_settings, 391	seq64::perform, 270
m_screenset_offset	m_status
seq64::mainwid, 182	seq64::event, 101
m_screenset_slots	m_sysex
seq64::mainwid, 182	seq64::event, 101
m_seq_number	m_table
seq64::sequence, 359	seq64::seqedit, 306
m_seqarea_seq_x	m_text_x
seq64::user_settings, 391	seq64::user_settings, 389
m_seqarea_x	m_tick
seq64::user_settings, 391	seq64::maintime, 174
m_seqchars_x	seq64::perform, 270
seq64::user_settings, 389	m_time_beat_width
m_seqdata_wid	seq64::sequence, 359
seq64::seqedit, 306	m_time_beats_per_measure
m_seqedit	seq64::sequence, 359
seq64::seqmenu, 321	m_timestamp
m_seqedit_bgsequence	seq64::event_list::event_key, 103

m_top_index	max_sets
seq64::eventslots, 127	seq64::user_settings, 384
m_us_per_quarter_note	mc_baseline_ppqn
seq64::sequence, 360	seq64::user_settings, 392
m_use_new_font	mc_max_zoom
seq64::user_settings, 388	seq64::user_settings, 391
m_v_page_increment	mc_min_zoom
seq64::perfroll, 279	seq64::user_settings, 391
m_v_perf_page_increment	measures_to_ticks
seq64::user_settings, 389	seq64, 58
m_white_pixmap	measurestring_to_pulses
seq64::font, 130	seq64, 51
m window	merge
seq64::gui_drawingarea_gtk2, 143	seq64::event_list, 106
m_window_redraw_rate_ms	midi_beat_width
seq64::user_settings, 389	seq64::user_settings, 386 midi_beats_per_bar
m_window_x	
seq64::gui_drawingarea_gtk2, 143	seq64::user_settings, 386
seq64::gui_window_gtk2, 147	midi_beats_per_minute
m_x	seq64::user_settings, 386
seq64::click, 74	midi_buss_override
m_xy_offset	seq64::user_settings, 385
seq64::eventslots, 127	midi_control_off
seq64::perfnames, 243	seq64::perform, 255
m_y	midi_control_on
seq64::click, 74	seq64::perform, 255
m_y_on_b_pixmap	midi_control_toggle
seq64::font, 130	seq64::perform, 255
m_zoom	midi_measures_to_pulses
seq64::seqedit, 305	seq64, 52
maintime	midi_ppqn
seq64::maintime, 171	seq64::user_settings, 385
mainwid	midi_splitter
seq64::mainwid, 177	seq64::midi_splitter, 205
mainwid border	midibus
seq64::user_settings, 385	seq64::midibus, 212, 213
mainwid_grid_style_t	midifile
seq64::user_settings, 383	seg64::midifile, 218
mainwid_spacing	midipulse
seq64::user_settings, 385	seq64, 48
mainwnd	min
seq64::mainwnd, 186 mainwnd cols	seq64, 65
_	mod_last_tick
seq64::user_settings, 384	seq64::sequence, 343
mainwnd_key_event	mod_timestamp
seq64::perform, 265	seq64::event, 99
mainwnd_rows	modify
seq64::user_settings, 384	seq64::perform, 252
make_directory	modify_current_event
seq64, 62	seq64::eventslots, 122
mark_all	move
seq64::event_list, 107	seq64::triggers, 369
mark_out_of_range	move_selected
seq64::event_list, 107	seq64::triggers, 368
mark_selected	move_selected_notes
seq64::sequence, 354	seq64::sequence, 351
mastermidibus	move_selected_triggers_to
seq64::mastermidibus, 193	seq64::sequence, 348
•	. ,

move_triggers	seq64::mainwid, 181
seq64::perform, 254	on_focus_out_event
seq64::sequence, 349	seq64::mainwid, 181
	on_grouplearnchange
name_change_callback	seq64::mainwnd, 190
seq64::seqedit, 303	on_key_press_event
name_to_value	seq64::eventedit, 114
seq64::editable_event, 83	seq64::keybindentry, 159
new_file	seq64::mainwnd, 190
seq64::mainwnd, 189	seq64::perfroll, 278
new_sequence	seq64::seqedit, 305
seq64::perform, 252	seq64::seqevent, 312
next	seq64::seqroll, 329
seq64::triggers, 370	on_key_release_event
next_data_line	seq64::mainwnd, 190
seq64::configfile, 77	on_leave_notify_event
next_trigger	seq64::seqkeys, 316
seq64::triggers, 370	on_motion_notify_event
<i>"</i>	seq64::Seq24PerfInput, 288
off_playing_notes	seq64::Seq24SeqEventInput, 290
seq64::sequence, 355	seq64::mainwid, 181
off_queued	seq64::seqdata, 295
seq64::sequence, 343	seq64::seqevent, 311
on_button_press_event	seq64::seqkeys, 315
seq64::Seq24PerfInput, 288	on_move_down
seq64::Seq24SeqEventInput, 289	seq64::eventslots, 126
seq64::Seq24SeqRollInput, 290	on_move_up
seq64::mainwid, 180	seq64::eventslots, 126
seq64::perfroll, 278	on_realize
seq64::seqdata, 295	seq64::eventslots, 126
seq64::seqevent, 311	seq64::gui_drawingarea_gtk2, 143
seq64::seqkeys, 315	seq64::maintime, 173
seq64::seqtime, 332	seq64::mainwid, 180
on_button_release_event	•
seq64::Seq24PerfInput, 288	seq64::perfnames, 242 seq64::perfroll, 278
seq64::Seq24SeqEventInput, 289	seq64::perftime, 283
seq64::Seq24SeqRollInput, 290	•
seq64::mainwid, 181	seq64::seqdata, 295
seq64::perfroll, 278	seq64::seqevent, 311
seq64::seqdata, 295	seq64::seqkeys, 315
seq64::seqevent, 311	seq64::seqtime, 332
seq64::seqkeys, 315	on_scroll_event
seq64::seqtime, 332	seq64::seqdata, 295
on_delete_event	seq64::seqedit, 305
seq64::eventedit, 115	seq64::seqkeys, 316
seq64::mainwnd, 190	seq64::seqroll, 329
seq64::seqedit, 305	on_size_allocate
on_enter_notify_event	seq64::eventslots, 126
seq64::seqkeys, 316	seq64::perfnames, 242
on_expose_event	seq64::seqkeys, 316
seq64::eventslots, 126	open_file
seq64::maintime, 173	seq64::mainwnd, 187
seq64::mainwid, 180	open_performance_edit
seq64::perfnames, 242	seq64::mainwnd, 189
seq64::perfroll, 278	open_performance_edit_2
seq64::perftime, 283	seq64::mainwnd, 189
seq64::seqdata, 295	operator<
on_focus_in_event	seq64::event, 96
seq64::eventslots, 126	seq64::event_list::event_key, 102

seq64::trigger, 361	perform
operator=	seq64::perform, 251
seq64::click, 74	perfroll_key_event
seq64::editable_events, 89	seq64::perform, 265
seq64::event, 96	perftime
seq64::event_list, 105	seq64::perftime, 282
seq64::keystroke, 167	play
seq64::triggers, 364	seq64::mastermidibus, 197
output	seq64::midibus, 214
seq64::jack_assistant, 152	seq64::perform, 259
output_func	seq64::sequence, 345
seq64::perform, 261	seq64::triggers, 365
output_thread_func	play_note_off
seq64, 65	seq64::sequence, 355
1 ,	play_note_on
page_movement	seq64::sequence, 354
seq64::eventslots, 124	
page_topper	playback_key_event
seq64::eventslots, 125	seq64::perform, 265
parse	poll_for_midi
seq64::midifile, 218	seq64::mastermidibus, 196
seq64::optionsfile, 232	pop_redo
seq64::userfile, 393	seq64::sequence, 341
parse_command_line_options	pop_undo
seq64, 60	seq64::sequence, 341
parse_options_files	popup_event_menu
seq64, 59	seq64::seqedit, 304
parse_prop_header	popup_menu
seq64::midifile, 220	seq64::seqmenu, 320
·	popup_midibus_menu
parse_proprietary_track	seq64::seqedit, 304
seq64::midifile, 221	popup_sequence_menu
parse_smf_0	seq64::seqedit, 304
seq64::midifile, 219	popup_tool_menu
parse_smf_1	seq64::seqedit, 304
seq64::midifile, 220	
partial_assign	port_exit seq64::mastermidibus, 197
seq64::sequence, 341	
paste	port_start
seq64::triggers, 368	seq64::mastermidibus, 197
paste_selected	position
seq64::sequence, 351	seq64::jack_assistant, 151
paste_trigger	seq64::midi_container, 201
seq64::sequence, 348	position_jack
pause	seq64::perform, 257
seq64::sequence, 355	pow2
pause_key	seq64::midifile, 221
seq64::perform, 263	ppqn
pause_playing	seq64::mainwnd, 187
seq64::mainwnd, 189	seq64::midi_splitter, 206
seq64::perfedit, 239	seq64::midifile, 219
seq64::perform, 263	ppqn_is_valid
perf_h_page_increment	seq64, 62
seq64::user_settings, 385	print
	seq64::sequence, 344
perf_v_page_increment	
seq64::user_settings, 385	seq64::triggers, 365
perfedit	print_triggers
seq64::perfedit, 236	seq64::sequence, 344
perfnames	private_bus
seq64::perfnames, 242	seq64::user_settings, 386

private_instrument	seq64::gui_drawingarea_gtk2, 139
seq64::user_settings, 386	reset
process_events	seq64::seqdata, 294
seq64::lash, 169	seq64::seqevent, 309
progress_color	seq64::seqroll, 327
seq64::gui_palette_gtk2, 145	seq64::seqtime, 331
prop_item_size	seq64::sequence, 355
seq64::midifile, 226	reset_draw_marker
pulse_length_us	seq64::sequence, 355
seq64, 56	reset_draw_trigger_marker
pulses_to_measurestring	seq64::sequence, 355
seq64, 50	reset_sequences
pulses_to_midi_measures	seq64::perform, 259
seq64, 50	s_global_lash_driver
pulses_to_string	seq64, 69
seq64, 50	SEQ64_SUPER_MASK
pulses_to_timestring	seq64, 48
seq64, 51	save_events
push_trigger_undo	seq64::editable_events, 90
seq64::perform, 254	seq64::eventslots, 122
seq64::sequence, 341	save_file
push_undo	seq64::mainwnd, 190
seq64::sequence, 341	save_playing_state
put	seq64::perform, 262
seq64::midi_container, 201	scroll_adjust
seq64::midi_list, 203	seq64::gui_drawingarea_gtk2, 142
seq64::midi_vector, 210	seq64::gui_window_gtk2, 147
put_event_on_bus	select
seq64::sequence, 357	seq64::triggers, 367
rc	
rc sen64_62	select_action_e
seq64, 62	select_action_e seq64::sequence, 341
seq64, 62 read_byte_array	select_action_e seq64::sequence, 341 select_all
seq64, 62 read_byte_array seq64::midifile, 223	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350
seq64, 62 read_byte_array seq64::midifile, 223 read_long	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::midifile, 222 redraw seq64::seqevent, 309 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106 seq64::sequence, 358	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::eventslots, 123 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106 seq64::sequence, 358 seq64::triggers, 367	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 348
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 349
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqevent, 307 remove seq64::event_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all seq64::sequence, 358	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 349 selected_trigger_start seq64::sequence, 348 seq64, 41 adjustment_dummy, 66
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all seq64::sequence, 358 remove_marked	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 349 selected_trigger_start seq64::sequence, 348 seq64, 41 adjustment_dummy, 66 beats_per_minute_from_tempo, 55
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all seq64::sequence, 358 remove_marked seq64::sequence, 358	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 349 selected_trigger_start seq64::sequence, 348 seq64, 41 adjustment_dummy, 66 beats_per_minute_from_tempo, 55 c_chord_text, 69
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all seq64::sequence, 358 remove_marked seq64::sequence, 354 render_string	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 348 seq64, 41 adjustment_dummy, 66 beats_per_minute_from_tempo, 55 c_chord_text, 69 c_controller_names, 66
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::midifile, 222 redraw seq64::seqvent, 309 seq64::seqvent, 309 seq64::seqvent_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all seq64::sequence, 358 remove_marked seq64::sequence, 354 render_string seq64::gui_drawingarea_gtk2, 139	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 348 seq64, 41 adjustment_dummy, 66 beats_per_minute_from_tempo, 55 c_chord_text, 69 c_controller_names, 66 c_mainwid_x, 69
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::mainwid, 177 seq64::seqevent, 309 seq64::seqroll, 327 remove seq64::event_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all seq64::sequence, 358 remove_marked seq64::sequence, 354 render_string seq64::gui_drawingarea_gtk2, 139 render_string_on_drawable	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 348 seq64, 41 adjustment_dummy, 66 beats_per_minute_from_tempo, 55 c_chord_text, 69 c_controller_names, 66 c_max_instruments, 69
seq64, 62 read_byte_array seq64::midifile, 223 read_long seq64::midifile, 222 read_seq_number seq64::midifile, 224 read_track_name seq64::midifile, 224 read_varinum seq64::midifile, 222 redraw seq64::midifile, 222 redraw seq64::seqvent, 309 seq64::seqvent, 309 seq64::seqvent_list, 106 seq64::sequence, 358 seq64::triggers, 367 remove_all seq64::sequence, 358 remove_marked seq64::sequence, 354 render_string seq64::gui_drawingarea_gtk2, 139	select_action_e seq64::sequence, 341 select_all seq64::sequence, 350 select_event seq64::sequence, 350 select_events seq64::sequence, 350 select_group_mute seq64::perform, 256 select_mute_group seq64::perform, 256 select_note_events seq64::sequence, 349 select_trigger seq64::sequence, 346 selected_trigger_end seq64::sequence, 349 selected_trigger_start seq64::sequence, 348 seq64, 41 adjustment_dummy, 66 beats_per_minute_from_tempo, 55 c_chord_text, 69 c_controller_names, 66 c_mainwid_x, 69

c_midibus_output_size, 66	seq_modifier_t, 48
c_music_scales, 49	seq_scroll_direction_t, 48
c_scales_policy, 67	shorten_file_spec, 53
c_scales_transpose_dn_neg, 68	string_is_void, 54
c_scales_transpose_up, 68	string_not_void, 53
c_select_all_notes, 69	string_to_midibyte, 53
choose_ppqn, 62	string_to_pulses, 52
clock_e, 49	strings_match, 54
clock_tick_duration_bogus, 57	tempo_from_beats_per_minute, 55
clock_ticks_from_ppqn, 57	tempo_to_bytes, 55
create_lash_driver, 64	ticks_to_delta_time_us, 57
DRAW_FIN, 49	timestring_to_pulses, 52
delete_lash_driver, 65	to_string, 60
delta_time_us_to_ticks, 56	versiontext, 69
double_ticks_from_ppqn, 58	write_options_files, 60
draw_type, 49	zoom_power_of_2, 55
e_clock_mod, 49	seq64::AbstractPerfInput, 71
e_clock_off, 49	seq64::Seq24PerfInput, 287
e_clock_pos, 49	handle_motion_key, 288
EVENT_ANY, 66	on_button_press_event, 288
EVENT_MIDI_SYSEX, 66	on_button_release_event, 288
EVENT_NULL_CHANNEL, 66	on_motion_notify_event, 288
extract_timing_numbers, 50	set_adding, 288
file_accessible, 61	seq64::Seq24SeqEventInput, 289
file_executable, 61	on_button_press_event, 289
file_exists, 60	on_button_release_event, 289
file is directory, 61	on_motion_notify_event, 290
file_readable, 60	set_adding, 289
file_writable, 61	seq64::Seq24SeqRollInput, 290
font_render, 65	on_button_press_event, 290
help_check, 59	on_button_release_event, 290
interaction method t, 49	set_adding, 290
jack session callback, 64	seq64::automutex, 72
jack_shutdown_callback, 63	seq64::click, 72
jack_sync_callback, 63	click, 73, 74
jack_timebase_callback, 63	m button, 74
lash_driver, 65	m modifier, 74
log2_time_sig_value, 54	
long_options, 69	m y, 74
make_directory, 62	operator=, 74
measures_to_ticks, 58	seg64::condition_var, 75
measurestring to pulses, 51	cond, 76
midi_measures_to_pulses, 52	seq64::configfile, 76
midipulse, 48	configfile, 77
min, 65	line after, 78
output thread func, 65	m_line, 78
parse_command_line_options, 60	next_data_line, 77
parse_options_files, 59	seq64::editable_event, 78
ppqn_is_valid, 62	analyze, 85
pulse_length_us, 56	category, 84
pulses_to_measurestring, 50	category_channel_message, 82
pulses_to_midi_measures, 50	category_meta_event, 82
pulses_to_string, 50	category_name, 82
pulses_to_timestring, 51	category_prop_event, 82
rc, 62	category_prop_event, 82 category_system_message, 82
s_global_lash_driver, 69	category_t, 82
SEQ64 SUPER MASK, 48	editable_event, 83
seq_event_type_t, 48	format_timestamp, 85
Joq_event_type_t, 40	iomai_imesiamp, 00

m_category, 87	any_selected_notes, 108
m_format_timestamp, 87	clear, 106
m_name_meta, 87	count, 105
m_name_status, 87	count_selected_events, 108
m_parent, 86	event_list, 105
name_to_value, 83	link_new, 107
set_status_from_string, 85	m_is_modified, 108
sm_category_arrays, 86	mark_all, 107
sm_category_names, 86	mark_out_of_range, 107
sm_channel_event_names, 86	merge, 106
sm_meta_event_names, 86	operator=, 105
sm_prop_event_names, 86	remove, 106
sm_system_event_names, 86	unmodify, 106
stock_event_string, 85	verify_and_link, 107
time_as_measures, 84	seq64::event_list::event_key, 101
time_as_minutes, 84	event key, 102
timestamp, 84	m_rank, 103
timestamp_format_t, 82	m_timestamp, 103
timestamp_format_t, 82	operator<, 102
· -	•
timestamp_pulses, 82	seq64::eventedit, 108
timestamp_time, 82	~eventedit, 112
value_to_name, 83	eventedit, 111
seq64::editable_events, 87	handle_insert, 114
add, 90	handle_modify, 114
count, 90	handle_save, 114
editable_events, 89	on_delete_event, 115
Key, 89	on_key_press_event, 114
load_events, 89	set_dirty, 113
m_current_event, 91	set_event_category, 113
m_midi_parameters, 91	set_event_data_0, 113
m_sequence, 91	set_event_data_1, 113
operator=, 89	set_event_name, 113
save_events, 90	set_event_timestamp, 113
seq64::event, 91	set_seq_ppqn, 112
\sim event, 96	set_seq_time_sig, 112
append_sysex, 100	set_seq_title, 112
check_channel, 97	v_adjustment, 113, 114
event, 96	seq64::eventslots, 115
get_data, 100	change_vert, 124
get_rank, 101	convert_y, 123
is_channel_msg, 97	decrement_bottom, 125
is_desired_cc_or_not_cc, 98	decrement_current, 125
is_note_msg, 98	decrement_top, 125
is_one_byte_msg, 98	delete_current_event, 121
is_two_byte_msg, 98	draw_event, 123
m_channel, 101	draw_events, 124
m_data, 101	increment_bottom, 126
m_has_link, 101	increment current, 125
m_status, 101	increment_top, 125
m_sysex, 101	insert event, 120, 121
mod_timestamp, 99	load_events, 120
operator<, 96	m_char_w, 127
operator=, 96	m_current_index, 127
set channel, 100	m setbox w, 127
set_data, 100	m_slots_chars, 127
set_status, 99	m_slots_y, 127
seq64::event_list, 103	m_top_index, 127
add, 105	m_xy_offset, 127
444, 100	xy_550t, 121

modify_current_event, 122	set_line, 137
on_expose_event, 126	seq64::gui_drawingarea_gtk2::rect, 286
on_focus_in_event, 126	seq64::gui_palette_gtk2, 144
on_move_down, 126	gui_palette_gtk2, 145
on_move_up, 126	line_color, 145
on_realize, 126	progress_color, 145
on_size_allocate, 126	seq64::gui_window_gtk2, 146
page_movement, 124	gui_window_gtk2, 147
page_topper, 125	m_redraw_period_ms, 147
save_events, 122	m_window_x, 147
select_event, 123	scroll_adjust, 147
set_current_event, 120	seq64::jack_assistant, 148
set_text, 123	∼jack_assistant, 150
seq64::font, 127	client_open, 153
BLACK_ON_CYAN, 129	deinit, 150
BLACK ON YELLOW, 129	error_message, 153
BLACK, 129	info_message, 152
CYAN ON BLACK, 129	init, 150
Color, 129	jack_assistant, 150
init, 129	jack_session_callback, 157
m_b_on_c_pixmap, 130	jack shutdown callback, 155
m_b_on_y_pixmap, 130	jack_sync_callback, 156
m_black_pixmap, 130	jack timebase callback, 156
m_c_on_b_pixmap, 130	output, 152
m_clip_mask, 130	position, 151
m_font_h, 130	session_event, 151
m_font_w, 129	set_beats_per_minute, 150
m_pixmap, 130	set_position, 155
m_white_pixmap, 130	set_ppqn, 152
m_y_on_b_pixmap, 130	show_position, 154
render_string_on_drawable, 129	show_position, 104
WHITE, 129	sm_status_pairs, 157
YELLOW_ON_BLACK, 129	start, 151
seq64::gui assistant, 131	stop, 151
gui assistant, 132	•
seq64::gui_assistant_gtk2, 132	sync, 155 seq64::jack_scratchpad, 157
jack_idle_connect, 133	seq64::keybindentry, 157
lash_timeout_connect, 133	events, 158
sm_internal_keys, 134	groups, 158
seq64::gui_drawingarea_gtk2, 134	keybindentry, 158
clear window, 137	
-	location, 158
draw_line, 137–139	m_key, 159
draw_line_on_pixmap, 138 draw_normal_rectangle_on_pixmap, 142	on_key_press_event, 159
	set, 159
draw_rectangle, 140, 141	type, 158
draw_rectangle_on_pixmap, 142	seq64::keys_perform, 159
force_draw, 137	~keys_perform, 161
m_background, 143	get_keys, 162
m_drop_x, 143	key_name, 162
m_foreground, 143	m_key_bpm_up, 163
m_mainperf, 143	m_key_show_ui_sequence_number, 163
m_pixmap, 143	set_all_key_events, 162
m_window, 143	set_all_key_groups, 162
m_window_x, 143	set_key_event, 162
on_realize, 143	set_key_group, 163
render_string, 139	set_keys, 161
render_string_on_pixmap, 139	show_ui_sequence_key, 162
scroll_adjust, 142	show_ui_sequence_number, 162

seq64::keys_perform_gtk2, 163		
key_name, 165 set_all_key_evorts, 165 set_all_key_evorts, 165 set_all_key_evorts, 165 set_all_key_evorts, 165 set_all_key_evorts, 165 seq64::keys_berform_transfer, 165 seq64::seystroke, 166, 167 m_is_press_t167 m_key, 167 m_key, 167 m_key, 167 m_modifier, 168 operatore, 167 seq64::lash, 168 handle_config, 169 handle_event, 169 init, 169 init, 169 init, 169 init, 169 seq64::maintime, 169 idle_progress, 172 m_bar_width, 173 m_bar_width, 173 m_bar_width, 173 m_bar_width, 173 m_bar_width, 173 m_lash_height, 173 m_calculate_base_sizes, 180 draw_marker_on_sequence_pixmap_n_window, 179 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 178 m_button_press_event, 180 on_button_press_event, 181 on_expose_event, 182 mainwid, 177 set_expose_event, 183 on_expose_eve	seq64::keys_perform_gtk2, 163	seq64::mainwnd, 182
set_all_key_events, 165 seq64:keyspromp, 165 seq64:keysprome, 166 seq64:keysprome, 166 is_letter, 167 m_is_pross, 167 m_is_pross, 167 m_modifier, 168 operator=, 167 seq64:lsah, 168 handle_config, 169 handle_event, 169 init, 169 lash, 168 process_events, 169 set_alsa_client_id, 169 seq64:maintime, 169 idle_progress, 172 m_bar_width, 173 m_bar_width, 173 m_bat_width, 173 m_bat_width, 173 m_lash_width, 173 m_seq64:maintiwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_pixmap, on_window, 179 draw_sequence_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_on_fiset, 182 m_screenset_offset, 182 m_sc	·	about_dialog, 187
set_all_key_groups, 155 seq64::keys_perform_transfer, 165 seq64::keys_perform_transfer, 165 seq64::keys_perform_transfer, 165 seq64::keys_perform_transfer, 165 seq64::keys_perform_transfer, 165 seq64::spsystroke, 166 is_letter, 167 keystroke, 166, 167 m_key, 167 m_key, 167 m_key, 167 m_moving_ter, 168 operator=, 167 seq64::lash, 168 operator=, 169 handle_event, 169 int, 169 handle_event, 169 int, 169 seq64::maintime, 169 idle_progress, 172 m_bar_width, 173 m_beat_width, 173 m_beat_width, 173 m_beat_width, 173 m_lesh_height, 173 m_lash_height, 173 m_lash_height, 173 m_lash_width, 173 m_lash_height, 173 m_lash_width, 173 m_lash_neight, 174 m_aintime, 171 on_expose_event, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_noving_seq, 182 m_screenset_offset, 182 m_noving_seq, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_offset, 181 on_noution_notity_event, 181 on_noution_notity_event, 181 on_notion_notity_event, 181 on_notion_not	key_name, 165	adj_callback_bpm, 188
seq64::keystroke, 166 is_letter, 167 keystroke, 166, 167 m_is_press, 167 m_key, 167 m_key, 167 m_modifier, 168 operator=, 167 seq64::ksh, 168 handle_config, 169 handle_event, 169 init, 169 lash, 168 process_events, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 173 m_bat_width, 173 m_bat_width, 173 m_bat_width, 173 m_bat_width, 173 m_lox_height, 173 m_lox_height, 173 m_lox_height, 173 m_lox_minume, 169 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_slots, 182 m_screenset_slots, 182 mainwid, 177 on_extopos_event, 181 on_rocus_out_event, 181 on_rocus_out_event	set_all_key_events, 165	adj_callback_ss, 188
seq64::keystroke, 166 is letter, 167 keystroke, 166, 167 m_ls_press, 167 m_key, 167 m_modifier, 168 operator=, 167 seq64::lash, 168 handle_config, 169 handle_event, 169 lash, 168 process_events, 169 set_alsa_client_id, 173 m_beat_width, 173 m_beat_width, 173 m_box_height, 173 m_box_height, 173 m_lox_width, 173 m_lox_width, 173 m_lox_midth, 173 m_flash_height, 173 m_flash_height, 173 m_ox_mose_event, 180 on_realize, 177 seq64:::maintime, 171 on_expose_event, 173 on_realize, 176 seq64:::maintime, 171 on_expose_event, 173 on_realize, 176 on_button_press_event, 180 on_button_press_event, 181 on_on_button_press_event, 181 on_nexpose_event, 181 o	set_all_key_groups, 165	edit_callback_notepad, 188
is_letter, 167 keystroke, 166, 167 m_is_press, 167 m_key, 167 m_key, 167 m_key, 167 m_key, 167 m_modifier, 168 operator=, 167 seq64::lash, 168 handle_cordig, 169 handle_event, 169 init, 169 init, 169 jon_key_release_event, 190 on_key_release_event, 190	seq64::keys_perform_transfer, 165	file_import_dialog, 187
is_letter, 167 keystroke, 166, 167 m_is_press, 167 m_key, 167 m_key, 167 m_key, 167 m_key, 167 m_modifier, 168 operator=, 167 seq64::lash, 168 handle_cordig, 169 handle_event, 169 init, 169 init, 169 jon_key_release_event, 190 on_key_release_event, 190	seg64::keystroke, 166	m adjust load offset, 191
keystroke, 166, 167 m_is_press, 167 m_key, 167 m_modifier, 168 m_modifier, 168 operator=, 167 seq64::lash, 168 handle_config, 169 handle_cvent, 169 init, 169 lash, 168 process_events, 169 set_ais_dient_id, 169 set_ais_dient_id, 169 idle_progress, 172 m_bar_width, 173 m_beat_width, 173 m_box_height, 173 m_box_height, 173 m_pox_width, 173 m_flash_neight, 173 m_pox_bez_event, 173 on_realize, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_moriton_press_event, 181 on_focus_in_event, 181 on_focus_out_event, 181 on_realize, 180 redraw, 177 set_from_xy, 179 set_sreenset, 177 timeout, 179 set_sreenset_on_pixmap, 179 set_sreenset, 180 on_focus_out_event, 181 on_realize, 180 redraw, 177 set_from_xy, 179 set_sreenset_on_pixmide, 179 set_best_per_minute, 194 set_popn, 195 set_lase, 191 m_mpan, 191 m_sigpipe, 191 mainwnd, 186 new_file, 189 on_glete_event, 190 on_sev_press_event, 190 on_key_press_event, 190 on_key_press_event, 190 on_levey_relate, 190		
m_is_press, 167 m_key, 167 m_key, 167 m_modifier, 168 operator=, 167 seq84::lash, 168 handle_config, 169 handle_config, 169 handle_event, 169 int, 168 process_events, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 173 m_bar_width, 173 m_bar_width, 173 m_box_leight, 173 m_box_leight, 173 m_flash_width, 173 m_flash_width, 173 m_flash_width, 173 m_flash_width, 173 m_flash_width, 173 m_flash_width, 173 m_sequence_or_or_pixmap, 179 m_sigpipe, 191 mainwid, 180 on_key_release_event, 190 on_key_press_event, 190 on_key_press		
m_key, 167 m_modifier, 168 operators, 167 seq64::lash, 168 handle_config, 169 handle_event, 169 init, 169 lash, 168 process_event, 169 set_alsa_client_id, 189 open_performance_edit, 189 open_performance_edit, 189 open_performance_edit, 189 open_performance_edit, 189 set_inga_e, 188 signal_action, 190 start_playing, 189 stop_playing, 189 stop_playing, 189 stop_playing, 189 timer_callback, 188 toggle_playing, 189 timer_callback, 188 toggle_playing, 189 update_window_title, 189 set_olock, 195 continue_from, 195 flush, 195 flush, 195 set_input, 196 m_beats_per_minute, 198 mastermidibus, 193 play, 197 on_button_press_event, 180 on_button_press_event, 181 on_expose_event, 180 on_button_press_event, 180 on_button_press_event, 180 on_button_press_event, 180 on_button_press_event, 181 on_expose_event, 180 on_button_press_event, 181 on_expose_event, 181 on_expose_event, 181 on_focus_in_event, 181 on_focus_in_eve		
m_modifier, 168 operator=, 167 seq64::ash, 168 handle_config, 169 handle_event, 169 init, 169 lash, 168 process_events, 169 set_alsa_client_id, 169 seq64::maintime, 169 idle_progress, 172 m_bar_width, 173 m_bar_width, 173 m_box_height, 173 m_box_height, 173 m_flash_height, 173 m_flash_height, 173 m_flash_width, 173 m_poqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_moving_seq, 182 m_moving_seq, 182 m_moving_seq, 182 m_mindind, 177 on_button_release_event, 181 on_focus_in_event, 181 on_focus_in_event, 181 on_focus_in_event, 181 on_motion_notify_event, 181 on_mealize, 180 oredraw_narker_on_sequence, 181 on_focus_in_event, 181 on_focus_in_event, 181 on_focus_in_event, 181 on_motion_notify_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_form_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178	_ _	
operator=, 167 seq64:ilash, 168 handle_config, 169 handle_event, 169 init, 169 init, 169 jash, 168 process_events, 169 set_alsa_client_id, 169 popen_performance_edit_2, 189 popen_performance_edit_2, 189 pause_playing, 189 pause_playing, 189 pause_playing, 189 pause_playing, 189 pause_playing, 189 set_image_nl88 signal_action, 190 start_playing, 188 stop_playing, 188 stop_playing, 188 stop_playing, 188 stoggle_playing, 189 update_window_title, 189 seq64:::maintime, 171 on_expose_event, 173 on_realize, 173 seq64:::maintime, 174 calculate_base_sizes, 180 draw_sequence_on_pixmap_on_window, 179 draw_sequence_on_pixmap_on_window, 179 draw_sequence_on_pixmap_n178 draw_sequence_on_pixmap_n178 draw_sequence_on_pixmap_n179 m_button_down, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 on_button_press_event, 180 on_focus_in_event, 181 on_exopose_event, 180 on_focus_in_event, 181 on_focus_out_event, 181 on_focus_out_event, 181 on_motion_notity_event, 181 on_realize, 180 redraw, 177 set_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_markers, 178 update_markers, 178 update_sequences_on_window, 178	_ ·	_ • • •
seq64::lash, 168 handle_config, 169 handle_event, 169 init, 169 lash, 168 process_events, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 seq64::maintime, 169 idle_progress, 172 m_bar_width, 173 m_beat_width, 173 m_box_width, 173 m_flash_width, 174 maintime, 171 on_expose_event, 173 on realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 180 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_focus_out_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 up		
handle_config, 169 handle_event, 169 init, 169 lash, 168 process_events, 169 set_alsa_client_id, 189 set_alsa_client_id, 169 spet_alsa_lient_id, 169 set_alsa_client_id, 169 spet_alsa_lient_id, 169 set_alsa_client_id, 169 spet_alsa_lient_id, 169 set_alsa_client_id, 169 set_alsa_clent_id, 169 set_alsa_clent_isa_floop set_alsa_client_id, 169 set_alsa_clent_isa_floop set_al	·	
handle_event, 169 int, 169 int, 169 lash, 168 process_events, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_width, 173 m_bar_width, 173 m_box_leight, 173 m_box_leight, 173 m_box_width, 173 m_flash_height, 173 m_flash_height, 173 m_flash_width, 173 m_flash_width, 173 m_flash_width, 173 m_paqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_realize, 180 redraw, 177 seq_form_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 undate_sequence_on_window, 178 on_realize, 180 redraw, 177 set_from_xy, 179 set_screenset_on_window, 178 undate_sequence_on_window, 178 on_key_release_event, 190 on_key_release_event, 180 open_performance_edit, 189 open_performance_edit, 29 set_image, 188 signal_action, 190 set_image, 188 stop_playing, 189 pudate_sevent, 189 open_performance_edit_2, 189 pause_playing, 189 pause_playing, 189 pause_playing, 189 pause_playing, 189 timer_calback, 188 toggle_playing, 189 update_window_title, 189 set_lneq. set_image, 182 file, 190 set_image, 188 top_playing, 189 update_yinde,	·	
init, 169 lash, 168 process_events, 169 set_alsa_client_id, 169 pause_playing, 189 pause_p	-	
lash, 168 process_events, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 set_alsa_client_id, 169 ppen_performance_edit, 189 pause_playing, 189 ppqn, 187 save_file, 190 set_image, 188 signal_action, 190 start_playing, 188 stop_playing, 188 stop_playing, 188 stop_playing, 188 stoggle_playing, 188 stoggle_playing, 189 update_window_title, 189 seq64::mastermidibus, 191 clock, 195 continue_from, 195 flush, 195 get_clock, 198 get_midi_event, 196 get_midi_in_bus_name, 195 get_midi_event, 196 get_midi_in_bus_name, 195 get_midi_event, 196 get_midi_in_bus_name, 195 get_midi_out_bus_name, 194 init, 194 init_clock, 196 is_more_input, 198 mastermidibus, 193 play, 197 poll_for_midi, 196 port_exit, 197 port_start, 197 set_beats_per_minute, 194 set_sequence_input, 196 start, 197 set_beats_per_minute, 194 set_sequence_input, 196 start, 199 pause_playing, 189 set_image, 188 signal_action, 190 start_playing, 188 stop_playing, 188 stop_playing, 189 update_window_title, 189 seq64::mastermidibus, 191 ~mastermidibus, 194 clock, 195 continue_from, 195 flush, 195 get_mid_in_bus_name, 195 get_mid_in_bus_name, 195 get_mid_in_bus_name, 195 get_mid_iout_bus_name, 196 in	- · · · · · · · · · · · · · · · · · · ·	
process_events, 169 set_alsa_client_id, 169 seq64:::maintime, 169 idle_progress, 172 m_bar_width, 173 m_beat_width, 173 m_beat_width, 173 m_box_width, 173 m_flash_height, 173 m_flash_height, 173 m_flash_width, 173 m_flash_width, 173 m_popn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 on_button_press_event, 180 on_button_release_event, 181 on_focus_out_event, 181 on_focus_out_event, 181 on_focus_out_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_markers, 178 update_sequences_on_window, 178 open_performance_edit_2, 189 open_performance_edit_2, 189 open_performance_edit_2, 189 pause_playing, 189 ste_image, 188 stop_playing, 189 itmer_callback, 188 toggle_playing, 188 stop_playing, 189 itmer_callback, 188 toggle_playing, 198 star_playing, 188 stop_playing, 189 star_playing, 188 stop_playing, 189 toggle_playing, 189 toggle_playing, 189 toggle_playing, 196 start_playing, 188 stop_playing, 189 toggle_playing, 198 toggle_playing, 19 seq.fom_2, 180 toggle_playing, 198 toggle_playing, 198 toggle_playing, 198 toggle_playing, 198 toggle_playing, 198 toggle_playin		
set_alsa_client_id, 169 seq64:::maintime, 169 idle_progress, 172 m_bar_width, 173 m_beat_width, 173 m_box_height, 173 m_flash_height, 173 m_flash_width, 173 m_popqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64:::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 178 m_screenset_offset, 182 m_moving_seq, 182 mainwid, 177 on_button_press_event, 180 on_button_press_event, 180 on_button_press_event, 181 on_motion_noitfy_event, 181 on_motion_noitfy_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_markers		• —
seq64::maintime, 169 idle_progress, 172 m_bar_width, 173 m_beat_width, 173 m_box_height, 173 m_box_width, 173 m_flash_height, 173 m_flash_width, 174 maintime, 171 on_expose_event, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_screenset_offset, 182 m_iscreenset_offset, 182 mon_button_press_event, 180 on_button_press_event, 181 on_focus_out_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update	• —	. — —
idle_progress, 172 m_bar_width, 173 m_beat_width, 173 m_box_height, 173 m_box_width, 173 m_box_width, 173 m_box_width, 173 m_box_width, 173 m_flash_height, 173 m_flash_height, 173 m_ppqn, 174 m_itck, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 179 draw_sequence_on_pixmap, 179 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 on_button_press_event, 180 on_button_press_event, 181 on_expose_event, 181 on_expose_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 ind 187 save_file, 190 set_image, 188 signal_action, 190 set_image, 188 signal_action, 190 set_image, 188 signal_action, 190 set_image, 188 signal_action, 190 start_playing, 188 stop_playing, 189 timer_callback, 188 togpel_paying, 189 timer_callback, 188 togpel_paying, 189 timer_callback, 188 togpel_paying, 189 timer_callback, 188 togpel_paying, 189 timer_callback, 188 top_playing, 189 timer_callback, 188 top_playing, 189 image, 180 image, 180 image, 180 image, 180 image, 180 stop_playing, 189 timer_callback, 188 top_playing, 189 timer_callback, 188 top_playing, 189 timer_callback, 188 top_playing, 189 image, 182 image, 182 fle, 189 stop_playing, 189 image, 182 fle, 189 seq_fex:mastermidibus, 191 ~mastermidibus, 191 ~mastermidibus, 191 ~mastermidibus, 192 get_midi_event, 196 get_midi_event, 196 is_more_input, 198 im_lock, 196 is_more_input, 196 is_more_input, 196 is_more_input, 196 is_more_input, 196 i		. – – – –
m_bar_width, 173 m_beat_width, 173 m_beat_width, 173 m_box_height, 173 m_box_width, 173 m_flash_height, 173 m_flash_height, 173 m_flash_width, 173 m_flash_width, 173 m_ppqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequences_on_pixmap, 179 m_button_down, 182 m_screenset_slots, 182 m_screenset_slots, 182 mainwid, 177 on_button_press_event, 181 on_focus_out_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 set_inaue, 188 signal_action, 190 set_image, 188 stop_playing, 188 toggle_playing, 189 timer_callback, 184 toggle_playing, 189 togle_playing, 189 togle_play		
m_beat_width, 173 set_image, 188 m_box_height, 173 signal_action, 190 m_box_width, 173 start_playing, 188 m_flash_height, 173 stop_playing, 189 m_flash_width, 173 timer_callback, 188 m_ppqn, 174 timer_callback, 188 m_indow, 171 timer_callback, 188 togle_playing, 189 update_indow_title, 189 seq64:::mastermidibus, 191 clock, 195 calculate_base_sizes, 180 flush, 195 draw_marker_on_sequence, 178 get_clock, 198 draw_sequence_pixmap, 178 get_input, 198 draw_sequence_pixmap, 178 get_midi_in_bus_name, 195		
m_box_height, 173 signal_action, 190 m_box_width, 173 start_playing, 188 m_flash_height, 173 stop_playing, 189 m_flash_width, 173 timer_callback, 188 m_ppqn, 174 toggle_playing, 189 m_tick, 174 update_window_title, 189 maintime, 171 seq64::mastermidibus, 191 on_expose_event, 173 clock, 195 on_realize, 173 continue_from, 195 seq64::mastermidibus, 191 continue_from, 195 calculate_base_sizes, 180 flush, 195 draw_marker_on_sequence, 178 get_clock, 195 draw_sequence_pixmap, 178 get_midi_event, 196 draw_sequence_pixmap_on_window, 179 get_midi_event, 196 draw_sequences_on_pixmap, 179 get_midi_event, 196 m_button_down, 182 get_midi_event, 196 m_screenset_offset, 182 init, 194 m_screenset_slots, 182 init_clock, 196 m_screenset_slots, 182 m_beats_per_minute, 198 on_button_release_event, 181 pol_for_midi, 196 on_focus_in_event, 181 port_exit, 197 on_realize, 180 set_beats_per_minute, 194 <td>m_bar_width, 173</td> <td>save_file, 190</td>	m_bar_width, 173	save_file, 190
m_box_width, 173 m_flash_height, 173 m_flash_height, 173 m_flash_width, 173 m_ppqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 mainwid, 177 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_markers, 178 update_sequences_on_window, 178 start_playing, 188 stop_playing, 189 timer_callback, 188 togple_playing, 188 stop_playing, 188 stop_playing, 188 stop_playing, 188 stop_playing, 188 timer_callback, 188 togple_playing, 188 ttopplaying, 188 togplaying, 189 timer_callback, 188 togplaying, 188 togplaying, 189 timer_callback, 188 togpleylaying, 189 update_marker, 188 toggle_playing, 18 continue_callbaches, 191 cock, 195 continue_callea. ped4::mastermidibus, 191 cock, 195 continue_callea. ped4::mastermidibus, 193 get_clock, 195 get_clock, 196 init, 196 pet_mid_iout_lous_name, 195 get_mid_iout_lous_name, 195 get_mid_iout_lous_name	m_beat_width, 173	set_image, 188
m_flash_height, 173 m_flash_width, 173 m_flash_width, 173 m_ppqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_slots, 182 mainwid, 177 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 set_bats_per_minute, 196 stop, 195 stop, 195 stop, 195 sysex, 197	m_box_height, 173	signal_action, 190
m_flash_width, 173 m_ppqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::masiermidibus, 191 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_pixmap_on_window, 179 draw_sequences_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_offset, 182 mainwid, 177 on_button_press_event, 180 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 180 on_button_release_event, 181 on_focus_in_event, 181 on_focus_out_event, 181 on_redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 timer_callback, 188 toggle_playing, 189 update_window_title, 189 seq64::mastermidibus, 191 ocotok, 195 seq64::mastermidibus, 194 clock, 195 flush, 195 get_clock, 198 get_inid_event, 196 get_mid_event, 196 get_mid_in_bus_name, 195 get_mid_io_ubus_name, 195 get_mid_io_ubus_name, 195 get_mid_io_utbus_name, 195 get_mid_io_ubus_name,	m_box_width, 173	start_playing, 188
m_ppqn, 174 m_tick, 174 maintime, 171 on_expose_event, 173 on_ealize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 mainwid, 177 on_expose_event, 180 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_redraw, 177 set_input, 197 set_screenset, 177 timeout, 179 update_markers, 178 update_markers, 178 update_sequences_on_window, 178 toggle_playing, 189 update_window_title, 189 seq64::mastermidibus, 191 ~mastermidibus, 194 clock, 195 flush, 195 get_midi_event, 198 get_input, 198 get_input, 198 get_midi_event, 196 get_midi_in_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_midi_event, 196 get_midi_in_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_midi_event, 196 get_mid_event, 196 get_midi_event, 196 ge	m_flash_height, 173	stop_playing, 189
m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequence_pixmap_on_window, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_offset, 182 mainwid, 177 on_button_press_event, 180 on_button_release_event, 181 on_focus_out_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_window_title, 189 seq64::mastermidibus, 191 ~mastermidibus, 194 clock, 195 continue_from, 195 flush, 195 get_clock, 198 get_injut, 198 get_midi_event, 196 get_midi_event, 196 get_midi_out_bus_name, 195 get_midi_event, 196 moticus_nevent, 182 init_clock, 196 is_more_input, 196 mastermidibus, 193 get_midi_event, 196 get_mide_event, 196 get_moide_event, 196 get_midi_event, 196 get_midi_event, 196 get_moide_event, 19	m_flash_width, 173	timer_callback, 188
m_tick, 174 maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequence_pixmap_on_window, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_offset, 182 mainwid, 177 on_button_press_event, 180 on_button_release_event, 181 on_focus_out_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_window_title, 189 seq64::mastermidibus, 191 ~mastermidibus, 194 clock, 195 continue_from, 195 flush, 195 get_clock, 198 get_injut, 198 get_midi_event, 196 get_midi_event, 196 get_midi_out_bus_name, 195 get_midi_event, 196 moticus_nevent, 182 init_clock, 196 is_more_input, 196 mastermidibus, 193 get_midi_event, 196 get_mide_event, 196 get_moide_event, 196 get_midi_event, 196 get_midi_event, 196 get_moide_event, 19	m ppqn, 174	toggle playing, 189
maintime, 171 on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequence_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 181 on_focus_out_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 seq_from_tarable trimitions, 191 continue_from, 195 continue_from, 195 flush, 195 continue_from, 195 flush, 195 get_midi_event, 196 get_m	_ · · ·	
on_expose_event, 173 on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_on_pixmap, 179 m_button_down, 182 m_screenset_slots, 182 m_ascreenset_slots, 182 mainwid, 177 on_button_release_event, 180 on_focus_in_event, 181 on_realize, 180 on_realize, 180 on_realize, 180 on_realize, 180 on_focus_out_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 ~mastermidibus, 195 flush, 195 get_midi_ence, 198 get_inidi_event, 196 get_midi_event, 196 get_midi_event, 196 get_midi_event, 194 init, 196 is_more_input, 196 mastermidibus, 193 get_midi_event, 198 materidicevent, 198 mastermidibus, 193 materidicevent, 198 mastermidibus, 195 met_midi_event, 198 mastermidibus, 195 met_midi_event, 196 is_more_input, 196 mastermidibus, 198 get_midi_event, 196 init, 194 init, 198 met_midi_event, 196 is_more_input, 196 mastermidibus, 193 pet_midi_event, 196 is_more_input, 196 set_lock, 197 set_input, 198 set_lock, 197 set_input, 198 set_lock, 197 set_input, 198 set_lock, 197 set_input, 198 set_lock, 197 set_input, 196 set_lock, 197 set_lock, 197 set_lock, 196 init, 19		
on_realize, 173 seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequences_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 on_button_press_event, 180 on_button_release_event, 181 on_focus_in_event, 181 on_focus_out_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_sequence_input, 196 start, 197 set_sequence_input, 198 stop, 195 start, 195 stop, 195 sysex, 197		•
seq64::mainwid, 174 calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequences_on_pixmap, 179 m_button_down, 182 m_screenset_offset, 182 mainwid, 177 on_button_release_event, 181 on_focus_in_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 continue_from, 195 flush, 195 get_clock, 198 get_clock, 198 get_clock, 198 get_input, 198 maticalievent, 196 init, 194 init, 196 init, 194 init, 194 init, 196 init, 194 init, 194 init, 196 init, 194 init, 194 init, 198 mastermidius, 193 play, 197 poll_for_midi, 196 port_exit, 197 port_exit, 197 set_beats_per_minute, 194 set_beats_pe		
calculate_base_sizes, 180 draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequences_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 mainwid, 177 on_button_release_event, 181 on_focus_in_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 flush, 195 get_clock, 198 get_input, 198 get_midi_event, 196 get_mid_event, 196 get_midi_event, 196 get_mid_event, 196 get_midi_event, 196 get_mid_event, 196 get_midi_event, 196 get_midi_event, 196 get_midi_event, 196 get_midi_event, 196 get_mid_event, 196 get_mid_ev	- · · · ·	
draw_marker_on_sequence, 178 draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequences_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 mainwid, 177 on_button_release_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 get_clock, 198 get_input, 198 get_midi_event, 196 get_midi_event, 196 get_midi_event, 195 get_midi_event, 196 get_midi_event, 196 get_midi_event, 196 get_midi_event, 196 get_midi_event, 194 midi_event, 194 init, 196 init	·	— :
draw_sequence_on_pixmap, 178 draw_sequence_pixmap_on_window, 179 draw_sequences_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 on_button_release_event, 181 on_realize, 180 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 get_input, 198 get_midi_event, 196 get_midi_event, 194 mid_in_bus_name, 195 get_midi_event, 196 get_midi_event, 194 mid_in_bus_name, 195 get_midi_event, 196 get_midi_event, 194 mid_in_bus_name, 195 get_midi_event, 196 mid_in_bus_name, 195 get_mid_event, 196 mid_event, 198 m_det_mid_event, 196 mid_event, 196 mid_event, 196 mid_event, 196 mid_event, 196 mid_event, 196 mid_event, 198 moit_event, 196 mid_event, 198 moit_event, 196 mid_event, 198 moit_event, 198 moit_event, 198 moit_event, 196 moit_event, 198 moit_event, 198 moit_event, 198 moit_event, 19		
draw_sequence_pixmap_on_window, 179 draw_sequences_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 on_button_release_event, 181 on_realize, 180 on_motion_notify_event, 181 on_redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 get_midi_event, 196 get_midi_event, 196 get_midi_event, 196 get_midi_event, 195 get_midi_event, 194 init_clock, 196 is_more_input, 196 m_beats_per_minute, 198 mastermidibus, 193 play, 197 on_beats_per_minute, 198 mastermidibus, 193 play, 197 poll_for_midi, 196 port_exit, 197 set_lock, 197 set_lock, 197 set_input, 198 set_screenset, 177 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		
draw_sequences_on_pixmap, 179 m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 m_button_press_event, 180 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_realize, 180 on_realize, 180 on_realize, 180 set_input, 197 on_redraw, 177 set_input, 198 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 get_midi_in_bus_name, 195 get_midi_out_bus_name, 195 get_midi_out_bus_name, 195 get_mid_iout_bus_name, 195 get_midi_out_bus_name, 194 init, 194 init, 194 m_set_move_input, 196 set_beats_per_minute, 198 set_beats_per_minute, 198 set_beats_per_minute, 194 set_beats_per_minute, 194 set_beats_per_minute, 198 set_beats_p		-
m_button_down, 182 m_moving_seq, 182 m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 m_beats_per_minute, 198 mastermidibus, 193 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_motion_notify_event, 181 on_realize, 180 on_realize, 180 redraw, 177 seq_from_xy, 179 seq_from_xy, 179 update_markers, 178 update_sequences_on_window, 178 get_midi_out_bus_name, 194 init, 194 int, 196 in, 194 int, 196 in, 194 int, 194 int, 194 int, 196 in, 194 int, 196 in, 194 int, 196 in, 194 int, 196 in, 194 int, 194 int, 196 in, 196 i		- — —
m_moving_seq, 182 m_screenset_offset, 182 m_screenset_slots, 182 m_screenset_slots, 182 minit_clock, 196 init_clock, 196 is_more_input, 196 mainwid, 177 m_beats_per_minute, 198 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 iinit_clock, 196 init_clock, 196 init_clock, 196 init_clock, 196 init_clock, 196 init_clock, 198 mastermidibus, 193 play, 197 poll_for_midi, 196 port_exit, 197 port_exit, 197 set_beats_per_minute, 194 set_clock, 197 set_input, 198 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		-
m_screenset_offset, 182 m_screenset_slots, 182 mainwid, 177 m_beats_per_minute, 198 mastermidibus, 193 on_button_press_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 init_clock, 196 is_more_input, 196 is_more_input, 196 is_more_input, 198 mastermidibus, 193 play, 197 poll_for_midi, 196 port_exit, 197 port_exit, 197 port_start, 197 set_beats_per_minute, 194 set_clock, 197 set_input, 198 set_ppqn, 194 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		
m_screenset_slots, 182 mainwid, 177 m_beats_per_minute, 198 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 sed_input, 198 set_beats_per_minute, 194 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 is_more_input, 196 m_beats_per_minute, 198 mastermidibus, 193 poll_for_midi, 196 port_exit, 197 port_exit, 197 port_start, 197 set_beats_per_minute, 194 set_clock, 197 set_input, 198 set_ppqn, 194 set_sequence_input, 196 start, 195 stop, 195 sysex, 197	_ •	•
mainwid, 177 m_beats_per_minute, 198 on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 m_beats_per_minute, 198 mastermidibus, 193 poll_for_midi, 196 port_exit, 197 port_start, 197 set_beats_per_minute, 194 set_beats_per_minute, 194 set_clock, 197 set_input, 198 set_ppqn, 194 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		- · · · ·
on_button_press_event, 180 on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 mastermidibus, 193 play, 197 poll_for_midi, 196 port_exit, 197 port_start, 197 set_beats_per_minute, 194 set_beats_per_minute, 194 set_clock, 197 set_input, 198 set_ppqn, 194 set_screenset, 177 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		·
on_button_release_event, 181 on_expose_event, 180 on_focus_in_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 poll_for_midi, 196 port_exit, 197 port_start, 197 set_beats_per_minute, 194 set_beats_per_minute, 194 set_clock, 197 set_input, 198 set_ppqn, 194 set_screenset, 177 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		
on_expose_event, 180 on_focus_in_event, 181 on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 sed_input, 198 sed_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 poll_for_midi, 196 port_exit, 197 set_beats_per_minute, 194 set_beats_per_minute, 194 set_beats_per_minute, 194 set_beats_per_minute, 194 set_beats_per_minute, 194 set_lock, 197 set_input, 198 set_ppqn, 194 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		
on_focus_in_event, 181		
on_focus_out_event, 181 on_motion_notify_event, 181 on_realize, 180 redraw, 177 set_input, 198 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 port_start, 197 set_beats_per_minute, 194 set_beats_per_minute, 194 set_lock, 197 set_input, 198 set_ppqn, 194 set_sequence_input, 196 start, 195 stop, 195 sysex, 197	on_expose_event, 180	poll_for_midi, 196
on_motion_notify_event, 181 on_realize, 180 redraw, 177 seq_from_xy, 179 set_screenset, 177 timeout, 179 update_markers, 178 update_sequences_on_window, 178 set_beats_per_minute, 194 set_beats_per_minute, 194 set_lock, 197 set_input, 198 set_ppqn, 194 set_sequence_input, 196 start, 195 stop, 195 sysex, 197	on_focus_in_event, 181	port_exit, 197
on_realize, 180	on_focus_out_event, 181	port_start, 197
redraw, 177 set_input, 198 seq_from_xy, 179 set_ppqn, 194 set_screenset, 177 set_sequence_input, 196 timeout, 179 start, 195 update_markers, 178 stop, 195 update_sequences_on_window, 178 sysex, 197	on_motion_notify_event, 181	set_beats_per_minute, 194
seq_from_xy, 179set_ppqn, 194set_screenset, 177set_sequence_input, 196timeout, 179start, 195update_markers, 178stop, 195update_sequences_on_window, 178sysex, 197	on_realize, 180	set_clock, 197
seq_from_xy, 179set_ppqn, 194set_screenset, 177set_sequence_input, 196timeout, 179start, 195update_markers, 178stop, 195update_sequences_on_window, 178sysex, 197	redraw, 177	set_input, 198
set_screenset, 177 set_sequence_input, 196 timeout, 179 start, 195 update_markers, 178 update_sequences_on_window, 178 set_sequence_input, 196 start, 195 stop, 195 sysex, 197		_ ·
timeout, 179 start, 195 update_markers, 178 stop, 195 update_sequences_on_window, 178 sysex, 197		· ·
update_markers, 178 stop, 195 update_sequences_on_window, 178 sysex, 197	-	_ · ·
update_sequences_on_window, 178 sysex, 197		
	• —	•
valid seguence, 178 seg64··midi container 199	valid_sequence, 178	seq64::midi_container, 199
	· · · · · · · · · · · · · · · · · · ·	

add_long, 201	parse, 218
add_variable, 201	parse_prop_header, 220
fill, 200	parse_proprietary_track, 221
get, 201	parse_smf_0, 219
position, 201	parse_smf_1, 220
put, 201	pow2, <mark>22</mark> 1
seq64::midi_list, 202	ppqn, 219
CharList, 203	prop_item_size, 226
get, 203	read_byte_array, 223
put, 203	read_long, 222
seq64::midi_measures, 203	read_seq_number, 224
m_divisions, 204	read_track_name, 224
seq64::midi_splitter, 204	read_varinum, 222
increment, 206	varinum_size, 225
m_smf0_channels, 207	write, 219
m_smf0_channels_count, 207	write_byte, 223
m_smf0_seq_number, 207	write_long, 222
midi_splitter, 205	write_prop_header, 224
ppqn, 206	write_proprietary_track, 225
split, 206	write_seq_number, 224
split_channel, 206	write_short, 223
seq64::midi_timing, 207	write_track_name, 223
m_beat_width, 209	write_varinum, 223
m_beats_per_measure, 208	seq64::mutex, 228
m_beats_per_minute, 208	sm_recursive_mutex, 229
m_ppqn, 209	seq64::options, 229
seq64::midi_vector, 209	button, 230
get, 210	e_jack_connect, 230
put, 210	e_jack_disconnect, 230
seq64::midibus, 210	e_jack_master, 230
•	
clock, 214	e_jack_master_cond, 230
clock, 214 continue_from, 214	e_jack_master_cond, 230 e_jack_start_mode_live, 230
clock, 214 continue_from, 214 deinit_in, 213	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_data, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_data, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_data, 227 m_disable_reported, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239 perfedit, 236
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_data, 227 m_disable_reported, 227 m_error_is_fatal, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239 perfedit, 236 set_beat_width, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_disable_reported, 227 m_error_message, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239 perfedit, 236 set_beats_per_bar, 237
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_data, 227 m_error_is_fatal, 227 m_error_message, 227 m_file_size, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239 perfedit, 236 set_beat_width, 238 set_beats_per_bar, 237 set_guides, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_data, 227 m_error_is_fatal, 227 m_error_message, 227 m_file_size, 227 m_new_format, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239 perfedit, 236 set_beat_width, 238 set_beats_per_bar, 237 set_guides, 238 set_snap, 238
clock, 214 continue_from, 214 deinit_in, 213 init_clock, 214 init_in, 213 init_in_sub, 214 init_out, 213 init_out_sub, 213 m_clock_mod, 215 midibus, 212, 213 play, 214 set_input, 215 sysex, 214 seq64::midifile, 215 add_trigger, 222 checklen, 222 errdump, 226 is_sysex_special_id, 226 m_char_list, 227 m_data, 227 m_error_is_fatal, 227 m_error_message, 227 m_file_size, 227 m_pos, 227	e_jack_master_cond, 230 e_jack_start_mode_live, 230 e_jack_start_mode_song, 230 e_jack_transport, 230 m_notebook, 230 seq64::optionsfile, 230 parse, 232 write, 233 seq64::perfedit, 233 ~perfedit, 237 collapse, 238 copy, 238 enqueue_draw, 237 enregister_peer, 237 expand, 238 grow, 238 init_before_show, 237 m_bpm, 239 m_bw, 239 pause_playing, 239 perfedit, 236 set_beat_width, 238 set_beats_per_bar, 237 set_guides, 238 set_snap, 238 start_playing, 239

undo, 238	m_max_sets, 270
zoom_check, 237	m_one_measure, 270
seq64::perfnames, 240	m_playback_mode, 269
draw_sequence, 242	m_playscreen_offset, 269
enqueue_draw, 242	m_right_tick, 270
m_char_w, 243	m_seqs, 269
m_namebox_w, 243	m_seqs_in_set, 270
m_names_chars, 242	m_sequence_count, 271
m_names_y, 243	m_sequence_max, 271
m_parent, 242	m_starting_tick, 270
m_setbox_w, 243	m_tick, 270
m_xy_offset, 243	mainwnd_key_event, 265
on_expose_event, 242	midi_control_off, 255
on_realize, 242	midi_control_on, 255
on_size_allocate, 242	midi_control_toggle, 255
perfnames, 242	modify, 252
seq64::perform, 243	move_triggers, 254
\sim perform, 251	new_sequence, 252
add_sequence, 253	output_func, 261
all_notes_off, 257	pause_key, 263
clamp_track, 268	pause_playing, 263
clear_all, 252	perform, 251
clear_sequence_triggers, 253	perfroll_key_event, 265
copy_triggers, 254	play, 259
decrement_beats_per_minute, 263	playback_key_event, 265
deinit_jack, 266	position_jack, 257
delete_sequence, 253	push_trigger_undo, 254
finish, 253	reset_sequences, 259
get_group_mute_state, 261	save_playing_state, 262
get_max_tick, 254	select_group_mute, 256
get_max_trigger, 255	select_mute_group, 256
get_screen_set_notepad, 255	seq_in_playing_screen, 266
get_sequence, 259	sequence_count, 252
handle midi control, 255	sequence_label, 264
highlight, 264	sequence_playing_off, 260
increment_beats_per_minute, 264	sequence_playing_on, 260
init_jack, 266	set active, 257
inner start, 268	set_beats_per_minute, 260
inner_stop, 268	set_group_mute_state, 260
install_sequence, 267	set_input_bus, 264
is active, 259	set_key_event, 268
is dirty edit, 258	set_key_group, 268
is dirty main, 258	set_left_tick, 253
is dirty names, 258	set offset, 261
is_dirty_perf, 258	set orig ticks, 260
is midi control valid, 266	set playing screenset, 256
is mseq valid, 267	set_right_tick, 254
is_screenset_valid, 266	set_screen_set_notepad, 256
is_seq_valid, 267	set_screenset, 256
jack_sync_callback, 269	set_sequence_control_status, 260
launch, 252	set was active, 258
launch_input_thread, 265	show_ui_sequence_key, 262
launch_output_thread, 265	show_ui_sequence_number, 262
lookup_keyevent_key, 262	sm_mc_dummy, 269
· — · — ·	
m_beat_width, 270	start, 257
m_beats_per_bar, 270	start_key, 263
m_is_modified, 271	start_playing, 262
m_left_tick, 270	stop, 257

stop_key, 263	seqdata, 294
stop_playing, 263	set_data_type, 294
unset_mode_group_learn, 256	update_sizes, 294
unset_sequence_control_status, 260	xy_to_rect, 294
seq64::performcallback, 271	seq64::seqedit, 296
seq64::perfroll, 272	apply_length, 302
\sim perfroll, 275	create_menus, 303
convert_x, 277	do_action, 304
convert_xy, 277	fill_top_bar, 303
draw_drawable_row, 278	get_measures, 302
draw_progress, 276	horizontal_adjust, 301
draw_sequence_on, 277	m_initial_snap, 305
enqueue_draw, 278	m_pos, 306
fill_background_pixmap, 276	m_seqdata_wid, 306
FruityPerfInput, 279	m_seqkeys_wid, 306
init_before_show, 276	m_seqtime_wid, 306
m_fruity_interaction, 279	m_table, 306
m_h_page_increment, 279	m_zoom, 305
m_parent, 279	name_change_callback, 303
m_v_page_increment, 279	on_delete_event, 305
on_button_press_event, 278	on_key_press_event, 305
on_button_release_event, 278	on_scroll_event, 305
on_expose_event, 278	popup_event_menu, 304
on_key_press_event, 278	popup_midibus_menu, 304
on_realize, 278	popup_sequence_menu, 304
set_guides, 276	popup_tool_menu, 304
set_ppqn, 277	seqedit, 301
set_zoom, 278	set_background_sequence, 303
snap_x, 277	set_data_type, 303
update_sizes, 276	set_key, 302
seq64::perftime, 280	set_measures, 302
enqueue_draw, 283	set_midi_bus, 302
key_press_event, 283	set_midi_channel, 302
m_left_marker_tick, 283	set_note_length, 301
m_measure_length, 283	set_scale, 302
m_parent, 283	set_snap, 301
m_right_marker_tick, 284	set_zoom, 301
on_expose_event, 283	timeout, 304
on_realize, 283	seq64::seqevent, 306
perftime, 282	change_horz, 310
set_guides, 282 seq64::rc settings, 284	convert_t, 311
home_config_directory, 286	convert_x, 311 draw background, 310
seq64::rect, 286	draw events on, 310
seq64::seqdata, 291	draw_events_on, 310 draw pixmap on window, 310
·	draw_pixmap_on_window, 310 drop_event, 310
change_horz, 295 draw events on, 294	idle redraw, 310
idle_redraw, 294	on_button_press_event, 311
m_number_h, 296	on_button_release_event, 311
m_number_offset_y, 296	on_key_press_event, 312
m_number_w, 296	on_motion_notify_event, 311
on_button_press_event, 295	on_realize, 311
on_button_release_event, 295	redraw, 309
on_expose_event, 295	reset, 309
on_motion_notify_event, 295	set_data_type, 309
on_realize, 295	set_data_type, 309 set_snap, 309
on scroll event, 295	snap_x, 311
reset, 294	start_paste, 310
.0001, 201	5.ca. (public), 0.10

undata aizas 200	rooot 221
update_sizes, 309 x to w, 310	reset, 331 seqtime, 331
seq64::seqkeys, 312	update_pixmap, 331
draw key, 315	seq64::sequence, 332
force_draw, 315	add_event, 345, 351
on_button_press_event, 315	add_note, 351
on_button_release_event, 315	add_rigger, 345
on_enter_notify_event, 316	adjust_trigger_offsets_to_length, 358
on leave notify event, 316	background_sequence, 357
on_motion_notify_event, 315	change_event_data_range, 352
on_realize, 315	clear triggers, 349
on_scroll_event, 316	copy_events, 357
on_size_allocate, 316	copy_selected, 350
set hint state, 314	copy_triggers, 349
seq64::seqmenu, 316	cut_selected, 351
~seqmenu, 319	decrement_selected, 353
is_edit_sequence, 320	del_trigger, 346
m_modified, 321	e_deselect, 341
m_seqedit, 321	e_is_selected, 341
popup_menu, 320	e remove one, 341
seq_clear_perf, 321	e select, 341
seq_copy, 320	e_select_one, 341
seq_cut, 320	e_toggle_selection, 341
seq_edit, 320	e_would_select, 341
seq_event_edit, 320	event_count, 341
seq_new, 320	fill_container, 356
seq_paste, 321	get_beat_width, 342
segmenu, 319	get_clipboard_box, 351
seq64::seqroll, 321	get_last_tick, 342
∼segroll, 326	get_max_trigger, 349
change_horz, 328	get_minmax_note_events, 355
convert_tn, 328	get_name, 342
draw_events_on, 328	get_next_event, 356
draw_events_on_pixmap, 327	get_next_note_event, 355
draw_progress_on_window, 327	get num selected events, 350
follow progress, 327	get_num_selected_notes, 350
horizontal_adjust, 327	get_selected_box, 351
m_pos, 329	get_trigger_state, 346
on_key_press_event, 329	grow_selected, 353
on_scroll_event, 329	grow_trigger, 346
redraw, 327	increment_selected, 353
reset, 327	intersect_events, 347
seqroll, 325	intersect_notes, 347
set_background_sequence, 326	intersect_triggers, 347
set_data_type, 326	is_dirty_edit, 344
set_key, 326	is_dirty_main, 344
set_scale, 326	is_dirty_names, 344
set_zoom, 326	is_dirty_perf, 344
snap_x, 328	link_new, 354
snap_y, <mark>328</mark>	m_32nds_per_quarter, 360
update_and_draw, 327	m_background_sequence, 360
update_background, 327	m_clocks_per_metronome, 359
update_sizes, 326	m_length, 359
xy_to_rect, 328	m_midi_channel, 359
seq64::seqtime, 329	m_musical_key, 360
on_button_press_event, 332	m_musical_scale, 360
on_button_release_event, 332	m_mutex, 360
on_realize, 332	m_parent, 359

m_playing_notes, 359	split_trigger, 346, 358
m_raise, 359	stream_event, 352
m_seq_number, 359	stretch_selected, 353
m_snap_tick, 359	toggle_queued, 343
m_time_beat_width, 359	transpose_notes, 357
m_time_beats_per_measure, 359	unpaint_all, 354
m_us_per_quarter_note, 360	unselect, 354
mark_selected, 354	unselect_triggers, 347
mod_last_tick, 343	verify_and_link, 354
move_selected_notes, 351	zero_markers, 354
move_selected_triggers_to, 348	seq64::trigger, 360
move_triggers, 349	operator<, 361
off_playing_notes, 355	seq64::triggers, 362
off_queued, 343	add, 365
partial_assign, 341	adjust_offset, 370
paste_selected, 351	adjust_offsets_to_length, 366
paste_trigger, 348	copy, <mark>369</mark>
pause, 355	get_maximum, 369
play, 345	get_selected_end, 368
play_note_off, 355	get_selected_start, 368
play_note_on, 354	get_state, 367
pop_redo, 341	grow, 366
pop_undo, 341	intersect, 367
print, 344	m_length, 370
print_triggers, 344	m_ppqn, 370
push_trigger_undo, 341	move, 369
push_undo, 341	move_selected, 368
put_event_on_bus, 357	next, 370
remove, 358	next_trigger, 370
remove_all, 358	operator=, 364
remove_marked, 354	paste, 368
reset, 355	play, 365
reset_draw_marker, 355	print, 365
reset_draw_trigger_marker, 355	remove, 367
select_action_e, 341	select, 367
select_all, 350	set_length, 364
select_events, 350	split, 366
select_note_events, 349	triggers, 364
select_trigger, 346	unselect, 367
selected_trigger_end, 349	seq64::user_instrument, 371
selected_trigger_start, 348	controller_active, 372
set_beat_width, 342	controller_max, 372
set_beats_per_bar, 341	controller_name, 372
set_dirty, 344	copy_definitions, 373
set_dirty_mp, 344	m_controller_count, 373
set_last_tick, 343	m_is_valid, 373
set_length, 342	set_controller, 372
set_master_midi_bus, 349	set_defaults, 372
set_midi_bus, 349	set_name, 373
set_midi_channel, 344	seq64::user_instrument_t, 373
set_parent, 357	controllers, 373
set_playing, 343	controllers_active, 373
set_quantized_rec, 343	instrument, 373
set_rec_vol, 342	seq64::user_midi_bus, 374
set_recording, 343	channel_count, 375
set_snap_tick, 343	channel_max, 375
set_thru, 344	copy_definitions, 375
set_trigger_offset, 357	instrument, 375

m_channel_count, 376	mainwnd_cols, 384
m_is_valid, 376	mainwnd_rows, 384
set_defaults, 375	max_sets, 384
set_instrument, 375	mc_baseline_ppqn, 392
seq64::user_midi_bus_t, 376	mc_max_zoom, 391
alias, 376	mc_min_zoom, 391
instrument, 376	midi_beat_width, 386
seq64::user_settings, 376	midi_beats_per_bar, 386
bus, 384	midi_beats_per_minute, 386
Busses, 383	midi_buss_override, 385
control_height, 385	midi_ppqn, 385
controller_active, 384	perf_h_page_increment, 385
controller_name, 384	perf_v_page_increment, 385
dump_summary, 385	private_bus, 386
grid_style_black, 383	private_instrument, 386
grid_style_max, 383	set_defaults, 384
grid_style_normal, 383	text_x, 384
grid_style_white, 383	text_y, 385
instrument, 384	zoom, 384
Instruments, 383	seq64::userfile, 392
m_allow_two_perfedits, 388	dump_setting_summary, 393
m_control_height, 387	parse, 393
m_current_zoom, 388	write, 393
m_global_seq_feature_save, 388	seq_clear_perf
m_gmute_tracks, 390	seq64::seqmenu, 321
m_grid_brackets, 387	seq_copy
m_grid_style, 386 m_h_perf_page_increment, 389	seq64::seqmenu, 320
m_instruments, 386	seq_cut seq64::seqmenu, 320
m_mainwid_border, 387	seq_edit
m_mainwid_x, 391	seq64::seqmenu, 320
m_mainwnd_cols, 387	seq event edit
m_mainwnd_cois, 387	seq64::seqmenu, 320
m max sequence, 391	seq event type t
m_max_sets, 387	seq64, 48
m_midi_beat_width, 390	seq from xy
m_midi_beats_per_measure, 390	seq64::mainwid, 179
m midi beats per minute, 390	seq_in_playing_screen
m_midi_buses, 386	seq64::perform, 266
m_midi_buss_override, 390	seg modifier t
m midi ppqn, 390	seq64, 48
m_progress_bar_colored, 389	seq new
m_progress_bar_thick, 389	seq64::seqmenu, 320
m_save_user_config, 391	seq_paste
m_segarea_seg_x, 391	seq64::seqmenu, 321
m_seqarea_x, 391	seq_scroll_direction_t
m seqchars x, 389	seq64, 48
m_seqedit_bgsequence, 388	segdata
m_seqedit_key, 388	seq64::seqdata, 294
m_seqedit_scale, 388	segedit
m_seqs_in_set, 390	seq64::seqedit, 301
m_text_x, 389	seqmenu
m_use_new_font, 388	seq64::seqmenu, 319
m_v_perf_page_increment, 389	segroll
m_window_redraw_rate_ms, 389	seq64::seqroll, 325
mainwid_border, 385	seqtime
mainwid_grid_style_t, 383	seq64::seqtime, 331
mainwid_spacing, 385	sequence_count
·	

seq64::perform, 252	seq64::eventedit, 113
sequence_label	seq64::sequence, 344
seq64::perform, 264	set_dirty_mp
sequence_playing_off	seq64::sequence, 344
seq64::perform, 260	set_event_category
sequence_playing_on	seq64::eventedit, 113
seq64::perform, 260	set_event_data_0
session_event	seq64::eventedit, 113
seq64::jack_assistant, 151	set_event_data_1
set	seq64::eventedit, 113
seq64::keybindentry, 159	set_event_name
set_active	seq64::eventedit, 113
seq64::perform, 257	set_event_timestamp
set_adding	seq64::eventedit, 113
seq64::Seq24PerfInput, 288	set_group_mute_state
seq64::Seq24SeqEventInput, 289	seq64::perform, 260
seq64::Seq24SeqRollInput, 290	set_guides
set_all_key_events	seq64::perfedit, 238
seq64::keys_perform, 162	seq64::perfroll, 276
seq64::keys_perform_gtk2, 165	seq64::perftime, 282
set_all_key_groups	set_hint_state
seq64::keys_perform, 162	seq64::seqkeys, 314
seq64::keys_perform_gtk2, 165	set_image
set_alsa_client_id	seq64::mainwnd, 188
seq64::lash, 169	set_input
set_background_sequence	seq64::mastermidibus, 198
seq64::seqedit, 303	seq64::midibus, 215
seq64::seqroll, 326	set_input_bus
set_beat_width	seq64::perform, 264
seq64::perfedit, 238	set_instrument
seq64::sequence, 342	seq64::user_midi_bus, 375
set_beats_per_bar	set_key
seq64::perfedit, 237	seq64::seqedit, 302
seq64::sequence, 341	seq64::seqroll, 326
set_beats_per_minute	set_key_event
seq64::jack_assistant, 150	seq64::keys_perform, 162
seq64::mastermidibus, 194	seq64::perform, 268
seq64::perform, 260	set_key_group
set_channel	seq64::keys_perform, 163
seq64::event, 100	seq64::perform, 268
set_clock	set_keys
seq64::mastermidibus, 197	seq64::keys_perform, 161
set_controller	set_last_tick
seq64::user_instrument, 372	seq64::sequence, 343
set_current_event	set_left_tick
seq64::eventslots, 120	seq64::perform, 253
set_data	set_length
seq64::event, 100	seq64::sequence, 342
set_data_type	seq64::triggers, 364
seq64::seqdata, 294	set_line
seq64::seqedit, 303	seq64::gui_drawingarea_gtk2, 137
seq64::seqevent, 309	set_master_midi_bus
seq64::seqroll, 326	seq64::sequence, 349
set_defaults	set_measures
seq64::user_instrument, 372	seq64::seqedit, 302
seq64::user_midi_bus, 375	set_midi_bus
seq64::user_settings, 384	seq64::seqedit, 302
set_dirty	seq64::sequence, 349

set_midi_channel	seq64::editable_event, 85
seq64::seqedit, 302	set_text
seq64::sequence, 344	seq64::eventslots, 123
set_name	set_thru
seq64::user_instrument, 373	seq64::sequence, 344
set_note_length	set_trigger_offset
seq64::seqedit, 301	seq64::sequence, 357
set_offset	set_was_active
seq64::perform, 261	seq64::perform, 258
set_orig_ticks	set_zoom
seq64::perform, 260	seq64::perfroll, 278
set_parent	seq64::seqedit, 301
seq64::sequence, 357	seq64::seqroll, 326
set_playing	shorten_file_spec
seq64::sequence, 343	seq64, 53
set_playing_screenset	show_position
seq64::perform, 256	seq64::jack_assistant, 154
set_position	show_statuses
seq64::jack_assistant, 155	seq64::jack_assistant, 153
set_ppqn	show_ui_sequence_key
seq64::jack_assistant, 152	seq64::keys_perform, 162
seq64::mastermidibus, 194	seq64::perform, 262
seq64::perfroll, 277	show_ui_sequence_number
set_quantized_rec	seq64::keys_perform, 162
seq64::sequence, 343	seq64::perform, 262
set_rec_vol	signal_action
seq64::sequence, 342	seq64::mainwnd, 190
set_recording	sm_category_arrays
seq64::sequence, 343	seq64::editable_event, 86
set_right_tick	sm_category_names
seq64::perform, 254	seq64::editable_event, 86
set_scale	sm_channel_event_names
seq64::seqedit, 302	seq64::editable_event, 86
seq64::seqroll, 326	sm_internal_keys
set_screen_set_notepad	seq64::gui_assistant_gtk2, 134
seq64::perform, 256	sm_mc_dummy
set_screenset	seq64::perform, 269
seq64::mainwid, 177	sm_meta_event_names
seq64::perform, 256	seq64::editable_event, 86
set_seq_ppqn	sm_prop_event_names
seq64::eventedit, 112	seq64::editable_event, 86
set_seq_time_sig	sm_recursive_mutex
seq64::eventedit, 112	seq64::mutex, 229
set_seq_title	sm_status_pairs
seq64::eventedit, 112	seq64::jack_assistant, 157
set_sequence_control_status	sm_system_event_names
seq64::perform, 260	seq64::editable_event, 86
set_sequence_input	snap_x
seq64::mastermidibus, 196	seq64::perfroll, 277
set_snap	seq64::seqevent, 311
seq64::perfedit, 238	seq64::seqroll, 328
seq64::seqedit, 301	snap_y
seq64::seqevent, 309	seq64::seqroll, 328
set_snap_tick	split
seq64::sequence, 343	seq64::midi_splitter, 206
set_status	seq64::triggers, 366
seq64::event, 99	split_channel
set_status_from_string	seq64::midi_splitter, 206

split_trigger	timeout
seq64::sequence, 346, 358	seq64::mainwid, 179
start	seq64::perfedit, 239
seq64::jack_assistant, 151	seq64::seqedit, 304
seq64::mastermidibus, 195	timer_callback
seq64::perform, 257	seq64::mainwnd, 188
start_key	timestamp
seq64::perform, 263	seq64::editable_event, 84
start_paste	timestamp_format_t
seq64::seqevent, 310	seq64::editable_event, 82
start_playing	timestamp_measures
seq64::mainwnd, 188	seq64::editable_event, 82
seq64::perfedit, 239	timestamp_pulses
seq64::perform, 262	seq64::editable_event, 82
stock_event_string	timestamp_time
seq64::editable_event, 85	seq64::editable_event, 82
stop	timestring_to_pulses
seq64::jack_assistant, 151	seq64, <mark>52</mark>
seq64::mastermidibus, 195	to_string
seq64::perform, 257	seq64, 60
stop_key	toggle_playing
seq64::perform, 263	seq64::mainwnd, 189
stop_playing	seq64::perfedit, 239
seq64::mainwnd, 189	toggle_queued
seq64::perform, 263	seq64::sequence, 343
stream_event	transpose_notes
seq64::sequence, 352	seq64::sequence, 357
stretch_selected	triggers
seq64::sequence, 353	seq64::triggers, 364
string_is_void	type
seq64, 54	seq64::keybindentry, 158
string_not_void	
seq64, 53	undo
string_to_midibyte	seq64::perfedit, 238
seq64, 53	unmodify
string_to_pulses	seq64::event_list, 106
seq64, 52	unpaint_all
strings_match	seq64::sequence, 354
seq64, 54	unselect
sync	seq64::sequence, 354
seq64::jack_assistant, 155	seq64::triggers, 367
sysex	unselect_triggers
seq64::mastermidibus, 197	seq64::sequence, 347
seq64::midibus, 214	unset_mode_group_learn
	seq64::perform, 256
tempo_from_beats_per_minute	unset_sequence_control_status
seq64, 55	seq64::perform, 260
tempo_to_bytes	update_and_draw
seq64, 55	seq64::seqroll, 327
text_x	update_background
seq64::user_settings, 384	seq64::seqroll, 327
text_y	update_markers
seq64::user_settings, 385	seq64::mainwid, 178
ticks_to_delta_time_us	•
	update_pixmap
seq64, 57	update_pixmap seq64::seqtime, 331
seq64, 57 time_as_measures	update_pixmap seq64::seqtime, 331 update_sequences_on_window
seq64, 57 time_as_measures seq64::editable_event, 84	update_pixmap seq64::seqtime, 331 update_sequences_on_window seq64::mainwid, 178
seq64, 57 time_as_measures seq64::editable_event, 84 time_as_minutes	update_pixmap seq64::seqtime, 331 update_sequences_on_window seq64::mainwid, 178 update_sizes
seq64, 57 time_as_measures seq64::editable_event, 84	update_pixmap seq64::seqtime, 331 update_sequences_on_window seq64::mainwid, 178

```
seq64::seqdata, 294
                                                             seq64::perfedit, 237
     seq64::seqevent, 309
                                                        zoom_power_of_2
                                                             seq64, 55
     seq64::seqroll, 326
update_window_title
     seq64::mainwnd, 189
v adjustment
     seq64::eventedit, 113, 114
valid sequence
     seq64::mainwid, 178
value_to_name
     seq64::editable_event, 83
varinum_size
    seq64::midifile, 225
verify_and_link
     seq64::event_list, 107
     seq64::sequence, 354
versiontext
    seq64, 69
WHITE
     seq64::font, 129
write
    seq64::midifile, 219
     seq64::optionsfile, 233
     seq64::userfile, 393
write_byte
     seq64::midifile, 223
write_long
     seq64::midifile, 222
write_options_files
     seq64, 60
write_prop_header
     seq64::midifile, 224
write_proprietary_track
     seq64::midifile, 225
write_seq_number
     seq64::midifile, 224
write_short
     seq64::midifile, 223
write track name
     seq64::midifile, 223
write_varinum
     seq64::midifile, 223
x_to_w
     seq64::seqevent, 310
xy_to_rect
     seq64::seqdata, 294
     seq64::seqroll, 328
YELLOW_ON_BLACK
     seq64::font, 129
zero_markers
    seq64::sequence, 354
zoom
     seq64::user_settings, 384
zoom_check
```