Sequencer64 Developer/Tester's Reference Manual 0.9.9.15

Generated by Doxygen 1.8.9.1

Sat Jan 30 2016 07:47:06

Contents

1	Sequ	uencer6	64																1
	1.1	Introdu	iction								٠.	 	 		 	 			 1
2	MIDI	l File Pa	rsing in S	equ	ence	er64													3
	2.1	Introdu	iction									 	 		 	 			 3
	2.2	SMF 1	Parsing .									 	 		 	 			 3
		2.2.1	MIDI File	Hea	ader,	MTh	nd					 	 		 	 			 3
		2.2.2	MIDI Trac	ck, N	//T rk							 	 		 	 			 4
			2.2.2.1	Ch	anne	el Eve	ents	3 .				 	 		 	 			 4
			2.2.2.2	Me	eta Ev	vents	s.					 	 		 	 			 5
		2.2.3	Meta Eve	ents								 	 		 	 			 6
			2.2.3.1	Se	quen	ice N	Num	ber	(0x0	00)		 	 		 	 			 6
			2.2.3.2	Tra	ack/So	eque	ence	e Na	ıme	(0x	(80	 	 		 	 			 7
			2.2.3.3	En	d of T	Track	k (0)	x2F)) .			 	 	 	 	 			 7
			2.2.3.4	Se	t Tem	тро Е	Ever	nt (0)x51	1) .		 	 	 	 	 			 7
			2.2.3.5	Tir	ne Si	gnat	ture	Eve	ent ((0x5	8)	 	 	 	 	 			 7
			2.2.3.6	Sy	sEx E	Even	nt (0:	xF0)) .			 	 		 	 			 8
			2.2.3.7	Se	quen	icer S	Spe	cific	; (0x	(7F)	١	 	 		 	 			 8
			2.2.3.8	No	n-Sp	ecific	c Er	nd o	f Se	eque	ence		 		 	 			 9
	2.3	SMF 0	Parsing .									 	 		 	 			 9
3	JAC	K, Live,	and Song	g Mc	odes	in S	equ	uenc	cer6	64									11
	3.1	Introdu	iction									 	 	 	 	 			 11
	3.2	JACK	Functions									 	 	 	 	 			 11
		3.2.1	jack_clier	nt_o	pen()) .						 	 	 	 	 			 12
		3.2.2	jack_on_s	shu	tdowr	n()						 	 	 	 	 			 12
		3.2.3	jack_set_	_syn	c_cal	llbac	ck()					 	 	 	 	 			 12
		3.2.4	jack_set_																
		3.2.5	jack_set_																
		3.2.6	jack_activ																
		3.2.7	jack_relea																
		328	iack clier																13

iv CONTENTS

9	Data	Structure Index	33
	8.1	Class Hierarchy	31
8	Hiera	archical Index	31
7	Depi	recated List	29
6	Todo	o List	27
	5.6	XPC License Summary	25
	5.5	XPC Affero License	24
	5.4	XPC Documentation License	24
	5.3	XPC Library License	24
	5.2	XPC Application License	23
	5.1	License Terms for the This Project.	23
5	Lice	nses	23
	4.6	Snipping of a MIDI file.	20
	4.5	Specific Fault Debugging	20
		4.4.2.1 Leak-Checking Basic Operation	20
		4.4.2 Full Valgrind Leak-Checking	20
		4.4.1 Valgrind Suppressions	19
	4.4	Tests Using Valgrind	19
		4.3.3 The Sequencer64 User File	19
		4.3.2 Patterns Window Key Shortcuts	19
		4.3.1 Button Clicks on a Pattern	18
	4.3	Tests in the Patterns Window	18
	4.2	Smoke Test	17
	4.1	Introduction	17
4	User	r Testing of Sequencer64 with Yoshimi	17
	3.5	JACK References	15
	3.4	Breakage	15
		3.3.3 JACK Transport	14
		3.3.2 No JACK, Song Mode	14
		3.3.1 No JACK, Live Mode	14
	3.3	Modes Operation	14
		3.2.13 jack_transport_query()	13
		3.2.12 jack_transport_reposition()	13
		3.2.11 jack_transport_locate()	13
		3.2.10 jack_transport_stop()	13
		3.2.9 jack_transport_start()	13

CONTENTS

	9.1	Data S	tructures	33
10	Data	Structu	ire Documentation	37
	10.1	seq64::	AbstractPerfInput Class Reference	37
	10.2	seq64:	automutex Class Reference	37
		10.2.1	Detailed Description	38
	10.3	seq64:	click Class Reference	38
		10.3.1	Detailed Description	39
		10.3.2	Constructor & Destructor Documentation	39
			10.3.2.1 click	39
			10.3.2.2 click	39
			10.3.2.3 click	39
		10.3.3	Member Function Documentation	40
			10.3.3.1 operator=	40
		10.3.4	Field Documentation	40
			10.3.4.1 m_x	40
			10.3.4.2 m_y	40
			10.3.4.3 m_button	40
			10.3.4.4 m_modifier	40
	10.4	seq64::	condition_var Class Reference	40
		10.4.1	Detailed Description	41
		10.4.2	Field Documentation	42
			10.4.2.1 cond	42
	10.5	seq64:	configfile Class Reference	42
		10.5.1	Constructor & Destructor Documentation	43
			10.5.1.1 configfile	43
		10.5.2	Member Function Documentation	43
			10.5.2.1 next_data_line	43
			10.5.2.2 line_after	43
		10.5.3	Field Documentation	43
			10.5.3.1 m_line	43
	10.6	seq64:	reditable_event Class Reference	43
		10.6.1	Detailed Description	47
		10.6.2	Member Enumeration Documentation	47
			10.6.2.1 category_t	47
			10.6.2.2 timestamp_format_t	47
		10.6.3		48
			10.6.3.1 editable_event	48
			10.6.3.2 editable_event	48
			10.6.3.3 editable_event	48

vi CONTENTS

	10.6.4	Member F	function Documentation	48
		10.6.4.1	value_to_name	48
		10.6.4.2	name_to_value	48
		10.6.4.3	category	49
		10.6.4.4	category	49
		10.6.4.5	timestamp	49
		10.6.4.6	timestamp	49
		10.6.4.7	time_as_measures	49
		10.6.4.8	time_as_minutes	50
		10.6.4.9	set_status_from_string	50
		10.6.4.10	format_timestamp	50
		10.6.4.11	stock_event_string	50
		10.6.4.12	analyze	50
	10.6.5	Field Docu	umentation	50
		10.6.5.1	sm_category_names	50
		10.6.5.2	sm_channel_event_names	51
		10.6.5.3	sm_system_event_names	51
		10.6.5.4	sm_meta_event_names	51
		10.6.5.5	sm_prop_event_names	51
		10.6.5.6	sm_category_arrays	51
		10.6.5.7	m_parent	51
		10.6.5.8	m_category	51
		10.6.5.9	m_format_timestamp	51
		10.6.5.10	m_name_status	51
		10.6.5.11	m_name_meta	52
10.7	seq64::	editable_ev	vents Class Reference	52
	10.7.1	Member T	ypedef Documentation	53
		10.7.1.1	Key	53
	10.7.2	Constructo	or & Destructor Documentation	53
		10.7.2.1	editable_events	53
		10.7.2.2	editable_events	53
	10.7.3	Member F	function Documentation	53
		10.7.3.1	operator=	53
		10.7.3.2	load_events	54
		10.7.3.3	save_events	54
		10.7.3.4	count	54
		10.7.3.5	add	54
		10.7.3.6	add	54
	10.7.4	Field Docu	umentation	55
		10.7.4.1	m_current_event	55

CONTENTS vii

		10.7.4.2 m_sequence	55
		10.7.4.3 m_midi_parameters	55
10.8 s	seq64::	event Class Reference	55
1	10.8.1	Detailed Description	59
1	10.8.2	Constructor & Destructor Documentation	60
		10.8.2.1 event	60
		10.8.2.2 ~event	60
1	10.8.3	Member Function Documentation	60
		10.8.3.1 operator=	60
		10.8.3.2 operator<	60
		10.8.3.3 check_channel	61
		10.8.3.4 is_channel_msg	61
		10.8.3.5 is_one_byte_msg	61
		10.8.3.6 is_two_byte_msg	61
		10.8.3.7 is_note_msg	62
		10.8.3.8 is_desired_cc_or_not_cc	63
		10.8.3.9 mod_timestamp	63
		10.8.3.10 set_status	63
		10.8.3.11 set_status	64
		10.8.3.12 set_channel	64
		10.8.3.13 set_data	64
		10.8.3.14 set_data	64
		10.8.3.15 get_data	64
		10.8.3.16 append_sysex	64
		10.8.3.17 get_rank	65
1	10.8.4	Field Documentation	65
		10.8.4.1 m_status	65
		10.8.4.2 m_channel	65
		10.8.4.3 m_data	65
		10.8.4.4 m_sysex	65
		10.8.4.5 m_has_link	65
10.9 s	seq64::	event_list::event_key Class Reference	65
1	10.9.1	Detailed Description	66
1	10.9.2	Constructor & Destructor Documentation	66
		10.9.2.1 event_key	66
		10.9.2.2 event_key	66
1	10.9.3	Member Function Documentation	66
		10.9.3.1 operator<	66
1	10.9.4	Field Documentation	66
		10.9.4.1 m_timestamp	66

viii CONTENTS

10.9.4.2 m_rank	67
10.10seq64::event_list Class Reference	67
10.10.1 Detailed Description	69
10.10.2 Constructor & Destructor Documentation	69
10.10.2.1 event_list	69
10.10.3 Member Function Documentation	69
10.10.3.1 operator=	69
10.10.3.2 count	69
10.10.3.3 add	69
10.10.3.4 unmodify	69
10.10.3.5 remove	70
10.10.3.6 clear	70
10.10.3.7 merge	70
10.10.3.8 link_new	70
10.10.3.9 verify_and_link	70
10.10.3.10mark_out_of_range	70
10.10.3.11mark_all	71
10.10.3.12any_selected_notes	71
10.10.3.13count_selected_events	71
10.10.4 Field Documentation	71
10.10.4.1 m_is_modified	71
10.11seq64::eventedit Class Reference	71
10.11.1 Constructor & Destructor Documentation	74
10.11.1.1 eventedit	74
10.11.1.2 ~eventedit	75
10.11.2 Member Function Documentation	75
10.11.2.1 enqueue_draw	75
10.11.2.2 set_seq_title	75
10.11.2.3 set_seq_time_sig	75
10.11.2.4 set_seq_ppqn	75
10.11.2.5 set_seq_count	76
10.11.2.6 set_event_category	76
10.11.2.7 set_event_timestamp	76
10.11.2.8 set_event_name	76
10.11.2.9 set_event_data_0	76
10.11.2.10set_event_data_1	76
10.11.2.11set_dirty	76
10.11.2.12v_adjustment	
To The Lague thomas and the control of the control	77
10.11.2.13v_adjustment	

CONTENTS

10.11.2.15handle_insert	 	78
10.11.2.16handle_modify	 	78
10.11.2.17handle_save	 	78
10.11.2.1&n_key_press_event	 	78
10.11.2.19on_delete_event	 	79
10.11.3 Field Documentation	 	79
10.11.3.1 m_redraw_ms	 	79
10.12seq64::eventslots Class Reference	 	79
10.12.1 Member Function Documentation	 	84
10.12.1.1 load_events	 	84
10.12.1.2 set_current_event	 	84
10.12.1.3 insert_event	 	84
10.12.1.4 insert_event	 	85
10.12.1.5 delete_current_event	 	85
10.12.1.6 modify_current_event	 	86
10.12.1.7 save_events	 	86
10.12.1.8 select_event	 	86
10.12.1.9 set_text	 	87
10.12.1.1@onvert_y	 	87
10.12.1.11draw_event	 	87
10.12.1.12draw_events	 	88
10.12.1.13change_vert	 	88
10.12.1.14page_movement	 	88
10.12.1.15page_topper	 	88
10.12.1.16decrement_top	 	88
10.12.1.17Increment_top	 	88
10.12.1.18decrement_current	 	89
10.12.1.19ncrement_current	 	89
10.12.1.20decrement_bottom	 	89
10.12.1.21increment_bottom	 	89
10.12.1.22on_realize	 	89
10.12.1.23on_expose_event	 	89
10.12.1.24on_focus_in_event	 	89
10.12.1.25on_size_allocate	 	89
10.12.1.26on_move_up	 	90
10.12.1.27on_move_down	 	90
10.12.2 Field Documentation	 	90
10.12.2.1 m_slots_chars	 	90
10.12.2.2 m_char_w	 	90
10.12.2.3 m_setbox_w	 	90

CONTENTS

10.12.2.4 m_slots_y	90
10.12.2.5 m_xy_offset	90
10.12.2.6 m_top_index	90
10.12.2.7 m_current_index	90
10.13seq64::font Class Reference	90
10.13.1 Member Enumeration Documentation	92
10.13.1.1 Color	92
10.13.2 Member Function Documentation	92
10.13.2.1 init	92
10.13.2.2 render_string_on_drawable	92
10.13.3 Field Documentation	93
10.13.3.1 m_font_w	93
10.13.3.2 m_font_h	93
10.13.3.3 m_pixmap	93
10.13.3.4 m_black_pixmap	93
10.13.3.5 m_white_pixmap	93
10.13.3.6 m_b_on_y_pixmap	93
10.13.3.7 m_y_on_b_pixmap	93
10.13.3.8 m_b_on_c_pixmap	93
10.13.3.9 m_c_on_b_pixmap	93
10.13.3.10m_clip_mask	93
10.14seq64::gui_assistant Class Reference	94
10.14.1 Detailed Description	94
10.14.2 Constructor & Destructor Documentation	95
10.14.2.1 gui_assistant	95
10.15seq64::gui_assistant_gtk2 Class Reference	95
10.15.1 Member Function Documentation	96
10.15.1.1 lash_timeout_connect	96
10.15.2 Field Documentation	96
10.15.2.1 sm_internal_keys	96
10.16seq64::gui_drawingarea_gtk2 Class Reference	96
10.16.1 Detailed Description	99
10.16.2 Member Function Documentation	99
10.16.2.1 clear_window	99
10.16.2.2 set_line	99
10.16.2.3 draw_line	99
10.16.2.4 draw_line	99
10.16.2.5 draw_line_on_pixmap	99
10.16.2.6 draw_line_on_pixmap	100
10.16.2.7 draw_line	100

CONTENTS xi

10.16.2.8 draw_line	100
10.16.2.9 draw_line	100
10.16.2.10draw_line	101
10.16.2.11render_string	101
10.16.2.12render_string_on_pixmap	101
10.16.2.13draw_rectangle	101
10.16.2.14draw_rectangle	101
10.16.2.15draw_rectangle	102
10.16.2.16draw_rectangle	102
10.16.2.17draw_rectangle	102
10.16.2.18draw_rectangle	103
10.16.2.19draw_rectangle_on_pixmap	103
10.16.2.20draw_rectangle_on_pixmap	103
10.16.2.21draw_normal_rectangle_on_pixmap	103
10.16.2.22bn_realize	104
10.16.3 Field Documentation	104
10.16.3.1 m_window	104
10.16.3.2 m_pixmap	104
10.16.3.3 m_background	104
10.16.3.4 m_foreground	104
10.16.3.5 m_mainperf	104
10.16.3.6 m_window_x	
10.16.3.7 m_drop_x	104
10.17seq64::gui_palette_gtk2 Class Reference	104
10.17.1 Detailed Description	105
10.17.2 Constructor & Destructor Documentation	105
10.17.2.1 gui_palette_gtk2	105
10.18seq64::gui_window_gtk2 Class Reference	105
10.18.1 Constructor & Destructor Documentation	107
10.18.1.1 gui_window_gtk2	107
10.18.2 Field Documentation	108
10.18.2.1 m_window_x	108
10.19seq64::jack_assistant Class Reference	108
10.19.1 Detailed Description	109
10.19.2 Constructor & Destructor Documentation	109
10.19.2.1 jack_assistant	109
10.19.2.2 ~jack_assistant	109
10.19.3 Member Function Documentation	110
10.19.3.1 init	110
10.19.3.2 restart	110

xii CONTENTS

10.19.3.3 start	 110
10.19.3.4 stop	 110
10.19.3.5 position	 111
10.19.3.6 output	 111
10.19.3.7 get_jack_ticks	 112
10.19.3.8 info_message	 112
10.19.3.9 error_message	 112
10.19.3.10client_open	 112
10.19.3.11show_statuses	 113
10.19.3.12sync	 113
10.19.3.13set_position	 113
10.19.4 Friends And Related Function Documentation	 114
10.19.4.1 jack_shutdown_callback	 114
10.19.4.2 jack_timebase_callback	 115
10.19.5 Field Documentation	 115
10.19.5.1 sm_status_pairs	 115
10.20seq64::jack_scratchpad Class Reference	 115
10.20.1 Detailed Description	 116
10.21seq64::keybindentry Class Reference	 116
10.21.1 Member Enumeration Documentation	 116
10.21.1.1 type	 116
10.21.2 Constructor & Destructor Documentation	 117
10.21.2.1 keybindentry	 117
10.21.3 Member Function Documentation	 117
10.21.3.1 set	 117
10.21.3.2 on_key_press_event	 117
10.21.4 Field Documentation	 117
10.21.4.1 m_key	 117
10.22seq64::keys_perform Class Reference	 117
10.22.1 Detailed Description	 119
10.22.2 Constructor & Destructor Documentation	 119
10.22.2.1 ~keys_perform	 119
10.22.3 Member Function Documentation	 119
10.22.3.1 set_keys	 119
10.22.3.2 get_keys	 120
10.22.3.3 show_ui_sequence_key	 120
10.22.3.4 show_ui_sequence_number	 120
10.22.3.5 key_name	 120
10.22.3.6 set_all_key_events	 120
10.22.3.7 set_all_key_groups	 120

CONTENTS xiii

10.22.3.8 set_key_event
10.22.3.9 set_key_group
10.22.4 Field Documentation
10.22.4.1 m_key_show_ui_sequence_number
10.22.4.2 m_key_bpm_up
10.23seq64::keys_perform_gtk2 Class Reference
10.23.1 Detailed Description
10.23.2 Constructor & Destructor Documentation
10.23.2.1 ~keys_perform_gtk2
10.23.3 Member Function Documentation
10.23.3.1 key_name
10.23.3.2 set_all_key_events
10.23.3.3 set_all_key_groups
10.24seq64::keys_perform_transfer Struct Reference
10.25seq64::keystroke Class Reference
10.25.1 Detailed Description
10.25.2 Constructor & Destructor Documentation
10.25.2.1 keystroke
10.25.2.2 keystroke
10.25.3 Member Function Documentation
10.25.3.1 operator=
10.25.3.2 is_letter
10.25.4 Field Documentation
10.25.4.1 m_is_press
10.25.4.2 m_key
10.25.4.3 m_modifier
10.26seq64::lash Class Reference
10.26.1 Detailed Description
10.26.2 Constructor & Destructor Documentation
10.26.2.1 lash
10.26.3 Member Function Documentation
10.26.3.1 set_alsa_client_id
10.26.3.2 process_events
10.26.3.3 init
10.26.3.4 handle_event
10.26.3.5 handle_config
10.27seq64::maintime Class Reference
10.27.1 Detailed Description
10.27.2 Constructor & Destructor Documentation
10.27.2.1 maintime

XIV

10.27.3 Member Function Documentation	130
10.27.3.1 idle_progress	130
10.27.3.2 on_realize	131
10.27.3.3 on_expose_event	131
10.27.4 Field Documentation	131
10.27.4.1 m_beat_width	131
10.27.4.2 m_bar_width	131
10.27.4.3 m_box_width	131
10.27.4.4 m_box_height	131
10.27.4.5 m_flash_width	131
10.27.4.6 m_flash_height	131
10.27.4.7 m_tick	131
10.27.4.8 m_ppqn	132
10.28seq64::mainwid Class Reference	132
10.28.1 Constructor & Destructor Documentation	134
10.28.1.1 mainwid	134
10.28.2 Member Function Documentation	134
10.28.2.1 set_screenset	134
10.28.2.2 redraw	134
10.28.2.3 draw_marker_on_sequence	134
10.28.2.4 update_markers	135
10.28.2.5 valid_sequence	135
10.28.2.6 draw_sequence_on_pixmap	135
10.28.2.7 draw_sequences_on_pixmap	135
10.28.2.8 draw_sequence_pixmap_on_window	135
10.28.2.9 seq_from_xy	136
10.28.2.10timeout	136
10.28.2.11calculate_base_sizes	136
10.28.2.12on_realize	136
10.28.2.13on_expose_event	136
10.28.2.14on_button_press_event	137
10.28.2.15on_button_release_event	137
10.28.2.16on_motion_notify_event	137
10.28.2.17on_focus_in_event	137
10.28.2.1&on_focus_out_event	138
10.28.3 Field Documentation	138
10.28.3.1 m_screenset_slots	138
10.28.3.2 m_screenset_offset	138
10.29seq64::mainwnd Class Reference	138
10.29.1 Constructor & Destructor Documentation	142

CONTENTS xv

10.29.1.1 mainwnd	
10.29.2 Member Function Documentation	
10.29.2.1 open_file	142
10.29.2.2 ppqn	143
10.29.2.3 file_import_dialog	143
10.29.2.4 about_dialog	143
10.29.2.5 adj_callback_ss	143
10.29.2.6 adj_callback_bpm	143
10.29.2.7 edit_callback_notepad	143
10.29.2.8 timer_callback	143
10.29.2.9 start_playing	144
10.29.2.10stop_playing	144
10.29.2.11open_performance_edit	144
10.29.2.12open_performance_edit_2	144
10.29.2.13update_window_title	144
10.29.2.14new_file	144
10.29.2.15save_file	144
10.29.2.16signal_action	144
10.29.2.17on_delete_event	145
10.29.2.1&on_key_press_event	145
10.29.2.19on_key_release_event	145
10.29.2.20on_grouplearnchange	145
10.29.3 Field Documentation	145
10.29.3.1 m_sigpipe	145
10.29.3.2 m_ppqn	145
10.29.3.3 m_main_wid	145
10.29.3.4 m_spinbutton_load_offset	145
10.30seq64::midi_container Class Reference	145
10.30.1 Member Function Documentation	147
10.30.1.1 fill	147
10.30.1.2 put	147
10.30.1.3 get	148
10.30.1.4 position	148
10.30.1.5 add_variable	148
10.30.1.6 add_long	148
10.31seq64::midi_list Class Reference	148
10.31.1 Member Typedef Documentation	
10.31.1.1 CharList	150
10.31.2 Member Function Documentation	
10.31.2.1 put	

xvi CONTENTS

10.31.2.2 get	50
10.32seq64::midi_measures Class Reference	50
10.32.1 Field Documentation	51
10.32.1.1 m_divisions	51
10.33seq64::midi_splitter Class Reference	51
10.33.1 Detailed Description	52
10.33.2 Constructor & Destructor Documentation	52
10.33.2.1 midi_splitter	52
10.33.3 Member Function Documentation	53
10.33.3.1 increment	53
10.33.3.2 split	53
10.33.3.3 ppqn	53
10.33.3.4 split_channel	53
10.33.4 Field Documentation	54
10.33.4.1 m_smf0_channels_count	54
10.33.4.2 m_smf0_channels	54
10.33.4.3 m_smf0_seq_number	54
10.34seq64::midi_timing Class Reference	54
10.34.1 Detailed Description	55
10.34.2 Field Documentation	55
10.34.2.1 m_beats_per_minute19	55
10.34.2.2 m_beats_per_measure	55
10.34.2.3 m_beat_width	55
10.34.2.4 m_ppqn	55
10.35seq64::midi_vector Class Reference	55
10.35.1 Member Function Documentation	57
10.35.1.1 put	57
10.35.1.2 get	57
10.36seq64::midibus Class Reference	57
10.36.1 Member Function Documentation	59
10.36.1.1 init_out	59
10.36.1.2 init_in	59
10.36.1.3 deinit_in	59
10.36.1.4 init_out_sub	59
10.36.1.5 init_in_sub	30
10.36.1.6 play	30
10.36.1.7 sysex	60
10.36.1.8 clock	60
10.36.1.9 continue_from	60
10.36.1.10init_clock	30

CONTENTS xvii

10.36.1.11set_input	160
10.37seq64::midifile Class Reference	160
10.37.1 Detailed Description	163
10.37.2 Constructor & Destructor Documentation	163
10.37.2.1 midifile	163
10.37.3 Member Function Documentation	164
10.37.3.1 parse	164
10.37.3.2 write	165
10.37.3.3 ppqn	166
10.37.3.4 parse_smf_0	166
10.37.3.5 parse_smf_1	166
10.37.3.6 parse_prop_header	166
10.37.3.7 parse_proprietary_track	167
10.37.3.8 pow2	168
10.37.3.9 read_long	168
10.37.3.10read_varinum	168
10.37.3.11write_long	168
10.37.3.12write_short	168
10.37.3.13read_byte_array	168
10.37.3.14write_byte	168
10.37.3.15write_varinum	169
10.37.3.16write_track_name	169
10.37.3.17read_track_name	169
10.37.3.18write_seq_number	169
10.37.3.19read_seq_number	169
10.37.3.20write_prop_header	170
10.37.3.21write_proprietary_track	170
10.37.3.22varinum_size	171
10.37.3.23prop_item_size	171
10.37.3.24errdump	171
10.37.3.25errdump	171
10.37.3.26s_sysex_special_id	172
10.37.4 Field Documentation	173
10.37.4.1 m_file_size	173
10.37.4.2 m_error_message	173
10.37.4.3 m_error_is_fatal	173
10.37.4.4 m_disable_reported	173
10.37.4.5 m_pos	173
10.37.4.6 m_data	173
10.37.4.7 m_char_list	173

xviii CONTENTS

10.37.4.8 m_new_format
10.37.4.9 m_smf0_splitter
10.38seq64::mutex Class Reference
10.38.1 Field Documentation
10.38.1.1 sm_recursive_mutex
10.39seq64::options Class Reference
10.39.1 Member Enumeration Documentation
10.39.1.1 button
10.39.2 Field Documentation
10.39.2.1 m_notebook
10.40seq64::optionsfile Class Reference
10.40.1 Detailed Description
10.40.2 Member Function Documentation
10.40.2.1 parse
10.40.2.2 write
10.41 seq64::perfedit Class Reference
10.41.1 Detailed Description
10.41.2 Constructor & Destructor Documentation
10.41.2.1 perfedit
10.41.2.2 ~perfedit
10.41.3 Member Function Documentation
10.41.3.1 init_before_show
10.41.3.2 enqueue_draw
10.41.3.3 enregister_peer
10.41.3.4 set_beats_per_bar
10.41.3.5 set_beat_width
10.41.3.6 set_guides
10.41.3.7 grow
10.41.3.8 expand
10.41.3.9 collapse
10.41.3.10copy
10.41.3.11undo
10.41.3.12imeout
10.41.3.13start_playing
10.41.3.14stop_playing
10.41.4 Field Documentation
10.41.4.1 m_bpm
10.41.4.2 m_bw
10.41.4.3 m_redraw_ms
10.42seq64::perfnames Class Reference

CONTENTS xix

10.42.1 Detailed Description	87
10.42.2 Constructor & Destructor Documentation	87
10.42.2.1 perfnames	87
10.42.3 Member Function Documentation	87
10.42.3.1 enqueue_draw	87
10.42.3.2 draw_sequence	87
10.42.3.3 on_realize	87
10.42.3.4 on_expose_event	87
10.42.3.5 on_size_allocate	87
10.42.4 Field Documentation	87
10.42.4.1 m_parent	87
10.42.4.2 m_names_chars	87
10.42.4.3 m_char_w	88
10.42.4.4 m_setbox_w	88
10.42.4.5 m_namebox_w	88
10.42.4.6 m_names_y	88
10.42.4.7 m_xy_offset	88
10.43seq64::perform Class Reference	88
10.43.1 Detailed Description	95
10.43.2 Constructor & Destructor Documentation	95
10.43.2.1 perform	95
10.43.2.2 ~perform	95
10.43.3 Member Function Documentation	95
10.43.3.1 modify	95
10.43.3.2 sequence_count	95
10.43.3.3 clear_all	95
10.43.3.4 launch	96
10.43.3.5 new_sequence	97
10.43.3.6 add_sequence	97
10.43.3.7 delete_sequence	97
10.43.3.8 clear_sequence_triggers	97
10.43.3.9 finish	98
10.43.3.10set_left_tick	98
10.43.3.11set_right_tick	98
10.43.3.12move_triggers	98
10.43.3.13copy_triggers	98
10.43.3.14push_trigger_undo	98
10.43.3.15get_max_trigger	99
10.43.3.16midi_control_toggle	99
10.43.3.17midi_control_on	99

CONTENTS

10.43.3.18midi_control_off
10.43.3.19handle_midi_control
10.43.3.20get_screen_set_notepad
10.43.3.21set_screen_set_notepad
10.43.3.22set_screenset
10.43.3.23set_playing_screenset
10.43.3.24select_group_mute
10.43.3.25unset_mode_group_learn
10.43.3.26select_mute_group
10.43.3.27start
10.43.3.28stop
10.43.3.29position_jack
10.43.3.30all_notes_off
10.43.3.31set_active
10.43.3.32set_was_active
10.43.3.33s_dirty_main
10.43.3.34s_dirty_edit
10.43.3.35s_dirty_perf
10.43.3.36s_dirty_names
10.43.3.37s_active
10.43.3.38get_sequence
10.43.3.39reset_sequences
10.43.3.40play
10.43.3.41set_orig_ticks
10.43.3.42set_beats_per_minute
10.43.3.43set_sequence_control_status
10.43.3.44unset_sequence_control_status
10.43.3.45sequence_playing_on
10.43.3.46sequence_playing_off
10.43.3.47set_group_mute_state
10.43.3.48get_group_mute_state
10.43.3.49output_func
10.43.3.50set_offset
10.43.3.51save_playing_state
10.43.3.52show_ui_sequence_key
10.43.3.53show_ui_sequence_number
10.43.3.54start_playing
10.43.3.55decrement_beats_per_minute
10.43.3.56ncrement_beats_per_minute
10.43.3.57highlight

CONTENTS xxi

10.43.3.5&sequence_label	207
10.43.3.59set_input_bus	207
10.43.3.60mainwnd_key_event	207
10.43.3.61perfroll_key_event	207
10.43.3.62aunch_input_thread	208
10.43.3.63aunch_output_thread	208
10.43.3.64init_jack	208
10.43.3.65deinit_jack	208
10.43.3.66seq_in_playing_screen	208
10.43.3.67s_modified	208
10.43.3.68s_midi_control_valid	208
10.43.3.69s_screenset_valid	208
10.43.3.70s_seq_valid	209
10.43.3.71is_mseq_valid	209
10.43.3.72/nstall_sequence	209
10.43.3.73nner_start	209
10.43.3.74clamp_track	210
10.43.3.75set_key_event	210
10.43.3.76set_key_group	210
10.43.4 Field Documentation	210
10.43.4.1 sm_mc_dummy	210
10.43.4.2 m_playscreen_offset	210
10.43.4.3 m_seqs	210
10.43.4.4 m_playback_mode	210
10.43.4.5 m_one_measure	210
10.43.4.6 m_left_tick	210
10.43.4.7 m_right_tick	211
10.43.4.8 m_starting_tick	211
10.43.4.9 m_tick	211
10.43.4.10m_seqs_in_set	211
10.43.4.11m_max_sets	211
10.43.4.12m_sequence_count	211
10.43.4.13m_sequence_max	211
10.43.4.14m_is_modified	211
10.44seq64::performcallback Struct Reference	211
10.44.1 Detailed Description	212
10.45seq64::perfroll Class Reference	212
10.45.1 Constructor & Destructor Documentation	215
10.45.1.1 ~perfroll	215
10.45.2 Member Function Documentation	216

xxii CONTENTS

10.45.2.1 set_guides	
10.45.2.2 update_sizes	217
10.45.2.3 init_before_show	
10.45.2.4 fill_background_pixmap	217
10.45.2.5 set_ppqn	217
10.45.2.6 convert_xy	217
10.45.2.7 convert_x	217
10.45.2.8 snap_x	218
10.45.2.9 start_playing	218
10.45.2.10stop_playing	218
10.45.2.11draw_sequence_on	218
10.45.2.12draw_drawable_row	218
10.45.2.13enqueue_draw	218
10.45.2.14on_realize	218
10.45.2.15on_expose_event	218
10.45.2.16on_button_press_event	219
10.45.2.17on_button_release_event	219
10.45.2.1&on_key_press_event	219
10.45.3 Friends And Related Function Documentation	219
10.45.3.1 FruityPerfInput	219
10.45.4 Field Documentation	219
10.45.4.1 m_parent	219
10.45.4.2 m_h_page_increment	219
10.45.4.3 m_v_page_increment	219
10.45.4.4 m_fruity_interaction	219
10.46seq64::perftime Class Reference	220
10.46.1 Constructor & Destructor Documentation	222
10.46.1.1 perftime	222
10.46.2 Member Function Documentation	222
10.46.2.1 set_guides	222
10.46.2.2 enqueue_draw	222
10.46.2.3 on_realize	222
10.46.2.4 on_expose_event	223
10.46.3 Field Documentation	223
10.46.3.1 m_parent	223
10.46.3.2 m_measure_length	223
10.46.3.3 m_left_marker_tick	
10.47seq64::rc_settings Class Reference	
10.47.1 Member Function Documentation	

CONTENTS xxiii

10.47.1.1 home_config_directory
10.48seq64::rect Class Reference
10.49seq64::gui_drawingarea_gtk2::rect Struct Reference
10.50seq64::Seq24PerfInput Class Reference
10.50.1 Member Function Documentation
10.50.1.1 on_button_press_event
10.50.1.2 on_button_release_event
10.50.1.3 on_motion_notify_event
10.50.1.4 set_adding
10.50.1.5 handle_motion_key
10.51seq64::Seq24SeqEventInput Struct Reference
10.51.1 Member Function Documentation
10.51.1.1 set_adding
10.51.1.2 on_button_press_event
10.51.1.3 on_button_release_event
10.51.1.4 on_motion_notify_event
10.52seq64::Seq24SeqRollInput Class Reference
10.52.1 Member Function Documentation
10.52.1.1 set_adding
10.52.1.2 on_button_press_event
10.52.1.3 on_button_release_event
10.53seq64::seqdata Class Reference
10.53.1 Constructor & Destructor Documentation
10.53.1.1 seqdata
10.53.2 Member Function Documentation
10.53.2.1 reset
10.53.2.2 set_zoom
10.53.2.3 set_data_type
10.53.2.4 idle_redraw
10.53.2.5 update_sizes
10.53.2.6 xy_to_rect
10.53.2.7 on_realize
10.53.2.8 on_button_press_event
10.53.2.9 on_button_release_event
10.53.2.10on_motion_notify_event
10.53.2.11on_scroll_event
10.53.3 Field Documentation
10.53.3.1 m_number_w
10.53.3.2 m_number_h
10.53.3.3 m_number_offset_y

xxiv CONTENTS

10.54seq64::seqedit Class Reference	235
10.54.1 Detailed Description	238
10.54.2 Constructor & Destructor Documentation	238
10.54.2.1 seqedit	238
10.54.3 Member Function Documentation	238
10.54.3.1 set_zoom	238
10.54.3.2 set_snap	238
10.54.3.3 set_note_length	238
10.54.3.4 set_measures	239
10.54.3.5 apply_length	239
10.54.3.6 get_measures	239
10.54.3.7 set_midi_channel	239
10.54.3.8 set_midi_bus	239
10.54.3.9 set_scale	239
10.54.3.10set_key	239
10.54.3.11set_background_sequence	240
10.54.3.12hame_change_callback	240
10.54.3.13set_data_type	240
10.54.3.14create_menus	240
10.54.3.15popup_event_menu	240
10.54.3.1@popup_midibus_menu	240
10.54.3.17popup_sequence_menu	241
10.54.3.1&popup_tool_menu	241
10.54.3.19do_action	241
10.54.3.20on_delete_event	241
10.54.4 Field Documentation	241
10.54.4.1 m_initial_snap	241
10.55seq64::seqevent Class Reference	242
10.55.1 Member Function Documentation	244
10.55.1.1 set_snap	244
10.55.1.2 set_data_type	244
10.55.1.3 update_sizes	244
10.55.1.4 draw_background	244
10.55.1.5 draw_pixmap_on_window	245
10.55.1.6 idle_redraw	245
10.55.1.7 x_to_w	245
10.55.1.8 drop_event	245
10.55.1.9 draw_events_on	245
10.55.1.10start_paste	245
10.55.1.11convert_x	245

CONTENTS xxv

10.55.1.12convert_t	245
10.55.1.13snap_x	245
10.55.1.14on_realize	245
10.55.1.15on_button_press_event	246
10.55.1.16on_button_release_event	246
10.55.1.17on_motion_notify_event	246
10.55.1.18on_key_press_event	246
10.56seq64::seqkeys Class Reference	246
10.56.1 Member Function Documentation	249
10.56.1.1 set_hint_state	249
10.56.1.2 draw_key	250
10.56.1.3 on_realize	250
10.56.1.4 on_button_press_event	250
10.56.1.5 on_button_release_event	250
10.56.1.6 on_motion_notify_event	250
10.56.1.7 on_enter_notify_event	250
10.56.1.8 on_leave_notify_event	250
10.57seq64::seqmenu Class Reference	251
10.57.1 Detailed Description	253
10.57.2 Constructor & Destructor Documentation	253
10.57.2.1 seqmenu	253
10.57.2.2 ∼seqmenu	253
10.57.3 Member Function Documentation	253
10.57.3.1 popup_menu	253
10.57.3.2 seq_edit	253
10.57.3.3 seq_event_edit	253
10.57.3.4 seq_new	254
10.57.3.5 seq_copy	254
10.57.3.6 seq_cut	254
10.57.3.7 seq_paste	254
10.57.3.8 seq_clear_perf	254
10.57.4 Field Documentation	254
10.57.4.1 m_seqedit	254
10.57.4.2 m_modified	254
10.58seq64::seqroll Class Reference	254
10.58.1 Member Function Documentation	258
10.58.1.1 reset	258
10.58.1.2 set_data_type	258
10.58.1.3 set_background_sequence	258
10.58.1.4 update_background	258

XXVI

CONTENTS xxvii

10.60.3.26set_dirty_mp
10.60.3.27set_dirty
10.60.3.28set_midi_channel
10.60.3.29print
10.60.3.3\print_triggers
10.60.3.31play
10.60.3.32set_orig_tick
10.60.3.33add_event
10.60.3.34add_trigger
10.60.3.35split_trigger
10.60.3.36grow_trigger
10.60.3.37del_trigger
10.60.3.38get_trigger_state
10.60.3.39select_trigger
10.60.3.4@unselect_triggers
10.60.3.41intersect_triggers
10.60.3.42ntersect_notes
10.60.3.43ntersect_events
10.60.3.44paste_trigger
10.60.3.45move_selected_triggers_to
10.60.3.46selected_trigger_start
10.60.3.47selected_trigger_end
10.60.3.48get_max_trigger
10.60.3.49move_triggers
10.60.3.50copy_triggers
10.60.3.51clear_triggers
10.60.3.52set_midi_bus
10.60.3.53set_master_midi_bus
10.60.3.54select_note_events
10.60.3.55select_events
10.60.3.56select_events
10.60.3.57get_num_selected_notes
10.60.3.58get_num_selected_events
10.60.3.59select_all
10.60.3.60copy_selected
10.60.3.61cut_selected
10.60.3.62paste_selected
10.60.3.63get_selected_box
10.60.3.64get_clipboard_box
10.60.3.65move_selected_notes

xxviii CONTENTS

10.60.3.66add_note	279
10.60.3.67add_event	279
10.60.3.6&tream_event	280
10.60.3.69change_event_data_range	280
10.60.3.70ncrement_selected	280
10.60.3.71decrement_selected	280
10.60.3.72grow_selected	281
10.60.3.73stretch_selected	281
10.60.3.74remove_marked	281
10.60.3.75mark_selected	281
10.60.3.76unpaint_all	281
10.60.3.77unselect	281
10.60.3.78verify_and_link	281
10.60.3.79ink_new	282
10.60.3.80zero_markers	282
10.60.3.81play_note_on	282
10.60.3.82play_note_off	282
10.60.3.83off_playing_notes	282
10.60.3.84reset_draw_marker	282
10.60.3.85reset_draw_trigger_marker	282
10.60.3.86get_next_note_event	282
10.60.3.87get_lowest_note_event	282
10.60.3.88get_highest_note_event	282
10.60.3.89get_next_event	283
10.60.3.90get_next_event	283
10.60.3.91fill_container	283
10.60.3.92 ranspose_notes	283
10.60.3.93background_sequence	283
10.60.3.94copy_events	283
10.60.3.95put_event_on_bus	284
10.60.3.96set_trigger_offset	284
10.60.3.97split_trigger	284
10.60.3.9&adjust_trigger_offsets_to_length	284
10.60.3.99remove	284
10.60.3.10@move	284
10.60.3.10/emove_all	284
10.60.4 Field Documentation	284
10.60.4.1 m_midi_channel	284
10.60.4.2 m_playing_notes	285
10.60.4.3 m_seq_number	285

CONTENTS xxix

10.60.4.4 m_length	285
10.60.4.5 m_snap_tick	285
10.60.4.6 m_time_beats_per_measure	285
10.60.4.7 m_time_beat_width	285
10.60.4.8 m_musical_key	285
10.60.4.9 m_musical_scale	285
10.60.4.10m_background_sequence	285
10.60.4.11m_mutex	285
10.61 seq64::trigger Class Reference	285
10.61.1 Detailed Description	286
10.62seq64::triggers Class Reference	287
10.62.1 Constructor & Destructor Documentation	289
10.62.1.1 triggers	289
10.62.2 Member Function Documentation	289
10.62.2.1 operator=	289
10.62.2.2 set_length	289
10.62.2.3 play	289
10.62.2.4 add	289
10.62.2.5 adjust_offsets_to_length	290
10.62.2.6 split	290
10.62.2.7 split	290
10.62.2.8 grow	290
10.62.2.9 remove	291
10.62.2.10get_state	291
10.62.2.11select	291
10.62.2.12unselect	291
10.62.2.13ntersect	291
10.62.2.14paste	292
10.62.2.15move_selected	292
10.62.2.16get_selected_start	292
10.62.2.17get_selected_end	292
10.62.2.18copy	292
10.62.2.19next	293
10.62.2.20next_trigger	293
10.62.2.21adjust_offset	293
10.62.3 Field Documentation	294
10.62.3.1 m_ppqn	294
10.62.3.2 m_length	294
10.63seq64::user_instrument Class Reference	294
10.63.1 Detailed Description	295

CONTENTS

10.63.2 Member Function Documentation	295
10.63.2.1 set_defaults	295
10.63.2.2 controller_max	295
10.63.2.3 controller_name	295
10.63.2.4 controller_active	295
10.63.2.5 set_controller	295
10.63.2.6 set_name	296
10.63.2.7 copy_definitions	296
10.63.3 Field Documentation	296
10.63.3.1 m_is_valid	296
10.63.3.2 m_controller_count	296
10.64seq64::user_instrument_t Struct Reference	296
10.64.1 Field Documentation	296
10.64.1.1 instrument	296
10.64.1.2 controllers	296
10.64.1.3 controllers_active	297
10.65seq64::user_midi_bus Class Reference	297
10.65.1 Detailed Description	298
10.65.2 Member Function Documentation	298
10.65.2.1 set_defaults	298
10.65.2.2 channel_count	298
10.65.2.3 channel_max	298
10.65.2.4 instrument	298
10.65.2.5 set_instrument	298
10.65.2.6 copy_definitions	298
10.65.3 Field Documentation	298
10.65.3.1 m_is_valid	298
10.65.3.2 m_channel_count	299
10.66seq64::user_midi_bus_t Struct Reference	299
10.66.1 Field Documentation	299
10.66.1.1 alias	299
10.66.1.2 instrument	299
10.67seq64::user_settings Class Reference	299
10.67.1 Detailed Description	305
10.67.2 Member Typedef Documentation	306
10.67.2.1 Busses	306
10.67.2.2 Instruments	306
10.67.3 Member Enumeration Documentation	306
10.67.3.1 mainwid_grid_style_t	306
10.67.4 Constructor & Destructor Documentation	306

CONTENTS xxxi

10.67.4.1 user_settings
10.67.5 Member Function Documentation
10.67.5.1 set_defaults
10.67.5.2 set_globals
10.67.5.3 get_globals
10.67.5.4 bus
10.67.5.5 instrument
10.67.5.6 controller_active
10.67.5.7 controller_name
10.67.5.8 zoom
10.67.5.9 mainwnd_rows
10.67.5.10mainwnd_cols
10.67.5.11max_sets
10.67.5.12text_x
10.67.5.13text_y
10.67.5.14mainwid_border
10.67.5.15mainwid_spacing
10.67.5.1&control_height
10.67.5.17dump_summary
10.67.5.1&perf_h_page_increment
10.67.5.19perf_v_page_increment
10.67.5.20midi_ppqn
10.67.5.21midi_buss_override
10.67.5.22midi_beats_per_bar
10.67.5.23midi_beats_per_minute
10.67.5.24midi_beat_width
10.67.5.25private_bus
10.67.5.2@private_instrument
10.67.6 Field Documentation
10.67.6.1 m_midi_buses
10.67.6.2 m_instruments
10.67.6.3 m_grid_style
10.67.6.4 m_grid_brackets
10.67.6.5 m_mainwnd_rows
10.67.6.6 m_mainwnd_cols
10.67.6.7 m_max_sets
10.67.6.8 m_mainwid_border
10.67.6.9 m_control_height
10.67.6.10m_global_seq_feature_save
10.67.6.11m_seqedit_scale

xxxii CONTENTS

dex	315
10.68.1.3 dump_setting_summary	 314
10.68.1.2 write	
10.68.1.1 parse	 314
10.68.1 Member Function Documentation	 314
10.68seq64::userfile Class Reference	 313
10.67.6.34mc_baseline_ppqn	 313
10.67.6.33mc_max_zoom	 313
10.67.6.32mc_min_zoom	 312
10.67.6.31m_save_user_config	 312
10.67.6.30m_mainwid_x	 312
10.67.6.29m_seqarea_seq_x	 312
10.67.6.28m_seqarea_x	 312
10.67.6.27m_max_sequence	 312
10.67.6.26m_gmute_tracks	 312
10.67.6.25m_seqs_in_set	 312
10.67.6.24m_midi_buss_override	 311
10.67.6.23m_midi_beat_width	 311
10.67.6.22m_midi_beats_per_minute	 311
10.67.6.21m_midi_beats_per_measure	 311
10.67.6.20m_midi_ppqn	 311
10.67.6.19m_seqchars_x	 311
10.67.6.18m_text_x	
10.67.6.17m_v_perf_page_increment	
10.67.6.16m_h_perf_page_increment	 310
10.67.6.15m_allow_two_perfedits	
10.67.6.14m_use_new_font	
10.67.6.13m_seqedit_bgsequence	
10.67.6.12m_seqedit_key	 310

Chapter 1

Sequencer64

Author(s) Chris Ahlstrom 2015-11-27

1.1 Introduction

Sequencer64 is a major cleanup, refactoring, and documentation of the Seq24 live-play MIDI sequencer.

The current document, generated by Doxygen, describes the functions, classes, modules, and other entities used in this project.

Also read the ROADMAP, README, and contrib/bugs_to_investigate files to understand the genesis of this project and the things that still need to be done with Sequencer64.

Also, we have pretty deeply documented *Seq24* and *Sequencer64* with PDF files that can be generated by git-cloning the following projects, installing a number of tools related to PDF and LaTeX, and running "make":

- https://github.com/ahlstromcj/seq24-doc.git
- https://github.com/ahlstromcj/sequencer64-doc.git

These project also have prebuilt PDFs should one not want to bother building them.

In the present document, we've left out a fair amount of side-code to cut down on the size of the document. For example, the main module, redundant Windows support, utility headers like easy_macros.h, standard stuff like the mutex module, the fruity variants (at least the ones already refactored into their own modules), etc., are all left out. Still, the resulting PDF is over 300 pages long.

Some useful references:

- http://acad.carleton.edu/courses/musc108-00-f14/pages/04/04StandardMID← IFiles.html
- http://www.midimusicadventures.com/qs/midi-zips/soundtracks/kq6gm.zip

Sequencer64

Chapter 2

MIDI File Parsing in Sequencer64

Author(s) Chris Ahlstrom 2016-01-16

2.1 Introduction

This section describes the parsing of a MIDI file. We start with the main format that is supported, SMF 1. Once we understood that we, we figured out how to split a SMF 0 tracks correctly.

We split the midifile::parse() function into two sections. The first section analyzes the header of the MIDI. Then, based on whether the file is SMF 1 (the normal case) or SMF 0, either the parse_smf_1() function of or the parse—smf_0() function is called. The parse_smf_0() function creates one sequence object per channel present in the SMF 0 file, plus the original track. The last pattern slot (sequence 16) will contain the original track data, and the rest will contain common data and then channel data for each channel. After the parsing is done, all the tracks (including the original track) will be added to the performance. The user then has the option of deleting the original track, which will be the last track.

2.2 SMF 1 Parsing

This section describes the parsing of the header chunk, MThd, and the track chunk, MTrk.

The midifile::parse() function starts by opening the MIDI file, getting its file-size, pre-allocating the data vector to that size, reading all of the characters into that vector, and then closing the file.

2.2.1 MIDI File Header, MThd

The data of the header is read:

```
"MThd"
Header ID:
                              read_long()
                                                  4 bytes
                             reau_____
read_long()
               6 read_long()
0, 1, 2 read_short()
MThd length:
                                                  4 bytes
                                                 2 bytes
No. of track: 1 or more
                              read short()
                                                  2 bytes
PPON:
                192
                               read_short()
                                                  2 bytes
```

The header ID and it's length are always the same values. The formats that Sequencer64 supports are 0 or 1. SMF 0 has only one track, while SMF 1 can support an arbitary number of tracks. The last value in the header is the PPQN value, which specifies the "pulses per quarter note", which is the basic time-resolution of events in the MIDI file. Common values are 96 or 192, but higher values are also common. Sequencer64 and its precursor, Seq24, default to 192.

2.2.2 MIDI Track, MTrk

Sequencer64 next reads the tracks specified in the file. Each track is assumed to cover a different MIDI channel, but always the same MIDI buss. (The MIDI buss is not a data item in standard MIDI files, but it is a special data item in Seq24/Sequencer64 MIDI files.) Each track is tagged by a standard chunk marker, "MTrk". Other markers are possible, and are to be ignored, if nothing else. Here are the values read at the beginning of a track:

```
Track ID: "MTrk" read_long() 4 bytes
Track length: varies read_long() 4 bytes
```

The track length is the number of bytes that need to be read in order to get all of the data in the track.

Next, a new sequence object is created, with the PPQN value passed to its constructor. The sequence then is hooked to the master MIDI buss object. The "RunningTime" accumulator is set to 0 for that track.

Next, the parse() function loops through the rest of the track, reading data and logging it to the sequence. Let's go through the loop, which is the meat of the processing.

TODO: An empty event is created before track processing, and re-used for every track and event. This seems dangerous. We moved the event constructor two levels of nesting deeper, and it seems to work fine.

Delta time. The amount time that passes from one event to the next is the *delta time*. For some events, the time doesn't matter, and is set to 0. This values is a *variable length value*, also known as a "VLV" or a "varinum". It provides a way of encoding arbitrarily large values, a byte at a time. For now, just note that a varinum is 1 or more bytes, and MIDI provides a way to tell when the varinum is complete.

```
Delta time: varies read_varinum() 1 or more bytes
```

2.2.2.1 Channel Events

Status. The byte after the delta time is examined by masking it against 0x80 to check the high bit. If not set, it is a "running status", it is replaced with the "last status", which is 0 at first.

```
Status byte: varies read_byte() 1 byte
```

If the high bit is set, it is a status, and is passed to the setter event::set_status().

The "RunningTime" accumulator is incremented by the delta-time. The current time is adjusted as per the PPQN ratio, if needed, and passed to the setter event::set_timestamp().

Now what does the status mean? First, the channel part of the status is masked out using the 0xF0 mask.

If it is a 2-data-byte event (note on, note off, aftertouch, control-change, or pitch-wheel), then the two data bytes are read:

```
Data byte 0: varies read_byte() 1 byte
Data byte 1: varies read_byte() 1 byte
```

If the status is a note-on event, with data[1] = 0, then it is converted to a note-off event, a fix for the output quirks of some MIDI devices, and the status of the event is amended to EVENT_NOTE_OFF.

If it is a 1-data-btye event (program change or channel pressure), then only data byte 0 is read.

Then the one or two data bytes are added to the event by overloads of event::set_data(), the event is added to the current sequence by sequence::add_event(), and the MIDI channel of the sequence is set by sequence::set_midi_channel().

Note that this is the point where parsing could detect a change in channel, and select a new sequence to support that channel, and add the events to that sequence, if the file were SMF 0.

Also note that the channel of the sequence is set every a new channel event/status is read. This should be done once, and then simply warned about if a non-matching channel occurs.

Lastly, note that it might be better to do the sequence function calls at the end of processing the event.

2.2 SMF 1 Parsing 5

2.2.2.2 Meta Events

If the event status masks off to 0xF0 (0xF0 to 0xFF), then it is a meta event. If the status is 0xFF, it is called a "Sequencer-specific", or "SeqSpec" event. For this kind of event, then a type byte and the length of the event are read.

```
Meta type: varies read_byte() 1 byte
Meta length: varies read_varinum() 1 or more bytes
```

If the type of the SeqSpec (0xFF) meta event is 0x7F, parsing checks to see if it is one of the Seq24 "proprietary" events. These events are tagged with various values that mask off to 0x24240000. The parser reads the tag:

```
Prop tag: 0x242400nn read_long() 4 bytes
```

These tags provide a way to save and recover Seq24/Sequencer64 properties from the MIDI file: MIDI buss, MIDI channel, time signature, sequence triggers, and (new), the key, scale, and background sequence to use with the track/sequence. Any leftover data for the tagged event is let go. Unknown tags ate skipped.

If the type of the SeqSpec (0xFF) meta event is 0x2F, then it is the End-of-Track marker. The current time is set using $sequence::set_length()$ and then $sequence::zero_markers()$ is called, and parsing is done for that track.

If the type of the SeqSpec (0xFF) meta event is 0x03, then it is the sequence name. The "length" number of bytes are read, and loaded by sequence::set_name().

If the type of the SeqSpec (0xFF) meta event is 0x00, then it is the sequence number, which is read:

```
Seq number: varies read_short() 2 bytes
```

Note that the sequence number might be modified latter to account for the current screenset in force for a file import operation.

Anything other SeqSpec type is simply skipped by reading the "length" number of bytes.

To summarize the process, here are the relevant event and sequence setter calls typically made while parsing a MIDI track:

```
1. perform::add_sequence()
   (a) sequence::sequence()
   (b) sequence::set_master_midi_bus())
   (c) sequence::add_event()
        i. event::event()
        ii. event::set_status()
        iii. event::set_timestamp()
        iv. event::set_data()
   (d) sequence::set_midi_channel()
        (e) sequence::set_length()
        (f) sequence::zero_markers()
        (g) sequence::set_name()
        (h) sequence::set_midi_bus()
2. xxxxx::yyyy()
```

2.2.3 Meta Events

Here, we summarize the MIDI meta events.

```
1. FF 00 02 ssss: Sequence Number.
```

```
2. FF 01 len text: Text Event.
```

- 3. FF 02 len text: Copyright Notice.
- 4. FF 03 len text: Sequence/Track Name.
- 5. FF 04 len text: Instrument Name.
- 6. FF 05 len text: Lyric.
- 7. FF 06 len text: Marker.
- 8. FF 07 len text: Cue Point.
- 9. FF 08 len text: Patch/program Name.
- 10. FF 09 len text: Device Name.
- 11. FF 0A through 0F len text: Other kinds of text events.
- 12. FF 20 01 cc: MIDI channel (obsolete, used by Cakewalk)
- 13. FF 21 01 pp: MIDI port (obsolete, used by Cakewalk)
- 14. FF 2F 00: End of Track.
- 15. FF 51 03 tttttt: Set Tempo, us/qn.
- 16. FF 54 05 hr mn se fr ff: SMPTE Offset.
- 17. FF 58 04 nn dd cc bb: Time Signature.
- 18. FF 59 02 sf mi: Key Signature.
- 19. FF 7F len data: Sequencer-Specific.

The next sections describe the events that Sequencer tries to handle. These are

- Sequence Number (0x00)
- Track Name (0x03)
- End-of-Track (0x2F)
- Set Tempo (0x51) (Sequencer64 only)
- Time Signature (0x58) (Sequencer64 only)
- Sequencer-Specific (0x7F)
- System Exclusive (0xF0) Sort of handled, functionality incomplete..

2.2.3.1 Sequence Number (0x00)

```
FF 00 02 ss ss
```

This optional event must occur at the beginning of a track, before any non-zero delta-times, and before any transmittable MIDI events. It specifies the number of a sequence.

2.2 SMF 1 Parsing 7

2.2.3.2 Track/Sequence Name (0x03)

```
FF 03 len text
```

If in a format 0 track, or the first track in a format 1 file, the name of the sequence. Otherwise, the name of the track.

2.2.3.3 End of Track (0x2F)

```
FF 2F 00
```

This event is not optional. It is included so that an exact ending point may be specified for the track, so that it has an exact length, which is necessary for tracks which are looped or concatenated.

2.2.3.4 Set Tempo Event (0x51)

The MIDI Set Tempo meta event sets the tempo of a MIDI sequence in terms of the microseconds per quarter note. This is a meta message, so this event is never sent over MIDI ports to a MIDI device.

After the delta time, this event consists of six bytes of data:

```
FF 51 03 tt tt tt
```

Example:

```
FF 51 03 07 A1 20
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x51 the meta event type that signifies this is a Set Tempo event.
- 3. 0x03 is the length of the event, always 3 bytes.
- 4. The remaining three bytes carry the number of microseconds per quarter note. For example, the three bytes above form the hexadecimal value 0x07A120 (500000 decimal), which means that there are 500,000 microseconds per quarter note.

Since there are 60,000,000 microseconds per minute, the event above translates to: set the tempo to 60,000,000 / 500,000 = 120 quarter notes per minute (120 beats per minute).

This event normally appears in the first track. If not, the default tempo is 120 beats per minute. This event is important if the MIDI time division is specified in "pulses per quarter note", which does not itself define the length of the quarter note. The length of the quarter note is then determined by the Set Tempo meta event.

Representing tempos as time per beat instead of beat per time allows absolutely exact DWORD-term synchronization with a time-based sync protocol such as SMPTE time code or MIDI time code. This amount of accuracy provided by this tempo resolution allows a four-minute piece at 120 beats per minute to be accurate within 500 usec at the end of the piece.

2.2.3.5 Time Signature Event (0x58)

After the delta time, this event consists of seven bytes of data:

```
FF 58 04 nn dd cc bb
```

The time signature is expressed as four numbers. nn and dd represent the numerator and denominator of the time signature as it would be notated. The numerator counts the number of beats in a measure (beats per measure or

beats per bar). The denominator is a negative power of two: 2 represents a quarter-note, 3 represents an eighth-note, etc. The denominator specifies the unit of the beat (e.g. 4 or 8). In Seq24/Sequencer64, this value is also called the "beat width".

The cc parameter expresses the number of MIDI clocks (or "ticks", or "pulses") in a metronome click. The standard MIDI clock ticks 24 times per quarter note, so a value of 6 would mean the metronome clicks every 1/8th note.

The bb parameter expresses the number of notated 32nd-notes in a MIDI quarter- note (24 MIDI Clocks). For example, a value of 16 means that the music plays two quarter notes for each quarter note metered out by the MIDI clock, so that the music plays at double speed.

Example:

```
FF 58 04 04 02 18 08
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x58 the meta event type that signifies this is a Time Signature event.
- 3. 0x04 is the length of the event, always 4 bytes.
- 4. 0x04 is the numerator of the time signature, and ranges from 0x00 to 0xFF.
- 5. 0x02 is the log base 2 of the denominator, and is the power to which 2 must be raised to get the denominator. Here, the denominator is 2 to 0x02, or 4, so the time signature is 4/4.
- 6. 0x18 is the metronome pulse in terms of the number of MIDI clock ticks per click. Assuming 24 MIDI clocks per quarter note, the value here (0x18 = 24) indidicates that the metronome will tick every 24/24 quarter note. If the value of the sixth byte were 0x30 = 48, the metronome clicks every two quarter notes, i.e. every half-note.
- 7. 0x08 defines the number of 32nd notes per beat. This byte is usually 8 as there is usually one quarter note per beat, and one quarter note contains eight 32nd notes.

If a time signature event is not present in a MIDI sequence, 4/4 signature is assumed.

In Sequencer64, the c_timesig SeqSpec event is given priority. The conventional time signature is used only if the c_timesig SeqSpec is not present in the file.

2.2.3.6 SysEx Event (0xF0)

If the meta event status value is 0xF0, it is called a "System-exclusive", or "SysEx" event.

```
FO len data F7
```

Sequencer64 has some code in place to store these messages, but the data is currently not actually stored or used. Although there is some infrastructure to support storing the SysEx event within a sequence, the SysEx information is simply skipped. Sequencer64 warns if the terminating 0xF7 SysEx terminator is not found at the expected length. Also, some malformed SysEx events have been encountered, and those are detected and skipped as well.

2.2.3.7 Sequencer Specific (0x7F)

This data, also known as SeqSpec data, provides a way to encode information that a specific sequencer application needs, while marking it so that other sequences can safely ignore the information.

```
FF 7F len data
```

In Seq24 and Sequencer64, the data portion starts with four bytes that indicate the kind of data for a particular SeqSpec event:

2.3 SMF 0 Parsing 9

In Seq24, these events are placed at the end of the song, but are not marked as SeqSpec data. Most MID← I applications handle this situation fine, but some (e.g. midicvt) do not. Therefore, Sequencer64 makes sure to wrap each data item in the 0xFF 0x7F wrapper.

Also, the last three items above (key, scale, and background sequence) can also be stored (by *Sequencer64*) with a particular sequence/track, as well as at the end of the song. Not sure if this bit of extra flexibility is useful, but it is there.

2.2.3.8 Non-Specific End of Sequence

Any other statuses are deemed unsupportable in Sequencer64, and abort parsing with an error.

If the —bus option is in force, sequence::set_midi_bus() is called to override the buss number (if any) stored with the sequence.

Finally, perform::add_sequence() adds the sequence to the encoded tune.

2.3 SMF 0 Parsing

After parsing SMF 1 track data, we end up with a number of sequences, each on a different MIDI channel. With SMF 0, data for all channels is present in a single track. Sequencer64 will read SMF 0 data, but we really need to be able to have one MIDI channel per track. So we need to take the data from the sequence and use it to make more sequences.

TODO:

```
sequence::add_event().
sequence::set_midi_channel().
sequence::set_length().
sequence::set_midi_bus().
perform::add_sequence().
```

For now, please look at the source code for more details.

JACK, Live, and Song Modes in Sequencer64

Author(s) Chris Ahlstrom 2016-01-23

3.1 Introduction

This section describes the interactions between JACK settings and the Live/Song Mode settings, with an eye to describing the proper behavior of Sequencer64 with JACK settings, how the Live/Song modes are supposed to work, and what bugs or issues remain in Sequencer64's JACK handling.

I'm not sure why Doxygen is applying the "code" font so often here. Weird, annoying.

3.2 JACK Functions

Please study the following URL and note these important points:

http://jackaudio.org/files/docs/html/transport-design.html

- The timebase master continuously updates position information, beats, timecode, etc. There is at most one master active at a time. If no client is registered as timebase master, frame numbers will be the only position information available.
- The timebase master registers a callback that updates position information while transport is rolling. Its output
 affects the following process cycle. This function is called immediately after the process callback in the same
 thread whenever the transport is rolling, or when any client has set a new position in the previous cycle.
- Clients that don't declare a sync callback are assumed ready immediately, anytime the transport wants to start. If a client doesn't require slow-sync processing, it can set its sync callback to NULL.
- The transport state is always valid; initially it is JackTransportStopped.
- When someone calls <code>jack_transport_start()</code>, the engine resets the poll bits and changes to a new state, <code>JackTransportStarting</code>.
- When all slow-sync clients are ready, the state changes to JackTransportRolling.

Does Sequencer64 need a latency callback?

 $\verb|http://jackaudio.org/files/docs/html/group_ClientCallbacks.html| \\$

(We need to see why most of the following is in a monospaced font. Is there a new Doxygen feature?)

Here are summaries of the JACK functions used in the jack_assistant module:

3.2.1 jack client open()

```
Open a client session with a JACK server. More complex and powerful than <tt>jack_client_new()</tt>.
Clients choose which of several servers to connect, and how to start the server automatically, if not already running. There is also an option for JACK to generate a unique client name.

const char * client_name, jack_options_t options, jack_status_t * status, ...
```

client_name of at most jack_client_name_size() characters. The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

options formed by OR-ing together JackOptions bits. Only the JackOpenOptions bits are allowed.

status (if non-NULL) an address for JACK to return information from the open operation. This status word is formed by OR-ing together the relevant JackStatus bits.

Optional parameters: depending on corresponding [options bits] additional parameters may follow status (in this order).

[JackServerName] (char *) server_name selects from among several possible concurrent server instances. Server names are unique to each user. If unspecified, use "default" unless \$JACK_DEFAULT_SERVER is defined in the process environment.

Returns:

Opaque client handle if successful. If this is NULL, the open operation failed, and *status includes JackFailure, and the caller is not a JACK client.

3.2.2 jack_on_shutdown()

Registers a function to call when the JACK server shuts down the client thread. It must be an asynchonrous POSIX signal handler: only async-safe functions, executed from another thread. A typical function might set a flag or write to a pipe so that the rest of the application knows that the JACK client thread has shut down. Clients do not need to call this function. It only helps clients understand what is going on. It should be called before <tt>jack_client_activate()</tt>.

3.2.3 jack_set_sync_callback()

Register/unregister as a slow-sync client; it can't respond immediately to transport position changes. The callback is run at the first opportunity after registration: if the client is active, this is the next process cycle, otherwise it is the first cycle after <tt>jack_activate()</tt>. After that, it runs as per JackSyncCallback rules. Clients that don't set this callback are assumed ready immediately any time the transport wants to start.

3.2.4 jack_set_process_callback()

Tells the JACK server to call the callback whenever there is work. The function must be suitable for real-time execution, it cannot call functions that might block for a long time: malloc(), free(), printf(), pthread_mutex_lock(), sleep(), wait(), poll(), select(), pthread_join(), pthread_cond_wait(), etc. In the current class, this function is a do-nothing function.

3.2 JACK Functions 13

3.2.5 jack_set_session_callback()

Tells the JACK server to call the callback when a session event is delivered. Setting more than one session callback per process is probably a design error. For a multiclient application, it's more sensible to create a JACK client with only one session callback.

3.2.6 jack activate()

Tells the JACK server that the application is ready to start processing.

3.2.7 jack_release_timebase()

TODO

3.2.8 jack client close()

TODO

3.2.9 jack_transport_start()

Starts the JACK transport rolling. Any client can make this request at any time. It takes effect no sooner than the next process cycle, perhaps later if there are slow-sync clients. This function is realtime-safe. No return code.

3.2.10 jack_transport_stop()

3.2.11 jack transport locate()

Repositions the transport to a new frame number. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

3.2.12 jack_transport_reposition()

Request a new transport position. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe. This call, made in the position() function, is currently disabled.

3.2.13 jack_transport_query()

Query the current transport state and position. This function is realtime-safe, and can be called from any thread. If called from the process thread, pos corresponds to the first frame of the current cycle and the state returned is valid for the entire cycle.

The first parameter is the client, which is a pointer to the JACK client structure.

The second parameter is a pointer to structure for returning current transport position; pos->valid will show which fields contain valid data. If pos is NULL, do not return position information.

This function returns the current transport state.

3.3 Modes Operation

3.3.1 No JACK, Live Mode

In ~/.config/sequencer64/sequencer64.rc, set:

- jack transport = 0
- jack master = 0
- jack master cond = 0
- jack_start_mode = 0

By changing the start mode to 0 (false), Sequencer64 is put into Live Mode. With this setting, control of the muting and unmuting of patterns resides in the main window (the patterns window). One can start the playback in the performance (song) window, but it will not affect which patterns play, at all.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.3.2 No JACK, Song Mode

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack_master = 0
- jack master cond = 0
- jack_start_mode = 1

By changing the start mode to 1 (true), Sequencer64 is put into Song Mode.

With this setting, control of the muting and unmuting of patterns resides in the song window (the performance window). The patterns shown in the pattern slots of the main window turn on and off whenever the progress bar is in the pattern as drawn in the perforance window.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.3.3 JACK Transport

In ~/.config/sequencer64/sequencer64.rc, set:

- jack transport = 1
- jack master = 0
- jack_master_cond = 0
- jack_start_mode = 0 or 1 (see previous section)

3.4 Breakage 15

The current behavior is that qjackctl and sequencer64 playback/progress seem to be independent of each other.

The workaround seems to be to set seq24/sequencer64 as JACK Master, or if another application (e.g. Qtractor) is JACK Master.

OLD BEHAVIOR:

```
Start qjackctl, verify that it sets up correctly, then click it's
"play" button to start the transport rolling. Run sequencer64, load a
file. Then note that starting playback (whether in the main window or
in the performance window) is ineffective, but resets the time counter
in qjackctl. Why? With JACK sync enabled by the macro:

[JACK transport slave]
    jack sync(): zero frame rate [single report]!?
    [JackTransportRolling]
    [JackTransportStarting] (every time space bar pressed)
    [Start playback]
```

END OF OLD BEHAVIOR.

3.4 Breakage

Old message about seq24 being broken:

```
\verb|http://lists.linuxaudio.org/pipermail/linux-audio-user/2010-November/073848. \leftarrow \verb|html||
```

```
i dont see the transport synchronisation working with a jackl svn version. you are still using only a sync callback.

and you are relying on the transport to go through the JackTransportStarting state.

this issue should be fixed.
iirc we came to the conclusion, that seq24 is broken, and we will not revert the changes in jack, which break it.

the quick and dirty fix on your side, would be to register an empty process_callback.

but the issue still remains. seq24 is NOT a slow sync client. but it registers a sync_callback.

and it even takes a lock in the sync callback.

the patch for jack-session support didnt get merged either.
```

Another one (no need for a URL):

```
I use seq24 for the majority of my projects but it isn't ideal (I should point out that I never finish anything). I don't like seq24's pianoroll editor, the way you do CC envelopes isn't ideal, it uses alsa-midi, there's unnecessary complexity in switching from pattern-trigger mode to song mode, and its insistence on being transport master while not even being able to adjust tempo when live is annoying
```

3.5 JACK References

- http://libremusicproduction.com/articles/demystifying-jack-%E2%80%93-beginners-guide
- http://jackaudio.org/files/docs/html/transport-design.html
- http://kxstudio.linuxaudio.org/Repositories

16	JACK, Live, and Song Modes in Sequencer64

User Testing of Sequencer64 with Yoshimi

Author(s) Chris Ahlstrom 2015-10-18

4.1 Introduction

This section describes user testing of Sequencer64 using Yoshimi. It will expand as we work our way through all the many use-cases that can be achieved with Sequencer64 and Yoshimi.

4.2 Smoke Test

Every so often we run Sequencer64 with a software synthesizer to make sure we haven't broken any functionality via our major refactoring efforts. We call it a "smoke test". We fire up the two application, and see if anything smokes.

This smoke test sets up Yoshimi with a very simple ALSA setup, and no instruments are loaded. Instead, only the "Simple Sound" is used on all channels. We've been doing this test with Yoshimi 1.3.6. The current Debian Sid ("testing") version of Yoshimi is 1.3.6-2, pulled from SourceForge. It seems to have issues, so we've been cloning and pulling the code from:

```
https://github.com/Yoshimi/yoshimi.git
```

After getting the application build and installed, the next step is to run it, using ALSA for MIDI and for audio:

```
$ yoshimi -a -A &
```

Next, fix up the configuration files for Sequencer64, \sim /.config/sequencer64/sequencer64.rc and \sim /.config/sequencer64/sequencer64.usr.

First hide sequencer64.usr somewhere, or delete it, as it will determine what MIDI devices are available, and we don't want that (yet). Second, make sure that sequencer64.rc makes the following setting:

```
[manual-alsa-ports]
# Set to 1 if you want seq24 to create its own ALSA ports and
# not connect to other clients
0  # number of manual ALSA ports
```

Next, run the newly-built version of Sequencer64. If desired, use the –bus option described below to force the buss number to the buss you need, as shown in the second version of the command:

```
$ sequencer64/sequencer64 &
$ sequencer64/sequencer64 --bus 5 &
```

In File / Options / MIDI Clock, observe the MIDI inputs made available by your system. Our system shows:

```
[0] 14:0 (Midi Through Port-0)

[1] 128:0 (TiMidity port 0)

[2] 128:0 (TiMidity port 1)

[3] 128:0 (TiMidity port 2)

[4] 128:0 (TiMidity port 3)

[5] 129:0 (input)
```

For some reason (a bug in Yoshimi?), input "[5]" doesn't indicate that it is Yoshimi, but it is. Take note of that input number... that is the MIDI buss number that is needed to drive Yoshimi.

Also make sure that of the clock settings for those busses are "Off".

The next instruction still works, but it is easier to simply pass the option -bus 5 to Sequencer64 when starting it up.

Now open the file sequencer64/contrib/midi/b4uacuse-GM-format.midi in Sequencer64. For all of the patterns (slots) that have lots of data in them, right click on the pattern and select *Midi Bus* / [5] 129:0 (input) and the desired channel number. (Doesn't matter much, just use up the lower channel numbers first).

Back in Yoshimi, select each Part corresponding to the channels you selected. Make sure *Enabled* is checked for each desired channel.

Back in Sequencer64, click on each pattern you want to hear, which highlights them in black. Now click the play button (green triangle). The song should play, with each part using the "Simple Sound". Not too bad for a bunch of sine waves, eh?

Now we can test the application more fully. Note that the instructions here are very light. Detailed instructions on the usage of Sequencer64 can be found in the following project, which contains a PDF file and the LaTeX code used to build it:

```
https://github.com/ahlstromcj/sequencer24-doc.git
```

Although it applies to an earlier version of the project, it still mostly holds true for Sequencer64.

4.3 Tests in the Patterns Window

The Patterns window is the inside portion of the main window, supported by the mainwid class. it contains a grid of boxes or slots, with each slot potentially containing a pattern, sequence, or track. Empty tracks (i.e. tracks that contain no events, like title-only tracks) are highlighted in yellow.

This window supports only a single variant of mouse-handling.

4.3.1 Button Clicks on a Pattern

A left-click on a pattern slot should cause the following to happen:

- 1. The pattern will be highlighted (white on a black background). This won't occur until the button is released.
- 2. During playback, the pattern will emit MIDI events and play its sequence.
- 3. If the pattern is dragged to another slot, whether playing is in progress or not, releasing the button in the destination slot will move the pattern to that slot.

A right-click on a pattern slot should cause the following to happen:

- 1. If the pattern is empty, then a pop-up menu to make a New pattern, paste a pattern, or make other selections will appear.
- 2. If the pattern is active, then a pop-up menu to Edit the pattern or make other selections will appear.
- 3. A second right-click, just off the menu, will dismiss the menu.

4.3.2 Patterns Window Key Shortcuts

First, note the selection of the File / Options / Keyboard / Show keys option. The tests here should work whether or not it is selected. The only difference is if the keys are shown.

We got a segfault during this test, when we weren't being systematic about it.

4.3.3 The Sequencer64 User File

To be discussed.

4.4 Tests Using Valgrind

Valgrind is a very useful tool for unearthing memory issues and other issues in an application, especially when one has the source code and can build the code with debugging information.

One runs the application from the command line, preceding its command line with valgrind and some of its options.

4.4.1 Valgrind Suppressions

One problem with valgrind is that it also uncovers errors in system libraries that one has no control over. These errors clutter the output, so we suppress them using a valgrind "suppressions" file. Here's how to create one:

```
$ valgrind --gen-suppressions=yes --log-file=val.supp ./Sequencer64/sequencer64
$ valgrind --gen-suppressions=all --log-file=val.supp ./Sequencer64/sequencer64
```

As the program runs, one is asked to print a suppression. If the error is due to a system or third-party library, answer "Y return", and then copy-and-paste the suppression to a file, giving it a name. For example, we provide a file contrib/seq64.supp containing suppressions of errors that annoy us. There are way too many "errors" in ALSA, GTK+, gtkmm, glibc, and more.

The second command collects all the suppressions. Passing the val.supp file through sed makes it immediately usable:

```
$ sed -i -e /^==/g val.supp
```

Running valgrind like this then shows mostly the errors we care about:

```
$ valgrind --suppressions=val.supp ./Sequencer64/sequencer64
```

We've added some other suppression files to the contrib directory. Too much! For example:

```
https://github.com/dtrebbien/GNOME.supp
```

However, overall this process is very painful, and we're going to eventually do all the valgrind work on the unit-test project for Sequencer64:

```
https://github.com/ahlstromcj/seq64-tests
```

4.4.2 Full Valgrind Leak-Checking

Here's how to capture errors, while suppressing the system errors and while generating a log file:

```
$ valgrind --suppressions=contrib/seq64.supp --leak-check=full \
    --track-origins=yes --log-file=valgrind.log --show-leak-kinds=all \
    ./Sequencer64/sequencer64
```

The errors can be also be re-routed to a log-file via the "2> valgrind.log" shell redirection.

Another idea is to precede the valgrind command with the following construct:

```
\ G_SLICE=debug-blocks\ valgrind\ \dots
```

G_SLICE=debug-blocks will turn off gtk's advanced memory management to allow valgrind to show correct results. This results in an amazing plethora or invalid read and invalid write errors in GNOME-related libraries. Sheesh!

And don't forget about Valgrind's "massif" memory-tracking tool! (More to come!)

4.4.2.1 Leak-Checking Basic Operation

For the first pass, just run Sequencer64, then immediately exit. Then scan the log file to see if any "errors" can be pinpointed to the application and library code.

Don't forget to run the same scenario without valgrind, in a console window, to see if any of our own debug/problem output occurs.

In any case, leakage tagged as "still reachable" isn't as bad as leakage tagged as "definitely lost" or "indirectly lost".

But good luck finding a Sequencer64 bug buried in the chaff of 3rd-party valgrind reports, even with some suppressions enabled. Apparently a lot of them have to do with data structures that are intended to last the full life of the application.

One can make the search a little easier by searching for the "seq64" namespace in the valgrind log.

4.5 Specific Fault Debugging

This section goes through specific debugging cases we encountered. They should be part of the regular testing of Sequencer64.

4.6 Snipping of a MIDI file.

In order to have a test file for the <code>seq64-tests</code> project, we loaded up the <code>b4uacuse-GM-format.midi</code> file, removed all but four of the tracks, and saved it as <code>b4uacuse-snipped.midi</code>. Loading this file into Sequencer64 caused the following:

```
$ ./Sequencer64/sequencer64
[Reading user configuration /home/ahlstrom/.config/sequencer64/sequencer64.usr]
[Reading rc configuration /home/ahlstrom/.config/sequencer64/sequencer64.rc]
get_sequence(): m_seqs[4] not null
Segmentation fault
```

First step, fire up a debugger and see what happened. We use cgdb, a text-based front-end for gdb with a "vi" feel.

```
$ cgdb ./Sequencer64/sequencer64
```

Just hit "r", do File / Open, navigate to b4uacuse-snipped.midi, select it, and watch what happens.

The "bt" (backtrace) command shows a pretty large stack, 52 items. Page up to the top of the stack, and select frame 1 ("fr 1"). This shows a mutex at a very low address, 0x650! Frame 2 shows we are in the automutex constructor, calling lock() on that same badly-located mutex. Frame 3 is in sequence::event_count(), same bad mutex, and the m_events member is at address 0x0. Obviously, we're dealing with an unallocated sequence.

Frame 4 is in mainwid::draw_sequence_on_pixmap(), just after we've retrieved the next sequence via perform ::get_sequence(4). But that would be the fifth sequence (the sequence numbers start at 0), and we snipped all but 4 from the file before we saved it.

So, one thing we need to do is *check* the value returned by get_sequence() before we try to use it. The other thing to do is figure out how we got to the fifth sequence, and fix that code as well. Using the command "p perf(). \leftarrow sequence count()", we verify that there are indeed only 4 sequences allocated.

Frame 5 is in mainwid::draw_sequences_on_pixmap(). That function tries to load all sequences on the current screen-set, from 0 to 31, without checking to see how many their actually are. Inefficient and dangerous.

Frame 6 is in mainwid::reset(). We could pass perf().sequence_count() here for checking, or get it in mainwid ::draw_sequences_on_pixmap().

Before we fix this issue, we need to load a file that works, to see why it does not fail for most files. We will put a breakpoint at the top mainwid::draw sequences_on_pixmap().

We hit the breakpoint before even loading a file, with a sequence_count() of 0. The call to valid_sequence(0) passes the test. We may want to make valid_sequence() take the sequence_count() into account. But the call to perf().is_active(0) prevents anything bad from happening at startup time.

Once we load a good file, the sequence_count() is 14 in mainwid::draw_sequences_on_pixmap(). We turn on the display of "offset" using the command "display offset", and "c" (for "continue") until offset = 14, which means we are beyond that last sequence. That bad access is prevented by perf().is_active(14).

So the fundamental problem is that perf().is_active(4) is not protecting the access when we load the "bad file". We need to find and fix that issue before papering over the problem with better access checks.

Start again, putting a breakpoint in the call to "new sequence(m_ppqn)" in midifile. This call sets up some members and clears the list of 256 playing notes. Add another breakpoint at "a_perf.add_sequence()" to see what's happening there.

What we find is that the first two tracks have proper sequence numbers as read from the MIDI file, 0 and 1. But the third one preserves the number from the old file, 4. We have a disjunction between the track number and the sequence number, a conceptual problem. We can leave it as is, and beef up the error-checking, or replace the sequence number with the track number when loading the file. What to do?

- Make sure that the is-active flag for all sequences is "false", that the pointers are always null, and make sure to test both of these items (depending on context) before doing anything with the sequence.
- Convert the sequence number to the track number upon saving the MIDI file, or upon reading the MIDI file, and use that number when adding the sequence to the perform object. This might affect some seq24/sequencer64 functionality, however. It's big move.

We need information on reading and importing.

First, if we look at a file that we created long ago by importing b4uacuse.mid, b4uacuse-GM-format. \leftarrow midi, it has its fourteen sequence numbers identical to their track numbers. No problem.

Second, if we just read b4uacuse.mid, a non-seq24-created MIDI file, we see that each of its tracks have no sequence number – they are all zero. The perform::add_sequence() simple iterates from the beginning of m_seqs[] until it finds an inactive m_seqs[i], and uses that element to hold the sequence pointer.

But now it also segfaults! Let's fix all the non-checked get_sequence() calls right away, it is too big an issue to ignore.

In the end, we have to be aware that a screen-set can have blank (null) slots interspersed amongst the active slots.

User Test	ing of Se	equencer	64 with Y	<u>'oshimi</u>

22

Licenses

Library This application and its libraries, sub-applications, and documents.

Author(s) Chris Ahlstrom 2015-09-10

5.1 License Terms for the This Project.

Wherever the tag \$XPC_SUITE_GPL_LICENSE\$ appears, or wherever reference to the GPL licensing scheme (any version) is mentioned, substitute the appropriate license text, depending on whether the project is a library, application, documentation, or server software. We're not going to include paragraphs of licensing information in every module; you are responsible for coming here to read the licensing information.

These licenses apply to each sub-project and file artifact in the project with which this license description was packaged.

Wherever the term **XPC** is encountered in this project, it refers to my projects, which go beyond the package that contains this document.

5.2 XPC Application License

The **XPC** application license is either the **GNU GPLv2**. or the **GNU GPLv3**. Generally, projects that originate with me use the latter language, while projects I have extended may specify the former license.

Copyright (C) 2015-2015 by Chris Ahlstrom

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the

Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.

The text of the GNU GPL version 3 license can also be found here:

http://www.gnu.org/licenses/gpl-3.0.txt

24 Licenses

5.3 XPC Library License

The XPC library license is the GNU LGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Lesser Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU LGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/lgpl-3.0.txt
```

5.4 XPC Documentation License

The XPC documentation license is the GNU FDLv1.3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This documentation is free documentation; you can redistribute it and/or modify it under the terms of the GNU Free Documentation License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Free Documentation License along with this documentation; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU FDL version 1.3 license can also be found here:

```
http://www.gnu.org/licenses/fdl.txt
```

5.5 XPC Affero License

The XPC "Affero" license is the GNU AGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This server software is free server software; you can redistribute it and/or modify it under the terms of the GNU Affero General Public License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Affero General Public License along with this server software; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU AGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/agpl-3.0.txt
```

At the present time, no **XPC** project uses the "Affero" license.

5.6 XPC License Summary

Include one of these licenses in your Doxygen documentation with one of the following Doxygen tags specified above:

```
\ref gpl_license_subproject
\ref gpl_license_application
\ref gpl_license_library
\ref gpl_license_documentation
\ref gpl_license_affero
```

For more information on navigating GNU licensing, see this page:

```
http://www.gnu.org/licenses/
```

Copies of these licenses (and some logos) are provided in the licenses directory of the main project (or you can search for them at *gnu.org*).

26 Licenses

Todo List

File calculations.cpp

There are additional user-interface and MIDI scaling variables in the perfroll module that we need to move here.

File perfnames.cpp

When bringing up this dialog, and starting play from it, some extra horizontal lines are drawn for some of the sequences. This happens even in seq24, so this is long standing behavior. Is it useful, and how? Where is it done? In perfroll?

Global seq64::editable events::save events ()

Consider what to do about the sequence::m_is_modified flag.

Global seq64::eventedit::handle save ()

Could also support writing the events to a new sequence, for added flexibility.

Global seq64::mainwid::timeout ()

We should use this callback to display the current time in the playback.

Global seq64::mainwnd::mainwnd (perform &a_p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAUL ← T_PPQN)

Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

Global seq64::mainwnd::on_key_press_event (GdkEventKey *a_ev)

Test this functionality in old and new application.

Global seq64::mainwnd::on_key_release_event (GdkEventKey *a_ev)

Test this functionality in old and new application.

Global seq64::perfedit::perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAU← LT_PPQN)

Offload most of the work into an initialization function like options does.

Global seq64::perform::add sequence (sequence *seq, int perf)

Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Global seg64::perform::is active (int seg)

We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Global seq64::perform::m seqs [c max sequence]

First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

Global seq64::perform::set_beats_per_minute (int bpm)

I think this logic is wrong, in that it needs only one of the two to be stopped before it sets the BPM, while it seems to me that both should be stopped; to be determined.

28 Todo List

Global seq64::perform::set_left_tick (midipulse tick, bool setstart=true)

The perform::m_one_measure member is currently hardwired to PPQN * 4.

Global seq64::seqedit::get_measures ()

Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

Global seq64::seqedit::seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT → PPQN)

Offload most of the work into an initialization function like options does.

Global seq64::seqedit::set background sequence (int seq)

Make the sequence pointer a reference.

Global seq64::seqmenu::m_modified

We need to make sure that the perform object is in control of the modification flag.

Global seq64::seqmenu::seq_clear_perf ()

All of seg_paste() can be offloaded to a (new) perform member function.

Global seq64::seqmenu::seq_copy ()

Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

Global seq64::seqmenu::seq_cut ()

A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard nonconst reference parameter.

Global seq64::seqmenu::seq_paste ()

All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

Global seq64::sequence::remove (event &e)

Use find instead in sequence::remove()!

Global seq64::triggers::next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_← offset)

It would be a bit simpler to simply return a trigger object, wouldn't it?

Deprecated List

Global seq64::sequence::get_name () const

30 **Deprecated List**

Hierarchical Index

8.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

32 Hierarchical Index

seq64::keys_perform
seq64::keys_perform_gtk2
seq64::keys_perform_transfer
seq64::keystroke
seq64::lash
seq64::midi_container
seq64::midi_list
seq64::midi_vector
seq64::midi_measures
seq64::midi_splitter
seq64::midi_timing
seq64::midibus
seq64::midifile
seq64::mutex
seq64::condition_var
seq64::options
seq64::perform
seq64::performcallback
seq64::mainwnd
seq64::rc_settings
seq64::rect
seq64::gui_drawingarea_gtk2::rect
seq64::Seq24SeqEventInput
seq64::Seq24SeqRollInput
seq64::seqmenu
seq64::mainwid
seq64::perfnames
seq64::sequence
seq64::trigger
seq64::triggers 287 seq64::user_instrument 294
seq64::user instrument t
seq64::user midi bus
seq64::user_midi_bus_t
seq64::user settings

Data Structure Index

9.1 Data Structures

Here are the data structures with brief descriptions:

seq64::AbstractPerfInput	
Provides an abstract base class to provide the minimal interface for the various "perf input" classes	??
seq64::automutex	
Provides a mutex that locks automatically when created, and unlocks when destroyed	??
seq64::click	
Encapsulates any possible mouse click	??
seq64::condition_var	
A mutex works best in conjunction with a condition variable	??
seq64::configfile	
This class is the abstract base class for optionsfile and userfile	??
seq64::editable_event	
Provides for the management of MIDI editable events	??
seq64::editable events	
Provides for the management of an ordered collection MIDI editable events	??
seg64::event	
Provides events for management of MIDI events	??
seq64::event list::event key	
Provides a key value for an event map	??
seq64::event_list	
Receptable for MIDI events	??
seq64::eventedit	
This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence	??
seq64::eventslots	
This class implements the left-side keyboard in the patterns window	??
seq64::font	
This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format	??
seq64::gui_assistant	
This class provides an interface for some of the GUI support needed in Sequencer64	??
seq64::gui_assistant_gtk2	
This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64	??
seq64::gui_drawingarea_gtk2	
Implements the basic drawing areas of the application	??
seq64::gui_palette_gtk2	
Implements a stock palette of Gdk::Color elements	??

34 Data Structure Index

seq64::gui_window_gtk2	
This class supports a basic interface for Gtk::Window-derived objects	??
seq64::jack_assistant	
This class provides the performance mode JACK support	??
seq64::jack_scratchpad	
Provide a temporary structure for passing data and results between a perform and jack_assistant object	??
seg64::keybindentry	
Class for management of application key-bindings	??
seq64::keys_perform	
This class supports the performance mode	??
seq64::keys_perform_gtk2	• •
This class supports the performance mode	??
seq64::keys_perform_transfer	• •
Provides a data-transfer structure to make it easier to fill in a keys_perform object's members	
using sscanf()	??
seq64::keystroke	• •
Encapsulates any practical keystroke	??
seq64::lash	• •
This class supports LASH operations, if compiled with LASH support (i.e	??
seq64::maintime	• •
This class provides the drawing of the progress bar at the top of the main window, along with two	
"pills" that move in time with the beat and measure	??
seq64::mainwid	• •
This class implement the piano roll area of the application	??
seq64::mainwnd	• • •
This class implements the functionality of the main window of the application, except for the	
Patterns Panel functionality, which is implemented in the mainwid class	??
seq64::midi_container	• •
This class is the abstract base class for a container of MIDI track information	??
seq64::midi_list	• •
This class is the std::list implementation of the midi_container	??
seq64::midi_measures	• •
Provides a data structure to hold the numeric equivalent of the measures string "measures↔	
:beats:divisions" ("m:b:d")	??
seq64::midi_splitter	
This class handles the parsing and writing of MIDI files	??
seq64::midi_timing	
We anticipate the need to have a small structure holding the parameters needed to calculate	
MIDI times within an arbitrary song	??
seq64::midi_vector	
This class is the std::vector implementation of the midi_container	??
seq64::midibus	
Provides a class for handling the MIDI buss on Linux	??
seg64::midifile	
This class handles the parsing and writing of MIDI files	??
seg64::mutex	• •
Simple wrapper for the pthread_mutex_t type used as a recursive mutex	??
seq64::options	• •
This class supports a full tabbed options dialog	??
seq64::optionsfile	• •
Provides a file for reading and writing the application' main configuration file	??
seq64::perfedit	• •
This class supports a Performance Editor that is used to arrange the patterns/sequences defined	
in the patterns panel	??
seq64::perfnames	• •
This class implements the left-side keyboard in the patterns window	??
The diaso implemente the fold dide helpodard in the patterns window	

9.1 Data Structures 35

seq64::perform	
This class supports the performance mode	??
seq64::performcallback	
Provides for notification of events	??
seq64::perfroll	
This class implements the performance roll user interface	??
seq64::perftime	
This class implements drawing the piano time at the top of the "performance window" (the "song	
editor")	??
seq64::rc_settings	
This class contains the options formerly named "global_xxxxxxx"	??
seq64::rect	
A small helper class representing a rectangle	??
seq64::gui_drawingarea_gtk2::rect	00
A small helper structure representing a rectangle	??
seq64::Seq24PerfInput	??
Implements the default (Seq24) performance input characteristics of this application	"
seq64::Seq24SeqEventInput This structure implement the normal interaction methods for Seq24	??
This structure implement the normal interaction methods for Seq24 seq64::Seq24SeqRollInput	11
Implements the Seq24 mouse interaction paradigm for the seqroll	??
seq64::seqdata	
This class supports drawing piano-roll eventis on a window	??
seq64::seqedit	٠.
Implements the Pattern Editor, which has references to:	??
seq64::seqevent	• •
Implements the piano event drawing area	??
seq64::seqkeys	• •
This class implements the left side piano of the pattern/sequence editor	??
seq64::seqmenu	
This class handles the right-click menu of the sequence slots in the pattern window	??
seq64::seqroll	
Implements the piano roll section of the pattern editor	??
seq64::seqtime	
This class implements the piano time, whatever that is	??
seq64::sequence	
Firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern	??
seq64::trigger	
This class hold a single trigger for a sequence object	??
seq64::triggers	
Receptable the triggers that can be used with a sequence object	??
seq64::user_instrument	
Provides data about the MIDI instruments, readable from the "user" configuration file	??
seq64::user_instrument_t	
This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr	
or \sim /.config/sequencer64/sequencer64.usr file	??
seq64::user_midi_bus	
Provides data about the MIDI busses, readable from the "user" configuration file	??
seq64::user_midi_bus_t	
This structure corresponds to [user-midi-bus-0] definitions in the ~/.seq24usr	
("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the	
application)	??
seq64::user_settings	
Holds the current values of sequence settings and settings that can modify the number of se-	
quences and the configuration of the user-interface	??
seq64::userfile	
Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24us	
configuration file	"

36 **Data Structure Index**

Data Structure Documentation

10.1 seq64::AbstractPerfInput Class Reference

Provides an abstract base class to provide the minimal interface for the various "perf input" classes. Inheritance diagram for seq64::AbstractPerfInput:



10.2 seq64::automutex Class Reference

Provides a mutex that locks automatically when created, and unlocks when destroyed.

Public Member Functions

• automutex (mutex &my_mutex)

Principal constructor gets a reference to a mutex parameter, and then locks the mutex.

∼automutex ()

The destructor unlocks the mutex.

Private Attributes

• mutex & m_safety_mutex

Provides the mutex reference to be used for locking.

10.2.1 Detailed Description

This has a couple of benefits. First, it is more threadsafe in the face of exception handling. Secondly, it can be done with just one line of code.

10.3 seq64::click Class Reference

Encapsulates any possible mouse click.

Public Member Functions

· click ()

The constructor for class click.

click (int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SE
Q64_NO_MASK)

Principal constructor for class click.

• click (const click &rhs)

Provides a stock copy constructor.

click & operator= (const click &rhs)

Provides a stock principal assignment operator.

• bool is_press () const

'Getter' function for member m_is_press

• bool is_left () const

'Getter' function for member m_button to test for the left button.

• bool is_middle () const

'Getter' function for member m_button to test for the middle button.

bool is_right () const

'Getter' function for member m_button to test for the right button.

• int x () const

'Getter' function for member m_x

• int y () const

'Getter' function for member m_y

int button () const

'Getter' function for member m_button

• seq_modifier_t modifier () const

'Getter' function for member m modifier

• bool mod_control () const

'Getter' function for member m_modifier tested for Ctrl key.

• bool mod_control_shift () const

'Getter' function for member m_modifier tested for Ctrl and Shift key.

• bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

• bool m_is_press

Determines if the click was a press or a release event.

• int m x

The x-coordinate of the click.

• int m_y

The y-coordinate of the click.

• int m button

The button that was pressed or released.

· seg modifier t m modifier

The optional modifier value.

10.3.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

10.3.2 Constructor & Destructor Documentation

```
10.3.2.1 seq64::click::click()
```

Sets all members to false, zero, or the lowest good value.

```
10.3.2.2 seq64::click::click ( int x, int y, int button = SEQ64_CLICK_BUTTON_LEFT, bool press = true, seq_modifier_t modkey = SEQ64_NO_MASK )
```

This function is the only way to set value for the click members (other than the copy constructor and principal assignment operator.

Parameters

X	The putative x value of the button click.
у	The putative y value of the button click.
button	The value of the button that was clicked, set to 1, 2, or 3.
press	Set to true if the event was a button press, false if it was a button release.
modkey	Indicates which modifier key (such as Ctrl or Alt), if any, was pressed at the same time as the
	click action.

10.3.2.3 seq64::click::click (const click & rhs)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be copied.

10.3.3 Member Function Documentation

10.3.3.1 click & seq64::click::operator= (const click & rhs)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be assigned from. The assignment is not made if "this" has the
	same address as this parameter.

10.3.4 Field Documentation

```
10.3.4.1 int seq64::click::m_x [private]
```

0 is the left-most coordinate.

```
10.3.4.2 int seq64::click::m_y [private]
```

0 is the top-most coordinate.

```
10.3.4.3 int seq64::click::m_button [private]
```

Left is 1, mmiddle is 2, and right is 3. These numbers are defined via macros, and are Linux-specific and Gtk-specific.


```
10.3.4.4 seq_modifier_t seq64::click::m_modifier [private]
```

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

10.4 seq64::condition_var Class Reference

A mutex works best in conjunction with a condition variable.

Inheritance diagram for seq64::condition_var:



Public Member Functions

• condition_var ()

Initialize the condition variable with the global variable.

• void wait ()

Waits for the confition variable.

• void signal ()

Signals the confition variable.

Private Attributes

pthread_cond_t m_cond

Provides a class-specific condition variable.

Static Private Attributes

· static const pthread_cond_t cond

Provides a "global" condition variable.

Additional Inherited Members

10.4.1 Detailed Description

Therefore this class derives from the mutex class. A "has-a" relationship might be more logical than this "is-a" relationship.

10.4.2 Field Documentation


10.4.2.1 const pthread_cond_t seq64::condition_var::cond [static], [private]

Define the static condition variable used by all mutex locks.

10.5 seq64::configfile Class Reference

This class is the abstract base class for optionsfile and userfile.

Inheritance diagram for seq64::configfile:



Public Member Functions

- configfile (const std::string &a_name)

 Provides the string constructor for a configuration file.
- virtual ~configfile ()

A rote destructor needed for a base class.

Protected Member Functions

void next_data_line (std::ifstream &a_file)
 Gets the next line of data from an input stream.

• void line_after (std::ifstream &a_file, const std::string &a_tag)

This function gets a specific line of text, specified as a tag.

Protected Attributes

std::string m name

Provides the name of the file.

char * m_d

Points to an allocated buffer that holds the data for the configuration file.

char m_line [SEQ64_LINE_MAX]

The current line of text being processed.

10.5.1 Constructor & Destructor Documentation

10.5.1.1 seq64::configfile::configfile (const std::string & name)

Parameters

name	The name of the configuration file.
------	-------------------------------------

10.5.2 Member Function Documentation

10.5.2.1 void seq64::configfile::next_data_line (std::ifstream & file) [protected]

If the line starts with a number-sign, a space (!), or a null, it is skipped, to try the next line. This occurs until an EOF is encountered.

We may try to convert this item to a reference; pointers can be subject to problems. For example, what if someone passes a nullpointer? For speed, we don't check it.

Member m_line is a "global" return value.

Parameters

a_file Points to an input stream.		
-------------------------------------	--	--

10.5.2.2 void seq64::configfile::line_after (std::ifstream & file, const std::string & tag) [protected]

Parameters

file	Points to the input file stream.
tag	Provides a tag to be found. Lines are read until a match occurs with this tag.

10.5.3 Field Documentation

10.5.3.1 char seq64::configfile::m_line[SEQ64_LINE_MAX] [protected]

This member receives an input line, and so needs to be a character buffer.

10.6 seq64::editable_event Class Reference

Provides for the management of MIDI editable events.

Inheritance diagram for seq64::editable_event:

```
seq64::event
 - m_timestamp
- m_status
- m_channel
 - m_data
 - m_sysex
- m_sysex_size
- m_linked
 - m_has_link
 - m_selected
- m_marked
- m_painted
 + event()
 + event()
+ operator=()
 + ~event()
+ operator<()
+ set_timestamp()
+ set_timestamp()
+ get_timestamp()
+ get_channel()
+ check_channel()
+ mod_timestamp()
 and 39 more...
+ is_channel_msg()
 + is_one_byte_msg()
 + is_two_byte_msg()
+ is_note_msg()
 + is_desired_cc_or_not_cc()
       seq64::editable_event
 + sm_category_names
+ sm_channel_event_names
+ sm_system_event_names
+ sm_meta_event_names
+ sm_category_arrays
- m_category_arrays
- m_parent
- m_category
- m_name_category
- m_format_timestamp
 - m_name_timestamp
- m_name_status
- m_name_meta
- m_name_seqspec
- m_name_channel
 - m_name_data
 + editable_event()
+ editable_event()
+ editable_event()
+ editable_event()
+ ~editable_event()
+ parent()
+ category()
+ category()
+ category_string()
 + category()
+ timestamp_string()
+ timestamp_string
and 14 more...
+ value_to_name()
+ name_to_value()
- editable_event()
- operator=()
- analyze()
```

Public Types

```
    enum category_t {
        category_name,
        category_channel_message,
        category_system_message,
        category_meta_event,
        category_prop_event }
```

```
    enum timestamp_format_t {
        timestamp_measures,
        timestamp_time,
        timestamp_pulses }
```

Public Member Functions

• editable_event (const editable_events &parent)

This constructor simply initializes all of the class members.

editable_event (const editable_events &parent, const event &ev)

Event constructor.

editable_event (const editable_event &rhs)

This copy constructor initializes most of the class members.

virtual ∼editable_event ()

This destructor current is a rote virtual function override.

· const editable events & parent () const

'Getter' function for member m_parent

category_t category () const

'Getter' function for member m_category

void category (category t c)

This principal assignment operator sets the class members.

· const std::string & category_string () const

'Getter' function for member m_category

void category (const std::string &cs)

'Setter' function for member m_category by value Also keeps the m_name_category member in synchrony, but looks up the name, rather than using the name parameter, to avoid storing abbreviations.

const std::string & timestamp_string () const

'Getter' function for member m_name_timestamp

· midipulse timestamp () const

'Getter' function for member event::get_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

• void timestamp (midipulse ts)

'Setter' function for member event::set_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

void timestamp (const std::string &ts_string)

'Setter' function for member event::set_timestamp() [string version]

• std::string time_as_pulses ()

Converts the current time-stamp to a string representation in units of pulses.

• std::string time_as_measures ()

Converts the current time-stamp to a string representation in units of measures, beats, and divisions.

std::string time_as_minutes ()

Converts the current time-stamp to a string representation in units of hours, minutes, seconds, and fraction.

void set_status_from_string (const std::string &ts, const std::string &s, const std::string &sd0, const std::string &sd1)

Converts a string into an event status, along with timestamp and data bytes.

• std::string format timestamp ()

Formats the current timestamp member as a string.

std::string stock_event_string ()

Converts the event into a string desribing the full event.

• std::string status_string () const

'Getter' function for member m_name_status

std::string meta_string () const

'Getter' function for member m_name_meta

std::string seqspec_string () const

'Getter' function for member m_name_seqspec

• std::string channel_string () const

'Getter' function for member m_name_channel

• std::string data_string () const

'Getter' function for member m_name_data

Static Public Member Functions

static std::string value to name (midibyte value, category t cat)

Provides a static lookup function that returns the name, if any, associated with a midibyte value.

static unsigned short name_to_value (const std::string &name, category_t cat)

Provides a static lookup function that returns the value, if any, associated with a name string.

Static Public Attributes

static const name_value_t sm_category_names []

An array of event categories and their names.

static const name_value_t sm_channel_event_names []

An array of MIDI channel events and their names.

static const name_value_t sm_system_event_names []

An array of MIDI system events and their names.

static const name_value_t sm_meta_event_names []

An array of Meta events and their names.

static const name_value_t sm_prop_event_names[]

An array of Sequencer64-specific events and their names.

• static const name_value_t *const sm_category_arrays[]

Provides for fast access (no ifs) to the correct name array for the given category.

Private Member Functions

• void analyze ()

Analyzes an editable-event to make all the settings it needs.

Private Attributes

· const editable events & m parent

Provides a reference to the container that holds this event.

· category_t m_category

Indicates the overall category of this event, which will be category_channel_message, category_system_message, category_meta_event, and category_prop_event.

std::string m_name_category

Holds the name of the event category for this event.

timestamp_format_t m_format_timestamp

Indicates the format to display the time-stamp.

std::string m_name_timestamp

Holds the string version of the MIDI pulses time-stamp.

std::string m_name_status

Holds the name of the status value for this event.

std::string m_name_meta

Holds the name of the meta message, if applicable.

std::string m_name_seqspec

If we eventually implement the editing of the Seq24/Sequencer64 "proprietary" meta sequencer-specific events, the name of the SeqSpec will be stored here.

std::string m name channel

Holds the channel description, if applicable.

• std::string m name data

Holds the data description, if applicable.

10.6.1 Detailed Description

It makes the following members of an event modifiable using human-readable strings:

```
- m_timestamp
```

- m_status
- m_channel
- m_data[]

Eventually, it would be nice to be able to edit, or at least view, the SysEx events and the Meta events. Those two will require extensions to make events out of them (SysEx is partly supported).

To the concepts of event, the editable_event class adds a category field and strings to represent all of these members.

10.6.2 Member Enumeration Documentation

10.6.2.1 enum seq64::editable_event::category_t

Enumerator

category_name These values determine the major kind of event, which determines what types of events are possible for this editable event object. These tags are accompanied by category names in sm_
category_names[]. The enum values are cast to midibyte values for the purposes of using the lookup infrastructure.

```
Indicates that the lookup needs to be done on the category names, as listed in sm_category_names[].
```

- *category_channel_message* Indicates a channel event, with a value ranging from 0x80 through 0xEF. Some examples are note on/off, control change, and program change. Values are looked up in sm_channel_← event_names[].
- category_system_message Indicates a system event, with a value ranging from 0xF0 through 0xFF. Some examples are SysEx start/end, song position, and stop/start/continue/reset. Values are looked up in sm
 _system_event_names[].
- category_meta_event Indicates a meta event, and there is a second value that is used to look up the name of the meta event, in sm meta event names[].
- category_prop_event Indicates a "proprietary", Sequencer64 event. Indicates to look up the name of the event in sm_prop_event_names[]. Not sure if these kinds of events will be stored separately.

10.6.2.2 enum seq64::editable event::timestamp format t

Enumerator

timestamp_measures Provides a code to indicate the desired timestamp format. Three are supported. All editable events will share the same timestamp format, but it seems good to make this a event class member, rather than something imposed from an outside static value. We shall see.

```
This format displays the time in "measures:beats:divisions" format, where measures and beats start at 1. Thus, "1:1:0" is equivalent to 0 pulses or to "0:0:0.0.0" in normal time values.
```

timestamp_time This format displays the time in "hh:mm:second.fraction" format. The value displayed should not depend upon the internal timing parameters of the event.

timestamp_pulses This format specifies a bare pulse format for the timestamp – a long integer ranging from 0 on up. Obviously, this representation depends on the PPQN value for the sequence holding this event.

10.6.3 Constructor & Destructor Documentation

10.6.3.1 seq64::editable_event::editable_event (const editable_events & parent)

editable_event::editable_event (): event (), m_category (category_name), m_name_category (), m_format_ \leftarrow timestamp (timestamp_measures), m_name_timestamp (), m_name_status (), m_name_meta (), m_name_ \leftarrow seqspec (), m_name_channel (), m_name_data () { // Empty body } Principal constructor.

10.6.3.2 seq64::editable_event::editable_event (const editable_events & parent, const event & ev)

This function basically adds all of the extra editable_event stuff to a standard event, so that the resulting editable—event is container-ready.

10.6.3.3 seq64::editable_event::editable_event (const editable_event & rhs)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx editable_events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs	Provides the editable_event object to be copied.
-----	--

10.6.4 Member Function Documentation

10.6.4.1 std::string seq64::editable_event::value_to_name (midibyte value, editable_event::category_t cat)
[static]

Parameters

value	The MIDI byte value to look up.
cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the name associated with the value. If there is no such name, then an empty string is returned.

10.6.4.2 unsigned short seq64::editable_event::name_to_value (const std::string & name, editable_event::category_t cat
) [static]

The string_match() function, which can match abbreviations, case-insensitively, is used to make the string comparisons.

name	The string value to look up.
cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the value associated with the name. If there is no such value, then SEQ64_END_OF_MIDIBYTE_

TABLE is returned.

10.6.4.3 void seq64::editable_event::category (category_t c)

Parameters

rhs	Provides the editable_event object to be assigned.
-----	--

Returns

Returns a reference to "this" object, to support the serial assignment of editable events.

editable_event & editable_event::operator = (const editable_event & rhs) { if (this != &rhs) { event::operator = (rhs); m_category = rhs.m_category; m_parent = rhs.m_parent; m_name_category = rhs.m_name_category; m_format = timestamp = rhs.m_format_timestamp; m_name_timestamp = rhs.m_name_timestamp; m_name_status = rhs. = rhs.m_name_status; m_name_meta = rhs.m_name_meta; m_name_seqspec = rhs.m_name_seqspec; m_name_category = rhs.m_name_seqspec; m_name_seqspec; m_name_category = rhs.m_name_seqspec; m_name_seqspec; m_name_category = rhs.m_name_seqspec; m_name_seqspec; m_name_se

10.6.4.4 void seq64::editable_event::category (const std::string & name)

Note that a bad value is translated to the value of category_name.

10.6.4.5 void seq64::editable_event::timestamp (midipulse ts)

Plus, we also have to set the string version at the same time.

Parameters

ts	Provides the timestamp in units of MIDI pulses.

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

10.6.4.6 void seq64::editable_event::timestamp (const std::string & ts_string)

Parameters

ts Provides the timestamp in units of MIDI pulses.
--

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format timestamp() function.

10.6.4.7 std::string seq64::editable_event::time_as_measures ()

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

```
10.6.4.8 std::string seq64::editable_event::time_as_minutes ( )
```

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

10.6.4.9 void seq64::editable_event::set_status_from_string (const std::string & ts, const std::string & s, const std::string & sd0, const std::string & sd1)

Currently, this function handles only the following two messages:

- · category_channel_message
- · category_system_message

After all of the numbering member items have been set, they are converted and assigned to the string versions via a call to the analyze() function.

Parameters

ts	Provides the time-stamp string of the event.
S	Provides the name of the event, such as "Program Change".
sd0	Provides the string defining the first data byte of the event.
sd1	Provides the string defining the second data byte of the event, if applicable to the event.

```
10.6.4.10 std::string seq64::editable_event::format_timestamp()
```

The format of the string representation is of the format selected by the m_format_timestamp member.

```
10.6.4.11 std::string seq64::editable_event::stock_event_string ( )
```

We get the time-stamp as a string, make sure the event is fully analyzed so that all items and strings are set correctly.

```
10.6.4.12 void seq64::editable_event::analyze( ) [private]
```

Used in the constructors. Some of the setters indirectly set the appropriate string representation, as well. Category:

```
This function can figure out if the status byte implies a channel message or a system message, and set the category string as well. However, at this time, detection of Meta events (0xFF) or Proprietary/SeqSpec events (0xFF with 0x2424) aren't able to be detected due to lack of context here (and due to the fact that currently such events are not yet stored in a sequence, and the least-significant-byte gets masked off anyway.)
```

Status:

```
We distinguish between channel and system messages, and then one— and two-byte messages, but don't yet distinguish the data values fully.
```

10.6.5 Field Documentation

10.6.5.1 const editable_event::name_value_t seq64::editable_event::sm_category_names [static]

Initializes the array of event/name pairs for the MIDI events categories.

Terminated by an empty string, the latter being the preferred test, for consistency with the other arrays and because 0 is often a legitimate code value.

10.6.5.2 const editable_event::name_value_t seq64::editable_event::sm_channel_event_names [static]

Initializes the array of event/name pairs for the channel MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

10.6.5.3 const editable event::name value t seq64::editable event::sm system event names [static]

Initializes the array of event/name pairs for the system MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

10.6.5.4 const editable_event::name_value_t seq64::editable_event::sm_meta_event_names [static]

Initializes the array of event/name pairs for all of the Meta events.

Terminated only by the empty string.

10.6.5.5 const editable_event::name_value_t seq64::editable_event::sm_prop_event_names [static]

Initializes the array of event/name pairs for all of the seq24/sequencer64-specific events.

Terminated only by the empty string. Note that the numbers reflect the masking off of the high-order bits by 0x242400FF.

10.6.5.6 const editable_event::name_value_t *const seq64::editable_event::sm_category_arrays [static]

Contains pointers (references cannot be stored in an array) to the desired array for a given category.

Too bad that an array of references is not possible.

This code could be considered a bit rococo.

10.6.5.7 const editable_events& seq64::editable_event::m_parent [private]

The container's "children" need to go to their "parent" to get certain items of information.

10.6.5.8 category_t seq64::editable_event::m_category [private]

The category_name value is not set here, since that category is used only for looking up the human-readable form of the category.

10.6.5.9 timestamp_format_t seq64::editable_event::m_format_timestamp [private]

The default is to display in timestamp_measures format.

10.6.5.10 std::string seq64::editable_event::m_name_status [private]

It will include the names of the channel messages and the system messages. The latter includes SysEx and Meta messages.

10.6.5.11 std::string seq64::editable_event::m_name_meta [private]

If not applicable, this name will be empty.

10.7 seq64::editable_events Class Reference

Provides for the management of an ordered collection MIDI editable events.

Public Member Functions

editable events (sequence &seq, int bpm)

This constructor hooks into the sequence object.

editable_events (const editable_events &rhs)

This copy constructor initializes most of the class members.

editable_events & operator= (const editable_events &rhs)

This principal assignment operator sets most of the class members.

virtual ∼editable events ()

This destructor current is a rote virtual function override.

· const midi_timing & timing () const

'Getter' function for member m_midi_parameters

midipulse string_to_pulses (const std::string &ts_string) const

Calculates the MIDI pulses (divisions) from a string using one of the free functions of the calculations module.

• bool load events ()

Accesses the sequence's event-list, iterating through it from beginning to end, wrapping each event in the list in an editable event and inserting it into the editable-event container.

• bool save_events ()

Erases the sequence's event container and recreates it using the edited container of editable events.

• Events & events ()

'Getter' function for member m_events

iterator begin ()

'Getter' function for member m_events.begin(), non-constant version.

const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

• iterator end ()

'Getter' function for member m_events.end(), non-constant version.

· const_iterator end () const

'Getter' function for member m_events.end(), constant version.

int count () const

Returns the number of events stored in m_events.

bool add (const event &e)

Adds an event, converted to an editable_event, to the internal event list.

· bool add (const editable event &e)

Adds an editable event to the internal event list.

bool replace (iterator ie, const editable_event &e)

Provides a wrapper for the iterator form of erase(), which is the only one that the editable_events container uses.

• void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

• iterator current_event () const

'Getter' function for member m_current_event The caller must make sure the iterator is not Events::end().

Private Types

typedef event_list::event_key Key

Types to use to with the multimap implementation.

Private Member Functions

void current_event (iterator cei)

'Setter' function for member m_current_event

Private Attributes

• Events m_events

Holds the editable_events.

• iterator m_current_event

Points to the current event, which is the event that has just been inserted.

• sequence & m_sequence

Provides a reference to the sequence containing the events to be edited.

· midi timing m midi parameters

Holds the current settings for the sequence (and usually for the whole MIDI tune as well).

10.7.1 Member Typedef Documentation

10.7.1.1 typedef event_list::event_key seq64::editable_events::Key [private]

These typenames are identical to those used in event_list, but of course they are in the editable_events scope instead.

10.7.2 Constructor & Destructor Documentation

10.7.2.1 seq64::editable_events::editable_events (sequence & seq, int bpm)

Parameters

seq	Provides a reference to the sequence object, which provides the events and some of the
	MIDI timing parameters.
bpm	Provides the beats/minute value, which the caller figures out how to get and provides in this
	parameter.

10.7.2.2 seq64::editable_events::editable_events (const editable_events & rhs)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs	Provides the editable_events object to be copied.
-----	---

10.7.3 Member Function Documentation

10.7.3.1 editable_events & seq64::editable_events::operator= (const editable_events & rhs)

Note that we need to reconstitute the event links here, as well.

rhs Provides the editable_events object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of editable_eventss.

```
10.7.3.2 bool seq64::editable_events::load_events()
```

Note that the new events will not have valid links (actually, no links). These links are used for associating Note Off events with their respective Note On events. To be consistent, we must take the time to reconstitute these links, using event list::verify_and_link().

Returns

Returns true if the size of the final editable_event container matches the size of the original events container.

```
10.7.3.3 bool seq64::editable_events::save_events()
```

Note that the old events are replaced only if the container of editable events is not empty. There are safer ways for the user to erase all the events.

Todo Consider what to do about the sequence::m_is_modified flag.

Returns

Returns true if the size of the final event container matches the size of the original editable_events container.

```
10.7.3.4 int seq64::editable_events::count( ) const [inline]
```

We like returning an integer instead of size_t, and rename the function so nobody is fooled.

10.7.3.5 bool seq64::editable_events::add (const event & e)

Parameters

e Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

10.7.3.6 bool seq64::editable_events::add (const editable_event & e)

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

e Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

Side-effect(s) Sets m_current_event, which can be used right-away in a single-threaded context to get an iterator to the event via the current_event() accessor.

10.7.4 Field Documentation

10.7.4.1 iterator seq64::editable_events::m_current_event [private]

(From this event we can get the current time and other parameters.) If the container were a plain map, we could instead use a key to access it. But we can at least use an iterator, rather than a bare pointer.

10.7.4.2 sequence& seq64::editable_events::m_sequence [private]

Besides the events, this object also holds the beats/measure, beat-width, and the PPQN value. The beats/minute have to be obtained from the application's perform object, and passed to the editable_events constructor by the caller


10.7.4.3 midi_timing seq64::editable_events::m_midi_parameters [private]

It holds the beats/minute, beats/measure, beat-width, and PPQN values needed to properly convert MIDI pulse timestamps to time and measure values.

10.8 seq64::event Class Reference

Provides events for management of MIDI events.

Inheritance diagram for seq64::event:



Public Member Functions

• event ()

This constructor simply initializes all of the class members.

• event (const event &rhs)

This copy constructor initializes most of the class members.

event & operator= (const event &rhs)

This principal assignment operator sets most of the class members.

virtual ∼event ()

This destructor explicitly deletes m sysex and sets it to null.

bool operator< (const event &rhsevent) const

If the current timestamp equal the event's timestamp, then this function returns true if the current rank is less than the event's rank.

void set_timestamp (midipulse time)

'Setter' function for member m_timestamp

• midipulse get_timestamp () const

'Getter' function for member m_timestamp

• midibyte get_channel () const

'Getter' function for member m channel

bool check_channel (int channel) const

Checks the channel number to see if the event's channel matches it, or if the event has no channel.

void mod_timestamp (midipulse a_mod)

Calculates the value of the current timestamp modulo the given parameter.

void set_status (midibyte status)

Sets the m_status member to the value of status.

void set_status (midibyte eventcode, midibyte channel)

This overload is useful when synthesizing events, such as converting a Note On event with a velocity of zero to a Note Off event.

void set channel (midibyte channel)

Sets the channel "nybble", without modifying the status "nybble".

• midibyte get status () const

'Getter' function for member m_status

void set_data (midibyte d1)

Clears the most-significant-bit of the d1 parameter, and sets it into the first byte of m_data.

• void set_data (midibyte d1, midibyte d2)

Clears the most-significant-bit of both parameters, and sets them into the first and second bytes of m_data.

void get_data (midibyte &d0, midibyte &d1) const

Retrieves the two data bytes from m_data[] and copies each into its respective parameter.

void increment_data1 ()

Increments the first data byte (m_data[1]) and clears the most significant bit.

void decrement_data1 ()

Decrements the first data byte $(m_data[1])$ and clears the most significant bit.

void increment_data2 ()

Increments the second data byte (m_data[1]) and clears the most significant bit.

void decrement_data2 ()

Decrements the second data byte (m_data[1]) and clears the most significant bit.

void restart_sysex ()

Deletes and clears out the SYSEX buffer.

bool append_sysex (midibyte *data, int len)

Appends SYSEX data to a new buffer.

• midibyte * get_sysex () const

'Getter' function for member m_sysex

void set_sysex_size (int len)

'Setter' function for member m_sysex_size

· int get sysex size () const

'Getter' function for member m_sysex_size

void link (event *a event)

Sets m_has_link and sets m_link to the provided event pointer.

event * get_linked () const

'Getter' function for member m linked

• bool is_linked () const

'Getter' function for member m_has_link

· void clear_link ()

'Setter' function for member m_has_link

• void paint ()

'Setter' function for member m_painted

· void unpaint ()

'Setter' function for member m_painted

• bool is_painted () const

'Getter' function for member m_painted

• void mark ()

'Setter' function for member m_marked

· void unmark ()

'Setter' function for member m_marked

bool is_marked () const

'Getter' function for member m_marked

· void select ()

'Setter' function for member m selected

· void unselect ()

'Setter' function for member m_selected

• bool is_selected () const

'Getter' function for member m_selected

void make_clock ()

Sets m_status to EVENT_MIDI_CLOCK;.

· midibyte data (int index) const

'Getter' function for member m_data[]

• midibyte get_note () const

Assuming m_data[] holds a note, get the note number, which is in the first data byte, m_data[0].

void set_note (midibyte note)

Sets the note number, clearing off the most-significant-bit and assigning it to the first data byte, m_data[0].

• midibyte get_note_velocity () const

'Getter' function for member m_data[1], the note velocity.

void set_note_velocity (int a_vel)

Sets the note velocity, with is held in the second data byte, m_data[1].

• bool is_note_on () const

Returns true if m_status is $EVENT_NOTE_ON$.

bool is_note_off () const

Returns true if m_status is EVENT_NOTE_OFF.

void print ()

Prints out the timestamp, data size, the current status byte, any SYSEX data if present, or the two data bytes for the status byte.

• int get_rank () const

This function is used in sorting MIDI status events (e.g.

Static Public Member Functions

• static bool is_channel_msg (midibyte m)

Static test for channel messages/statuses.

static bool is_one_byte_msg (midibyte m)

Static test for channel messages that have only one data byte.

static bool is_two_byte_msg (midibyte m)

Static test for channel messages that have two data bytes.

static bool is_note_msg (midibyte m)

Static test for messages that involve notes and velocity.

static bool is desired cc or not cc (midibyte m, midibyte cc, midibyte datum)

Static test for channel messages that are either not control-change messages, or are and match the given controller value.

Private Attributes

• midipulse m_timestamp

Provides the MIDI timestamp in ticks, otherwise known as the "pulses" in "pulses per quarter note" (PPQN).

• midibyte m_status

This is the status byte without the channel.

· midibyte m channel

In order to be able to handle MIDI channel-splitting of an SMF 0 file, we need to store the channel, even if we override it when playing the MIDI data.

midibyte m_data [SEQ64_MIDI_DATA_BYTE_COUNT]

The two bytes of data for the MIDI event.

midibyte * m_sysex

Points to the data buffer for SYSEX messages.

• int m_sysex_size

Gives the size of the SYSEX message.

• event * m_linked

This event is used to link Note Ons and Offs together.

bool m_has_link

Indicates that a link has been made.

• bool m_selected

Answers the question "is this event selected in editing.".

· bool m marked

Answers the question "is this event marked in processing.".

bool m_painted

Answers the question "is this event being painted.".

10.8.1 Detailed Description

A MIDI event consists of 3 bytes:

```
-# Status byte, 1sssnnn, where the sss bits specify the type of
message, and the nnnn bits denote the channel number.
The status byte always starts with 0.
```

```
-# The first data byte, 0xxxxxxx, where the data byte always
start with 0, and the xxxxxxx values range from 0 to 127.
```

-# The second data byte, 0xxxxxxx.

This class may have too many member functions.

10.8.2 Constructor & Destructor Documentation

```
10.8.2.1 seq64::event::event ( const event & rhs )
```

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Note that now events are also copied when creating the editable_events container, so this function is even more important. The event links, for linking Note Off events to their respective Note On events, are dropped. Generally, they will need to be reconstituted by calling the event_list::verify_and_link() function.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links, as noted above.

Parameters

rhs	Provides the event object to be copied.
	, '

```
10.8.2.2 seq64::event::~event() [virtual]
```

The restart_sysex() function does what we need.

10.8.3 Member Function Documentation

```
10.8.3.1 event & seq64::event::operator= ( const event & rhs )
```

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the member are not set to useful value when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs	Provides the event object to be assigned.
1115	1 Tovides the event object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of events.

```
10.8.3.2 bool seq64::event::operator< ( const event & rhs ) const
```

Otherwise, it returns true if the current timestamp is less than the event's timestamp.

Warning

The less-than operator is supposed to support a "strict weak ordering", and is supposed to leave equivalent values in the same order they were before the sort. However, every time we load and save our sample MIDI file, events get reversed. Here are program-changes that get reversed:

```
Save N: 0070: 6E 00 C4 48 00 C4 0C 00 C4 57 00 C4 19 00 C4 26 Save N+1: 0070: 6E 00 C4 26 00 C4 19 00 C4 57 00 C4 0C 00 C4 48
```

The 0070 is the offset within the versions of the b4uacuse-seq24.midi file.

Because of this mis-feature, and the very slow speed of loading a MIDI file when Sequencer64 is built for debugging, we are exploring using an std::mulitmap instead of an std::list. Search for occurrences of the SEQ64_USE_EVENT_MAP macro. (This actually works better than a list, for loading MIDI event, we have found, but may cause the upper limit of the number of playing sequences to drop a little, due to the overhead of incrementing multimap iterators versus list iterators).

Parameters

rhs	The object to be compared against.

Returns

Returns true if the time-stamp and "rank" are less than those of the comparison object.

10.8.3.3 bool seq64::event::check_channel (int channel) const [inline]

Used in the SMF 0 track-splitting code.

10.8.3.4 static bool seq64::event::is_channel_msg (midibyte m) [inline], [static]

This function requires that the channel data have already been masked off.

Parameters

m	The channel status or message byte to be tested.
---	--

Returns

Returns true if the byte represents a MIDI channel message.

10.8.3.5 static bool seq64::event::is_one_byte_msg (midibyte m) [inline], [static]

The rest have two.

Parameters

|--|

Returns

Returns true if the byte represents a MIDI channel message that has only one data byte. However, if this function returns false, it might not be a channel message at all, so be careful.

10.8.3.6 static bool seq64::event::is_two_byte_msg (midibyte m) [inline], [static]

Parameters

m	The channel status or message byte to be tested.

Returns

Returns true if the byte represents a MIDI channel message that has two data bytes. However, if this function returns false, it might not be a channel message at all, so be careful.

10.8.3.7 static bool seq64::event::is_note_msg(midibyte m) [inline], [static]

m The channel status or message byte to be tested.

Returns

Returns true if the byte represents a MIDI note message.

10.8.3.8 static bool seq64::event::is_desired_cc_or_not_cc (midibyte *m*, midibyte *cc*, midibyte *datum*) [inline], [static]

Note

The old logic was the first line, but can be simplified to the second line; the third line shows the abstract representation. Also made sure of this using a couple truth tables.

```
(m != EVENT_CONTROL_CHANGE) || (m == EVENT_CONTROL_CHANGE && d == cc)
    (m != EVENT_CONTROL_CHANGE) || (d == cc)
    a || (! a && b) => a || b

\param m
    The channel status or message byte to be tested.

\param cc
    The desired cc value, which the datum must match, if the message is a control-change message.

\param datum
    The current datum, to be compared to cc, if the message is a control-change message.

\return
    Returns true if the message is not a control-change, or if it is and the cc and datum parameters match.
```

10.8.3.9 void seq64::event::mod_timestamp (midipulse a_mod) [inline]

Parameters

a_mod | The value to mod the timestamp against.

Returns

Returns a value ranging from 0 to a mod-1.

10.8.3.10 void seg64::event::set_status (midibyte status)

If a_status is a channel event, then the channel portion of the status is cleared using a bitwise AND against $EVE \leftarrow NT_CLEAR_CHAN_MASK$.

Found in yet another fork of seq24:

```
// ORL fait de la merde
```

He also provided a very similar routine: set_status_midibus().

status	The status byte, perhaps read from a MIDI file or edited in the sequencer's event editor.
	Sometime, this byte will have the channel nybble masked off. If that is the case, the event-
	code/channel overload of this function is more appropriate.

10.8.3.11 void seq64::event::set_status (midibyte eventcode, midibyte channel)

Parameters

eventcode	The status byte, perhaps read from a MIDI file. This byte is assumed to have already had its
	low nybble cleared by masking against EVENT_CLEAR_CHAN_MASK.
channel	The channel byte. Combined with the event-code, this makes a valid MIDI "status" byte. This
	byte is assume to have already had its high nybble cleared by masking against EVENT_G
	ET_CHAN_MASK.

10.8.3.12 void seq64::event::set_channel (midibyte channel) [inline]

Note that the sequence channel generally overrides this value.

Parameters

channel	The channel byte.
---------	-------------------

10.8.3.13 void seq64::event::set_data (midibyte d1) [inline]

Parameters

d1	The byte value to set. We should make these all "midibytes".

10.8.3.14 void seq64::event::set_data (midibyte d1, midibyte d2) [inline]

Parameters

d1	The first byte value to set. We should make these all "midibytes".
d2	The second byte value to set. We should make these all "midibytes".

10.8.3.15 void seq64::event::get_data (midibyte & d0, midibyte & d1) const [inline]

Parameters

d0	[out] The return reference for the first byte.
d1	[out] The return reference for the first byte.

10.8.3.16 bool seq64::event::append_sysex (midibyte * data, int dsize)

First, a buffer of size m_sysex_size+dsize is created. The existing SYSEX data (stored in m_sysex) is copied to this buffer. Then the data represented by data and dsize is appended to that data buffer. Then the original SYSEX buffer, m_sysex, is deleted, and m_sysex is assigned to the new buffer.

data	Provides the additional SYSEX data. If not provided, nothing is done, and false is returned.
dsize	Provides the size of the additional SYSEX data. If not provided, nothing is done.

Returns

Returns false if there was an EVENT_SYSEX_END byte in the appended data, or if an error occurred, and the caller needs to stop trying to process the data.

10.8.3.17 int seq64::event::get_rank() const

The ranking, from high to low, is note off, note on, aftertouch, channel pressure, and pitch wheel, control change, and program changes.

note on/off, aftertouch, control change, etc.) The sort order is not determined by the actual status values.

The lower the ranking the more upfront an item comes in the sort order.

Returns

Returns the rank of the current m_status byte.

10.8.4 Field Documentation

```
10.8.4.1 midibyte seq64::event::m_status [private]
```

The channel will be appended on the MIDI bus. The high nibble = type of event; The low nibble = channel. Bit 7 is present in all status bytes.

```
10.8.4.2 midibyte seq64::event::m_channel [private]
```

This member adds another 4 bytes to the event object, most likely.

```
10.8.4.3 midibyte seq64::event::m_data[SEQ64_MIDI_DATA_BYTE_COUNT] [private]
```

Remember that the most-significant bit of a data byte is always 0.

```
10.8.4.4 midibyte* seq64::event::m_sysex [private]
```

This really ought to be a Boost or STD scoped pointer. Currently, it doesn't seem to be used.

```
10.8.4.5 bool seq64::event::m_has_link [private]
```

This item is used [via the get_link() and link() accessors] in the sequence class.

10.9 seq64::event_list::event_key Class Reference

Provides a key value for an event map.

Public Member Functions

event_key (midipulse tstamp, int rank)

Principal event_key constructor.

event_key (const event &e)

Event-based constructor.

• bool operator< (const event key &rhs) const

Provides the minimal operator needed to sort events using an event_key.

Private Attributes

• midipulse m_timestamp

The primary key-value for the key.

int m_rank

The sub-key-value for the key.

10.9.1 Detailed Description

Its types match the m_timestamp and get_rank() function of this event class.

10.9.2 Constructor & Destructor Documentation

10.9.2.1 seq64::event_list::event_key::event_key (midipulse tstamp, int rank)

Parameters

tstamp	The time-stamp is the primary part of the key. It is the most important key item.
rank	Rank is an arbitrary number used to prioritize events that have the same time-stamp. See the
	event::get_rank() function for more information.

10.9.2.2 seq64::event_list::event_key::event_key (const event & rhs)

This constructor makes it even easier to create an event_key. Note that the call to event::get_rank() makes a simple calculation based on the status of the event.

Parameters

rhs	Provides the event key to be copied.

10.9.3 Member Function Documentation

10.9.3.1 bool seq64::event_list::event_key::operator< (const event_key & rhs) const

Parameters

е	Provides the event key to be compared against.

10.9.4 Field Documentation

10.9.4.1 midipulse seq64::event_list::event_key::m_timestamp [private]

10.9.4.2 int seq64::event_list::event_key::m_rank [private]

10.10 seg64::event_list Class Reference

The event list class is a receptable for MIDI events.

Data Structures

· class event key

Provides a key value for an event map.

Public Member Functions

event_list ()

Principal constructor.

event_list (const event_list &a_rhs)

Copy constructor.

event_list & operator= (const event_list &a_rhs)

Principal assignment operator.

∼event_list ()

A rote destructor.

• iterator begin ()

'Getter' function for member m_events.begin(), non-constant version.

• const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

• iterator end ()

'Getter' function for member m_events.end(), non-constant version.

• const_iterator end () const

'Getter' function for member m_events.end(), constant version.

• int count () const

Returns the number of events stored in m_events.

• bool empty () const

Returns true if there are no events.

• bool add (const event &e, bool postsort=true)

Adds an event to the internal event list in an optionally sorted manner.

• bool is_modified () const

'Getter' function for member m_is_modified

void unmodify ()

 ${\it 'Setter' function for member $m_{is_modified This function may be needed by some of the sequence editors.}$

• void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

• void merge (event_list &el, bool presort=true)

Provides a merge operation for the event multimap analogous to the merge operation for the event list.

• void sort ()

Wrapper for std::list::sort(), or, since multimaps are always sorted, an empty function.

Static Public Member Functions

· static event & dref (iterator ie)

Dereference access for list or map.

static const event & dref (const iterator ie)

Dereference const access for list or map.

Private Types

typedef std::multimap< event_key, event > Events

Types to use to swap between list and multimap implementations.

Private Member Functions

• void link new ()

Links a new event.

· void clear_links ()

Clears all event links and unmarks them all.

• void verify_and_link (midipulse slength)

This function verifies state: all note-ons have an off, and it links note-offs with their note-ons.

· void mark selected ()

Marks all selected events.

void mark_out_of_range (midipulse slength)

Marks all events that have a time-stamp that is out of range.

void mark_all ()

Marks all events.

• void unmark all ()

Unmarks all events.

void unpaint_all ()

Unpaints all list-events.

int count_selected_notes () const

Counts the selected note-on events in the event list.

• bool any_selected_notes () const

Indicates that at least one note is selected.

• int count_selected_events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

void select_all ()

Selects all events, unconditionally.

• void unselect all ()

Deselects all events, unconditionally.

void print ()

Prints a list of the currently-held events.

· const Events & events () const

'Getter' function for member m_events

Private Attributes

· Events m_events

This list holds the current pattern/sequence events.

· bool m_is_modified

A new flag to indicate if an event was added or removed.

10.10.1 Detailed Description

Two implementations, an std::multimap, and the original, an std::list, are provided for comparison, and are selected at build time, by manually defining the SEQ64_USE_EVENT_MAP macro near the top of this module.

10.10.2 Constructor & Destructor Documentation

10.10.2.1 seq64::event_list::event_list (const event_list & rhs)

Parameters

rhs

10.10.3 Member Function Documentation

10.10.3.1 event_list & seq64::event_list::operator= (const event_list & rhs)

Follows the stock rules for such an operator, just assigning member values.

Parameters

rhs	Provides the event list to be assigned.

```
10.10.3.2 int seq64::event_list::count() const [inline]
```

We like returning an integer instead of size t, and rename the function so nobody is fooled.

```
10.10.3.3 bool seq64::event_list::add ( const event & e, bool postsort = true )
```

It is a wrapper, wrapper for insert() or push_front(), with an option to call sort().

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. That's why we're exploring using a multimap as the container.

Parameters

е	Provides the event to be added to the list.
postsort	If true, and the std::list implementation has been built in, then the event list is sorted after the
	addition. This is a time-consuming operation.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

10.10.3.4 void seq64::event_list::unmodify() [inline]

But use it with great caution.

```
10.10.3.5 void seq64::event_list::remove(iterator ie) [inline]
```

Currently, no check on removal is performed. Set the modified-flag.

```
10.10.3.6 void seq64::event_list::clear( ) [inline]
```

Set the modified-flag.

```
10.10.3.7 void seq64::event_list::merge ( event_list & el, bool presort = true )
```

We have certain constraints to preserve, as the following discussion shows.

For std::list, sequence merges list T into list A by first calling T.sort(), and then A.merge(T). The merge() operation merges T into A by transferring all of its elements, at their respective ordered positions, into A. Both containers must already be ordered.

The merge effectively removes all the elements in T (which becomes empty), and inserts them into their ordered position within container (which expands in size by the number of elements transferred). The operation is performed without constructing nor destroying any element, whether T is an Ivalue or an rvalue, or whether the value-type supports move-construction or not.

Each element of T is inserted at the position that corresponds to its value according to the strict weak ordering defined by operator <. The resulting order of equivalent elements is stable (i.e. equivalent elements preserve the relative order they had before the call, and existing elements precede those equivalent inserted from x). The function does nothing if (8x == this).

For std::multimap, sorting is automatic. However, unless move-construction is supported, merging will be less efficient than for the list version. Also, we need a way to include duplicates of each event, so we need to use a multimap. Once all this setup, merging is really just insertion. And, since sorting isn't needed, the multimap actually turns out to be faster.

Parameters

el	Provides the event list to be merged into the current event list.
presort	If true, the events are presorted. This is a requirement for merging an std::list, but is a no-op
	for the std::multimap implementation.

```
10.10.3.8 void seq64::event_list::link_new( ) [private]
```

This function checks for a note on, then look for its note off. This function is provided in the event_list because it does not depend on any external data. Also note that any desired thread-safety must be provided by the caller.

```
10.10.3.9 void seq64::event_list::verify_and_link( midipulse slength ) [private]
```

Threadsafe

Parameters

slength	Provides the length beyond which events will be pruned.

```
10.10.3.10 void seq64::event_list::mark_out_of_range ( midipulse slength ) [private]
```

Used for killing (pruning) those events not in range. If the current time-stamp is greater than the length, then the event is marked for pruning.

Note

This code was comparing the timestamp as greater than or equal to the sequence length. However, being equal is fine. This may explain why the midifile code would add one tick to the length of the last note when processing the end-of-track.

Parameters

sleng	gth	Provides the length beyond which events will be pruned.

```
10.10.3.11 void seq64::event_list::mark_all( ) [private]
```

Not yet used, but might come in handy with the event editor dialog.

```
10.10.3.12 bool seq64::event_list::any_selected_notes( ) const [private]
```

Acts like event_list::count_selected_notes(), but stops after finding a selected note. We could add a flag to count
__selected_notes() to break, I suppose.

```
10.10.3.13 int seq64::event_list::count_selected_events ( midibyte status, midibyte cc ) const [private]
```

If the event is a control change (CC), then it must also match the given CC value.

10.10.4 Field Documentation


```
10.10.4.1 bool seq64::event_list::m_is_modified [private]
```

We may need to give client code a way to reload the sequence. This is currently an issue when a seqroll and an eventedit/eventslots are active for the same sequence.

10.11 seg64::eventedit Class Reference

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.

Inheritance diagram for seq64::eventedit:



Public Member Functions

- eventedit (perform &p, sequence &seq)
 - Principal constructor, has a reference to a perform object.
- ∼eventedit ()

This rote constructor does nothing.

• void enqueue_draw ()

Helper wrapper for calling perfroll::queue_draw() for one or both eventedits.

void set_seq_title (const std::string &title)

Sets m label seg name to the title.

void set_seq_time_sig (const std::string &sig)

Sets m_label_time_sig to the time-signature string.

void set seg ppqn (const std::string &p)

Sets m_label_ppqn to the parts-per-quarter-note string.

void set_seq_count ()

Sets m_label_ev_count to the number-of-events string.

void set_event_category (const std::string &c)

Sets m_label_category to the category string.

void set_event_timestamp (const std::string &ts)

Sets m_entry_ev_timestamp to the time-stamp string.

void set_event_name (const std::string &n)

Sets m_entry_ev_name to the name-of-event string.

• void set_event_data_0 (const std::string &d)

Sets m_entry_ev_data_0 to the first data byte string.

void set_event_data_1 (const std::string &d)

Sets m_entry_data_1 to the second data byte string.

· void perf_modify ()

Provides a way to mark the perform object as modified, when the modified sequence is saved.

void set dirty (bool flag=true)

Sets the "modified" status of the user-interface.

void v_adjustment (int value)

Sets the parameters for the vertical scroll-bar, using only the value parameter.

void v_adjustment (int value, int lower, int upper)

Sets the parameters for the vertical scroll-bar that is associated with the eventslots event-list user-interface.

Private Member Functions

• bool timeout ()

Handles a drawing timeout.

• void handle_delete ()

Initiates the deletion of the current editable event.

void handle_insert ()

Initiates the insertion of a new editable event.

void handle_modify ()

Passes the edited fields to the current editable event in the eventslot.

void handle_save ()

Handles saving the edited data back to the original sequence.

• void handle_cancel ()

Cancels the edits and closes the dialog box.

· void on realize ()

This callback function calls the base-class on_realize() function, and then connects the eventedit::timeout() function to the Glib signal-timeout, with a redraw timeout of m_redraw_ms.

• bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on_delete_event (GdkEventAny *event)

Handles an on-delete event.

Private Attributes

• Gtk::Table * m table

A whole horde of GUI elements.

• Gtk::Label * m label index

Items to size the m indexslots member.

Gtk::Label * m_label_seq_name

Items for the inside of the m_showbox member.

• Gtk::Label * m_label_category

Items for the inside of the m_editbox member.

• Gtk::Label * m label right

Padding for the right side of the user-interface.

· sequence & m seq

A reference to the sequence being edited, to control its editing flag.

int m_redraw_ms

Provides the timer period for the eventedit timer, used to determine the rate of redrawing.

Additional Inherited Members

10.11.1 Constructor & Destructor Documentation

10.11.1.1 seq64::eventedit::eventedit (perform & p, sequence & seq)

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner. Adjustment parameters:

```
value initial value lower minimum value upper maximum value step_increment step increment page_increment page_size page size
```

Table constructor parameters:

rows columns homogenous

Table attach() parameters:


```
child widget to add.

left_attach column number to attach left side of a child widget right_attach column number to attach right side of a child widget top_attach row number to attach the top of a child widget bottom_attach row number to attach the bottom of a child widget xoptions properties of the child widget when table resized yoptions same as xoptions, except vertical.

xpadding padding on L and R of widget added to table ypadding amount of padding above and below the child widget
```

Layout:

We're going to change the layout.



р	Refers to the main performance object.
seq	Refers to the sequence holding the event data to be edited.

10.11.1.2 seq64::eventedit::~eventedit()

We're going to have to run the application through valgrind to make sure that nothing is left behind.

10.11.2 Member Function Documentation

10.11.2.1 void seq64::eventedit::enqueue_draw ()

Parameters

forward	If true (the default), pass the call to the peer. When passing this call to the peer, this parameter
	is set to false to prevent an infinite loop and the resultant stack overflow.

10.11.2.2 void seq64::eventedit::set_seq_title (const std::string & title)

Parameters

title	The name of the sequence.

10.11.2.3 void seq64::eventedit::set_seq_time_sig (const std::string & sig)

Parameters

sia	The time signature of the sequence.
oig	The time signature of the sequence.

10.11.2.4 void seq64::eventedit::set_seq_ppqn (const std::string & p)

Parameters		
p The parts-per-quarter-note string for the sequence.		
10.11.2.5 void seq64::eventedit::set_seq_count()		
Parameters		
c The number-of-events string for the sequence.		
10.11.2.6 void seq64::eventedit::set_event_category (const std::string & c)		
Parameters		
c The category string for the current event.		
10.11.2.7 void seq64::eventedit::set_event_timestamp (const std::string & ts)		
Parameters		
ts The time-stamp string for the current event.		
10.11.2.8 void seq64::eventedit::set_event_name (const std::string & n) Parameters		
n The name-of-event string for the current event.		
10.11.2.9 void seq64::eventedit::set_event_data_0 (const std::string & d) Parameters		
d The first data byte string for the current event.		
10.11.2.10 void seq64::eventedit::set_event_data_1 (const std::string & d) Parameters		
d The second data byte string for the current event.		
10.11.2.11 void seq64::eventedit::set_dirty (bool flag = true)		
This includes changing a label and enabling/disabling the Save button.		
Parameters Compared to the production of the		
flag If true, the modified status is indicated, otherwise it is cleared.		

10.11.2.12 void seq64::eventedit::v_adjustment (int value)

This function overload provides a common use case.

Parameters

value	The new current value to be indicated by the scroll-bar.
-------	--

10.11.2.13 void seq64::eventedit::v_adjustment (int value, int lower, int upper)

It keeps the frame scroll-bar in sync with the frame movement actions. Some of the parameters are obtained from the eventslots object:

```
Page size comes from eventslots::line_maximum().Page increment is a little less than the page-size value.
```

Parameters

value	The current value to be indicated by the scroll-bar. It will lie between the lower and upper parameter.
lower	The lowest value to be indicated by the scroll-bar.
upper	The highest value to be indicated by the scroll-bar.

```
10.11.2.14 bool seq64::eventedit::timeout( ) [private]
```

It redraws events in the the eventslots objects. This function is called frequently and continuously.

```
10.11.2.15 void seq64::eventedit::handle_insert( ) [private]
```

The event's location will be determined by the timestamp and existing events. Note that we have to recalibrate the scroll-bar when we insert/delete events by calling v_adjustment().

```
10.11.2.16 void seq64::eventedit::handle_modify( ) [private]
```

Note that there are two cases to worry about. If the timestamp has not changed, then we can simply modify the existing current event in place. Otherwise, we need to delete the old event and insert the new one. But that is done for us by eventslots::modify_current_event().

```
10.11.2.17 void seq64::eventedit::handle_save( ) [private]
```

The event list in the original sequence is cleared, and the editable events are converted to plain events, and added to the container, one by one.

Todo Could also support writing the events to a new sequence, for added flexibility.

```
10.11.2.18 bool seq64::eventedit::on_key_press_event( GdkEventKey * ev ) [private]
```

If the Up or Down arrow is pressed (later, k and j :-), then we tell the eventslots object to move the "current event" highlighting up or down. In Gtkmm, these arrows also cause movement from one edit field to the next, so we disable that process if the event was handled here.

Note that some vi-like keys were supported, but they are needed for the edit fields, so cannot be used here. Also, the Delete key is needed for the edit fields. For now, we replace it with the asterisk, which is easy to access from the numeric pad of a keyboard, and allows for rapid deletion. The Insert key also causes confusing effects in the edit fields, so we replace it by the slash. Note that the asterisk and slash should not be required in any of the edit fields.

HOWEVER, there are still some issues with "/", so you'll just have to click the button to insert an event.

10.11.2.19 bool seq64::eventedit::on_delete_event (GdkEventAny * event) [private]

It sets the sequence object's editing flag to false, and deletes "this". This function is called if the "Close" ("X") button in the window's title bar is clicked. That is a different action from clicking the Close button.

Returns

Always returns false.

10.11.3 Field Documentation


10.11.3.1 int seq64::eventedit::m_redraw_ms [private]

This is hardwired to 40 ms in Linux, and 20 ms in Windows.

10.12 seq64::eventslots Class Reference

This class implements the left-side keyboard in the patterns window.

Inheritance diagram for seq64::eventslots:



Public Member Functions

- eventslots (perform &p, eventedit &parent, sequence &seq, Gtk::Adjustment &vadjust)

 Principal constructor for this user-interface object.
- int event_count () const

'Getter' function for member m_event_count Returns the number of total events in the sequence represented by the eventslots object.

• int line_count () const

'Getter' function for member m_line_count Returns the current number of rows (events) in the eventslots's display.

• int line maximum () const

'Getter' function for member m_line_maximum Returns the maximum number of rows (events) in the eventslots's display.

· int line_increment () const

Provides the "page increment" or "line increment" of the frame, This value is the current line-maximum of the frame minus its overlap value.

• int top_index () const

'Getter' function for member m_top_index

int current_index () const

'Getter' function for member m_current_index

int pager_index () const

'Getter' function for member m_pager_index

Private Member Functions

• bool load events ()

Grabs the event list from the sequence and uses it to fill the editable-event list.

• void set_current_event (const editable_events::iterator ei, int index, bool full_redraw=true)

Set the current event, which is the event that is highlighted.

· bool insert event (const editable event &edev)

Inserts an event.

 bool insert_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Inserts an event based on the setting provided, which the eventedit object gets from its Entry fields.

• bool delete_current_event ()

Deletes the current event, and makes adjustments due to that deletion.

bool modify_current_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Modifies the data in the currently-selected event.

• bool save events ()

Writes the events back to the sequence.

void select_event (int event_index=SEQ64_NULL_EVENT_INDEX, bool full_redraw=true)

Selects and highlights the event that is located in the frame at the given event index.

 void set_text (const std::string &evcategory, const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Sets the text in the parent dialog, eventedit.

• void enqueue draw ()

Wraps queue_draw().

• int convert_y (int y)

Converts a y-value into an event index relative to 0 (the top of the eventslots window/pixmap) and returns it.

• void draw_event (editable_events::iterator ei, int index)

Draw the given slot/event.

· void draw events ()

Draws all of the events in the current eventslots frame.

void change_vert ()

Change the vertical offset of events.

void page_movement (int new_value)

Adjusts the vertical position of the frame according to the given new scrollbar/vadjust value.

void page_topper (editable_events::iterator newcurrent)

Adjusts the vertical position of the frame according to the given new bottom iterator.

• int decrement_top ()

Decrements the top iterator, if possible.

int increment_top ()

Increments the top iterator, if possible.

• int decrement current ()

Decrements the current iterator, if possible.

• int increment current ()

Increments the current iterator, if possible.

• int decrement_bottom ()

Decrements the bottom iterator, if possible.

int increment_bottom ()

Increments the bottom iterator, if possible.

void update pixmap ()

This function does nothing.

· void draw area ()

This function does nothing.

• void redraw ()

Redraw the given sequence.

• void on_realize ()

Handles the callback when the window is realized.

bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

• bool on_button_press_event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button.

• bool on_button_release_event (GdkEventButton *ev)

Handles a button-release for the right button, bringing up a popup menu.

bool on_focus_in_event (GdkEventFocus *ev)

This callback is an attempt to get keyboard focus into the eventslots pixmap area.

bool on_focus_out_event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

• bool on_scroll_event (GdkEventScroll *ev)

Handle the scrolling of the window.

void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

void on_move_up ()

Move to the previous event.

void on_move_down ()

Move to the next event.

void on_frame_up ()

Move to the previous frame.

• void on_frame_down ()

Move to the next frame.

• void on_frame_home ()

Move to the first frame.

• void on_frame_end ()

Move to the last frame.

Private Attributes

· eventedit & m parent

Provides a link to the eventedit that created this object.

• sequence & m_seq

Provides a reference to the sequence that this dialog is meant to view or modify.

· editable_events m_event_container

Holds the editable events for this sequence.

· int m_slots_chars

Provides the number of the characters in the name box.

· int m char w

Provides the "real" width of a character.

· int m setbox w

Provides the width of the "set number" box.

int m_slots_box_w

Provides the width of the "slot" box.

• int m_slots_x

Provides the width of the names box, which is the width of a character for 24 characters.

· int m slots y

Provides the height of the names box, which is hardwired to 24 pixels.

· int m xy offset

Provides the horizontal and vertical offsets of the text relative to the names box.

int m_event_count

The current number of events in the edited container.

int m_line_count

Counts the number of displayed events, which depends on how many events there are (m_event_count) and the size of the event list (m_line_maximum).

· int m line maximum

Counts the maximum number of displayed events, which depends on the size of the event list (and thus the size of the dialog box for the event editor).

· int m line overlap

Provides a little overlap for paging through the frame.

• int m_top_index

The index of the event that is 0th in the visible list of events.

• int m current index

Indicates the index of the current event within the frame.

• editable_events::iterator m_top_iterator

Provides the top "pointer" to the start of the editable-events section that is being shown in the user-interface.

• editable events::iterator m bottom iterator

Provides the bottom "pointer" to the end of the editable-events section that is being shown in the user-interface.

• editable events::iterator m current iterator

Provides the "pointer" to the event currently in focus.

• int m_pager_index

Indicates the event index that matches the index value of the vertical pager.

Additional Inherited Members

10.12.1 Member Function Documentation

10.12.1.1 bool seq64::eventslots::load_events() [private]

Determines how many events can be shown in the GUI [later] and adjusts the top and bottom editable-event iterators to show the first page of events.

Returns

Returns true if the event iterators were able to be set up as valid.

10.12.1.2 void seq64::eventslots::set_current_event (const editable_events::iterator *ei*, int *index*, bool *full_redraw =* true)

[private]

Note in the snprintf() calls that the first digit is part of the data byte, so that translation is easier.

Parameters

ei	The iterator that points to the event.
index	The index (re 0) of the event, starting at the top line of the frame. It is a frame index, not a
	container index.
full_redraw	If true (the default) does a full redraw of the frame. Otherwise, only the current event is drawn.
	Generally, the only time a single event (actually, two adjacent events) is convenient to draw is
	when using the arrow keys, where the speed of keystroke auto-repeats makes the full-frame
	update scrolling very flickery and disconcerting.

10.12.1.3 bool seq64::eventslots::insert_event (const editable_event & edev) [private]

What actually happens here depends if the new event is before the frame, within the frame, or after the frame, based on the timestamp.

If before the frame: To keep the previous events visible, we do not need to increment the iterators (insertion does not affect multimap iterators), but we do need to increment their indices. The contents shown in the frame should not change.

If at the frame top: The new timestamp equals the top timestamp. We don't know exactly where the new event goes in the multimap, but we do have an new event.

If at the frame bottom: TODO

If after the frame: No action needed if the bottom event is actually at the bottom of the frame. But if the frame is not yet filled, we need to increment the bottom iterator, and its index.

Note

Actually, it is far easier to just adjust all the counts and iterators and redraw the screen, as done by the page_topper() function.

Parameters

ev	The event to insert, prebuilt.

Returns

Returns true if the event was inserted.

10.12.1.4 bool seq64::eventslots::insert_event (const std::string & evtimestamp, const std::string & evname, const std::string & evdata0, const std::string & evdata1) [private]

It calls the other insert_event() overload.

Note that we need to qualify the temporary event class object we create below, with the seq64 namespace, otherwise the compiler thinks we're trying to access some Gtkmm thing.

Parameters

evtimestamp	The time-stamp of the new event, as obtained from the event-edit timestamp field.
evname	The type name (status name) of the new event, as obtained from the event-edit event-name
	field.
evdata0	The first data byte of the new event, as obtained from the event-edit data 1 field.
evdata1	The second data byte of the new event, as obtained from the event-edit data 2 field. Used
	only for two-parameter events.

Returns

Returns true if the event was inserted.

10.12.1.5 bool seq64::eventslots::delete_current_event() [private]

To delete the current event, this function moves the current iterator to the next event, deletes the previously-current iterator, adjusts the event count and the bottom iterator, and redraws the pixmap. The exact changes depend upon whether the deleted event was at the top of the visible frame, within the visible frame, or at the bottom the visible frame. Note that only visible events can be the current event, and thus get deleted.

Basically, when an event is deleted, the frame (delimited by the event-index members) stays in place, while the frame iterators move to the previous event. If the top of the frame would move to before the first event, then the frame must shrink.

Top case: If the current iterator is the top (of the frame) iterator, then the top iterator needs to be incremented. The new top event has the same index as the now-gone top event. The index of the bottom event is decremented, since an event before it is now gone. The bottom iterator moves to the next event, which is now at the bottom of the frame. The current event is treated like the top event.

Inside case: If the current iterator is in the middle of the frame, the top iterator and index remain unchanged. The current iterator is incremented, but its index is now the same as the old bottom index. Same for the bottom iterator.

Bottom case: If the current iterator (and bottom iterator) point to the last event in the frame, then both of them need to be decremented. The frame needs to be moved up by one event, so that the current event remains at the bottom (it's just simpler to manage that way).

If there is no event after the bottom of the frame, the iterators that now point to end() must backtrack one event. If the container becomes empty, then everything is invalidated.

Returns

Returns true if the delete was possible. If the container was empty or became empty, then false is returned.

10.12.1.6 bool seq64::eventslots::modify_current_event (const std::string & evtimestamp, const std::string & evname, const std::string & evdata0, const std::string & evdata1) [private]

If the timestamp has changed, however, we can't just modify the event in place. Instead, we finish modifying the event, but tell the caller to delete and reinsert the new event (in its proper new location based on timestamp).

This function always copies the original event, modifiles the copy, deletes the original event, and inserts the "new" event into the editable-event container.

Parameters

evtimestamp	Provides the new event time-stamp as edited by the user.
evname	Provides the event name as edited by the user.
evdata0	Provides the time-stamp as edited by the user.
evtimestamp	Provides the time-stamp as edited by the user.

Returns

Returns true simply if the event-count is greater than 0.

```
10.12.1.7 bool seq64::eventslots::save_events( ) [private]
```

Also sets the dirty flag for the sequence, via the sequence::add_event() function, but this doesn't seem to set the perform dirty flag. So now we pass the modification buck to the parent, who passes it to the perform object.

We added a copy_events() function in the sequence class to replace add_event() for the purpose of reconstructing the events container for the sequence. It is locked by a mutex, and so will not draw until all is done, preventing a nasty segfault (all segfaults are nasty).

We create a new plain event container here, and then passing it to the new locked/threadsafe sequence::copy_
events() function that clears the sequence container and copies the events from the parameter container.

Note that this code will operate event if all events were deleted.

Returns

Returns true if the operations succeeded.

```
10.12.1.8 void seq64::eventslots::select_event ( int event_index = SEQ64_NULL_EVENT_INDEX, bool full_redraw = true ) [private]
```

The event index is provided by converting the y-coordinate of the mouse pointer into a slot number, and then an event index (actually the slot-distance from the m_top_iterator. Confusing, yes no?

Note that, if the event index is negative, then we just queue up a draw operation, which should paint an empty frame – the event container is empty.

Parameters

event_index	Provides the numeric index of the event in the event frame, or SEQ64_NULL_EVENT if there
	is no event to draw.

full_redraw	Defaulting to true, this parameter can be set to false in some case to reduce the flickering of	
	the frame under fast movement.	

10.12.1.9 void seq64::eventslots::set_text (const std::string & evcategory, const std::string & evtimestamp, const std::string & evdata1) [private]

Parameters

evtimestamp	The event time-stamp to be set in the parent.
evname	The event name to be set in the parent.
evdata0	The first event data byte to be set in the parent.
evdata1	The second event data byte to be set in the parent.

10.12.1.10 int seq64::eventslots::convert_y (int y) [private]

Parameters

_		
	V	The v coordinate of the position of the mouse click in the eventslot window/pixmap.
	y	The y coordinate of the position of the mode click in the events of window/pixmap.
	,	, , , , , , , , , , , , , , , , , , , ,

Returns

Returns the index of the event position in the user-interface, which should range from 0 to m_line_count.

10.12.1.11 void seq64::eventslots::draw_event (editable_events::iterator ei, int index) [private]

The slot contains the event details in (so far) one line of text in the box:

| timestamp | event kind | channel | data 0 name + value | data 1 name + value

Currently, this view shows only events that get copied to the sequence's event list. This rules out the following items from the view:

- MThd (song header)
- MTrk and Meta TrkEnd (track marker, a sequence has only one track)
- SeqNr (sequence number)
- SeqSpec (but there are three that might appear, see below)
- Meta TrkName

The events that are shown in this view are:

- One-data-value events:
 - Program Change
 - Channel Pressure
- Two-data-value events:
 - Note Off
 - Note On
 - Aftertouch
 - Control Change
 - Pitch Wheel
- Other:
 - SysEx events, with partial show of data bytes
 - SeqSpec events (TBD):
 - Key
 - Scale
 - Background sequence

The index of the event is shown in the editor portion of the eventedit dialog.

```
10.12.1.12 void seq64::eventslots::draw_events( ) [private]
```

It first clears the whole bitmap to white, so that no artifacts from the previous state of the frame are left behind. Need to figure out how to calculate the number of displayable events.

```
m_line_maximum = ???
```

```
10.12.1.13 void seq64::eventslots::change_vert( ) [private]
```

Note that m_vadjust is the Gtk::Adjustment object that the eventedit parent passes to the gui_drawingarea_gtk2 constructor.

The top-event and bottom-event indices (and their corresponding editable-event iterators) delimit the part of the event container that is displayed in the eventslots user-interface. The top-event index starts at 0, and the bottom-event is larger (initially, by 42 slots).

When the scroll-bar thumb moves up or down, we need to change both event indices and both event iterators by the corresponding amount. Luckily, the std::multimap iterator is bidirectional.

Note that we may need to reduce the movement of events to a value less than a page; it can be limited backwards by the value of the top index, and forward by the value of the bottom index.

```
10.12.1.14 void seq64::eventslots::page_movement(int new_value) [private]
```

The adjustment is done via movement from the current position.

Do we even need a way to detect excess movement? The scrollbar, if properly set up, should never move the frame too high or too low. Verified by testing.

Parameters

new_value	Provides the new value of the scrollbar position.
-----------	---

```
10.12.1.15 void seq64::eventslots::page_topper( editable_events::iterator newcurrent ) [private]
```

The adjustment is done "from scratch". We've found page movement to be an insoluable problem in some editing circumstances. So now we move to the inserted event, and make it the top event.

However, always moving an inserted event to the top is a bit annoying. So now we backtrack so that the inserted event is at the bottom.

Parameters

newcurrent Provides the iterator to the event to be shown at the bottom of the frame.

```
10.12.1.16 int seq64::eventslots::decrement_top( ) [private]
```

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

```
10.12.1.17 int seq64::eventslots::increment_top( ) [private]
```

Also handles the top-event index, so that the GUI can display the proper event numbers.

Returns

Returns the top index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented, or would increment to the end of the container.

```
10.12.1.18 int seq64::eventslots::decrement_current( ) [private]
```

Returns

Returns the decremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

```
10.12.1.19 int seq64::eventslots::increment_current( ) [private]
```

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

```
10.12.1.20 int seq64::eventslots::decrement_bottom( ) [private]
```

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

```
10.12.1.21 int seq64::eventslots::increment_bottom() [private]
```

There is an issue in paging down using the scrollbar where, at the bottom of the scrolling, the bottom iterator ends up bad. Not yet sure how this happens, so for now we backtrack one event if this happens.

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented.

```
10.12.1.22 void seq64::eventslots::on_realize( ) [private]
```

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

```
10.12.1.23 bool seq64::eventslots::on_expose_event( GdkEventExpose * ev ) [private]
```

It draws all of the sequences.

```
10.12.1.24 bool seq64::eventslots::on_focus_in_event( GdkEventFocus * ev ) [private]
```

See the same function in the perfroll module.

```
10.12.1.25 void seq64::eventslots::on_size_allocate( Gtk::Allocation & a ) [private]
```

It first calls the base-class version of this function.

```
10.12.1.26 void seq64::eventslots::on_move_up( ) [private]
```

We must scroll up if the event is now before the frame, and should be made the new top event of the frame. Note that this function isn't really an event-response callback. It is called byh eventedit::on_key_press_event().

```
10.12.1.27 void seq64::eventslots::on_move_down( ) [private]
```

We must scroll down if the event is now after the frame. Note that this function isn't really an event-response callback. It is called byh eventedit::on_key_press_event().

10.12.2 Field Documentation

```
10.12.2.1 int seq64::eventslots::m_slots_chars [private]
```

Pretty much hardwired to 24 at present.

```
10.12.2.2 int seq64::eventslots::m_char_w [private]
```

This value is obtained from a font-renderer accessor function.

```
10.12.2.3 int seq64::eventslots::m_setbox_w [private]
```

This used to be hardwired to 6 * 2 (character-width times two).

```
10.12.2.4 int seq64::eventslots::m_slots_y [private]
```

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

```
10.12.2.5 int seq64::eventslots::m_xy_offset [private]
```

Currently hardwired.

```
10.12.2.6 int seq64::eventslots::m_top_index [private]
```

It is used in numbering the events that are shown in the event-slot frame. Do not confuse it with m_current_index, which is relative to the frame, not the container-beginning.

```
10.12.2.7 int seq64::eventslots::m_current_index [private]
```

This event will also be pointed to by the m_current_event iterator. Do not confuse it with m_top_index, which is relative to the container-beginning, not the frame.

10.13 seq64::font Class Reference

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

Public Types

```
    enum Color {
        BLACK,
        WHITE,
        BLACK_ON_YELLOW,
        YELLOW_ON_BLACK,
        BLACK_ON_CYAN,
        CYAN_ON_BLACK }
```

Public Member Functions

• font ()

Rote default constructor.

• void init (Glib::RefPtr< Gdk::Window > windo)

Initialization function for a window on which fonts will be drawn.

void render_string_on_drawable (Glib::RefPtr< Gdk::GC > m_gc, int x, int y, Glib::RefPtr< Gdk::Drawable > drawable, const char *str, font::Color col) const

Draws a text string.

• int char_width () const

'Getter' function for member m_font_w

int char_height () const

'Getter' function for member m font h

int padded_height () const

'Getter' function for member m_padded_h

Private Attributes

• bool m_use_new_font

If true, use the new font, which is a little bit more modern looking.

· int m cell w

Specifies the cell width of the whole cell.

• int m_cell_h

Specfies the cell height of the whole cell.

• int m_font_w

Specifies the exact width of a character cell, in pixels.

• int m_font_h

Specifies the exact height of a character cell, in pixels.

int m_offset

Provides an ad hoc small horizontal or vertical offset for printing strings.

· int m padded h

Provides a common constant used by much of the drawing code, but only marginally related to the padded character height.

const Glib::RefPtr< Gdk::Pixmap > * m_pixmap

Points to the current pixmap (m_black_pixmap or m_white_pixmap) to use to render a string.

 $\bullet \ \, Glib::RefPtr < Gdk::Pixmap > m_black_pixmap \\$

The pixmap in the file src/pixmaps/font_b.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_white_pixmap

The pixmap in the file src/pixmaps/font_w.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m b on y pixmap

The pixmap in the file src/pixmaps/font_y.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_y_on_b_pixmap

The pixmap in the file src/pixmaps/font_yb.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_b_on_c_pixmap

The pixmap in the file src/pixmaps/cyan_wenfont_y.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_c_on_b_pixmap

The pixmap in the file src/pixmaps/cyan_wenfont_yb.xpm is loaded into this object.

Glib::RefPtr< Gdk::Bitmap > m_clip_mask

This object is instantiated as a default object.

10.13.1 Member Enumeration Documentation

10.13.1.1 enum seq64::font::Color

Enumerator

BLACK A simple enumeration to describe the basic colors used in writing text. Basically, these two values cause the selection of one or another pixmap (font_b_xpm and font_w_xpm). We've added two more pixmaps to draw black text on a yellow background (font_y.xpm) and yellow text on a black background (font_yb.xpm).

```
The first supported color. A black font on a white background.
```

WHITE The second supported color. A white font on a black background.

BLACK_ON_YELLOW A new color, for drawing black text on a yellow background.

YELLOW_ON_BLACK A new color, for drawing yellow text on a black background.

BLACK_ON_CYAN A new color, for drawing black text on a cyan background.

CYAN_ON_BLACK A new color, for drawing cyan text on a black background.

10.13.2 Member Function Documentation

```
10.13.2.1 void seq64::font::init ( Glib::RefPtr < Gdk::Window > wp )
```

This function loads four pixmaps that contain the characters to be used to draw text strings.

One pixmap has white characters on a black background, one has black characters on a white background, one has yellow characters on a black background, and one has black characters on a yellow background.

```
10.13.2.2 void seq64::font::render_string_on_drawable ( Glib::RefPtr< Gdk::GC > a\_gc, int x, int y, Glib::RefPtr< Gdk::Drawable > a\_draw, const char * str, font::Color col ) const
```

This function grabs the proper font bitmap, extracts the current character pixmap from it, and slaps it down where it needs to be to render the character in the string.

Parameters

	5 11 11 11 11 11 11 11 11 11 11 11 11 11
a_gc	Provides the graphics context for drawing the text using GTK+.
X	The horizontal location of the text.
у	The vertical location of the text.
a_draw	The drawable object on which to draw the text.
str	The string to draw. Should use a constant string reference instead.
col	The font color to use to draw the string. The supported values are font::BLACK, font::WH←
	ITE, font::BLACK_ON_YELLOW, font::YELLOW_ON_BLACK. The actual correct colors are
	provided by selecting one of four font pixmaps, as described in the init() function.

10.13.3 Field Documentation

```
10.13.3.1 int seq64::font::m_font_w [private]
```

Currently defaults to $cf_{text_w} = 6$. Note that a lot of stuff depends on this being 6 at present, even with our new, slightly wider, font.

```
10.13.3.2 int seq64::font::m_font_h [private]
```

Currently defaults to cf_text_h = 10. Note that a lot of stuff depends on this being 10 at present, even with our new, slightly wider, font. But some of the drawing code doesn't use the character height, but the padded character height.

```
10.13.3.3 const Glib::RefPtr<Gdk::Pixmap>* seq64::font::m_pixmap [mutable], [private]
```

This member used to be an object, but it's probably a bit faster to just use a pointer (or a reference).

```
10.13.3.4 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_black_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is resources/pixmaps/wenfont ← _b.xmp pixmap.

```
10.13.3.5 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_white_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is $resources/pixmaps/wenfont \leftarrow _w.xmp$ pixmap.

```
10.13.3.6 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_y_pixmap [private]
```

It contains a black font on a yellow background. The new-style font, if selected, is resources/pixmaps/wenfont ← _y.xmp pixmap.

```
10.13.3.7 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_y_on_b_pixmap [private]
```

It contains a yellow font on a black background. The new-style font, if selected, is resources/pixmaps/wenfont ← _yb.xmp pixmap.

```
10.13.3.8 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_c_pixmap [private]
```

It contains a black font on a cyan background. It is available only for the new font-style.

```
10.13.3.9 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_c_on_b_pixmap [private]
```

It contains a cyan font on a black background. It is available only for the new font-style.


```
10.13.3.10 Glib::RefPtr<Gdk::Bitmap> seq64::font::m_clip_mask [private]
```

All we know is it seems to be a requirement for creating a pixmap object from an XMP file.

10.14 seq64::gui_assistant Class Reference

This class provides an interface for some of the GUI support needed in Sequencer64.

Inheritance diagram for seq64::gui_assistant:



Public Member Functions

• gui_assistant (keys_perform &kp)

This constructor wires in some externally (for now) created objects.

virtual ~gui_assistant ()

Stock base-class implementation of a virtual destructor.

• const keys_perform & keys () const

'Getter' function for member m_keys_perform The const getter.

keys_perform & keys ()

'Getter' function for member m_keys_perform The un-const getter.

Private Attributes

• keys_perform & m_keys_perform

Provides a reference to the app-specific GUI-specific keys_perform-derived object that an application is going to use for handling sequence-control keys.

10.14.1 Detailed Description

It also contain a number of helper objects that all kind of go together; only this assistant object will need to be passed around (by non-GUI code).

10.14.2 Constructor & Destructor Documentation


10.14.2.1 seq64::gui_assistant::gui_assistant (keys_perform & kp)

Parameters

kp	Provides a set of key codes to be used by the perform object to control patterns and their
	performance.

10.15 seq64::gui_assistant_gtk2 Class Reference

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64. Inheritance diagram for seq64::gui_assistant_gtk2:



Public Member Functions

• gui_assistant_gtk2 ()

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

• virtual void quit ()

Calls the Glib Main object's quit() function.

virtual void lash_timeout_connect (lash *lashobject)

 ${\it Connects the JACK session-event callback to the Glib idle object.}$

Static Private Attributes

static keys_perform_gtk2 sm_internal_keys
 Provides a pre-made keys_perform object.

10.15.1 Member Function Documentation

10.15.1.1 void seq64::gui_assistant_gtk2::lash_timeout_connect(lash * lashobject) [virtual]

If JACK session support is not enabled, we might emit a message. This mainly prevents a compiler warning about an unused parameter. Connects the LASH timeout-event callback to the Glib timeout object. The time-out value is set to 250 ms.

Implements seq64::gui_assistant.

10.15.2 Field Documentation


10.15.2.1 keys_perform_gtk2 seq64::gui_assistant_gtk2::sm_internal_keys [static], [private]

This object is set into the reference provided in the gui_assistant base class.

10.16 seq64::gui_drawingarea_gtk2 Class Reference

Implements the basic drawing areas of the application.

Inheritance diagram for seq64::gui_drawingarea_gtk2:



Data Structures

· struct rect

A small helper structure representing a rectangle.

Public Member Functions

gui_drawingarea_gtk2 (perform &p, int window_x=0, int window_y=0)

Perform-only constructor.

gui_drawingarea_gtk2 (perform &a_perf, Gtk::Adjustment &a_hadjust, Gtk::Adjustment &a_vadjust, int window x=0, int window y=0)

Principal constructor.

~gui_drawingarea_gtk2 ()

Provides a destructor to delete allocated objects.

• int window x () const

'Getter' function for member m_window_x

• int window_y () const

'Getter' function for member m_window_y

• int current x () const

'Getter' function for member m_current_x

int current_y () const

'Getter' function for member m_current_y

int drop_x () const

'Getter' function for member m_drop_x

int drop_y () const

'Getter' function for member m_drop_y

Protected Member Functions

• perform & perf ()

'Getter' function for member m_mainperf

• void clear window ()

Clears the main window.

• void set_line (Gdk::LineStyle Is, int width=1)

A small wrapper function for readability in line-drawing.

void draw_line (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window.

void draw_line (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window after setting the given foreground color.

void draw_line_on_pixmap (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap.

void draw_line_on_pixmap (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap after setting the given foreground color.

 $\bullet \ \ void \ \frac{draw_line}{draw_line} \ (Glib::RefPtr < Gdk::Pixmap > \&pixmap, int \ x1, int \ y1, int \ x2, int \ y2) \\$

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

• void draw line (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap after setting the given foreground color.

• void draw_line (Glib::RefPtr< Gdk::Drawable > &drawable, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

void draw_line (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the drawable after setting the given foreground color.

void render_string (int x, int y, const std::string &s, font::Color color)

A small wrapper function for readability in string-drawing to the window.

void render_string_on_pixmap (int x, int y, const std::string &s, font::Color color)

A small wrapper function for readability in string-drawing to the pixmap.

void draw_rectangle (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the window.

• void draw rectangle (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing.

void draw_rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "drawable" context, where the foreground color has already been specified.

• void draw_rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any drawable context.

void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "pixmap" context, where the foreground color has already been specified.

void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any pixmap context.

void draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

void draw_rectangle_on_pixmap (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

• void draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

void draw drawable (int xsrc, int ysrc, int xdest, int ydest, int width, int height)

Provides the most common use case for redrawing.

void on_realize ()

For this GTK callback, on realization of window, initialize the shiz.

Protected Attributes

• Glib::RefPtr< Gdk::GC > m gc

The graphics context, which is required for ever drawing and rendering operation.

• Glib::RefPtr< Gdk::Window > m window

Provides the default "window".

Gtk::Adjustment & m_vadjust

Provides an object for vertical "adjustments".

Gtk::Adjustment & m_hadjust

Provides an object for horizontal "adjustments".

Glib::RefPtr< Gdk::Pixmap > m pixmap

Provides the default "pixmap".

• Glib::RefPtr< Gdk::Pixmap> m_background

Another pixmap, used for backgrounds.

Glib::RefPtr< Gdk::Pixmap > m_foreground

Another pixmap, used for foregrounds.

• perform & m_mainperf

A frequent hook into the main perform object.

int m_window_x

Window sizes.

• int m_current_x

The x and y value of the current location of the mouse (during dragging?)

• int m_drop_x

These values are used when roping and highlighting a bunch of events.

Private Member Functions

· void gtk drawarea init ()

Does basic initialization for each of the constructors.

Additional Inherited Members

10.16.1 Detailed Description

Note that this class really "isn't a" gui_pallete_gtk2; it should simply have one. But that base class must be derived from Gtk::DrawingArea. We don't want to waste some space by using a "has-a" relationship, and also put up with having to access the palette indirectly. So, in this case, we tolerate the less strict implementation.

10.16.2 Member Function Documentation

10.16.2.1 void seq64::gui_drawingarea_gtk2::clear_window() [inline], [protected]

One less need to access m_window directly.

10.16.2.2 void seq64::gui_drawingarea_gtk2::set_line (Gdk::LineStyle *ls*, int width = 1) [inline], [protected]

Sets the attributes of a line to be drawn.

Parameters

Is	Provides the Gtk-specific line style.
width	Provides the width of the line to be drawn. It defaults to the most common value, 1.

10.16.2.3 void seq64::gui_drawingarea_gtk2::draw_line(int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
<i>y</i> 2	The y coordinate of the ending point.

10.16.2.4 void seq64::gui_drawingarea_gtk2::draw_line (const Color & c, int x1, int y1, int x2, int y2) [protected]

Parameters

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

10.16.2.5 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
<i>y2</i>	The y coordinate of the ending point.

10.16.2.6 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (const Color & c, int x1, int y1, int x2, int y2) [protected]

Parameters

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

10.16.2.7 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Pixmap > & pixmap, int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

pixmap	Provides the Gdk::Pixmap pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
<i>y</i> 2	The y coordinate of the ending point.

10.16.2.8 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Pixmap > & pixmap, const Color & c, int x1, int y1, int x2, int y2) [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
<i>y</i> 2	The y coordinate of the ending point.

10.16.2.9 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & drawable, int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.

x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

10.16.2.10 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & drawable, const Color & c, int x1, int x2, int x2, int y2) [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

10.16.2.11 void seq64::gui_drawingarea_gtk2::render_string (int x, int y, const std::string & s, font::Color color)
[inline], [protected]

Parameters

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.

10.16.2.12 void seq64::gui_drawingarea_gtk2::render_string_on_pixmap (int x, int y, const std::string & s, font::Color color) [inline], [protected]

Parameters

	The x-coordinate of the origin.
	The y-coordinate of the origin.
	The string to be drawn.
colo	The color with which to draw the string.

10.16.2.13 void seq64::gui_drawingarea_gtk2::draw_rectangle(int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

Parameters

X	The x-coordinate of the origin.
у	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_
	foreground(color). Defaults to true.

10.16.2.14 void seq64::gui_drawingarea_gtk2::draw_rectangle (const Color & c, int x, int y, int lx, int ly, bool fill = true)

[protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

С	Provides the foreground color to set.
X	The x-coordinate of the origin.
у	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_~
	foreground(color). Defaults to true.

10.16.2.15 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & drawable, int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

Parameters

drawable	The object on which to draw the rectangle.
X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set
	foreground(color). Defaults to true.

10.16.2.16 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & drawable, const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

Parameters

drawable	The surface on which to draw the box.
С	Provides the foreground color to set.
X	The x-coordinate of the origin.
у	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_ foreground(color). Defaults to true.

10.16.2.17 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr < Gdk::Pixmap > & pixmap, int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

Parameters

drawable	The object on which to draw the rectangle.
X	The x-coordinate of the origin.
у	The y-coordinate of the origin.
lx	The width of the box.

ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_~
	foreground(color). Defaults to true.

10.16.2.18 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr < Gdk::Pixmap > & pixmap, const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It also supports setting the foreground color to the draw rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

Parameters

pixmap	The surface on which to draw the box.
С	Provides the foreground color to set.
X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_{\leftarrow}
	foreground(color). Defaults to true.

10.16.2.19 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill = true)
[inline], [protected]

Parameters

X	The x-coordinate of the origin.
у	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_c
	foreground(color). Defaults to true.

10.16.2.20 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

С	Provides the foreground color to set.
X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_~
	foreground(color). Defaults to true.

10.16.2.21 void seq64::gui_drawingarea_gtk2::draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill = true) [protected]

It uses Gtk to get the proper background styling for the rectange.

Parameters

X	The x-coordinate of the origin.
у	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_
	foreground(color). Defaults to true.

10.16.2.22 void seq64::gui_drawingarea_gtk2::on_realize() [protected]

It allocates any additional resources that weren't initialized in the constructor.

10.16.3 Field Documentation

```
10.16.3.1 Glib::RefPtr<Gdk::Window> seq64::gui_drawingarea_gtk2::m_window [protected]
```

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

```
10.16.3.2 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_pixmap [protected]
```

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

```
10.16.3.3 Glib::RefPtr < Gdk::Pixmap > seq64::gui_drawingarea_gtk2::m_background [protected]
```

Our wrappers still leave this member exposed <giggle>.

```
10.16.3.4 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_foreground [protected]
```

Our wrappers still leave this member exposed.

```
10.16.3.5 perform& seq64::gui_drawingarea_gtk2::m_mainperf [protected]
```

We could move this into yet another base class, since a number of classes don't need it. Probably not worth the effort at this time.

```
10.16.3.6 int seq64::gui_drawingarea_gtk2::m_window_x [protected]
```

Could make this constant, but some windows are resizable.


```
10.16.3.7 int seq64::gui_drawingarea_gtk2::m_drop_x [protected]
```

Provides the x and y value of where the dragging started.

10.17 seq64::gui_palette_gtk2 Class Reference

Implements a stock palette of Gdk::Color elements.

Inheritance diagram for seq64::gui_palette_gtk2:



Public Member Functions

- gui_palette_gtk2 ()
 - Principal constructor.
- ~gui_palette_gtk2 ()

Provides a destructor to delete allocated objects.

Protected Types

• typedef Gdk::Color Color

Provides a type for the color object.

10.17.1 Detailed Description

Note that this class must be derived from Gtk::DrawingArea (or Gtk::Widget) in order to get access to the $get_\leftarrow default_colormap()$ function used in the constructor.

10.17.2 Constructor & Destructor Documentation


10.17.2.1 seq64::gui_palette_gtk2::gui_palette_gtk2()

In the constructor you can only allocate colors; get_window() returns 0 because this window has not be realized.

10.18 seq64::gui_window_gtk2 Class Reference

This class supports a basic interface for Gtk::Window-derived objects.

Inheritance diagram for seq64::gui_window_gtk2:



Public Member Functions

• gui_window_gtk2 (perform &p, int window_x=0, int window_y=0)

Principal constructor, has a reference to the all-important perform object.

• \sim gui_window_gtk2 ()

This rote constructor does nothing.

Protected Member Functions

• perform & perf ()

'Getter' function for member m_mainperf

Private Attributes

• perform & m_mainperf

The master object, sort of a sequence buss.

• int m window x

Window sizes.

- 10.18.1 Constructor & Destructor Documentation
- 10.18.1.1 seq64::gui_window_gtk2::gui_window_gtk2 (perform & p, int $window_x = 0$, int $window_y = 0$)

Parameters

a_perf | Refers to the main performance object.

10.18.2 Field Documentation

10.18.2.1 int seq64::gui_window_gtk2::m_window_x [private]

Could make this constant, but some windows are resizable.

10.19 seq64::jack_assistant Class Reference

This class provides the performance mode JACK support.

Public Member Functions

jack_assistant (perform &parent, int ppqn=SEQ64_USE_DEFAULT_PPQN, int bpm=SEQ64_DEFAULT_
 —
 BEATS_PER_MEASURE, int beatwidth=SEQ64_DEFAULT_BEAT_WIDTH)

This constructor initializes a number of member variables, some of them public!

∼jack assistant ()

The destructor doesn't need to do anything yet.

• bool is_running () const

'Getter' function for member m_jack_running

bool is_master () const

'Getter' function for member m_jack_master

• perform & parent ()

 ${\it 'Getter' function for member m_jack_parent Needed for external callbacks}.$

• bool init ()

Initializes JACK support.

• bool restart ()

Let's try to recover from the JackFailures somehow.

· void deinit ()

Tears down the JACK infrastructure.

• void start ()

If JACK is supported, starts the JACK transport.

• void stop ()

If JACK is supported, stops the JACK transport.

void position (bool to_left_tick, bool relocate=false)

If JACK is supported and running, sets the position of the transport to the new frame number, frame 0.

bool output (jack_scratchpad &pad)

Performance output function for JACK, called by the perform function of the same name.

Private Member Functions

void set_ppqn (int ppqn)

'Setter' function for member m_ppqn For the future, changing the PPQN internally.

double get_jack_ticks () const

Helper function for obtaining "jack_ticks_converted".

double frame_to_ticks (jack_nframes_t frame) const

Another helper function.

bool info_message (const std::string &msg)

Common-code for console messages.

bool error_message (const std::string &msg)

Common-code for error messages.

jack_client_t * client_open (const std::string &clientname)

A more full-featured initialization for a JACK client, which is meant to be called by the init() function.

void show_statuses (unsigned bits)

Loops through the full set of JACK bits, showing the information for any bits that are set in the given parameter.

int sync (jack_transport_state_t state=(jack_transport_state_t)(-1))

A helper function for syncing up with JACK parameters.

void set position (midipulse currenttick)

Provides the code that was effectively commented out in the perform::position_jack() function.

Static Private Attributes

static jack_status_pair_t sm_status_pairs []

Provides a list of JACK status bits, and a brief string to explain the status bit.

Friends

• int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)

Global functions for JACK support and JACK sessions.

void jack_shutdown_callback (void *arg)

This callback is to shutdown JACK by clearing the jack_assistant::m_jack_running flag.

void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

10.19.1 Detailed Description

WHY PERFORMANCE MODE? Only works in that mode???

10.19.2 Constructor & Destructor Documentation

```
10.19.2.1 seq64::jack_assistant::jack_assistant ( perform & parent, int ppqn = SEQ64_USE_DEFAULT_PPQN, int bpm = SEQ64_DEFAULT_BEATS_PER_MEASURE, int beatwidth = SEQ64_DEFAULT_BEAT_WIDTH )
```

Note that the perform object currently calls jack_assistant::init(), but that call could be made here instead.

Parameters

parent Provides a reference to the main perform object that needs to control JACK event.

10.19.2.2 seq64::jack_assistant::~jack_assistant()

The perform object currently calls jack_assistant::deinit(), but that call could be made here instead.

10.19.3 Member Function Documentation

```
10.19.3.1 bool seq64::jack_assistant::init()
```

Then we become a new client of the JACK server.

Note the USE_JACK_SYNC_CALLBACK macro. A sync callback is needed for polling of slow-sync clients. But seq24/sequencer64 are not slow-sync clients. Therefore, let's conditionally comment out the sync callback code. One of the author's of JACK notes that seq24 is wrong to set up a sync callback. However, this macro is currently enabled.

Jack transport settings:

```
There are three settings: On, Master, and Master Conditional. Currently, they can all be selected in the user-interface's File / Options / JACK/LASH page. We really want only the proper combinations to be set, for clarity (the user-interface now takes care of this. We need to initialize if any of them are set, and the rc_settings::with_jack() function tells us that.
```

jack_set_process_callback() patch:

```
Implemented first patch from freddix/seq24 GitHub project, to fix JACK transport. One line of code. Well, we added some error-checking. :-) Found some old notes on the Web the this patch really only works (to prevent seq24 freeze) if seq24 is set as JACK Master, or if another client application, such as Qtractor, is running as JACK Master (and then seq24 will apparently follow it).
```

Returns

Returns true if JACK is now considered to be running (or if it was already running.)

```
10.19.3.2 bool seq64::jack_assistant::restart()
```

For now, we don't know what is causing this code, which doesn't seem to much affect the JACK transport functionality. This function does nothing.

Returns

Will return true if the restart succeeded. Currently always return false.

```
10.19.3.3 void seq64::jack_assistant::start ( )
```

This function assumes that m jack client is not null, if m jack running is true.

Found this note in the Hydrogen code:

```
When jack_transport_start() is called, it takes effect from the next processing cycle. The location info from the timebase_master, if there is one, will not be available until the _next_ next cycle. The code must therefore wait one cycle before syncing up with timebase_master.
```

```
10.19.3.4 void seq64::jack_assistant::stop ( )
```

This function assumes that m_jack_client is not null, if m_jack_running is true.

10.19.3.5 void seq64::jack_assistant::position (bool to_left_tick, bool relocate = false)

This new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

```
http://jackaudio.org/files/docs/html/transport-design.html
```

This position() function is called via perform::position_jack() in the mainwnd, perfedit, perfroll, and seqroll graphical user-interface support objects.

The code that was disabled sets the current tick to 0 or, if state was true, to the leftmost tick (which is probably the position of the L marker). The current tick is then converted to a frame number, and then we locate the transport to that position. We're going to enable this code, but make it dependent on a new boolean parameter that defaults to false, in anticipation of trying it out later.

These repositions reset the progress bars. We don't always want that, it should be an option. TODO. jack_transport_reposition():

```
Requests a new transport position. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

It's pos parameter provides the requested new transport position. Fill pos->valid to specify which fields should be taken into account. If you mark a set of fields as valid, you are expected to fill them all. Note that "frame" is always assumed, and generally needs to be set:

http://comments.gmane.org/gmane.comp.audio.jackit/18705

Returns 0 if a valid request, EINVAL if the position structure is rejected.
```

Warning

A lot of this code is effectively disabled by an early return statement.

Parameters

to_left_tick	If true, the current tick is set to the leftmost tick, instead of the 0th tick. Now used, but only
	if relocate is true. One question is, do we want to perform this function if rc().with_jack_~
	transport() is true? Seems like we should be able to do it only if m_jack_master is true.
relocate	If true (it defaults to false), then we allow the relocation of the JACK transport to the current ←
	_tick or the left tick, rather than to frame 0. EXPERIMENTAL, enables dead code from seq24.
	Seems to work if set to true when we are the JACK Master. Enabling this code makes "klick
	-j -P" work, after a fashion. It clicks, but at a way too rapid rate.

10.19.3.6 bool seq64::jack_assistant::output (jack_scratchpad & pad)

This code comes from perform::output_func() from seq24.

USE_JACK_TRANSPORT_QUERY_STATUS macro: Sequencer64 (and Seq24) yields JackFailure errors. If we don't respond to them by setting m_jack_running to false, then we get endless errors, and can get a segfault when exiting the application. If we do set m_jack_running to false and then return, we have to disable JACK, and fall back to Sequencer64's own timing. Right now, the best policy is to ignore JackFailure here. At least until we can figure out what causes it.

Note

Follow up on this note found "out there": "Maybe I'm wrong but if I understood correctly, recent jack1 transport no longer goes into Jack_Transport_Starting state before going to Jack_Transport_Rolling (this was deliberately dropped), but seq24 currently needs this to start off with jack transport." On the other hand, some people have no issues. This may have been due to the lack of m_jack_pos initialization.

Parameters

pad	Provide a JACK scratchpad for sharing certain items between the perform object and the
	jack_assistant object.

Returns

Returns true if JACK is running.

```
10.19.3.7 double seq64::jack_assistant::get_jack_ticks( ) const [private]
```

Note that we will need to replace 4.0 with a member value.

10.19.3.8 bool seq64::jack_assistant::info_message (const std::string & msg) [private]

Adds markers and a newline.

Parameters

msg	The message to print, sans the newline.
-----	---

Returns

Returns true.

```
10.19.3.9 bool seq64::jack_assistant::error_message ( const std::string & msg ) [private]
```

Adds markers, and sets m_jack_running to false.

Parameters

msg	The message to print, sans the newline.

Returns

Returns false for convenience/brevity in setting function return values.

```
10.19.3.10 jack_client_t * seq64::jack_assistant::client_open ( const std::string & clientname ) [private]
```

Status bits for jack status t return pointer:

```
JackNameNotUnique means that the client name was not unique. With JackUseExactName, this is fatal. Otherwise, the name was modified by appending a dash and a two-digit number in the range "-01" to "-99". The jack_get_client_name() function returns the exact string used. If the specified client_name plus these extra characters would be too long, the open fails instead.
```

JackServerStarted means that the JACK server was started as a result of this operation. Otherwise, it was running already. In either case the caller is now connected to jackd, so there is no race condition. When the server shuts down, the client will find out.

Returns

Returns true if JACK ...

```
10.19.3.11 void seg64::jack_assistant::show_statuses(unsigned bits) [private]
```

For reference, here are the enumeration values from /usr/include/jack/types.h:

```
JackFailure
                  = 0 \times 01
JackInvalidOption = 0x02
JackNameNotUnique = 0x04
JackServerStarted
                  = 0x08
JackServerFailed
                  = 0x10
JackServerError
                  = 0x20
JackNoSuchClient
                  = 0x40
                  = 0x80
JackLoadFailure
JackInitFailure = 0x100
JackShmFailure
                  = 0x200
JackVersionError = 0x400
JackBackendError = 0x800
JackClientZombie
                  = 0x1000
```

Sequencer64 is not a slow-sync client, so that callback is not really needed, but we probably need this sub-function here to start out with the right values for interacting with JACK.

Note the call to jack_transport_query(). This call is *not* is seq24, but seems to be needed in sequencer64 because we put m_jack_pos in the initializer list, which sets all its fields to 0. Seq24 accesses m_jack_pos before it ever gets set, but its fields have values. These values are bogus, but are consistent from run to run on my computer, and allow seq24 to follow another JACK Master, on some computers. It explains why people had different experiences with JACK sync.

If we explicity call jack_transport_query() here, without changing the *state* parameter, then sequencer64 also can follow another JACK Master. (CURRENTLY BUGGY!)

Note that we should consider massaging the following jack_position_t members to set them to 0 (or 0.0) if less than 1.0 or 0.5:

```
- bar_start_tick
- ticks_per_beat
- beats_per_minute
- frame_time
- next_time
- audio_frames_per_video_frame
```

Also, why does bbt_offset start at 2128362496?

```
10.19.3.13 void seq64::jack_assistant::set_position ( midipulse currenttick ) [private]
```

We might be able to use it in other functions.

Computing the BBT information from the frame number is relatively simple here, but would become complex if we supported tempo or time signature changes at specific locations in the transport timeline.

```
ticks * 10 = jack ticks;
jack ticks / ticks per beat = num beats;
num beats / beats per minute = num minutes
num minutes * 60 = num seconds
num secords * frame_rate = frame
```

10.19.4 Friends And Related Function Documentation

10.19.4.1 void jack_shutdown_callback (void * arg) [friend]

Parameters

arg	Points to the jack_assistant in charge of JACK support for the perform object.

10.19.4.2 void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t * pos, int new pos, void * arg) [friend]

The original version of the function, enabled by defining USE_ORIGINAL_TIMEBASE_CALLBACK, worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

```
http://essej.net/sooperlooper/
```

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set. (Do we have more work to do in Sequencer64 in this case?) Note that this code does not change beats_per_bar, beat_type, ticks per beat, or beats per minute. It also hardwires pos->beats per bar and pos->beat type to 4.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We probably need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

- -# Calculate the "delta" ticks based on the current frame, the ticks_per_beat, the beats_per_minute, and the frame_rate. The old code saves this in a local, the new code assigns it to pos->tick.
- -# Old code: save this delta as a positive value.
- -# Figure out the settings and modify bar, beat, tick, and bar_start_tick. The old and new code seem to have the same intent, but it seems like the new code is faster and also correct.
 - Old code: Calculations are made by division and mod operations.
 - New code: Calculations are made by increments and decrements in a while loop.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next
	cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains
	extended position information from the current cycle. If TRUE, it contains whatever was set
	by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback
	is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in
	qjacketl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

10.19.5 Field Documentation

10.19.5.1 jack_status_pair_t seq64::jack_assistant::sm_status_pairs [static], [private]

Terminated by a 0 value and an empty string.

10.20 seq64::jack_scratchpad Class Reference

Provide a temporary structure for passing data and results between a perform and jack assistant object.

10.20.1 Detailed Description

The jack_assistant class already has access to the members of perform, but it needs access to and modification of "local" variables in perform::output_func(). This scratchpad is useful even if JACK support is not enabled.

10.21 seq64::keybindentry Class Reference

Class for management of application key-bindings.

Inherits Entry.

Public Member Functions

keybindentry (type t, unsigned int *location to write=nullptr, perform *p=nullptr, long s=0)

This constructor initializes the member with values dependent on the value type provided in the first parameter.

void set (unsigned int val)

Gets the key name from the integer value; if there is one, then it is printed into a temporary buffer, otherwise the value is printed into that buffer as is.

virtual bool on_key_press_event (GdkEventKey *event)

Handles a key press by calling set() with the event's key value.

Private Types

```
enum type {
location,
events,
groups }
```

Private Attributes

unsigned int * m_key

Points to the value of the key that is part of this key-binding.

• type m_type

Stores the type of key-binding.

perform * m_perf

Stores an optional pointer to a perform object.

• long m_slot

Provides???

10.21.1 Member Enumeration Documentation

```
10.21.1.1 enum seq64::keybindentry::type [private]
```

Enumerator

location Provides the type of keybindings that can be made. Used for handling a keystroke made while a keyboard-options field is active, for selecting a key via the keyboard, and binding to pattern/sequence boxes, we think. It is used in the options class to associate a key with the binding.

events Used for binding to events.

groups Used for binding to groups.

10.21.2 Constructor & Destructor Documentation

10.21.2.1 seq64::keybindentry::keybindentry (type t, unsigned int * location_to_write = nullptr, perform * p = nullptr, long s = 0)

Usage In options, a pointer to a new key-binding entry is managed by calling keybindentry (keybindentry ::location, &perf->keyname).

Parameters

t	Provides the type of key-binding: location, events, or groups.
location_to_write	The location that holds the value of the key associated with the key-binding. The default value
	of this parameter is the null pointer.
р	Points to the performance object used with this key-binding. The default value of this param-
	eter is the null pointer.
S	Provides the slot value for this key-binding. The default value of this parameter is zero.

10.21.3 Member Function Documentation

10.21.3.1 void seq64::keybindentry::set (unsigned int val)

Then we call set_text(buf). The set_width_char() function is then called.

10.21.3.2 bool seq64::keybindentry::on_key_press_event (GdkEventKey * event) [virtual]

This value is used to set the event or key depending on the value of m_type.

10.21.4 Field Documentation


10.21.4.1 unsigned int* seq64::keybindentry::m_key [private]

Not yet sure by the address of this key value is needed. It can be a null pointer, as well.

10.22 seq64::keys_perform Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform:



Public Member Functions

• keys_perform ()

This construction initializes a vast number of member variables, some of them public!

• \sim keys_perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

void set_keys (const keys_perform_transfer &kpt)

Copies fields from the transfer structure in this object.

· void get_keys (keys_perform_transfer &kpt)

Copies fields from this object into the transfer structure.

bool show_ui_sequence_key () const

Accessor m_key_show_ui_sequency_key

• bool show_ui_sequence_number () const

Accessor m_key_show_ui_sequency_number

virtual std::string key name (unsigned int key) const

Obtains the name of the key.

• virtual void set_all_key_events ()

Provides base class functionality.

virtual void set_all_key_groups ()

Provides base class functionality.

void set_key_event (unsigned int keycode, long sequence_slot)

At construction time, this function sets up one keycode and one event slot.

void set_key_group (unsigned int keycode, long group_slot)

At construction time, this function sets up one keycode and one group slot.

Protected Types

typedef std::map< unsigned int, long > SlotMap

This typedef defines a map in which the key is the keycode, that is, the integer value of a keystroke, and the value is the pattern/sequence number or slot.

typedef std::map< long, unsigned int > RevSlotMap

This typedef is like SlotMap, but used for lookup in the other direction.

Private Attributes

• bool m_key_show_ui_sequence_key

If set, shows the shortcut-keys on each filled pattern slot in the main window.

bool m_key_show_ui_sequence_number

If set, shows the sequence number on each filled pattern and empty pattern slot in the main window.

unsigned int m_key_bpm_up

Provides key assignments for some key sequencer features.

10.22.1 Detailed Description

It has way too many data members, many of the public. Might be ripe for refactoring.

10.22.2 Constructor & Destructor Documentation

```
10.22.2.1 seq64::keys_perform::~keys_perform()
```

Finally, any active patterns/sequences are deleted.

10.22.3 Member Function Documentation

10.22.3.1 void seg64::keys_perform::set_keys (const keys_perform_transfer & kpt)

This structure holds all of the key settings from the File / Options / Keyboard tab dialog.

Parameters

kpt	The structure that holds the values of the keys to be used for various purposes in controlling
	a performance live.

10.22.3.2 void seq64::keys_perform::get_keys (keys_perform_transfer & kpt)

Parameters

kpt	The structure that holds the values of the keys to be used for various purposes in controlling
	a performance live.

10.22.3.3 bool seq64::keys_perform::show_ui_sequence_key()const [inline]

Used in mainwid, options, optionsfile, userfile, and perform.

10.22.3.4 bool seq64::keys_perform::show_ui_sequence_number() const [inline]

Used in mainwid, options, optionsfile, userfile, and perform.

10.22.3.5 std::string seq64::keys_perform::key_name(unsigned int key) const [virtual]

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string.

Parameters

key	Provides the numeric value of the keystroke.

Returns

Returns the name of the key, in the format "Key 0xkkkk".

Reimplemented in seq64::keys_perform_gtk2.

10.22.3.6 virtual void seq64::keys_perform::set_all_key_events() [inline], [virtual]

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys perform gtk2.

10.22.3.7 virtual void seq64::keys_perform::set_all_key_groups() [inline], [virtual]

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

10.22.3.8 void seq64::keys_perform::set_key_event (unsigned int keycode, long sequence_slot)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
sequence_slot	The perform event slot into which the keycode will be assigned.

10.22.3.9 void seq64::keys_perform::set_key_group (unsigned int keycode, long group_slot)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
group_slot	The perform group slot into which the keycode will be assigned.

10.22.4 Field Documentation

10.22.4.1 bool seq64::keys_perform::m_key_show_ui_sequence_number [private]

Also show the sequence number as part of the sequence name in the performance window (song editor).


10.22.4.2 unsigned int seq64::keys_perform::m_key_bpm_up [private]

Used in mainwnd, options, optionsfile, perfedit, seqroll, userfile, and perform.

10.23 seq64::keys_perform_gtk2 Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform_gtk2:



Public Member Functions

• keys_perform_gtk2 ()

This construction initializes a vast number of member variables, some of them public!

virtual ~keys_perform_gtk2 ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

virtual std::string key_name (unsigned int key) const

Obtains the name of the key.

virtual void set_all_key_events ()

Sets up the keys for arming/unmuting events in the Gtk-2 environment.

virtual void set_all_key_groups ()

Sets up the keys for group events in the Gtk-2 environment.

Additional Inherited Members

10.23.1 Detailed Description

It has way too many data members, many of the public. Might be ripe for refactoring.

10.23.2 Constructor & Destructor Documentation

```
10.23.2.1 seq64::keys_perform_gtk2::~keys_perform_gtk2() [virtual]
```

Finally, any active patterns/sequences are deleted.

10.23.3 Member Function Documentation

```
10.23.3.1 std::string seq64::keys_perform_gtk2::key_name ( unsigned int key ) const [virtual]
```

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string.

Reimplemented from seq64::keys_perform.

```
10.23.3.2 void seq64::keys_perform_gtk2::set_all_key_events( ) [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

```
10.23.3.3 void seq64::keys_perform_gtk2::set_all_key_groups() [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

10.24 seg64::keys perform transfer Struct Reference

Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf().

10.25 seq64::keystroke Class Reference

Encapsulates any practical keystroke.

Public Member Functions

· keystroke ()

The default constructor for class keystroke.

keystroke (unsigned int key, bool press=SEQ64_KEYSTROKE_PRESS, int modkey=int(SEQ64_NO_MAS

K))

The principal constructor.

· keystroke (const keystroke &rhs)

Provides the rote copy constructor.

keystroke & operator= (const keystroke &rhs)

Provides the rote principal assignment operator.

• bool is_press () const

'Getter' function for member m_is_press

• bool is letter (int ch=SEQ64 KEYSTROKE BAD VALUE) const

'Getter' function for member m_key to test letters, handles ASCII only.

· bool is delete () const

m_key to test for a delete-causing key.

· unsigned int key () const

'Getter' function for member m_key

• seq_modifier_t modifier () const

'Getter' function for member m modifier

bool mod_control () const

'Getter' function for member m modifier tested for Ctrl key.

· bool mod control shift () const

'Getter' function for member m_modifier tested for Ctrl and Shift key.

bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

bool m_is_press

Determines if the key was a press or a release.

unsigned int m_key

The key that was pressed or released.

seq_modifier_t m_modifier

The optional modifier value.

10.25.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

10.25.2 Constructor & Destructor Documentation

10.25.2.1 seq64::keystroke::keystroke (unsigned int key, bool press = SEQ64_KEYSTROKE_PRESS, int modkey = int (SEQ64_NO_MASK))

Parameters

key	The keystroke number of the key that was pressed or released.
press	If true, the keystroke action was a press, otherwise it was a release.
modkey	The modifier key combination that was pressed, if any, in the form of a bit-mask, as defined
	in the gdk_basic_keys module. Common mask values are SEQ64_SHIFT_MASK, SEQ64←
	_CONTROL_MASK, SEQ64_MOD1_MASK, and SEQ64_MOD4_MASK. If no modifier, this
	value is SEQ64_NO_MASK.

10.25.2.2 seq64::keystroke::keystroke (const keystroke & rhs)

Parameters

rhs	The object to be copied.

10.25.3 Member Function Documentation

10.25.3.1 keystroke & seq64::keystroke::operator= (const keystroke & rhs)

Parameters

rhs	The object to be assigned.

Returns

Returns the reference to the current object, for use in assignment chains.

10.25.3.2 bool seq64::keystroke::is_letter (int ch = SEQ64_KEYSTROKE_BAD_VALUE) const

Parameters

ch	An optional character to test as an ASCII letter.

Returns

If a character is not provided, true is returned if it is an upper or lower-case letter. Otherwise, true is returned if the m_key value matches the character case-insensitively.

Tricky Code

10.25.4 Field Documentation

10.25.4.1 bool seq64::keystroke::m_is_press [private]

See the SEQ64_KEYSTROKE_PRESS and SEQ64_KEYSTROKE_RELEASE readability macros.

10.25.4.2 unsigned int seq64::keystroke::m_key [private]

Generally, the extended ASCII range (0 to 255) is supported. However, Gtk-2.x/3.x will generally support the full gamut of characters defined in the gdk_basic_keys.h module. We define minimum and maximum range macros for keystrokes that are a bit generous.

10.25.4.3 seq_modifier_t seq64::keystroke::m_modifier [private]

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

10.26 seq64::lash Class Reference

This class supports LASH operations, if compiled with LASH support (i.e.

Public Member Functions

lash (perform &p, int argc, char **argv)

This constructor calls lash_extract(), using the command-line arguments, if SEQ64_LASH_SUPPORT is enabled.

• void set_alsa_client_id (int id)

Make ourselves a LASH ALSA client.

• void start ()

Process any LASH events every 250 msec, which is an arbitrarily chosen interval.

• bool process_events ()

Process LASH events.

Private Member Functions

· bool init ()

Initializes LASH support, if enabled.

void handle_event (lash_event_t *conf)

Handle a LASH event.

• void handle_config (lash_config_t *conf)

Handle a LASH configuration item.

Private Attributes

• perform & m perform

A hook into the single perform object in the application.

10.26.1 Detailed Description

SEQ64_LASH_SUPPORT is defined). All of the #ifdef skeleton work is done in this class in such a way that any other part of the code can use this class whether or not lash support is actually built in; the functions will just do nothing.

10.26.2 Constructor & Destructor Documentation

10.26.2.1 seq64::lash::lash (perform & p, int argc, char ** argv)

We fixed the crazy usage of argc and argv here and in the client code in the seq24 module.

Parameters

р	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

10.26.3 Member Function Documentation

10.26.3.1 void seq64::lash::set_alsa_client_id (int id)

/param id The ALSA client ID to be set.

10.26.3.2 bool seq64::lash::process_events()

Returns

Always returns true.

10.26.3.3 bool seq64::lash::init() [private]

Returns

Returns true if the LASH subsystem was able to be initialized, and a LASH client representative (m_client) was allocated.

10.26.3.4 void seq64::lash::handle_event(lash_event_t * ev) [private]

Parameters

ev	Provides the event to be handled.

 $\textbf{10.26.3.5} \quad \textbf{void} \ \textbf{seq64::lash::handle_config(lash_config_t*conf}) \quad \texttt{[private]}$

Currently incomplete.

Parameters

conf	Provides the configuration item to handle.

10.27 seq64::maintime Class Reference

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

Inheritance diagram for seq64::maintime:



Public Member Functions

• maintime (perform &p, int ppqn=SEQ64_USE_DEFAULT_PPQN)

This constructor sets up the colors black, white, and grey, and then allocates them.

Private Member Functions

int idle_progress (midipulse ticks)

This function clears the window, sets the foreground to black, draws the "time" window's rectangle, and then draws a rectangle for noting the progress of the beat, and the progress for a bar.

· void on realize ()

Handles realization of the window.

bool on_expose_event (GdkEventExpose *ev)

This function merely idles.

Private Attributes

• const int m_beat_width

Provides the divisor for ticks to produce a beat value.

· const int m bar width

Provides the divisor for ticks to produce a bar value.

• const int m_pill_width

Provides the width of the pills, little black squares that show the progress of a beat and a bar (measure).

const int m_box_width

The width/length of the rectangle to be drawn inside the maintime window.

· const int m box height

The height of the rectangle to be drawn inside the maintime window.

· const int m flash width

The width/length of the flashing rectangle to be drawn inside the maintime window.

· const int m_flash_height

The height of the flashing rectangle to be drawn inside the maintime window.

· const int m flash x

The x value at which a flash should occur.

· const int m box less pill

The width/length of the maintime window minus the width of the pill.

· midipulse m tick

Saves the tick value for on_expose_event().

• int m_ppqn

Provides the active PPQN value.

Additional Inherited Members

10.27.1 Detailed Description

We added a lot of members to hold the results of calculations that involve what are essentially constant. This saves CPU time, and maybe a little memory for the code to make those calculations more than once.

10.27.2 Constructor & Destructor Documentation

10.27.2.1 seq64::maintime::maintime (perform & p, int ppqn = SEQ64_USE_DEFAULT_PPQN)

In the constructor you can only allocate colors; get_window() would return 0 because the windows has not yet been realized.

10.27.3 Member Function Documentation

10.27.3.1 int seq64::maintime::idle_progress (midipulse *ticks*) [private]

Idle hands do the devil's work. We should eventually support some generic coloring for "dark themes". The default coloring is better for "light themes".

Parameters

ticks Provides the main tick setting. This setting is provided by mainwnd(), in its timer callback.

Returns

Always returns 1 (it used to return "true"!).

```
10.27.3.2 void seq64::maintime::on_realize( ) [private]
```

It performs the base class's on_realize() function. It then allocates some additional resources: a window, a GC (?), and it clears the window. Then it sets the default size of the window, specified by GUI constructor parameters.

```
10.27.3.3 bool seq64::maintime::on_expose_event( GdkEventExpose * a_e ) [private]
```

We don't need the m_tick member, the function works as well if 0 is passed in. We've removed m_tick permanently.

Actually, it might be useful after all, to avoid flickering under JACK transport. Let's put it back for now. (It doesn't help, but we will leave it in, the overhead is small.)

10.27.4 Field Documentation

```
10.27.4.1 const int seq64::maintime::m_beat_width [private]
```

Currently, this value is hardwired to 4, but will eventually be wired up as usr().midi_beat_width().

```
10.27.4.2 const int seq64::maintime::m_bar_width [private]
```

Currently, this value is hardwired to 16, but will eventually be wired up as usr().midi_beat_width() * usr().midi_\circ
beats_per_bar().

```
10.27.4.3 const int seq64::maintime::m_box_width [private]
```

This item absolutely depends on the main window being non-resizable.

```
10.27.4.4 const int seq64::maintime::m_box_height [private]
```

This item absolutely depends on the main window being non-resizable.

```
10.27.4.5 const int seq64::maintime::m_flash_width [private]
```

Just a bit smaller than m_box_width.

```
10.27.4.6 const int seq64::maintime::m_flash_height [private]
```

Just a bit smaller than m_box_width.

```
10.27.4.7 midipulse seq64::maintime::m_tick [private]
```

It might actually be useful after all. And the overhead is tiny.


10.27.4.8 int seq64::maintime::m_ppqn [private]

While this is effectively a constant for the duration of a tune, it might change as different tunes are loaded.

10.28 seq64::mainwid Class Reference

This class implement the piano roll area of the application.

Inheritance diagram for seq64::mainwid:



Public Member Functions

· mainwid (perform &p)

This constructor sets a lot of the members, but not all.

~mainwid ()

A rote destructor.

void set_screenset (int ss)

Set the current screen-set.

Private Member Functions

· virtual void redraw (int seq)

This virtual function, overridden from the seqmenu base class, draws the the given pattern/sequence again.

· void reset ()

This function redraws everything and queues up a redraw operation.

• void draw_marker_on_sequence (int seq, int tick)

Does the actual drawing of one pattern/sequence position marker, a vertical progress bar.

void update_sequences_on_window ()

Updates the image of multiple sequencers.

· void update markers (int ticks)

Draw the cursors (long vertical bars) on each sequence, so that they follow the playing progress of each sequence in the mainwid (Patterns Panel.)

bool valid_sequence (int seq)

Common-code helper function.

void draw_sequence_on_pixmap (int seq)

This function draws a specific pattern/sequence on the pixmap located in the main window of the application, the Patterns Panel.

void draw_sequences_on_pixmap ()

This function fills the pixmap with sequences.

void fill_background_window ()

This function updates the background window, clearing it.

void draw_pixmap_on_window ()

This function queues the blit of pixmap to window.

void draw_sequence_pixmap_on_window (int seq)

This function draws a sequence pixmap in the Patterns Panel.

int seq_from_xy (int x, int y)

Translates XY coordiinates in the Patterns Panel to a sequence number.

• int timeout ()

Provides a stock callback, because some kind of callback is need.

void calculate_base_sizes (int seq, int &basex, int &basey)

Provides a way to calculate the base x and y size values for the pattern map.

void on_realize ()

For this GTK callback, on realization of window, initialize the shiz.

• bool on_expose_event (GdkEventExpose *ev)

Implements the GTK expose event callback.

• bool on_button_press_event (GdkEventButton *ev)

Handles a press of a mouse button.

bool on_button_release_event (GdkEventButton *ev)

Handles a release of a mouse button.

• bool on_motion_notify_event (GdkEventMotion *p0)

Handle the motion of the mouse if a mouse button is down and in another sequence and if the current sequence is not in edit mode.

bool on_focus_in_event (GdkEventFocus *)

Handles an on-focus event.

bool on_focus_out_event (GdkEventFocus *)

Handles an out-of-focus event.

Private Attributes

• int m_mainwnd_rows

These values are assigned to the values given by the constants of similar names in globals.h, and we will make them parameters later.

· int m screenset slots

Provides a convenience variable for avoiding multiplications.

· int m screenset offset

Provides a convenience variable for avoiding multiplications.

Additional Inherited Members

10.28.1 Constructor & Destructor Documentation

10.28.1.1 seg64::mainwid::mainwid (perform & p)

And it asks for a size of c_mainwid_x by c_mainwid_y. It adds GDK masks for button presses, releases, and motion, and key presses and focus changes.

Parameters

p Provides the reference to the all-important perform object.

10.28.2 Member Function Documentation

10.28.2.1 void seq64::mainwid::set_screenset (int ss)

Parameters

a ss Provides the screen-set number to set.

10.28.2.2 void seq64::mainwid::redraw(int seqnum) [private], [virtual]

Parameters

seqnum Provides the number of the sequence to draw.

Implements seq64::segmenu.

10.28.2.3 void seq64::mainwid::draw_marker_on_sequence(int seqnum, int tick) [private]

If the sequence has no events, this function doesn't bother even drawing a position marker.

Note that, when Sequencer64 first comes up, and perform::is_dirty_main() is called, no sequences exist yet.

Parameters

seqnum	Provides the number of the sequence to draw.
tick	Provides the location to draw the marker.

10.28.2.4 void seq64::mainwid::update_markers (int ticks) [private]

Parameters

ticks	Starting point for drawing the markers
lichs	Starting point for drawing the markers.

10.28.2.5 bool seq64::mainwid::valid_sequence(int seqnum) [private]

Parameters

seqnum	Provides the number of the sequence to validate.

Returns

Returns true if the sequence number is valid for the current m_screenset value.

10.28.2.6 void seq64::mainwid::draw_sequence_on_pixmap(int seqnum) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset).

Also, we now ignore the sequence if it does not exist. :-D

Note

If only the main window is up, then the sequences just play (muted by default) – the progress bars move in each pattern. Gaps in the sequence in the Song (performance) Editor don't change the appearance of the patterns if only the main window is up. But, if the Song Editor window is up, and the song is started using the controls in the Song Editor, then the active patterns are black while playing, and white when gaps in the sequence are encountered. The muting status in the main window is ignored. The muting in the Song (performance) windows is in force.

Parameters

aaanum	Provides the number of the sequence slot that needs to be drawn.
sequani	Provides the number of the sequence slot that needs to be drawn.

10.28.2.7 void seq64::mainwid::draw_sequences_on_pixmap() [private]

Please note that draw_sequence_on_pixmap() also draws the empty slots of inactive sequences, so we cannot take shortcuts here.

10.28.2.8 void seq64::mainwid::draw_sequence_pixmap_on_window(int seqnum) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset. This function is used when dragging a pattern from one pattern-slot to another pattern-slot.

We have to add 1 pixel to the y height in order to avoid leaving behind a line at the bottom of an empty pattern-slot.

Parameters

seqnu	ım	Provides the number of the sequence to draw.

10.28.2.9 int seq64::mainwid::seq_from_xy(int x, int y) [private]

Parameters

a_x	Provides the x coordinate.
a_y	Provides the y coordinate.

Returns

Returns -1 if the sequence number cannot be calculated.

10.28.2.10 int seq64::mainwid::timeout() [private]

Todo We should use this callback to display the current time in the playback.

Returns

Always returns true.

10.28.2.11 void seq64::mainwid::calculate_base_sizes (int seqnum, int & basex, int & basey) [private]

The values are returned as side-effects.

Parameters

seqnum	Provides the number of the sequence to calculate.
basex	A return parameter for the x coordinate of the base size.
basey	A return parameter for the y coordinate of the base size.

10.28.2.12 void seq64::mainwid::on_realize() [private]

It allocates any additional resources that weren't initialized in the constructor.

This function used to call font::init(), and was the only place where the font::init() function was called. The init() function gets a color-map from the window. We need a more fool-proof was to do this!

10.28.2.13 bool seq64::mainwid::on_expose_event(GdkEventExpose * ev) [private]

Parameters

ev	The expose event.

Returns

Always returns true.

10.28.2.14 bool seq64::mainwid::on_button_press_event (GdkEventButton * p) [private]

If the press is a single left-click, and no Ctrl key is pressed, then this function grabs the focus, calculates the pattern/sequence over which the button press occurred, and sets the m_button_down flag if it is over a pattern. In the release event callback, this then causes the sequence arming/muting to be toggled.

If the press is a single Ctrl-left-click, this function brings up the New or Edit menu. The New menu is brought up if the grid slot is empty, and the Edit menu otherwise. Another way to bring up the same functionality is described in the next paragraph.

If the press is a double-click, it first acts just like two single-clicks (which might confuse the user at first). Then it brings up the Edit menu for the sequence. This new behavior is closer to what users have come to expect from a double-click.

We also handle a Ctrl-double-click as a signal to do an event edit, instead of a sequence edit. The event editor provides a way to look at all events in detail, without having to select the type of event to see.

Parameters

p Provides the parameters of the button event.

Returns

Always returns true.

10.28.2.15 bool seq64::mainwid::on_button_release_event (GdkEventButton * p) [private]

This event is a lot more complex than a press. The left button toggles playback status. The right button brings up a popup menu. If the slot is empty, then a "New" popup is presented, otherwise an "Edit" and selection popup is presented.

Parameters

Provides the parameters of the button event.

Returns

Always returns true.

10.28.2.16 bool seq64::mainwid::on_motion_notify_event(GdkEventMotion * p) [private]

This function moves the selected pattern to another pattern slot.

The perform::delete_sequence() function sets the perform modification flag.

Parameters

p | Provides the parameters of the button event.

Returns

Always returns true.

10.28.2.17 bool seq64::mainwid::on_focus_in_event(GdkEventFocus*) [private]

Just sets the Gtk::HAS FOCUS flag.

Returns

Always returns false.


10.28.2.18 bool seq64::mainwid::on_focus_out_event(GdkEventFocus *) [private] Just unsets the Gtk::HAS_FOCUS flag. Returns Always returns false. 10.28.3 Field Documentation 10.28.3.1 int seq64::mainwid::m_screenset_slots [private] It is equally to m_mainwnd_rows * m_mainwnd_cols. 10.28.3.2 int seq64::mainwid::m_screenset_offset [private]

It is equally to m_screenset_slots * m_screenset.

10.29 seq64::mainwnd Class Reference

This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.

Inheritance diagram for seq64::mainwnd:



Public Member Functions

- mainwnd (perform &a_p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT_PPQN)

 The constructor the main window of the application.
- \sim mainwnd ()

This destructor must explicitly delete some allocated resources.

void open_file (const std::string &)

Opens and parses (reads) a MIDI file.

• int ppqn () const

'Getter' function for member m ppgn

void ppqn (int ppqn)

'Setter' function for member m_ppqn We can't set the PPQN value when the mainwnd is created, we have to do it later, using this function.

Private Member Functions

· void file import dialog ()

Presents a file dialog to import a MIDI file.

· void options dialog ()

Opens the File / Options dialog.

void about_dialog ()

Presents a Help / About dialog.

void adj_callback_ss ()

This function is the callback for adjusting the screen-set value.

void adj callback bpm ()

This function is the callback for adjusting the BPM value.

void edit_callback_notepad ()

A callback function for handling an edit to the screen-set notepad.

• bool timer callback ()

This function is the GTK timer callback, used to draw our current time and BPM on_events (the main window).

• void start_playing ()

Starts playing of the song.

void stop_playing ()

Stops the playing of the song.

• void learn_toggle ()

Toggle the group-learn status.

void open_performance_edit ()

Opens the Performance Editor (Song Editor).

void open_performance_edit_2 ()

Opens the second Performance Editor (Song Editor).

void enregister_perfedits ()

This function brings together the two perfedit objects, so that they can tell each other when to queue up a draw operation.

void sequence_key (int seq)

Use the sequence key to toggle the playing of an active pattern in the current screen-set.

void update_window_title ()

Updates the title shown in the title bar of the window.

void toLower (std::string &)

Converts a string to lower-case letters.

void file_new ()

A callback function for the File / New menu entry.

• void file open ()

A callback function for the File / Open menu entry.

• void file save ()

A callback function for the File / Save menu entry.

• void file save as ()

A callback function for the File / Save As menu entry.

• void file_exit ()

A callback function for the File / Exit menu entry.

• void new_file ()

Actually does the work of setting up for a new file.

• bool save file ()

Saves the current state in a MIDI file.

void choose file ()

Creates a file-chooser dialog.

int query_save_changes ()

Queries the user to save the changes made while the application was running.

· bool is_save ()

If the data is modified, then the user is queried, and the file is save if okayed.

• bool install_signal_handlers ()

Installs the signal handlers and pipe code.

• bool signal_action (Glib::IOCondition condition)

Handles saving or exiting actions when signalled.

bool on_delete_event (GdkEventAny *a_e)

This callback function handles a delete event from ...?

bool on_key_press_event (GdkEventKey *a_ev)

Handles a key press event.

bool on_key_release_event (GdkEventKey *a_ev)

Handles a key release event.

virtual void on_grouplearnchange (bool state)

Notification handler for learn mode toggle.

Static Private Member Functions

• static void handle_signal (int sig)

This function is the handler for system signals (SIGUSR1, SIGINT...) It writes a message to the pipe and leaves as soon as possible.

Private Attributes

• Gtk::MenuBar * m_menubar

Theses objects support the menu and its sub-menus.

• int m_ppqn

Saves the PPQN value obtained from the MIDI file (or the default value, the global ppqn, if SEQ64_USE_DEFAUL

→ T PPQN was specified in reading the MIDI file.

• mainwid * m_main_wid

The biggest sub-components of mainwnd.

• maintime * m_main_time

Is this the bar at the top that shows moving squares?

perfedit * m_perf_edit

A pointer to the song/performance editor.

perfedit * m_perf_edit_2

A pointer to an optional second song/performance editor.

• options * m_options

A pointer to the program options.

• Gdk::Cursor m_main_cursor

Mouse cursor?

• Gtk::Button * m_button_learn

This button is the learn button, otherwise known as the "L" button.

Gtk::Button * m_button_stop

Implements the red square stop button.

• Gtk::Button * m_button_play

Implements the green triangle play button.

• Gtk::Button * m_button_perfedit

The button for bringing up the Song Editor (Performance Editor).

• Gtk::SpinButton * m spinbutton bpm

The spin/adjustment controls for the BPM (beats-per-minute) value.

• Gtk::SpinButton * m_spinbutton_ss

The spin/adjustment controls for the screen set value.

Gtk::SpinButton * m spinbutton load offset

The spin/adjustment controls for the load offset value.

Gtk::Entry * m_entry_notes

What is this?

sigc::connection m timeout connect

Provides a timeout handler.

Static Private Attributes

• static int m_sigpipe [2]

Interesting; what is this used for.

Additional Inherited Members

10.29.1 Constructor & Destructor Documentation

10.29.1.1 seq64::mainwnd::mainwnd(perform & p, bool allowperf2 = true, int ppqn = SEQ64_USE_DEFAULT_PPQN

This constructor is way too large; it would be nicer to provide a number of well-named initialization functions.

Parameters

р	Refers to the main performance object.
allowperf2	Indicates if a second perfedit window should be created. This is currently a run-time option,
	selectable in the "user" configuration file.

Todo Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

View menu items and their hot keys.

View menu items and their hot keys.

Help menu items

Top panel items, including the logo (updated for the new version of this application) and the "timeline" progress bar.

10.29.2 Member Function Documentation

10.29.2.1 void seq64::mainwnd::open_file (const std::string & fn)

We leave the ppqn parameter set to the SEQ64_USE_DEFAULT for now, to preserve the legacy behavior of using the global ppqn, and scaling the running time against the PPQN read from the MIDI file. Later, we can provide a value like 0, that will certainly be changed by reading the MIDI file.

We don't need to specify the "oldformat" or "global sequence" parameters of the midifile constructor when reading the MIDI file, since reading handles both the old and new formats, dealing with new constructs only if they are present in the file.

Parameters

fn Provides the file-name for the MIDI file to be opened.

```
10.29.2.2 void seq64::mainwnd::ppqn ( int ppqn ) [inline]
m_ppqn = choose_ppqn(ppqn);
10.29.2.3 void seq64::mainwnd::file_import_dialog( ) [private]
```

Note that every track of the MIDI file will be imported, even if the track is only a label track (without any MIDI events), or a very long track.

The main difference between the Open operation and the Import operation seems to be that the latter can read MIDI files into a screen-set greater than screen-set 0. No, that's not true, so far. No matter what the current screen-set setting, the import is appended after the current data in screen-set 0. Then, if it overflows that screen-set, the overflow goes into the next screen-set.

It might be nice to have the option of importing a MIDI file into a specific screen-set, for better organization, as well as being able to offset the sequence number.

Also, it is important to note that perf().clear_all() is not called by this routine, as we are merely adding to what might already be there.

```
10.29.2.4 void seq64::mainwnd::about_dialog( ) [private]
```

I (Chris) took the liberty of tacking my name at the end, and hope to eventually have done enough work to warrant having it there.

```
10.29.2.5 void seq64::mainwnd::adj_callback_ss( ) [private]
```

Sets the screen-set value in the Performance/Song window, the Patterns, and something about setting the text based on a screen-set notepad from the Performance/Song window.

Let the perform object keep track of modifications.

Screen-set notepad?

```
10.29.2.6 void seq64::mainwnd::adj_callback_bpm( ) [private]
```

Let the perform object keep track of modifications.

```
10.29.2.7 void seq64::mainwnd::edit_callback_notepad( ) [private]
```

Let the perform object keep track of modifications.

```
10.29.2.8 bool seq64::mainwnd::timer_callback( ) [private]
```

Note

When Sequencer64 first starts up, and no MIDI tune is loaded, the call to mainwid::update_markers() leads to trying to do some work on sequences that don't yet exist. Also, if a sequence is changed by the event editor, we get a crash; need to find out how sequence away with the changes.

```
10.29.2.9 void seq64::mainwnd::start_playing( ) [inline], [private]
```

The rc_settings::jack_start_mode() function is used (if jack is running) to determine if the playback mode is "live" (false) or "song" (true). An accessor to perform::start_playing().

Note

This overrides the old behavior of playing live mode if the song is started from the main window.

```
10.29.2.10 void seq64::mainwnd::stop_playing() [inline], [private]
```

An accessor to perform::stop playing().

```
10.29.2.11 void seq64::mainwnd::open_performance_edit( ) [private]
```

We will let perform keep track of modifications, and not just set an is-modified flag just because we opened the song editor. We're going to centralize the modification flag in the perform object, and see if it can work.

```
10.29.2.12 void seq64::mainwnd::open_performance_edit_2( ) [private]
```

Experiment: open a second one and see what happens. It works, but one needs to tell the other to redraw if a change is made.

```
10.29.2.13 void seq64::mainwnd::update_window_title( ) [private]
```

Note that the name of the application is obtained by the "(SEQ64_PACKAGE)" construction.

The format of the caption bar is the name of the package/application, followed by the file-specification (shortened if necessary so that the name of the file itself can be seen), ending with the PPQN value in parentheses.

```
10.29.2.14 void seq64::mainwnd::new_file( ) [private]
```

Not sure that we need to clear the modified flag here, especially since it is now centralizeed in the perform object. Let perf().clear_all() handle it now.

```
10.29.2.15 bool seq64::mainwnd::save_file( ) [private]
```

Here we specify the current value of m_ppqn, which was set when reading the MIDI file. We also let midifile tell the perform that saving worked, so that the "is modified" flag can be cleared. The midifile class is already a friend of perform.

```
10.29.2.16 bool seq64::mainwnd::signal_action ( Glib::IOCondition condition ) [private]
```

Returns

Returns true if the signalling was able to be completed, even if it was an unexpected signal.

```
10.29.2.17 bool seq64::mainwnd::on_delete_event( GdkEventAny * a_e ) [private]
```

Any changed data is saved. If the pattern is playing, then it is stopped.

```
10.29.2.18 bool seq64::mainwnd::on_key_press_event ( GdkEventKey * ev ) [private]
```

It also handles the control-key and modifier-key combinations matching the entries in its list of if statements.

Todo Test this functionality in old and new application.

```
10.29.2.19 bool seq64::mainwnd::on_key_release_event( GdkEventKey * ev ) [private]
```

Is this worth turning into a switch statement? Or offloading to a perform member function? The latter.

Todo Test this functionality in old and new application.

Returns

Always returns false.

```
10.29.2.20 void seq64::mainwnd::on_grouplearnchange ( bool state ) [private], [virtual]
```

This handler responds to a learn-mode change from perf().

Reimplemented from seq64::performcallback.

10.29.3 Field Documentation

```
10.29.3.1 int seq64::mainwnd::m_sigpipe [static],[private]
```

This static member provides a couple of pipes for signalling/messaging.

```
10.29.3.2 int seq64::mainwnd::m_ppqn [private]
```

We need it early here to be able to pass it along to child objects.

```
10.29.3.3 mainwid* seq64::mainwnd::m_main_wid [private]
```

The first is the Patterns Panel.


```
10.29.3.4 Gtk::SpinButton* seq64::mainwnd::m_spinbutton_load_offset [private]
```

However, where is this button located? It is handled in the code, but I've never seen the button!

10.30 seq64::midi_container Class Reference

This class is the abstract base class for a container of MIDI track information.

Inheritance diagram for seq64::midi_container:



Public Member Functions

midi_container (sequence &seq)

Fills in the few members of this class.

virtual ∼midi_container ()

A rote constructor needed for a base class.

void fill (int tracknumber)

This function fills the given track (sequence) with MIDI data from the current sequence, preparatory to writing it to a file.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

• virtual bool done () const

Instead of checking for the size of the container when "emptying" it [see the midifile::write() function], use this function, which is overridden to match the type of container being used.

• virtual void put (midibyte b)=0

Provides a way to add a MIDI byte into the container.

• virtual midibyte get ()=0

Provide a way to get the next byte from the container.

Protected Member Functions

· unsigned int position () const

Returns the current position.

Private Member Functions

• void add variable (midipulse v)

This function masks off the lower 8 bits of the long parameter, then shifts it right 7, and, if there are still set bits, it encodes it into the buffer in reverse order.

void add long (midipulse x)

What is the difference between this function and add_list_var()?

Private Attributes

• sequence & m_sequence

Provide a hook into a sequence so that we can exchange data with a sequence object.

unsigned int m_position_for_get

Provides the position in the container when making a series of get() calls on the container.

10.30.1 Member Function Documentation

```
10.30.1.1 void seq64::midi_container::fill ( int tracknumber )
```

Note that some of the events might not come out in the same order they were stored in (we see that with program-change events).

This function replaces sequence::fill_container().

Now, for sequence 0, an alternate format for writing the sequencer number chunk is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assume to increment. This application doesn't use with that shortcut.

Triggers:

```
Triggers are added by first calling add_variable(0), which is needed because why? Then 0xFF 0x7F is written, followed by the length value, which is the number of triggers at 3 long integers per trigger, plus the 4-byte code for triggers, c_triggers_new = 0x24240008.
```

Not threadsafe The sequence object bound to this container needs to provide the locking mechanism when calling this function.

Parameters

tracknumber | Provides the track number. This number is masked into the track information.

```
10.30.1.2 virtual void seq64::midi_container::put ( midibyte b ) [pure virtual]
```

The original seg24 container used an std::list and a push front operation.

Implemented in seq64::midi_list, and seq64::midi_vector.

10.30.1.3 virtual midibyte seq64::midi_container::get() [pure virtual] It also increments m_position_for_get. Implemented in seq64::midi_list, and seq64::midi_vector. 10.30.1.4 unsigned int seq64::midi_container::position() const [inline], [protected] Before the return, the position counter is incremented to the next position. 10.30.1.5 void seq64::midi_container::add_variable (midipulse ν) [private] This function "replaces" sequence::add_list_var(). 10.30.1.6 void seq64::midi_container::add_long (midipulse x) [private]


This function "replaces" sequence::add_long_list().

This was a *global* internal function called addLongList(). Let's at least make it a private member now, and hew to the naming conventions of this class.

10.31 seq64::midi_list Class Reference

This class is the std::list implementation of the midi_container.

Inheritance diagram for seq64::midi_list:



Public Member Functions

• midi list (sequence &seq)

This constructor fills in the members.

virtual ∼midi_list ()

A rote constructor needed for a base class.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

• virtual bool done () const

For popping data from the MIDI list, we are done when the container is empty.

virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

· virtual midibyte get ()

Provide a way to get the next byte from the container.

Private Types

typedef std::list< midibyte > CharList
 Provides the type of this container.

Private Attributes

CharList m_char_list

The container itself.

Additional Inherited Members

10.31.1 Member Typedef Documentation

```
10.31.1.1 typedef std::list<midibyte> seq64::midi_list::CharList [private]
```

This type is basically the same as the container used in the midifile module, and almost identical to the CharList type defined in the sequence module.

10.31.2 Member Function Documentation

```
10.31.2.1 virtual void seq64::midi_list::put( midibyte b ) [inline], [virtual]
```

The original seq24 list used an std::list and a push_front operation.

Implements seq64::midi_container.

```
10.31.2.2 virtual midibyte seq64::midi_list::get( ) [inline], [virtual]
```

In this implementation, m_position_for_get is not used. The elements of the container are popped off backward! Implements seq64::midi container.

10.32 seq64::midi_measures Class Reference

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b←:d").

Public Member Functions

• midi_measures ()

Default constructor for midi_measures.

• midi_measures (int measures, int beats, int divisions)

Principal constructor for midi_measures.

• int measures () const

'Getter' function for member m_measures

• void measures (int m)

'Setter' function for member m_measures We can add validation later.

· int beats () const

'Getter' function for member m beats

void beats (int b)

'Setter' function for member m_beats We can add validation later.

· int divisions () const

'Getter' function for member m_divisions

· void divisions (int d)

'Setter' function for member m divisions We can add validation later.

Private Attributes

• int m_measures

The integral number of measures in the measures-based time.

· int m beats

The integral number of beats in the measures-based time.

• int m_divisions

The integral number of divisions/pulses in the measures-based time.

10.32.1 Field Documentation

10.32.1.1 int seq64::midi_measures::m_divisions [private]

There are two possible translations of the two bytes of a division. If the top bit of the 16 bits is 0, then the time division is in "ticks per beat" (or "pulses per quarter note"). If the top bit is 1, then the time division is in "frames per second". This function deals only with the ticks/beat definition.

10.33 seq64::midi_splitter Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

• midi_splitter (int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

~midi_splitter ()

A rote destructor.

• bool log_main_sequence (sequence &seq, int seqnum)

Logs the main sequence (an SMF 0 track) for later usage in splitting the track.

• void initialize ()

Resets the SMF 0 support variables in preparation for parsing a new MIDI file.

· void increment (int channel)

Processes a channel number by raising its flag in the m_smf0_channels[] array.

bool split (perform &p, int screenset)

This function splits an SMF 0, splitting all of the channels in the sequence out into separate sequences, and adding each to the perform object.

• int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

· int count () const

'Getter' function for member m_smf0_channels_count

Private Member Functions

bool split channel (const sequence &main seq, sequence *seq, int channel)

This function splits the given sequence into new sequences, one for each channel found in the SMF 0 track.

Private Attributes

• int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.

bool m_use_default_ppqn

Indicates that the default PPQN is in force.

· int m_smf0_channels_count

Provides support for SMF 0, indicates how many channels were found in the file in a single sequence.

• bool m_smf0_channels [16]

Provides support for SMF 0, holds a bool value that indicates the occurrence of a given channel.

• sequence * m_smf0_main_sequence

Provides support for SMF 0, points to the initial SMF 0 sequence, from which the single-channel sequences will be created.

• int m_smf0_seq_number

Provides support for SMF 0, holds the prospective sequence number of the main (SMF 0) sequence.

10.33.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

10.33.2 Constructor & Destructor Documentation

10.33.2.1 seq64::midi_splitter::midi_splitter(int ppqn = SEQ64_USE_DEFAULT_PPQN)

Parameters

name	Provides the name of the MIDI file to be read or written.
ppqn	Provides the initial value of the PPQN setting. It is handled differently for parsing (reading)
	versus writing the MIDI file.
	Reading.
	 If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used.
	The m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the MIDI file, ppqn, is then use to scale the running-time of the sequence relative to DEFAULT_PPQN.
	 Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
	 Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller must query for the PPQN set during parsing, and pass it to the constructor when preparing to write the file. See how it is done in the mainwand class.

oldformat	If true, write out the MIDI file using the old Seq24 format, instead of the new MIDI-compliant sequencer-specific format, for the seq24-specific SeqSpec tags defined in the globals module. This option is false by default. Note that this option is only used in writing; reading can handle either format transparently.
globalbgs	If true, write any non-default values of the key, scale, and background sequence to the global "proprietary" section of the MIDI file, instead of to each sequence. Note that this option is only used in writing; reading can handle either format transparently.

10.33.3 Member Function Documentation

10.33.3.1 void seq64::midi_splitter::increment (int channel)

If it is the first entry for that channel, m_smf0_channels_count is incremented. We won't check the channel number, to save time, until someday we segfault :-D

10.33.3.2 bool seq64::midi_splitter::split (perform & p, int screenset)

Lastly, it adds the SMF 0 track as the last track; the user can then examine it before removing it. Is this worth the effort?

There is a little oddity, in that, if the SMF 0 track has events for only one channel, this code will still create a new sequence, as well as the main sequence. Not sure if this is worth extra code to just change the channels on the main sequence and put it into the correct track for the one channel it contains.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded. Returns false if no SMF 0 main sequence was logged.

```
10.33.3.3 int seq64::midi_splitter::ppqn( ) const [inline]
```

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midi_splitter constructor.

```
10.33.3.4 bool seq64::midi_splitter::split_channel ( const sequence & main_seq, sequence * s, int channel )

[private]
```

Note that the events that are read from the MIDI file have delta times. Sequencer64 converts these delta times to cumulative times. We need to preserve that here. Conversion back to delta times is needed only when saving the sequences to a file. This is done in midi container::fill().

We have to accumulate the delta times in order to be able to set the length of the sequence in pulses.

Luckily, we don't have to worry about copying triggers, since the imported SMF 0 track won't have any Seq24/← Sequencer24 triggers.

It doesn't set the sequence number of the sequence; that is set when the sequence is added to the perform object.

Parameters

main_seq	This parameter is the whole SMF 0 track that was read from the MIDI file. It contains all of
	the channel data that needs to be split into separate sequences.
S	Provides the new sequence that needs to have its settings made, and all of the selected
	channel events added to it.
channel	Provides the MIDI channel number (re 0) that marks the channel data the needs to be ex-
	tracted and added to the new sequence.

Returns

Returns true if at least one event got added. If none were added, the caller should delete the sequence object represented by parameter *s*.

10.33.4 Field Documentation

10.33.4.1 int seq64::midi_splitter::m_smf0_channels_count [private]

SMF 1 file parsing will only warn about more than one channel found in a given sequence.

10.33.4.2 bool seq64::midi_splitter::m_smf0_channels[16] [private]

Obviously, we don't have to worry about multiple MIDI busses.

10.33.4.3 int seq64::midi_splitter::m_smf0_seq_number [private]

We want to be able to add that sequence last, for easier and cleaner removal of that sequence by the user.

10.34 seq64::midi_timing Class Reference

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

Public Member Functions

• midi_timing ()

Defaults constructor for midi_timing.

• midi_timing (int bpminute, int bpmeasure, int beatwidth, int ppqn)

Principal constructor for midi_timing.

• int beats_per_minute () const

'Getter' function for member m_beats_per_minute

void beats_per_minute (int b)

'Setter' function for member m_beats_per_minute We can add validation later.

• int beats_per_measure () const

'Getter' function for member m_beats_per_measure

void beats_per_measure (int b)

'Setter' function for member m_beats_per_measure We can add validation later.

int beat_width () const

'Getter' function for member m_beats_per_beat_width

void beat_width (int bw)

'Setter' function for member m_beats_per_beat_width We can add validation later.

• int ppqn () const

'Getter' function for member m_ppqn

• void ppqn (int p)

'Setter' function for member m_ppqn We can add validation later.

Private Attributes

• int m_beats_per_minute

This value should match the BPM value selected when editing the song.

· int m beats per measure

This value should match the numerator value selected when editing the sequence.

int m beat width

This value should match the denominator value selected when editing the sequence.

int m_ppqn

This value provides the precision of the MIDI song.

10.34.1 Detailed Description

Although Seq24/Sequencer64 currently are heavily dependent on hard-wired values, that will be rectified eventually, so let us get ready for it.

10.34.2 Field Documentation

```
10.34.2.1 int seq64::midi_timing::m_beats_per_minute [private]
```

This value is most commonly set to 120, but is also read from the MIDI file. This value is needed if one want to calculate durations in true time units such as seconds, but is not needed to calculate the number of pulses/ticks/divisions.

```
10.34.2.2 int seq64::midi_timing::m_beats_per_measure [private]
```

This value is most commonly set to 4.

```
10.34.2.3 int seq64::midi_timing::m_beat_width [private]
```

This value is most commonly set to 4, meaning that the fundamental beat unit is the quarter note.


```
10.34.2.4 int seq64::midi_timing::m_ppqn [private]
```

This value is most commonly set to 192, but is also read from the MIDI file. We are still working getting "non-standard" values to work.

10.35 seq64::midi_vector Class Reference

This class is the std::vector implementation of the midi_container.

Inheritance diagram for seq64::midi_vector:



Public Member Functions

• midi vector (sequence &seq)

This constructor fills in the members.

virtual ∼midi_vector ()

A rote constructor needed for a base class.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

• virtual bool done () const

For iterating through the data in the MIDI vector, we are done when we've gotten the last element of the container.

virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

· virtual midibyte get ()

Provide a way to get the next byte from the container.

Private Types

typedef std::vector< midibyte > CharVector
 Provides the type of this container.

Private Attributes

CharVector m_char_vector

The container itself.

Additional Inherited Members

10.35.1 Member Function Documentation

```
10.35.1.1 virtual void seq64::midi_vector::put( midibyte b ) [inline], [virtual]
```

The original seq24 list used an std::list and a push_front operation.

Implements seq64::midi_container.

```
10.35.1.2 virtual midibyte seq64::midi_vector::get( ) [inline], [virtual]
```

In this implementation, m_position_for_get is used.

Implements seq64::midi_container.

10.36 seq64::midibus Class Reference

Provides a class for handling the MIDI buss on Linux.

Public Member Functions

```
• ∼midibus ()
```

A rote empty destructor.

bool init_out ()

Initialize the MIDI output port.

• bool init_in ()

Initialize the MIDI input port.

• bool deinit_in ()

Deinitialize the MIDI input?

• bool init_out_sub ()

Initialize the output in a different way?

• bool init_in_sub ()

Initialize the output in a different way?

• void print ()

Prints m_name.

const std::string & get_name () const

'Getter' function for member n_name

• int get id () const

'Getter' function for member m_id

• void play (event *e24, midibyte channel)

This play() function takes a native event, encodes it to ALSA event, and puts it in the queue.

void sysex (event *e24)

Takes a native SYSEX event, encodes it to an ALSA event, and then puts it in the queue.

• void start ()

This function gets the MIDI clock a-runnin', if the clock type is not e_clock_off.

• void stop ()

Stop the MIDI buss.

void clock (midipulse tick)

Generates the MIDI clock, starting at the given tick value.

• void continue_from (midipulse tick)

Continue from the given tick.

· void init clock (midipulse tick)

Initialize the clock, continuing from the given tick.

void set_clock (clock_e clocktype)

'Setter' function for member m_clock_type

clock_e get_clock () const

'Getter' function for member m_clock_type

void set_input (bool inputing)

Input functions.

bool get_input () const

'Getter' function for member m_inputing

· void flush ()

Flushes our local queue events out into ALSA.

· int get_client () const

'Getter' function for member m_dest_addr_client The address of client.

int get_port () const

'Getter' function for member m_dest_addr_port

Static Public Member Functions

static void set_clock_mod (int clockmod)

Set the clock mod to the given value, if legal.

static int get_clock_mod ()

Get the clock mod.

Private Attributes

• int m id

The ID of the midibus object.

clock_e m_clock_type

The type of clock to use.

bool m_inputing

TBD.

• int m_ppqn

Provides the PPQN value in force, currently a constant.

• const int m_dest_addr_client

Destination address of client.

· const int m_dest_addr_port

Destination port of client.

· const int m_local_addr_client

Local address of client.

• int m_local_addr_port

Local port of client.

• int m_queue

Another ID of the MIDI queue?

• std::string m_name

The name of the MIDI buss.

• midipulse m_lasttick

The last (most recent? final?) tick.

• mutex m_mutex

Locking mutex.

Static Private Attributes

• static int m_clock_mod

This is another name for "16 * 4".

Friends

· class mastermidibus

The master MIDI bus sets up the buss.

10.36.1 Member Function Documentation

```
10.36.1.1 bool seq64::midibus::init_out()
```

Returns

Returns true unless setting up ALSA MIDI failed in some way.

```
10.36.1.2 bool seq64::midibus::init_in ( )
```

Returns

Returns true unless setting up ALSA MIDI failed in some way.

```
10.36.1.3 bool seq64::midibus::deinit_in()
```

Returns

Returns true, unless an error occurs.

```
10.36.1.4 bool seq64::midibus::init_out_sub( )
```

Returns

Returns true unless setting up the ALSA port failed in some way.

10.36.1.5 bool seq64::midibus::init_in_sub()

Returns

Returns true unless setting up the ALSA port failed in some way.

10.36.1.6 void seq64::midibus::play (event * e24, midibyte channel)

Threadsafe

Parameters

e24	The event to be played on this bus.
channel	The channel of the playback.

10.36.1.7 void seq64::midibus::sysex (event * e24)

Parameters

e24 The event to be handled.

10.36.1.8 void seq64::midibus::clock (midipulse tick)

Parameters

tick	Provides the starting tick.
------	-----------------------------

10.36.1.9 void seq64::midibus::continue_from (midipulse tick)

Parameters

tick The continuing tick.	
---------------------------	--

10.36.1.10 void seq64::midibus::init_clock (midipulse tick)

Parameters

tick	The starting tick.

10.36.1.11 void seq64::midibus::set_input (bool inputing)

Set status to of "inputting" to the given value.

If the parameter is true, then init_in() is called; otherwise, deinit_in() is called.

Parameters

inputing	The inputing value to set.

10.37 seq64::midifile Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

 midifile (const std::string &name, int ppqn=SEQ64_USE_DEFAULT_PPQN, bool oldformat=false, bool globalbgs=true)

Principal constructor.

∼midifile ()

A rote destructor.

• bool parse (perform &a_perf, int a_screen_set=0)

This function opens a binary MIDI file and parses it into sequences and other application objects.

• bool write (perform &a perf)

Write the whole MIDI data and Seq24 information out to the file.

• const std::string & error_message () const

'Getter' function for member m error message

· bool error_is_fatal () const

'Getter' function for member m_error_is_fatal

• int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

Private Member Functions

bool parse_smf_0 (perform &p, int screenset)

This function parses an SMF 0 binary MIDI file as if it were an SMF 1 file, then, if more than one MIDI channel was encountered in the sequence, splits all of the channels in the sequence out separate sequences, and deletes the original sequence.

bool parse smf 1 (perform &p, int screenset, bool is smf0=false)

This function parses an SMF 1 binary MIDI file; it is basically the original seq25 midifile::parse() function.

• midilong parse_prop_header (int file_size)

Parse the proprietary header, figuring out if it is the new format, or the legacy format, for sequencer-specific data.

bool parse_proprietary_track (perform &a_perf, int file_size)

After all of the conventional MIDI tracks are read, we're now at the "proprietary" Seq24 data section, which describes the various features that Seq24 supports.

• int pow2 (int logbase2)

Internal function for simple calculation of a power of 2 without a lot of math.

• bool checklen (midilong len, midibyte type)

Internal function to check for and report a bad length value.

• midilong read_long ()

Reads 4 bytes of data using read_byte().

midishort read_short ()

Reads 2 bytes of data using read_byte().

• midibyte read byte ()

Reads 1 byte of data directly from the m_data vector, incrementing m_pos after doing so.

midilong read_varinum ()

Read a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

void write_long (midilong)

Writes 4 bytes, using the write_byte() function.

void write_short (midishort)

Writes 2 bytes, using the write_byte() function.

void read_byte_array (midibyte *b, int len)

A helper function to simplify reading midi_control data from the MIDI file.

void write_byte (midibyte c)

Writes 1 byte.

void write_varinum (midilong)

Writes a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

void write_track_name (const std::string &trackname)

Writes out a track name.

std::string read_track_name ()

Reads the track name.

• void write_seq_number (midishort seqnum)

Writes out a sequence number.

int read_seq_number ()

Reads the sequence number.

• void write track end ()

Writes out the end-of-track marker.

void write_prop_header (midilong tag, long len)

We want to write:

bool write_proprietary_track (perform &a_perf)

Writes out the proprietary section, using the new format if the legacy format is not in force.

· long varinum_size (long len) const

Calculates the length of a variable length value.

· long prop_item_size (long datalen) const

Calculates the size of a proprietary item, as written by the write_prop_header() function, plus whatever is called to write the data.

• long track_name_size (const std::string &trackname) const

Calculates the size of a trackname and the meta event that specifies it.

void errdump (const std::string &msg)

Helper function to emit more useful error messages.

void errdump (const std::string &msg, unsigned long p)

Helper function to emit more useful error messages for erroneous long values.

• long seq_number_size () const

Returns the size of a sequence-number event, which is always 5 bytes, plus one byte for the delta time that precedes it

long track_end_size () const

Returns the size of a track-end event, which is always 3 bytes.

bool is_sysex_special_id (midibyte ch)

Check for special SysEx ID byte.

Private Attributes

• int m file size

Holds the size of the MIDI file.

std::string m_error_message

Holds the last error message, useful for trouble-shooting without having Sequencer64 running in a console window.

· bool m error is fatal

Indicates if the error should be considered fatal.

bool m_disable_reported

Indicates that file reading has already been disabled (due to serious errors), so don't complain about it anymore.

• int m pos

Holds the position in the MIDI file.

const std::string m_name

The unchanging name of the MIDI file.

• $std::vector < midibyte > m_data$

This vector of characters holds our MIDI data.

std::list< midibyte > m_char_list

Provides a list of characters.

bool m_new_format

Use the new format for the proprietary footer section of the Seq24 MIDI file.

• bool m_global_bgsequence

Indicates to store the new key, scale, and background sequence in the global, "proprietary" section of the MIDI song.

• int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.

• bool m_use_default_ppqn

Indicates that the default PPQN is in force.

• midi_splitter m_smf0_splitter

Provides support for SMF 0.

10.37.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

10.37.2 Constructor & Destructor Documentation

10.37.2.1 seq64::midifile::midifile (const std::string & name, int ppqn = SEQ64_USE_DEFAULT_PPQN, bool oldformat = false, bool globalbgs = true)

Parameters

name	Provides the name of the MIDI file to be read or written.
ppqn	Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file.
	Reading.
	 If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the MIDI file, ppqn, is then use to scale the running-time of the sequence relative to DEFAULT_PPQN.
	 Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
	 Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller must query for the PPQN set during parsing, and pass it to the constructor when preparing to write the file. See how it is done in the mainwand class.

oldformat	If true, write out the MIDI file using the old Seq24 format, instead of the new MIDI-compliant
	sequencer-specific format, for the seq24-specific SeqSpec tags defined in the globals mod-
	ule. This option is false by default. Note that this option is only used in writing; reading can
	handle either format transparently.
globalbgs	If true, write any non-default values of the key, scale, and background sequence to the global
	"proprietary" section of the MIDI file, instead of to each sequence. Note that this option is
	only used in writing; reading can handle either format transparently.

10.37.3 Member Function Documentation

10.37.3.1 bool seq64::midifile::parse (perform & p, int screenset = 0)

In addition to the standard MIDI track data in a normal track, Seq24 adds four sequencer-specific events just before the end of the track:

```
c_triggers_new: SeqSpec FF 7F 1C 24 24 00 08 00 00 ...
c_midibus: SeqSpec FF 7F 05 24 24 00 01 00
c_timesig: SeqSpec FF 7F 06 24 24 00 06 04 04
c_midich: SeqSpec FF 7F 05 24 24 00 02 06
```

Standard MIDI provides for the port and channel specifications, but they are apparently considered obsolete:

Obsolete meta-event: Replacement:

```
MIDI port (buss): FF 21 01 po Device (port) name: FF 09 len text MIDI channel: FF 20 01 ch
```

What do other applications use for specifying port/channel?

Note on the is-modified flag. We now assume that the perform object is starting from scratch when parsing. But we let mainwind tell the perform object when to clear everything with perform:clear_all(). The mainwind does this for a new file, opening a file, but not for a file import, which might be done simply to add more MIDI tracks to the current composition. So, if parsing succeeds, all we want to do is make sure the flag is set.

Parsing a file successfully is not always a modification of the setup. For instance, the first read of a MIDI file should start clean, not dirty.

SysEx notes:

Some files (e.g. Dixie04.mid) do not always encode System Exclusive messages properly for a MIDI file. Instead of a varinum length value, they are followed by extended IDs (0x7D, 0x7E, or 0x7F).

We've covered some of those cases by disabling access to m_data if the position passes the size of the file, but we want try to bypass these odd cases properly. So we look ahead for one of these special values.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file. This value
	ranges from -31 to 0 to +31 (32 is the maximum screen-set available in Seq24). This offset is
	added to the sequence number read in for the sequence, to place it elsewhere in the imported
	tune, and locate it in a specific screen-set. If this parameter is non-zero, the we will assume
	that the perform data is dirty.

Returns

Returns true if the parsing succeeded.

10.37.3.2 bool seq64::midifile::write (perform & p)

Parameters

р	Provides the object that will contain and manage the entire performance.

Returns

Returns true if the write operations succeeded.

Note

Seq24 reverses the order of some events, due to popping from its container. Not an issue here.

```
10.37.3.3 int seq64::midifile::ppqn() const [inline]
```

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midifile constructor.

10.37.3.4 bool seq64::midifile::parse_smf_0 (perform & p, int screenset) [private]

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded.

```
10.37.3.5 bool seq64::midifile::parse_smf_1 ( perform & p, int screenset, bool is_smf0 = false ) [private]
```

It assumes the file-data has already been read into memory. It also assumes that the ID, track-length, and format have already been read.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded.

```
10.37.3.6 midilong seq64::midifile::parse_prop_header( int file_size ) [private]
```

The new format creates a final track chunk, starting with "MTrk". Then comes the delta-time (here, 0), and the event. An event is a MIDI event, a SysEx event, or a Meta event.

A MIDI Sequencer Specific meta message includes either a delta time or absolute time, and the MIDI Sequencer Specific event encoded as follows:

```
0x00 0xFF 0x7F length data
```

For convenience, this function first checks the amount of file data left. If enough, then it reads a long value. If the value starts with 0×00 0xFF 0x7F, then that is a SeqSpec event, which signals usage of the new

Sequencer64 "proprietary" format. Otherwise, it is probably the old format, and the long value is a control tag (0x242400nn), which can be returned immedidately.

If it is the new format, we back up to the FF, then get the next byte, which should be a 7F. If so, then we read the length (a variable length value) of the data, and then read the long value, which should be the control tag, which, again, is returned by this function.

Note

Most sequencers seem to be tolerant of both the lack of an "MTrk" marker and of the presence of an unwrapped control tag, and so can handle both the old and new formats of the final proprietary track.

Parameters

file_size	The size of the data file. This value is compared against the member m_pos (the position
	inside m_data[]), to make sure there is enough data left to process.

Returns

Returns the control-tag value found. These are the values, such as c_midich, found in the globals module, that indicate the type of sequencer-specific data that comes next. If there is not enough data to process, then 0 is returned.

10.37.3.7 bool seq64::midifile::parse_proprietary_track(perform & p, int file_size) [private]

It consists of series of tags:

- · c midictrl
- · c midiclocks
- · c notes
- · c bpmtag (beats per minute)
- c_mutegroups
- · c_musickey (new, added if usr() global_seq_feature() is true)
- c musicscale (ditto)
- c_backsequence (ditto)

(There are more tags defined in the globals module, but they are not used in this function. This doesn't quite make sense, as there are also some "triggers" values, and we're pretty sure the application uses them. Oh, it turns out that they are set up by actions performed on each sequence, and are stored as sequencer-specific ("SeqSpec") data with each track's data as held in the MIDI container for the track. See the midi_container module for more information.)

The format is (1) tag ID; (2) length of data; (3) the data.

First, we separate out this function for a little more clarity. Then we added code to handle reading both the legacy Seq24 format and the new, MIDI-compliant format. Note that even the new format is not quite correct, since it doesn't handle a MIDI manufacturer's ID, making it a single byte that is part of the data. But it does have the "MTrk" marker and track name, so that must be processed for the new format.

Now, in our "midicvt" project, we have a test MIDI file, b4uacuse-non-mtrk.midi that is good, except for having a tag "MUnk" instead of "MTrk". We should consider being more permissive, if possible. Otherwise, though, the only penality is that the "proprietary" chunk is completely skipped.

Parameters

р	The performance object that is being set via the incoming MIDI file.
file_size	The file size as determined in the parse() function.

There are also implicit parameters, with the m_pos and m_new_format member variables.

```
10.37.3.8 int seq64::midifile::pow2 (int logbase2) [private]
```

Use for calculating the denominator of a time signature.

Parameters

logbase2	Provides the power to which 2 is to be raised. This integer is probably only rarely greater than
	4 (which represents a denominator of 16).

Returns

Returns 2 raised to the logbase2 power.

```
10.37.3.9 midilong seq64::midifile::read_long( ) [private]
```

Warning

This code looks endian-dependent and integer-size dependent.

```
10.37.3.10 midilong seq64::midifile::read_varinum( ) [private]
```

This function reads the bytes while bit 7 is set in each byte. Bit 7 is a continuation bit. See write_varinum() for more information.

```
10.37.3.11 void seq64::midifile::write_long( midilong a_x ) [private]
```

Warning

This code looks endian-dependent.

```
10.37.3.12 void seq64::midifile::write_short ( midishort a_x ) [private]
```

Warning

This code looks endian-dependent.

10.37.3.13 void seq64::midifile::read_byte_array(midibyte * b, int len) [inline], [private]

Parameters

	b	The byte array to receive the data.
ĺ	len	The number of bytes in the array, and to be read.

```
10.37.3.14 void seq64::midifile::write_byte( midibyte c) [inline], [private]
```

The byte is written to the m_char_list member, using a call to push_back().

```
10.37.3.15 void seq64::midifile::write_varinum ( midilong value ) [private]
```

A MIDI file Variable Length Value is stored in bytes. Each byte has two parts: 7 bits of data and 1 continuation bit. The highest-order bit is set to 1 if there is another byte of the number to follow. The highest-order bit is set to 0 if this byte is the last byte in the VLV.

To recreate a number represented by a VLV, first you remove the continuation bit and then concatenate the leftover bits into a single number.

To generate a VLV from a given number, break the number up into 7 bit units and then apply the correct continuation bit to each byte.

In theory, you could have a very long VLV number which was quite large; however, in the standard MIDI file specification, the maximum length of a VLV value is 5 bytes, and the number it represents can not be larger than 4 bytes.

Here are some common cases:

```
Numbers between 0 and 127 (0x7F) are represented by a single byte.
0x80 is represented as "0x81 0x00".
0x0FFFFFFFF (the largest number) is represented as "0xFF 0xFF 0xFF".
```

Also see the varinum_size() function.

```
10.37.3.16 void seq64::midifile::write track name ( const std::string & trackname ) [private]
```

Note that we have to precede this "event" with a delta time value, set to 0.

```
10.37.3.17 std::string seq64::midifile::read_track_name( ) [private]
```

Meant only for usage in the proprietary footer track, in the new file format.

Returns

Returns the track name, or an empty string if there was a problem.

```
10.37.3.18 void seq64::midifile::write_seq_number( midishort seqnum ) [private]
```

The format is "00 FF 00 02 ss ss", where "02" is actually the constant length of the data. We have to precede these values with a 0 delta time, of course.

Now, for sequence 0, an alternate format is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assumed to increment. Our application doesn't bother with that shortcut.

```
10.37.3.19 int seq64::midifile::read_seq_number( ) [private]
```

Meant only for usage in the proprietary footer track, in the new file format.

Returns

Returns the sequence number found, or -1 if it was not found.

10.37.3.20 void seq64::midifile::write_prop_header(midilong control_tag, long data_length) [private]

- 0x4D54726B. The track tag "MTrk". The MIDI spec requires that software can skip over non-standard chunks. "Prop"? Would require a fix to midicvt.
- 0xaabbccdd. The length of the track. This needs to be calculated somehow.
- 0x00. A zero delta time.
- 0x7f7f. Sequence number, a special value, well out of normal range.
- · The name of the track:
 - "Seq24-Spec"
 - "Sequencer64-S"

Then follows the proprietary data, written in the normal manner. Finally, tack on the track-end meta-event. Components of final track size:

```
-# Delta time. 1 byte, always 0x00.

-# Sequence number. 5 bytes. OPTIONAL. We won't write it.

-# Track name. 3 + 10 or 3 + 15

-# Series of proprietary specs:

-# Prop header:

-# If legacy format, 4 bytes.

-# Otherwise, 2 bytes + varinum_size(length) + 4 bytes.

-# Length of the prop data.

-# Track End. 3 bytes.
```

Writes a "proprietary" Seq24 footer header in either the new MIDI-compliant format, or the legacy Seq24 format. This function does not write the data. It replaces calls such as "write_long(c_midich)" in the proprietary secton of write().

The legacy format just writes the control tag (0x242400xx). The new format writes 0x00 0xFF 0x7F len 0x242400xx; the first 0x00 is the delta time.

In the new format, the 0x24 is a kind of "manufacturer ID". At http://www.midi.org/techspecs/manid. \leftarrow php we see that most manufacturer IDs start with 0x00, and are thus three bytes long, or start with codes at 0x40 and above. Similary, this site shows that no manufacturer uses 0x24:

```
http://sequence15.blogspot.com/2008/12/midi-manufacturer-ids.html
```

Warning

Currently, the manufacturer ID is not handled; it is part of the data, which can be misleading in programs that analyze MIDI files.

Parameters

control_tag	Determines the type of sequencer-specific section to be written. It should be one of the value
	in the globals module, such as c_midibus or c_mutegroups.
data_length	The amount of data that will be written. This parameter does not count the length of the
	header itself.

```
10.37.3.21 bool seq64::midifile::write_proprietary_track( perform & p ) [private]
```

The first thing to do, for the new format only, is calculate the length of this big section of data. This was quite tricky; we tweaked and adjusted until the midicvt program handled the whole new-format file without emitting any errors. Here's the basics of what Seq24 did for writing the data in this part of the file:

- -# Write the c_midictrl value, then write a 0. To us, this looks like no one wrote any code to write this data. And yet, the parsing code can handles a non-zero value, which is the number of sequences as a long value, not a byte. So shouldn't we write 4 bytes, not one? Yes, indeed, we made a mistake. However, we should be writing out the full data set as well. But not even Seq24 does that! Perhaps they decided it was best kept in the "rc" configuration file.
- -# MORE TO COME.

```
10.37.3.22 long seq64::midifile::varinum_size ( long len ) const [private]
```

This function is needed when calculating the length of a track. Note that it handles only the following situations:

https://en.wikipedia.org/wiki/Variable-length_quantity

```
1 byte: 0x00 to 0x7F
2 bytes: 0x80 to 0x3FFF
3 bytes: 0x4000 to 0x001FFFFF
4 bytes: 0x200000 to 0x0FFFFFFF
```

Returns

Returns values as noted above. Anything beyond that range returns 0.

```
10.37.3.23 long seq64::midifile::prop_item_size ( long data_length ) const [private]
```

If using the new format, the length includes the sum of sequencer-specific tag (0xFF 0x7F) and the size of the variable-length value. Then, for legacy and new format, 4 bytes are added for the Seq24 MIDI control value, and then the data length is added.

10.37.3.24 void seq64::midifile::errdump (const std::string & msg) [private]

It adds the file offset to the message.

Parameters

msg	The main error message string, without an ending newline character.

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

10.37.3.25 void seq64::midifile::errdump (const std::string & msg, unsigned long value) [private]

It adds the file offset to the message.

Parameters

msg	The main error message string, without an ending newline character.
value	The long value to show as part of the message.

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

10.37.3.26 bool seq64::midifile::is_sysex_special_id(midibyte ch) [inline], [private]

Parameters

ch Provides the byte to be checked against 0x7D through 0x7F.

Returns

Returns true if the byte is SysEx special ID.

10.37.4 Field Documentation

```
10.37.4.1 int seq64::midifile::m_file_size [private]
```

This variable was added when loading a file that caused an attempt to load data well beyond the file-size of the midicvt test file Dixie04.mid.

```
10.37.4.2 std::string seq64::midifile::m_error_message [private]
```

If empty, there's no pending error. Currently most useful in the parse() function.

```
10.37.4.3 bool seq64::midifile::m_error_is_fatal [private]
```

The caller can query for this value after getting the return value from parse().

```
10.37.4.4 bool seq64::midifile::m_disable_reported [private]
```

Once is enough.

```
10.37.4.5 int seq64::midifile::m_pos [private]
```

This is at least a 31-bit value in the recent architectures running Linux and Windows, so it will handle up to 2 Gb of data. This member is used as the offset into the m_data vector.

```
10.37.4.6 std::vector<midibyte> seq64::midifile::m_data [private]
```

We could also use a string of characters, unsigned. This member is resized to the putative size of the MIDI file, in the parse() function. Then the whole file is read into it, as if it were an array. This member is an input buffer.

```
10.37.4.7 std::list<midibyte> seq64::midifile::m_char_list [private]
```

The class pushes each MIDI byte into this list using the write_byte() function. Also note that the write() function calls sequence::fill_list() to fill a temporary std::list<char> (!) buffer, then writes that data *backwards* to this member. This member is an output buffer.

```
10.37.4.8 bool seq64::midifile::m_new_format [private]
```


In the new format, each sequencer-specific value (0x242400xx, as defined in the globals module) is preceded by the sequencer-specific prefix, 0xFF 0x7F len id/date). By default, the new format is used, but the user can specify the —legacy (-I) option, or make a soft link to the sequence24 binary called "seq24", to write the data in the old format. [We will eventually add the —legacy option to the "rc" configuration file.] Note that reading can handle either format transparently.

10.37.4.9 midi_splitter seq64::midifile::m_smf0_splitter [private]

This object holds all of the information needed to split a multi-channel sequence.

10.38 seq64::mutex Class Reference

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex. Inheritance diagram for seq64::mutex:



Public Member Functions

• mutex ()

The constructor assigns the recursive mutex to the local locking mutex.

· void lock () const

Lock the mutex.

· void unlock () const

Unlock the mutex.

Protected Attributes

• pthread mutex t m mutex lock

Provides a mutex lock usable by a single module or class.

Static Private Attributes

static const pthread_mutex_t sm_recursive_mutex

Provides a way to disable the locking.

10.38.1 Field Documentation

```
10.38.1.1 const pthread_mutex_t seq64::mutex::sm_recursive_mutex [static], [private]
```

Define the static recursive mutex and its condition variable.

Mostly experimental, we want to disable locking to see if we can speed up MIDI file reading when the application is compiled for debugging. It takes about 8 seconds to read our sample MIDI files. This does not solve the problem of the long MIDI-file parsing, however.

```
static bool sm_mutex_enabled;
```

Provides a recursive mutex that can be used by the whole application, apparently.

10.39 seq64::options Class Reference

This class supports a full tabbed options dialog.

Inherits Dialog.

Private Types

```
    enum button {
    e_jack_transport,
    e_jack_master,
    e_jack_master_cond,
    e_jack_start_mode_live,
    e_jack_start_mode_song,
    e_jack_connect,
    e_jack_disconnect }
```

Private Attributes

perform & m_mainperf

The performance object to which some of these options apply.

• Gtk::Button * m_button_ok

The famous "OK" button's pointer.

• Gtk::CheckButton * m_button_jack_transport

Main JACK transport selection.

• Gtk::CheckButton * m_button_jack_master

Main JACK transport master selection.

• Gtk::CheckButton * m_button_jack_master_cond

Main JACK transport master-conditional selection.

• Gtk::Notebook * m_notebook

Not sure yet what this notebook is for.

10.39.1 Member Enumeration Documentation

10.39.1.1 enum seq64::options::button [private]

Enumerator

e_jack_transport Defines buttons indices or IDs for some controls related to JACK. These values are handled in options::transport_callback(). Some of them set JACK-related values in the rc_settings object, while the others set up or tear down the JACK support of sequencer24.

The JACK Transport settings are a little messy. They should be radio buttons, and control each other's settings. Currently, if the user wants to set up for JACK Master, the JACK Transport button must also be checked.

```
Turns on the "with JACK Transport" option,
rc_settings::with_jack_transport().
```

- e_jack_master Turns on the "with JACK Master" option, rc_settings::with_jack_master(). If another application is already JACK Master, this will fail.
- e_jack_master_cond Turns on the "with JACK Master" option rc_settings::with_jack_master_cond(). This option makes sequencer64 the JACK Master conditionally, that is, if no other application has claimed that role.
- e_jack_start_mode_live Doesn't directly do anything; the live mode versus song mode is set by the e_jack
 _start_mode_song value.
- e_jack_start_mode_song Sets the "JACK start mode" value to true, which means that sequencer64 is in song mode. This value is obtained via rc_settings::jack_start_mode().
- **e_jack_connect** Causes the perform object's JACK initialization function, perform::init_jack(), to be called.
- **e_jack_disconnect** Causes the perform object's JACK deinitialization function, perform::deinit_jack(), to be called.

10.39.2 Field Documentation


10.39.2.1 Gtk::Notebook* seq64::options::m_notebook [private]

Must be a GTK thang.

10.40 seq64::optionsfile Class Reference

Provides a file for reading and writing the application' main configuration file.

Inheritance diagram for seq64::optionsfile:



Public Member Functions

• optionsfile (const std::string &name)

Principal constructor.

• \sim optionsfile ()

A rote destructor.

• bool parse (perform &perf)

Parse the \sim /.seq24rc or \sim /.config/sequencer64/sequencer64.rc file.

bool write (const perform &perf)

This options-writing function is just about as complex as the options-reading function.

Additional Inherited Members

10.40.1 Detailed Description

The settings that are passed around are provided or used by the perform class.

10.40.2 Member Function Documentation

10.40.2.1 bool seq64::optionsfile::parse (perform & p) [virtual]

[midi-control]

Get the number of sequence definitions provided in the [midi-control] section. Ranges from 32 on up. Then read in all of the sequence lines. The first 32 apply to the first screen set. There can also be a comment line "# mute in group" followed by 32 more lines. Then there are addditional comments and single lines for BPM up, BPM down, Screen Set Up, Screen Set Down, Mod Replace, Mod Snapshot, Mod Queue, Mod Gmute, Mod Glearn, and Screen Set Play. These are all forms of MIDI automation useful to control the playback while not sitting near the computer.

[mute-group]

The mute-group starts with a line that indicates up to 32 mute-groups are defined. A common value is 1024, which means there are 32 groups times 32 keys. But this value is currently thrown away. This value is followed by 32 lines of data, each contained 4 sets of 8 settings. See the seq24-doc project on GitHub for a much more detailed description of this section.

[midi-clock]

The MIDI-clock section defines the clocking value for up to 16 output busses. The first number, 16, indicates how many busses are specified. Generally, these busses are shown to the user with names such as "[1] seq24 1".

[keyboard-control]

The keyboard control defines the keys that will toggle the stage of each of up to 32 patterns in a pattern/sequence box. These keys are displayed in each box as a reminder. The first number specifies the Key number, and the second number specifies the Sequence number.

[keyboard-group]

The keyboard group specifies more automation for the application. The first number specifies the Key number, and the second number specifies the Group number. This section should be better described in the seq24-doc project on GitHub.

[jack-transport]

This section covers various JACK settings, one setting per line. In order, the following numbers are specfied:

```
    jack_transport - Enable sync with JACK Transport.
    jack_master - Seq24 will attempt to serve as JACK Master.
    jack_master_cond - Seq24 will fail to be Master if there is already a Master set.
    jack_start_mode:

            0 = Playback will be in Live mode. Use this to allow muting and unmuting of loops.
            1 = Playback will use the Song Editor's data.
```

[midi-input]

This section covers the MIDI input busses, and has a format similar to "[midi-clock]". Generally, these busses are shown to the user with names such as "[1] seq24 1", and currently there is only one input buss. The first field is the port number, and the second number indicates whether it is disabled (0), or enabled (1).

[midi-clock-mod-ticks]

This section covers.... One common value is 64.

[manual-alsa-ports]

This section covers.... Set to 1 if you want seq24 to create its own ALSA ports and not connect to other clients.

[last-used-dir]

This section simply holds the last path-name that was used to read or write a MIDI file. We still need to add a check for a valid path, and currently the path must start with a "/", so it is not suitable for Windows.

[interaction-method]

This section specified the kind of mouse interaction.

- 0 = 'seq24' (original Seq24 method).
- 1 = 'fruity' (similar to a certain fruity sequencer we like).

The second data line is set to "1" if Mod4 can be used to keep seq24 in note-adding mode even after the right-clic is released, and "0" otherwise.	:k
mplements seq64::configfile.	

10.40.2.2 bool seq64::optionsfile::write (const perform & p) [virtual]

Parameters

p Provides a const reference to the main perform object. However, we have to cast away the constness, because too many of the perform getter functions are used in non-const contexts.

Returns

Returns true if the write operations all succeeded.


New boolean to show sequence numbers; ignored in legacy mode.

Implements seq64::configfile.

10.41 seq64::perfedit Class Reference

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

Inheritance diagram for seq64::perfedit:



Public Member Functions

- perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAULT_PPQN)

 Principal constructor, has a reference to a perform object.
- \sim perfedit ()

This rote constructor does nothing.

• void init_before_show ()

This function forwards its call to the perfroll function of the same name.

• void enqueue_draw (bool forward=true)

Helper wrapper for calling perfroll::queue_draw() for one or both perfedits.

void enregister_peer (perfedit *peer)

Register the peer perfedit object.

Private Member Functions

void set_beats_per_bar (int bpm)

Sets the beats-per-measure text and value to the given value, and then calls set_guides().

void set beat width (int bw)

Sets the BW (beat width, or the denominator in the time signature) text and values to the given value, and then calls set_guides().

void set_snap (int snap)

Sets the snap text and values to the given value, and then calls set_guides().

· void set_guides ()

Sets the guides, which are the L and R user-interface elements.

• void grow ()

Increments the size of the perfroll and perftime objects.

void set_looped ()

Set the looping in the perform object.

• void expand ()

Implement the expand action.

· void collapse ()

Implement the collapse action.

· void copy ()

Implement the copy (actually, expand-and-copy) action.

• void undo ()

Implement the undo feature (Ctrl-Z).

• void popup_menu (Gtk::Menu *menu)

Opens the given popup menu.

• bool timeout ()

Handles a drawing timeout.

void start_playing ()

Implement the playing.

• void stop_playing ()

Stop the playing.

• void on_realize ()

This callback function calls the base-class on_realize() function, and then connects the perfedit::timeout() function to the Glib signal-timeout, with a redraw timeout of m_redraw_ms.

• bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on delete event (GdkEventAny *)

All this callback function does is return false.

Private Attributes

perfedit * m_peer_perfedit

The partner instance of perfedit.

• Gtk::Table * m_table

A whole horde of GUI elements.

Gtk::Menu * m_menu_bpm

Menus for time signature, beats per measure, beat width.

• int m snap

Set snap-to in "pulses".

• int m_bpm

The current "beats per measure" value.

• int m bw

The current "beat width" value.

• int m_ppqn

The current "parts per quarter note" value.

int m_standard_bpm

The standard "beats per measure" of Sequencer64, which here matches the beats-per-measure displayed in the perfroll (piano roll).

• int m_redraw_ms

Provides the timer period for the perfedit timer, used to determine the rate of redrawing.

Additional Inherited Members

10.41.1 Detailed Description

It has a segroll and piano roll? No, it has a perform, a perfnames, a perfroll, and a perftime.

10.41.2 Constructor & Destructor Documentation

```
10.41.2.1 seq64::perfedit::perfedit ( perform & p, bool second_perfedit = false, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Parameters

p | Refers to the main performance object.

Todo Offload most of the work into an initialization function like options does.

```
10.41.2.2 seq64::perfedit::~perfedit()
```

We're going to have to run the application through valgrind to make sure that nothing is left behind.

10.41.3 Member Function Documentation

```
10.41.3.1 void seq64::perfedit::init_before_show()
```

It does not seem to need to also forward to the perftime function of the same name.

10.41.3.2 void seq64::perfedit::enqueue_draw (bool forward = true)

Parameters

forward	If true (the default), pass the call to the peer. When passing this call to the peer, this parameter
	is set to false to prevent an infinite loop and the resultant stack overflow.

```
10.41.3.3 void seq64::perfedit::enregister_peer ( perfedit * peer ) [inline]
```

This function is meant to be called by mainwind, which creates the perfedits and then makes sure they get along.

```
10.41.3.4 void seq64::perfedit::set_beats_per_bar(int bpm) [private]
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

```
10.41.3.5 void seq64::perfedit::set_beat_width(int bw) [private]
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

```
10.41.3.6 void seq64::perfedit::set_guides( ) [private]
```

See the set snap() function.

It's a little confusing; I assigned the label "m_standard_bpm" to the value 4 in "measure_pulse = $192 * 4 * m_bpm / m_bw$ ", but I am not sure I understand this equation... why the extra factor of 4? That 4 appears in "c_ppqn * 4" a lot in the original code.

```
10.41.3.7 void seq64::perfedit::grow( ) [private]
```

Make sure that setting the modified flag makes sense for this operation. It doesn't seem to modify members.

```
10.41.3.8 void seq64::perfedit::expand( ) [private]
```

This action opens up a space of events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, moving its triggers, and telling the perfroll to redraw.

```
10.41.3.9 void seq64::perfedit::collapse( ) [private]
```

This action removes all events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, not moving its triggers (they go away), and telling the perfoll to redraw.

```
10.41.3.10 void seq64::perfedit::copy( ) [private]
```

This action opens up a space of events between the L and R (left and right) markers, and copies the information from the same amount of events that follow the R marker. This action is preceded by pushing an Undo operation in the perform object, copying its triggers, and telling the perfroll to redraw.

```
10.41.3.11 void seq64::perfedit::undo() [private]
```

We pop an Undo trigger, and then ask the perfroll to queue up a (re)drawing action.

```
10.41.3.12 bool seq64::perfedit::timeout() [private]
```

It redraws "dirty" sequences in the perfroll and the perfnames objects, and shows draw progress on the perfroll. This function is called frequently and continuously. It will work for both perfedit windows, if both are up.

```
10.41.3.13 void seq64::perfedit::start_playing() [inline], [private]
```

JACK will be used if it is present and, in the application, enabled. This call also sets rc().is_pattern_playing(true), indirectly. Note that, if the JACK-start-mode value is false, the perfedit's unmute/mute feature is disabled. We no longer hardwire the boolean parameter to "true". (We might reconsider that at some point.)

```
10.41.3.14 void seq64::perfedit::stop_playing() [inline], [private]
```

This call also sets rc().is_pattern_playing(true).

10.41.4 Field Documentation

```
10.41.4.1 int seq64::perfedit::m_bpm [private]
```

Do not confuse it with BPM (beats per minute). The numerator of the time signature.

```
10.41.4.2 int seq64::perfedit::m_bw [private]
```

The denominator of the time signature.


```
10.41.4.3 int seq64::perfedit::m_redraw_ms [private]
```

This is hardwired to 40 ms in Linux, and 20 ms in Windows.

10.42 seq64::perfnames Class Reference

This class implements the left-side keyboard in the patterns window.

Inheritance diagram for seq64::perfnames:



Public Member Functions

- perfnames (perform &p, perfedit &parent, Gtk::Adjustment &vadjust)
 - Principal constructor for this user-interface object.
- void redraw_dirty_sequences ()

Redraws sequences that have been modified.

Private Member Functions

• void enqueue_draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

• int convert_y (int y)

Converts a y-value into a sequence number and returns it.

• void draw_sequence (int sequence)

Draw the given sequence.

· void change_vert ()

Change the vertial offset of a sequence/pattern.

void update_pixmap ()

This function does nothing.

· void draw area ()

This function does nothing.

• void redraw (int sequence)

Redraw the given sequence.

· void on_realize ()

Handles the callback when the window is realized.

bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

• bool on_button_press_event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button.

• bool on_button_release_event (GdkEventButton *ev)

Handles a button-release for the right button, bringing up a popup menu.

• void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

• bool on scroll event (GdkEventScroll *ev)

Handle the scrolling of the window.

Private Attributes

perfedit & m_parent

Provides a link to the perfedit that created this object.

int m_names_chars

Provides the number of the characters in the name box.

• int m_char_w

Provides the "real" width of a character.

int m_setbox_w

Provides the width of the "set number" box.

• int m_namebox_w

Provides the width of the "name" box.

• int m_names_x

Provides the width of the names box, which is the width of a character for 24 characters.

int m_names_y

Provides the height of the names box, which is hardwired to 24 pixels.

int m_xy_offset

Provides the horizontal and vertical offsets of the text relative to the names box.

Additional Inherited Members

10.42.1 Detailed Description

Obsolete Note the usage of virtual base classes. Since these can add some extra overhead, we should determine if we can do without the virtuality (and indeed it doesn't seem to be needed).

10.42.2 Constructor & Destructor Documentation

```
10.42.2.1 seq64::perfnames::perfnames ( perform & p, perfedit & parent, Gtk::Adjustment & vadjust )
```

Weird is that the window (x,y) are set to (c_names_x, 100), when c_names_y is 22 (now 24) in globals.h.

10.42.3 Member Function Documentation

```
10.42.3.1 void seq64::perfnames::enqueue_draw( ) [private]
```

The parent perfedit will call perfnames::queue_draw() on behalf of this object, and it will pass a perfnames.::enqueue_draw() to the peer perfedit's perfnames, if the peer exists.

```
10.42.3.2 void seq64::perfnames::draw_sequence(int seqnum) [private]
```

This function has to be prepared to handle an almost endless list of sequences, including unused ones, to draw them all with compatible styles. The sequences are grouped by set-number. The set-number occurs every 32 sequences in the leftmost column of the window.

```
10.42.3.3 void seq64::perfnames::on_realize( ) [private]
```

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

```
10.42.3.4 bool seq64::perfnames::on_expose_event( GdkEventExpose * ev ) [private]
```

It draws all of the sequences.

```
10.42.3.5 void seq64::perfnames::on_size_allocate ( Gtk::Allocation & a ) [private]
```

It first calls the base-class version of this function.

10.42.4 Field Documentation

```
10.42.4.1 perfedit& seq64::perfnames::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
10.42.4.2 int seq64::perfnames::m_names_chars [private]
```

Pretty much hardwired to 24 at present.

```
10.42.4.3 int seq64::perfnames::m_char_w [private]
```

This value is obtained from a font-renderer accessor function.

```
10.42.4.4 int seq64::perfnames::m_setbox_w [private]
```

This used to be hardwired to 6 * 2 (character-width times two).

```
10.42.4.5 int seq64::perfnames::m_namebox_w [private]
```

This used to be a weird calculation based on character width.

```
10.42.4.6 int seq64::perfnames::m_names_y [private]
```

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

```
10.42.4.7 int seq64::perfnames::m_xy_offset [private]
```

Currently hardwired.

10.43 seq64::perform Class Reference

This class supports the performance mode.

Public Member Functions

• perform (gui_assistant &mygui, int ppqn=SEQ64_USE_DEFAULT_PPQN)

This construction initializes a vast number of member variables, some of them public (but we're working on that)!

∼perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

· bool is_modified () const

'Getter' function for member m_is_modfied

• void modify ()

'Setter' function for member m_is_modified This setter only sets the modified-flag to true.

int sequence_count () const

'Getter' function for member m_sequence_count It is better to call this getter before bothering to even try to use a sequence.

• int sequence_max () const

'Getter' function for member m_sequence_max

· const gui_assistant & gui () const

 ${\it 'Getter' function for member m_gui_support The \ const \ getter.}$

• gui_assistant & gui ()

'Getter' function for member m_gui_support The un-const getter.

const keys_perform & keys () const

'Getter' function for member m_gui_support.keys() The const getter.

• keys perform & keys ()

'Getter' function for member m_gui_support.keys() The un-const getter.

• mastermidibus & master_bus ()

'Getter' function for member m_master_bus

bool is_running () const

'Getter' function for member m_running

· bool is learn mode () const

'Getter' function for member m_mode_group_learn

void enregister (performcallback *pfcb)

Adds a pointer to an object to be notified by this perform object.

· void clear all ()

Clears all of the patterns/sequences.

• void launch (int ppqn)

Calls the MIDI buss and JACK initialization functions and the input/output thread-launching functions.

void new_sequence (int seq)

Creates a new pattern/sequence for the given slot, and sets the new pattern's master MIDI bus address.

void add_sequence (sequence *seq, int perf)

Adds a pattern/sequence pointer to the list of patterns.

• void delete_sequence (int seq)

Deletes a pattern/sequence by number.

bool is sequence in edit (int seq)

Check if the pattern/sequence, given by number, has an edit in progress.

void clear_sequence_triggers (int seq)

Clears the patterns/sequence for the given sequence, if it is active.

• void finish ()

The rough opposite of launch(); it doesn't stop the threads.

• midipulse get_tick () const

'Getter' function for member m_tick

void set_left_tick (midipulse tick, bool setstart=true)

Set the left marker at the given tick.

• midipulse get_left_tick () const

'Getter' function for member m_left_tick

void set_start_tick (midipulse tick)

'Setter' function for member m_starting_tick

• midipulse get_starting_tick () const

'Getter' function for member m_starting_tick

void set_right_tick (midipulse tick, bool setstart=true)

Set the right marker at the given tick.

midipulse get_right_tick () const

'Getter' function for member m_right_tick

void move_triggers (bool direction)

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are moved by the difference between the right and left in the specified direction.

• void copy_triggers ()

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are copied, offset by the difference between the right and left.

void push_trigger_undo ()

For every active sequence, call that sequence's push_trigger_undo() function.

• void pop trigger undo ()

For every active sequence, call that sequence's pop_trigger_undo() function.

void split_trigger (int seqnum, midipulse tick)

Convenience function for perfroll's split-trigger functionality.

• midipulse get_max_trigger ()

Locates the largest trigger value among the active sequences.

· void collapse ()

Convenience function for perfedit's collapse functionality.

void copy ()

Convenience function for perfedit's copy functionality.

void expand ()

Convenience function for perfedit's expand functionality.

midi_control & midi_control_toggle (int seq)

Retrieves a reference to a value from m_midi_cc_toggle[].

midi_control & midi_control_on (int seq)

Retrieves a reference to a value from m_midi_cc_on[].

• midi_control & midi_control_off (int seq)

Retrieves a reference to a value from m_midi_cc_off[].

• void handle_midi_control (int control, bool state)

Handle the MIDI Control values that provide some automation for the application.

const std::string & get_screen_set_notepad (int screen_set) const

Retrieves the given string from m_screen_set_notepad[].

const std::string & current_screen_set_notepad () const

Returns the notepad text for the current screen-set.

• void set_screen_set_notepad (int screenset, const std::string ¬e)

Copies the given string into m_screen_set_notepad[].

void set_screen_set_notepad (const std::string ¬e)

Sets the notepad text for the current screen-set.

void set_screenset (int ss)

Sets the m_screenset value (the index or ID of the current screen set).

• int get_screenset () const

'Getter' function for member m_screenset

void set_playing_screenset ()

Sets the screen set that is active, based on the value of m_playing_screen.

• int get_playing_screenset () const

'Getter' function for member m_playing_screen

void mute_group_tracks ()

Will need to study this one more closely.

void select_and_mute_group (int g_group)

Select a mute group and then mutes the track in the group.

• void set_mode_group_mute ()

'Setter' function for member m_mode_group

void unset_mode_group_mute ()

 ${\it 'Setter' function for member m_mode_group\ Unsets\ this\ member.}$

void select_group_mute (int g_mute)

Makes some checks on all of the active sequences, and sets the group mute flag, m_mute_group_selected, to the clamped g-mute value.

void set_mode_group_learn ()

Sets the group-mute mode, then the group-learn mode, then notifies all of the notification subscribers.

void unset_mode_group_learn ()

Notifies all of the notification subscribers that group-learn is being turned off.

· void select mute group (int group)

Makes some checks and sets the group mute flag, m_mute_group_selected, to the clamped g-mute value, if all goes well (no null sequences are encountered).

· void start (bool state)

If JACK is not running, call inner start() with the given state.

void stop ()

If JACK is not running, call inner_stop().

void start_jack ()

If JACK is supported, starts the JACK transport.

void stop_jack ()

If JACK is supported, stops the JACK transport.

void position_jack (bool state)

If JACK is supported and running, sets the position of the transport.

void off sequences ()

For all active patterns/sequences, set the playing state to false.

void all_notes_off ()

For all active patterns/sequences, turn off its playing notes.

void set_active (int seq, bool active)

Sets or unsets the active state of the given pattern/sequence number.

void set_was_active (int seq)

Sets was-active flags: main, edit, perf, and names.

· bool is_dirty_main (int seq)

Checks the pattern/sequence for main-dirtiness.

bool is dirty edit (int seq)

Checks the pattern/sequence for edit-dirtiness.

• bool is_dirty_perf (int seq)

Checks the pattern/sequence for perf-dirtiness.

· bool is dirty names (int seq)

Checks the pattern/sequence for names-dirtiness.

bool is_active (int seq)

Checks the pattern/sequence for activity.

sequence * get_sequence (int seq)

Retrieves the actual sequence, based on the pattern/sequence number.

void reset_sequences ()

For all active patterns/sequences, get its playing state, turn off the playing notes, set playing to false, zero the markers, and, if not in playback mode, restore the playing state.

void play (midipulse tick)

Plays all notes to the current tick.

void set_orig_ticks (midipulse tick)

For every pattern/sequence that is active, sets the "original ticks" value for the pattern.

void set_beats_per_minute (int bpm)

Sets the value of the BPM into the master MIDI buss, after making sure it is squelched to be between 20 and 500.

• int get_beats_per_minute ()

Retrieves the BPM setting of the master MIDI buss.

void set_looping (bool looping)

'Setter' function for member m_looping

void set sequence control status (int status)

If the given status is present in the c_status_snapshot, the playing state is saved.

void unset_sequence_control_status (int status)

If the given status is present in the c_status_snapshot, the playing state is restored.

· void sequence playing on (int seq)

Turn off the playing of a sequence, if it is active.

void sequence_playing_off (int seq)

Turn off the playing of a sequence, if it is active.

void set group mute state (int g track, bool mute state)

This function sets the mute state of an element in the m_mute_group array.

• bool get_group_mute_state (int g_track)

The "inverse" of set_group_mute_state(), it gets the value of the desired track.

void mute_all_tracks ()

Mutes all tracks in the current set of active patterns/sequences.

void output func ()

Performance output function.

· void input_func ()

This function is called by input_thread_func().

void set offset (int offset)

Calculates the offset into the screen sets.

void save_playing_state ()

For all active patterns/sequences, this function gets the playing status and saves it in m_sequence_state[i].

void restore_playing_state ()

For all active patterns/sequences, this function gets the playing status from m_sequence_state[i] and sets it for the sequence.

• bool show_ui_sequence_key () const

Accessor m_show_ui_sequency_key Provides access to keys().show_ui_sequence_key().

• bool show_ui_sequence_number () const

Accessor m_show_ui_sequency_number Provides access to keys().show_ui_sequence_number().

bool is_playing () const

'Getter' function for member rc().is_pattern_playing() Provide a convenience function so that clients don't have to mess with a global variable when they're dealing with a perform object.

void start playing (bool jackflag=false)

Encapsulates a series of calls used in mainwnd.

void stop_playing ()

Encapsulates a series of calls used in mainwnd.

void learn_toggle ()

Encapsulates some calls used in mainwnd.

• int decrement_beats_per_minute ()

Encapsulates some calls used in mainwnd.

• int increment_beats_per_minute ()

Encapsulates some calls used in mainwnd.

• int decrement screenset ()

Encapsulates some calls used in mainwnd.

int increment_screenset ()

Encapsulates some calls used in mainwnd.

• bool highlight (const sequence &) const

True if a sequence is empty and should be highlighted.

• bool is_smf_0 (const sequence &seq) const

True if the sequence is an SMF 0 sequence.

void sequence_key (int seq)

Handle a sequence key to toggle the playing of an active pattern in the selected screen-set.

• std::string sequence_label (const sequence &seq)

Provides a way to format the sequence parameters string for display in the mainwid or perfnames modules.

void set input bus (int bus, bool input active)

Sets the input bus, and handles the special "key labels on sequence" and "sequence numbers on sequence" functionality.

bool mainwnd_key_event (const keystroke &k)

Provided for mainwnd::on_key_press_event() and mainwnd::on_key_release_event() to call.

bool perfroll_key_event (const keystroke &k, int drop_sequence)

 $Provided \ for \ perfroll::on_key_press_event() \ and \ perfroll::on_key_release_event() \ to \ call.$

Private Member Functions

• void launch input thread ()

Creates the input thread using input_thread_func().

void launch_output_thread ()

Creates the output thread using output_thread_func().

void init_jack ()

Initializes JACK support, if SEQ64_JACK_SUPPORT is defined.

void deinit jack ()

Tears down the JACK infrastructure.

bool seq_in_playing_screen (int seq)

A helper function for determining if the mode group is in force, the playing screenset is the same as the current screenset, and the sequence is in the range of the playing screenset.

void is_modified (bool flag)

'Setter' function for member m_is_modified This setter is private.

· bool is midi control valid (int seq) const

Checks the parameter against c_midi_controls.

bool is_screenset_valid (int screenset) const

Checks the screenset against m_max_sets.

void set_running (bool running)

'Setter' function for member m_running

void set_playback_mode (bool playbackmode)

'Setter' function for member m_playback_mode

int mute_group_offset (int track)

A helper function to calculate the index into the mute-group array, based on the desired track.

• bool is_seq_valid (int seq) const

Provides common code to check for the bounds of a sequence number.

• bool is_mseq_valid (int seq) const

Validates the sequence number, which is important since they're currently used as array indices.

bool install_sequence (sequence *seq, int seqnum)

A private helper function for add_sequence() and new_sequence().

• void inner_start (bool state)

Locks on m_condition_var.

void inner_stop ()

Unconditionally, and without locking, clears the running status, resets the sequences, and set musemidiclock false.

• int clamp_track (int track) const

Provides common code to keep the track value valid.

void set_all_key_events ()

Pass-along function for keys().set_all_key_events.

void set_all_key_groups ()

Pass-along function for keys().set_all_key_events.

void set_key_event (unsigned int keycode, long sequence_slot)

At construction time, this function sets up one keycode and one event slot.

· void set_key_group (unsigned int keycode, long group_slot)

At construction time, this function sets up one keycode and one group slot.

Private Attributes

· gui_assistant & m_gui_support

Support for a wide range of GUI-related operations.

• bool m_mute_group [c_gmute_tracks]

Mute group support.

int m_playing_screen

Playing screen support.

· int m playscreen offset

Playing screen sequence number offset.

sequence * m_seqs [c_max_sequence]

Provides a "vector" of patterns/sequences.

• mastermidibus m master bus

Provides our MIDI buss.

• pthread_t m_out_thread

Provides information for managing pthreads.

bool m_playback_mode

Specifies the playback mode.

int m_ppqn

Holds the current PPQN for usage in various actions.

· midipulse m one measure

Holds the "one measure's worth" of pulses (ticks), which is normally m_ppqn * 4.

midipulse m_left_tick

Holds the position of the left (L) marker, and it is first defined as 0.

• midipulse m_right_tick

Holds the position of the right (R) marker, and it is first defined as the end of the fourth measure.

midipulse m_starting_tick

Holds the starting tick for playing.

• midipulse m_tick

MIDI Clock support.

• bool m_usemidiclock

More MIDI clock support.

• bool m_midiclockrunning

More MIDI clock support.

int m_midiclocktick

More MIDI clock support.

· int m_midiclockpos

More MIDI clock support.

• int m_seqs_in_set

We will eventually replace $c_seqs_in_set$ with this member, which defaults to the value of $c_seqs_in_set$.

int m_max_sets

A replacement for the c_max_sets constant.

· int m_sequence_count

Keeps track of created sequences, whether or not they are active.

• int m_sequence_max

A replacement for the c_max_sequence constant.

· bool m is modified

It may be a good idea to eventually centralize all of the dirtiness of a performance here.

condition_var m_condition_var

A condition variable to protect...

· jack_assistant m_jack_asst

A wrapper object for the JACK support of this application.

Static Private Attributes

· static midi control sm mc dummy

Provides a dummy, inactive midi_control object to handle out-of-range midi_control indicies.

Friends

• int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)

Global functions for JACK support and JACK sessions.

10.43.1 Detailed Description

It has way too many data members, many of the public. Might be ripe for refactoring.

10.43.2 Constructor & Destructor Documentation

10.43.2.1 seq64::perform::perform (gui assistant & mygui, int ppqn = SEQ64_USE_DEFAULT_PPQN)

Parameters

mygui

Provides access to the GUI assistant that holds many things, including the containers of keys and the "events" they provide. This is a base-class reference; for a real class, see the gui_assistant_gtk2 class in the seq_gtkmm2 GUI-specific library. Note that we access the m_gui_support member using the gui() accessor function.

```
10.43.2.2 seq64::perform::~perform()
```

Finally, any active or inactive (but allocated) patterns/sequences are deleted, and their pointers nullified.

10.43.3 Member Function Documentation

```
10.43.3.1 void seq64::perform::modify( ) [inline]
```

The setter that will, is_modified(), is private. No one but perfrom and its friends should falsify this flag.

```
10.43.3.2 int seq64::perform::sequence_count() const [inline]
```

In many cases at startup, or when loading a file, there are no sequences yet, and still the code calls functions that try to access them.

```
10.43.3.3 void seq64::perform::clear_all()
```

The mainwand module calls this function. Note that perform now handles the "is modified" flag on behalf of all external objects, to centralize and simplify the dirtying of a MIDI tune.

Anything else to clear? What about all the other sequence flags? We can beef up delete_sequence() for them, at some point.

10.43.3.4 void seq64::perform::launch (int ppqn)

This function is called in main(). We collected all the calls here as a simplification, and renamed it because it is more than just initialization. This function must be called after the perform constructor and after the configuration file and command-line configuration overrides.

Parameters

ppqn	Provides the PPQN value, which is either the default value (192) or is read from the "user"
	configuration file.

10.43.3.5 void seq64::perform::new_sequence (int seq)

Then it activates the pattern [this is done in the install sequence() function]. It doesn't deal with thrown exceptions.

This function is called by the seqmenu and mainwid objects to create a new sequence. We now pass this sequence to install_sequence() to better handle potential memory leakage, and to make sure the sequence gets counted. Also, adding a new sequence from the user-interface is a significant modification, so the "is modified" flag gtes set.

Parameters

seq	The prospective sequence number of the new sequence.

10.43.3.6 void seq64::perform::add_sequence (sequence * seq, int prefnum)

No check is made for a null pointer, but the install_sequence() call will make sure such a pointer is officially logged.

This function checks for the preferred sequence number. This is the number that was specified by the Sequence Number meta-event for the current track. If the preferred sequence number is in the valid range (0 to m_sequence — max) and it is not active, add it and activate it. Otherwise, iterate through all patterns from prefnum to m_ sequence max and add and activate the first one that is not active, and then finish.

Finally, note that this function is used only by midifile, when reading in a MIDI song. Therefore, the "is modified" flag is *not* set by this function; loading a sequence from a file is not a modification that should lead to a prompt for saving the file later.

Todo Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Warning

The logic of the if-statement in this function was such that *prefnum* could be out-of-bounds in the else-clause. We reworked the logic to be airtight. This bug was caught by gcc 4.8.3 on CentOS, but not on gcc 4.9.3 on Debian Sid!

Parameters

seq	The pointer to the pattern/sequence to add.
prefnum	The preferred sequence number of the pattern, as explained above. If this value is out-of-
	range, then it is basically ignored.

10.43.3.7 void seq64::perform::delete_sequence (int seq)

We now also solidify the deletion by setting the pointer to null after deletion, so it will blow up if accidentally accessed. The final act is to raise the "is modified" flag, since deleting an existing sequence is always a significant modification.

Now, this function obviously sets the "active" flag for the sequence to false. But there are a few other flags that are not modified; shouldn't we also falsify them here?

10.43.3.8 void seq64::perform::clear_sequence_triggers (int seq)

Parameters

seq	Provides the desired sequence. Hopefull, the is_active() function validates this value.
-----	---

10.43.3.9 void seq64::perform::finish() [inline]

A minor simplification for the main() routine, hides the JACK support macro.

10.43.3.10 void seq64::perform::set_left_tick (midipulse tick, bool setstart = true)

We let the caller determine if this setting is a modification. If the left tick is later than the right tick, the right tick is move to one measure past the left tick.

Todo The perform::m_one_measure member is currently hardwired to PPQN * 4.

Parameters

tick	The tick (MIDI pulse) at which to place the left tick. If the left tick is greater than or equal to the right tick, then the right ticked is moved forward by one "measure's length" ($m_ppqn * 4$) past the left tick.
setstart	If true (the default, and longstanding implicit setting), then the starting tick is also set to the
	left tick.

10.43.3.11 void seq64::perform::set_right_tick (midipulse tick, bool setstart = true)

This setting is made only if the tick parameter is at or beyond the first measure. We let the caller determine is this setting is a modification.

Parameters

tick	The tick (MIDI pulse) at which to place the right tick. If less than or equal to the left tick setting, then the left tick is backed up by one "measure's worth" ($m_ppqn * 4$) worth of ticks from the new right tick.
setstart	If true (the default, and longstanding implicit setting), then the starting tick is also set to the
	left tick, if that got changed.

10.43.3.12 void seq64::perform::move_triggers (bool direction)

Parameters

a_direction	Specifies the desired direction; false = left, true = right.

10.43.3.13 void seq64::perform::copy_triggers ()

This copies the triggers between the L marker and R marker to the R marker.

10.43.3.14 void seq64::perform::push_trigger_undo()

Too bad we cannot yet keep track of all the undoes for the sake of properly handling the "is modified" flag.

10.43.3.15 midipulse seq64::perform::get_max_trigger()

Returns

Returns the highest trigger value, or zero. It is not clear why this function doesn't return a "no trigger found" value. Is there always at least one trigger, at 0?

10.43.3.16 midi_control & seq64::perform::midi_control_toggle (int seq)

Parameters

seq	Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired
	midi_control object. Note that this value is unsigned simply to make the legality check of the
	parameter easier.

10.43.3.17 midi_control & seq64::perform::midi_control_on (int seq)

Parameters

seq	Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired
	midi_control object.

10.43.3.18 midi_control & seq64::perform::midi_control_off (int seq)

Parameters

seq	Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired
	midi_control object.

10.43.3.19 void seq64::perform::handle_midi_control (int ctrl, bool state)

Parameters

ctrl	The MIDI control value to use to perform an operation.
state	The state of the control, used with:
	- c_midi_control_mod_replace - c_midi_control_mod_snapshot - c_midi_control_mod_queue - c_midi_control_mod_gmute - c_midi_control_mod_glearn

10.43.3.20 const std::string & seq64::perform::get_screen_set_notepad (int *screenset*) const

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_notepad[] array. This value
	is validated.

Returns

Returns a reference to the desired string, or to an empty string if the screen-set number is invalid.

 $10.43.3.21 \quad \text{void seq64::perform::set_screen_set_notepad (int \textit{screenset}, const std::string \& \textit{notepad}) }$

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_xxx[] arrays.
notepad	Provides the string date to copy into the notepad. Not sure why a pointer is used, instead of
	nice "const std::string &" parameter. And this pointer isn't checked.

10.43.3.22 void seq64::perform::set_screenset (int ss)

It's not clear that we need to set the "is modified" flag just because we changed the screen set.

Parameters

SS	The index of the desired string set. It is forced to range from 0 to m_max_sets - 1.
----	--

10.43.3.23 void seq64::perform::set_playing_screenset()

For each value up to m_seqs_in_set (32), the index of the current sequence in the currently screen set (m_playing _ _screen) is obtained. If it is active and the sequence actually exists. Null sequences are no longer flagged as an error, they are just ignored.

Modifies m_playing_screen, and mutes the group tracks.

10.43.3.24 void seq64::perform::select_group_mute (int a_g_mute)

Null sequences are no longer flagged as an error, they are just ignored.

Parameters

	The provided of the provide groups alegan and to be between 0 and as ease in each 1
a a mule	The number of the mute group, clamped to be between 0 and m_seqs_in_set-1.
<u> </u>	

10.43.3.25 void seq64::perform::unset_mode_group_learn()

Then unsets the group-learn mode flag.

10.43.3.26 void seq64::perform::select_mute_group (int a_group)

Null sequences are no longer flagged as an error, they are just ignored.

Will need to study this one more closely.

Parameters

a_group	Provides the group to mute. Note that this parameter is essentially a track	or sequence
	number.	

10.43.3.27 void seq64::perform::start (bool state)

Parameters

state

```
10.43.3.28 void seq64::perform::stop ( )
```

The logic seems backward here, in that we call inner_stop() if JACK is not running. Or perhaps we misunderstand the meaning of m_jack_running?

```
10.43.3.29 void seq64::perform::position_jack ( bool state )
```

If we run "klick -j -P" and then start Sequencer64, we get:

```
klick: src/metronome_jack.cc:52: virtual void
MetronomeJack::process_callback(sample_t*, nframes_t): Assertion
'pos.beat > 0 && pos.beat <= pos.beats_per_bar' failed.</pre>
```

Let's try enabling the relocate parameter if we're JACK Master. This removes the error from klick, but it clicks at an extremely fast rate!

```
10.43.3.30 void seq64::perform::all_notes_off()
```

Then flush the MIDI buss.

```
10.43.3.31 void seg64::perform::set_active ( int seg, bool active )
```

If setting it active, the sequence::number() setter is called. It won't modify the sequence's internal copy of the sequence number if it has already been set.

Parameters

seq	Provides the prospective sequence number.
active	True if the sequence is to be set to the active state.

10.43.3.32 void seq64::perform::set_was_active (int seq)

Why do we need this routine?

Parameters

sea	The pattern number. It is checked for invalidity.

10.43.3.33 bool seq64::perform::is_dirty_main (int seq)

See the sequence::is_dirty_main() function.

Parameters

	,
seq	The pattern number. It is checked for invalidity.

Returns

Returns the was-active-main flag value, before setting it to false. Returns false if the pattern was invalid.

10.43.3.34 bool seq64::perform::is_dirty_edit (int seq)

Parameters

seq	The pattern number. It is checked for invalidity.
-----	---

Returns

Returns the was-active-edit flag value, before setting it to false. Returns false if the pattern was invalid.

10.43.3.35 bool seq64::perform::is_dirty_perf (int seq)

Parameters

seq	The pattern number. It is checked for invalidity.
-----	---

Returns

Returns the was-active-perf flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

10.43.3.36 bool seq64::perform::is_dirty_names (int seq)

Parameters

seq	The pattern number. It is checked for invalidity.

Returns

Returns the was-active-names flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

10.43.3.37 bool seq64::perform::is_active(int seq) [inline]

Todo We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Parameters

seq	The pattern number. It is checked for invalidity. This can lead to "too many" (i.e. redundant)
	checks, but we're trying to centralize such checks in this function.

Returns

Returns the value of the active-flag, or false if the sequence was invalid or null.

10.43.3.38 sequence* seq64::perform::get_sequence(int seq) [inline]

Parameters

seq	The prospective sequence number.

Returns

Returns the value of m_seqs[seq] if seq is valid. Otherwise, a null pointer is returned.

10.43.3.39 void seq64::perform::reset_sequences ()

Note that these calls could be folded into one member function of the sequence class.

Finally, flush the MIDI buss.

10.43.3.40 void seq64::perform::play (midipulse tick)

Starts the playing of all the patterns/sequences.

This function just runs down the list of sequences and has them dump their events.

Parameters

tick	Provides the tick at which to start playing.
------	--

10.43.3.41 void seq64::perform::set_orig_ticks (midipulse tick)

Parameters

tick

10.43.3.42 void seq64::perform::set_beats_per_minute (int bpm)

Replaces perform::set_bpm() from seq24.

The value is set only if neither JACK nor this performance object are running.

It's not clear that we need to set the "is modified" flag just because we changed the beats per minute. Does this setting get saved to the MIDI file?

Todo I think this logic is wrong, in that it needs only one of the two to be stopped before it sets the BPM, while it seems to me that both should be stopped; to be determined.

10.43.3.43 void seq64::perform::set_sequence_control_status (int status)

Then the given status is OR'd into the m control status.

10.43.3.44 void seq64::perform::unset_sequence_control_status (int status)

Then the given status is reversed in m_control_status.

10.43.3.45 void seq64::perform::sequence_playing_on (int seq)

Parameters

seq	The number of the sequence to be turned on.

10.43.3.46 void seq64::perform::sequence_playing_off (int seq)

Parameters

seq	The number of the sequence to be turned off.
-----	--

10.43.3.47 void seq64::perform::set_group_mute_state (int gtrack, bool muted)

The index value is the track number offset by the number of the selected mute group (which seems equivalent to a set number) times the number of sequences in a set.

Parameters

gtrack	The number of the track to be muted/unmuted.
muted	This boolean indicates the state to which the track should be set.

10.43.3.48 bool seq64::perform::get_group_mute_state (int gtrack)

Parameters

gtrack	The number of the track for which the state is to be obtained. Like set_group_mute_state(),
	this value is offset by adding m_mute_group_selected * m_seqs_in_set.

Returns

Returns the value of m_mute_group[gtrack + set offset]

10.43.3.49 void seq64::perform::output_func()

This function is called by the free function output_thread_func(). Here's how it works:

```
It runs while m_outputing is true.MORE TO COME
```

Change Note ca 2016-01-26 Hurray, seq24 is coming back to life! We see that there is a fix for clock tick drift here, which relies on using long and long long values. See the Changelog for seq24 0.9.3.

- 1. Get delta time (current last).
- 2. Get delta ticks from time.
- 3. Add to current_ticks.
- 4. Compute prebuffer ticks.
- 5. Play from current tick to prebuffer.

Figure out how much time we need to sleep, and do it.

```
10.43.3.50 void seq64::perform::set_offset ( int offset ) [inline]
```

Sets m_offset = offset * c_mainwnd_rows * c_mainwnd_cols;

Parameters

offset | The desired offset.

```
10.43.3.51 void seq64::perform::save_playing_state()
```

Inactive patterns get the value set to false.

```
10.43.3.52 bool seq64::perform::show_ui_sequence_key( )const [inline]
```

Used in mainwid, options, optionsfile, userfile, and perform.

```
10.43.3.53 bool seq64::perform::show_ui_sequence_number() const [inline]
```

Used in mainwid, optionsfile, and perform.

```
10.43.3.54 void seq64::perform::start_playing ( bool jackflag = false )
```

We've reversed the start() and start_jack() calls so that JACK is started first, to match all of the other use-cases for playing that we've found in the code.

Note that the complementary function, stop_playing(), is an inline function defined in the header file.

Note

It would be nice to know why the following code snippet disables the mute/unmute functionality of the performance/song editor:

```
position_jack(false);
    start_jack();
    start(false);

The jack_assistant::position() function doesn't use the boolean
parameter at present; that code is effectively disabled.

Okay, now it does, if the "relocate" parameter is true. See
    perform::position_jack() and jack_assistant::position(). This
    parameter, when true, allows the "klick" application to get
    proper position data.

The perform::start() function passes its boolean flag to
    perform::inner_start(), which sets the playback mode to that flag; if
    that flag is false, that turns off "song" mode. So that explains why
    mute/unmute is disabled.
```

Parameters

Indicates if the caller wants to start the playback in JACK mode. In the seq42 (yes, "42", not "24") code at GitHub, this flag was identical to the "global_jack_start_mode" flag, which is true for Song Mode, and false for Live Mode. False disables Song Mode.

```
10.43.3.55 int seq64::perform::decrement_beats_per_minute() [inline]
```

Actually does a lot of work in those function calls.

```
10.43.3.56 int seq64::perform::increment_beats_per_minute() [inline]
```

Actually does a lot of work in those function calls.

10.43.3.57 bool seq64::perform::highlight (const sequence &) const [inline]

This setting is currently a build-time option, but could be made a run-time option later.

10.43.3.58 std::string seq64::perform::sequence_label (const sequence & seq)

This string goes on the bottom-left of those user-interface elements.

The format of this string is something like the following example, depending on the "show sequence numbers" option. The values shown are, in this order, sequence number (if allowed), buss number, channel number, beats per bar, and beat width.

```
No sequence number: 31-16 4/4
Sequence number: 9 31-16 4/4
```

The sequence number and buss number are re 0, while the channel number is displayed re 1, unless it is an SMF 0 null channel (0xFF), in which case it is 0.

Note

Later, we could add the sequence hot-key to this string, though showing that is not much use in perfnames. Also, this function is a stilted mix of direct access and access through sequence number.

Parameters

seq	Provides the reference to the sequence, use for getting the sequence parameters to be written
	to the label string.

Returns

Returns the filled in label if the sequence is active. Otherwise, an empty string is returned.

10.43.3.59 void seq64::perform::set_input_bus (int bus, bool active)

This function is called by options::input_callback().

Tricky Code See the bus parameter. We should provide two separate functions for this feature, but it is already combined into one input-callback function with a lot of other functionality in the options module.

Parameters

bus	If this value is greater than SEQ64_DEFAULT_BUSS_MAX (32), then it is treated as a user-
	interface flag (PERFORM_KEY_LABELS_ON_SEQUENCE or PERFORM_NUM_LABEL←
	S_ON_SEQUENCE) that causes all the sequences to be dirtied, and thus get redrawn iwht
	the new user-interface setting.
active	Indicates whether the buss or the user-interface feature is active or inactive.

10.43.3.60 bool seq64::perform::mainwnd_key_event (const keystroke & k)

Returns

Returns true if the key was handled.

10.43.3.61 bool seq64::perform::perfroll_key_event (const keystroke & k, int drop_sequence)

The "is modified" flag is raised if something is deleted, but we cannot yet handle the case where we undo all the changes. So, for now, we play it safe with the user, even if the user gets annoyed because he knows that he undid all the changes.

Returns

Returns true if the key was handled.

```
10.43.3.62 void seq64::perform::launch_input_thread( ) [private]
```

This might be a good candidate for a small thread class derived from a small base class.

```
10.43.3.63 void seq64::perform::launch_output_thread( ) [private]
```

This might be a good candidate for a small thread class derived from a small base class.

```
10.43.3.64 void seq64::perform::init_jack( ) [inline], [private]
```

Who calls this routine? The main() routine of the application [via launch()], and the options module, when the Connect button is pressed.

```
10.43.3.65 void seq64::perform::deinit_jack( ) [inline],[private]
```

Called by launch() and in the options module, when the Disconnect button is pressed.

```
10.43.3.66 bool seq64::perform::seq_in_playing_screen ( int seq ) [private]
```

Parameters

seq	Provides the index of the desired sequence.
-----	---

Returns

Returns true if the sequence adheres to the conditions noted above.

```
10.43.3.67 void seq64::perform::is_modified ( bool flag ) [inline], [private]
```

The modify() setter, which is public, can only set m_is_motified to true.

```
10.43.3.68 bool seg64::perform::is_midi_control_valid(int seg) const [inline], [private]
```

Parameters

sea	The value that should be in the c_midi_controls range.
, ,	

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

```
10.43.3.69 bool seq64::perform::is_screenset_valid(int screenset) const [inline], [private]
```

Parameters

screenset	The prospective screenset value.
-----------	----------------------------------

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

10.43.3.70 bool seq64::perform::is_seq_valid (int seq) const [private]

Also see the function is mseq valid(), which also checks the pointer stored in the m seq[] array.

We considered checking the *seq* param against sequence_count(), but this function is called while creating sequences that add to that count, so we continue checking against the "container" size. Also, it is possible to have holes in the array representing inactive sequences, so that sequencer_count() would be too limiting.

Parameters

seq	The sequencer number, in interval [0, m_sequence_max).

Returns

Returns true if the sequence number is valid.

10.43.3.71 bool seq64::perform::is_mseq_valid (int seq) const [private]

It also evaluates the m_seq[seq] pointer value.

Note

Since we can have holes in the sequence array, where there are inactive sequences, we check if the sequence is even active before emitting a message about a null pointer for the sequence. We only want to see messages that indicate actual problems.

Parameters

sec	Provides the sequence number to be checked. It is checked for validity. We cannot compare
	the sequence number versus the sequence_count(), because the current implementation can
	have inactive holes (with null pointers) interspersed with active pointers.

Returns

Returns true if the sequence number is valid as per is_seq_valid(), and the sequence pointer is not null.

10.43.3.72 bool seq64::perform::install_sequence (sequence * seq, int seqnum) [private]

It is common code and using it prevents inconsistences. It assumes values have already been checked. It does not set the "is modified" flag, since adding a sequence by loading a MIDI file should not set it. Compare new_\circ sequence(), used by mainwid and seqmenu, with add_sequence(), used by midifile.

Parameters

seq	The pointer to the pattern/sequence to add.
seqnum	The sequence number of the pattern to be added.

Returns

Returns true if a sequence was removed, or the sequence was successfully added. In other words, if a real change in sequence pointers occurred. It is up to the caller to decide if the change warrants setting the "is modified" flag.

```
10.43.3.73 void seq64::perform::inner_start ( bool state ) [private]
```

Then, if not is_running(), the playback mode is set to the given state. If that state is true, call off_sequences(). Set the running status, and signal the condition. Then unlock.

```
10.43.3.74 int seq64::perform::clamp_track( int track ) const [inline], [private]
```

Note the bug we found, where we checked for track > m_seqs_in_set, but set it to m_seqs_in_set - 1 in that case!

```
10.43.3.75 void seq64::perform::set_key_event ( unsigned int keycode, long sequence_slot ) [inline], [private]
```

It is called 32 times, corresponding to the pattern/sequence slots in the Patterns window. It first removes the given key-code from the regular and reverse slot-maps. Then it removes the sequence-slot from the regular and reverse slot-maps. Finally, it adds the sequence-slot with a key value of key-code, and adds the key-code with a value of sequence-slot.

```
10.43.3.76 void seq64::perform::set_key_group ( unsigned int keycode, long group_slot ) [inline], [private]
```

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window. Compare it to the set_key← events() function.

10.43.4 Field Documentation

```
10.43.4.1 midi_control seq64::perform::sm_mc_dummy [static], [private]
```

Instantiate the dummy midi_control object, which is used in lieu of a null pointer.

We're taking code that basically works already, in the sense that it never seems to access a null pointer. So we're not even risking data transfers between this dummy object and the ones we really want to use.

```
10.43.4.2 int seq64::perform::m_playscreen_offset [private]
```

Saves some multiplications, should make the code easier to grok, and centralizes the use of c_seqs_in_set, which we want to be able to change at run-time, as a future enhancement.

```
10.43.4.3 sequence* seq64::perform::m_seqs[c_max_sequence] [private]
```

Todo First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

```
10.43.4.4 bool seq64::perform::m_playback_mode [private]
```

There are two, "live" and "song", indicated by the following values:

```
m_playback_mode == false: live mode
m_playback_mode == true: playback/song mode
```

```
10.43.4.5 midipulse seq64::perform::m_one_measure [private]
```

We can save some multiplications, and, more importantly, later define a more flexible definition of "one measure's worth" than simply four quarter notes.

```
10.43.4.6 midipulse seq64::perform::m_left_tick [private]
```

Note that "tick" is actually "pulses".

```
10.43.4.7 midipulse seq64::perform::m_right_tick [private]
```

Note that "tick" is actually "pulses".

```
10.43.4.8 midipulse seq64::perform::m_starting_tick [private]
```

By default, this value is always reset to the value of the "left tick". We want to eventually be able to leave it at the last playing tick, to support a "pause" functionality. Note that "tick" is actually "pulses".

```
10.43.4.9 midipulse seq64::perform::m_tick [private]
```

The m_tick member holds the tick to be used in displaying the progress bars and the maintime pill.

```
10.43.4.10 int seq64::perform::m_seqs_in_set [private]
```

This change will require some arrays to be dynamically allocated (vectors).

```
10.43.4.11 int seq64::perform::m_max_sets [private]
```

Again, currently set to the old value, which is used in hard-wired array sizes. To make it variable will require a move from arrays to vectors.

```
10.43.4.12 int seq64::perform::m_sequence_count [private]
```

Used by the install_sequence() function.

```
10.43.4.13 int seq64::perform::m_sequence_max [private]
```

However, this value is already 32 * 32 = 1024, and is probably enough for any usage. Famous last words?


```
10.43.4.14 bool seq64::perform::m_is_modified [private]
```

All the GUIs seem to use a perform object. IN PROGRESS.

10.44 seq64::performcallback Struct Reference

Provides for notification of events.

Inheritance diagram for seq64::performcallback:



10.44.1 Detailed Description

Provide a response to a group-learn change event.

10.45 seq64::perfroll Class Reference

This class implements the performance roll user interface.

Inheritance diagram for seq64::perfroll:



Public Member Functions

• perfroll (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=S← EQ64_USE_DEFAULT_PPQN)

Principal constructor.

∼perfroll ()

This destructor deletes the interaction object.

void set_guides (int snap, int measure, int beat)

This function sets the m_snap, m_measure_length, and m_beat_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

· void update sizes ()

Updates the sizes of various items.

void init_before_show ()

Sets the roll-lengths ticks member.

void fill background pixmap ()

This function updates the background of the Performance roll.

• void increment size ()

Increments the value of m roll length ticks by the PPQN * 512, then calls update sizes().

• void draw all ()

Provides a very common sequence of calls used in perfroll_input.

void redraw_progress ()

Helper function to simplify the client call.

Private Member Functions

• void draw progress ()

Draws the progess line that shows where we are in the performance.

void redraw_dirty_sequences ()

Redraws patterns/sequences that have been modified.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

void convert_xy (int x, int y, midipulse &ticks, int &seq)

Converts a tick-offset....

void convert x (int x, midipulse &ticks)

Converts a tick-offset on the x coordinate.

void snap_x (int &x)

This function performs a 'snap' action on x.

void start_playing ()

Start the performance playing.

void stop_playing ()

Stop the performance playing.

void draw_sequence_on (int seqnum)

Draws the given pattern/sequence on the given drawable area.

void draw background on (int segnum)

Draws the given pattern/sequence background on the given drawable area.

void draw_drawable_row (long y)

Not quite sure what this draws yet.

void change horz ()

Changes the 4-bar horizontal offset member and queues up a draw operation.

void change_vert ()

Changes the 4-bar vertical offset member and queues up a draw operation.

void split_trigger (int sequence, midipulse tick)

Splits a trigger, whatever that means.

• void enqueue_draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

void on_realize ()

Provides the on-realization callback.

bool on_expose_event (GdkEventExpose *ev)

Handles the on-expose event.

• bool on_button_press_event (GdkEventButton *ev)

This callback function handles a button press by forwarding it to the interaction object's button-press function.

bool on_button_release_event (GdkEventButton *ev)

This callback function handles a button release by forwarding it to the interaction object's button-release function.

bool on_motion_notify_event (GdkEventMotion *ev)

Handles motion notification by forwarding it to the interaction object's motion-notification callback function.

bool on scroll event (GdkEventScroll *ev)

Handles horizontal and vertical scrolling.

bool on_focus_in_event (GdkEventFocus *ev)

This callback handles an in-focus event by setting the flag to HAS_FOCUS.

bool on focus out event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

void on_size_allocate (Gtk::Allocation &al)

Upon a size allocation event, this callback calls the base-class version of this function, then sets m_window_x and m_window_y, and calls update_sizes().

bool on key press event (GdkEventKey *ev)

This callback function handles a key-press event.

void on_size_request (GtkRequisition *)

This do-nothing callback effectively throws away a size request.

Private Attributes

· perfedit & m parent

Provides a link to the perfedit that created this object.

· int m_h_page_increment

Provides the horizontal page increment for the horizontal scrollbar.

• int m v page increment

Provides the vertical page increment for the vertical scrollbar.

· FruityPerfInput m fruity interaction

We need both styles of interaction object present.

• Seq24PerfInput m_seq24_interaction

Provides support for standard Seq24 mouse handling, plus the keystroke handlers.

Friends

class FruityPerfInput

These friend implement interaction-specific behavior, although only the Seq24 interactions support keyboard processing, except for some common functionality provided by perform::perfroll_key_event().

Additional Inherited Members

10.45.1 Constructor & Destructor Documentation

10.45.1.1 seq64::perfroll::~perfroll ()

Well, now there are two objects, so no explicit deletion necessary.

10.45.2 Member Function Documentation

10.45.2.1 void seq64::perfroll::set_guides (int snap, int measure, int beat)

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set ←
	_guides(). This is actually equal to the measure-pulses divided by the snap value in perfedit;
	the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set ←
	_guides().
beat	Provides the number of beat-pulses (pulses per beat) as calculated in perfedit::set_guides().

10.45.2.2 void seq64::perfroll::update_sizes ()

Note

Trying to figure out what the 16 is. So take the "bars-visible" calculation, the c_perf_scale_x value, assume that "ticks" is another name for "pulses", and assume that "beats" is a quarter note. Ignoring the numbers, the units come out to:

```
pixels * ticks / pixel
bars = ------
ticks / beat * beats / bar
```

Thus, the 16 is a "beats per bar" or "beats per measure" value. This doesn't quite make sense, but there are 16 divisions per beat on the perfroll user-interface. So for now we'll call it the latter, and make a variable called "m_divs_per_beat", see its definition in the class initializer list.

10.45.2.3 void seq64::perfroll::init_before_show()

First, it gets the largest trigger value among the active sequences. Then it truncates this value to the nearest PPQN * 16 ticks. Then it adds PPQN * 4096 ticks.

```
10.45.2.4 void seq64::perfroll::fill_background_pixmap( )
```

This first thing done is to clear the background by painting it with a filled white rectangle.

```
10.45.2.5 void seq64::perfroll::set_ppqn ( int ppqn ) [private]
```

The m_ticks_per_bar member replaces the global ppqn times 16. This construct is parts-per-quarter-note times 4 quarter notes times 4 sixteenth notes in a bar. (We think...)

The m_perf_scale_x member starts out at c_perf_scale_x, which is 32 ticks per pixel at the default tick rate of 192 PPQN. We adjust this now. But note that this calculation still involves the c_perf_scale_x constant.

```
10.45.2.6 void seq64::perfroll::convert_xy ( int x, int y, midipulse & d_tick, int & d_seq ) [private]
```

The results are returned via the d_tick and d_seq parameters.

```
10.45.2.7 void seq64::perfroll::convert_x ( int x, midipulse & tick ) [private]
```

The result is returned via the tick parameter.

10.45.2.8 void seq64::perfroll::snap_x (int & x) [private]

- m_snap = number pulses to snap to
- m_perf_scale_x = number of pulses per pixel

Therefore mod = m_snap/m_perf_scale_x equals the number pixels to snap to.

```
10.45.2.9 void seq64::perfroll::start_playing( ) [private]
```

We need to keep in sync with perfedit's start_playing()... wish we could call it directly. Well, now we go to the source, calling perform::start_playing(). Note that we no longer pass "true" as the playback parameter, instead using the global JACK-start-mode flag. (We might reconsider that, later.)

Note

The old behavior was to call this function with true, I believe, which means that starting the song from the performance window forces playback to use the song/performance mode.

```
10.45.2.10 void seq64::perfroll::stop_playing( ) [private]
```

We need to keep in sync with perfedit's stop_playing()... wish we could call it directly. Well, now we go to the source, calling perform::stop_playing().

```
10.45.2.11 void seq64::perfroll::draw_sequence_on(int segnum) [private]
```

Statement nesting from hell!

```
10.45.2.12 void seq64::perfroll::draw_drawable_row( long y ) [private]
```

It is involved in the drawing of a greyed (selected) row.

What's weird is that we divide y by m_names_y, then multiply it by m_names_y, before passing the result to draw—drawable(). However, if we just as y casted to an int, then the drawing of the row is only partial, vertically.

```
10.45.2.13 void seq64::perfroll::enqueue_draw( ) [private]
```

The parent perfedit will call perfroll::queue_draw() on behalf of this object, and it will pass a perfroll::enqueue_draw() to the peer perfedit's perfroll, if the peer exists.

```
10.45.2.14 void seq64::perfroll::on_realize( ) [private]
```

Calls the base-class version first.

Then it allocates the additional resources need, that couldn't be initialized in the constructor, and makes some connections.

```
10.45.2.15 bool seq64::perfroll::on_expose_event( GdkEventExpose * ev ) [private]
```

Returns

Always returns true.

10.45.2.16 bool seq64::perfroll::on_button_press_event(GdkEventButton * ev) [private]

This gives us Seq24 versus Fruity behavior.

One minor issue: Fruity behavior doesn't yet provide the keystroke behavior we now handle for the Seq24 mode of operation.

```
10.45.2.17 bool seg64::perfroll::on_button_release_event( GdkEventButton * ev ) [private]
```

This gives us Seg24 versus Fruity behavior.

```
10.45.2.18 bool seq64::perfroll::on_key_press_event ( GdkEventKey * ev ) [private]
```

If we don't check the event type first, then the ev->keyval value is something weird like 65507. Note that we pass the functionality on to the perform::perfroll_key_event() function for the handling of delete, cut, copy, paste, and undo operations. If the keystroke is not handled by that function, then we handle it here.

Note that only the Seq24 input interaction object handles additional keystrokes not handled by the perfroll_key_ event() function.

10.45.3 Friends And Related Function Documentation

```
10.45.3.1 friend class FruityPerfInput [friend]
```

The perfedit class needs access to the private enqueue draw() function.

10.45.4 Field Documentation

```
10.45.4.1 perfedit& seq64::perfroll::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
10.45.4.2 int seq64::perfroll::m_h_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 4, for now. Might be a useful "user" configuration option.

```
10.45.4.3 int seq64::perfroll::m_v_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 8, for now. Might be a useful "user" configuration option.

```
10.45.4.4 FruityPerfInput seq64::perfroll::m_fruity_interaction [private]
```

Even if the user specifies the fruity interaction, the Seq24 interaction is still needed to handle our new keystroke support for the perfroll. We need both objects to exist all the time, similar to the Fruity/Seq24 roles in the seqroll object.

Obsolete AbstractPerfInput * m_interaction

10.46 seq64::perftime Class Reference

This class implements drawing the piano time at the top of the "performance window" (the "song editor"). Inheritance diagram for seq64::perftime:



Public Member Functions

perftime (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_P
 — PQN)

Principal constructor.

void set_guides (int snap, int measure)

Sets the m_snap value and the m_measure_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

· void increment size ()

This function does nothing.

Private Member Functions

• void enqueue draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

• void change_horz ()

Change the m_4bar_offset and queue a draw operation.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

long tick_to_pixel (midipulse tick)

Common calculation to convert a pulse/tick value to a perftime x value.

midipulse pixel_to_tick (long pixel)

The inverse of tick_to_pixel().

• void update_sizes ()

This function does nothing.

• int idle_progress ()

This function just returns true.

void update_pixmap ()

This function does nothing.

void draw_pixmap_on_window ()

This function does nothing.

void on_realize ()

Implements the on-realization event, then allocates some resources the could not be allocated in the constructor.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Implement the button-press event.

void on_size_allocate (Gtk::Allocation &r)

Implements a size-allocation event.

bool on_button_release_event (GdkEventButton *)

This button-release handler does nothing.

Private Attributes

perfedit & m_parent

Provides a link to the perfedit that created this object.

· int m_4bar_offset

Not yet sure exactly what this member represents.

int m_tick_offset

This member is m_4bar_offset times 16 times the current PPQN, to save some calculations and centralize this value.

• int m_ppqn

The current value of PPQN, which we are trying to get to work everywhere, when PPQN is changed from the global ppqn = 192.

• int m_snap

Snap value, starts out very small, equal to m_ppqn.

· int m measure length

Provides the length of a measure in pulses or ticks.

· int m left marker tick

Holds the current location of the left (L) marker when arrow movement is in force.

int m_right_marker_tick

Holds the current location of the right (R) marker when arrow movement is in force.

• int m perf scale x

A class version of the global c_perf_scale_x factor.

int m_timearea_y

A class version of the global c_timerarea_y factor.

Additional Inherited Members

10.46.1 Constructor & Destructor Documentation

```
10.46.1.1 seq64::perftime::perftime ( perform & p, perfedit & parent, Gtk::Adjustment & hadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

In the constructor you can only allocate colors; get_window() returns 0 because we have not been realized.

Note

Note that we still have to use a global constant in the base-class constructor; we cannot assign it to the corresponding member beforehand.

10.46.2 Member Function Documentation

```
10.46.2.1 void seq64::perftime::set_guides ( int snap, int measure )
```

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set←
	_guides(). This is actually equal to the measure-pulses divided by the snap value in perfedit;
	the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set←
	_guides().

```
10.46.2.2 void seq64::perftime::enqueue_draw( ) [private]
```

The parent perfedit will call perftime::queue_draw() on behalf of this object, and it will pass a perftime::enqueue_cdraw() to the peer perfedit's perftime, if the peer exists.

```
10.46.2.3 void seq64::perftime::on_realize( ) [private]
```

It is important to call the base-class version of this function.

Done in base-class's on realize() and in its constructor now.

```
m_window = get_window();
m_gc = Gdk::GC::create(m_window);
m_window->clear();
set_size_request(10, m_timearea_y);
```

10.46.2.4 bool seq64::perftime::on_expose_event(GdkEventExpose * ev) [private]

Note

The perfedit object is created early on. When brought on-screen from mainwand (the main window), first, perftime::on_realize() is called, then this event is called.

It crashes trying to set the foreground color.

10.46.3 Field Documentation

```
10.46.3.1 perfedit& seq64::perftime::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
10.46.3.2 int seq64::perftime::m_measure_length [private]
```

This value is m_ppqn * 4, though eventually we want to employ a more flexible representation of measure length.

```
10.46.3.3 int seq64::perftime::m_left_marker_tick [private]
```

Otherwise it is -1.

10.46.3.4 int seq64::perftime::m_right_marker_tick [private]

Otherwise it is -1.

10.47 seq64::rc_settings Class Reference

This class contains the options formerly named "global_xxxxxx".

Public Member Functions

• rc_settings ()

Default constructor.

• rc_settings (const rc_settings &rhs)

Copy constructor.

rc_settings & operator= (const rc_settings &rhs)

Principal assignment operator.

• std::string config_filespec () const

Constructs the full path and file specification for the "rc" file based on whether or not the legacy Seq24 filenames are being used.

• std::string user_filespec () const

Constructs the full path and file specification for the "user" file based on whether or not the legacy Seq24 filenames are being used.

void set_defaults ()

Sets the default values.

· bool auto option save () const

Accessor m_auto_option_save

bool legacy_format () const

Accessor m_legacy_format

• bool lash_support () const

Accessor m_lash_support

· bool allow mod4 mode () const

Accessor m_allow_mod4_mode

• bool show_midi () const

Accessor m_show_midi

• bool priority () const

Accessor m_priority

· bool stats () const

Accessor m stats

bool pass_sysex () const

Accessor m_pass_sysex

bool with_jack_transport () const

Accessor m_with_jack_transport

bool with_jack_master () const

Accessor m_with_jack_master

· bool with jack master cond () const

Accessor m_with_jack_master_cond

bool with_jack () const

Accessor m_with_jack_transport m_with_jack_master, and m_with_jack_master_cond, to save client code some trouble.

• bool jack_start_mode () const

Accessor m_jack_start_mode,

· bool manual_alsa_ports () const

Accessor m_manual_alsa_ports

• bool is_pattern_playing () const

Accessor m_is_pattern_playing

bool print_keys () const

Accessor m_print_keys

• bool device_ignore () const

Accessor m_device_ignore

• int device_ignore_num () const

'Getter' function for member m_device_ignore_num

interaction_method_t interaction_method () const

'Getter' function for member m_interaction_method

• const std::string & filename () const

'Getter' function for member m_filename

const std::string & jack_session_uuid () const

'Getter' function for member m_jack_session_uuid

· const std::string & last used dir () const

'Getter' function for member m_last_used_dir

const std::string & config_directory () const

'Getter' function for member m_config_directory

• const std::string & config_filename () const

'Getter' function for member m_config_filename

const std::string & user_filename () const

'Getter' function for member m_user_filename

· const std::string & config filename alt () const

'Getter' function for member m_config_filename_alt;

const std::string & user_filename_alt () const

'Getter' function for member m_user_filename_alt

void device_ignore_num (int value)

'Setter' function for member m_device_ignore_num However, please note that this value, while set in the options processing of the main module, does not appear to be used anywhere in the code in seq24, Sequencer24, and this application.

void interaction_method (interaction_method_t value)

'Setter' function for member m_interaction_method

void filename (const std::string &value)

'Setter' function for member m filename

void jack_session_uuid (const std::string &value)

'Setter' function for member m_jack_session_uuid

void last_used_dir (const std::string &value)

'Setter' function for member m last used dir

void config_directory (const std::string &value)

'Setter' function for member m_config_directory

void config_filename (const std::string &value)

'Setter' function for member m_config_filename

void user filename (const std::string &value)

'Setter' function for member m_user_filename

void config_filename_alt (const std::string &value)

'Setter' function for member m_config_filename_alt;

void user_filename_alt (const std::string &value)

'Setter' function for member m_user_filename_alt

Private Member Functions

• std::string home_config_directory () const

Provides the directory for the configuration file, and also creates the directory if necessary.

Private Attributes

std::string m_filename

Provides the name of current MIDI file.

10.47.1 Member Function Documentation

10.47.1.1 std::string seq64::rc_settings::home_config_directory() const [private]

If the legacy format is in force, then the home directory for the configuration is (in Linux) "/home/username", and the configuration file is ".seq24rc".

If the new format is in force, then the home directory is (in Linux) "/home/username/.config/sequencer64", and the configuration file is "sequencer64.rc".

Returns

Returns the selection home configuration directory. If it does not exist or could not be created, then an empty string is returned.

10.48 seg64::rect Class Reference

A small helper class representing a rectangle.


10.49 seq64::gui_drawingarea_gtk2::rect Struct Reference

A small helper structure representing a rectangle.

10.50 seq64::Seq24PerfInput Class Reference

Implements the default (Seq24) performance input characteristics of this application.

Inheritance diagram for seq64::Seq24PerfInput:



Public Member Functions

- bool on_button_press_event (GdkEventButton *a_ev, perfroll &roll)

 Handles the normal variety of button-press event.
- bool on_button_release_event (GdkEventButton *a_ev, perfroll &roll)

 Handles various button-release events.
- bool on_motion_notify_event (GdkEventMotion *a_ev, perfroll &roll)

 Handles the normal motion-notify event.

Private Member Functions

void set_adding (bool a_adding, perfroll &roll)
 A popup menu (which one?) calls this.

• bool handle_motion_key (bool is_left, perfroll &roll)

Handles the keystroke motion-notify event for moving a pattern back and forth in the performance.

· bool is adding () const

'Getter' function for member m_adding

Private Attributes

bool m adding

Indicates we are in the middle of adding a sequence segment to the performance.

• midipulse m_effective_tick

The current tick for the current segment?

10.50.1 Member Function Documentation

```
10.50.1.1 bool seq64::Seq24PerfInput::on_button_press_event ( GdkEventButton * ev, perfroll & roll ) [virtual]
```

Is there any easy way to use ctrl-left-click as the middle button here?

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

```
10.50.1.2 bool seq64::Seq24Perfinput::on_button_release_event ( GdkEventButton * ev, perfroll & roll ) [virtual]
```

Any use for the middle-button or ctrl-left-click we can add?

Returns

Returns true if any modification occurred.

Implements seq64::AbstractPerfInput.

```
10.50.1.3 bool seq64::Seq24PerfInput::on_motion_notify_event( GdkEventMotion * ev, perfroll & roll ) [virtual]
```

Returns

Returns true if a modification occurs. This function used to always return true.

Implements seq64::AbstractPerfInput.

```
\textbf{10.50.1.4} \quad \textbf{void seq64::Seq24PerfInput::set\_adding ( bool \textit{adding, perfroll \& roll })} \quad \texttt{[private]}
```

What does it mean?

```
10.50.1.5 bool seq64::Seq24PerfInput::handle_motion_key ( bool is_left, perfroll & roll ) [private]
```

What happens when the mouse is used to drag the pattern is that, first, roll.m_drop_tick is set by left-clicking into the pattern to select it. As the pattern is dragged, the drop-tick value does not change, but the tick (converted from the moving x value) does.

Then the button-handler sets roll.m_moving = true, and calculates roll.m_drop_tick_trigger_offset = roll.m_drop_tick - p.get_sequence(dropseq)->selected_trigger_start();

The motion handler sees that roll.m_moving is true, gets the new tick value from the new x value, offsets it, and calls p.get_sequence(dropseq)->move_selected_triggers_to(tick, true).

When the user releases the left button, then roll.m_growing is turned of and the roll draw_all()'s.

Parameters

is_left	False denotes the right arrow key, and true denotes the left arrow key.
roll	Provides a reference to the parent roll, which keeps track of most of the information about the
	status of the window.

Returns

Returns true if there was some action able to happen that would necessitate a window update. We've updated triggers::move_selected() [called indirectly near the end of this routine] to return false if no more movement could be made. This prevents this routine from moving way ahead after movement of the selected (in the user-interface) trigger stops.

10.51 seq64::Seq24SeqEventInput Struct Reference

This structure implement the normal interaction methods for Seq24.

Public Member Functions

Seq24SeqEventInput ()

Default constructor.

void set_adding (bool a_adding, seqevent &ths)

Changes the mouse cursor to a pencil or a left pointer in the given seqevent aobject, depending on the first parameter.

bool on_button_press_event (GdkEventButton *a_ev, seqevent &ths)

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *a_ev, seqevent &ths)

Implements the on-button-release callback.

bool on_motion_notify_event (GdkEventMotion *a_ev, seqevent &ths)

Implements the on-motion-notify event.

10.51.1 Member Function Documentation

10.51.1.1 void seq64::Seq24SeqEventInput::set_adding (bool adding, seqevent & seqev)

Modifies m_adding as well.

10.51.1.2 bool seq64::Seq24SeqEventInput::on_button_press_event (GdkEventButton * a_ev, seqevent & seqev)

Set values for dragging, then reset the box that holds dirty redraw spot. Then do the rest.

Returns

Returns true if a likely modification was made. This function used to return true all the time.

Needs update. seqev.m_seq.unselect(); ???????

10.51.1.3 bool seq64::Seq24SeqEventInput::on_button_release_event (GdkEventButton * a_ev, seqevent & seqev)

Returns

Returns true if a likely modification was made. This function used to return true all the time.

10.51.1.4 bool seq64::Seq24SeqEventInput::on_motion_notify_event (GdkEventMotion * a_ev, seqevent & seqev)

Returns

Returns true if a likely modification was made. This function used to return true all the time.

10.52 seq64::Seq24SeqRollInput Class Reference

Implements the Seq24 mouse interaction paradigm for the seqroll.

Public Member Functions

• Seq24SeqRollInput ()

Default constructor.

• void set_adding (bool a_adding, seqroll &ths)

Changes the mouse cursor pixmap according to whether a note is being added or not.

• bool on_button_press_event (GdkEventButton *a_ev, seqroll &ths)

Implements the on-button-press event handling for the Seq24 style of mouse interaction.

bool on_button_release_event (GdkEventButton *a_ev, seqroll &ths)

Implements the on-button-release event handling for the Seq24 style of mouse interaction.

• bool on_motion_notify_event (GdkEventMotion *a_ev, seqroll &ths)

Seq24-style on-motion mouse interaction.

10.52.1 Member Function Documentation

10.52.1.1 void seq64::Seq24SeqRollInput::set_adding (bool adding, seqroll & sroll)

What calls this? It is actually a right click.

10.52.1.2 bool seq64::Seq24SeqRollInput::on_button_press_event (GdkEventButton * ev, seqroll & sroll)

This function now uses the needs_update flag to determine if the perform object should modify().

Returns

Returns the value of needs_update. It used to return only true.

10.52.1.3 bool seq64::Seq24SeqRollInput::on_button_release_event (GdkEventButton * ev, seqroll & sroll)

This function now uses the needs update flag to determine if the perform object should modify().


Returns

Returns the value of needs_update. It used to return only true.

10.53 seq64::seqdata Class Reference

This class supports drawing piano-roll eventis on a window.

Inheritance diagram for seq64::seqdata:



Public Member Functions

- seqdata (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust)

 Principal constructor.
- void reset ()

This function calls update_size().

• void redraw ()

Updates the pixmap and queues up a redraw operation.

void set_zoom (int a_zoom)

Sets the zoom to the given value and resets the view via the reset function.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given value, and the control to the optional given value, which defaults to 0, then calls redraw().

Private Member Functions

• int idle redraw ()

Draws events on this object's built-in window and pixmap.

• void update sizes ()

Updates the sizes in the pixmap if the view is realized, and queues up a draw operation.

void update pixmap ()

Simply calls draw_events_on_pixmap().

void draw_line_on_window ()

Draws on vertical line on the data window.

void xy_to_rect (int x1, int y1, int x2, int y2, int &rx, int &ry, int &rw, int &rh)

This function takes two points, and returns an Xwin rectangle, returned via the last four parameters.

void draw events on (Glib::RefPtr< Gdk::Drawable > drawable)

Draws events on the given drawable object.

void change_horz ()

Change the scrolling offset on the x-axis, and redraw.

· void force_draw ()

Force a redraw.

void convert_x (int x, midipulse &tick)

This function takes screen coordinates, and gives the horizontaol tick value based on the current zoom, returned via the second parameter.

• void render_number (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, const char *const num)

Convenience function for rendering numbers.

void draw_events_on_pixmap ()

Simply calls draw_events_on() for this object's built-in pixmap.

void draw_pixmap_on_window ()

Simply queues up a draw operation.

void on_realize ()

Implements the on-realization event, by calling the base-class version and then allocating the resources that could not be allocated in the constructor.

• bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Implement a button-press event.

• bool on_button_release_event (GdkEventButton *ev)

Implement a button-release event.

bool on_motion_notify_event (GdkEventMotion *ev)

Handles a motion-notify event.

bool on_leave_notify_event (GdkEventCrossing *ev)

Handles an on-leave notification event.

• bool on_scroll_event (GdkEventScroll *ev)

Implements the on-scroll event.

void on_size_allocate (Gtk::Allocation &)

Handle a size-allocation event.

Private Attributes

• int m zoom

one pixel == m_zoom ticks

· int m number w

The adjusted width of a digit in a data number.

· int m_number_h

The adjusted height of all digits in a data number.

int m number offset y

A new value to make it easier to adapt the vertical number drawing of a data item's numeric value to a different font.

• midibyte m_status

What is the data window currently editing?

Additional Inherited Members

10.53.1 Constructor & Destructor Documentation

```
10.53.1.1 seq64::seqdata::seqdata ( sequence & seq, perform & p, int zoom, Gtk::Adjustment & hadjust )
```

In the constructor you can only allocate colors, get_window() returns 0 because we have not been realized.

10.53.2 Member Function Documentation

```
10.53.2.1 void seq64::seqdata::reset ( )
```

Then, regardless of whether the view is realized, updates the pixmap and queues up a draw operation.

Note

If it weren't for the is realized() condition, we could just call update sizes(), which does all this anyway.

```
10.53.2.2 void seq64::seqdata::set_zoom ( int zoom )
```

This begs the question, do we have GUI access to the zoom setting?

```
10.53.2.3 void seq64::seqdata::set_data_type ( midibyte status, midibyte control )
```

Perhaps we should check that at least one of the parameters causes a change.

```
10.53.2.4 int seq64::seqdata::idle_redraw( ) [private]
```

This drawing is done only if there is no dragging in progress, to guarantee no flicker.

```
10.53.2.5 void seq64::seqdata::update_sizes() [private]
```

It creates a pixmap with window dimensions given by m_window_x and m_window_y.

10.53.2.6 void seq64::seqdata::xy_to_rect(int x1, int y1, int x2, int y2, int & rx, int & ry, int & rw, int & rh) [private]

It checks the mins/maxes, then fills in x, y, and width, height.

```
10.53.2.7 void seq64::seqdata::on_realize( ) [private]
```

It also connects up the change_horz() function.

Note that this function creates a small pixmap for every possible y-value, where y ranges from 0 to MIDI_COUNT \leftarrow _MAX-1 = 127. It then fills each pixmap with a numeric representation of that y value, up to three digits (left-padded with spaces).

```
10.53.2.8 bool seq64::seqdata::on_button_press_event ( GdkEventButton * ev ) [private]
```

Returns

Always returns true.

```
10.53.2.9 bool seq64::seqdata::on_button_release_event( GdkEventButton * ev ) [private]
```

Returns

Returns true if a modification occurred, and in that case also sets the perform modification flag.

```
10.53.2.10 bool seq64::seqdata::on_motion_notify_event( GdkEventMotion * ev ) [private]
```

It converts the x,y of the mouse to ticks, then sets the events in the event-data-range, updates the pixmap, draws events in the window, and draws a line on the window.

Returns

Returns true if a change in event data occurred. If true, then the perform modification flag is set.

```
10.53.2.11 bool seq64::seqdata::on_scroll_event( GdkEventScroll * a_ev ) [private]
```

This scroll event only handles basic scrolling, without any modifier keys such as SEQ64_CONTROL_MASK or SEQ64K_SHIFT_MASK.

Returns

Always returns true.

10.53.3 Field Documentation

```
10.53.3.1 int seq64::seqdata::m_number_w [private]
```

By "adjusted", well this is just a minor tweak for appearances.

```
10.53.3.2 int seq64::seqdata::m_number_h [private]
```

Basically, the character height times 3. By "adjusted", well this is just a minor tweak for appearances.


```
10.53.3.3 int seq64::seqdata::m_number_offset_y [private]
```

This value was hardwired as 8, for a character height of 10.

10.54 seq64::seqedit Class Reference

Implements the Pattern Editor, which has references to:

Inheritance diagram for seq64::seqedit:



Public Member Functions

seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 Principal constructor.

∼seqedit ()

A rote destructor.

Private Member Functions

void set_zoom (int zoom)

Selects the given zoom value.

void set_snap (int snap)

Selects the given snap value.

· void set note length (int note length)

Selects the given note-length value.

void set_beats_per_bar (int bpm)

Set the bpm (beats per measure) value, using the given parameter, and some internal values passed to apply_\(-\cup \left| \left| \left| \text{length}().

void set_beat_width (int bw)

Set the bw (beat width) value, using the given parameter, and some internal values passed to apply_length().

void set rec vol (int recvol)

Passes the given parameter to sequence::set_rec_vol().

· void set measures (int lim)

Set the measures value, using the given parameter, and some internal values passed to apply_length().

void apply_length (int bpm, int bw, int measures)

Sets the sequence length based on the three given parameters.

long get_measures ()

Calculates the measures value based on the bpm (beats per measure), ppqn (parts per quarter note), and bw (beat width) values, and returns the resultant measures value.

void set_midi_channel (int midichannel)

Selects the given MIDI channel parameter in the main sequence object, so that it will use that channel.

void set_midi_bus (int midibus)

Selects the given MIDI buss parameter in the main sequence object, so that it will use that buss.

void set_scale (int scale)

Selects the given scale value.

• void set_key (int note)

Selects the given key (signature) value.

void set_background_sequence (int seq)

Draws the given background sequence on the Pattern editor so that the musician has something to see that can be played against.

• void name change callback ()

Set the name for the main sequence to this object's entry name.

void play_change_callback ()

Passes the play status to the sequence object.

void record_change_callback ()

Passes the recording status to the sequence object.

void q_rec_change_callback ()

Passes the quantized-recording status to the sequence object.

void thru_change_callback ()

Passes the MIDI Thru status to the sequence object.

void undo_callback ()

Pops an undo operation from the sequence object, and then tell the segroll, seqtime, seqdata, and seqevent objects to redraw.

void redo_callback ()

Pops a redo operation from the sequence object, and then tell the segroll, seqtime, seqdata, and seqevent objects to redraw.

void set_data_type (midibyte status, midibyte control=0)

Sets the data type based on the given parameters.

void fill_top_bar ()

This function inserts the user-interface items into the top bar or panel of the pattern editor; this bar has two rows of user interface elements.

· void create menus ()

Creates the various menus by pushing menu elements into the menus.

void popup_menu (Gtk::Menu *menu)

Pops up the given pop-up menu.

void popup_event_menu ()

Populates the event-selection menu that drops from the "Event" button in the bottom row of the Pattern editor.

• void popup_midibus_menu ()

Populates the MIDI Output buss pop-up menu.

void popup_sequence_menu ()

Populates the "set background sequence" menu (drops from the button that has some note-bars on it at the right of the second row of the top bar).

void popup_tool_menu ()

Sets up the pop-up menus that are brought up by pressing the Tools button, which shows a hammer image.

void popup_midich_menu ()

Populates the MIDI Channel pop-up menu.

Gtk::Image * create_menu_image (bool state=false)

Sets the manu pixmap depending on the given state, where true is a full menu (black backgroun), and empty menu (gray background).

• bool timeout ()

Update the window after a time out, based on dirtiness and on playback progress.

· void do action (int action, int var)

Implements the actions brought forth from the Tools (hammer) button.

void on_realize ()

On realization, calls the base-class version, and connects the redraw timeout signal, timed at c_redraw_ms.

bool on_delete_event (GdkEventAny *event)

Handles an on-delete event.

• bool on scroll event (GdkEventScroll *ev)

Handles an on-scroll event.

bool on_key_press_event (GdkEventKey *ev)

Handles a key-press event.

Private Attributes

• int m zoom

Provides the zoom values: 0 1 2 3 4, and 1, 2, 4, 8, 16.

• int m_snap

Use in setting the snap-to in pulses, off = 1.

• int m scale

Settings for the music scale and key.

• Gtk::Menu * m_menu_length

Provides the length in measures.

• Gtk::Menu * m menu bpm

These member provife the time signature, beats per measure, and beat width menus.

• int m_pos

Basically the sequence number.

• midibyte m_editing_status

Indicates what is the data window currently editing?

Static Private Attributes

static int m_initial_snap
 Static data members.

Additional Inherited Members

10.54.1 Detailed Description

- · perform
- · segroll
- · seqkeys
- seqdata
- · segtime
- · segevent
- · sequence

This class has a metric ton of user-interface objects and other members.

10.54.2 Constructor & Destructor Documentation

```
10.54.2.1 seq64::seqedit::seqedit ( perform & p, sequence & seq, int pos, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

If provided, override the scale, key, and background-sequence with the values stored in the file with the sequence, if they are set to non-default values. This is a new feature.

Todo Offload most of the work into an initialization function like options does.

10.54.3 Member Function Documentation

```
10.54.3.1 void seq64::seqedit::set_zoom(int z) [private]
```

It is passed to the seqroll, seqtime, seqdata, and seqevent objects, as well.

The notation is in pixels:ticks, but I would prefer to use pulses/pixel (pulses per pixel). Oh well.

Finally, note that this value of zoom is saved to the "user" configuration file when Sequencer64 exit.

```
10.54.3.2 void seq64::seqedit::set_snap( int snap ) [private]
```

It is passed to the seqroll, seqevent, and sequence objects, as well.

```
10.54.3.3 void seq64::seqedit::set_note_length ( int notelength ) [private]
```

It is passed to the seqroll object, as well.

Warning

Currently, we don't handle changes in the global PPQN after the creation of the menu. The creation of the menu hard-wires the values of note-length. To adjust for a new global PQN, we will need to store the original PPQN (m_original_ppqn = m_ppqn), and then adjust the notelength based on the new PPQN. For example if the new PPQN is twice as high as 192, then the notelength should double, though the text displayed in the "Note length" field should remain the same. A double value would be needed to handle the setting of a smaller m_ppqn. Not needed until we support a set_ppqn() function in this class. Another option is to rebuild the menu.

Parameters

notelenath	Provides the note length in units of MIDI pulses. For example
Hotelength	1 Tovides the note length in drifts of Miles pulses. To example

10.54.3.4 void seq64::seqedit::set_measures(int lim) [private]

Parameters

lim Provides the sequence length, in measures.

```
10.54.3.5 void seq64::seqedit::apply_length ( int bpm, int bw, int measures ) [private]
```

There's an implicit "adjust-triggers = true" parameter used in sequence::set_length().

Then the segroll, segtime, segdata, and segevent objects are reset().

```
10.54.3.6 long seq64::seqedit::get_measures( ) [private]
```

Todo Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

```
10.54.3.7 void seq64::seqedit::set_midi_channel(int midichannel) [private]
```

Should this change raise the is-modified flag?

```
10.54.3.8 void seq64::seqedit::set_midi_bus(int bus) [private]
```

Should this change raise the is-modified flag?

```
10.54.3.9 void seq64::seqedit::set_scale( int scale ) [private]
```

It is passed to the seqroll and seqkeys objects, as well. As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

```
10.54.3.10 void seq64::seqedit::set_key( int key ) [private]
```

It is passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

```
10.54.3.11 void seq64::seqedit::set_background_sequence(int seqnum) [private]
```

As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data, but only if less or equal to the maximum single-byte MIDI value, 127.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

Todo Make the sequence pointer a reference.

```
10.54.3.12 void seq64::seqedit::name_change_callback( ) [private]
```

That name is the name the user has given to the sequence being edited.

```
10.54.3.13 void seq64::seqedit::set_data_type ( midibyte status, midibyte control = 0 ) [private]
```

This function uses the hardwired array c_controller_names.

Parameters

status	The current editing status.
control	The control value. However, we really need to validate it!

```
10.54.3.14 void seq64::seqedit::create_menus() [private]
```

The first menu is the Zoom menu, represented in the pattern/sequence editor by a button with a magnifying glass. The values are "pixels to ticks", where "ticks" are actually the "pulses" of "pulses per quarter note". We would prefer the notation "n" instead of "1:n", as in "n pulses per pixel". The Snap menu is actually the Grid Snap button, which shows two arrows pointing to a central bar.

The note-length menu is on the button that shows four notes.

This menu lets one set the key of the sequence, and is brought up by the button with the "golden key" image on it.

This button shows a down around for the bottom half of the time signature. It's tooltip is "Time signature. Length of beat." But it is called bw, or beat width, in the code.

This menu is shown when pressing the button at the bottom of the window that has "Vol" as its label. Let's show the numbers as well to help the user. And we'll have to document this change.

This menu sets the scale to show on the panel, and the button shows a "staircase" image. See the c_music_scales enumeration defined in the globals module.

This section sets up two different menus. The first is m_menu_length. This menu lets on set the sequence length in bars (not the MIDI channel). The second menu is the m_menu_bpm, or BPM, which here means "beats per measure" (not "beats per minute").

```
10.54.3.15 void seq64::seqedit::popup_event_menu() [private]
```

This menu has a large number of items. I think they are filled in in code, but can also be loaded from \sim /.seq24usr. To be determined. Create the 8 sub-menus for the various ranges of controller changes, shown 16 per sub-menu.

```
10.54.3.16 void seq64::seqedit::popup_midibus_menu() [private]
```

The MIDI busses are obtained by getting the mastermidibus object, and iterating through the busses that it contains.

```
10.54.3.17 void seq64::seqedit::popup_sequence_menu() [private]
```

It is populated with an "Off" menu entry, and a second "[0]" menu entry that pulls up a drop-down menu of all of the patterns/sequences that are present in the MIDI file for screen-set 0. If more screensets have active sequences, then their screen-set number appears in the screen-set section of the menu.

Now, at present, we can only save background sequence numbers that are less than 128, which means the sequences from 0 to 127, or the first four screen sets. Higher sequences can be selected, but, right now, they cannot be saved. We'll probably fix that at some point, low priority.

```
10.54.3.18 void seq64::seqedit::popup_tool_menu( ) [private]
```

This button shows three sub-menus that need to be filled in by this function. All the functions accessed here seem to be implemented by the do_action() function.

```
10.54.3.19 void seq64::seqedit::do_action(int action, int var) [private]
```

Note that the push_undo() calls push all of the current events (in sequence::m_events) onto the stack (as a single entry).

```
10.54.3.20 bool seq64::seqedit::on_delete_event ( GdkEventAny * event ) [private]
```

It tells the sequence to stop recording, tells the perform object's mastermidibus to stop processing input, and sets the sequence object's editing flag to false.

Warning

This function also calls "delete this"!

Returns

Always returns false.

10.54.4 Field Documentation

```
10.54.4.1 int seq64::seqedit::m_initial_snap [static], [private]
```

These items apply to all of the instances of segedit, and are passed on to the following constructors:

- seqdata
- · segevent
- · seqroll
- · seqtime

The snap and note-length defaults would be good to write to the "user" configuration file. The scale and key would be nice to write to the proprietary section of the MIDI song. Or, even more flexibly, to each sequence, if that makes sense to do, since all tracks would generally be in the same key. Right, Charles Ives?

Note that, currently, that some of these "initial values" are modified, so that they are "contagious". That is, the next sequence to be opened in the sequence editor will adopt these values. This is a long-standing feature of Seq24, but strikes us as a bit too surprising and tricky.

10.55 seq64::seqevent Class Reference

Implements the piano event drawing area.

Inheritance diagram for seq64::seqevent:



Public Member Functions

seqevent (perform &p, sequence &seq, int zoom, int snap, seqdata &seqdata_wid, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

• void reset ()

This function basically resets the whole widget as if it was realized again.

· void redraw ()

Adjusts the scrolling offset for ticks, updates the pixmap, and draws it on the window.

void set zoom (int a zoom)

Sets zoom to the given value, and resets if the value ended up being changed.

void set snap (int a snap)

'Setter' function for member m snap

void set_data_type (midibyte a_status, midibyte a_control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

• void update_sizes ()

If the window is realized, this function creates a pixmap with window dimensions, the updates the pixmap, and queues up a redraw.

void draw_background ()

This function updates the background.

void draw_events_on_pixmap ()

This function fills the main pixmap with events.

void draw_pixmap_on_window ()

This function currently just queues up a draw operation for the pixmap.

void draw_selection_on_window ()

Draw the selected events on the window.

void update_pixmap ()

Redraws the background pixmap on the main pixmap, then puts the events on.

Private Member Functions

• int idle_redraw ()

Implements redraw while idling.

void x_to_w (int a_x1, int a_x2, int &a_x, int &a_w)

This function checks the mins / maxes.

void drop_event (midipulse a_tick)

Drops (adds) an event at the given tick.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > a_draw)

Draws events on the given drawable object.

void start_paste ()

Starts a paste operation.

• void change_horz ()

Changes the horizontal scrolling offset for ticks, then updates the pixmap and forces a redraw.

· void force_draw ()

Forces a draw on the current drawable area of the window.

• void convert x (int x, midipulse &tick)

Takes the screen x coordinate, multiplies it by the current zoom, and returns the tick value in the given parameter.

void convert_t (midipulse ticks, int &x)

Converts the given tick value to an x corrdinate, based on the zoom, and returns it via the second parameter.

void snap_y (int &y)

This function performs a 'snap' on y.

void snap_x (int &a_x)

This function performs a 'snap' on x.

void on_realize ()

Implements the on-realize callback.

bool on_expose_event (GdkEventExpose *a_ev)

Implements the on-expose event callback.

bool on_button_press_event (GdkEventButton *a_ev)

Implements the on-button-press event callback.

bool on_button_release_event (GdkEventButton *a_ev)

Implements the on-button-release event callback.

bool on_motion_notify_event (GdkEventMotion *a_ev)

Implements the on-motion-notify event callback.

bool on_focus_in_event (GdkEventFocus *)

Responds to a focus event by setting the HAS_FOCUS flag.

bool on_focus_out_event (GdkEventFocus *)

Responds to a unfocus event by resetting the HAS_FOCUS flag.

bool on_key_press_event (GdkEventKey *a_p0)

Implements the key-press event callback function.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event callback.

Private Attributes

• FruitySeqEventInput m_fruity_interaction

Why should we need both at the same time? Just load the one that is specified in the configuration.

• int m zoom

Zoom setting, means that one pixel == m_zoom ticks.

• bool m_selecting

Used when highlighting a bunch of events.

• midibyte m_status

Indicates what is the data window currently editing?

Additional Inherited Members

10.55.1 Member Function Documentation

```
10.55.1.1 void seq64::seqevent::set_snap ( int a_snap ) [inline]
```

Simply sets the snap member.

```
10.55.1.2 void seq64::seqevent::set_data_type ( midibyte status, midibyte control = 0 )
```

Then redraws.

```
10.55.1.3 void seq64::seqevent::update_sizes ( )
```

This ends up filling the background with dotted lines, etc.

```
10.55.1.4 void seq64::seqevent::draw_background()
```

It sets the foreground to white, draws the rectangle, in order to clear the pixmap.

```
10.55.1.5 void seq64::seqevent::draw_pixmap_on_window()
```

Old comments:

```
It then tells event to do the same. We changed something on this window, and chances are we need to update the event widget as well and update our velocity window.
```

```
10.55.1.6 int seq64::seqevent::idle_redraw( ) [private]
```

Who calls this routine?

```
10.55.1.7 void seq64::seqevent::x_to_w ( int a_x1, int a_x2, int & a_x, int & a_w ) [private]
```

Then it fills in x and the width.

```
10.55.1.8 void seq64::seqevent::drop_event( midipulse a_tick ) [private]
```

It sets the first byte properly for after-touch, program-change, channel-pressure, and pitch-wheel. The type of event is determined by m_status.

```
10.55.1.9 void seq64::seqevent::draw_events_on( Glib::RefPtr< Gdk::Drawable > draw) [private]
```

Parameters

```
draw The given drawable object.
```

```
10.55.1.10 void seq64::seqevent::start_paste( ) [private]
```

It gets the clipboard box that selected elements are in, makes a coordinate conversion, and then, sets the m_\circ} selected rectangle to hold the (x,y,w,h) of the selected events.

```
10.55.1.11 void seq64::seqevent::convert_x (int x, midipulse & tick ) [inline], [private]
```

Why not just return it normally?

```
10.55.1.12 void seq64::seqevent::convert_t ( midipulse ticks, int & x ) [inline], [private]
```

Why not just return it normally?

```
10.55.1.13 void seq64::seqevent::snap_x(int & x) [private]
```

- snap = number pulses to snap to
- m_zoom = number of pulses per pixel
- Therefore snap / m_zoom = number of pixels to snap to.

```
10.55.1.14 void seq64::seqevent::on_realize( ) [private]
```

It calls the base-class version, and then allocates additional resource not allocated in the constructor. Finally, it connects up the change_horz function.

```
10.55.1.15 bool seq64::seqevent::on_button_press_event ( GdkEventButton * a_ev ) [private]
```

It distinguishes between the Seg24 and Fruity varieties of mouse interaction.

Odd. In the legacy code, each case fell through to the next case to the "default" case! We will assume for now that this is incorrect.

Note that returning "true" from a Gtkmm event-handler stops the propagation of the event to higher-level widgets. The Fruity and Seq24 event handlers return true, always. In the legacy code, though, the fall-through code caused false to be returned, always. Not sure what effect this had. Added some fixes, but then commented them out until better testing can be done.

```
10.55.1.16 bool seq64::seqevent::on_button_release_event ( GdkEventButton * a_ev ) [private]
```

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

```
10.55.1.17 bool seg64::segevent::on motion notify event ( GdkEventMotion * a ev ) [private]
```

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

```
10.55.1.18 bool seq64::seqevent::on_key_press_event( GdkEventKey * ev ) [private]
```

It handles deleted a selection via the Backspace or Delete keys, cut via Ctrl-X, copy via Ctrl-C, paste via Ctrl-V, and undo via Ctrl-Z.

Would be nice to provide redo functionality via Ctrl-Y. :-)


Returns

Returns true if an event was handled. Only some of the handled events also cause the perform modification flag to be set as a side-effect.

10.56 seq64::seqkeys Class Reference

This class implements the left side piano of the pattern/sequence editor.

Inheritance diagram for seq64::seqkeys:



Public Member Functions

• seqkeys (sequence &seq, perform &p, Gtk::Adjustment &vadjust)

Principal constructor.

• void set_scale (int a_scale)

Sets the musical scale, then resets.

void set_key (int a_key)

Sets the musical key, then resets.

void set_hint_key (int a_key)

Sets a key to grey so that it can serve as a scale hint.

void set_hint_state (bool a_state)

Sets the hint state to the given value.

Private Member Functions

· void draw area ()

Draws the updated pixmap on the drawable area of the window where the keys' location is hardwired.

void update_pixmap ()

Updates the pixmaps to prepare it for the next draw operation.

• void convert y (int a y, int &a note)

Takes the screen y coordinate, and returns the note value in the second parameter.

void draw_key (int a_key, bool a_state)

Draws the given key according to the given state.

· void change_vert ()

Changes the y offset of the scrolling, and the forces a draw.

void force draw ()

Forces a draw operation on the whole window.

· void reset ()

Resetting the keys view updates the pixmap and queues up a draw operation.

· bool is_black_key (int key) const

Detects a black key.

• void on_realize ()

Implements the on-realize event.

bool on_expose_event (GdkEventExpose *a_ev)

Implements the on-expose event, by drawing on the window.

bool on_button_press_event (GdkEventButton *a_ev)

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *a_ev)

Implements the on-button-release event callback.

• bool on motion notify event (GdkEventMotion *a p0)

Implements the on-motion-notify event handler.

bool on_enter_notify_event (GdkEventCrossing *p0)

Implements the on-enter notification event handler.

bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave notification event handler.

bool on scroll event (GdkEventScroll *a ev)

Implements the on-scroll-event notification event handler.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocation notification event handler.

Private Attributes

bool m keying

What is this?

Additional Inherited Members

- 10.56.1 Member Function Documentation
- 10.56.1.1 void seq64::seqkeys::set_hint_state (bool state)

Parameters

state	Provides the value for hinting, where true == on, false == off.
-------	---

10.56.1.2 void seq64::seqkeys::draw_key(int key, bool state) [private]

It accounts for the black keys and the white keys, and for the highlighting of the active key.

Parameters

key	The key to be drawn.
state	How the key is to be drawn, where false == normal, true == grayed. A key is greyed when the
	mouse cursor is at the same vertical location on the piano as the key.

10.56.1.3 void seq64::seqkeys::on_realize() [private]

Call the base-class version and then allocates resources that could not be allocated in the constructor. It connects the change_vert() function and then calls it.

```
10.56.1.4 bool seq64::seqkeys::on_button_press_event( GdkEventButton * ev ) [private]
```

It currently handles only the left button. This button, pressed on the piano keyboard, causes m_keying to be set to true, and the given note to play.

Returns

Always returns true.

```
10.56.1.5 bool seq64::seqkeys::on_button_release_event ( GdkEventButton * ev ) [private]
```

It currently handles only the left button, and only if m_keying is true.

This function is used after pressing on one of the keys on the left-side

Returns

Always returns true. piano keyboard, to make it play, and turns off the playing of the note. Always returns true.

```
10.56.1.6 bool seq64::seqkeys::on_motion_notify_event( GdkEventMotion * a_p0 ) [private]
```

This allows rolling down the keyboard, playing the notes one-by-one.

Returns

Always returns false.

```
10.56.1.7 bool seq64::seqkeys::on_enter_notify_event ( GdkEventCrossing * p0 ) [private]
```


I think this greys the current key.

10.56.1.8 bool seq64::seqkeys::on_leave_notify_event(GdkEventCrossing * p0) [private]

I think this un-greys the current key.

10.57 seq64::seqmenu Class Reference

This class handles the right-click menu of the sequence slots in the pattern window. Inheritance diagram for seq64::seqmenu:



Public Member Functions

• segmenu (perform &a_p)

Principal constructor.

virtual ∼seqmenu ()

Provides a rote base-class destructor.

• int current sequence () const

'Getter' function for member m_current_seq

bool is_modified () const

'Getter' function for member m_modified

Protected Member Functions

void current sequence (int seq)

'Setter' function for member m_current_seq

void is_modified (bool flag)

'Setter' function for member m modified

sequence * get_current_sequence () const

'Getter' function for member m_mainperf.get_sequence(current_sequence()) This call is used many, many times.

void popup menu ()

This function sets up the File menu entries.

void seq_edit ()

This menu callback launches the sequence-editor (pattern editor) window.

void seq event edit ()

This menu callback launches the new event editor window.

Private Member Functions

· void seq_new ()

This function sets the new sequence into the perform object, a bit prematurely, though.

void seq copy ()

Copies the selected (current) sequence to the clipboard sequence.

void seq_cut ()

Deletes the selected (current) sequence and copies it to the clipboard sequence, if it is not in edit mode.

• void seq_paste ()

Pastes the sequence clipboard into the current sequence, if the current sequence slot is not active.

void seq_clear_perf ()

If the current sequence is active, this function pushes a trigger undo in the main perform object, clears its sequence triggers for the current sequence, and sets the dirty flag of the sequence.

void set_bus_and_midi_channel (int a_bus, int a_ch)

Sets up the bus, MIDI channel, and dirtiness flag of the current sequence in the main perform object, as per the give parameters.

void mute_all_tracks ()

Mutes all tracks in the main perform object.

Private Attributes

· perform & m_mainperf

Provides a reference to the central object involved in managing a song and performance.

· sequence m clipboard

Holds a copy of data concerning a sequence, which can then be pasted into another pattern slot.

seqedit * m_seqedit

Points to the latest sequdit object, if created.

• eventedit * m eventedit

Points to the latest eventedit object, if created.

int m_current_seq

References the current sequence by sequence number.

· bool m modified

Indicates if a sequence has been created.

10.57.1 Detailed Description

It is an abstract base class.

10.57.2 Constructor & Destructor Documentation

```
10.57.2.1 seq64::seqmenu::seqmenu ( perform & p )
```

Apart from filling in some of the members, this function initializes the clipboard, so that we don't get a crash on a paste with no previous copy.

```
10.57.2.2 seq64::seqmenu::~seqmenu() [virtual]
```

A rote destructor.

This is necessary in an abstraction base class.

If we determine that we need to delete the m_sequedit pointer, we can do it here. But that is not likely, because we can have many new sequedit objects in play, because we can edit many at once.

10.57.3 Member Function Documentation

```
10.57.3.1 void seq64::seqmenu::popup_menu() [protected]
```

It also sets up the pattern popup menu entries that are used in mainwid. Note that, for the selected sequence, the "Edit" and "Event Edit" menu entries are not included if a pattern editor or event editor is already running.

```
10.57.3.2 void seq64::seqmenu::seq_edit( ) [protected]
```

If it is already open for that sequence, this function just raises it.

Note that the m_seqedit member to which we save the new pointer is currently there just to avoid a compiler warning.

Also, if a new sequences is created, we set the m_modified flag to true, even though the sequence might later be deleted. Too much modification to keep track of!

An oddity is that calling show_all() here does not work unless the seqedit() constructor makes its show_all() call.

```
10.57.3.3 void seq64::seqmenu::seq_event_edit( ) [protected]
```

If it is already open for that sequence, this function just raises it.

Note that the m_eventedit member to which we save the new pointer is currently there just to avoid a compiler warning.

This menu entry is available only if the selected sequence is active. That is, if the sequence has already been created

An oddity is that we need the show_all() call here in order to see the dialog. A situation different from that for seqedit!

```
10.57.3.4 void seq64::seqmenu::seq_new() [private]
```

For one thing, if current_sequence() is either a -1 or is greater than the maximum allowed sequence number, perform::is_active() will return false, and we have no idea whether the sequence is not active or the sequence number is just invalid. So we need to check the pointer we got before trying to use it.

```
10.57.3.5 void seq64::seqmenu::seq_copy( ) [private]
```

Todo Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

```
10.57.3.6 void seq64::seqmenu::seq_cut( ) [private]
```

Todo A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

```
10.57.3.7 void seq64::seqmenu::seq_paste( ) [private]
```

Then it sets the dirty flag for the destination sequence.

Todo All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

```
10.57.3.8 void seq64::seqmenu::seq_clear_perf( ) [private]
```

Todo All of seq paste() can be offloaded to a (new) perform member function.

10.57.4 Field Documentation

```
10.57.4.1 seqedit* seq64::seqmenu::m_seqedit [private]
```

Change Note Added by Chris on 2015-08-02 based on compiler warnings and a comment warning in the seq_edit() function. We'll save the result of that function here, and will let valgrind tell us later if Gtkmm takes care of it.

```
10.57.4.2 bool seq64::seqmenu::m_modified [private]
```

Todo We need to make sure that the perform object is in control of the modification flag.

10.58 seg64::segroll Class Reference

Implements the piano roll section of the pattern editor.

Inheritance diagram for seq64::seqroll:



Public Member Functions

• seqroll (perform &perf, sequence &seq, int zoom, int snap, seqkeys &seqkeys_wid, int pos, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

∼seqroll ()

Provides a destructor to delete allocated objects.

· void reset ()

This function basically resets the whole widget as if it was realized again.

· void redraw ()

Redraws unless m_ignore_redraw is true.

void redraw_events ()

Redraws events unless m_ignore_redraw is true.

void set_key (int key)

Sets the music key to the given value, and then resets the view.

void set scale (int scale)

Sets the music scale to the given value, and then resets the view.

void set snap (int snap)

Sets the snap to the given value, and then resets the view.

void set zoom (int zoom)

Sets the zoom to the given value, and then resets the view.

void set_note_length (int note_length)

'Setter' function for member m_note_length

void set_ignore_redraw (bool ignore)

'Setter' function for member m_ignore_redraw

void set_data_type (midibyte status, midibyte control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

void set_background_sequence (bool state, int seq)

This function sets the given sequence onto the piano roll of the pattern editor, so that the musician can have another pattern to play against.

void update_pixmap ()

This function draws the background pixmap on the main pixmap, and then draws the events on it.

• void update_sizes ()

Update the sizes of items based on zoom, PPQN, BPM, BW (beat width) and more.

void update_background ()

Updates the background of this window.

• void draw_background_on_pixmap ()

Draws the main pixmap.

void draw_events_on_pixmap ()

Fills the main pixmap with events.

void draw_selection_on_window ()

Draws the current selecton on the main window.

void draw_progress_on_window ()

Draw a progress line on the window.

· void start_paste ()

Starts a paste operation.

• void update_and_draw (int force=false)

Wraps up some common code.

Private Member Functions

• int idle redraw ()

Draw the events on the main window and on the pixmap.

void convert_tn (midipulse ticks, int note, int &x, int &y)

This function takes the given note and tick, and returns the screen coordinates via the pointer parameters.

void snap x (int &x)

Performs a 'snap' operation on the x coordinate.

void xy_to_rect (int x1, int y1, int x2, int y2, int &x, int &y, int &w, int &h)

This function checks the mins / maxes, and then fills in the x, y, width, and height values.

void convert_tn_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l, int &x, int &y, int &w, int &h)

Converts a tick/note box to an x/y rectangle.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

Draws events on the given drawable area.

• void change_horz ()

Change the horizontal scrolling offset and redraw.

void change_vert ()

Change the vertical scrolling offset and redraw.

· void force_draw ()

Set the pixmap into the window and then draws the selection on it.

void on realize ()

Implements the on-realize event handling.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event handling.

• bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event handling.

• bool on_button_release_event (GdkEventButton *ev)

Implements the on-button-release event handling.

• bool on_motion_notify_event (GdkEventMotion *ev)

Implements the on-motion-notify event handling.

bool on_focus_in_event (GdkEventFocus *)

Implements the on-focus event handling.

bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

• bool on_key_press_event (GdkEventKey *ev)

Implements the on-key-press event handling.

bool on_scroll_event (GdkEventScroll *a_ev)

Implements the on-scroll event handling.

• void on size allocate (Gtk::Allocation &)

Implements the on-size-allocate event handling.

bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave-notify event handling.

bool on enter notify event (GdkEventCrossing *p0)

Implements the on-enter-notify event handling.

Private Attributes

• FruitySeqRollInput m_fruity_interaction

Provides a fruity input object, whether it is needed or not.

• Seq24SeqRollInput m_seq24_interaction

Provides a normal seq24 input object, which is always needed to handle, for example, keystroke input.

• int m_zoom

one pixel == m zoom ticks*

• midibyte m status

Indicates what is the data window currently editing.

• bool m_selecting

When highlighting a bunch of events.

int m_move_delta_x

Tells where the dragging started.

Friends

· class FruitySeqRollInput

These friend implement interaction-specific behavior, although only the Seq24 interactions support keyboard processing.

Additional Inherited Members

```
10.58.1 Member Function Documentation
```

```
10.58.1.1 void seq64::seqroll::reset ( )
```

It's almost identical to the change_horz() function!

```
10.58.1.2 void seq64::seqroll::set_data_type ( midibyte status, midibyte control )
```

Unlike the same function in seqevent, this version does not redraw.

```
10.58.1.3 void seq64::seqroll::set_background_sequence ( bool state, int seq )
```

The state parameter sets the boolean m_drawing_background_seq.

Parameters

```
state If true, the background sequence will be drawn.
```

seq Provides the sequence number, which is checked against the SEQ64_IS_LEGAL_SEQUENCE() macro before being used. This macro allows the value SEQ64_SEQUENCE_LIMIT, which disables the background sequence.

```
10.58.1.4 void seq64::seqroll::update_background()
```

The first thing done is to clear the background, painting it white.

```
10.58.1.5 void seq64::seqroll::draw_events_on_pixmap( )
```

Just calls draw_events_on().

```
10.58.1.6 void seq64::seqroll::convert_tn ( midipulse a_ticks, int a_note, int & a_x, int & a_y ) [private]
```

This function is the "inverse" of convert xy().

```
10.58.1.7 void seq64::seqroll::snap_x ( int & x ) [private]
```

This function is similar to snap y(), but it calculates a modulo value from the snap and zoom settings.

```
- m_snap = number pulses to snap to
- m_zoom = number of pulses per pixel
```

Therefore, m snap / m zoom = number pixels to snap to.

```
10.58.1.8 void seq64::seqroll::draw_events_on( Glib::RefPtr< Gdk::Drawable > draw) [private]
```

"Method 0" seems be the one that draws the background sequence, if active. "Method 1" draws the sequence itself.

10.58.1.9 bool seq64::seqroll::on_key_press_event(GdkEventKey * ev) [private]

The start/end key may be the same key (i.e. SPACEBAR). Allow toggling when the same key is mapped to both triggers (i.e. SPACEBAR).

Concerning the usage of the arrow keys in this function: This code is reached, but has no visible effect. Why? I think they were meant to move the point for playback. We may HAVE A BUG with our new handling of triggers, or maybe these depend upon the proper playback mode. In any case, the old functionality is preserved. However, if there are notes selected, then these keys support selection movement.

10.58.1.10 bool seq64::seqroll::on_scroll_event (GdkEventScroll * ev) [private]

This scroll event only handles basic scrolling without any modifier keys such as SEQ64_CONTROL_MASK or S← EQ64_SHIFT_MASK.

10.59 seq64::seqtime Class Reference

This class implements the piano time, whatever that is.

Inheritance diagram for seq64::seqtime:

```
seq64::gui_palette_gtk2
                                                           seqo4::gul_p
- m_black
- m_white
- m_grey
- m_dk_grey
- m_lt_grey
- m_red
- m_orange
- m_yellow
- m_green
- m_blue
- m_dk_cyan
- m_bg_color
- m_fg_color
- m_ti_palette
                                                - m_tg_color

+ gui_palette_gtk2()
+ yaui_palette_gtk2()
+ black()
+ white()
+ grey()
+ dark_grey()
+ red()
+ variange()
+ yellow()
and 7 more...
          seq64::gui_drawingarea_gtk2
     # m_gc
# m_gc
# m_window
# m_window
# m_vadjust
# m_hadjust
# m_pixmap
# m_bixmap
# m_background
# m_mainperf
# m_window_x
# m_window_y
# m_current_y
# m_drop_x
# m_drop_y
# m_drop_y

gu drawingarea_gtk2()

gu drawingarea_gtk2()

gu drawingarea_gtk2()

yundrawingarea_gtk2()

yundrawingarea_gtk2()

yundrawingarea_gtk2()

yundrawingarea_gtk2()

yundrawingarea_gtk2()

drawingarea_gtk2()

# draw_line()

                                - m_seq
- m_scroll_offset_ticks
- m_scroll_offset_x
- m_zoom
- m_ppqn
          - m_ppqn

+ seqtime()
+ reset()
+ redraw()
+ set_zoom()
- draw_pixmap_on_window()
- draw_pixmap_on_window()
- update_pixmap()
- change_horz()
- update_sizes()
- force_draw()
- idle_progress()
- on_realize()
- on_size_allocate()
- on_button_press_event()
- on_button_release_event()
```

Public Member Functions

• void set_zoom (int zoom)

Sets the zoom to the given value and resets the window.

Private Member Functions

```
    bool idle_progress ()
        Simply returns true.
    bool on_button_press_event (GdkEventButton *)
        Implements the on-button-press event handler.
    bool on_button_release_event (GdkEventButton *)
        Implements the on-button-release event handler.
```

Private Attributes

```
int m_zoomone pixel == m_zoom ticks
```

Additional Inherited Members

10.59.1 Member Function Documentation

```
10.59.1.1 bool seq64::seqtime::on_button_press_event ( GdkEventButton * ) [inline], [private]
Simply returns false.

10.59.1.2 bool seq64::seqtime::on_button_release_event ( GdkEventButton * ) [inline], [private]
Simply returns false.
```

10.60 seg64::sequence Class Reference

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

Public Types

```
enum select_action_e {
e_select,
e_select_one,
e_is_selected,
e_would_select,
e_deselect,
e_toggle_selection,
e_remove_one }
```

Public Member Functions

```
    sequence (int ppqn=SEQ64_USE_DEFAULT_PPQN)
        Principal constructor.
    ~sequence ()
        A rote destructor.
    void partial_assign (const sequence &rhs)
        A cut-down version of principal assignment operator.
```

• event_list & events ()

'Getter' function for member m_events

· const event_list & events () const

'Getter' function for member m events

bool any_selected_notes () const

'Getter' function for member m_events.any_selected_notes()

• triggers::List & triggerlist ()

'Getter' function for member m_triggers

• int number () const

'Getter' function for member m_seq_number

• void number (int seqnum)

'Setter' function for member m_seq_number This setter will set the sequence number only if it has not already been set.

• int event_count () const

Returns the number of events stored in m_events.

void push undo ()

Pushes the event-list into the undo-list.

void pop_undo ()

If there are items on the undo list, this function pushes the event-list into the redo-list, puts the top of the undo-list into the event-list, pops from the undo-list, calls verify_and_link(), and then calls unselect.

void pop redo ()

If there are items on the redo list, this function pushes the event-list into the undo-list, puts the top of the redo-list into the event-list, pops from the redo-list, calls verify_and_link(), and then calls unselect.

· void push trigger undo ()

Calls triggers::push_undo() with locking.

void pop_trigger_undo ()

Calls triggers::pop_undo() with locking.

void set_name (const std::string &name)

Sets the sequence name member, m_name.

void set_name (char *name)

Sets the sequence name member, m_n name.

• int get_ppqn () const

'Getter' function for member m_ppqn Provided as a convenience for the editable_events class.

void set_beats_per_bar (int beatspermeasure)

'Setter' function for member m_time_beats_per_measure

• int get beats per bar () const

'Getter' function for member m_time_beats_per_measure

void set_beat_width (int beatwidth)

'Setter' function for member m time beat width

int get_beat_width () const

'Getter' function for member m_time_beat_width

void set_rec_vol (int rec_vol)

'Setter' function for member m_rec_vol

void set_song_mute (bool mute)

'Setter' function for member m_song_mute

· bool get song mute () const

'Getter' function for member m_song_mute

const char * get_name () const

'Getter' function for member m_name pointer

· const std::string & name () const

'Getter' function for member m_name

void set_editing (bool edit)

'Setter' function for member m_editing

bool get_editing () const

'Getter' function for member m_editing

void set_raise (bool edit)

'Setter' function for member m_raise

• bool get_raise (void) const

'Getter' function for member m_raise

• void set_length (midipulse len, bool adjust_triggers=true)

Sets the length (m_length) and adjusts triggers for it, if desired.

• midipulse get_length () const

'Getter' function for member m length

midipulse get_last_tick ()

Returns the last tick played, and is used by the editor's idle function.

midipulse mod_last_tick ()

Some MIDI file errors and other things can lead to an m_length of 0, which causes arithmetic errors when m_last_tick is modded against it.

void set_playing (bool)

Sets the playing state of this sequence.

• bool get_playing () const

'Getter' function for member m_playing

void toggle_playing ()

Toggles the playing status of this sequence.

void toggle_queued ()

'Setter' function for member m_queued and m_queued_tick

void off_queued ()

'Setter' function for member m_queued

• bool get_queued () const

'Getter' function for member m_queued

midipulse get_queued_tick () const

'Getter' function for member m gueued tick

bool check_queued_tick (midipulse tick) const

Helper function for perform.

void set_recording (bool)

'Setter' function for member m_recording and m_notes_on

bool get_recording () const

'Getter' function for member m_recording

void set_snap_tick (int st)

'Setter' function for member m_snap_tick

void set_quantized_rec (bool qr)

'Setter' function for member m_quantized_rec

• bool get_quantized_rec () const

'Getter' function for member m_quantized_rec

void set_thru (bool)

'Setter' function for member m_thru

• bool get thru () const

'Getter' function for member m_thru

• bool is_dirty_main ()

Returns the value of the dirty main flag, and sets that flag to false (i.e.

• bool is dirty edit ()

Returns the value of the dirty edit flag, and sets that flag to false.

bool is_dirty_perf ()

Returns the value of the dirty performance flag, and sets that flag to false.

• bool is_dirty_names ()

Returns the value of the dirty names (heh heh) flag, and sets that flag to false.

void set_dirty_mp ()

Sets the dirty flags for names, main, and performance.

void set_dirty ()

Call set_dirty_mp() and then sets the dirty flag for editing.

· midibyte get midi channel () const

'Getter' function for member m_midi_channel

• bool is_smf_0 () const

Returns true if this sequence is an SMF 0 sequence.

void set_midi_channel (midibyte ch)

Sets the m_midi_channel number.

• void print ()

Prints a list of the currently-held events.

void print_triggers ()

Prints a list of the currently-held triggers.

void play (midipulse tick, bool playback_mode)

The play() function dumps notes starting from the given tick, and it pre-buffers ahead.

void set_orig_tick (midipulse tick)

'Setter' function for member m_last_tick

· bool add event (const event &er)

Adds an event to the internal event list in a sorted manner.

• void add_trigger (midipulse tick, midipulse len, midipulse offset=0, bool adjust offset=true)

Adds a trigger.

void split_trigger (midipulse tick)

Splits a trigger.

void grow_trigger (midipulse tick_from, midipulse tick_to, midipulse len)

Grows a trigger.

• void del trigger (midipulse tick)

Deletes a trigger, that brackets the given tick, from the trigger-list.

bool get_trigger_state (midipulse tick)

Checks the list of triggers against the given tick.

bool select_trigger (midipulse tick)

Checks the list of triggers against the given tick.

• bool unselect_triggers ()

Unselects all triggers.

• bool intersect triggers (midipulse position, midipulse &start, midipulse &ender)

This function examines each trigger in the trigger list.

• bool intersect_notes (midipulse position, midipulse position_note, midipulse &start, midipulse &ender, int ¬e)

This function examines each note in the event list.

bool intersect_events (midipulse posstart, midipulse posend, midibyte status, midipulse &start)

This function examines each non-note event in the event list.

• void del selected trigger ()

Deletes the first selected trigger that is found.

void cut_selected_trigger ()

Copies and deletes the first selected trigger that is found.

· void copy selected trigger ()

Copies the first selected trigger that is found.

• void paste_trigger ()

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

bool move_selected_triggers_to (midipulse tick, bool adjust_offset, int which=2)

Moves selected triggers as per the given parameters.

midipulse selected trigger start ()

Gets the last-selected trigger's start tick.

midipulse selected_trigger_end ()

Gets the selected trigger's end tick.

midipulse get_max_trigger ()

Get the ending value of the last trigger in the trigger-list.

• void move_triggers (midipulse start_tick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

• void copy_triggers (midipulse start_tick, midipulse distance)

Copies triggers to...

• void clear_triggers ()

Clears the whole list of triggers.

• midipulse get_trigger_offset () const

'Getter' function for member m_trigger_offset

void set_midi_bus (char mb)

Sets the midibus number to dump to.

· char get midi bus () const

'Getter' function for member m bus

void set_master_midi_bus (mastermidibus *mmb)

'Setter' function for member m masterbus

• int select_note_events (midipulse tick_s, int note_h, midipulse tick_f, int note_l, select_action_e action)

This function selects events in range of tick start, note high, tick end, and note low.

• int select_events (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)

Select all events in the given range, and returns the number selected.

int select_events (midibyte status, midibyte cc, bool inverse=false)

Select all events with the given status, and returns the number selected.

· int get num selected notes () const

Counts the selected notes in the event list.

• int get num selected events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

void select_all ()

Selects all events, unconditionally.

• void copy_selected ()

Copies the selected events.

void cut_selected (bool copyevents=true)

Cuts the selected events.

void paste_selected (midipulse tick, int note)

Pastes the selected notes (and only note events) at the given tick and the given note value.

• void get selected box (midipulse &tick s, int ¬e h, midipulse &tick f, int ¬e I)

Returns the 'box' of the selected items.

void get_clipboard_box (midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)

Returns the 'box' of the clipboard items.

• void move_selected_notes (midipulse deltatick, int deltanote)

Removes and adds reads selected in position.

• void add_note (midipulse tick, midipulse len, int note, bool paint=false)

Adds a note of a given length and note value, at a given tick location.

void add_event (midipulse tick, midibyte status, midibyte d0, midibyte d1, bool paint=false)

Adds a event of a given status value and data values, at a given tick location.

· void stream_event (event &ev)

Streams the given event.

bool change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int d_s, int d f)

Changes the event data range.

void increment_selected (midibyte status, midibyte control)

Increments events the match the given status and control values.

void decrement_selected (midibyte status, midibyte control)

Decrements events the match the given status and control values.

void grow_selected (midipulse deltatick)

Moves note off event.

void stretch selected (midipulse deltatick)

Performs a stretch operation on the selected events.

void remove marked ()

Removes marked events.

void mark selected ()

Marks the selected events.

void unpaint_all ()

Unpaints all events in the event-list.

· void unselect ()

Deselects all events, unconditionally.

void verify_and_link ()

This function verifies state: all note-ons have an off, and it links note-offs with their note-ons.

• void link new ()

Links a new event.

• void zero_markers ()

Resets everything to zero.

• void play_note_on (int note)

Plays a note from the piano roll on the main bus on the master MIDI buss.

void play_note_off (int note)

Turns off a note from the piano roll on the main bus on the master MIDI buss.

• void off_playing_notes ()

Sends a note-off event for all active notes.

• void reset_draw_marker ()

This refreshes the play marker to the last tick.

void reset_draw_trigger_marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

draw type get next note event (midipulse *tick s, midipulse *tick f, int *note, bool *selected, int *velocity)

Each call to seqdata() fills the passed references with a events elements, and returns true.

int get_lowest_note_event ()

Goes through the list of notes, and picks the one with the lowest value.

int get highest note event ()

Goes through the list of notes, and picks the one with the highest value.

• bool get_next_event (midibyte status, midibyte cc, midipulse *tick, midibyte *d0, midibyte *d1, bool *selected)

Get the next event in the event list that matches the given status and control character.

bool get_next_event (midibyte *status, midibyte *cc)

Get the next event in the event list.

bool get next trigger (midipulse *tick on, midipulse *tick off, bool *selected, midipulse *tick offset)

Get the next trigger in the trigger list, and set the parameters based on that trigger.

• void fill container (midi container &c, int tracknumber)

This function fills the given character list with MIDI data from the current sequence, preparatory to writing it to a file.

• void quantize_events (midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)

Not deleting the ends, not selected.

• void transpose_notes (int steps, int scale)

Transposes notes by the given steps, in accordance with the given scale.

midibyte musical_key () const

'Getter' function for member m_musical_key

• void musical_key (int key)

'Setter' function for member m musical key

midibyte musical_scale () const

'Getter' function for member m musical scale

· void musical_scale (int scale)

'Setter' function for member m musical scale

int background_sequence () const

'Getter' function for member m_background_sequence

· void background sequence (int bs)

'Setter' function for member m_background_sequence Only partial validation at present, we do not want the upper limit to be hard-wired at this time.

· void show events () const

A member function to dump a summary of events stored in the event-list of a sequence.

void copy_events (const event_list &newevents)

Copies an external container of events into the current container, effectively replacing all of its events.

Private Member Functions

void put event on bus (event &ev)

Takes an event that this sequence is holding, and places it on the midibus.

void set_trigger_offset (midipulse trigger_offset)

Sets m_trigger_offset and wraps it to m_length.

void split_trigger (trigger &trig, midipulse splittick)

Splits the trigger given by the parameter into two triggers.

void adjust_trigger_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length of ???, for all triggers, and undo triggers.

• void remove (event list::iterator i)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

• void remove (event &e)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

· void remove_all ()

Clears all events from the event container.

Private Attributes

· event list m events

This list holds the current pattern/sequence events.

• midibyte m_midi_channel

Contains the proper MIDI channel for this sequence.

midibyte m_bus

Contains the proper MIDI bus number for this sequence.

· bool m_song_mute

Provides a flag for the song playback mode muting.

int m_notes_on

Provides a member to hold the polyphonic step-edit note counter.

mastermidibus * m_masterbus

Provides the master MIDI buss which handles the output of the sequence to the proper buss and MIDI channel.

int m_playing_notes [SEQ64_MIDI_NOTES_MAX]

Provides a "map" for Note On events.

· bool m was playing

Indicates if the sequence was playing.

bool m_playing

True if sequence playback currently is in progress for this sequence.

· bool m_recording

True if sequence recording currently is in progress for this sequence.

bool m_dirty_main

These flags indicate that the content of the sequence has changed due to recording, editing, performance management, or even (?) a name change.

bool m editing

Indicates that the sequence is currently being edited.

• std::string m_name

Provides the name/title for the sequence.

midipulse m_last_tick

These members manage where we are in the playing of this sequence, including triggering.

const int m_maxbeats

This constant provides ...?

• int m_ppqn

Holds the PPQN value for this sequence, so that we don't have to rely on a global constant value.

int m_seq_number

A new member so that the sequence number is carried along with the sequence.

• midipulse m_length

Holds the length of the sequence in pulses (ticks).

midipulse m_snap_tick

The size of snap in units of pulses (ticks).

int m_time_beats_per_measure

Provides the number of beats per bar used in this sequence.

• int m_time_beat_width

Provides with width of a beat.

int m_rec_vol

The volume to be used when recording.

midibyte m_musical_key

Holds a copy of the musical key for this sequence, which we now support writing to this sequence.

midibyte m_musical_scale

Holds a copy of the musical scale for this sequence, which we now support writing to this sequence.

• int m_background_sequence

Holds a copy of the background sequence number for this sequence, which we now support writing to this sequence.

• mutex m_mutex

Provides locking for the sequence.

Static Private Attributes

• static event_list m_events_clipboard

A static clipboard for holding pattern/sequence events.

10.60.1 Detailed Description

More members than you can shake a stick at.

10.60.2 Member Enumeration Documentation

10.60.2.1 enum seq64::sequence::select_action_e

Enumerator

e_select This enumeration is used in selecting events and note. Se the select_note_events() and select_← events() functions.

```
To select ...
```

- e_select_one To select ...
- e_is_selected The events are selected ...
- e_would_select The events would be selected ...
- e_deselect To deselect the event under the cursor.
- **e_toggle_selection** To toggle the selection of the event under the cursor.
- e_remove_one To remove one note under the cursor.

10.60.3 Member Function Documentation

10.60.3.1 void seq64::sequence::partial_assign (const sequence & rhs)

We're replacing that incomplete function (many members are not assigned) with the more accurately-named partial_assign() function.

It did not assign them all, so we created this partial_assign() function to do this work, and replaced operator =() with this function in client code.

Threadsafe

```
10.60.3.2 int seq64::sequence::event_count() const

Threadsafe

10.60.3.3 void seq64::sequence::push_undo()

Threadsafe

10.60.3.4 void seq64::sequence::pop_undo()

Threadsafe

10.60.3.5 void seq64::sequence::pop_redo()

Threadsafe
```

10.60.3.6 void seq64::sequence::push_trigger_undo ()

10.60.3.7 void seq64::sequence::set_beats_per_bar (int beatspermeasure)

Parameters

beatspermea-	The new setting of the beats-per-bar value.
sure	

10.60.3.8 void seq64::sequence::set_beat_width (int beatwidth)

Threadsafe

Parameters

beatwidth	The new setting of the beat width value.

```
10.60.3.9 int seq64::sequence::get_beat_width() const [inline]
```

Threadsafe

10.60.3.10 void seq64::sequence::set_rec_vol (int recvol)

Threadsafe

Parameters

recvol The new setting of the recording volume setting.

```
10.60.3.11 const char* seq64::sequence::get_name() const [inline]
```

Deprecated

```
10.60.3.12 void seq64::sequence::set_length ( midipulse len, bool adjust_triggers = true )
```

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks:

```
L = M x B x 4 x P / W
L == length (ticks or pulses)
M == number of measures
B == beats per measure
P == pulses per quarter-note
W == beat width in beats per measure

For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4, P can be 192 (but we want to support higher values), and W is 4.
So L = 100 * 4 * 4 * 192 / 4 = 76800 ticks. Seems small.
Threadsafe
```

10.60.3.13 midipulse seq64::sequence::get_last_tick()

If m_length is 0, this function returns m_last_tick - m_trigger_offset, to avoid an arithmetic exception. Should we return 0 instead?

10.60.3.14 midipulse seq64::sequence::mod_last_tick() [inline]

This function replaces the "m_last_tick % m_length", returning m_last_tick if m_length is 0 or 1.

```
10.60.3.15 void seq64::sequence::set_playing (bool p)
```

When playing, and the sequencer is running, notes get dumped to the ALSA buffers.

Parameters

p Provides the playing status to set. True means to turn on the playing, false means to turn it off, and turn off any notes still playing.

```
10.60.3.16 void seq64::sequence::toggle_queued()
```

Toggles the queued flag and sets the dirty-mp flag. Also calculates the queued tick based on m_last_tick. If m_{\leftarrow} length is bad (i.e. zero), then m_queued_tick is set to 0, to avoid an arithmetic error.

Threadsafe

```
10.60.3.17 void seq64::sequence::off_queued ( )
```

Toggles the queued flag and sets the dirty-mp flag.

Threadsafe

```
10.60.3.18 void seq64::sequence::set_recording ( bool r )
```

Threadsafe

```
10.60.3.19 void seq64::sequence::set_snap_tick ( int st )
```

Threadsafe

```
10.60.3.20 void seq64::sequence::set_quantized_rec ( bool qr )
```

Threadsafe

```
10.60.3.21 void seg64::sequence::set_thru ( bool r )
```

Threadsafe

```
10.60.3.22 bool seq64::sequence::is_dirty_main()
```

resets it). This flag signals that a redraw is needed from recording.

Threadsafe

```
10.60.3.23 bool seq64::sequence::is_dirty_edit( )
```

Threadsafe

```
10.60.3.24 bool seq64::sequence::is_dirty_perf()
```

```
10.60.3.25 bool seq64::sequence::is_dirty_names()

Threadsafe

10.60.3.26 void seq64::sequence::set_dirty_mp()

Not threadsafe

10.60.3.27 void seq64::sequence::set_dirty()

Threadsafe

10.60.3.28 void seq64::sequence::set_midi_channel(midibyte ch)

Threadsafe

10.60.3.29 void seq64::sequence::print()

Not threadsafe

10.60.3.30 void seq64::sequence::print_triggers()

Not threadsafe
```

This function is called by the sequencer thread, performance. The tick comes in as global tick.

It turns the sequence off after we play in this frame.

Parameters

tick	Provides the current end-tick value.
playback_mode	Provides how playback is managed. True indicates that it is performance/song-editor play-
	back, controlled by the set of patterns and triggers set up in that editor, and saved with the
	song in seq24 format. False indicates that the playback is controlled by the main windows, in
	live mode.

Threadsafe

10.60.3.32 void seq64::sequence::set_orig_tick (midipulse tick)

Threadsafe

10.60.3.33 bool seq64::sequence::add_event (const event & er)

Then it reset the draw-marker and sets the dirty flag.

Currently, when reading a MIDI file [see the midifile::parse() function], only the main events (notes, after-touch, pitch, program changes, etc.) are added with this function. So, we can rely on reading only playable events into a sequence. Well, actually, certain meta-events are also read, to obtain channel, buss, and more settings. Also read for a sequence, if the global-sequence flag is not set, are the new key, scale, and background sequence parameters.

This module (sequencer) adds all of those events as well, but it can surely add other events. We should assume that any events added by sequencer are playable/usable.

Threadsafe

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. Actually, this is true only in Seq24, we've fixed that behavior for Sequencer64.

Parameters

ер	Provide a reference to the event to be added; the event is copied into the events container.

10.60.3.34 void seq64::sequence::add_trigger (midipulse tick, midipulse len, midipulse offset = 0, bool fixoffset = true)

A pass-through function that calls triggers::add().

10.60.3.35 void seq64::sequence::split_trigger (midipulse splittick)

This is the public overload of split trigger.

Threadsafe

10.60.3.36 void seq64::sequence::grow_trigger (midipulse tickfrom, midipulse tickto, midipulse len)

Parameters

tickfro	om	The desired from-value back which to expand the trigger, if necessary.
tick	kto	The desired to-value towards which to expand the trigger, if necessary.
le	en	The additional length to append to tickto for the check.

Threadsafe

10.60.3.37 void seq64::sequence::del_trigger (midipulse tick)

Threadsafe

10.60.3.38 bool seq64::sequence::get_trigger_state (midipulse tick)

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick	Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

10.60.3.39 bool seq64::sequence::select_trigger (midipulse tick)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick	Provides the tick of interest.
------	--------------------------------

Returns

Returns true if a trigger is found that brackets the given tick.

10.60.3.40 bool seq64::sequence::unselect_triggers ()

Returns

Always returns false.

10.60.3.41 bool seq64::sequence::intersect_triggers (_midipulse position, midipulse & start, midipulse & ender_)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit.

Threadsafe

Parameters

position	The position to examine.
start	The destination for the starting tick of the matching trigger.
ender	The destination for the ending tick of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

10.60.3.42 bool seq64::sequence::intersect_notes (midipulse *position*, midipulse *position_note*, midipulse & *start*, midipulse & *ender*, int & *note*)

If the given position is between the current notes on and off time values, values, the these values are copied to the start and end parameters, respectively, the note value is copied to the note parameter, and then we exit.

Threadsafe

Parameters

position	The position to examine.
position_note	I think this is the note value we might be looking for ???
start	The destination for the starting timestamp of the matching note.
ender	The destination for the ending timestamp of the matching note.
note	The destination for the note of the matching event. Why is this an int value???

Returns

Returns true if a event was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

10.60.3.43 bool seq64::sequence::intersect_events (midipulse *posstart,* midipulse *posend,* midibyte *status,* midipulse & *start*

If the given position is between the current notes's timestamp-start and timestamp-end values, the these values are copied to the posstart and posend parameters, respectively, and then we exit.

Parameters

posstart	The starting position to examine.
posend	The ending position to examine.
status	The desired status value.
start	The destination for the starting timestamp of the matching trigger.

Returns

Returns true if a event was found whose start/end timestamps contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

```
10.60.3.44 void seq64::sequence::paste_trigger()
```

Why isn't this protected by a mutex? We will eventually enable this see if anything bad happens, such as a deadlock, or corruption.

10.60.3.45 bool seq64::sequence::move_selected_triggers_to (midipulse tick, bool adjustoffset, int which = 2)

```
min_tick][0 1][max_tick 2

If we are moving the 0, use first as offset.

If we are moving the 1, use the last as the offset.

If we are moving both (2), use first as offset.
```

Threadsafe

Returns

Returns the value of triggers::move_selected(), which indicate that the movement could be made. Used in Seq24PerfInput::handle_motion_key().

```
10.60.3.46 midipulse seq64::sequence::selected_trigger_start ( )
```

Threadsafe

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then -1 is returned.

```
10.60.3.47 midipulse seq64::sequence::selected_trigger_end ( )
```

Threadsafe

```
10.60.3.48 midipulse seq64::sequence::get_max_trigger()
```

Threadsafe

```
10.60.3.49 void seq64::sequence::move_triggers ( midipulse starttick, midipulse distance, bool direction )
```

Note the dependence on the m_length member being kept in sync with the parent's value of m_length.

```
10.60.3.50 void seq64::sequence::copy_triggers ( midipulse starttick, midipulse distance )
Threadsafe
10.60.3.51 void seq64::sequence::clear_triggers ( )
Threadsafe
10.60.3.52 void seq64::sequence::set_midi_bus ( char mb )
Threadsafe
10.60.3.53 void seq64::sequence::set_master_midi_bus ( mastermidibus * mmb )
Threadsafe
Parameters
              mmb
                      Provides a pointer to the master MIDI buss for this sequence. This should be a reference.
10.60.3.54 int seq64::sequence::select_note_events ( midipulse a_tick_s, int a_note_h, midipulse a_tick_f, int a_note_l,
           select_action_e a_action )
Returns the number selected.
Threadsafe
10.60.3.55 int seq64::sequence::select_events ( midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc,
           select_action_e action )
Note that there is also an overloaded version of this function.
Threadsafe
10.60.3.56 int seq64::sequence::select_events ( midibyte status, midibyte cc, bool inverse = false )
Note that there is also an overloaded version of this function.
Threadsafe
Warning
      This used to be a void function, so it just returns 0 for now.
10.60.3.57 int seq64::sequence::get_num_selected_notes ( ) const
Threadsafe
10.60.3.58 int seq64::sequence::get_num_selected_events ( midibyte status, midibyte cc ) const
If the event is a control change (CC), then it must also match the given CC value.
Threadsafe
```

```
10.60.3.59 void seq64::sequence::select_all()

Threadsafe
```

10.60.3.60 void seq64::sequence::copy_selected()

Threadsafe

10.60.3.61 void seq64::sequence::cut_selected (bool copyevents = true)

Threadsafe

10.60.3.62 void seq64::sequence::paste_selected (midipulse tick, int note)

I wonder if we can get away with just getting a reference to m_events_clipboard, rather than copying the whole thing, for speed.

Threadsafe

10.60.3.63 void seq64::sequence::get_selected_box (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l)

Note the common-code betweem this function and get_clipboard_box().

Threadsafe

10.60.3.64 void seq64::sequence::get_clipboard_box (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l)

Note the common-code betweem this function and get_selected_box().

Threadsafe

10.60.3.65 void seq64::sequence::move_selected_notes (midipulse delta_tick, int delta_note)

Parameters

delta_tick	Provides the amount of time to move the selected notes.
delta_note	Provides the amount of pitch to move the selected notes.

10.60.3.66 void seq64::sequence::add_note (midipulse tick, midipulse length, int note, bool paint = false)

It adds a single note-on / note-off pair.

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Threadsafe

10.60.3.67 void seq64::sequence::add_event (midipulse *tick*, midibyte *status*, midibyte *d0*, midibyte *d1*, bool *paint* = false)

The a_paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

10.60.3.68 void seq64::sequence::stream_event (event & ev)

Threadsafe

10.60.3.69 bool seq64::sequence::change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int data_s, int data_f)

Changes only selected events, if any.

Threadsafe

Let t == the current tick value; ts == tick start value; tf == tick finish value; ds = data start value; df == data finish value; d = the new data value.

Then

If this were an interpolation formula it would be:

Something is not quite right; to be investigated.

Parameters

tick_s	Provides the starting tick value.
tick_f	Provides the ending tick value.
status	Provides the event status that is to be changed.
CC	Provides the event control value.
data_s	Provides the starting data value.
data_f	Provides the finishing data value.

Returns

Returns true if the data was changed.

10.60.3.70 void seq64::sequence::increment_selected (midibyte astat, midibyte control)

The supported statuses are:

- EVENT_NOTE_ON
- EVENT_NOTE_OFF
- EVENT_AFTERTOUCH
 EVENT_CONTROL_CHANGE
- EVENT_PITCH_WHEEL
- EVENT_PROGRAM_CHANGE
- EVENT_CHANNEL_PRESSURE

Threadsafe

10.60.3.71 void seq64::sequence::decrement_selected (midibyte astat, midibyte control)

The supported statuses are:

- · One-byte messages
 - EVENT_PROGRAM_CHANGE
 - EVENT_CHANNEL_PRESSURE
- · Two-byte messages
 - EVENT_NOTE_ON
 - EVENT_NOTE_OFF
 - EVENT_AFTERTOUCH
 - EVENT CONTROL CHANGE
 - EVENT_PITCH_WHEEL

Threadsafe

```
10.60.3.72 void seq64::sequence::grow_selected ( midipulse delta_tick )
```

If an event is not linked, this function now ignores the event's timestamp, rather than risk a segfault on a null pointer.

Threadsafe

Parameters

```
delta_tick An offset for each linked event's timestamp.
```

```
10.60.3.73 void seq64::sequence::stretch_selected ( midipulse delta_tick )
```

This should move a note off event, according to old comments, but it doesn't seem to do that. See the grow_← selected() function.

Threadsafe

```
10.60.3.74 void seq64::sequence::remove_marked ( )
```

Note how this function handles removing a value to avoid incrementing a now-invalid iterator.

Threadsafe

```
10.60.3.75 void seq64::sequence::mark_selected ( )
```

Threadsafe

```
10.60.3.76 void seq64::sequence::unpaint_all ( )
```

Threadsafe

```
10.60.3.77 void seg64::sequence::unselect()
```

Threadsafe

```
10.60.3.78 void seq64::sequence::verify_and_link()
```

```
10.60.3.79 void seq64::sequence::link_new()
Threadsafe
10.60.3.80 void seq64::sequence::zero_markers ( )
This function is used when the sequencer stops.
Threadsafe
10.60.3.81 void seq64::sequence::play_note_on ( int a_note )
It flushes a note to the midibus to preview its sound, used by the virtual piano.
Threadsafe
10.60.3.82 void seq64::sequence::play_note_off ( int a_note )
Threadsafe
10.60.3.83 void seq64::sequence::off_playing_notes ( )
Threadsafe
10.60.3.84 void seq64::sequence::reset_draw_marker( )
It resets the draw marker so that calls to get_next_note_event() will start from the first event.
Threadsafe
10.60.3.85 void seq64::sequence::reset_draw_trigger_marker()
Threadsafe
10.60.3.86 draw_type seq64::sequence::get_next_note_event ( midipulse * a_tick_s, midipulse * a_tick_f, int * a_note, bool *
           a_selected, int * a_velocity )
When it has no more events, returns a false.
10.60.3.87 int seq64::sequence::get_lowest_note_event()
Threadsafe
Returns
      Returns the note with the lowest value. If there are no notes in the list, then SEQ64_MIDI_COUNT_MAX-1 is
      returned, which of course doesn't tell the caller much.
10.60.3.88 int seq64::sequence::get_highest_note_event()
Threadsafe
```

Returns

Returns the note with the highest value. If there are no notes in the list, then 0 is returned, which of course doesn't tell the caller much.

10.60.3.89 bool seq64::sequence::get_next_event (midibyte status, midibyte cc, midipulse *tick, midibyte *tick

Then set the rest of the parameters parameters using that event.

Note the usage of event::is_desired_cc_or_not_cc(status, cc, *d0); Either we have a control change with the right CC or it's a different type of event.

10.60.3.90 bool seq64::sequence::get_next_event (midibyte * a_status, midibyte * a_cc)

Then set the status and control character parameters using that event.

10.60.3.91 void seq64::sequence::fill_container (midi_container & c, int tracknumber)

Note that some of the events might not come out in the same order they were stored in (we see that with programchange events.

Parameters

С	Provides the std::list object to push events to the front, which thus inserts them in backwards
	order. (These events are then popped back, which restores the order, with some exceptions).
tracknumber	Provides the track number. This number is masked into the track information.

10.60.3.92 void seq64::sequence::transpose_notes (int steps, int scale)

If the scale value is 0, this is "no scale", which is the chromatic scale, where all 12 notes, including sharps and flats, are part of the scale.

10.60.3.93 void seg64::sequence::background_sequence(int bs) [inline]

Disabling the sequence number (setting it to SEQ64_SEQUENCE_LIMIT) is valid.

10.60.3.94 void seq64::sequence::copy_events (const event_list & newevents)

Compare this function to the remove_all() function. Copying the container is a lot of work, but fairly fast, even with an std::multimap as the container.

Threadsafe Note that we had to consolidate the replacement of all the events in the container in order to prevent the "Save to Sequence" button in the eventedit object from causing the application to segfault. It would segfault when the mainwand timer callback would fire, causing updates to the sequence's slot pixmap, which would then try to access deleted events. Part of the issue was that note links were dropped when copying the events, so now we call verify_and_link() to hopefully reconstitute the links.

Parameters

newevents	Provides the container of MIDI events that will completely replace the current container. Nor-
	mally this container is supplied by the event editor, via the eventslots class.

10.60.3.95 void seq64::sequence::put_event_on_bus(event & ev) [private]

Threadsafe

10.60.3.96 void seq64::sequence::set_trigger_offset (midipulse trigger_offset) [private]

If m length is 0, then it is simply set to the parameter.

Threadsafe

Parameters

trigger_offset	The full trigger offset to set.	

10.60.3.97 void seq64::sequence::split_trigger (trigger & trig, midipulse splittick) [private]

This is the private overload of split_trigger.

Threadsafe

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is short-
	ened.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

10.60.3.98 void seq64::sequence::adjust_trigger_offsets_to_length (midipulse newlength) [private]

Threadsafe

Might can get rid of this function?

10.60.3.99 void seq64::sequence::remove (event_list::iterator i) [private]

If it's a note off, and that note is currently playing, then send a note off.

Not threadsafe

10.60.3.100 void seq64::sequence::remove(event & e) [private]

Finds the given event in m_events, and removes the first iterator matching that.

Not threadsafe

Todo Use find instead in sequence::remove()!

10.60.3.101 void seq64::sequence::remove_all() [private]

Unsets the modified flag. Also see the new copy_events() function.

10.60.4 Field Documentation

10.60.4.1 midibyte seq64::sequence::m_midi_channel [private]

However, if this value is EVENT_NULL_CHANNEL (0xFF), then this sequence is an SMF 0 track, and has no single channel.

```
10.60.4.2 int seq64::sequence::m_playing_notes[SEQ64_MIDI_NOTES_MAX] [private]
```

It is used when muting, to shut off the notes that are playing.

```
10.60.4.3 int seq64::sequence::m_seq_number [private]
```

This number is set in the perform::install_sequence() function.

```
10.60.4.4 midipulse seq64::sequence::m_length [private]
```

This value should be a power of two when used as a bar unit.

```
10.60.4.5 midipulse seq64::sequence::m_snap_tick [private]
```

It starts out as the value m_ppqn / 4.

```
10.60.4.6 int seq64::sequence::m_time_beats_per_measure [private]
```

Defaults to 4. Used by the sequence editor to mark things in correct time on the user-interface.

```
10.60.4.7 int seq64::sequence::m_time_beat_width [private]
```

Defaults to 4, which means the beat is a quarter note. A value of 8 would mean it is an eighth note. Used by the sequence editor to mark things in correct time on the user-interface.

```
10.60.4.8 midibyte seq64::sequence::m_musical_key [private]
```

If the value is SEQ64_KEY_OF_C, then there is no musical key to be set.

```
10.60.4.9 midibyte seq64::sequence::m_musical_scale [private]
```

If the value is the enumeration value c scale off, then there is no musical scale to be set.

```
10.60.4.10 int seq64::sequence::m_background_sequence [private]
```

If the value is greater than max_sequence(), then there is no background sequence to be set.

```
10.60.4.11 mutex seq64::sequence::m_mutex [mutable], [private]
```

Made mutable for use in certain locked getter functions.

10.61 seq64::trigger Class Reference

This class hold a single trigger for a sequence object.

Public Member Functions

• trigger ()

Initializes the trigger structure.

bool operator< (const trigger &rhs)

This operator compares only the m_tick_start members.

• midipulse tick_start () const

'Getter' function for member m tick start

void tick_start (midipulse s)

'Setter' function for member m_tick_start

void increment_tick_start (midipulse s)

'Setter' function for member m_tick_start

void decrement_tick_start (midipulse s)

'Setter' function for member m_tick_start

• midipulse tick_end () const

'Getter' function for member m_tick_end

• void tick_end (midipulse e)

'Setter' function for member m_tick_end

void increment_tick_end (midipulse s)

'Setter' function for member m_tick_end

• void decrement_tick_end (midipulse s)

'Setter' function for member m_tick_end

• midipulse offset () const

'Getter' function for member m_offset

• void offset (midipulse o)

'Setter' function for member m_offset

· void increment_offset (midipulse s)

'Setter' function for member m_offset

void decrement_offset (midipulse s)

'Setter' function for member m_offset

• bool selected () const

'Getter' function for member $m_selected$

void selected (bool s)

 ${\it 'Setter' function for member m_selected'}$

Private Attributes

• midipulse m_tick_start

Provides the starting tick for this trigger.

• midipulse m_tick_end

Provides the ending tick for this trigger.

• midipulse m_offset

Provides the offset for this trigger.

· bool m_selected

Indicates that the trigger is part of a selection.

10.61.1 Detailed Description

This class is used in playback, and is contained in the triggers class.

10.62 seq64::triggers Class Reference

The triggers class is a receptable the triggers that can be used with a sequence object.

Public Types

typedef std::list< trigger > List

Exposes the triggers type, currently needed for midi_container only.

Public Member Functions

• triggers (sequence &parent)

Principal constructor.

∼triggers ()

A rote destructor.

triggers & operator= (const triggers &rhs)

Principal assignment operator.

void set_ppqn (int ppqn)

'Setter' function for member m_ppqn We have to set this value after construction for best safety.

void set length (int len)

'Setter' function for member m_length We have to set this value after construction for best safety.

· List & triggerlist ()

'Getter' function for member m_triggers

void push_undo ()

Pushes the list-trigger into the trigger undo-list, then flags each item in the undo-list as unselected.

• void pop_undo ()

If the trigger undo-list has any items, the list-trigger is pushed into the redo list, the top of the undo-list is coped into the list-trigger, and then pops from the undo-list.

· void print (const std::string &seqname)

Prints a list of the currently-held triggers.

bool play (midipulse &start_tick, midipulse &end_tick)

If playback-mode (live mode?) is in force, that is, if using in-triggers and on/off triggers, this function handles that kind of playback.

• void add (midipulse tick, midipulse len, midipulse offset=0, bool adjustoffset=true)

Adds a trigger.

void adjust_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length of ???, for all triggers, and undo triggers.

void split (midipulse tick)

Splits the first trigger that brackets the splittick parameter.

void split (trigger &trig, midipulse split_tick)

Splits the trigger given by the parameter into two triggers.

· void grow (midipulse tick_from, midipulse tick_to, midipulse length)

Grows a trigger.

• void remove (midipulse tick)

Deletes the first trigger that brackets the given tick from the trigger-list.

• bool get_state (midipulse tick)

Checks the list of triggers against the given tick.

bool select (midipulse tick)

Checks the list of triggers against the given tick.

bool unselect ()

Unselects all triggers.

· bool intersect (midipulse position, midipulse &start, midipulse &end)

This function examines each trigger in the trigger list.

• void remove selected ()

Deletes the first selected trigger that is found.

void copy_selected ()

Copies the first selected trigger that is found.

· void paste ()

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

• bool move_selected (midipulse tick, bool adjustoffset, int which=2)

Moves selected triggers as per the given parameters.

· midipulse get selected start ()

Gets the selected trigger's start tick.

• midipulse get_selected_end ()

Gets the selected trigger's end tick.

midipulse get_maximum ()

Get the ending value of the last trigger in the trigger-list.

· void move (midipulse start tick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

void copy (midipulse start_tick, midipulse distance)

Not sure what these diagrams are for yet.

• void clear ()

Clears the whole list of triggers.

• bool next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

'Getter' function for member m_trigger_offset

trigger next_trigger ()

Get the next trigger in the trigger list, and set the parameters based on that trigger.

· void reset_draw_trigger_marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

Private Member Functions

· midipulse adjust offset (midipulse offset)

Adjusts the given offset by mod'ing it with m_length and adding m_length if needed, and returning the result.

Private Attributes

• sequence & m parent

Holds a reference to the parent sequence object that owns this trigger object.

· List m_triggers

This list holds the current pattern/triggers events.

trigger m_clipboard

This item holds a single copied trigger, to be pasted later.

Stack m undo stack

Handles the undo list for a series of operations on triggers.

Stack m_redo_stack

Handles the redo list for a series of operations on triggers.

List::iterator m_iterator_play_trigger

An iterator for cycling through the triggers during playback.

· List::iterator m_iterator_draw_trigger

An iterator for cycling through the triggers during drawing.

bool m_trigger_copied

Set to true if there is an active trigger in the trigger clipboard.

• midipulse m_trigger_offset

Offset.

• int m_ppqn

Holds the value of the PPQN from the parent sequence, for easy access.

· int m length

Holds the value of the length from the parent sequence, for easy access.

10.62.1 Constructor & Destructor Documentation

10.62.1.1 seq64::triggers::triggers (sequence & parent)

Parameters

parent	The triggers object often needs to tell its parent sequence object what to do (such as stop
	playing).

10.62.2 Member Function Documentation

10.62.2.1 triggers & seq64::triggers::operator= (const triggers & rhs)

Follows the stock rules for such an operator, but does a little more then just assign member values. Currently, it does not assign them all, so we should create a partial_copy() function to do this work, and use it where it is needed.

```
10.62.2.2 void seq64::triggers::set_length ( int len ) [inline]
```

Also, there a chance that the length of the parent might change from time to time. Currently, only the sequence constructor and midifile call this function.

10.62.2.3 bool seq64::triggers::play (midipulse & start_tick, midipulse & end_tick)

This is a new function for sequence::play() to call.

Parameters

start_tick	Provides the starting tick value, and returns the modified value as a side-effect.
end_tick	Provides the ending tick value, and returns the modified value as a side-effect.

Returns

Returns true if we're through playing the frame, and the caller should stop the playback.

10.62.2.4 void seq64::triggers::add (midipulse tick, midipulse len, midipulse offset = 0, bool fixoffset = true)

What is this?

```
< >
<s es ee
< >
< >
< >
< >
```

Parameters

tick	Provides the tick (pulse) time at which the trigger goes on.
len	Provides the length of the trigger. This value is actually calculated from the "on" value minus
	the "off" value read from the MIDI file.
offset	This value specifies the offset of the trigger. It is a feature of the c_triggers_new that c_ <-
	triggers doesn't have. It is the third value in the trigger specification of the Sequencer64 MIDI
	file.
fixoffset	If true, the offset parameter is modified by adjust_offset() first. We think that basically makes
	sure it is positive.

10.62.2.5 void seq64::triggers::adjust_offsets_to_length (midipulse newlength)

Parameters

newlength	h
-----------	---

COMMON CODE?

COMMON CODE?

10.62.2.6 void seq64::triggers::split (midipulse splittick)

This is the first trigger where splittick is greater than L and less than R.

Parameters

splittick	Provides the tick that must be bracketed for the split to be made.

10.62.2.7 void seq64::triggers::split (trigger & trig, midipulse splittick)

The original trigger ends 1 tick before the splittick parameter, and the new trigger starts at splittick and ends where the original trigger ended.

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is short-
	ened.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

10.62.2.8 void seq64::triggers::grow (midipulse tickfrom, midipulse tickto, midipulse len)

This function looks for the first trigger where the tickfrom parameter is between the trigger's tick-start and tick-end values. If found then the trigger's start is moved back to tickto, if necessary, or the trigger's end is moved to tickto plus the length parameter, if necessary.

Then this new trigger is added, and the function breaks from the search loop.

Parameters

	tickfrom	The desired from-value back which to expand the trigger, if necessary.
	tickto	The desired to-value towards which to expand the trigger, if necessary.
ſ	len	The additional length to append to tickto for the check.

10.62.2.9 void seq64::triggers::remove (midipulse tick)

Parameters

tick	Provides the tick to be examined.

10.62.2.10 bool seq64::triggers::get_state (midipulse tick)

If any trigger is found to bracket that tick, then true is returned.

Parameters

|--|

Returns

Returns true if a trigger is found that brackets the given tick.

10.62.2.11 bool seq64::triggers::select (midipulse tick)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick	Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

10.62.2.12 bool seq64::triggers::unselect ()

Returns

Always returns false.

10.62.2.13 bool seq64::triggers::intersect (midipulse position, midipulse & start, midipulse & ender)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit.

Parameters

position The position to examine.	
-----------------------------------	--

start	The destination for the starting tick (m_tick_start) of the matching trigger.
ender	The destination for the ending tick (m_tick_end) of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

```
10.62.2.14 void seq64::triggers::paste ( )
```

It pastes at the copy end.

10.62.2.15 bool seq64::triggers::move_selected (midipulse tick, bool fixoffset, int which = 2)

```
mintick][0 1][maxtick 2
```

Parameters

which	Selects which movement will be done. This parameter has three possible values:
	If we are moving the 0, use first as offset.
	If we are moving the 1, use the last as the offset.
	If we are moving both (2), use first as offset.

Returns

Returns true if there was room to move. Otherwise, false is returned. We need this feature to support keystoke movement of a selected trigger in the perfroll window, and keep it from continually incremented when there can be no more movement. This causes moving the other direction to be delayed while the accumulating movement counter is used up. However, right now we can't rely on this result, and ignore it. There may be no way around this minor issue.

```
10.62.2.16 midipulse seq64::triggers::get_selected_start ( )
```

We guess this ends up selecting only one trigger, otherwise only the last selected one would effectively set the result.

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

```
10.62.2.17 midipulse seq64::triggers::get_selected_end ( )
```

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

10.62.2.18 void seq64::triggers::copy (midipulse starttick, midipulse distance)

```
[
     ] [
         ]
... a
. . .
5
      play
      offset
3
  10 play
] [
           ] [] orig
[
            [ ][ ] [] split on the R marker, shift first
      delete middle
        ][][]
                     move ticks
          ] [
          ][ ] [] split on L
               [ ] [] increase all after L
```

Copies triggers to...

```
10.62.2.19 bool seq64::triggers::next ( midipulse * tick_on, midipulse * tick_off, bool * selected, midipulse * offset )
```

Get the next trigger in the trigger list, and set the parameters based on that trigger.

```
midipulse get_trigger_offset () const { return m_trigger_offset; }
```

Todo It would be a bit simpler to simply return a trigger object, wouldn't it?

Parameters

i	tick_on	Return value for the retrieval of the starting tick for the trigger.
i	tick_off	Return value for the retrieval of the ending tick for the trigger.
Se	elected	Return value for the retrieval of the is-selected flag for the trigger.
	offset	Return value for the retrieval of the offset for the trigger.

Returns

Returns true if a trigger was found. If false, the caller cannot rely on the values returned through the return parameters.

Side-effect(s) The value of the m_iterator_draw_trigger member will be altered by this call, unless pointing to the end of the triggerlist, or if there are no triggers.

```
10.62.2.20 trigger seq64::triggers::next_trigger()
```

Returns

Returns the next trigger. If there is none, a default trigger object is returned.

Side-effect(s) The value of the m_iterator_draw_trigger member will be altered by this call, unless pointing to the end of the triggerlist, or if there are no triggers.

10.62.2.21 midipulse seq64::triggers::adjust_offset(midipulse offset) [private]

Parameters

offset Provides the offset, mod'ed against m_length, used to adjust the offset.

Returns

Returns the new offset. However, if m length is 0, no change is made, and the original offset is returned.

10.62.3 Field Documentation

```
10.62.3.1 int seq64::triggers::m_ppqn [private]
```

This should not change, but we have to set it after construction, and so we provide a setter for it, set_ppqn(), called by the sequence constructor.

```
10.62.3.2 int seq64::triggers::m_length [private]
```

This might change, we're not yet sure.

10.63 seq64::user_instrument Class Reference

Provides data about the MIDI instruments, readable from the "user" configuration file.

Public Member Functions

• user_instrument (const std::string &name="")

Default constructor.

• user_instrument (const user_instrument &rhs)

Copy constructor.

• user_instrument & operator= (const user_instrument &rhs)

Principal assignment operator.

• bool is_valid () const

'Getter' function for member m_is_valid

void set_defaults ()

Sets the default values.

• const std::string & name () const

'Getter' function for member m_instrument_def.instrument (name of instrument)

· int controller_count () const

'Getter' function for member m_controller_count This function returns the number of active controllers.

• int controller max () const

'Getter' function for member MIDI_CONTROLLER_MAX This function returns the maximum number of controllers, active or inactive.

• const std::string & controller_name (int c) const

'Getter' function for member m_instrument_def.controllers[c]

bool controller_active (int c) const

'Getter' function for member m_instrument_def.controllers_active[c]

• void set_controller (int c, const std::string &cname, bool isactive)

'Setter' function for member m_instrument_def.controllers[c] and .controllers_active[c] Only sets the controller values if the object is already valid.

Private Member Functions

void set_name (const std::string &instname)

'Setter' function for member m_instrument_def.instrument

void copy_definitions (const user_instrument &rhs)

Copies the array members from one instance of user_instrument to this one.

Private Attributes

· bool m is valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

int m controller count

Provides the actual number of non-default controllers actually set.

user_instrument_t m_instrument_def

The instance of the structure that this class wraps.

10.63.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

10.63.2 Member Function Documentation

10.63.2.1 void seq64::user_instrument::set_defaults ()

Also invalidates the object.

10.63.2.2 int seq64::user_instrument::controller_max() const [inline]

Remember that the controller numbers for each MIDI instrument range from 0 to 127 (MIDI_CONTROLLER_MAX-1).

10.63.2.3 const std::string & seg64::user_instrument::controller_name (int c) const

Parameters

c The index of the desired controller.

Returns

The name of the desired controller has is returned. If the index c is out of range, or the object is not valid, then a reference to an internal, empty string is returned.

10.63.2.4 bool seq64::user_instrument::controller_active (int c) const

Parameters

c The index of the desired controller.

Returns

The status of the desired controller has is returned. If the index c is out of range, or the object is not valid, then false is returned.

10.63.2.5 void seq64::user_instrument::set_controller (int c, const std::string & cname, bool isactive)

Parameters

С	The index of the desired controller.
cname The name of the controller to be set as the controller name.	
isactive A flag that indicates if the desired controller is active.	

10.63.2.6 void seq64::user_instrument::set_name (const std::string & instname) [private]

If the name parameter is not empty, the validity flag is set to true, otherwise it is set to false. Too tricky?

10.63.2.7 void seq64::user_instrument::copy_definitions (const user_instrument & rhs) [private]

Does not include the validity flag.

10.63.3 Field Documentation

10.63.3.1 bool seg64::user_instrument::m_is_valid [private]

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call. However, setting an empty name for the instrument member will render the object invalid.

10.63.3.2 int seq64::user_instrument::m_controller_count [private]

Often, the "user" configuration file has only a few out of the 128 assigned explicitly.

10.64 seq64::user_instrument_t Struct Reference

This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/susr file.

Data Fields

· std::string instrument

Provides the name of the "instrument" being supported.

std::string controllers [SEQ64_MIDI_CONTROLLER_MAX]

Provides a list of up to 128 controllers (e.g.

• bool controllers_active [SEQ64_MIDI_CONTROLLER_MAX]

Provides a flag that indicates if each of up to 128 controller is active and supported.

10.64.1 Field Documentation

10.64.1.1 std::string seq64::user_instrument_t::instrument

Do not confuse "instrument" with "program" here. An "instrument" is most likely a hardware MIDI sound-box (though it could be a software synthesizer as well.

10.64.1.2 std::string seq64::user_instrument_t::controllers[SEQ64_MIDI_CONTROLLER_MAX]

"Modulation"). If a controller isn't present, or if General MIDI is in force, this name might be empty.

10.64.1.3 bool seq64::user_instrument_t::controllers_active[SEQ64_MIDI_CONTROLLER_MAX]

If false, it might be an unsupported controller or a General MIDI device.

10.65 seq64::user_midi_bus Class Reference

Provides data about the MIDI busses, readable from the "user" configuration file.

Public Member Functions

• user_midi_bus (const std::string &name="")

Default constructor.

• user_midi_bus (const user_midi_bus &rhs)

Copy constructor.

• user_midi_bus & operator= (const user_midi_bus &rhs)

Principal assignment operator.

· bool is_valid () const

'Getter' function for member m_is_valid

void set_defaults ()

Sets the default values.

• const std::string & name () const

'Getter' function for member m_midi_bus_def.alias (name of alias)

• int channel_count () const

'Getter' function for member m_channel_count

• int channel_max () const

'Getter' function for member SEQ64_MIDI_BUS_CHANNEL_MAX

• int instrument (int channel) const

'Getter' function for member m_midi_bus_def.instrument[channel]

• void set_instrument (int channel, int instrum)

'Getter' function for member m_midi_bus_def.instrument[channel]

Private Member Functions

void set name (const std::string &name)

'Setter' function for member m_midi_bus_def.alias (name of alias) Also sets the validity flag according to the emptiness of the name parameter.

void copy_definitions (const user_midi_bus &rhs)

Copies the member fields from one instance of user_midi_bus to this one.

Private Attributes

• bool m_is_valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

int m_channel_count

Provides the actual number of non-default buss channels actually set.

user_midi_bus_t m_midi_bus_def

The instance of the structure that this class wraps.

10.65.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

10.65.2 Member Function Documentation

```
10.65.2.1 void seq64::user_midi_bus::set_defaults ( )
```

Also invalidates the object. All 16 of the channels are set to SEQ64_GM_INSTRUMENT_FLAG (-1).

10.65.2.2 int seq64::user_midi_bus::channel_count() const [inline]

Returns

This function returns the number of channels. Basically this value is always the same as that returned by channel max(), but this pair of functions is consistent with the count functions in the user instrument class.

10.65.2.3 int seq64::user_midi_bus::channel_max() const [inline]

Returns

Returns the maximum number of MIDI buss channels. Remember that the instrument channels for each MIDI buss range from 0 to 15 (MIDI_BUS_CHANNEL_MAX-1).

10.65.2.4 int seq64::user_midi_bus::instrument (int channel) const

Parameters

channel	Provides the desired buss channel number.
---------	---

Returns

The instrument number of the desired buss channel is returned. If the channel number is out of range, or the object is not valid, then SEQ64_GM_INSTRUMENT_FLAG (-1) is returned.

10.65.2.5 void seg64::user_midi_bus::set_instrument (int channel, int instrum)

Does not alter the validity flag, just checks it.

Parameters

channel	Provides the desired buss channel number.
instrum	Provides the instrument number to set that channel to.

10.65.2.6 void seq64::user_midi_bus::copy_definitions (const user_midi_bus & rhs) [private]

Does not include the validity flag.

10.65.3 Field Documentation

10.65.3.1 bool seq64::user_midi_bus::m_is_valid [private]

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call.

10.65.3.2 int seq64::user_midi_bus::m_channel_count [private]

Often, the "user" configuration file has only a few out of the 16 assigned explicitly.

10.66 seq64::user_midi_bus_t Struct Reference

This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the application).

Data Fields

std::string alias

Provides the user's desired name for the MIDI bus.

int instrument [SEQ64_MIDI_BUS_CHANNEL_MAX]

Provides an implicit list of MIDI channels from 0 to 15 (1 to 16) and the "instrument" number assigned to each channel.

10.66.1 Field Documentation

10.66.1.1 std::string seq64::user_midi_bus_t::alias

For example, "2x2 A" for some kind of MIDI card or USB MIDI cable. If manual-alsa-ports is enabled, this could be something like "[0] seq24 0", and that is what should be shown in that case.

10.66.1.2 int seq64::user_midi_bus_t::instrument[SEQ64_MIDI_BUS_CHANNEL_MAX]

Note that the "instrument" is not a MIDI program number. Instead, it is the number associated with a "user-instrument" section in the "user" configuration file.

10.67 seg64::user settings Class Reference

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

Public Member Functions

· user settings ()

Scale factor for PPQN.

user_settings (const user_settings &rhs)

Copy constructor.

user_settings & operator= (const user_settings &rhs)

Principal assignment operator.

· void set_defaults ()

Sets the default values.

void normalize ()

Calculate the derived values from the already-set values.

· void set globals () const

Copies the current values of the member variables into their corresponding global variables.

• void get globals ()

Copies the current values of the global variables into their corresponding member variables.

bool add_bus (const std::string &alias)

Adds a user bus to the container, but only does so if the name parameter is not empty.

bool add instrument (const std::string &instname)

Adds a user instrument to the container, but only does so if the name parameter is not empty.

const user_midi_bus & bus (int index)

'Getter' function for member Unlike the non-const version this function is public.

const user_instrument & instrument (int index)

'Getter' function for member Unlike the non-const version this function is public.

• int bus_count () const

'Getter' function for member m_midi_buses.size()

void set bus instrument (int index, int channel, int instrum)

'Getter' function for member m_midi_buses[index].instrument[channel] Currently this function is used, in the userfile ::parse() function.

• int bus_instrument (int buss, int channel)

'Getter' function for member m_midi_buses[buss].instrument[channel]

const std::string & bus_name (int buss)

'Getter' function for member m_midi_buses[buss].name

int instrument_count () const

'Getter' function for member m_instruments.size()

void set instrument controllers (int index, int cc, const std::string &ccname, bool isactive)

 $'Setter'\ function\ for\ member\ m_midi_instrument_defs[index]. controllers,\ controllers_active$

const std::string & instrument_name (int instrum)

'Getter' function for member m instruments[instrument].instrument (name of instrument)

const std::string & instrument_name (int buss, int channel)

Gets the correct instrument number from the buss and channel, and then looks up the name of the instrument.

bool instrument_controller_active (int instrum, int cc)

'Getter' function for member m instruments[instrument].controllers active[controller]

• bool controller_active (int buss, int channel, int cc)

A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

const std::string & instrument_controller_name (int instrum, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller]

const std::string & controller_name (int buss, int channel, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller] A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

• int grid_style () const

'Getter' function for member m_grid_style Checks for normal style.

bool grid_is_normal () const

'Getter' function for member m_grid_style Checks for normal style.

· bool grid is white () const

'Getter' function for member m_grid_style Checks for the white style.

bool grid_is_black () const

'Getter' function for member m_grid_style Checks for the black style.

• int grid_brackets () const

'Getter' function for member m_grid_brackets

• int mainwnd rows () const

'Getter' function for member m_mainwnd_rows

int mainwnd_cols () const

'Getter' function for member m_mainwnd_cols

• int seqs in set () const

'Getter' function for member m_seqs_in_set, dependent member

int gmute_tracks () const

'Getter' function for member m_gmute_tracks, dependent member

• int max_sets () const

'Getter' function for member m_max_sets

int max_sequence () const

'Getter' function for member m_max_sequence, dependent member

• int text x () const

'Getter' function for member m_text_x, not user modifiable, not saved

int text_y () const

'Getter' function for member m_text_y, not user modifiable, not saved

• int segchars x () const

'Getter' function for member m_seqchars_x, not user modifiable, not saved

int seqchars_y () const

'Getter' function for member m_seqchars_y, not user modifiable, not saved

int segarea x () const

'Getter' function for member m_segarea_x, not user modifiable, not saved

• int seqarea_y () const

'Getter' function for member m_seqarea_y, not user modifiable, not saved

int seqarea_seq_x () const

'Getter' function for member m_seqarea_seq_x, not user modifiable, not saved

• int seqarea_seq_y () const

'Getter' function for member m_seqarea_seq_y, not user modifiable, not saved

int mainwid border () const

'Getter' function for member m_mainwid_border

· int mainwid_spacing () const

'Getter' function for member m_mainwid_spacing

int mainwid_x () const

'Getter' function for member m_mainwid_x, dependent member

• int mainwid_y () const

'Getter' function for member m_mainwid_y, dependent member

• int control_height () const

'Getter' function for member m_control_height

· int zoom () const

'Getter' function for member m_current_zoom

• void zoom (int value)

'Setter' function for member m_current_zoom This value is not modified unless the value parameter is between 1 and 32, inclusive.

· bool global seq feature () const

'Getter' function for member m_global_seq_feature_save

void global_seq_feature (bool flag)

'Setter' function for member m_global_seq_feature_save

• int seqedit_scale () const

'Getter' function for member m_seqedit_scale

• void seqedit_scale (int scale)

'Setter' function for member m_seqedit_scale

int seqedit_key () const

'Getter' function for member m_seqedit_key

void seqedit_key (int key)

'Setter' function for member m_seqedit_key

• int seqedit_bgsequence () const

'Getter' function for member m_seqedit_bgsequence

void seqedit_bgsequence (int seqnum)

'Setter' function for member m_seqedit_bgsequence Note that SEQ64_IS_LEGAL_SEQUENCE() allows the SE← Q64_SEQUENCE LIMIT (0x800 = 2048) value, to turn off the use of a background sequence.

• bool use_new_font () const

'Getter' function for member m_use_new_font

bool allow_two_perfedits () const

'Getter' function for member m_allow_two_perfedits

int perf_h_page_increment () const

'Getter' function for member m_h_perf_page_increment

• int perf_v_page_increment () const

'Getter' function for member m_v_perf_page_increment

· bool save_user_config () const

'Getter' function for member m_save_user_config

void save_user_config (bool flag)

'Setter' function for member m_save_user_config

• int midi_ppqn () const

'Getter' function for member m_midi_ppqn

int midi_beats_per_bar () const

'Getter' function for member m_midi_beats_per_measure

· int midi beats per minute () const

'Getter' function for member m_midi_beats_per_minute

int midi_beat_width () const

'Getter' function for member m_midi_beat_width

• char midi_buss_override () const

'Getter' function for member m_midi_buss_override

• int min_zoom () const

'Getter' function for member mc_min_zoom

• int max_zoom () const

'Getter' function for member mc_max_zoom

• int baseline_ppqn () const

'Getter' function for member mc_baseline_ppqn

void use_new_font (bool flag)

'Setter' function for member m_use_new_font

void allow_two_perfedits (bool flag)

Sets the value of allowing two perfedits to be created and shown to the user.

· void perf h page increment (int inc)

Sets the horizontal page increment size for the horizontal scrollbar of a perfedit window.

void perf_v_page_increment (int inc)

Sets the vertical page increment size for the vertical scrollbar of a perfedit window.

void midi_ppqn (int ppqn)

'Setter' function for member m_midi_ppqn This value can be set from 96 to 960 (this upper limit will be determined by what Sequencer64 can actually handle).

· void midi buss override (char buss)

'Setter' function for member m_midi_buss_override This value can be set from 0 to 31.

Protected Member Functions

void grid brackets (int thickness)

'Getter' function for member m_grid_brackets

· void grid style (int gridstyle)

'Setter' function for member m_grid_style

void mainwnd_rows (int value)

'Setter' function for member m_mainwnd_rows This value is not modified unless the value parameter is between 4 and 8. inclusive.

· void mainwnd cols (int value)

'Setter' function for member m_mainwnd_cols This value is not modified unless the value parameter is between 8 and 10, inclusive.

• void max_sets (int value)

'Setter' function for member m_max_sets This value is not modified unless the value parameter is between 32 and 64, inclusive.

void text_x (int value)

'Setter' function for member m_text_x This value is not modified unless the value parameter is between 6 and 6, inclusive.

void text_y (int value)

'Setter' function for member m_text_y This value is not modified unless the value parameter is between 12 and 12, inclusive.

void seqchars_x (int value)

'Setter' function for member m_seqchars_x This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 15.

void segchars y (int value)

'Setter' function for member m_seqchars_y This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 5.

void segarea_x (int value)

'Setter' function for member m segarea x

void seqarea_y (int value)

'Setter' function for member m_seqarea_y

void seqarea_seq_x (int value)

'Setter' function for member m_segarea_seg_x

void segarea seg y (int value)

'Setter' function for member m_seqarea_seq_y

void mainwid_border (int value)

'Setter' function for member m_mainwid_border This value is not modified unless the value parameter is between 0 and 3, inclusive.

void mainwid_spacing (int value)

'Setter' function for member m_mainwid_spacing This value is not modified unless the value parameter is between 2 and 6, inclusive.

void control height (int value)

'Setter' function for member m_control_height This value is not modified unless the value parameter is between 0 and 4, inclusive.

• void dump_summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

void midi_beats_per_bar (int beatsperbar)

'Setter' function for member m_midi_beats_per_measure This value can be set from 1 to 16.

void midi_beats_per_minute (int beatsperminute)

'Setter' function for member m_midi_beats_minute This value can be set from 20 to 500.

void midi_beat_width (int beatwidth)

'Setter' function for member m_midi_beatwidth This value can be set to any power of 2 in the range from 1 to 16.

Private Types

```
    enum mainwid_grid_style_t {
        grid_style_normal,
        grid_style_white,
        grid_style_black,
        grid_style_max }
```

• typedef std::vector< user midi bus > Busses

[user-midi-bus-definitions]

typedef std::vector< user_instrument > Instruments

[user-instrument-definitions]

Private Member Functions

user_midi_bus & private_bus (int buss)

'Getter' function for member m_midi_buses[index] (internal function) If the index is out of range, then an invalid object is returned

• user_instrument & private_instrument (int instrum)

'Getter' function for member m_instruments[index] If the index is out of range, then a invalid object is returned.

Private Attributes

· Busses m midi buses

Provides data about the MIDI busses, readable from the "user" configuration file.

• Instruments m_instruments

Provides data about the MIDI instruments, readable from the "user" configuration file.

mainwid_grid_style_t m_grid_style

[user-interface-settings]

· int m grid brackets

Specify drawing brackets (like the old Seq24) or a solid box.

• int m_mainwnd_rows

Number of rows in the Patterns Panel.

· int m mainwnd cols

Number of columns in the Patterns Panel.

int m_max_sets

Maximum number of screen sets that can be supported.

· int m mainwid border

These control sizes.

· int m_control_height

This constants seems to be created for a future purpose, perhaps to reserve space for a new bar on the mainwid pane.

int m_current_zoom

Provides the initial zoom value, in units of.

bool m_global_seq_feature_save

If true, this value provide a bit of backward-compatibility with the global key/scale/background-sequence persistence feature.

int m_seqedit_scale

Replaces sequence is loaded into the sequence editor.

int m_seqedit_key

Replaces seqedit::m_initial_key as the repository for the key to apply when a sequence is loaded into the sequence editor.

• int m_seqedit_bgsequence

Replaces sequedit::m_initial_sequence as the repository for the background sequence to apply when a sequence is loaded into the sequence editor.

· bool m_use_new_font

Sets the usage of the font.

bool m allow two perfedits

Enables the usage of two perfedit windows, for added convenience in editing multi-set songs.

int m_h_perf_page_increment

Allows a changed to the page size for the horizontal scroll bar.

int m_v_perf_page_increment

Allows a changed to the page size for the vertical scroll bar.

• int m text x

Constants for the mainwid class.

int m_seqchars_x

Constants for the mainwid class.

int m_midi_ppqn

Provides the universal PPQN setting for the duration of this setting.

• int m_midi_beats_per_measure

Provides the universal and unambiguous MIDI value for beats per measure, also called "beats per bar" (BPB).

· int m midi beats per minute

Provides the universal and unambiguous MIDI value for beats per minute (BPM).

· int m midi beat width

Provides the universal MIDI value for beats width (BW).

char m_midi_buss_override

Provides a universal override of the buss number for all sequences, for the purpose of convenience of of testing.

· int m_seqs_in_set

Number of patterns/sequences in the Patterns Panel, also known as a "set" or "screen set".

• int m_gmute_tracks

Number of group-mute tracks that can be supported, which is m_seqs_in_set squared, or 1024.

· int m max sequence

The maximum number of patterns supported is given by the number of patterns supported in the panel (32) times the maximum number of sets (32), or 1024 patterns.

• int m_seqarea_x

The m_seqarea_x and m_seqarea_y constants are derived from the width and heights of the default character set, and the number of characters in width, and the number of lines, in a pattern/sequence box.

• int m segarea seg x

Area of what? Doesn't look at all like it is based on the size of characters.

int m_mainwid_x

The width of the main pattern/sequence grid, in pixels.

bool m_save_user_config

Provides a temporary variable that can be set from the command line to cause the "user" state to be saved into the "user" configuration file.

• const int mc_min_zoom

Provides the minimum zoom value, currently a constant.

const int mc_max_zoom

Provides the maximum zoom value, currently a constant.

const int mc_baseline_ppqn

Permanent storage for the baseline, default PPQN used by Seq24.

10.67.1 Detailed Description

These settings will eventually be made part of the "user" settings file.

10.67.2 Member Typedef Documentation

```
10.67.2.1 typedef std::vector<user_midi_bus> seq64::user_settings::Busses [private]
```

Internal type for the container of user_midi_bus objects. Sorry about the "confusion" about "bus" versus "buss". See Google for arguments about it.

```
10.67.2.2 typedef std::vector<user instrument> seq64::user settings::Instruments [private]
```

Internal type for the container of user_instrument objects.

10.67.3 Member Enumeration Documentation

```
10.67.3.1 enum seq64::user_settings::mainwid_grid_style_t [private]
```

Enumerator

grid_style_normal Provides a setting to control the overall style of grid-drawing for the pattern slots in mainwid. These values can be specified in the [user-interface-settings] section of the "user" configuration file.

```
The grid background color is the normal background color for the current GTK theme. The box is drawn with brackets on either side.
```

grid_style_white The grid background color is white. This style better fits displaying the white-on-black sequence numbers. The box is drawn with brackets on either side.

grid_style_black The grid background color is black.

grid_style_max Marks the end of the list, and is an illegal value.

10.67.4 Constructor & Destructor Documentation

```
10.67.4.1 seq64::user_settings::user_settings()
```

Default constructor.

Should this be a float (6 significant digits) or two integers for scaling?

10.67.5 Member Function Documentation

```
10.67.5.1 void seq64::user_settings::set_defaults ( )
```

For the m_midi_buses and m_instruments members, this function can only iterate over the current size of the vectors. But the default size is zero!

```
10.67.5.2 void seq64::user_settings::set_globals() const
```

Should be called at initialization, and after settings are read from the "user" configuration file.

DO NOT PUT ANY GLOBALS HERE UNTIL THEIR EFFECTS HAVE BEEN TESTED!!!!

```
10.67.5.3 void seq64::user_settings::get_globals()
```

Should be called before settings are written to the "user" configuration file.

```
10.67.5.4 const user_midi_bus& seq64::user_settings::bus(int index) [inline]
Cannot append the const specifier.
10.67.5.5 const user_instrument& seq64::user_settings::instrument( int index ) [inline]
Cannot append the const specifier.
10.67.5.6 bool seq64::user_settings::controller_active ( int buss, int channel, int cc ) [inline]
It also has a shorter name.
10.67.5.7 const std::string& seq64::user settings::controller name (int buss, int channel, int cc) [inline]
It also has a shorter name.
10.67.5.8 void seq64::user_settings::zoom ( int value )
The default value is 2.
10.67.5.9 void seq64::user_settings::mainwnd_rows ( int value ) [protected]
The default value is 4. Dependent values are recalculated after the assignment.
10.67.5.10 void seq64::user_settings::mainwnd_cols ( int value ) [protected]
The default value is 8. Dependent values are recalculated after the assignment.
10.67.5.11 void seq64::user_settings::max_sets ( int value ) [protected]
The default value is 32. Dependent values are recalculated after the assignment.
10.67.5.12 void seq64::user_settings::text_x ( int value ) [protected]
The default value is 6. Dependent values are recalculated after the assignment. This value is currently restricted,
until we can code up a bigger font.
10.67.5.13 void seq64::user_settings::text_y ( int value ) [protected]
The default value is 12. Dependent values are recalculated after the assignment. This value is currently restricted,
until we can code up a bigger font.
10.67.5.14 void seg64::user settings::mainwid border (int value) [protected]
The default value is 0. Dependent values are recalculated after the assignment.
```

The default value is 2. Dependent values are recalculated after the assignment.

10.67.5.15 void seq64::user_settings::mainwid_spacing (int value) [protected]

```
10.67.5.16 void seq64::user_settings::control_height(int value) [protected]
```

The default value is 0. Dependent values are recalculated after the assignment.

```
10.67.5.17 void seq64::user_settings::dump_summary( ) [protected]
```

Does its work only if PLATFORM_DEBUG and SEQ64_USE_DEBUG_OUTPUT are defined. Only enabled in emergencies:-D.

```
10.67.5.18 void seq64::user_settings::perf_h_page_increment ( int inc )
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 6 (which is 24 measures, the same as the typical width of the perfroll)

```
10.67.5.19 void seq64::user_settings::perf_v_page_increment ( int inc )
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 18 (which is 18 tracks, slightly more than the typical height of the perfroll)

```
10.67.5.20 void seq64::user_settings::midi_ppqn ( int value )
```

The default value is 192. Dependent values may be recalculated after the assignment.

```
10.67.5.21 void seq64::user_settings::midi_buss_override ( char buss )
```

The default value is -1, which means that there is no buss override. It provides a way to override the buss number for smallish MIDI files. It replaces the buss-number read from the file. This option is turned on by the —bus option, and is merely a convenience feature for the quick previewing of a tune. (It's called "developer laziness".)

```
10.67.5.22 void seq64::user_settings::midi_beats_per_bar(int value) [protected]
```

The default value is 4.

```
10.67.5.23 void seq64::user_settings::midi_beats_per_minute( int value ) [protected]
```

The default value is 120.

```
10.67.5.24 void seq64::user_settings::midi_beat_width(int bw) [protected]
```

The default value is 4.

```
10.67.5.25 user_midi_bus & seq64::user_settings::private_bus(int index) [private]
```

This invalid object has an empty alias, and all the instrument numbers are -1.

```
10.67.5.26 user_instrument & seq64::user_settings::private_instrument(int index) [private]
```

This invalid object has an empty(), instrument name, false for all controllers_active[] values, and empty controllers[] string values.

10.67.6 Field Documentation

10.67.6.1 Busses seq64::user_settings::m_midi_buses [private]

Since this object is a vector, its size is adjustable.

10.67.6.2 Instruments seq64::user_settings::m_instruments [private]

The size is adjustable, and grows as objects are added.

10.67.6.3 mainwid grid style t seq64::user_settings::m_grid_style [private]

Specifies the current grid style.

```
10.67.6.4 int seq64::user_settings::m_grid_brackets [private]
```

0 = no brackets, 1 and above is the thickness of the brakets. 1 is the normal thickness of the brackets, 2 is a two-pixel thickness, and so on.

```
10.67.6.5 int seq64::user_settings::m_mainwnd_rows [private]
```

The current value is 4, and if changed, many other values depend on it. Together with m_mainwnd_cols, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set". We would like to be able to change this value from 4 to 8, and maybe allow the values of 5, 6, and 7 as well. But if we could just get 8 working, then well would Sequencer64 deserve the 64 in its name.

```
10.67.6.6 int seq64::user_settings::m_mainwnd_cols [private]
```

The current value is 4, and probably won't change, since other values depend on it. Together with m_mainwnd_rows, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set".

```
10.67.6.7 int seq64::user_settings::m_max_sets [private]
```

Basically, that the number of times the Patterns Panel can be filled. 32 sets can be created. Although this value is part of the "user" configuration file, it is likely that it will never change. Rather, the number of sequences per set would change. We'll see.

```
10.67.6.8 int seq64::user_settings::m_mainwid_border [private]
```

We'll try changing them and see what happens. Increasing these value spreads out the pattern grids a little bit and makes the Patterns panel slightly bigger. Seems like it would be useful to make these values user-configurable.

```
10.67.6.9 int seq64::user_settings::m_control_height [private]
```

But it is used only in this header file, to define m_mainwid_y, but doesn't add anything to that value.

```
10.67.6.10 bool seq64::user_settings::m_global_seq_feature_save [private]
```

In this feature, applying one of these three changes to a sequence causes them to also be applied to sequences that are subsequently opened for editing. However, we improve on this feature by allowing the changes to be saved in the global, proprietary part of the saved MIDI file.

If false, the user can still save the key/scale/background-sequence values with each individual sequence, so they can be different.

This value will be true by default, unless changed in the "user" configuration file.

```
10.67.6.11 int seq64::user_settings::m_seqedit_scale [private]
```

Its default value is c_scale_off. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musicscale, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musicscale.

```
10.67.6.12 int seq64::user_settings::m_seqedit_key [private]
```

Its default value is SEQ64_KEY_OF_C. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musickey, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musickey.

```
10.67.6.13 int seq64::user_settings::m_seqedit_bgsequence [private]
```

Its default value is SEQ64_SEQUENCE_LIMIT. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored, if it has a valid (but not "legal") value, in the "proprietary" track at the end of the file, under the control tag c_backsequence, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_backsequence.

```
10.67.6.14 bool seq64::user_settings::m_use_new_font [private]
```

By default, in normal mode, the new font is used. In legacy mode, the old font is used.

```
10.67.6.15 bool seq64::user_settings::m_allow_two_perfedits [private]
```

Defaults to true.

```
10.67.6.16 int seq64::user_settings::m_h_perf_page_increment [private]
```

The value used to be hardwired to 1 (in four-measure units), now it defaults to 4 (16 measures at a time). The value of 1 is already covered by the scrollbar arrows.

```
10.67.6.17 int seq64::user_settings::m_v_perf_page_increment [private]
```

The value used to be hardwired to 1 (in single-track units), now it defaults to 8. The value of 1 is already covered by the scrollbar arrows.

```
10.67.6.18 int seq64::user_settings::m_text_x [private]
```

The m_text_x and m_text_y constants help define the "seqarea" size. It looks like these two values are the character width (x) and height (y) in pixels. Thus, these values would be dependent on the font chosen. But that, currently, is hard-wired. See the m_font_6_12[] array for the default font specification.

However, please not that font files are not used. Instead, the fonts are provided by two pixmaps in the src/pixmap
directory: font_b.xpm (black lettering on a white background) and font_w.xpm (white lettering on a black background).

We have added black-on-yellow and yellow-on-black versions of the fonts, to support the highlighting of pattern boxes if they are empty of actual MIDI events.

We have also added a set of four new font files that are roughly the same size, and are treated as the same size, but look smooth and less like a DOS-era font.

The font module does not use these values directly, but does define some similar variables that differ slightly between the two styles of font. There are a lot of tricks and hard-wired places to fix before further work can be done with fonts in Sequencer64.

```
10.67.6.19 int seq64::user_settings::m_seqchars_x [private]
```

The m_seqchars_x and m_seqchars_y constants help define the "seqarea" size. These look like the number of characters per line and the number of lines of characters, in a pattern/sequence box.

```
10.67.6.20 int seq64::user_settings::m_midi_ppqn [private]
```

This variable replaces the global ppqn. The default value of this setting is 192 parts-per-quarter-note (PPQN). There is still a lot of work to get a different PPQN to work properly in speed of playback, scaling of the user interface, and other issues. Note that this value can be changed by the still-experimental –ppqn option. There is one remaining trace of the global, though: DEFAULT_PPQN.

```
10.67.6.21 int seq64::user_settings::m_midi_beats_per_measure [private]
```

This variable will replace the global beats per measure. The default value of this variable is SEQ64_DEFAULT_← BEATS_PER_MEASURE (4). For external access, we will call this value "beats per bar", abbreviate it "BPB", and use "bpb" in any accessor function names. Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BPB value, either for MIDI purposes or for drawing the piano-roll grids. So we might need a couple different versions of this variable.

```
10.67.6.22 int seq64::user_settings::m_midi_beats_per_minute [private]
```

This variable will replace the global beats per minute. The default value of this variable is DEFAULT_BPM (120). This variable should apply to the whole session; there's probably no way to support a diffent tempo for each sequence. But we shall see. For external access, we will call this value "beats per minute", abbreviate it "BPM", and use "bpm" in any accessor function names.

```
10.67.6.23 int seq64::user_settings::m_midi_beat_width [private]
```

This variable will replace the global beat_width. The default value of this variable is DEFAULT_BEAT_WIDTH (4). Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BW value, either for MIDI purposes or for drawing the user-interface. So we might need a couple different versions of this variable. For external access, we will call this value "beat width", abbreviate it "BW", and use "bw" in any accessor function names.

```
10.67.6.24 char seq64::user_settings::m_midi_buss_override [private]
```

This variable replaces the global buss-override variable, and is set via the command-line option —bus.

```
10.67.6.25 int seq64::user_settings::m_seqs_in_set [private]
```

This value is $4 \times 8 = 32$ by default.

Warning

Currently implicit/explicit in a number of the "rc" file and rc_settings. Would probably want the left 32 or the first 32 items in the main window only to be subject to keystroke control. This value is calculated by the normalize() function, and is *not* part of the "user" configuration file.

```
10.67.6.26 int seq64::user_settings::m_gmute_tracks [private]
```

This value is *not* part of the "user" configuration file; it is calculated by the normalize() function.

```
10.67.6.27 int seq64::user_settings::m_max_sequence [private]
```

It is a derived value, and not stored in the "user" file.

```
m_max_sequence = m_seqs_in_set * m_max_sets;
```

```
10.67.6.28 int seq64::user_settings::m_seqarea_x [private]
```

Compare these two constants to m_seqarea_seq_x(y), which was in mainwid.h, but is now in this file.

```
10.67.6.29 int seq64::user_settings::m_seqarea_seq_x [private]
```

These are used only in the mainwid module.

```
10.67.6.30 int seq64::user_settings::m_mainwid_x [private]
```

Affected by the m_mainwid_border and m_mainwid_spacing values.

```
10.67.6.31 bool seq64::user_settings::m_save_user_config [private]
```

Normally, this state is not saved. It is not saved because there is currently no user-interface for editing it, and because it can pick up some command-line options, and it is not right to have them written to the "user" configuration file.

(The "rc" configuration file is a different case, having historically always been saved, and having a number of command-line options, such as JACK settings that should generally be permanent on a given system.)

Anyway, this flag can be set by the -user-save option. This setting is never saved. But note that, if no "user" configuration file is found, it is then saved anyway.

```
10.67.6.32 const int seq64::user_settings::mc_min_zoom [private]
```

It's value is 1.

10.67.6.33 const int seq64::user_settings::mc_max_zoom [private]

It's value is 32.


10.67.6.34 const int seq64::user_settings::mc_baseline_ppqn [private]

This value is necessary in order to keep user-interface elements stable when different PPQNs are used. It is set to DEFAULT_PPQN.

10.68 seq64::userfile Class Reference

Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24usr configuration file

Inheritance diagram for seq64::userfile:



Public Member Functions

- userfile (const std::string &a_name)
 - Principal constructor.
- ∼userfile ()

A rote destructor needed for a derived class.

• bool parse (perform &a_perf)

Parses a "usr" file, filling in the given perform object.

bool write (const perform &a_perf)

This function just returns false, as there is no "perform" information in the user-file yet.

Private Member Functions

• void dump_setting_summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

Additional Inherited Members

10.68.1 Member Function Documentation

```
10.68.1.1 bool seq64::userfile::parse ( perform & a_perf ) [virtual]
```

This function opens the file as a text file (line-oriented).

Parameters

```
a_perf The performance object, currently unused.
```

Implements seq64::configfile.

10.68.1.2 bool seq64::userfile::write (const perform & a_perf) [virtual]

Parameters

```
a_perf | The performance object, currently unused.
```

Implements seq64::configfile.

10.68.1.3 void seq64::userfile::dump_setting_summary() [private]

Does work only if PLATFORM_DEBUG is defined; see the user_settings class.

Index

\sim event	seq64::perform, 202
seq64::event, 60	analyze
\sim eventedit	seq64::editable_event, 50
seq64::eventedit, 75	any_selected_notes
~jack_assistant	seq64::event_list, 71
seq64::jack_assistant, 109	append_sysex
~keys_perform	seq64::event, 64
seq64::keys_perform, 119	apply_length
~keys_perform_gtk2	seq64::seqedit, 239
seq64::keys_perform_gtk2, 123	2040 120404, 200
~perfedit	BLACK
seq64::perfedit, 182	seq64::font, 92
	BLACK_ON_CYAN
~perform	seq64::font, 92
seq64::perform, 195	-
~perfroll	BLACK_ON_YELLOW
seq64::perfroll, 215	seq64::font, 92
\sim seqmenu	background_sequence
seq64::seqmenu, 253	seq64::sequence, 283
	bus
about_dialog	seq64::user_settings, 306
seq64::mainwnd, 143	Busses
add	seq64::user_settings, 306
seq64::editable_events, 54	button
seq64::event_list, 69	seq64::options, 175
seq64::triggers, 289	• •
add event	CYAN ON BLACK
seq64::sequence, 273, 279	seq64::font, 92
add_long	calculate_base_sizes
seq64::midi_container, 148	seq64::mainwid, 136
add_note	category
seq64::sequence, 279	seq64::editable_event, 49
	category_channel_message
add_sequence	seq64::editable event, 47
seq64::perform, 197	. –
add_trigger	category_meta_event
seq64::sequence, 274	seq64::editable_event, 47
add_variable	category_name
seq64::midi_container, 148	seq64::editable_event, 47
adj_callback_bpm	category_prop_event
seq64::mainwnd, 143	seq64::editable_event, 47
adj_callback_ss	category_system_message
seq64::mainwnd, 143	seq64::editable_event, 47
adjust_offset	category_t
seq64::triggers, 293	seq64::editable_event, 47
adjust_offsets_to_length	change_event_data_range
seq64::triggers, 290	seq64::sequence, 280
adjust_trigger_offsets_to_length	change_vert
seq64::sequence, 284	seq64::eventslots, 88
alias	channel_count
seq64::user_midi_bus_t, 299	seq64::user_midi_bus, 298
all_notes_off	channel_max

seq64::user_midi_bus, 298	сору
CharList	seq64::perfedit, 183
seq64::midi_list, 150	seq64::triggers, 292
• —	
check_channel	copy_definitions
seq64::event, 61	seq64::user_instrument, 296
clamp_track	seq64::user_midi_bus, 298
seq64::perform, 209	copy_events
clear	seq64::sequence, 283
seq64::event_list, 70	copy_selected
clear_all	seq64::sequence, 279
seq64::perform, 195	copy_triggers
clear_sequence_triggers	seq64::perform, 198
seq64::perform, 197	seq64::sequence, 277
clear_triggers	count
seq64::sequence, 278	seq64::editable_events, 54
clear_window	seq64::event_list, 69
seq64::gui_drawingarea_gtk2, 99	count_selected_events
click	seq64::event list, 71
	create_menus
seq64::click, 39	seq64::seqedit, 240
client_open	cut_selected
seq64::jack_assistant, 112	seq64::sequence, 279
clock	sequalite, 279
seq64::midibus, 160	decrement_beats_per_minute
collapse	seq64::perform, 206
seq64::perfedit, 183	decrement_bottom
Color	seq64::eventslots, 89
seq64::font, 92	•
cond	decrement_current
seq64::condition_var, 42	seq64::eventslots, 89
configfile	decrement_selected
seq64::configfile, 43	seq64::sequence, 280
continue_from	decrement_top
seq64::midibus, 160	seq64::eventslots, 88
control_height	deinit_in
_ ·	seq64::midibus, 159
seq64::user_settings, 307	deinit_jack
controller_active	seq64::perform, 208
seq64::user_instrument, 295	del_trigger
seq64::user_settings, 307	seq64::sequence, 274
controller_max	delete_current_event
seq64::user_instrument, 295	seq64::eventslots, 85
controller_name	delete_sequence
seq64::user_instrument, 295	seq64::perform, 197
seq64::user_settings, 307	do action
controllers	seq64::seqedit, 241
seq64::user instrument t, 296	draw_background
controllers active	seq64::seqevent, 244
seq64::user instrument t, 296	draw_drawable_row
convert t	seq64::perfroll, 218
seq64::seqevent, 245	• •
convert_tn	draw_event
	seq64::eventslots, 87
seq64::seqroll, 258	draw_events
convert_x	seq64::eventslots, 87
seq64::perfroll, 217	draw_events_on
seq64::seqevent, 245	seq64::seqevent, 245
convert_xy	seq64::seqroll, 258
seq64::perfroll, 217	draw_events_on_pixmap
convert_y	seq64::seqroll, 258
seq64::eventslots, 87	draw_key

seq64::seqkeys, 250	seq64::sequence, 269
draw line	edit_callback_notepad
seq64::gui_drawingarea_gtk2, 99–101	seq64::mainwnd, 143
draw_line_on_pixmap	editable_event
seq64::gui_drawingarea_gtk2, 99, 100	seq64::editable_event, 48
draw_marker_on_sequence	editable_events
seq64::mainwid, 134	seq64::editable_events, 53
draw_normal_rectangle_on_pixmap	enqueue_draw
seq64::gui_drawingarea_gtk2, 103	seq64::eventedit, 75
draw pixmap on window	seq64::evertedit, 73
seq64::seqevent, 244	seq64::perfnames, 187
draw_rectangle	·
	seq64::perfroll, 218
seq64::gui_drawingarea_gtk2, 101–103	seq64::perftime, 222
draw_rectangle_on_pixmap	enregister_peer
seq64::gui_drawingarea_gtk2, 103	seq64::perfedit, 183
draw_sequence	errdump
seq64::perfnames, 187	seq64::midifile, 171
draw_sequence_on	error_message
seq64::perfroll, 218	seq64::jack_assistant, 112
draw_sequence_on_pixmap	event
seq64::mainwid, 135	seq64::event, 60
draw_sequence_pixmap_on_window	event_count
seq64::mainwid, 135	seq64::sequence, 269
draw_sequences_on_pixmap	event_key
seq64::mainwid, 135	seq64::event_list::event_key, 66
drop_event	event_list
seq64::seqevent, 245	seq64::event_list, 69
dump_setting_summary	eventedit
seq64::userfile, 314	seq64::eventedit, 74
dump_summary	events
seq64::user_settings, 308	seq64::keybindentry, 116
	expand
e_deselect	seq64::perfedit, 183
seq64::sequence, 269	
e_is_selected	file_import_dialog
seq64::sequence, 269	seq64::mainwnd, 143
e_jack_connect	fill
seq64::options, 176	seq64::midi_container, 147
e_jack_disconnect	fill_background_pixmap
seq64::options, 176	seq64::perfroll, 217
e_jack_master	fill_container
seq64::options, 176	seq64::sequence, 283
e_jack_master_cond	finish
seq64::options, 176	seq64::perform, 198
e_jack_start_mode_live	format_timestamp
seq64::options, 176	seq64::editable_event, 50
e_jack_start_mode_song	FruityPerfInput
seq64::options, 176	seq64::perfroll, 219
e_jack_transport	coqopoo, =
seq64::options, 176	get
e_remove_one	seq64::midi_container, 147
seg64::seguence, 269	seg64::midi list. 150
seq64::sequence, 269 e select	seq64::midi_list, 150 seq64::midi_vector, 157
e_select	seq64::midi_vector, 157
e_select seq64::sequence, 269	seq64::midi_vector, 157 get_beat_width
e_select seq64::sequence, 269 e_select_one	seq64::midi_vector, 157 get_beat_width seq64::sequence, 271
e_select seq64::sequence, 269 e_select_one seq64::sequence, 269	seq64::midi_vector, 157 get_beat_width seq64::sequence, 271 get_clipboard_box
e_select seq64::sequence, 269 e_select_one seq64::sequence, 269 e_toggle_selection	seq64::midi_vector, 157 get_beat_width seq64::sequence, 271 get_clipboard_box seq64::sequence, 279
e_select seq64::sequence, 269 e_select_one seq64::sequence, 269	seq64::midi_vector, 157 get_beat_width seq64::sequence, 271 get_clipboard_box

get_globals	grow_selected
seq64::user_settings, 306	seq64::sequence, 281
get_group_mute_state	grow_trigger
seq64::perform, 205	seq64::sequence, 274
get_highest_note_event	gui_assistant
seq64::sequence, 282	seq64::gui_assistant, 95
get_jack_ticks	gui_palette_gtk2
seq64::jack_assistant, 112	seq64::gui_palette_gtk2, 105
get_keys	gui_window_gtk2
seq64::keys_perform, 120	seq64::gui_window_gtk2, 107
get_last_tick	handle config
seq64::sequence, 271	handle_config
get_lowest_note_event	seq64::lash, 127
seq64::sequence, 282	handle_event
get_max_trigger	seq64::lash, 127
seq64::perform, 198	handle_insert
seq64::sequence, 277	seq64::eventedit, 78
get_measures	handle_midi_control
seq64::seqedit, 239	seq64::perform, 199
get_name	handle_modify
seq64::sequence, 271	seq64::eventedit, 78
get_next_event	handle_motion_key
seq64::sequence, 283	seq64::Seq24PerfInput, 227
get_next_note_event	handle_save
seq64::sequence, 282	seq64::eventedit, 78
get_num_selected_events	highlight
seq64::sequence, 278	seq64::perform, 206
get_num_selected_notes	home_config_directory
seq64::sequence, 278	seq64::rc_settings, 225
get_rank	idle_progress
seq64::event, 65	
get_screen_set_notepad	seq64::maintime, 130
seq64::perform, 199	idle_redraw
get_selected_box	seq64::seqdata, 233
seq64::sequence, 279	seq64::seqevent, 245 increment
get_selected_end	
seq64::triggers, 292	seq64::midi_splitter, 153
get_selected_start	increment_beats_per_minute
seq64::triggers, 292	seq64::perform, 206
get_sequence	increment_bottom
seq64::perform, 203	seq64::eventslots, 89
get_state	increment_current
seq64::triggers, 291	seq64::eventslots, 89
get_trigger_state	increment_selected
seq64::sequence, 274	seq64::sequence, 280
grid_style_black	increment_top
seq64::user settings, 306	seq64::eventslots, 88
. – •	info_message
grid_style_max	seq64::jack_assistant, 112
seq64::user_settings, 306	init
grid_style_normal	seq64::font, 92
seq64::user_settings, 306	seq64::jack_assistant, 110
grid_style_white	seq64::lash, 127
seq64::user_settings, 306	init_before_show
groups	seq64::perfedit, 182
seq64::keybindentry, 116	seq64::perfroll, 217
grow	init_clock
seq64::perfedit, 183	seq64::midibus, 160
seq64::triggers, 290	init_in

seq64::midibus, 159	is_one_byte_msg
init_in_sub	seq64::event, 61
seq64::midibus, 159	is_screenset_valid
init_jack	seq64::perform, 208
seq64::perform, 208	is_seq_valid
init_out	seq64::perform, 208
seq64::midibus, 159	is_sysex_special_id
init_out_sub	seq64::midifile, 171
seq64::midibus, 159	is_two_byte_msg
inner_start	seq64::event, 61
seq64::perform, 209	
insert_event	jack_assistant
seq64::eventslots, 84	seq64::jack_assistant, 109
install_sequence	jack_shutdown_callback
seq64::perform, 209	seq64::jack_assistant, 114
instrument	jack_timebase_callback
seq64::user_instrument_t, 296	seq64::jack_assistant, 115
seq64::user_midi_bus, 298	Vov
seq64::user_midi_bus_t, 299	Key
seq64::user_settings, 307	seq64::editable_events, 53
Instruments	key_name
seq64::user_settings, 306	seq64::keys_perform, 120
intersect	seq64::keys_perform_gtk2, 123
seq64::triggers, 291	keybindentry
intersect_events	seq64::keybindentry, 117
seq64::sequence, 275	keystroke
intersect_notes	seq64::keystroke, 124, 125
seq64::sequence, 275	lash
intersect_triggers	
seq64::sequence, 275	seq64::lash, 126
is_active	lash_timeout_connect seq64::gui_assistant_gtk2, 96
seq64::perform, 203	launch
is_channel_msg	seq64::perform, 195
seq64::event, 61	launch_input_thread
is_desired_cc_or_not_cc	seq64::perform, 207
seq64::event, 63	launch output thread
is_dirty_edit	seq64::perform, 208
seq64::perform, 202	line_after
seq64::sequence, 272	seq64::configfile, 43
is_dirty_main	link_new
seq64::perform, 202	seq64::event_list, 70
seq64::sequence, 272	seq64::sequence, 281
is_dirty_names	load_events
seq64::perform, 203	seq64::editable_events, 54
seq64::sequence, 272	seq64::eventslots, 84
is dirty perf	location
seq64::perform, 203	seq64::keybindentry, 116
seq64::sequence, 272	36404Reybilidentity, 110
is_letter	m_allow_two_perfedits
seq64::keystroke, 125	seq64::user_settings, 310
is_midi_control_valid	m_b_on_c_pixmap
seq64::perform, 208	seq64::font, 93
is_modified	m_b_on_y_pixmap
seq64::perform, 208	seq64::font, 93
is_mseq_valid	m_background
seq64::perform, 209	seq64::gui_drawingarea_gtk2, 104
is_note_msg	m_background_sequence
seq64::event, 61	seq64::sequence, 285
ooqo+ovoni, or	3040+354u51105, 200

and the control of the	
m_bar_width	seq64::midifile, 173
seq64::maintime, 131	m_flash_height
m_beat_width	seq64::maintime, 131
seq64::maintime, 131	m_flash_width
seq64::midi_timing, 155	seq64::maintime, 131
m_beats_per_measure	m_font_h
seq64::midi_timing, 155	seq64::font, 93
m_beats_per_minute	m_font_w
seq64::midi_timing, 155	seq64::font, 93
m_black_pixmap	m_foreground
seq64::font, 93	seq64::gui_drawingarea_gtk2, 104
m_box_height	m_format_timestamp
	_ ·
seq64::maintime, 131	seq64::editable_event, 51
m_box_width	m_fruity_interaction
seq64::maintime, 131	seq64::perfroll, 219
m_bpm	m_global_seq_feature_save
seq64::perfedit, 184	seq64::user_settings, 309
m_button	m_gmute_tracks
seq64::click, 40	seq64::user_settings, 312
m_bw	m_grid_brackets
seq64::perfedit, 184	seq64::user settings, 309
m_c_on_b_pixmap	m_grid_style
seq64::font, 93	seq64::user_settings, 309
•	. – •
m_category	m_h_page_increment
seq64::editable_event, 51	seq64::perfroll, 219
m_channel	m_h_perf_page_increment
seq64::event, 65	seq64::user_settings, 310
m_channel_count	m_has_link
seq64::user_midi_bus, 298	seq64::event, 65
m_char_list	m_initial_snap
seq64::midifile, 173	seq64::seqedit, 241
m_char_w	m instruments
seq64::eventslots, 90	seq64::user_settings, 309
seq64::perfnames, 187	m is modified
m clip mask	seq64::event_list, 71
seq64::font, 93	seq64::perform, 211
•	
m_control_height	m_is_press
seq64::user_settings, 309	seq64::keystroke, 125
m_controller_count	m_is_valid
seq64::user_instrument, 296	seq64::user_instrument, 296
m_current_event	seq64::user_midi_bus, 298
seq64::editable_events, 55	m_key
m_current_index	seq64::keybindentry, 117
seq64::eventslots, 90	seq64::keystroke, 125
m_data	m_key_bpm_up
seq64::event, 65	seq64::keys_perform, 121
seq64::midifile, 173	m_key_show_ui_sequence_number
m_disable_reported	seq64::keys_perform, 121
·	
seq64::midifile, 173	m_left_marker_tick
m_divisions	seq64::perftime, 223
seq64::midi_measures, 151	m_left_tick
m_drop_x	seq64::perform, 210
seq64::gui_drawingarea_gtk2, 104	m_length
m_error_is_fatal	seq64::sequence, 285
seq64::midifile, 173	seq64::triggers, 294
m_error_message	m_line
seq64::midifile, 173	seq64::configfile, 43
m_file_size	m_main_wid

seq64::mainwnd, 145	seq64::options, 176
m_mainperf	m_number_h
seq64::gui_drawingarea_gtk2, 104	seq64::seqdata, 234
m_mainwid_border	m_number_offset_y
seg64::user settings, 309	seq64::seqdata, 234
m_mainwid_x	m_number_w
seq64::user_settings, 312	seq64::seqdata, 234
m_mainwnd_cols	m one measure
seq64::user_settings, 309	seq64::perform, 210
m_mainwnd_rows	m_parent
seg64::user settings, 309	seq64::editable event, 51
m_max_sequence	seq64::perfnames, 187
seq64::user_settings, 312	seq64::perfroll, 219
m max sets	seq64::perftime, 223
seq64::perform, 211	m_pixmap
seq64::user_settings, 309	seq64::font, 93
m_measure_length	seq64::gui_drawingarea_gtk2, 104
seq64::perftime, 223	m_playback_mode
m_midi_beat_width	seq64::perform, 210
seq64::user_settings, 311	m_playing_notes
m_midi_beats_per_measure	seq64::sequence, 284
seg64::user settings, 311	m_playscreen_offset
m_midi_beats_per_minute	seq64::perform, 210
seq64::user_settings, 311	m pos
m midi buses	seq64::midifile, 173
seq64::user_settings, 309	m_ppqn
m_midi_buss_override	seq64::maintime, 131
seq64::user_settings, 311	seq64::mainwnd, 145
m_midi_channel	seq64::midi_timing, 155
seq64::sequence, 284	seq64::triggers, 294
m_midi_parameters	m rank
seq64::editable_events, 55	seq64::event_list::event_key, 66
m_midi_ppqn	m_redraw_ms
seq64::user_settings, 311	seq64::eventedit, 79
m modified	seq64::perfedit, 184
seg64::segmenu, 254	m_right_marker_tick
m_modifier	seq64::perftime, 223
seg64::click, 40	m right tick
seq64::keystroke, 125	seq64::perform, 210
m_musical_key	m_save_user_config
seq64::sequence, 285	seq64::user_settings, 312
m_musical_scale	m screenset offset
seg64::sequence, 285	seq64::mainwid, 138
m_mutex	m screenset slots
seg64::sequence, 285	seq64::mainwid, 138
m name meta	m seq number
seq64::editable_event, 51	seq64::sequence, 285
m_name_status	m_seqarea_seq_x
seq64::editable_event, 51	seq64::user_settings, 312
m namebox w	m segarea x
seq64::perfnames, 188	seq64::user_settings, 312
m_names_chars	m_seqchars_x
seq64::perfnames, 187	seq64::user_settings, 311
m_names_y	m_seqedit
seq64::perfnames, 188	seq64::seqmenu, 254
m_new_format	m_seqedit_bgsequence
seq64::midifile, 173	seq64::user_settings, 310
m_notebook	m_seqedit_key

seq64::user_settings, 310	m_v_perf_page_increment
m_seqedit_scale	seq64::user_settings, 310
seq64::user_settings, 310	m_white_pixmap
m_seqs	seq64::font, 93
seq64::perform, 210	m_window
m_seqs_in_set	seq64::gui_drawingarea_gtk2, 104
seq64::perform, 211	m_window_x
seq64::user_settings, 311	seq64::gui_drawingarea_gtk2, 104
m_sequence	seq64::gui_window_gtk2, 108
seq64::editable_events, 55	m_x
m_sequence_count	seq64::click, 40
seq64::perform, 211	m_xy_offset
m_sequence_max	seq64::eventslots, 90
seq64::perform, 211	seq64::perfnames, 188
m_setbox_w	m_y
seq64::eventslots, 90	seq64::click, 40
seq64::perfnames, 188	m_y_on_b_pixmap
m_sigpipe	seq64::font, 93
seq64::mainwnd, 145	maintime
m_slots_chars	seq64::maintime, 129
seq64::eventslots, 90	mainwid
m_slots_y	seq64::mainwid, 134
seq64::eventslots, 90	mainwid_border
m_smf0_channels	seq64::user_settings, 307
seq64::midi_splitter, 154	mainwid_grid_style_t
m_smf0_channels_count	seq64::user_settings, 306
seq64::midi_splitter, 154	mainwid_spacing
m_smf0_seq_number	seq64::user_settings, 307
seq64::midi_splitter, 154	mainwnd
m_smf0_splitter	seq64::mainwnd, 142
seq64::midifile, 173	mainwnd_cols
m_snap_tick	seq64::user_settings, 307
seq64::sequence, 285	mainwnd_key_event
m_spinbutton_load_offset	seq64::perform, 207
seq64::mainwnd, 145	mainwnd_rows
m_starting_tick	seq64::user settings, 307
seq64::perform, 211	mark all
m status	seq64::event_list, 71
seq64::event, 65	mark out of range
m sysex	seq64::event_list, 70
seq64::event, 65	mark_selected
m text x	seq64::sequence, 281
seq64::user_settings, 310	max_sets
m tick	seq64::user_settings, 307
seq64::maintime, 131	
•	mc_baseline_ppqn
seq64::perform, 211	seq64::user_settings, 313
m_time_beat_width	mc_max_zoom
seq64::sequence, 285	seq64::user_settings, 312
m_time_beats_per_measure	mc_min_zoom
seq64::sequence, 285	seq64::user_settings, 312
m_timestamp	merge
seq64::event_list::event_key, 66	seq64::event_list, 70
m_top_index	midi_beat_width
seq64::eventslots, 90	seq64::user_settings, 308
m_use_new_font	midi_beats_per_bar
seq64::user_settings, 310	seq64::user_settings, 308
m_v_page_increment	midi_beats_per_minute
seq64::perfroll, 219	seq64::user_settings, 308

midi_buss_override	seq64::seqkeys, 250
seq64::user_settings, 308	seq64::seqtime, 261
midi_control_off	on_button_release_event
seq64::perform, 199	seq64::Seq24PerfInput, 227
midi_control_on	seq64::Seq24SeqEventInput, 229
seq64::perform, 199	seq64::Seq24SeqRollInput, 230
midi_control_toggle	seq64::mainwid, 137
seq64::perform, 199	seq64::perfroll, 219
midi_ppqn	seq64::seqdata, 234
seq64::user_settings, 308	seq64::seqevent, 246
midi_splitter	seq64::seqkeys, 250
seq64::midi_splitter, 152	seq64::seqtime, 261
midifile	on_delete_event
seq64::midifile, 163	seq64::eventedit, 78
mod_last_tick	seq64::mainwnd, 144
seq64::sequence, 271	seq64::seqedit, 241
mod_timestamp	on_enter_notify_event
seq64::event, 63	seq64::seqkeys, 250
modify	on_expose_event
seq64::perform, 195	seq64::eventslots, 89
modify_current_event	seq64::maintime, 131
seq64::eventslots, 86	seq64::mainwid, 136
move_selected	seq64::perfnames, 187
seq64::triggers, 292	seq64::perfroll, 218
move_selected_notes	seq64::perftime, 222
seq64::sequence, 279	on_focus_in_event
move_selected_triggers_to	seq64::eventslots, 89
seq64::sequence, 277	seq64::mainwid, 137
move_triggers	on_focus_out_event
seq64::perform, 198	seq64::mainwid, 137
seq64::sequence, 277	on_grouplearnchange
name change callback	seq64::mainwnd, 145
name_change_callback	on_key_press_event
seq64::seqedit, 240 name to value	seq64::eventedit, 78
seq64::editable_event, 48	seq64::keybindentry, 117
new file	seq64::mainwnd, 145
seq64::mainwnd, 144	seq64::perfroll, 219
new sequence	seq64::seqevent, 246
seq64::perform, 197	seq64::seqroll, 258
next	on_key_release_event
seq64::triggers, 293	seq64::mainwnd, 145
next_data_line	on_leave_notify_event
seq64::configfile, 43	seq64::seqkeys, 250
next_trigger	on_motion_notify_event
seq64::triggers, 293	seq64::Seq24PerfInput, 227
3040+trigg013, 230	seq64::Seq24SeqEventInput, 229
off_playing_notes	seq64::mainwid, 137
seq64::sequence, 282	seq64::seqdata, 234
off_queued	seq64::seqevent, 246
seq64::sequence, 272	seq64::seqkeys, 250
on_button_press_event	on_move_down
seq64::Seq24PerfInput, 227	seq64::eventslots, 90
seq64::Seq24SeqEventInput, 229	on_move_up
seq64::Seq24SeqRollInput, 230	seq64::eventslots, 89
seq64::mainwid, 136	on_realize
seq64::perfroll, 218	seq64::eventslots, 89
seq64::seqdata, 234	seq64::gui_drawingarea_gtk2, 104
seq64::seqevent, 245	seq64::maintime, 131
1 7 7	

seq64::mainwid, 136	seq64::user_settings, 308
seq64::perfnames, 187	perf_v_page_increment
seq64::perfroll, 218	seq64::user_settings, 308
seq64::perftime, 222	perfedit
seq64::seqdata, 233	seq64::perfedit, 182
seq64::seqevent, 245	perfnames
seq64::seqkeys, 250	seq64::perfnames, 187
on_scroll_event	perform
seq64::seqdata, 234	seq64::perform, 195
seq64::seqroll, 259	perfroll_key_event
on size allocate	seq64::perform, 207
seq64::eventslots, 89	perftime
seq64::perfnames, 187	seq64::perftime, 222
open_file	play
seq64::mainwnd, 142	seq64::midibus, 160
open_performance_edit	seq64::perform, 204
seq64::mainwnd, 144	seq64::sequence, 273
open_performance_edit_2	
seq64::mainwnd, 144	seq64::triggers, 289
operator<	play_note_off
seq64::event, 60	seq64::sequence, 282
seq64::event_list::event_key, 66	play_note_on
operator=	seq64::sequence, 282
seq64::click, 40	pop_redo
seq64::editable_events, 53	seq64::sequence, 269
	pop_undo
seq64::event, 60	seq64::sequence, 269
seq64::event_list, 69	popup_event_menu
seq64::keystroke, 125	seq64::seqedit, 240
seq64::triggers, 289	popup_menu
output	seq64::seqmenu, 253
seq64::jack_assistant, 111	popup_midibus_menu
output_func	seq64::seqedit, 240
seq64::perform, 205	popup_sequence_menu
page movement	seq64::seqedit, 240
seq64::eventslots, 88	popup_tool_menu
page_topper	seq64::seqedit, 241
seq64::eventslots, 88	position
parse	seq64::jack_assistant, 110
seq64::midifile, 164	seq64::midi_container, 148
seq64::optionsfile, 177	position jack
seq64::userfile, 314	seq64::perform, 202
parse_prop_header	pow2
seq64::midifile, 166	seq64::midifile, 168
parse_proprietary_track	ppqn
	seq64::mainwnd, 143
seq64::midifile, 167	seq64::midi_splitter, 153
parse_smf_0	seq64::midifile, 166
seq64::midifile, 166	·
parse_smf_1	print
seq64::midifile, 166	seq64::sequence, 273
partial_assign	print_triggers
seq64::sequence, 269	seq64::sequence, 273
paste	private_bus
seq64::triggers, 291	seq64::user_settings, 308
paste_selected	private_instrument
seq64::sequence, 279	seq64::user_settings, 308
paste_trigger	process_events
seq64::sequence, 277	seq64::lash, 127
perf_h_page_increment	prop_item_size

seq64::midifile, 171	seq64::triggers, 291
push_trigger_undo	select_action_e
seq64::perform, 198	seq64::sequence, 269
seq64::sequence, 269	select_all
push_undo	seq64::sequence, 278
seq64::sequence, 269	select_event
put	seq64::eventslots, 86
seq64::midi_container, 147	select_events
seq64::midi_list, 150	seq64::sequence, 278
seq64::midi_vector, 157	select_group_mute
put_event_on_bus	seq64::perform, 201
seq64::sequence, 283	select_mute_group
wasal buda away	seq64::perform, 201
read_byte_array	select_note_events
seq64::midifile, 168	seq64::sequence, 278
read_long	select_trigger
seq64::midifile, 168	seq64::sequence, 274
read_seq_number	selected_trigger_end
seq64::midifile, 169	seq64::sequence, 277
read_track_name	selected_trigger_start
seq64::midifile, 169	seq64::sequence, 277
read_varinum	seq64::AbstractPerfInput, 37
seq64::midifile, 168 redraw	seq64::Seq24PerfInput, 226
	handle_motion_key, 227
seq64::mainwid, 134 remove	on_button_press_event, 227
seq64::event_list, 69	on_button_release_event, 227
seq64::sequence, 284	on_motion_notify_event, 227
seq64::triggers, 291	set_adding, 227
remove_all	seq64::Seq24SeqEventInput, 229
seq64::sequence, 284	on_button_press_event, 229
remove_marked	on_button_release_event, 229
seq64::sequence, 281	on_motion_notify_event, 229
render_string	set_adding, 229
seq64::gui_drawingarea_gtk2, 101	seq64::Seq24SeqRollInput, 230
render_string_on_drawable	on_button_press_event, 230
seq64::font, 92	on_button_release_event, 230
render_string_on_pixmap	set_adding, 230
seq64::gui drawingarea gtk2, 101	seq64::automutex, 37
reset	seq64::click, 38
seq64::seqdata, 233	click, 39
seq64::seqroll, 258	m_button, 40
reset_draw_marker	m_modifier, 40
seq64::sequence, 282	m_x, 40
reset draw trigger marker	m_y, <mark>40</mark>
seq64::sequence, 282	operator=, 40
reset sequences	seq64::condition_var, 40
seq64::perform, 203	cond, 42
restart	seq64::configfile, 42
seq64::jack_assistant, 110	configfile, 43
, , _ ,	line_after, 43
save_events	m_line, 43
seq64::editable_events, 54	next_data_line, 43
seq64::eventslots, 86	seq64::editable_event, 43
save_file	analyze, 50
seq64::mainwnd, 144	category, 49
save_playing_state	category_channel_message, 47
seq64::perform, 205	category_meta_event, 47
select	category_name, 47

category_prop_event, 47	set_channel, 64
category_system_message, 47	set_data, 64
category_t, 47	set_status, 63, 64
editable_event, 48	seq64::event_list, 67
format_timestamp, 50	add, 69
m_category, 51	any_selected_notes, 71
m_format_timestamp, 51	clear, 70
m_name_meta, 51	count, 69
m_name_status, 51	count_selected_events, 71
m_parent, 51	event_list, 69
name_to_value, 48	link_new, 70
set_status_from_string, 50	m_is_modified, 71
sm_category_arrays, 51	mark_all, 71
sm_category_names, 50	mark_out_of_range, 70
sm_channel_event_names, 50	merge, 70
sm_meta_event_names, 51	operator=, 69
sm_prop_event_names, 51	remove, 69
sm_system_event_names, 51	unmodify, 69
stock_event_string, 50	verify_and_link, 70
time_as_measures, 49	seq64::event_list::event_key, 65
time_as_minutes, 49	event_key, 66
timestamp, 49	m_rank, <mark>66</mark>
timestamp_format_t, 47	m_timestamp, 66
timestamp_measures, 47	operator<, 66
timestamp_pulses, 48	seq64::eventedit, 71
timestamp_time, 48	\sim eventedit, 75
value_to_name, 48	enqueue_draw, 75
seq64::editable_events, 52	eventedit, 74
add, 54	handle_insert, 78
count, 54	handle_modify, 78
editable_events, 53	handle_save, 78
Key, 53	m_redraw_ms, 79
load_events, 54	on_delete_event, 78
m_current_event, 55	on_key_press_event, 78
m_midi_parameters, 55	set_dirty, 76
m_sequence, 55	set_event_category, 76
operator=, 53	set_event_data_0, 76
save_events, 54	set_event_data_1, 76
seq64::event, 55	set_event_name, 76
\sim event, 60	set_event_timestamp, 76
append_sysex, 64	set_seq_count, 76
check_channel, 61	set_seq_ppqn, 75
event, 60	set_seq_time_sig, 75
get_data, 64	set_seq_title, 75
get_rank, 65	timeout, 78
is_channel_msg, 61	v_adjustment, 76, 78
is_desired_cc_or_not_cc, 63	seq64::eventslots, 79
is_note_msg, 61	change_vert, 88
is_one_byte_msg, 61	convert_y, 87
is_two_byte_msg, 61	decrement_bottom, 89
m_channel, 65	decrement_current, 89
m_data, 65	decrement_top, 88
m_has_link, 65	delete_current_event, 85
m_status, 65	draw_event, 87
m_sysex, 65	draw_events, 87
mod_timestamp, 63	increment_bottom, 89
operator<, 60	increment current, 89
operator=, 60	increment_top, 88
	= 17

	insert_event, 84	m_pixmap, 104
	load_events, 84	m_window, 104
	m_char_w, 90	m_window_x, 104
	m_current_index, 90	on_realize, 104
	m_setbox_w, 90	render_string, 101
	m_slots_chars, 90	render_string_on_pixmap, 101
	m_slots_y, 90	set_line, 99
	m_top_index, 90	seq64::gui_drawingarea_gtk2::rect, 226
	m_xy_offset, 90	seq64::gui_palette_gtk2, 104
	modify_current_event, 86	gui_palette_gtk2, 105
	on_expose_event, 89	seq64::gui_window_gtk2, 105
	on_focus_in_event, 89	gui_window_gtk2, 107
	on_move_down, 90	m_window_x, 108
	on_move_up, 89	seq64::jack_assistant, 108
	on_realize, 89	~jack_assistant, 109
	on_size_allocate, 89	client_open, 112
	page movement, 88	error_message, 112
	page_topper, 88	get_jack_ticks, 112
	save events, 86	info_message, 112
	select_event, 86	init, 110
	set_current_event, 84	jack_assistant, 109
	set_text, 87	jack_shutdown_callback, 114
	64::font, 90	jack_timebase_callback, 115
	BLACK, 92	output, 111
	BLACK ON CYAN, 92	position, 110
	BLACK ON YELLOW, 92	restart, 110
	CYAN_ON_BLACK, 92	set_position, 113
	Color, 92	show statuses, 113
	init, 92	sm_status_pairs, 115
	m_b_on_c_pixmap, 93	start, 110
	m_b_on_y_pixmap, 93	stop, 110
	m_black_pixmap, 93	sync, 113
	m_c_on_b_pixmap, 93	seq64::jack_scratchpad, 115
	m clip mask, 93	seq64::keybindentry, 116
	m_font_h, 93	events, 116
	m font w, 93	groups, 116
	:	
	m_pixmap, 93 m white pixmap, 93	keybindentry, 117 location, 116
		m key, 117
	m_y_on_b_pixmap, 93	— *·
	render_string_on_drawable, 92	on_key_press_event, 117
	WHITE, 92	set, 117
	YELLOW_ON_BLACK, 92	type, 116
	4::gui_assistant, 94	seq64::keys_perform, 117
	gui_assistant, 95	~keys_perform, 119
•	64::gui_assistant_gtk2, 95	get_keys, 120
	lash_timeout_connect, 96	key_name, 120
	sm_internal_keys, 96	m_key_bpm_up, 121
•	4::gui_drawingarea_gtk2, 96	m_key_show_ui_sequence_number, 121
	clear_window, 99	set_all_key_events, 120
	draw_line, 99–101	set_all_key_groups, 120
	draw_line_on_pixmap, 99, 100	set_key_event, 120
	draw_normal_rectangle_on_pixmap, 103	set_key_group, 121
	draw_rectangle, 101–103	set_keys, 119
	draw_rectangle_on_pixmap, 103	show_ui_sequence_key, 120
	m_background, 104	show_ui_sequence_number, 120
	m_drop_x, 104	seq64::keys_perform_gtk2, 121
	m_foreground, 104	\sim keys_perform_gtk2, 123
	m_mainperf, 104	key_name, 123

set_all_key_events, 123	m_main_wid, 145
set_all_key_groups, 123	m_ppqn, 145
seq64::keys_perform_transfer, 123	m_sigpipe, 145
seq64::keystroke, 123	m_spinbutton_load_offset, 145
is_letter, 125	mainwnd, 142
keystroke, 124, 125	new_file, 144
m_is_press, 125	on_delete_event, 144
m_key, 125	on_grouplearnchange, 145
m_modifier, 125	on_key_press_event, 145
operator=, 125	on_key_release_event, 145
seq64::lash, 126	open_file, 142
handle_config, 127	open_performance_edit, 144
handle_event, 127	open_performance_edit_2, 144
init, 127	ppqn, 143
lash, 126	save_file, 144
process_events, 127	signal_action, 144
set_alsa_client_id, 127	start_playing, 144
seq64::maintime, 127	stop_playing, 144
idle_progress, 130	timer_callback, 143
m_bar_width, 131	update_window_title, 144
m_beat_width, 131	seq64::midi_container, 145
m_box_height, 131	add_long, 148
m_box_width, 131	add_variable, 148
m_flash_height, 131	fill, 147
m_flash_width, 131	get, 147
m_ppqn, 131	position, 148
m_tick, 131	put, 147
maintime, 129	seq64::midi_list, 148
on_expose_event, 131	CharList, 150
on_realize, 131	get, 150
seq64::mainwid, 132	put, 150
calculate_base_sizes, 136	seq64::midi_measures, 150
draw_marker_on_sequence, 134	m_divisions, 151
draw_sequence_on_pixmap, 135	seq64::midi_splitter, 151
draw_sequence_pixmap_on_window, 135	increment, 153
draw_sequences_on_pixmap, 135	m_smf0_channels, 154
m_screenset_offset, 138	m_smf0_channels_count, 154
m_screenset_slots, 138	m_smf0_seq_number, 154
mainwid, 134	midi_splitter, 152
on_button_press_event, 136	ppqn, 153
on_button_release_event, 137	split, 153
on_expose_event, 136	split_channel, 153
on_focus_in_event, 137	seq64::midi_timing, 154
on_focus_out_event, 137	m_beat_width, 155
on_motion_notify_event, 137	m_beats_per_measure, 155
on_realize, 136	m_beats_per_minute, 155
redraw, 134	m_ppqn, 155
seq_from_xy, 136	seq64::midi_vector, 155
set_screenset, 134	get, 157
timeout, 136	put, 157
update_markers, 135	seq64::midibus, 157
valid_sequence, 135	clock, 160
seq64::mainwnd, 138	continue_from, 160
about_dialog, 143	deinit_in, 159
adj_callback_bpm, 143	init_clock, 160
adj_callback_ss, 143	init_in, 159
edit_callback_notepad, 143	init_in_sub, 159
file_import_dialog, 143	init_out, 159

init out sub, 159 play, 160 set_input, 160 set_inpu		
set_input, 160 sysex, 160 seq64::midfile, 160 erdump, 171 is_sysex_special_id, 171 m_char_list, 173 m_data, 173 m_data, 173 m_error_is_fatal, 173 m_error_is_fatal, 173 m_error_is_fatal, 173 m_new_format, 173 m_new_format, 173 m_new_format, 173 m_sml0_splitter, 173 midfile, 163 parse_t04 parse_prop_feader, 166 parse_prop_feader, 166 parse_prop_feader, 166 parse_sml_0, 166 parse_sml_0, 166 parse_sml_1, 166 parse_sml_0, 166 parse_proprietary_track, 167 parse_sml_0, 168 pow2, 168 pow0, 168 pow0, 168 read_long, 168 read_long, 168 read_soq_number, 169 read_varinum, 168 varinum_size, 171 write_short, 168 write_prop_header, 169 write_prop_head		• •
sysex, 160 seq64:midifile, 160 errdump, 171 is sysex special id, 171 m_char_list, 173 m_disable_reported, 173 m_disable_reported, 173 m_error_message, 173 m_merror_message, 173 m_mos, 173 m_mos, 173 m_mos, 173 m_mos, 173 m_mos, 173 m_sidifile, 163 parse, 164 parse_prop_header, 173 midifile, 163 parse, 166 parse_prop_header, 166 parse_prop_header, 166 parse_prop_leader, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_prop_lems_size, 171 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_varinum, 168 varinum, size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_prop_header, 169 write_spot_ntiles write_long, 168 write_prop_header, 169 write_spot_ntiles write_track_name, 169 write_spot_ntiles write_track_name, 169 w	• •	• —
seq64:midfile, 160 errdump, 171 is_sysex_special_id, 171 m_char_list, 173 m_data_l, 173 m_disable_reported, 173 m_error_is_fatal, 173 m_error_message, 173 m_lile_size, 173 m_new_format, 173 m_pos, 173 m_sm0_splitte, 173 m_sm0_splitte, 173 m_sm10_splitte, 173 m_sm10_splitte, 173 m_smidfile, 163 parse_prop_header, 166 parse_prop_leader, 166 parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 prop_litem_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 read_track_name, 169 read_track_name, 169 read_track_name, 169 write_sport, 168 write_prop_header, 169 write_warnum, 168 seq64::metcy, 174 sm_recursive_mutex, 175 e_jack_connect, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 parse, 177 write, 179 seq64::perfedit, 179 v-perfedit, 182 m_bw, 184 m_pw, 184 m_pw, 184 m_perfedit, 182 set_beat_with, 183 set_beat_wi	_ ·	
errdump, 171 is_sysex_special_id, 171 m_char_list, 173 m_data, 173 m_data, 173 m_data, 173 m_error_message, 173 m_new_format, 173 m_sml(s) spiter, 173 midiffile, 163 parse, 164 parse_prop_header, 166 parse_prop_leader, 166 parse_prop_leader, 166 parse_sml(), 166 pow2, 168 popn, 166 prop, ilem_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_long, 168 read_seq_number, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_prop_header, 169 write_yrop_header, 169 write_yrop_header, 169 write_yrop_header, 169 write_prop_header, 169 write_prop_header, 169 write_yrop_header, 169 write_prop_header, 169 read_varinum, 168 seq64::mutex, 174 set_beats_per_lar, 183 set_beats_per_lar, 183 set_beats_per_lar, 183 set_beats_per_lear, 183 set_beats_per	•	•
is_sysex_special_id, 171 m_char_list, 173 m_char_list, 173 m_disable_reported, 173 m_disable_reported, 173 m_error_is_fatal, 173 m_error_message, 173 m_lile_size, 173 m_new_format, 173 m_sml_osplitter, 173 m_sml_osplitt	•	_
m_char_list, 173 m_dida, 173 m_disable_reported, 173 m_error_is_fatal, 173 m_error_is_fatal, 173 m_error_message, 173 m_new_format, 173 m_new_format, 173 m_new_format, 173 m_new_format, 173 m_smf0_splitter, 173 midfile, 163 parse, 164 parse_prop_header, 166 parse_prop_header, 166 parse_smf_1, 166 parse_smf_1, 166 pow2, 168 popu, 166 prop_litem_size, 171 red_byte_array, 168 read_long, 168 read_seq_number, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_long, 168 write_prop_header, 169 write_prop_intersy_track, 170 write_seq_number, 169 write_prop_intersy_track, 170 write_seq_number, 169 write_prop_intersy_track, 170 write_seq_number, 169 write_prop_intersy_track, 170 e_jack_connect, 176 e_jack_start_mode_live, 176 e_jack_connect, 177 write, 179 write, 179 write, 179 seq64::perfedit, 182 set_beat_with, 183 set_pat_with, 183 set_beat_with, 183 set_beat_with, 183 set_beat_withe, 184 timeout, 18	•	
m_data, 173 m_disable_reported, 173 m_error_is_fatal, 173 m_error_message, 173 m_file_size, 173 m_new_format, 173 m_pos, 173 m_sm0_splitter, 173 m_smf0_splitter, 173 m_smf0_splitter, 173 m_indifile, 163 parse, 164 parse_prop_header, 166 parse_proprietary_track, 167 parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_propmietary_track, 167 parse_smf_1, 166 parse_prop_meader, 168 prop_item_size, 171 read_byte_array, 168 read_sq_number, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write_byte, 168 write_byte, 168 write_borp_teader, 169 write_prop_header, 169 write_prop_header, 169 write_soc_number, 169 write_prop_header, 169 write_soc_number, 169 write_track_name, 169 n_track_trace_track_name, 169 clear_sequen		— ·
m_disable_reported, 173 m_error_is_fatal, 173 m_error_message, 173 m_file_size, 173 m_file_size, 173 m_new_format, 173 m_sml0_splitter, 173 m_sml0_splitter, 173 midifile, 163 parse_164 parse_prop_header, 166 parse_sml_0, 166 parse_sml_0, 166 parse_sml_1, 166 parse_sml_1, 166 pow2, 168 popq, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_prop_header, 169 write_prop_header, 169 write_short, 168 write_prop_header, 169 write_stort, 168 write_long, 168 write_prop_header, 169 write_stort, 168 write_prop_header, 169 write_stort, 168 seq64::mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_176 e_jack_master_176 e_jack_master_food_ir76 e_jack_transport, 176 m_notebook, 176 seq64::options, 177 write, 179 seq64:perfedit, 179 write, 179 seq64:perfedit, 179 seq64:perfedit, 179 seq64:perfedit, 179 seq64:perfedit, 179 seq64:perfedit, 182 set_beat_width, 183 set_beats_width, 183 set_beats_width, 183 set_beats_width, 183 set_beats_width, 183 set_beats_width, 183 set_beats_width, 183 set_peats_via, 209 set_ar_playing, 184 timoud, 183 undo, 183 undo, 183 undo, 183 undo, 183 undo, 183 set_peats_playing, 184 timoud, 183 undo, 183 undo, 183 undo, 183 undo, 183 set_peats_playing, 184 timoud, 183 undo, 183 undo, 183 set_peats_playing, 184 timoud, 183 undo, 183 undo, 183 set_peats_playing, 184 timoud, 183 undo, 183 undo, 183 undo, 183 set_peats_playing, 184 timoud, 183 undo, 183 set_peats_playing, 184 timoud, 183 undo, 183 set_pelex_ined, 189 timoud, 183 undo, 183 undo, 183 tim_peat_playing, 1		<i>= '</i>
m_error_is_fatal, 173 m_error_message, 173 m_file_size, 173 m_new_format, 173 m_mow_format, 173 set_beat_width, 183 set_guides, 183 set_guides, 183 start_playing, 184 stop_playing, 184		
m_error_message, 173 m_file_size, 173 m_new_format, 173 m_pos, 173 m_smfl0_splitter, 173 m_smfl0_splitter, 173 m_smfl0_splitter, 173 m_smfl0_splitter, 173 m_smfl0_splitter, 173 m_smfl0_splitter, 173 midfile, 163 parse, 164 parse_prop_header, 166 parse_proprietary_track, 167 parse_smf_0, 166 parse_smf_1, 166 pov2_168 pov2_168 pop0_168 pop0_168 pop0_lem_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_seq_number, 169 read_track_name, 169 read_track_name, 169 read_track_name, 169 write_brop_header, 168 write_prop_header, 169 write_prop_header, 169 write_sphort, 168 write_prop_header, 169 write_short, 168 write_track_name, 169 read_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 read_track_name, 1	·	•
m_file_size, 173 m_new_format, 173 m_new_format, 173 m_stop_playing, 184 m_smf0_splitter, 173 midfile, 163 parse, 164 parse_prop_header, 166 parse_prop_header, 166 parse_prop_feater_track, 167 parse_smf_0, 166 pow2, 168 pow2, 168 pop, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_seq_number, 169 write_seq_number, 169 write_seq_number, 169 write_seq_number, 169 write_short, 168 write_prop_header, 169 write_short, 168 write_long, 168 write_rop_header, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_varinum, 168 seq64::perform, 185 seq64::perform, 195 button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_master_track e_jack_start_mode_live, 176 e_jack_transport, 176 m_notebook, 176 seq64::perfortin, 179 model track_parse, 177 write, 179 seq64::perfortin, 199 is_active, 203 is_dirty_main, 202 is_dirty_main, 203	:	
m_new_format, 173 m_pos, 173 m_smid_splitter, 173 midifile, 163 parse, 164 parse_prop_header, 166 parse_prop_leader, 166 parse_prop_leader, 166 parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 pow2, 168 pow2, 168 popq, 168 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_varinum, 168 varinum_size, 171 write, 164 write_prop_header, 169 write_short, 168 write_tack_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 cep64::mptrons, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 m_notebook, 176 seq64::pperfodit, 179 cepeffedit, 179 cepeffedit, 179 cepeffedit, 179 sep64::perfedit, 179 se_dfirty_mames, 203 start_playing, 184 stop_playing, 184 seq64::perframes, 187 eracquence, 187 enqueue_draw, 187 enqueue_d	-	. _
m_pos, 173 m_smf0_splitter, 173 m_smf0_splitter, 173 midfile, 163 parse, 164 parse prop_header, 166 parse_proprietary_track, 167 parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 pow2, 168 ppop, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_varinum, 168 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_prop_header, 169 write_sed_number, 169 clear_sequence_triggers, 197 copy_triggers, 198 decrement_beats_per_minute, 206 deinit_jack, 208 delete_sequence, 197 finish, 198 set_one, 203 handle_mid_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start_cop parse, 177 write, 179 seq64::perfodit, 179 is_active, 203 is_dirty_names, 203		
m_smf0_splitter, 173 midfile, 163 parse, 164 parse_prop_header, 166 parse_prop_header, 166 parse_prop_header, 166 parse_prop_header, 166 parse_smf_0, 166 parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 pow2, 168 pow2, 168 popq, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_varinum, 168 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_prop_header, 169 write_propietary_track, 170 write_seq_number, 169 write_track_name, 169 write_varinum, 168 write_track_name, 169 write_propietary_track, 170 write_seq_number, 169 write_track_name, 169 write_track_name, 169 write_track_name, 169 write_track_name, 169 write_prop_header, 169 write_propietary_track, 170 write_seq_number, 169 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 seq64::mutex, 176 e_jack_disconnect, 176 e_jack_disconnect, 176 e_jack_disconnect, 176 e_jack_transport, 176 e_		_ · · ·
midfile, 163 parse, 164 parse, 164 parse prop header, 166 parse proprietary_track, 167 parse_smf_0, 166 parse_smf_0, 166 parse_smf_1, 166 parse_smf_0, 168 read_long, 168 varioum_size, 171 write, 164 write_byte, 168 write_long, 168 write_pop_leader, 169 write_prop_leader, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_track_name, 169 write_short, 168 write_varinum, 168 seq64::mutex, 174 seq64::mutex, 174 seq64::mutex, 175 seq64::mutex, 176 e_jack_master_cond, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::moterous, 176 parse, 177 write, 179 seq64::moterous, 187 names_setars, 187 m_names_y, 188 m_names_y, 188 m_names_chars, 187 m_names_y, 188 m_parent, 187 m_nates_y, 188 m_parent, 187 m_setbox_w, 188 m_names_chars, 187 m_nates_v, 187 m_nates_v, 188 m_setox_w, 188 m_parent, 187 m_setox_w, 188 m_parent, 187 verfermames, 189	_ ·	
parse, 164 parse prop header, 166 parse proprietary_track, 167 parse_smf_0, 166 parse_smf_1, 166 pow2, 168 ppqn, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_prop_header, 169 write_proprietary_track, 170 write_seq_number, 169 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 read-seq_number, 169 derad_sequence, 197 inish, 198 get_group_mute_state, 205 get_max_trigger, 198 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 init_jack, 208 is_ditty_main, 202 is_ditty_mains, 203	·	
parse_prop_header, 166 parse_proprietary_track, 167 parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 parse_smf_1, 166 pow2, 168 ppqn, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_seq_number, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_long, 168 write_prop_header, 169 write_prop_header, 169 write_prop_header, 169 write_short, 168 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_start_mode_live, 176 e_jack_start_mode_live, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::operfedit, 179 ~perfedit, 182 draw_sequence, 187 m_nendebox, u, 188 mn_char_w, 187 m_namebox, w, 188 m_names_charx, 187 m_namebox, w, 188 m_names_charx, usl m_namebox, usla m_namebox, w, 188 m_names_charx, usla m_namebox, usla m_namebox, usla m_namebox, usla m_namebox, usla m_namebox, usla m_namebox, usla m_names_charx, 187 m_namebox, usla m_names_charx, 187 m_names_coa, usla dra_mame_charx, 187 m_names_charx, 188 m_names_charx, 187 m_names_charx, 187 m_names_charx, 187 m_names_charx, 187 m_names_charx m_names_charx m_names_charx m_names		
parse_proprietary_track, 167 parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 pow2, 168 ppqn, 166 pow2, 168 ppqn, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_prop_header, 169 write_prop_header, 169 write_short, 168 write_short, 168 write_short, 168 write_strack_name, 169 write_short, 168 write_strack_name, 169 prite_strack_name, 187 prite_strack_nam	• •	·
parse_smf_0, 166 parse_smf_1, 166 parse_smf_1, 166 pow2, 168 popq, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_varinum, 168 varinum_size, 171 write, 164 write_ptop-leader, 169 write_prop-leader, 169 write_prop-leader, 169 write_short, 168 write_short, 168 write_varinum, 168 seq64::mutex, 174 seq64::petrons, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_pack4::perfedit, 179 verperfedit, 179 verperfedit, 182 m_namesox_w, 188 m_names_y, 188 m_names_y, 188 m_names_y, 188 m_parent, 187 m_setbox_w, 188 m_xy_offset, 188 on_expose_event, 187 on_size_allocate, 187 on_realize, 18		<u> </u>
parse_smf_1, 166 pow2, 168 popq, 168 popq, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_varinum, 168 varinum_size, 171 write_long, 168 write_prop_header, 169 write_short, 168 write_short, 168 write_varinum, 168 write_varinum, 168 seq64::mutex, 174 seq64::mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 e_parse, 177 write, 179 seq64::optionsfile, 176 parse, 177 write, 179 seq64::optionsfile, 179 ~perfedit, 182 m_names_vars, 187 m_names_v, 188 m_names_vars, 187 m_names_v, 188 m_names_vars, 187 m_names_v, 188 m_names_vars, 187 m_setbox_w, 188 m_xy_offset, 188 m_xy_offset, 188 m_aparent, 187 m_setbox_w, 188 m_aparent, 187 m_setbox_w, 188 m_xy_offset, 188 m_aparent, 187 m_setbox_w, 188 m_xy_offset, 188 m_aparent, 187 m_setbox_w, 188 m_aparent, 187 m_setbox_w, 188 m_xy_offset, 188 m_aparent, 187 m_setbox_w, 188 m_xy_offset, 188 n_aparent, 187 m_setbox_w, 188 m_xy_offset, 188 n_aparent, 187 m_setbox_w, 188 m_xy_offset, 188 n_xy_offset, 188 n_aparent, 187 m_setbox_w, 188 m_xy_offset, 188 n_aparent, 187 m_setbox_w, 188 n_xy_offset, 188 n_ead_sequent, 187 n_seq6::perform, 188 ~perform, 188 ~perform, 188 ~perform, 195 on_expose_event,		• —
ppw2, 168 ppqn, 166 prop_item_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_long, 168 read_seq_number, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_pop_header, 169 write_proprietary_track, 170 write_seq_number, 169 write_track_name, 169 write_varinum, 168 write_varinum, 168 write_varinum, 168 write_varinum, 168 write_varinum, 169 mrite_varinum, 168 seq64::mutex, 174 seq64::potions, 175 button, 175 e_jack_connect, 176 e_jack_master, 176 e_jack_master, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 m_notebook, 176 seq64::potionsfile, 176 parse, 177 write, 179 seq64::potionsfile, 176 parse, 177 write, 179 seq64::potionsfile, 179 ~perfedit, 182 m_names_y, 188 m_names_y, 188 m_names_y, 188 m_parent, 187 m_parent, 188 m_parent, 187 m_parent, 188 m_parent, 187 m_parent, 188 m_parent, 187 m_parent, 187 m_parent, 187 m_parent, 187 m_parent, 187 m_parent, 188 m_parent, 187 m_parent, 187 m_parent, 187 m_parent, 188 m_parent, 187 m_parent, 187 m_parent, 287 m_parent, 188 m_parent, 187 m_parent, 188 m_parent, 187 m_parent, 188 m_parent, 187 m_parent, 187 m_parent, 187 m_parent, 188 m_parent, 18	. – –	
ppqn, 166 prop_item_size, 171 read_byte_array, 168 read_byte_array, 168 read_long, 168 read_seq_number, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_byte, 168 write_prop_header, 169 write_proprietary_track, 170 write_seq_number, 169 write_short, 168 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 seq64::options, 175 e_jack_connect, 176 e_jack_tart_mode_live, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsflie, 176 parse, 177 write, 179 seq64::optionsflie, 176 parse, 177 write, 179 seq64::optedit, 179 ~perfedit, 179 ~perfedit, 182 m_names_y, 188 m_parent, 187 m_names_y, 188 m_parent, 187 m_parent, 187 m_names_y, 188 m_parent, 187 m_natebox, 188 m_parent, 187 m_natebox, 188 m_parent, 187 m_names_y, 188 m_parent, 187 m_names_y, 188 m_parent, 187 m_names_y, 188 m_parent, 187 m_natebox, 188 m_nsetbox, 188 m_parent, 187 m_natebox, 188 m_nsetbox, 187 all_note_off, 202 clam_track_209 clar_all_note_off, 202 clam_track_209 clar_all_note_off, 202 clam_track_201 clam_track_209 clar_all_note_off, 202 clam_track_209 clar_all_note_off, 202 clam_track_209 clar_all_note_off, 202 clam_track_203 clam_track_203 clam_track_203 clam_track_203 clam_track_203 clam_track_204 clam_track_205 clam_track_206 clam_track_206 clam_track_207 clam_track_207 clam_track_209 clam_track_209 clam_track_209 clam_track_209 clam_track_209 clam_track_209 clam_track_201 clam_track_201 clam_track_201 clam_track_201 clam_track_201 clam_track_201 clam_track_201 clam_track_201 clam_track_209 clam_t	. – – :	
prop_item_size, 171 read_byte_array, 168 read_long, 168 read_long, 168 read_seq_number, 169 read_track_name, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_long, 168 write_prop_header, 169 write_short, 168 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::options file, 176 parse, 177 write, 193 write_squames, 169 m_specific and solution of the properties of the proper	·	
read_byte_array, 168 read_long, 168 read_seq_number, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_long, 168 write_prop_header, 169 write_seq_number, 169 write_seq_number, 169 write_starinum, 168 write_short, 168 write_warinum, 168 ceq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 m_notebook, 176 m_notebook, 176 m_notebook, 176 parse, 177 write, 179 seq64::perfedit, 179 sis_dirty_names, 203 m_xy_offset, 188 n_xy_offset, 188 n_xy_offset, 188 n_xy_offset, 188 n_xy_offset, 188 n_xy_offset, 188 n_xy_offset, 188 n_eads n_exp_cfet, 187 on_expose_event, 187 perfamms, 187 seq64::perform, 188 ~perform, 188 ~perform, 195 add_sequence, 197 all_notes_off, 202 clamp_track, 209 clear_all, 195 clear_sequence_triggers, 197 copy_triggers, 198 decrement_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 is_active, 203 is_dirty_edit, 202 is_dirty_names, 203	• • •	
read_long, 168 read_seq_number, 169 read_track_name, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_long, 168 write_long, 168 write_short, 168 write_short, 168 write_track_name, 169 write_varinum, 168 clear_sequence_triggers, 197 copy_triggers, 198 write_varinum, 168 seq64::mutex, 175 seq64::options, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 m_notebook, 176 seq64::optionsfile, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::optionsfile, 179 ~perfedit, 179 seq64::perfedit, 179 on_exipte, 188 on_expose_event, 187 on_expose_expose_event, 187 on_expose_expose_event, 187 on_expose		— -
read_seq_number, 169 read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_long, 168 write_prop_header, 169 write_short, 168 write_track_name, 169 write_start_mode_live, 176 e_jack_start_mode_love, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 e_jack_start_mode_song, 176 m_notebook, 176 seq64::options file, 176 parse, 177 write, 179 seq64::optionsfile, 179 perfedit, 182		
read_track_name, 169 read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_long, 168 write_prop_header, 169 write_seq_number, 169 write_seq_number, 169 write_track_name, 169 write_tvarinum, 168 seq64::mutex, 174 seq64::mutex, 175 seq64::options, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 sis_dirty_names, 203	_ -	— •—
read_varinum, 168 varinum_size, 171 write, 164 write_byte, 168 write_byte, 168 write_long, 168 write_prop_header, 169 write_prop_header, 169 write_seq_number, 169 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 seq64::mutex, 174 seq64::mutex, 175 sed64::options, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::perfedit, 179 sis_dirty_names, 203		_ · _
varinum_size, 171 write, 164 write, 168 write_byte, 168 write_long, 168 write_long, 168 write_prop_header, 169 write_propheader, 169 write_seq_number, 169 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::metex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_note_off, 202 clamp_track, 209 clamp_track, 209 clamp_track, 209 clamp_track, 209 clamp_track, 209 clear_all, 195 clear_sequence_triggers, 197 copy_triggers, 198 decrement_beats_per_minute, 206 deinit_jack, 208 delete_sequence, 197 finish, 198 get_group_mute_state, 205 get_group_mute_state, 205 get_group_mute_state, 205 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 is_active, 203 is_dirty_edit, 202 seq64::perfedit, 179 is_dirty_edit, 202 is_dirty_names, 203		
write, 164 write_byte, 168 write_long, 168 write_long, 168 write_prop_header, 169 write_proprietary_track, 170 write_seq_number, 169 write_short, 168 ceq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 e_jack_tra		
write_byte, 168 write_long, 168 write_long, 168 write_long, 168 write_prop_header, 169 write_prop_header, 169 write_proprietary_track, 170 write_seq_number, 169 write_short, 168 write_short, 168 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 179 seq64::perfedit, 179 seq64::perfedit, 179 seq64::perfedit, 182 **perform, 195 add_sequence, 197 add_sequence, 197 clamp_track, 208 clear_set_unce_triggers, 197 clear_all, 195 clear_all, 195 clear_all, 195 clear_sequence_triggers, 197 clear_sequence_triggers, 197 derivate, 208 deter_sequence, 197 finish, 198 deter_sequence, 197 finish, 198 get_group_mute_state, 205 get_max_trigger, 198 get_screen_set_notepad, 199 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 install_sequence, 209 seq64::perfedit, 179 is_dirty_edit, 202 is_dirty_main, 202 is_dirty_names, 203		•
write_long, 168 write_prop_header, 169 write_proprietary_track, 170 write_proprietary_track, 170 write_seq_number, 169 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::optionsfile, 176 parse, 177 write, 179 seq64::optionsfile, 179 write_long, 168 add_sequence, 197 all_notes_off, 202 clamp_track, 209 clear_all, 195 clear_sequence_triggers, 197 clear_sequence_triggers, 198 decrement_beats_per_minute, 206 deinit_jack, 208 delete_sequence, 197 finish, 198 get_group_mute_state, 205 get_max_trigger, 198 get_screen_set_notepad, 199 get_screen_set_notepad, 199 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 seq64::optionsfile, 176 install_sequence, 209 seq64::perfedit, 179 is_active, 203 is_dirty_edit, 202 is_dirty_names, 203		• •
write_prop_header, 169 write_proprietary_track, 170 write_seq_number, 169 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::optionsfile, 179 write_proprietary_track, 170 clamp_track, 209 clear_all, 195 clear_sequence_triggers, 197 clear_sequence_triggers, 198 decrement_beats_per_minute, 206 deinit_jack, 208 delete_sequence, 197 finish, 198 get_group_mute_state, 205 get_max_trigger, 198 get_screen_set_notepad, 199 get_screen_set_notepad, 199 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 seq64::optionsfile, 176 install_sequence, 209 seq64::perfedit, 179 is_active, 203 write, 179 seq64::perfedit, 179 is_dirty_main, 202 is_dirty_names, 203	_ ·	•
write_proprietary_track, 170 write_seq_number, 169 write_short, 168 write_short, 168 clear_sequence_triggers, 197 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 m_notebook, 176 m_notebook, 176 parse, 177 write_track, 209 clear_all, 195 clear_sequence_triggers, 197 copy_triggers, 198 decrement_beats_per_minute, 206 deinit_jack, 208 delete_sequence, 197 finish, 198 get_group_mute_state, 205 get_max_trigger, 198 get_screen_set_notepad, 199 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 seq64::optionsfile, 176 install_sequence, 209 is_active, 203 write, 179 is_active, 203 is_dirty_edit, 202 is_dirty_names, 203	_ ·	_ ·
write_seq_number, 169 write_short, 168 write_short, 168 write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 button, 175 e_jack_connect, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 m_notebook, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write_track_name, 169 clear_sequence_triggers, 197 copy_triggers, 198 decrement_beats_per_minute, 206 deinit_jack, 208 delete_sequence, 197 finish, 198 get_group_mute_state, 205 get_max_trigger, 198 get_screen_set_notepad, 199 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 parse, 177 write, 179 seq64::perfedit, 179 is_dirty_edit, 202 is_dirty_main, 202 is_dirty_names, 203		
write_short, 168		
write_track_name, 169 write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 seq64::options, 175 button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_master, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 init_jack, 208 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 179 is_dirty_edit, 202 seq64::perfedit, 182 is_dirty_names, 203	— .	- '
write_varinum, 168 seq64::mutex, 174 sm_recursive_mutex, 175 seq64::options, 175 button, 175 e_jack_connect, 176 e_jack_master, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::optionsfile, 176 seq64::optionsfile, 176 seq64::optionsfile, 179 seq64::optionsfile,		
seq64::mutex, 174 sm_recursive_mutex, 175 seq64::options, 175 button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_master, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 init_jack, 208 get_group_mute_state, 205 get_max_trigger, 198 get_screen_set_notepad, 199 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 seq64::optionsfile, 176 parse, 177 is_active, 203 write, 179 seq64::perfedit, 179 perfedit, 182 is_dirty_main, 202 is_dirty_names, 203		33
sm_recursive_mutex, 175 seq64::options, 175 button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_master, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 182 delete_sequence, 197 finish, 198 get_group_mute_state, 205 get_max_trigger, 198 get_screen_set_notepad, 199 get_sequence, 203 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 is_active, 203 is_active, 203 seq64::optionsfile, 176 parse, 177 is_dirty_edit, 202 is_dirty_names, 203	-	
seq64::options, 175 button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_master, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179	•	
button, 175 e_jack_connect, 176 e_jack_disconnect, 176 e_jack_master, 176 e_jack_master_cond, 176 e_jack_start_mode_live, 176 e_jack_transport, 176 m_notebook, 176 m_notebook, 176 parse, 177 write, 179 seq64::perfedit, 179		_ ·
e_jack_connect, 176 e_jack_disconnect, 176 get_max_trigger, 198 get_screen_set_notepad, 199 e_jack_master, 176 get_sequence, 203 e_jack_master_cond, 176 handle_midi_control, 199 highlight, 206 e_jack_start_mode_live, 176 highlight, 206 increment_beats_per_minute, 206 e_jack_transport, 176 init_jack, 208 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 179 operfedit, 182 is_dirty_names, 203	·	
e_jack_disconnect, 176 e_jack_master, 176 get_sequence, 203 e_jack_master_cond, 176 handle_midi_control, 199 e_jack_start_mode_live, 176 highlight, 206 e_jack_transport, 176 init_jack, 208 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 182 get_screen_set_notepad, 199 get_seqe_notepad, 199 get_seqe_notepad, 199 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 is_active, 203 is_dirty_edit, 202 is_dirty_main, 202 is_dirty_names, 203		
e_jack_master, 176 get_sequence, 203 e_jack_master_cond, 176 handle_midi_control, 199 highlight, 206 e_jack_start_mode_live, 176 highlight, 206 e_jack_transport, 176 increment_beats_per_minute, 206 e_jack_transport, 176 init_jack, 208 m_notebook, 176 inner_start, 209 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 179 seq64::perfedit, 182 is_dirty_names, 203	- -	
e_jack_master_cond, 176 handle_midi_control, 199 e_jack_start_mode_live, 176 highlight, 206 e_jack_start_mode_song, 176 e_jack_transport, 176 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 179 ~perfedit, 182 handle_midi_control, 199 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 is_active, 203 is_dirty_edit, 202 is_dirty_main, 202 is_dirty_names, 203	- -	
e_jack_start_mode_live, 176 highlight, 206 e_jack_start_mode_song, 176 increment_beats_per_minute, 206 e_jack_transport, 176 init_jack, 208 m_notebook, 176 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 179 ~perfedit, 182 highlight, 206 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 is_active, 209 is_active, 203 is_dirty_edit, 202 is_dirty_main, 202 is_dirty_names, 203	_ , _	· - ·
e_jack_start_mode_song, 176 increment_beats_per_minute, 206 e_jack_transport, 176 init_jack, 208 inner_start, 209 seq64::optionsfile, 176 parse, 177 write, 179 seq64::perfedit, 179 seq64::perfedit, 179 ~perfedit, 182 increment_beats_per_minute, 206 init_jack, 208 inner_start, 209 install_sequence, 209 is_active, 203 is_dirty_edit, 202 is_dirty_main, 202 is_dirty_names, 203		
e_jack_transport, 176		
m_notebook, 176 inner_start, 209 seq64::optionsfile, 176 install_sequence, 209 parse, 177 is_active, 203 write, 179 is_dirty_edit, 202 seq64::perfedit, 179 is_dirty_main, 202 ~perfedit, 182 is_dirty_names, 203		. _
seq64::optionsfile, 176 install_sequence, 209 parse, 177 is_active, 203 write, 179 is_dirty_edit, 202 seq64::perfedit, 179 is_dirty_main, 202 ~perfedit, 182 is_dirty_names, 203	-	_
parse, 177 is_active, 203 write, 179 is_dirty_edit, 202 seq64::perfedit, 179 is_dirty_main, 202 ∼perfedit, 182 is_dirty_names, 203		
write, 179 is_dirty_edit, 202 seq64::perfedit, 179 is_dirty_main, 202 ~perfedit, 182 is_dirty_names, 203	·	_ ·
seq64::perfedit, 179 is_dirty_main, 202 ~perfedit, 182 is_dirty_names, 203	•	
~perfedit, 182 is_dirty_names, 203		_ ·
·	• •	_ ·
Collapse, 100 IS_CIRTY_peri, 203	•	_ ·
	Collapse, 100	15_u11 ty_pe11, 203

is_midi_control_valid, 208	show_ui_sequence_key, 206
is_modified, 208	show_ui_sequence_number, 206
is_mseq_valid, 209	sm_mc_dummy, 210
is_screenset_valid, 208	start, 201
is_seq_valid, 208	start_playing, 206
launch, 195	stop, 201
launch_input_thread, 207	unset_mode_group_learn, 201
launch_output_thread, 208	unset_sequence_control_status, 204
m_is_modified, 211	seq64::performcallback, 211
m_left_tick, 210	seq64::perfroll, 212
m_max_sets, 211	\sim perfroll, 215
m one measure, 210	convert_x, 217
m_playback_mode, 210	convert_xy, 217
m_playscreen_offset, 210	draw drawable row, 218
m_right_tick, 210	draw_sequence_on, 218
m_seqs, 210	enqueue_draw, 218
m_seqs_in_set, 211	fill_background_pixmap, 217
m_sequence_count, 211	FruityPerfInput, 219
m sequence max, 211	init before show, 217
m_starting_tick, 211	m fruity interaction, 219
m tick, 211	m_h_page_increment, 219
mainwnd key event, 207	m parent, 219
midi_control_off, 199	m_v_page_increment, 219
midi_control_on, 199	on_button_press_event, 218
midi_control_toggle, 199	on_button_release_event, 219
modify, 195	on_expose_event, 218
move_triggers, 198	on_key_press_event, 219
new_sequence, 197	on_realize, 218
output_func, 205	set_guides, 216
perform, 195	set_ppqn, 217
perfroll_key_event, 207	snap_x, 217
play, 204	start_playing, 218
position_jack, 202	stop_playing, 218
push_trigger_undo, 198	update_sizes, 217
reset_sequences, 203	seq64::perftime, 220
save_playing_state, 205	enqueue_draw, 222
select_group_mute, 201	m_left_marker_tick, 223
select_mute_group, 201	m_measure_length, 223
seq_in_playing_screen, 208	m_parent, 223
sequence_count, 195	m_right_marker_tick, 223
sequence_label, 206	on_expose_event, 222
sequence_playing_off, 204	on_realize, 222
sequence_playing_on, 204	perftime, 222
set_active, 202	set_guides, 222
set_beats_per_minute, 204	seq64::rc_settings, 223
set_group_mute_state, 205	home_config_directory, 225
set_input_bus, 207	seq64::rect, 225
set_key_event, 210	seq64::seqdata, 230
set_key_group, 210	idle_redraw, 233
set_left_tick, 198	m_number_h, 234
set_offset, 205	m_number_offset_y, 234
set_orig_ticks, 204	m_number_w, 234
set_playing_screenset, 201	on_button_press_event, 234
set_right_tick, 198	on button release event, 234
set_ngni_tick, 196 set_screen_set_notepad, 199	on_motion_notify_event, 234
·	· ·
set_screenset, 201	on_realize, 233
set_sequence_control_status, 204	on_scroll_event, 234
set_was_active, 202	reset, 233

seqdata, 233	m_modified, 254
set_data_type, 233	m_seqedit, 254
set_zoom, 233	popup_menu, 253
update_sizes, 233	seq_clear_perf, 254
xy_to_rect, 233	seq_copy, 254
seq64::seqedit, 235	seq_cut, 254
apply_length, 239	seq_edit, 253
create_menus, 240	seq_event_edit, 253
do_action, 241	seq_new, 253
get_measures, 239	seq_paste, 254
m_initial_snap, 241	segmenu, 253
name_change_callback, 240	seq64::seqroll, 254
on_delete_event, 241	convert tn, 258
popup_event_menu, 240	draw_events_on, 258
popup_midibus_menu, 240	draw_events_on_pixmap, 258
popup sequence menu, 240	on_key_press_event, 258
popup_tool_menu, 241	on scroll event, 259
seqedit, 238	reset, 258
set_background_sequence, 239	set_background_sequence, 258
set_data_type, 240	set_data_type, 258
 .	
set_key, 239	snap_x, 258
set_measures, 239	update_background, 258
set_midi_bus, 239	seq64::seqtime, 259
set_midi_channel, 239	on_button_press_event, 261
set_note_length, 238	on_button_release_event, 261
set_scale, 239	seq64::sequence, 261
set_snap, 238	add_event, 273, 279
set_zoom, 238	add_note, 279
seq64::seqevent, 242	add_trigger, 274
convert_t, 245	adjust_trigger_offsets_to_length, 284
convert_x, 245	background_sequence, 283
draw_background, 244	change_event_data_range, 280
draw_events_on, 245	clear_triggers, 278
draw_pixmap_on_window, 244	copy_events, 283
drop_event, 245	copy_selected, 279
idle_redraw, 245	copy_triggers, 277
on_button_press_event, 245	cut_selected, 279
on_button_release_event, 246	decrement_selected, 280
on_key_press_event, 246	del_trigger, 274
on_motion_notify_event, 246	e_deselect, 269
on_realize, 245	e_is_selected, 269
set_data_type, 244	e_remove_one, 269
set_snap, 244	e_select, 269
snap_x, 245	e_select_one, 269
start_paste, 245	e_toggle_selection, 269
update_sizes, 244	e_would_select, 269
x_to_w, 245	event_count, 269
seq64::seqkeys, 246	fill_container, 283
draw_key, 250	get_beat_width, 271
on_button_press_event, 250	get_clipboard_box, 279
on_button_release_event, 250	get_highest_note_event, 282
on_enter_notify_event, 250	get_last_tick, 271
on_leave_notify_event, 250	- ·
	get_lowest_note_event, 282
	-
on_motion_notify_event, 250	get_max_trigger, 277
on_motion_notify_event, 250 on_realize, 250	get_max_trigger, 277 get_name, 271
on_motion_notify_event, 250 on_realize, 250 set_hint_state, 249	get_max_trigger, 277 get_name, 271 get_next_event, 283
on_motion_notify_event, 250 on_realize, 250	get_max_trigger, 277 get_name, 271

get_num_selected_notes, 278	set_beats_per_bar, 269
get_selected_box, 279	set_dirty, 273
get_trigger_state, 274	set_dirty_mp, 273
grow_selected, 281	set_length, 271
grow_trigger, 274	set_master_midi_bus, 278
increment_selected, 280	set_midi_bus, 278
intersect_events, 275	set_midi_channel, 273
intersect_notes, 275	set_orig_tick, 273
intersect_triggers, 275	set_playing, 271
is_dirty_edit, 272	set_quantized_rec, 272
is_dirty_main, 272	set_rec_vol, 271
is_dirty_names, 272	set_recording, 272
is_dirty_perf, 272	set_snap_tick, 272
link new, 281	set thru, 272
m_background_sequence, 285	set_trigger_offset, 284
m_length, 285	split_trigger, 274, 284
m_midi_channel, 284	stream_event, 279
m_musical_key, 285	stretch_selected, 281
m_musical_scale, 285	toggle_queued, 272
m_mutex, 285	transpose_notes, 283
m playing notes, 284	unpaint_all, 281
m_seq_number, 285	unselect, 281
m_snap_tick, 285	unselect_triggers, 275
m_time_beat_width, 285	verify_and_link, 281
m_time_beats_per_measure, 285	zero markers, 282
mark_selected, 281	seq64::trigger, 285
mod last tick, 271	seq64::triggers, 287
move_selected_notes, 279	add, 289
move_selected_triggers_to, 277	adjust_offset, 293
move_triggers, 277	adjust_offsets_to_length, 290
off_playing_notes, 282	copy, 292
off_queued, 272	get_selected_end, 292
partial_assign, 269	get_selected_start, 292
paste_selected, 279	get_state, 291
paste_trigger, 277	grow, 290
play, 273	intersect, 291
play_note_off, 282	m_length, 294
play_note_on, 282	m_ppqn, 294
pop_redo, 269	move_selected, 292
pop_undo, 269	next, 293
print, 273	next_trigger, 293
print_triggers, 273	operator=, 289
push_trigger_undo, 269	paste, 291
push_undo, 269	play, 289
put_event_on_bus, 283	remove, 291
remove, 284	select, 291
remove_all, 284	set_length, 289
remove_marked, 281	split, 290
reset_draw_marker, 282	triggers, 289
reset_draw_trigger_marker, 282	unselect, 291
select_action_e, 269	seq64::user_instrument, 294
select_all, 278	controller_active, 295
select_events, 278	controller_max, 295
select_note_events, 278	controller_name, 295
select_trigger, 274	copy_definitions, 296
selected_trigger_end, 277	m_controller_count, 296
selected_trigger_start, 277	m_is_valid, 296
set_beat_width, 271	set_controller, 295

set_defaults, 295	m_seqedit_scale, 310
set_name, 296	m_seqs_in_set, 311
seq64::user_instrument_t, 296	m_text_x, 310
controllers, 296	m_use_new_font, 310
controllers_active, 296	m_v_perf_page_increment, 310
instrument, 296	mainwid_border, 307
seq64::user_midi_bus, 297	mainwid_grid_style_t, 306
channel_count, 298	mainwid_spacing, 307
channel_max, 298	mainwnd cols, 307
copy_definitions, 298	mainwnd_rows, 307
instrument, 298	max sets, 307
m channel count, 298	mc_baseline_ppqn, 313
m_is_valid, 298	mc_max_zoom, 312
set defaults, 298	mc_min_zoom, 312
set instrument, 298	midi_beat_width, 308
seq64::user_midi_bus_t, 299	midi_beats_per_bar, 308
alias, 299	midi_beats_per_minute, 308
instrument, 299	midi buss override, 308
seq64::user_settings, 299	midi_ppqn, 308
bus, 306	perf_h_page_increment, 308
Busses, 306	
	perf_v_page_increment, 308 private_bus, 308
control_height, 307 controller_active, 307	
	private_instrument, 308
controller_name, 307	set_defaults, 306
dump_summary, 308	set_globals, 306
get_globals, 306	text_x, 307
grid_style_black, 306	text_y, 307
grid_style_max, 306	user_settings, 306
grid_style_normal, 306	zoom, 307
grid_style_white, 306	seq64::userfile, 313
instrument, 307	dump_setting_summary, 314
Instruments, 306	parse, 314
m_allow_two_perfedits, 310	write, 314
m_control_height, 309	seq_clear_perf
m_global_seq_feature_save, 309	seq64::seqmenu, 254
m_gmute_tracks, 312	seq_copy
m_grid_brackets, 309	seq64::seqmenu, 254
m_grid_style, 309	seq_cut
m_h_perf_page_increment, 310	seq64::seqmenu, 254
m_instruments, 309	seq_edit
m_mainwid_border, 309	seq64::seqmenu, 253
m_mainwid_x, 312	seq_event_edit
m_mainwnd_cols, 309	seq64::seqmenu, 253
m_mainwnd_rows, 309	seq_from_xy
m_max_sequence, 312	seq64::mainwid, 136
m_max_sets, 309	seq_in_playing_screen
m_midi_beat_width, 311	seq64::perform, 208
m_midi_beats_per_measure, 311	seq_new
m_midi_beats_per_minute, 311	seq64::seqmenu, 253
m_midi_buses, 309	seq_paste
m_midi_buss_override, 311	seq64::seqmenu, 254
m_midi_ppqn, 311	seqdata
m_save_user_config, 312	seq64::seqdata, 233
m_seqarea_seq_x, 312	seqedit
m_seqarea_x, 312	seq64::seqedit, 238
m_seqchars_x, 311	seqmenu
m_seqedit_bgsequence, 310	seq64::seqmenu, 253
m_seqedit_key, 310	sequence_count

seq64::perform, 195	set_event_data_0
sequence_label	seq64::eventedit, 76
seq64::perform, 206	set_event_data_1
sequence_playing_off	seq64::eventedit, 76
seq64::perform, 204	set_event_name
sequence_playing_on	seq64::eventedit, 76
seq64::perform, 204	set_event_timestamp
set	seq64::eventedit, 76
seq64::keybindentry, 117	set_globals
set_active	seq64::user_settings, 306
seq64::perform, 202	set_group_mute_state
set_adding	seq64::perform, 205
seq64::Seq24PerfInput, 227	set_guides
seq64::Seq24SeqEventInput, 229	seq64::perfedit, 183
seg64::Seg24SegRollInput, 230	seq64::perfroll, 216
set_all_key_events	seq64::perftime, 222
seq64::keys_perform, 120	set_hint_state
seq64::keys_perform_gtk2, 123	seq64::seqkeys, 249
set_all_key_groups	set_input
seq64::keys_perform, 120	seq64::midibus, 160
	•
seq64::keys_perform_gtk2, 123	set_input_bus
set_alsa_client_id	seq64::perform, 207
seq64::lash, 127	set_instrument
set_background_sequence	seq64::user_midi_bus, 298
seq64::seqedit, 239	set_key
seq64::seqroll, 258	seq64::seqedit, 239
set_beat_width	set_key_event
seq64::perfedit, 183	seq64::keys_perform, 120
seq64::sequence, 271	seq64::perform, 210
set_beats_per_bar	set_key_group
seq64::perfedit, 183	seq64::keys_perform, 121
seq64::sequence, 269	seq64::perform, 210
set_beats_per_minute	set_keys
seq64::perform, 204	seq64::keys_perform, 119
set_channel	set_left_tick
seq64::event, 64	seq64::perform, 198
set_controller	set_length
seq64::user_instrument, 295	seq64::sequence, 271
set_current_event	seq64::triggers, 289
seq64::eventslots, 84	set_line
set_data	seq64::gui_drawingarea_gtk2, 99
seq64::event, 64	set_master_midi_bus
set_data_type	seq64::sequence, 278
seq64::seqdata, 233	set_measures
seq64::seqedit, 240	seq64::seqedit, 239
seq64::seqevent, 244	set_midi_bus
seq64::seqroll, 258	seq64::seqedit, 239
set defaults	seq64::sequence, 278
seq64::user_instrument, 295	set_midi_channel
seq64::user_midi_bus, 298	seq64::seqedit, 239
seq64::user_settings, 306	seq64::sequence, 273
set_dirty	set_name
seq64::eventedit, 76	seq64::user_instrument, 296
seq64::sequence, 273	set_note_length
set_dirty_mp	seq64::seqedit, 238
seq64::sequence, 273	set offset
set_event_category	seq64::perform, 205
seq64::eventedit, 76	set_orig_tick
Jogo movemball, 10	001_011 <u>9_</u> 11011

seq64::sequence, 273	show_ui_sequence_key
set_orig_ticks	seq64::keys_perform, 120
seq64::perform, 204	seq64::perform, 206
set_playing	show_ui_sequence_number
seq64::sequence, 271	seq64::keys_perform, 120
set_playing_screenset	seq64::perform, 206
seq64::perform, 201	signal_action
set_position	seq64::mainwnd, 144
seq64::jack_assistant, 113	sm_category_arrays
–	seq64::editable_event, 51
set_ppqn	•
seq64::perfroll, 217	sm_category_names
set_quantized_rec	seq64::editable_event, 50
seq64::sequence, 272	sm_channel_event_names
set_rec_vol	seq64::editable_event, 50
seq64::sequence, 271	sm_internal_keys
set_recording	seq64::gui_assistant_gtk2, 96
seq64::sequence, 272	sm_mc_dummy
set_right_tick	seq64::perform, 210
seq64::perform, 198	sm_meta_event_names
set_scale	seq64::editable_event, 51
seq64::seqedit, 239	sm_prop_event_names
set_screen_set_notepad	seq64::editable_event, 51
seq64::perform, 199	sm_recursive_mutex
set_screenset	seq64::mutex, 175
seq64::mainwid, 134	sm_status_pairs
seq64::perform, 201	seq64::jack_assistant, 115
set_seq_count	sm_system_event_names
seq64::eventedit, 76	seq64::editable_event, 51
set_seq_ppqn	snap_x
seq64::eventedit, 75	seq64::perfroll, 217
set_seq_time_sig	seq64::seqevent, 245
seq64::eventedit, 75	seq64::seqroll, 258
set_seq_title	split
seq64::eventedit, 75	seq64::midi_splitter, 153
set_sequence_control_status	seq64::triggers, 290
seq64::perform, 204	split channel
set snap	seq64::midi_splitter, 153
seq64::seqedit, 238	split_trigger
seq64::seqevent, 244	seq64::sequence, 274, 284
set_snap_tick	start
seq64::sequence, 272	
	seq64::jack_assistant, 110
set_status	seq64::perform, 201
seq64::event, 63, 64	start_paste
set_status_from_string	seq64::seqevent, 245
seq64::editable_event, 50	start_playing
set_text	seq64::mainwnd, 144
seq64::eventslots, 87	seq64::perfedit, 184
set_thru	seq64::perform, 206
seq64::sequence, 272	seq64::perfroll, 218
set_trigger_offset	stock_event_string
seq64::sequence, 284	seq64::editable_event, 50
set_was_active	stop
seq64::perform, 202	seq64::jack_assistant, 110
set_zoom	seq64::perform, 201
seq64::seqdata, 233	stop_playing
seq64::seqedit, 238	seq64::mainwnd, 144
show_statuses	seq64::perfedit, 184
seq64::jack_assistant, 113	seq64::perfroll, 218

stream_event	update_markers
seq64::sequence, 279	seq64::mainwid, 135
stretch_selected	update_sizes
seq64::sequence, 281	seq64::perfroll, 217
sync	seq64::seqdata, 233
seq64::jack_assistant, 113	seq64::seqevent, 244
sysex	update_window_title
seq64::midibus, 160	seq64::mainwnd, 144
	user_settings
text_x	seq64::user_settings, 306
seq64::user_settings, 307	
text_y	v_adjustment
seq64::user_settings, 307	seq64::eventedit, 76, 78
time_as_measures	valid_sequence
seq64::editable_event, 49	seq64::mainwid, 135
time_as_minutes	value_to_name
seq64::editable_event, 49	seq64::editable_event, 48
timeout	varinum_size
seq64::eventedit, 78	seq64::midifile, 171
seg64::mainwid, 136	verify and link
seq64::perfedit, 183	seq64::event_list, 70
timer_callback	seq64::sequence, 281
seq64::mainwnd, 143	30404304461100, 201
timestamp	WHITE
seq64::editable_event, 49	seq64::font, 92
timestamp_format_t	write
	seq64::midifile, 164
seq64::editable_event, 47	seq64::optionsfile, 179
timestamp_measures	seq64::userfile, 314
seq64::editable_event, 47	write_byte
timestamp_pulses	seq64::midifile, 168
seq64::editable_event, 48	write_long
timestamp_time	
seq64::editable_event, 48	seq64::midifile, 168
toggle_queued	write_prop_header seq64::midifile, 169
seq64::sequence, 272	-
transpose_notes	write_proprietary_track seq64::midifile, 170
seq64::sequence, 283	•
triggers	write_seq_number
seq64::triggers, 289	seq64::midifile, 169
type	write_short
seq64::keybindentry, 116	seq64::midifile, 168
	write_track_name
undo	seq64::midifile, 169
seq64::perfedit, 183	write_varinum
unmodify	seq64::midifile, 168
seq64::event_list, 69	
unpaint_all	x_to_w
seq64::sequence, 281	seq64::seqevent, 245
unselect	xy_to_rect
seq64::sequence, 281	seq64::seqdata, 233
seq64::triggers, 291	VELLOW ON BLACK
unselect_triggers	YELLOW_ON_BLACK
seq64::sequence, 275	seq64::font, 92
unset_mode_group_learn	zara markara
seq64::perform, 201	zero_markers
unset_sequence_control_status	seq64::sequence, 282
seq64::perform, 204	zoom
update_background	seq64::user_settings, 307
seq64::seqroll, 258	