


# CS19541-COMPUTER NETWORKS-LAB MANUAL

## Practical-8

**AIM:** - a) Simulate Virtual LAN configuration using CISCO Packet Tracer Simulation.



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
S1	VLAN 1	192.168.1.11	255.255.255.0	N/A
S2	VLAN 1	192.168.1.12	255.255.255.0	N/A
PC-A	NIC	192.168.10.3	255.255.255.0	192.168.10.1
PC-B	NIC	192.168.10.4	255.255.255.0	192.168.10.1

*Blank Line - no additional information*

### Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Create VLANs and Assign Switch Ports

Part 3: Maintain VLAN Port Assignments and the VLAN Database Part 4: Configure an 802.1Q Trunk between the Switches

### Background / Scenario

Modern switches use virtual local-area networks (VLANs) to improve network performance by separating large Layer 2 broadcast domains into smaller ones. VLANs can also be used as a security measure by controlling which hosts can communicate. In general, VLANs make it easier to design a network to support the goals of an organization.

VLAN trunks are used to span VLANs across multiple devices. Trunks allow the traffic from multiple VLANs to travel over a single link, while keeping the VLAN identification and segmentation intact.

In this Packet Tracer Physical Mode (PTPM) activity, you will create VLANs on both switches in the topology, assign VLANs to switch access ports, and verify that VLANs are working as expected. You will then create a VLAN trunk between the two switches to allow hosts in the same VLAN to communicate through the trunk, regardless of which switch to which the host is attached.

### Instructions

**Part 1: Build the Network and Configure Basic Device Settings**

**Step 1: Build the network as shown in the topology.**

Attach the devices as shown in the topology diagram, and cable as necessary. a. Click and drag both switch **S1** and **S2** to the **Rack**.

- b. Click and drag both **PC-A** and **PC-B** to the **Table** and use the power button to turn them on.

## **CS19541-COMPUTER NETWORKS-LAB MANUAL**

- c. Provide network connectivity by connecting **Copper Straight-through** cables, as shown in the topology.
- d. Connect **Console Cable** from device **PC-A** to **S1** and from device **PC-B** to **S2**.

### **Step 2: Configure basic settings for each switch.**

- a. From the **Desktop Tab** on each PC, use the **Terminal** to console into each switch and enable privileged EXEC mode.  
*Open configuration window*
- b. Enter configuration mode.
- c. Assign a device name to each switch.
- d. Assign **class** as the privileged EXEC encrypted password.
- e. Assign **cisco** as the console password and enable login.
- f. Assign **cisco** as the vty password and enable login.
- g. Encrypt the plaintext passwords.
- h. Create a banner that warns anyone accessing the device that unauthorized access is prohibited.
- i. Configure the IP address listed in the Addressing Table for VLAN 1 on the switch.  
**Note:** The VLAN 1 address is not grade because you will remove it later in the activity. However, you will need VLAN 1 to test connectivity later in this Part.
- j. Shut down all interfaces that will not be used.
- k. Set the clock on each switch.  
**Note:** The clock setting cannot be graded in Packet Tracer.
- l. Save the running configuration to the startup configuration file.

*Close configuration window*

### **Step 3: Configure PC hosts.**

From the **Desktop** tab on each **PC**, click IP Configuration and enter the addressing information as displayed in the Addressing Table.

### **Step 4: Test connectivity.**

Test network connectivity by attempting to ping between each of the cabled devices.

Questions:

- Can PC-A ping PC-B?
- Can PC-A ping S1?
- Can PC-B ping S2?
- Can S1 ping S2?

*Close configuration window*

# **CS19541-COMPUTER NETWORKS-LAB MANUAL**

## **Part 2: Create VLANs and Assign Switch Ports**

In Part 2, you will create Management, Operations, Parking Lot, and Native VLANs on both switches. You will then assign the VLANs to the appropriate interface. The **show vlan** command is used to verify your configuration settings.

### **Step 1: Create VLANs on the switches.**

From the **Desktop Tab** on each **PC**, use Terminal to continue configuring both network switches.

*Open configuration window*

- a. Create the VLANs on **S1**.

```
S1(config)# vlan 10
S1(config-vlan)# name Operations
S1(config-vlan)# vlan 20
S1(config-vlan)# name Parking_Lot
S1(config-vlan)# vlan 99
S1(config-vlan)# name Management
S1(config-vlan)# vlan 1000
S1(config-vlan)# name Native
S1(config-vlan)# end
```

- b. Create the same VLANs on **S2**.

- c. Issue the **show vlan brief** command to view the list of VLANs on **S1**.

```
S1# show vlan brief
```

VLAN Name	Status	Ports
1 default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24 Gi0/1, Gi0/2
10 Operations	active	
20 Parking_Lot	active	
99 Management	active	
1000 Native	active	
1002 fddi-default	active	
1003 token-ring-default	active	
1004 fddinet-default	active	
1005 trnet-default	active	

Questions:

What is the default VLAN?

What ports are assigned to the default VLAN?

# CS19541-COMPUTER NETWORKS-LAB MANUAL

## Step 2: Assign VLANs to the correct switch interfaces.

- a. Assign VLANs to the interfaces on S1.
  - 1) Assign PC-A to the Operation VLAN.

```
S1(config)# interface f0/6
S1(config-if)# switchport mode access
S1(config-if)# switchport access vlan 10
```
  - 2) From VLAN 1, remove the management IP address and configure it on VLAN 99.

```
S1(config)# interface vlan 1
S1(config-if)# no ip address
S1(config-if)# interface vlan 99
S1(config-if)# ip address 192.168.1.11 255.255.255.0
S1(config-if)# end
```
- b. Issue the **show vlan brief** command and verify that the VLANs are assigned to the correct interfaces. c. Issue the **show ip interface brief** command.  
Question:  
What is the status of VLAN 99? Explain.
- d. Assign **PC-B** to the Operations VLAN on **S2**.
- e. From VLAN 1, remove the management IP address and configure it on VLAN 99 according to the Addressing Table.
- f. Use the **show vlan brief** command to verify that the VLANs are assigned to the correct interfaces.  
Questions:  
Is S1 able to ping S2? Explain.  
Is PC-A able to ping PC-B? Explain.

## Part 3: Maintain VLAN Port Assignments and the VLAN Database

In Part 3, you will change port VLAN assignments and remove VLANs from the VLAN database.

### Step 1: Assign a VLAN to multiple interfaces.

From the **Desktop Tab** on each **PC**, use **Terminal** to continue configuring both network switches.

#### *Open configuration window*

- a. On S1, assign interfaces F0/11 – 24 to VLAN99.

```
S1(config)# interface range f0/11-24
S1(config-if-range)# switchport mode access
S1(config-if-range)# switchport access vlan 99
S1(config-if-range)# end
```
- b. Issue the **show vlan brief** command to verify VLAN assignments.
- c. Reassign F0/11 and F0/21 to VLAN 10.
- d. Verify that VLAN assignments are correct.

### Step 2: Remove a VLAN assignment from an interface.

- a. Use the **no switchport access vlan** command to remove the VLAN 99 assignment to F0/24.

```
S1(config)# interface f0/24
S1(config-if)# no switchport access vlan
S1(config-if)# end
```
- b. Verify that the VLAN change was made.  
Question:

## **CS19541-COMPUTER NETWORKS-LAB MANUAL**

Which VLAN is F0/24 now associated with?

### **Step 3: Remove a VLAN ID from the VLAN database.**

- a. Add VLAN 30 to interface F0/24 without issuing the global VLAN command.

```
S1(config)# interface f0/24
```

```
S1(config-if)# switchport access vlan 30
```

**% Access VLAN does not exist. Creating vlan 30**

**Note:** Current switch technology no longer requires that the **vlan** command be issued to add a VLAN to the database. By assigning an unknown VLAN to a port, the VLAN will be created and added to the VLAN database.

- b. Verify that the new VLAN is displayed in the VLAN table.

Question:

What is the default name of VLAN 30?

- c. Use the **no vlan 30** command to remove VLAN 30 from the VLAN database.

```
S1(config)# no vlan 30
```

```
S1(config)# end
```

- d. Issue the **show vlan brief** command. F0/24 was assigned to VLAN 30.

Question:

After deleting VLAN 30 from the VLAN database, why is F0/24 no longer displayed in the output of the **show vlan brief** command? What VLAN is port F0/24 now assigned to? What happens to the traffic destined to the host that is attached to F0/24?

- e. On interface F0/24, issue the **no switchport access vlan** command.

- f. Issue the **show vlan brief** command to determine the VLAN assignment for F0/24.

Questions:

To which VLAN is F0/24 assigned?

**Note:** Before removing a VLAN from the database, it is recommended that you reassign all the ports assigned to that VLAN.

Why should you reassign a port to another VLAN before removing the VLAN from the VLAN database?

*Close configuration window.*

### **Part 4: Configure an 802.1Q Trunk Between the Switches**

In Part 4, you will configure interface F0/1 to use the Dynamic Trunking Protocol (DTP) to allow it to negotiate the trunk mode. After this has been accomplished and verified, you will disable DTP on interface F0/1 and manually configure it as a trunk.

#### **Step 1: Use DTP to initiate trunking on F0/1.**

The default DTP mode of a 2960 switch port is dynamic auto. This allows the interface to convert the link to a trunk if the neighboring interface is set to trunk or dynamic desirable mode.

*Open configuration window*

- a. On S1, set F0/1 to negotiate trunk mode.

```
S1(config)# interface f0/1
```

```
S1(config-if)# switchport mode dynamic desirable
```

## **CS19541-COMPUTER NETWORKS-LAB MANUAL**

Sep 19 02:51:47.257: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up  
Sep 19 02:51:47.291: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan99, changed state to up  
You should also receive link status messages on S2.  
S2#  
Sep 19 02:42:19.424: %LINK-3-UPDOWN: Interface FastEthernet0/1, changed state to up  
Sep 19 02:42:21.454: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan99, changed state to up  
Sep 19 02:42:22.419: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

- b. On **S1** and **S2**, issue the **show vlan brief** command. Interface F0/1 is no longer assigned to VLAN 1. Trunked interfaces are not listed in the VLAN table.
- c. Issue the **show interfaces trunk** command to view trunked interfaces. Notice that the mode on **S1** is set to desirable, and the mode on **S2** is set to auto.  
**S1# show interfaces trunk**

**S2# show interfaces trunk**

**Note:** By default, all VLANs are allowed on a trunk. The **switchport trunk** command allows you to control what VLANs have access to the trunk. For this activity, keep the default settings. This allows all VLANs to traverse F0/1.

*Close configuration window*

- d. Verify that VLAN traffic is traveling over trunk interface F0/1.

Questions:

Can S1 ping S2?  
Can PC-A ping PC-B?  
Can PC-A ping S1?  
Can PC-B ping S2?

### **Step 2: Manually configure trunk interface F0/1.**

The **switchport mode trunk** command is used to manually configure a port as a trunk. This command should be issued on both ends of the link.

- a. On interface F0/1, change the switchport mode to force trunking. Make sure to do this on both switches.

*Open configuration window*

**S1(config)# interface f0/1**

**S1(config-if)# switchport mode trunk**

- b. Issue the **show interfaces trunk** command to view the trunk mode. Notice that the mode changed from **desirable** to **on**.

**S1# show interfaces trunk**

- c. Modify the trunk configuration on both switches by changing the native VLAN from VLAN 1 to VLAN 1000.

**S1(config)# interface f0/1**

**S1(config-if)# switchport trunk native vlan 1000**

- d. Issue the **show interfaces trunk** command to view the trunk. Notice the Native VLAN information is updated.

**S2# show interfaces trunk**

Questions:

Why might you want to manually configure an interface to trunk mode instead of using DTP?

Why might you want to change the native VLAN on a trunk?

*Close configuration window*

## **CS19541-COMPUTER NETWORKS-LAB MANUAL**

### **Reflection Questions**

1. What is needed to allow hosts on VLAN 10 to communicate to hosts on VLAN 99?
  2. What are some primary benefits that an organization can receive through effective use of VLANs?
- 
- 

### **b) Design and configure a VLAN for the below given scenario.**

There are 10 faculty in Robotics department, sitting in 3 different blocks. Design and configure a Virtual LAN for Robotics department (using switch and Ethernet cables) so that all the faculty are logically in the same LAN.

### **Student observation:-**


- a) Draw and Label the VLAN for Qb).
- b) Show the ip configuration for each device.
- c) Write the commands used for VLAN configuration in switch.

# CS19541-COMPUTER NETWORKS-LAB MANUAL

## Practical-8

### AIM:-b) Configuration of Wireless LAN using CISCO Packet Tracer.

Design a topology with three PCs connected from Linksys Wireless routers.



Perform following configuration:-

- Configure Static IP on PC and Wireless Router
- Set SSID to MotherNetwork
- Set IP address of router to 192.168.0.1, PC0 to 192.168.0.2, PC1 to 192.168.0.3 and PC2 to 192.168.0.4.
- Secure your network by configuring WAP key on Router
- Connect PC by using WAP key

To complete these tasks follow these step by step instructions:-

Step1:- Click on wireless router,

- Select Administration tab from top Menu, set username and password to admin and click on Save Setting.



## CS19541-COMPUTER NETWORKS-LAB MANUAL

- Next click on wireless tab and set default SSID to MotherNetwork.
- Now Select wireless security and change Security Mode to WEP



- Set Key1 to 0123456789




- Again go in the end of page and Click on Save Setting
- Now we have completed all given task on Wireless router. Now configure the static IP on all three PC's
- Double click on pc select Desktop tab click on IP configuration select Static IP and set IP as given below

PC	IP	Subnet Mask	Default Gateway
PC0	192.168.0.2	255.255.255.0	192.168.0.1
PC1	192.168.0.3	255.255.255.0	192.168.0.1
PC2	192.168.0.4	255.255.255.0	192.168.0.1

## CS19541-COMPUTER NETWORKS-LAB MANUAL

- Now it's time to connect PC's from Wireless router. To do so click PC select Desktop click on PC Wireless




- Click on connect tab and click on Refresh button



As you can see in image that Wireless device is accessing MotherNetwork on CH 6 and signal strength is 100%. In left side you can see that WEP security is configured in network. Click on connect button to connect MotherNetwork

- It will ask for WAP key insert 0123456789 and click connect

## CS19541-COMPUTER NETWORKS-LAB MANUAL



It will connect you with wireless router.

As you can see in image below that system is connected. And PCI card is active.



- Repeat same process on PC1 and PC2.

## **CS19541-COMPUTER NETWORKS-LAB MANUAL**

### **Student observation:**

- c) What is SSID of a wireless router?
- d) What is a security key in wireless router?
- e) Configure a simple Wireless LAN in your lab using a real access point and write down the configurations in your notebook.