1 memcached.json

memcached.json — memcached configuration file

DESCRIPTION

memcached.json is a JSON encoded file specifying the properties used to configure the memcached server. Some of the parameters may be changed at runtime by instructing memcached to reread the configuration file. These properties is explicitly marked as such.

The following sections describes the various attributes that may be specified.

root

This is the root directory of the Couchbase server installation.

admin

Specify the username used for administrive operations (like bucket management). To disable the use of an administrative role you should set this to an empty string.

breakpad

The **breakpad** attribute is used to configure the Breakpad crash catcher. When enabled (and on a supported platform), if memcached crashes a minidump containing information on the state of memcached will be written to disk. It is an object with the following attributes:

```
enabled

A boolean value specifying if Breakpad is enabled.

If true (and *minidump_dir* is set) minidumps will
be output to directory specified by *minidump_dir*.

If not specified then defaults to false.

minidump_dir

A string value specifying the directory to write any outputted minidumps to. If not specified then
Breakpad is not enabled.

content

A string value specifying what data will be included in generated minidumps. Currently the only permitted value is "default".
```

enabled, minidump_dir and content may be modified at runtime by instructing memcached to reread the configuration file.

require_init

The **require_init** attribute is a boolean value that is used to disable disable all user commands while the server (Couchbase Server) is initializing the node (creating the buckets etc). Until the node is initialized memcached will only allow the "admin user" to connect to the cluster and run commands. All other users will receive a "NOT INITIALIZED" response for all commands except SASL requests; which will be allowed, but upon a successful authentication "NOT INITIALIZED" will be returned unless the SASL authentication was done for the admin user.

rbac file

Specify the filename containing all of the RBAC definitions

audit file

Specify the filename containing all of the Audit configurations

ssl_cipher_list

Specify the list of ciphers to use. The format of the string is described in ciphers (https://www.openssl.org/docs/apps/ciphers.html). By default no value is specified causing whatever openssl defaults to to be enabled. Some values may be:

HIGH Only enable "high" encrypthion ciphers (keys > 128 bits)

MEDIUM In addition to the high encryption ciphers, also allow 128 bit encryption

threads

The **threads** attribute specify the number of threads used to serve clients. By default this number is set to 75% of the number of cores available on the system (but no less than 4). The value for threads should be specified as an integral number.

interfaces

The **interfaces** attribute is used to specify an array of interfaces memcached should listen at. Each entry in the interfaces array is an object describing a single interface with the following properties:

host A string value specifying the hostname to bind to. If the attribute is missing (or set to "*") IN_ADDR_ANY is used. An integral number specifying the port number port IPv4 A boolean value specifying if IPv4 should be enabled or not. By default IPv4 is enabled. IPv6 A boolean value specifying if IPv6 should be enabled or not. By default IPv6 is enabled. An integral number specifying the maximum number of maxconn concurrent clients that may be connected. backlog An integral number specifying the backlog size set to listen. A boolean value if TCP_NODELAY should be set or not. tcp_nodelay By default tcp_nodelay is enabled. An object specifying SSL related properties. ssl See below. protocol A string value specifying the protocol enabled for this port. If not present the memcached binary protocol is used. Legal values: "greenstack" or "memcached"

The ssl object contains the two mandatory attributes:

key A string value with the absolute path to the

file containing the private key to use.

cert A string value with the absolute path to the

file containing the X.509 certificate to use.

maxconn, backlog, tcp_nodelay, ssl.key and ssl.cert may be modified by instructing memcached to reread the configuration file.

extensions

The **extensions** attribute is used to specify an array of extensions which should be loaded. Each entry in the extensions array is an object describing a single extension with the following attributes:

module A string value containing the module to load. This may

either be an absolute path, or the systems library path will be searched for the object. When loaded memcached calls the method memcached_extensions_initialize().

config A string value containing configuration attributes to

the module. The config value is passed transparently

to the module.

engine

The **engine** attribute is used to specify the engine to load. It is an object with the following attributes:

module A string value containing the module to load. This may

either be an absolute path, or the systems library path

will be searched for the object. The object must

implement the engine api.

config A string value containing configuration attributes to

the module. The config value is passed transparently

to the module.

require_sasl

The **require_sasl** attribute specify if performing SASL authentication is required or not. The value is a boolean value which is set to false by default.

default_reqs_per_event

The **default_reqs_per_event** attribute is an integral value specifying the number of request that may be served per client before serving the next client (to avoid starvation). The default value is 20.

default_reqs_per_event may be updated by instructing memcached to reread the configuration file.

verbosity

The **verbosity** attribute is an integral value specifying the amount of output produced by the memcached server. By default this value is set to 0 resulting in only warnings to be emitted. Setting this value too high will produce a lot of output which is most likely meaningless for most people.

verbosity may be updated by instructing memcached to reread the configuration file.

datatype_support

The **datatype_support** attribute is a boolean value to enable the support for using the datatype extension. By default this support is **disabled**.

max_packet_size

The **max_packet_size** attribute is an integer value that specify the maximum packet size (in MB) allowed to be received from clients without disconnecting them. This is a safetynet for avoiding the server to try to spool up a 4GB packet. When a packet is received on the network with a body bigger than this threshold EINVAL is returned to the client and the client is disconnected.

EXAMPLES

```
A Sample memcached.json: {
    "threads" : 4,
```

```
"threads" : 4,
"interfaces" :
[
        "maxconn" : 1000,
        "port" : 11310,
        "backlog" : 1024,
        "host" : "*",
        "IPv4" : true,
        "IPv6" : true,
        "tcp_nodelay" : true,
        "ssl" :
            "key" : "/etc/memcached/pkey",
            "cert" : "/etc/memcached/cert"
    },
        "maxconn" : 10000,
        "port" : 11210,
        "backlog" : 1024,
        "host" : "*",
        "IPv4" : true,
        "IPv6" : true,
        "tcp_nodelay" : true
    },
        "maxconn" : 1000,
        "port" : 11213,
        "host" : "127.0.0.1",
        "IPv6" : false
    }
```

```
],
    "extensions" :
        {
            "module" : "stdin_term_handler.so",
            "config" : ""
        },
            "module" : "file_logger.so",
            "config" : "cyclesize=10485760; sleeptime=19; filename=data/n_0/logs/ \leftarrow
               memcached.log"
    ],
    "engine" : {
        "module" : "bucket_engine.so",
        "config" : "admin=_admin;default_bucket_name=default;auto_create=false"
   },
    "require_sasl" : false,
    "prefix_delimiter" : ":",
    "allow_detailed" : true,
    "detail_enabled" : false,
   "default_reqs_per_event" : 20,
   "reqs_per_event_high_priority" : 50,
    "reqs_per_event_med_priority" : 5,
    "reqs_per_event_low_priority" : 1,
    "verbosity" : 0,
    "lock_memory" : false,
    "large_memory_pages" : false,
    "daemonize" : false,
    "pid_file" : "/var/run/memcached.pid",
    "datatype_support" : true,
    "breakpad" : {
        "enabled" : true,
        "minidump_dir" : "/opt/couchbase/var/lib/couchbase/crash",
        "content" : "default"
   }
}
```

COPYRIGHT

Copyright 2014 Couchbase, Inc.