wannier90: User Guide

Version 1.2

15th January 2010

# Chapter 1

# Introduction

## 1.1 Methodology

wannier90 computes maximally-localised Wannier functions (MLWF) following the method of Marzari and Vanderbilt (MV) [1]. For entangled energy bands, the method of Souza, Marzari and Vanderbilt (SMV) [2] is used. We introduce briefly the methods and key definitions here, but full details can be found in the original papers and in Ref. [4].

First-principles codes typically solve the electronic structure of periodic materials in terms of Bloch states,  $\psi_{n\mathbf{k}}$ . These extended states are characterised by a band index n and crystal momentum  $\mathbf{k}$ . An alternative representation can be given in terms of spatially localised functions known as Wannier functions (WF). The WF centred on a lattice site  $\mathbf{R}$ ,  $w_{n\mathbf{R}}(\mathbf{r})$ , is written in terms of the set of Bloch states as

$$w_{n\mathbf{R}}(\mathbf{r}) = \frac{V}{(2\pi)^3} \int_{BZ} \left[ \sum_{m} U_{mn}^{(\mathbf{k})} \psi_{m\mathbf{k}}(\mathbf{r}) \right] e^{-i\mathbf{k}\cdot\mathbf{R}} d\mathbf{k} , \qquad (1.1)$$

where V is the unit cell volume, the integral is over the Brillouin zone (BZ), and  $\mathbf{U^{(k)}}$  is a unitary matrix that mixes the Bloch states at each  $\mathbf{k}$ .  $\mathbf{U^{(k)}}$  is not uniquely defined and different choices will lead to WF with varying spatial localisations. We define the spread  $\Omega$  of the WF as

$$\Omega = \sum_{n} \left[ \langle w_{n\mathbf{0}}(\mathbf{r}) | r^2 | w_{n\mathbf{0}}(\mathbf{r}) \rangle - |\langle w_{n\mathbf{0}}(\mathbf{r}) | \mathbf{r} | w_{n\mathbf{0}}(\mathbf{r}) \rangle|^2 \right]. \tag{1.2}$$

The total spread can be decomposed into a gauge invariant term  $\Omega_{\rm I}$  plus a term  $\tilde{\Omega}$  that is dependant on the gauge choice  $\mathbf{U^{(k)}}$ .  $\tilde{\Omega}$  can be further divided into terms diagonal and off-diagonal in the WF basis,  $\Omega_{\rm D}$  and  $\Omega_{\rm OD}$ ,

$$\Omega = \Omega_{\rm I} + \tilde{\Omega} = \Omega_{\rm I} + \Omega_{\rm D} + \Omega_{\rm OD} \tag{1.3}$$

where

$$\Omega_{\rm I} = \sum_{n} \left[ \langle w_{n\mathbf{0}}(\mathbf{r}) | r^2 | w_{n\mathbf{0}}(\mathbf{r}) \rangle - \sum_{\mathbf{R}m} |\langle w_{n\mathbf{R}}(\mathbf{r}) | \mathbf{r} | w_{n\mathbf{0}}(\mathbf{r}) \rangle|^2 \right]$$
(1.4)

$$\Omega_{\rm D} = \sum_{n} \sum_{\mathbf{R} \neq \mathbf{0}} |\langle w_{n\mathbf{R}}(\mathbf{r}) | \mathbf{r} | w_{n\mathbf{0}}(\mathbf{r}) \rangle|^2$$
(1.5)

wannier90: User Guide

$$\Omega_{\rm OD} = \sum_{m \neq n} \sum_{\mathbf{R}} |\langle w_{m\mathbf{R}}(\mathbf{r}) | \mathbf{r} | w_{n\mathbf{0}}(\mathbf{r}) \rangle|^2$$
(1.6)

The MV method minimises the gauge dependent spread  $\tilde{\Omega}$  with respect the set of  $\mathbf{U^{(k)}}$  to obtain MLWF.

wannier90 requires two ingredients from an initial electronic structure calculation.

1. The overlaps between the cell periodic part of the Bloch states  $|u_{n\mathbf{k}}\rangle$ 

$$M_{mn}^{(\mathbf{k},\mathbf{b})} = \langle u_{m\mathbf{k}} | u_{n\mathbf{k}+\mathbf{b}} \rangle, \tag{1.7}$$

where the vectors **b**, which connect a given k-point with its neighbours, are determined by wannier90 according to the prescription outlined in Ref. [1].

2. As a starting guess the projection of the Bloch states  $|\psi_{n\mathbf{k}}\rangle$  onto trial localised orbitals  $|g_n\rangle$ 

$$A_{mn}^{(\mathbf{k})} = \langle \psi_{m\mathbf{k}} | g_n \rangle, \tag{1.8}$$

Note that  $\mathbf{M}^{(\mathbf{k},\mathbf{b})}$ ,  $\mathbf{A}^{(\mathbf{k})}$  and  $\mathbf{U}^{(\mathbf{k})}$  are all small,  $N \times N$  matrices<sup>1</sup> that are independent of the basis set used to obtain the original Bloch states.

To date, wannier90 has been used in combination with electronic codes based on plane-waves and pseudopotentials (norm-conserving and ultrasoft [5]) as well as mixed basis set techniques such as FLAPW [6].

#### 1.1.1 Entangled Energy Bands

The above description is sufficient to obtain MLWF for an isolated set of bands, such as the valence states in an insulator. In order to obtain MLWF for entangled energy bands we use the "disentanglement" procedure introduced in Ref. [2].

We define an energy window (the "outer window"). At a given k-point  $\mathbf{k}$ ,  $N_{\text{win}}^{(\mathbf{k})}$  states lie within this energy window. We obtain a set of N Bloch states by performing a unitary transformation amongst the Bloch states which fall within the energy window at each k-point:

$$|u_{n\mathbf{k}}^{\text{opt}}\rangle = \sum_{m \in N_{\text{win}}^{(\mathbf{k})}} U_{mn}^{\text{dis}(\mathbf{k})} |u_{m\mathbf{k}}\rangle$$
 (1.9)

where  $\mathbf{U}^{\mathrm{dis}(\mathbf{k})}$  is a rectangular  $N \times N_{\mathrm{win}}^{(\mathbf{k})}$  matrix<sup>2</sup>. The set of  $\mathbf{U}^{\mathrm{dis}(\mathbf{k})}$  are obtained by minimising the gauge invariant spread  $\Omega_{\mathrm{I}}$  within the outer energy window. The MV procedure can then be used to minimise  $\tilde{\Omega}$  and hence obtain MLWF for this optimal subspace.

It should be noted that the energy bands of this optimal subspace may not correspond to any of the original energy bands (due to mixing between states). In order to preserve exactly the properties of a system in a given energy range (e.g., around the Fermi level) we introduce a second energy window. States lying within this inner, or "frozen", energy window are included unchanged in the optimal subspace.

<sup>&</sup>lt;sup>1</sup>Technically, this is true for the case of an isolated group of N bands from which we obtain N MLWF. When using the disentanglement procedure of Ref. [2],  $\mathbf{A^{(k)}}$ , for example, is a rectangular matrix. See Section 1.1.1. 
<sup>2</sup>As  $\mathbf{U}^{\mathrm{dis(k)}}$  is a rectangular matrix this is a unitary operation in the sense that  $(\mathbf{U}^{\mathrm{dis(k)}})^{\dagger}\mathbf{U}^{\mathrm{dis(k)}} = \mathbf{1}$ .

## 1.1.2 Getting Help

The latest version of wannier90 and documentation can always be found at

```
http://www.wannier.org
```

There is a wannier90 mailing list for discussing issues in the development, theory, coding and algorithms pertinent to MLWF. You can register for this mailing list by following the links at

```
http://www.wannier.org/forum.html
```

Finally, many frequently asked questions are answered in Chapter 9.

#### 1.1.3 Citation

We ask that you acknowledge the use of wannier90 in any publications arising from the use of this code through the following reference

```
[ref] A. A. Mostofi, J. R. Yates, Y.-S. Lee, I. Souza, D. Vanderbilt and N. Marzari, wannier90: A Tool for Obtaining Maximally-Localised Wannier Functions, Comput. Phys. Commun. 178, 685 (2008)
```

It would also be appropriate to cite the original articles:

Maximally localized generalized Wannier functions for composite energy bands, N. Marzari and D. Vanderbilt, *Phys. Rev. B* **56**, 12847 (1997)

Maximally localized Wannier functions for entangled energy bands, I. Souza, N. Marzari and D. Vanderbilt, *Phys. Rev. B* **65**, 035109 (2001)

#### 1.1.4 Credits

The present release of wannier90 was written by Arash A. Mostofi (Imperial College London, UK), Jonathan R. Yates (University of Oxford, UK), and Young-Su Lee (KIST, S. Korea). Contributors to the code include Matthew Shelley (Imperial College London, UK) and Nicolas Poilvert (MIT, USA). wannier90 is based on routines written for isolated bands by Nicola Marzari and David Vanderbilt, for entangled bands by Ivo Souza, Nicola Marzari, and David Vanderbilt, and for quantum transport by Marco Nardelli.

Acknowledgements: Stefano de Gironcoli (SISSA, Trieste, Italy) for the PWSCF interface; Michel Posternak (EPFL, Switzerland) for the original plotting routines.

wannier90 © 2010 Arash A. Mostofi, Jonathan R. Yates, Young-Su Lee, Ivo Souza, David Vanderbilt and Nicola Marzari

## 1.1.5 Licence

All the material in this distribution is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WAR-RANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

# Chapter 2

# **Parameters**

## 2.1 Usage

```
wannier90.x [-pp] [seedname]
```

- seedname: If a seedname string is given the code will read its input from a file seedname.win.

  The default value is wannier.
- -pp: This optional flag tells the code to generate a list of the required overlaps and then exit. This information is written to the file seedname.nnkp.

## 2.2 seedname.win File

The wannier90 input file seedname.win has a flexible free-form structure.

The ordering of the keywords is not significant. Case is ignored (so num\_bands is the same as Num\_Bands). Characters after !, or # are treated as comments. Most keywords have a default value that is used unless the keyword is given in seedname.win. Keywords can be set in any of the following ways

```
num_wann 4
num_wann = 4
num_wann : 4
```

A logical keyword can be set to .true. using any of the following strings: T, true, .true.. For further examples see Section 10.1 and the the wannier90 Tutorial.

# 2.3 Keyword List

Keyword	Type	Description	
	System Parameters		
NUM_WANN	I	Number of WF	
NUM_BANDS	I	Number of bands passed to the code	
UNIT_CELL_CART	P	Unit cell vectors in Cartesian coor-	
		dinates	
ATOMS_CART *	P	Positions of atoms in Cartesian co-	
		ordinates	
ATOMS_FRAC *	R	Positions of atoms in fractional co-	
		ordinates with respect to the lattice	
		vectors	
MP_GRID	I	Dimensions of the Monkhorst-Pack	
		grid of k-points	
KPOINTS	R	List of k-points in the Monkhorst-	
		Pack grid	
GAMMA_ONLY	L	Wavefunctions from underlying ab	
		initio calculation are manifestly real	
SPINORS	L	WF are spinors	
SHELL_LIST	I	Which shells to use in finite differ-	
		ence formula	
SEARCH_SHELLS	I	The number of shells to search	
		when determining finite difference	
		formula	
KMESH_TOL	R	The tolerance to control if two	
		kpoint belong to the same shell	

Table 2.1: seedname.win file keywords defining the system. Argument types are represented by, I for a integer, R for a real number, P for a physical value, L for a logical value and S for a text string.

<sup>\*</sup> ATOMS\_CART and ATOMS\_FRAC may not both be defined in the same input file.

Keyword	Type	Description
	Job	Control
POSTPROC_SETUP	L	To output the seedname.nnkp file
EXCLUDE_BANDS	I	List of bands to exclude from the
		calculation
RESTART	С	Restart from checkpoint file
IPRINT	I	Output verbosity level
LENGTH_UNIT	S	System of units to output lengths
WVFN_FORMATTED	L	Read the wavefunctions from a
		(un)formatted file
SPIN	S	Which spin channel to read
DEVEL_FLAG	S	Flag for development use
TIMING_LEVEL	I	Determines amount of timing infor-
		mation written to output
OPTIMISATION	I	Optimisation level
TRANSLATE_HOME_CELL	L	To translate final Wannier centres to
		home unit cell when writing xyz file
WRITE_XYZ	L	To write atomic positions and final
		centres in xyz file format

Table 2.2: seedname.win file keywords defining the system. Argument types are represented by, I for a integer, R for a real number, P for a physical value, L for a logical value and S for a text string. TRANSLATE\_HOME\_CELL only relevant if WRITE\_XYZ is .true.

Keyword	Type	Description		
Dis	Disentanglement Parameters			
DIS_WIN_MIN	P	Bottom of the outer energy window		
DIS_WIN_MAX	P	Top of the outer energy window		
DIS_FROZ_MIN	P	Bottom of the inner (frozen) energy		
		window		
DIS_FROZ_MAX	P	Top of the inner (frozen) energy		
		window		
DIS_NUM_ITER	I	Number of iterations for the minimi-		
		sation of $\Omega_{\rm I}$		
DIS_MIX_RATIO	R	Mixing ratio during the minimisa-		
		tion of $\Omega_{\rm I}$		
DIS_CONV_TOL	R	The convergence tolerance for find-		
		$\log\Omega_{ m I}$		
DIS_CONV_WINDOW	I	The number of iterations over which		
		convergence of $\Omega_{\rm I}$ is assessed.		

Table 2.3: seedname.win file keywords controlling the disentanglement. Argument types are represented by, I for a integer, R for a real number, P for a physical value, L for a logical value and S for a text string.

Keyword	Type	Description			
V	Wannierise Parameters				
NUM_ITER	I	Number of iterations for the minimi-			
		sation of $\Omega$			
NUM_CG_STEPS	I	During the minimisation of $\Omega$ the			
		number of Conjugate Gradient steps			
		before resetting to Steepest De-			
	_	scents			
CONV_WINDOW	I	The number of iterations over which convergence of $\Omega$ is assessed			
CONV_TOL	P	The convergence tolerance for find-			
CONVLICE	1	$\operatorname{ing} \Omega$			
CONV_NOISE_AMP	R	The amplitude of random noise ap-			
		plied towards end of minimisation			
		procedure			
CONV_NOISE_NUM	I	The number of times random noise			
		is applied			
NUM_DUMP_CYCLES	I	Control frequency of check-pointing			
NUM_PRINT_CYCLES	I	Control frequency of printing			
WRITE_R2MN	L	Write matrix elements of $r^2$ between WF to file			
GUIDING_CENTRES	L	Use guiding centres			
NUM_GUIDE_CYCLES	I I	Frequency of guiding centres			
NUM_NO_GUIDE_ITER	I	The number of iterations after			
1.0MILIOLGOIDELITEIT	_	which guiding centres are used			
TRIAL_STEP *	R	The trial step length for the			
		parabolic line search during the			
		minimisation of $\Omega$			
FIXED_STEP *	R	The fixed step length to take dur-			
		ing the minimisation of $\Omega$ , instead			
		of doing a parabolic line search			
USE_BLOCH_PHASES **	L	To use phases for initial projections			

Table 2.4: seedname.win file keywords controlling the wannierisation. Argument types are represented by, I for a integer, R for a real number, P for a physical value, L for a logical value and S for a text string. \* FIXED\_STEP and TRIAL\_STEP may not both be defined in the same input file. \*\*Cannot be used in conjunction with disentanglement.

Keyword	Type	Description	
Plot Parameters			
WANNIER_PLOT	L	Plot the WF	
WANNIER_PLOT_LIST	I	List of WF to plot	
WANNIER_PLOT_SUPERCELL	I	Size of the supercell for plotting the WF	
WANNIER_PLOT_FORMAT	S	File format in which to plot the WF	
WANNIER_PLOT_MODE	S	Mode in which to plot the WF, molecule or crystal	
WANNIER_PLOT_RADIUS	R	Cut-off radius of WF*	
BANDS_PLOT	L	Plot interpolated band structure	
KPOINT_PATH	Р	K-point path for the interpolated band structure	
BANDS_NUM_POINTS	I	Number of points along the first section of the k-point path	
BANDS_PLOT_FORMAT	S	File format in which to plot the interpolated bands	
BANDS_PLOT_PROJECT	I	WF to project the band structure onto	
BANDS_PLOT_MODE	S	Slater-Koster type interpolation or Hamiltonian cut-off	
BANDS_PLOT_DIM	I	Dimension of the system	
FERMI_SURFACE_PLOT	L	Plot the Fermi surface	
FERMI_SURFACE_NUM_POINTS	I	Number of points in the Fermi surface plot	
FERMI_ENERGY	Р	The Fermi energy	
FERMI_SURFACE_PLOT_FORMAT	S	File format for the Fermi surface plot	
HR_PLOT	L	Write the Hamiltonian in the WF basis	
HR_CUTOFF	Р	Cut-off for the absolute value of the Hamiltonian	
DIST_CUTOFF	Р	Cut-off for the distance between WF	
DIST_CUTOFF_MODE	S	Dimension in which the distance between WF is calculated	
ONE_DIM_AXIS	S	Extended direction for a one- dimensional system	
TRANSLATION_CENTRE_FRAC	R	Centre of the unit cell to which final WF are translated	

Table 2.5: seedname.win file keywords controlling the plotting. Argument types are represented by, I for a integer, R for a real number, P for a physical value, L for a logical value and S for a text string. \* Only applies when WANNIER\_PLOT\_FORMAT is cube.

Keyword	Type	Description	
Transport Parameters			
TRANSPORT	L	Calculate quantum conductance	
		and density of states	
TRANSPORT_MODE	S	Bulk or left-lead_conductor_right-	
		lead calculation	
TRAN_WIN_MIN	P	Bottom of the energy window for	
		transport calculation	
TRAN_WIN_MAX	P	Top of the energy window for trans-	
		port calculation	
TRAN_ENERGY_STEP	R	Sampling interval of the energy val-	
		ues	
FERMI_ENERGY	R	The Fermi energy	
TRAN_NUM_BB	I	Size of a bulk Hamiltonian	
TRAN_NUM_LL	I	Size of a left-lead Hamiltonian	
TRAN_NUM_RR	I	Size of a right-lead Hamiltonian	
TRAN_NUM_CC	I	Size of a conductor Hamiltonian	
TRAN_NUM_LC	I	Number of columns in a left-	
	_	lead_conductor Hamiltonian	
TRAN_NUM_CR	I	Number of rows in a conduc-	
	т .	tor_right-lead Hamiltonian	
TRAN_NUM_CELL_LL	I	Number of unit cells in PL of left lead	
TDAN NUM CELL DD	I		
TRAN_NUM_CELL_RR	1	Number of unit cells in PL of right lead	
TRAN_NUM_BANDC	I	Half-bandwidth+1 of a band-	
I KAN_NUW_BANDC	1	diagonal conductor Hamiltonian	
TRAN_WRITE_HT	L	Write the Hamiltonian for transport	
TITAL WILL ELLI		calculation	
TRAN_READ_HT	L	Read the Hamiltonian for transport	
110111 ( 21021 12 211 1		calculation	
TRAN_USE_SAME_LEAD	L	Left and right leads are the same	
TRAN_GROUP_THRESHOLD	R	Distance that determines the group-	
		ing of WFs	
HR_CUTOFF	Р	Cut-off for the absolute value of the	
		Hamiltonian	
DIST_CUTOFF	Р	Cut-off for the distance between WF	
DIST_CUTOFF_MODE	S	Dimension in which the distance be-	
		tween WF is calculated	
ONE_DIM_AXIS	S	Extended direction for a one-	
		dimensional system	
TRANSLATION_CENTRE_FRAC	R	Centre of the unit cell to which final	
		WF are translated	

Table 2.6: seedname.win file keywords controlling transport. Argument types are represented by, I for a integer, R for a real number, P for a physical value, L for a logical value and S for a text string.

## 2.4 System

## 2.4.1 integer :: num\_wann

Number of WF to be found.

No default.

#### 2.4.2 integer :: num\_bands

Total number of bands passed to the code in the seedname.mmn file.

Default num\_bands=num\_wann

#### 2.4.3 Cell Lattice Vectors

The cell lattice vectors should be specified in Cartesian coordinates.

begin unit\_cell\_cart
[units]

$$A_{1x}$$
  $A_{1y}$   $A_{1z}$   
 $A_{2x}$   $A_{2y}$   $A_{2z}$   
 $A_{3x}$   $A_{3y}$   $A_{3z}$ 

end unit\_cell\_cart

Here  $A_{1x}$  is the x-component of the first lattice vector  $\mathbf{A}_1$ ,  $A_{2y}$  is the y-component of the second lattice vector  $\mathbf{A}_2$ , etc.

[units] specifies the units in which the lattice vectors are defined: either Bohr or Ang.

The default value is Ang.

#### 2.4.4 Ionic Positions

The ionic positions may be specified in fractional coordinates relative to the lattice vectors of the unit cell, or in absolute Cartesian coordinates. Only one of atoms\_cart and atoms\_frac may be given in the input file.

#### Cartesian coordinates

begin atoms\_cart
[units]

$$\begin{array}{cccc} P & R_x^P & R_y^P & R_z^P \\ Q & R_x^Q & R_y^Q & R_z^Q \\ \cdot & & \end{array}$$

end atoms\_cart

The first entry on a line is the atomic symbol. The next three entries are the atom's position  $\mathbf{R} = (R_x, R_y, R_z)$  in Cartesian coordinates. The first line of the block, [units], specifies the units in which the coordinates are given and can be either bohr or ang. If not present, the default is ang.

#### Fractional coordinates

begin atoms\_frac

end atoms\_frac

The first entry on a line is the atomic symbol. The next three entries are the atom's position in fractional coordinates  $\mathbf{F} = F_1 \mathbf{A}_1 + F_2 \mathbf{A}_2 + F_3 \mathbf{A}_3$  relative to the cell lattice vectors  $\mathbf{A}_i$ ,  $i \in [1,3]$ .

#### 2.4.5 integer, dimension :: mp\_grid(3)

Dimensions of the regular (Monkhorst-Pack) k-point mesh. For example, for a  $2 \times 2 \times 2$  grid:

mp\_grid : 2 2 2

No default.

## 2.4.6 K-points

Each line gives the coordinate  $\mathbf{K} = K_1\mathbf{B}_1 + K_2\mathbf{B}_2 + K_3\mathbf{B}_3$  of a k-point in relative (crystallographic) units, i.e., in fractional units with respect to the primitive reciprocal lattice vectors  $\mathbf{B}_i$ ,  $i \in [1, 3]$ . The position of each k-point in this list assigns its numbering; the first k-point is k-point 1, the second is k-point 2, and so on.

begin kpoints

$$\begin{array}{cccc} K_1^1 & K_2^1 & K_3^1 \\ K_1^2 & K_2^2 & K_3^2 \\ \vdots & & & \end{array}$$

end kpoints

There is no default.

### 2.4.7 logical :: gamma\_only

If gamma\_only=TRUE, then wannier90 uses a branch of algorithms for disentanglement and localisation that exploit the fact that the Bloch eigenstates obtained from the underlying ab initio calculation are manifestly real. This can be the case when only the  $\Gamma$ -point is used to sample the Brillouin zone. The localisation procedure that is used in the  $\Gamma$ -only branch is based on the method of Ref. [3].

The default value is FALSE.

#### 2.4.8 logical :: spinors

If spinors=TRUE, then wannier90 will expect to find twice as many wannier functions as initial projections.

The default value is FALSE.

#### 2.4.9 Shells

The MV scheme requires a finite difference expression for  $\nabla_{\mathbf{k}}$  defined on a uniform Monkhorst-Pack mesh of k-points. The vectors  $\{\mathbf{b}\}$  connect each mesh-point  $\mathbf{k}$  to its nearest neighbours.  $N_{\rm sh}$  shells of neighbours are included in the finite-difference formula, with  $M_s$  vectors in the  $s^{\rm th}$  shell. For  $\nabla_{\mathbf{k}}$  to be correct to linear order, we require that the following equation is satisfied (Eq. B1 of Ref. [1]):

$$\sum_{s}^{N_{\rm sh}} w_s \sum_{i}^{M_s} b_{\alpha}^{i,s} b_{\beta}^{i,s} = \delta_{\alpha\beta} , \qquad (2.1)$$

where  $\mathbf{b}^{i,s}$ ,  $i \in [1, M_s]$ , is the  $i^{\text{th}}$  vector belonging to the  $s^{\text{th}}$  shell with associated weight  $w_s$ , and  $\alpha$  and  $\beta$  run over the three Cartesian indices.

#### 2.4.10 integer :: shell\_list(:)

shell\_list is vector listing the shells to include in the finite difference expression. If this keyword is absent, the shells are chosen automatically.

#### 2.4.11 integer :: search\_shells

Specifies the number of shells of neighbours over which to search in attempting to determine an automatic solution to the B1 condition Eq. 2.1. Larger values than the default may be required in special cases e.g. for very long thin unit cells.

The default value is 12.

wannier90: User Guide

#### 2.4.12 real(kind=dp) :: kmesh\_tol

Two kpoints belong to the same shell if the distance between them is less than kmesh\_tol. Units are Ang.

The default value is 0.000001 Ang.

## 2.5 Projection

The projections block defines a set of localised functions used to generate an initial guess for the unitary transformations. This data will be written in the seedname.nnkp file to be used by a first-principles code.

```
begin projections
```

end projections

If guiding\_centres=TRUE, then the projection centres are used as the guiding centres in the Wannierisation routine.

For details see Section 3.1.

## 2.6 Job Control

## 2.6.1 logical :: postproc\_setup

If postproc\_setup=TRUE, then the wannier code will write seedname.nnkp file and exit. If wannier90 is called with the option -pp, then postproc\_setup is set to TRUE, over-riding its value in the seedname.win file.

The default value is FALSE.

#### 2.6.2 integer :: iprint

This indicates the level of verbosity of the output from 0, the bare minimum, to 3, which corresponds to full debugging output.

The default value is 1.

## 2.6.3 integer :: optimisation

This indicates the level of optimisation used in the code. This is a trade between speed and memory. A positive number indicates fastest execution time at the cost of more memory. Zero or negative numbers indicates a smaller memory footprint - at increased execution time.

At the moment the only values that have an effect are optimisation<=0 (low memory) and optimisation>0 (fast)

The default value is 3.

## 2.6.4 character(len=20) :: length\_unit

The length unit to be used for writing quantities in the output file seedname.wout.

The valid options for this parameter are:

```
- Ang (default)
```

- Bohr

## 2.6.5 character(len=50) :: devel\_flag

Not a regular keyword. Its purpose is to allow a developer to pass a string into the code to be used inside a new routine as it is developed.

No default.

#### 2.6.6 integer :: exclude\_bands(:)

A k-point independent list of states to excluded from the calculation of the overlap matrices; for example to select only valence states, or ignore semi-core states. This keyword is passed to the first-principles code via the seedname.nnkp file. For example, to exclude bands 2, 6, 7, 8 and 12:

```
exclude_bands : 2, 6-8, 12
```

## 2.6.7 character(len=20) :: restart

If restart is present the code will attempt to restart the calculation from the seedname.chk file. The value of the parameter determines the position of the restart

The valid options for this parameter are:

- default. Restart from the point at which the check file seedname.chk was written
- wannierise. Restart from the beginning of the wannierise routine
- plot. Go directly to the plotting phase
- transport. Go directly to the transport routines

#### 2.6.8 character(len=20) :: wvfn\_formatted

If wvfn\_formatted=TRUE, then the wavefunctions will be read from disk as formatted (ie ASCII) files; otherwise they will be read as unformatted files. Unformatted is generally preferable as the files will take less disk space and I/O is significantly faster. However such files will not be transferable between all machine architectures and formatted files should be used if transferability is required (i.e., for test cases).

The default value of this parameter is FALSE.

## 2.6.9 character(len=20) :: spin

For bands from a spin polarised calculation spin determines which set of bands to read in, either up or down.

The default value of this parameter is up.

## 2.6.10 integer :: timing\_level

Determines the amount of timing information regarding the calculation that will be written to the output file. A value of 1 produces the least information.

The default value is 1.

#### 2.6.11 logical :: translate\_home\_cell

Determines whether to translate the final Wannier centres to the home unit cell at the end of the calculation. Mainly useful for molecular systems in which the molecule resides entirely within the home unit cell and user wants to write an xyz file (write\_xyz=.TRUE.) for the WF centres to compare with the structure.

The default value is false.

## 2.6.12 logical :: write\_xyz

Determines whether to write the atomic positions and final Wannier centres to an xyzfile, seedname\_centres.xyz, for subsequent visualisation.

The default value is false.

# 2.7 Disentanglement

These keywords control the disentanglement routine of Ref. [2], i.e., the iterative minimisation of  $\Omega_{\rm I}$ . This routine will be activated if num\_wann < num\_bands.

### 2.7.1 real(kind=dp) :: dis\_win\_min

The lower bound of the outer energy window for the disentanglement procedure. Units are eV.

The default is the lowest eigenvalue in the system.

## 2.7.2 real(kind=dp) :: dis\_win\_max

The upper bound of the outer energy window for the disentanglement procedure. Units are eV.

The default is the highest eigenvalue in the given states (i.e., all states are included in the disentanglement procedure).

## 2.7.3 real(kind=dp) :: dis\_froz\_min

The lower bound of the inner energy window for the disentanglement procedure. Units are eV.

If dis\_froz\_max is given, then the default for dis\_froz\_min is dis\_win\_min.

## 2.7.4 real(kind=dp) :: dis\_froz\_max

The upper bound of the inner (frozen) energy window for the disentanglement procedure. If dis\_froz\_max is not specified, then there are no frozen states. Units are eV.

No default.

#### 2.7.5 integer :: dis\_num\_iter

In the disentanglement procedure, the number of iterations used to extract the most connected subspace.

The default value is 200.

## 2.7.6 real(kind=dp) :: dis\_mix\_ratio

In the disentanglement procedure, the mixing parameter to use for convergence (see pages 4-5 of Ref. [2]). A value of 0.5 is a 'safe' choice. Using 1.0 (i.e., no mixing) often gives faster convergence, but may cause the minimisation of  $\Omega_{\rm I}$  to be unstable in some cases.

Restriction:  $0.0 < dis_mix_ratio \le 1.0$ 

The default value is 0.5

#### 2.7.7 real(kind=dp) :: dis\_conv\_tol

In the disentanglement procedure, the minimisation of  $\Omega_I$  is said to be converged if the fractional change in the gauge-invariant spread between successive iterations is less than dis\_conv\_tol for dis\_conv\_window iterations. Units are Å<sup>2</sup>.

The default value is 1.0E-10

## 2.7.8 integer :: dis\_conv\_window

In the disentanglement procedure, the minimisation is said to be converged if the fractional change in the spread between successive iterations is less than dis\_conv\_tol for dis\_conv\_window iterations.

The default value of this parameter is 3.

## 2.8 Wannierise

Iterative minimisation of  $\widetilde{\Omega}$ , the non-gauge-invariant part of the spread functional.

## 2.8.1 integer :: num\_iter

Total number of iterations in the minimisation procedure.

The default value is 100

## 2.8.2 integer :: num\_cg\_steps

Number of conjugate gradient steps to take before resetting to steepest descents.

The default value is 5

#### 2.8.3 integer :: conv\_window

If  $conv\_window > 1$ , then the minimisation is said to be converged if the change in  $\Omega$  over  $conv\_window$  successive iterations is less than  $conv\_tol$ . Otherwise, the minimisation proceeds for num\_iter iterations (default).

The default value is -1

## 2.8.4 real(kind=dp) :: conv\_tol

If conv\_window > 1, then this is the convergence tolerance on  $\Omega$ , otherwise not used. Units are  $\mathring{A}^2$ .

The default value is 1.0E-10

## 2.8.5 real(kind=dp) :: conv\_noise\_amp

If  $conv\_noise\_amp > 0$ , once convergence (as defined above) is achieved, some random noise f is added to the search direction, and the minimisation is continued until convergence is achieved once more. If the same value of  $\Omega$  as before is arrived at, then the calculation is considered to be converged. If not, then random noise is added again and the procedure repeated up to a maximum of  $conv\_noise\_num$  times.  $conv\_noise\_amp$  is the amplitude of the random noise f that is added to the search direction:  $0 < |f| < conv\_noise\_amp$ . This functionality requires  $conv\_window > 1$ . If  $conv\_window$  is not specified, it is set to the value 5 by default.

If  $conv\_noise\_amp \le 0$ , then no noise is added (default).

The default value is -1.0

#### 2.8.6 integer :: conv\_noise\_num

If conv\_noise\_amp > 0, then this is the number of times in the minimisation that random noise is added.

The default value is 3

#### 2.8.7 integer :: num\_dump\_cycles

Write sufficient information to do a restart every num\_dump\_cycles iterations.

The default is 100

## 2.8.8 integer :: num\_print\_cycles

Write data to the master output file seedname.wout every num\_print\_cycles iterations.

The default is 1

## 2.8.9 logical :: write\_r2mn

If write\_r2mn = true, then the matrix elements  $\langle m|r^2|n\rangle$  (where m and n refer to WF) are written to file seedname.r2mn at the end of the Wannierisation procedure.

The default value of this parameter is FALSE.

### 2.8.10 logical :: guiding\_centres

Use guiding centres during the minimisation, in order to avoid local minima.

The default value is FALSE.

## 2.8.11 integer :: num\_guide\_cycles

If guiding\_centres is set to true, then the guiding centres are used only every num\_guide\_cycles.

The default value is 1.

## 2.8.12 integer :: num\_no\_guide\_iter

If guiding\_centres is set to true, then the guiding centres are used only after num\_no\_guide\_iter minimisation iterations have been completed.

The default value is 0.

## 2.8.13 real(kind=dp) :: trial\_step

The value of the trial step for the parabolic fit in the line search minimisation used in the minimisation of the spread function. Cannot be used in conjunction with fixed\_step (see below). If the minimisation procedure doesn't converge, try decreasing the value of trial\_step to give a more accurate line search.

The default value is 2.0

#### 2.8.14 real(kind=dp) :: fixed\_step

If this is given a value in the input file, then a fixed step of length fixed\_step (instead of a parabolic line search) is used at each iteration of the spread function minimisation. Cannot be used in conjunction with trial\_step. This can be useful in cases in which minimisation with a line search fails to converge.

There is no default value.

## 2.8.15 logical :: use\_bloch\_phases

Determines whether to use the Bloch functions as the initial guess for the projections. Can only be used if disentanglement = false.

Th default value is false.

## 2.9 Post-Processing

#### Capabilities:

- Plot the WF
- Plot the interpolated band structure
- Plot the Fermi surface
- Output the Hamiltonian in the WF basis
- Transport calculation (quantum conductance and density of states)

#### 2.9.1 logical :: wannier\_plot

If wannier\_plot = TRUE, then the code will write out the wannier functions in a super-cell wannier\_plot\_supercell times the original unit cell in a format specified by wannier\_plot\_format

The default value of this parameter is FALSE.

## 2.9.2 integer :: wannier\_plot\_supercell

Dimension of the 'super-unit-cell' in which the WF are plotted. The super-unit-cell is wannier\_plot\_supercell times the unit cell along all three linear dimensions (the 'home' unit cell is kept approximately in the middle).

The default value is 2.

## 2.9.3 character(len=20) :: wannier\_plot\_format

WF can be plotted in either XCrySDen (xsf) format or Gaussian cube format. The valid options for this parameter are:

- xcrysden (default)
- cube

If wannier\_plot\_format=cube: Most visualisation programs (including XCrySDen) are only able to handle cube files for systems with orthogonal lattice vectors. wannier90 checks this on reading the seedname.win and reports an error if cube format has been selected and the lattice vectors are not mutually orthogonal.

<sup>&</sup>lt;sup>1</sup>It's worth noting that the visualisation program VMD (http://www.ks.uiuc.edu/Research/vmd), for example, is able to deal with certain special cases of non-orthogonal lattice vectors. See http://www.ks.uiuc.edu/Research/vmd/plugins/molfile/cubeplugin.html. At present wannier90 only supports orthogonal lattice vectors for cube output.

#### 2.9.4 integer :: wannier\_plot\_list(:)

A list of WF to plot. The WF numbered as per the **seedname.wout** file after the minimisation of the spread.

The default behaviour is to plot all WF. For example, to plot WF 4, 5, 6 and 10:

```
wannier_plot_list : 4-6, 10
```

## 2.9.5 character(len=20) :: wannier\_plot\_mode

Choose the mode in which to plot the WF, either as a molecule or as a crystal. Only relevant if wannier\_plot\_format=xcrysden.

The valid options for this parameter are:

```
- crystal (default)
```

- molecule

## 2.9.6 real(kind=dp) :: wannier\_plot\_radius

If wannier\_plot\_format is cube, then wannier\_plot\_radius determines the cut-off radius of the WF for the purpose of plotting. wannier\_plot\_radius must be greater than 0. Units are Å.

The default value is 3.5.

## 2.9.7 logical :: bands\_plot

If bands\_plot = TRUE, then the code will calculate the band structure, through Wannier interpolation, along the path in k-space defined by bands\_kpath using bands\_num\_points along the first section of the path and write out an output file in a format specified by bands\_plot\_format.

The default value is FALSE.

## 2.9.8 kpoint\_path

Defines the path in k-space along which to calculate the bandstructure. Each line gives the start and end point (with labels) for a section of the path. Values are in fractional coordinates with respect to the primitive reciprocal lattice vectors.

```
begin kpoint_path
```

end kpoint\_path

There is no default

#### 2.9.9 integer :: bands\_num\_points

If bands\_plot = TRUE, then the number of points along the first section of the bandstructure plot given by kpoint\_path. Other sections will have the same density of k-points.

The default value for bands\_num\_points is 100.

#### 2.9.10 character(len=20) :: bands\_plot\_format

Format in which to plot the interpolated band structure. The valid options for this parameter are:

```
- gnuplot (default)
```

- xmgrace

Note: it is possible to request output in both formats eg bands\_format = gnuplot xmgrace

## 2.9.11 integer :: bands\_plot\_project(:)

If present wannier90 will compute the contribution of this set of WF to the states at each point of the interpolated band structure. The WF are numbered according to the seedname.wout file. The result is written in the seedname\_band.dat file, and a corresponding gnuplot script to seedname\_band\_proj.dat .

For example, to project on to WFs 2, 6, 7, 8 and 12:

```
bands_plot_project : 2, 6-8, 12
```

## 2.9.12 character(len=20) :: bands\_plot\_mode

To interpolate the band structure along the k-point path, either use the Slater-Koster interpolation scheme or truncate the Hamiltonian matrix in the WF basis. Truncation criteria are provided by hr\_cutoff and dist\_cutoff.

The valid options for this parameter are:

```
- s-k (default)
```

- cut

#### 2.9.13 integer :: bands\_plot\_dim

Dimension of the system. If bands\_plot\_dim <3 and bands\_plot\_mode = cut, lattice vector  $\mathbf{R} = N_1 \mathbf{A}_1 + N_2 \mathbf{A}_2 + N_3 \mathbf{A}_3$ , where  $N_i = 0$  if  $\mathbf{A}_i$  is parallel to any of the confined directions specified by one\_dim\_axis, are exclusively used in the band structure interpolation.

The valid options for this parameter are:

- 3 (default)
- -2
- 1

## 2.9.14 logical :: fermi\_surface\_plot

If fermi\_surface\_plot = TRUE, then the code will calculate, through Wannier interpolation, the eigenvalues on a regular grid with fermi\_surface\_num\_points in each direction. The code will write a file in bxsf format which can be read by XCrySDen in order to plot the Fermi surface.

The default value is FALSE.

## 2.9.15 integer :: fermi\_surface\_num\_points

If fermi\_surface\_plot = TRUE, then the number of divisions in the regular k-point grid used to calculate the Fermi surface.

The default value for fermi\_surface\_num\_points is 50.

## 2.9.16 real(kind=dp) :: fermi\_energy

The Fermi energy in eV. This parameter is written into the bxsf file.

The default value is 0.0

## 2.9.17 character(len=20) :: fermi\_surface\_plot\_format

Format in which to plot the Fermi surface. The valid options for this parameter are:

```
- xcrysden (default)
```

## 2.9.18 logical :: hr\_plot

If hr\_plot = TRUE, then the Hamiltonian matrix in the WF basis will be written to a file seedname\_hr.dat.

The default value is FALSE.

#### 2.9.19 logical :: transport

If transport = TRUE, then the code will calculate quantum conductance and density of states of a one-dimensional system. The results will be written to files seedname\_qc.dat and seedname\_dos.dat, respectively. Since both quantities are a function of energy, they will be evaluated from tran\_win\_min to tran\_win\_max with an interval of tran\_energy\_step.

The default value of this parameter is FALSE.

## 2.9.20 character(len=20) :: transport\_mode

If transport\_mode = bulk, quantum conductance and density of states are calculated for a perfectly-periodic one-dimensional system. In this case, the transport part can either use the Hamiltonian matrix in the WF basis generated by wannier90 or a Hamiltonian matrix provided by the external file seedname\_htB.dat.

If transport\_mode = 1cr, quantum conductance and density of states are calculated for a system where semi-infinite, left and right leads are connected through a central conductor region. In this case, the transport part will work independently from the disentanglement and wannierise procedure. Details of the method is described in Ref. [7].

If tran\_read\_ht = TRUE then the Hamiltonian matrices must be provided by the five external files: seedname\_htL.dat, seedname\_htC.dat, seedname\_htC.dat, seedname\_htC.dat, seedname\_htR.dat. If tran\_read\_ht = FALSE then the Hamiltonian matrices are found automatically provided the supercell adheres to conditions outlined in Section 7.3.

The valid options for this parameter are:

```
- bulk (default)
```

- lcr

#### 2.9.21 real(kind=dp) :: tran\_win\_min

The lower bound of the energy window for the transport calculation. Units are eV.

The default value is -3.0.

#### 2.9.22 real(kind=dp) :: tran\_win\_max

The upper bound of the energy window for the transport calculation. Units are eV.

The default value is 3.0.

#### 2.9.23 real(kind=dp) :: tran\_energy\_step

Sampling interval of the energy values from tran\_win\_min to tran\_win\_max. Units are eV.

The default value is 0.01.

## 2.9.24 real(kind=dp) :: fermi\_energy

The Fermi energy in eV. The energy axis of the quantum conductance and density of states data will be shifted rigidly by this amount.

The default value is 0.0

#### 2.9.25 integer :: tran\_num\_bb

Size of a bulk Hamiltonian matrix. This number is equal to the number of WFs in one principal layer.

A one-dimensional system can be viewed as an array of principal layers which are defined in a way that localized basis functions inside a certain principal layer only interact with those in the nearest neighbor principal layer. In wannier90 a principal layer will be an integer multiple of a unit cell, and the size is determined by hr\_cutoff and/or dist\_cutoff. The criterion is rather arbitrary when WFs are adopted as a localized basis set, and it is up to a user's choice.

The default value is 0.

## 2.9.26 integer :: tran\_num\_ll

Size of a left-lead Hamiltonian matrix. If transport\_mode = lcr and tran\_read\_ht = FALSE then tran\_num\_ll is the number of Wannier functions in a principal layer.

The default value is 0.

## 2.9.27 integer :: tran\_num\_rr

Size of a right-lead Hamiltonian matrix.

The default value is 0.

#### 2.9.28 integer :: tran\_num\_cc

Size of a conductor Hamiltonian matrix.

The default value is 0.

#### 2.9.29 integer :: tran\_num\_lc

Number of columns in a left-lead\_conductor Hamiltonian matrix. Number of rows must be equal to tran\_num\_11.

The default value is 0.

### 2.9.30 integer :: tran\_num\_cr

Number of rows in a conductor\_right-lead Hamiltonian matrix. Number of columns must be equal to tran\_num\_rr.

The default value is 0.

## 2.9.31 integer :: tran\_num\_cell\_ll

Number of unit cells in one principal layer of left lead. Used if transport\_mode = lcr and tran\_read\_ht = FALSE.

The default value is 0.

## 2.9.32 integer :: tran\_num\_cell\_rr

Number of unit cells in one principal layer of right lead. Not used at present.

The default value is 0.

### 2.9.33 integer :: tran\_num\_bandc

Half-bandwidth+1 of a band-diagonal conductor Hamiltonian matrix.

The Hamiltonian matrix of a central conductor part, which is read from seedname\_htC.dat, will be diagonally dominant when tran\_num\_cc is very large. tran\_num\_bandc is used to construct a compact matrix which contains the non-zero band-diagonal part of a full conductor Hamiltonian matrix. Setting this parameter is only meaningful when tran\_num\_bandc is greater than tran\_num\_lc and tran\_num\_cr.

The default value is 0.

## 2.9.34 logical :: tran\_write\_ht

If tran\_write\_ht = TRUE, then the Hamiltonian matrix formatted for the transport calculation will be written to a file seedname\_htB.dat.

The default value is FALSE.

### 2.9.35 logical :: tran\_read\_ht

If tran\_write\_ht = TRUE, then the Hamiltonian matrix formatted for the transport calculation will be read from a set of files described in the parameter transport\_mode. Set tran\_write\_ht = FALSE to perform automated lcr calculations (see Section 7.3).

The default value is FALSE.

## 2.9.36 logical :: tran\_use\_same\_lead

If tran\_use\_same\_lead = TRUE, then the left and the right leads are the same. In this case, seedname\_htR.dat is not required.

The default value is TRUE.

## 2.9.37 real(kind=dp) :: tran\_group\_threshold

Used to group and sort Wannier functions according to the positions of their centres. Wannier functions in a group are within  $tran_group_threshold$  from one another in x,y and z directions. Units are Å

The default is 0.15

## 2.9.38 real(kind=dp) :: translation\_centre\_frac(3)

Centre of the unit cell to which the final Wannier centers are translated. Numbers are in fractional coordinates with respect to the lattice vectors.

The default value is (0.0,0.0,0.0).

## 2.9.39 real(kind=dp) :: hr\_cutoff

The absolute value of the smallest matrix element of the Hamiltonian in the WF basis. If  $h_{mn}(\mathbf{R}) > \text{hr\_cutoff}$ , then the matrix element  $h_{mn}(\mathbf{R})$  is retained and used in the band structure interpolation (when bands\_plot\_mode = cut) or in the transport calculation. Otherwise it is deemed to be insignificant and is discarded. Units are eV.

The default value is 0.0.

#### 2.9.40 real(kind=dp) :: dist\_cutoff

The largest distance between two WFs for which the Hamiltonian matrix element is retained and used in the band interpolation (when bands\_plot\_mode = cut) or in the transport calculation. Units are Å.

The default value is 1000.0.

#### 2.9.41 character(len=20) :: dist\_cutoff\_mode

Dimension in which the distance between two WFs is calculated. The vector connecting two WFs may be projected to a line (one\_dim) or a plane (two\_dim). The size of the projected vector is calculated, and dist\_cutoff is applied. When one\_dim or two\_dim is used, one\_dim\_axis must be given to specify extended or confined direction.

The valid options for this parameter are:

```
- three_dim (default)
```

- two\_dim
- one\_dim

## 2.9.42 character(len=20) :: one\_dim\_axis

Extended direction for a one-dimensional system or confined direction for a two-dimensional system. This direction must be parallel to one of the Cartesian axes.

The valid options for this parameter are:

- x
- у
- z

No default.

# Chapter 3

# **Projections**

## 3.1 Specification of projections in seedname.win

Here we describe the projection functions used to construct the initial guess  $A_{mn}^{(\mathbf{k})}$  for the unitary transformations.

Each projection is associated with a site and an angular momentum state defining the projection function. Optionally, one may define, for each projection, the spatial orientation, the radial part, the diffusivity, and the volume over which real-space overlaps  $A_{mn}$  are calculated.

The code is able to

- 1. project onto s,p,d and f angular momentum states, plus the hybrids sp, sp $^{3}$ , sp $^{3}$ d, sp $^{3}$ d $^{2}$ .
- 2. control the radial part of the projection functions to allow higher angular momentum states, e.g., both 3s and 4s in silicon.

The atomic orbitals of the hydrogen atom provide a good basis to use for constructing the projection functions: analytical mathematical forms exist in terms of the good quantum numbers n, l and m; hybrid orbitals (sp, sp<sup>2</sup>, sp<sup>3</sup>, sp<sup>3</sup>d etc.) can be constructed by simple linear combination  $|\phi\rangle = \sum_{nlm} C_{nlm} |nlm\rangle$  for some coefficients  $C_{nlm}$ .

The angular functions that use as a basis for the projections are not the canonical spherical harmonics  $Y_{lm}$  of the hydrogenic Schrödinger equation but rather the real (in the sense of non-imaginary) states  $\Theta_{lm_r}$ , obtained by a unitary transformation. For example, the canonical eigenstates associated with l=1,  $m=\{-1,0,1\}$  are not the real  $p_x$ ,  $p_y$  and  $p_z$  that we want. See Section 3.3 for our mathematical conventions regarding projection orbitals for different n, l and  $m_r$ .

We use the following format to specify projections in <seedname>.win:

Begin Projections
[units]

site:ang\_mtm:zaxis:xaxis:radial:zona

:

#### End Projections

Notes:

#### units:

Optional. Either Ang or Bohr to specify whether the projection centres specified in this block (if given in Cartesian co-ordinates) are in units of Angstrom or Bohr, respectively. The default value is Ang.

#### site:

C, Al, etc. applies to all atoms of that type

f=0,0.50,0 – centre on (0.0,0.5,0.0) in fractional coordinates (crystallographic units) relative to the direct lattice vectors

c=0.0,0.805,0.0 – centre on (0.0,0.805,0.0) in Cartesian coordinates in units specified by the optional string units in the first line of the projections block (see above).

#### ang\_mtm:

Angular momentum states may be specified by 1 and mr, or by the appropriate character string. See Tables 3.1 and 3.2. Examples:

1=2,mr=1 or dz2 - a single projection with  $l=2, m_{\rm r}=1$  (i.e.,  ${\rm d}_{z^2}$ )

1=2,mr=1,4 or dz2,dx2-y2 - two functions:  $d_{z^2}$  and  $d_{xz}$ 

1=-3 or sp3 – four sp<sup>3</sup> hybrids

Specific hybrid orbitals may be specified as follows:

1=-3,mr=1,3 or sp3-1,sp3-3 – two specific  $sp^3$  hybrids

Multiple states may be specified by separating with ';', e.g.,

sp3;1=0 or 1=-3;1=0 – four  $sp^3$  hybrids and one s orbital

zaxis (optional):

z=1,1,1- set the z-axis to be in the (1,1,1) direction. Default is z=0,0,1

xaxis (optional):

x=1,1,1- set the x-axis to be in the (1,1,1) direction. Default is x=1,0,0

#### radial (optional):

r=2 – use a radial function with one node (ie second highest pseudostate with that angular momentum). Default is r=1. Radial functions associated with different values of r should be orthogonal to each other.

#### zona (optional):

zona=2.0 – the value of  $\frac{Z}{a}$  for the radial part of the atomic orbital (controls the diffusivity of the radial function). Units always in reciprocal Angstrom. Default is zona=1.0.

#### Examples

1. CuO, s,p and d on all Cu; sp<sup>3</sup> hybrids on O:

Cu:1=0;1=1;1=2

2. A single projection onto a  $p_z$  orbital orientated in the (1,1,1) direction:

```
c=0,0,0:l=1,mr=1:z=1,1,1 or c=0,0,0:pz:z=1,1,1
```

3. Project onto s, p and d (with no radial nodes), and s and p (with one radial node) in silicon:

Si:1=0;1=1;1=2

Si:1=0;1=1:r=2

## 3.2 Short-Cuts

## 3.2.1 Random projections

It is possible to specify the projections, for example, as follows:

Begin Projections

random

C:sp3

End Projections

in which case wannier90 uses four sp<sup>3</sup> orbitals centred on each C atom and then chooses the appropriate number of randomly-centred s-type Gaussian functions for the remaining projection functions. If the block only consists of the string random and no specific projection centres are given, then all of the projection centres are chosen randomly.

#### 3.2.2 Bloch phases

Setting use\_bloch\_phases = true in the input file absolves the user of the need to specify explicit projections. In this case, the Bloch wave-functions are used as the projection orbitals, namely  $A_{mn}^{(\mathbf{k})} = \langle \psi_{m\mathbf{k}} | \psi_{n\mathbf{k}} \rangle = \delta_{mn}$ .

## 3.3 Orbital Definitions

The angular functions  $\Theta_{lm_r}(\theta,\varphi)$  associated with particular values of l and  $m_r$  are given in Tables 3.1 and 3.2.

The radial functions  $R_r(r)$  associated with different values of r should be orthogonal. One choice would be to take the set of solutions to the radial part of the hydrogenic Schrödinger equation for l=0, i.e., the radial parts of the 1s, 2s, 3s... orbitals, which are given in Table 3.3.

l	$m_{ m r}$	Name	$\Theta_{lm_{ m r}}( heta,arphi)$
0	1	S	$\frac{1}{\sqrt{4\pi}}$
1	1	pz	$\sqrt{\frac{3}{4\pi}}\cos\theta$
1	2	px	$\sqrt{\frac{3}{4\pi}}\sin\theta\cos\varphi$
1	3	ру	$\sqrt{\frac{3}{4\pi}}\sin\theta\sin\varphi$
2	1	dz2	$\sqrt{\frac{5}{16\pi}}(3\cos^2\theta - 1)$
2	2	dxz	$\sqrt{\frac{15}{4\pi}}\sin\theta\cos\theta\cos\varphi$
2	3	dyz	$\sqrt{\frac{15}{4\pi}}\sin\theta\cos\theta\sin\varphi$
2	4	dx2-y2	$\sqrt{\frac{15}{16\pi}}\sin^2\theta\cos2\varphi$
2	5	dxy	$\sqrt{\frac{15}{16\pi}}\sin^2\theta\sin2\varphi$
3	1	fz3	$\frac{\sqrt{7}}{4\sqrt{\pi}}(5\cos^3\theta - 3\cos\theta)$
3	2	fxz2	$\frac{\sqrt{21}}{4\sqrt{2\pi}}(5\cos^2\theta - 1)\sin\theta\cos\varphi$
3	3	fyz2	$\frac{\sqrt{21}}{4\sqrt{2\pi}}(5\cos^2\theta - 1)\sin\theta\sin\varphi$
3	4	fz(x2-y2)	$\frac{\sqrt{105}}{4\sqrt{\pi}}\sin^2\theta\cos\theta\cos2\varphi$
3	5	fxyz	$\frac{\sqrt{105}}{4\sqrt{\pi}}\sin^2\theta\cos\theta\sin2\varphi$
3	6	fx(x2-3y2)	$\frac{\sqrt{35}}{4\sqrt{2\pi}}\sin^3\theta(\cos^2\varphi - 3\sin^2\varphi)\cos\varphi$
3	7	fy(3x2-y2)	$\frac{\sqrt{35}}{4\sqrt{2\pi}}\sin^3\theta(3\cos^2\varphi-\sin^2\varphi)\sin\varphi$

Table 3.1: Angular functions  $\Theta_{lm_r}(\theta,\varphi)$  associated with particular values of l and  $m_r$  for  $l \geq 0$ .

l	$m_{ m r}$	Name	$\Theta_{lm_{ m r}}( heta,arphi)$
-1	1	sp-1	$\frac{1}{\sqrt{2}}$ s $+\frac{1}{\sqrt{2}}$ px
-1	2	sp-2	$\frac{1}{\sqrt{2}}$ s $-\frac{1}{\sqrt{2}}$ px
-2	1	sp2-1	$\frac{1}{\sqrt{3}}s - \frac{1}{\sqrt{6}}px + \frac{1}{\sqrt{2}}py$
-2	2	sp2-2	$\frac{1}{\sqrt{3}}$ s $-\frac{1}{\sqrt{6}}$ px $-\frac{1}{\sqrt{2}}$ py
-2	3	sp2-3	$\frac{1}{\sqrt{3}}$ s $+\frac{2}{\sqrt{6}}$ px
-3	1	sp3-1	$\frac{1}{2}(s + px + py + pz)$
-3	2	sp3-2	$\frac{1}{2}(\mathtt{s}+\mathtt{px}-\mathtt{py}-\mathtt{pz})$
-3	3	sp3-3	$\frac{1}{2}(s-px+py-pz)$
-3	4	sp3-4	$\frac{1}{2}(s - px - py + pz)$
-4	1	sp3d-1	$\frac{1}{\sqrt{3}}$ s $-\frac{1}{\sqrt{6}}$ px $+\frac{1}{\sqrt{2}}$ py
-4	2	sp3d-2	$\frac{1}{\sqrt{3}}$ s $-\frac{1}{\sqrt{6}}$ px $-\frac{1}{\sqrt{2}}$ py
-4	3	sp3d-3	$\frac{1}{\sqrt{3}}$ s $+\frac{2}{\sqrt{6}}$ px
-4	4	sp3d-4	$rac{1}{\sqrt{2}}$ pz $+rac{1}{\sqrt{2}}$ dz2
-4	5	sp3d-5	$-rac{1}{\sqrt{2}}$ pz $+rac{1}{\sqrt{2}}$ dz2
-5	1	sp3d2-1	$\frac{1}{\sqrt{6}}s - \frac{1}{\sqrt{2}}px - \frac{1}{\sqrt{12}}dz^2 + \frac{1}{2}dx^2y^2$
-5	2	sp3d2-2	$\frac{1}{\sqrt{6}}s + \frac{1}{\sqrt{2}}px - \frac{1}{\sqrt{12}}dz^2 + \frac{1}{2}dx^2y^2$
-5	3	sp3d2-3	$\frac{1}{\sqrt{6}}$ s $-\frac{1}{\sqrt{2}}$ py $-\frac{1}{\sqrt{12}}$ dz2 $-\frac{1}{2}$ dx2-y2
-5	4	sp3d2-4	$\frac{1}{\sqrt{6}}s + \frac{1}{\sqrt{2}}py - \frac{1}{\sqrt{12}}dz^2 - \frac{1}{2}dx^2y^2$
-5	5	sp3d2-5	$\frac{1}{\sqrt{6}}s - \frac{1}{\sqrt{2}}pz + \frac{1}{\sqrt{3}}dz2$
-5	6	sp3d2-6	$\frac{1}{\sqrt{6}}s + \frac{1}{\sqrt{2}}pz + \frac{1}{\sqrt{3}}dz2$

Table 3.2: Angular functions  $\Theta_{lm_{\rm r}}(\theta,\varphi)$  associated with particular values of l and  $m_{\rm r}$  for l<0, in terms of the orbitals defined in Table 3.1.

r	$R_{ m r}(r)$
1	$2\alpha^{3/2}\exp(-\alpha r)$
2	$\frac{1}{2\sqrt{2}}\alpha^{3/2}(2-\alpha r)\exp(-\alpha r/2)$
3	$\sqrt{\frac{4}{27}}\alpha^{3/2}(1 - 2\alpha r/3 + 2\alpha^2 r^2/27)\exp(-\alpha r/3)$

Table 3.3: One possible choice for the radial functions  $R_{\rm r}(r)$  associated with different values of r: the set of solutions to the radial part of the hydrogenic Schrödinger equation for l=0, i.e., the radial parts of the 1s, 2s, 3s... orbitals, where  $\alpha=Z/a={\tt zona}$ .

# Chapter 4

# Code Overview

wannier90 can operate in two modes:

- 1. Post-processing mode: read in the overlaps and projections from file as computed inside a first-principles code. We expect this to be the most common route to using wannier90, and is described in Ch. 5;
- 2. Library mode: as a set of library routines to be called from within a first-principles code that passes the overlaps and projections to the wannier90 library routines and in return gets the unitary transformation corresponding to MLWF. This route should be used if the MLWF are needed within the first-principles code, for example in post-LDA methods such as LDA+U or SIC, and is described in Ch. 6.




Figure 4.1: Schematic overview of the module structure of wannier90. Modules may only use data and subroutines from lower modules.

# Chapter 5

# wannier90 as a post-processing tool

This is a description of how to use wannier90 as a post-processing tool.

The code must be run twice. On the first pass either the logical keyword postproc\_setup must be set to .true. in the input file seedname.win or the code must be run with the command line option -pp. Running the code then generates the file seedname.nnkp which provides the information required to construct the  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  overlaps (Ref. [1], Eq. (25)) and  $A_{mn}^{(\mathbf{k})}$  (Ref. [1], Eq. (62); Ref. [2], Eq. (22)).

Once the overlaps and projection have been computed and written to files seedname.mmn and seedname.amn, respectively, set postproc\_setup to .false. and run the code. Output is written to the file seedname.wout.

# 5.1 seedname.nnkp file

OUTPUT, if postproc\_setup = .true.

The file seedname.nnkp provides the information needed to determine the required overlap elements  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  and projections  $A_{mn}^{(\mathbf{k})}$ . It is written automatically when the code is invoked with the -pp command-line option (or when postproc\_setup=.true. in seedname.win. There should be no need for the user to edit this file.

Much of the information in seedname.nnkp is arranged in blocks delimited by the strings begin block\_name...end block\_name, as described below.

#### 5.1.1 Keywords

The first line of the file is a user comment, e.g., the date and time:

File written on 12Feb2006 at 15:13:12

The only logical keyword is calc\_only\_A, eg,

calc\_only\_A : F

#### 5.1.2 Real\_lattice block

```
begin real_lattice
2.250000 0.000000 0.000000
0.000000 2.250000 0.000000
0.000000 0.000000 2.250000
end real_lattice
```

The real lattice vectors in units of Angstrom.

# 5.1.3 Recip\_lattice block

```
begin recip_lattice
2.792527 0.000000 0.000000
0.000000 2.792527 0.000000
0.000000 0.000000 2.792527
end recip_lattice
```

The reciprocal lattice vectors in units of inverse Angstrom.

# 5.1.4 Kpoints block

```
begin kpoints
8
0.00000 0.00000 0.00000
0.00000 0.50000 0.00000
.
.
.
0.50000 0.50000 0.50000
end kpoints
```

The first line in the block is the total number of k-points num\_kpts. The subsequent num\_kpts lines specify the k-points in crystallographic co-ordinates relative to the reciprocal lattice vectors.

# 5.1.5 Projections block

```
begin projections
  n_proj
  centre    l    mr    r
    z-axis    x-axis    zona
  centre    l    mr    r
```

```
z-axis x-axis zona
.
.
end projections
```

Notes:

n\_proj: integer; the number of projection centres, equal to the number of MLWF num\_wann.

centre: three real numbers; projection function centre in crystallographic co-ordinates relative to the direct lattice vectors.

1 mr r: three integers; l and  $m_r$  specify the angular part  $\Theta_{lm_r}(\theta,\varphi)$ , and r specifies the radial part  $R_r(r)$  of the projection function (see Tables 3.1, 3.2 and 3.3).

z-axis: three real numbers; default is 0.0 0.0 1.0; defines the axis from which the polar angle  $\theta$  in spherical polar coordinates is measured.

x-axis: three real numbers; must be orthogonal to z-axis; default is 1.0 0.0 0.0 or a vector perpendicular to z-axis if z-axis is given; defines the axis from with the azimuthal angle  $\varphi$  in spherical polar coordinates is measured.

zona: real number; the value of  $\frac{Z}{a}$  associated with the radial part of the atomic orbital. Units are in reciprocal Angstrom.

# 5.1.6 nnkpts block

```
begin nnkpts
    10
    1    2    0    0    0
    .
    .
end nnkpts
```

First line: nntot, the number of nearest neighbours belonging to each k-point of the Monkhorst-Pack mesh

Subsequent lines: nntot×num\_kpts lines, ie, nntot lines of data for each k-point of the mesh.

Each line of consists of 5 integers. The first is the k-point number nkp. The second to the fifth specify it's nearest neighbours k + b: the second integer points to the k-point that is the periodic image of the k + b that we want; the last three integers give the G-vector, in reciprocal lattice units, that brings the k-point specified by the second integer (which is in the first BZ) to the actual k + b that we need.

#### 5.1.7 exclude\_bands block

begin exclude\_bands

```
8
1
2
.
end exclude_bands
```

To exclude bands (independent of k-point) from the calculation of the overlap and projection matrices, for example to ignore shallow-core states. The first line is the number of states to exclude, the following lines give the states for be excluded.

# 5.1.8 An example of projections

As a concrete example: one wishes to have a set of four  $\mathrm{sp}^3$  projection orbitals on, say, a carbon atom at (0.5,0.5,0.5) in fractional co-ordinates relative to the direct lattice vectors. In this case  $\mathrm{seedname.win}$  will contain the following lines:

```
begin projections
C:l=-1
end projections
```

and seedname.nnkp, generated on the first pass of wannier90 (with postproc\_setup=T), will contain:

```
begin projections
  0.50000
             0.50000
                       0.50000
                                  -1 1
    0.000 0.000 1.000
                         1.000
                               0.000 0.000
                                              2.00
  0.50000
             0.50000
                       0.50000
                                  -1 2 1
                         1.000 0.000 0.000
    0.000 0.000 1.000
                                              2.00
  0.50000
            0.50000
                       0.50000
                                  -1 3 1
    0.000 0.000 1.000
                         1.000
                               0.000 0.000
                                              2.00
  0.50000
             0.50000
                       0.50000
                                  -1 4 1
                         1.000 0.000 0.000
    0.000 0.000 1.000
                                              2.00
end projections
```

where the first line tells us that in total four projections are specified, and the subsquent lines provide the projection centre, the angular and radial parts of the orbital (see Section 3.3 for definitions), the z and x axes, and the diffusivity and cut-off radius for the projection orbital.

PWSCF, or any other *ab initio* electronic structure code, then reads **seedname.nnkp** file, calculates the projections and writes them to **seedname.amn**.

# 5.2 seedname.mmn file

INPUT.

The file seedname.mmn contains the overlaps  $M_{mn}^{(\mathbf{k},\mathbf{b})}$ .

First line: a user comment, e.g., the date and time

Second line: 3 integers: num\_bands, num\_kpts, nntot

Then: num\_kpts × nntot blocks of data:

First line of each block: 5 integers. The first specifies the  $\mathbf{k}$  (i.e., gives the ordinal corresponding to its position in the list of k-points in seedname.win). The 2nd to 5th integers specify  $\mathbf{k} + \mathbf{b}$ . The 2nd integer, in particular, points to the k-point on the list that is a periodic image of  $\mathbf{k} + \mathbf{b}$ , and in particular is the image that is actually mentioned in the list. The last three integers specify the  $\mathbf{G}$  vector, in reciprocal lattice units, that brings the k-point specified by the second integer, and that thus lives inside the first BZ zone, to the actual  $\mathbf{k} + \mathbf{b}$  that we need.

Subsequent num\_bands × num\_bands lines of each block: two real numbers per line. These are the real and imaginary parts, respectively, of the actual scalar product  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  for  $m,n\in[1,\text{num\_bands}]$ . The order of these elements is such that the first index m is fastest.

# 5.3 seedname.amn file

INPUT.

The file seedname.amn contains the projection  $A_{mn}^{(\mathbf{k})}$ .

First line: a user comment, e.g., the date and time

Second line: 3 integers: num\_bands, num\_kpts, num\_wann

Subsequently num\_bands  $\times$  num\_wann  $\times$  num\_kpts lines: 3 integers and 2 real numbers on each line. The first two integers are the band indices m and n. The third integer specifies the k by giving the ordinal corresponding to its position in the list of k-points in seedname.win. The real numbers are the real and imaginary parts, respectively, of the actual  $A_{mn}^{(k)}$ .

# 5.4 seedname.eig file

INPUT.

Required if any of disentanglement, plot\_bands, plot\_fermi\_surface or hr\_plot are .true.

The file seedname.eig contains the Kohn-Sham eigenvalues  $\varepsilon_{n\mathbf{k}}$  (in eV) at each point in the Monkhorst-Pack mesh.

Each line consist of two integers and a real number. The first integer is the band index, the second integer gives the ordinal corresponding to the k-point in the list of k-points in seedname.win, and the real number is the eigenvalue.

E.g.,

1	1	-6.43858831271328
2	1	19.3977795287297
3	1	19.3977795287297
4	1	19.3977795287298

# 5.5 Interface with PWSCF

At the time of writing there are public, fully functioning, interfaces between wannier90 and PWSCF, ABINIT (www.abinit.org), SIESTA (www.icmab.es/siesta/) and FLEUR (www.fleur.de). Interfaces to other electronic structure codes are in progress, e.g., CASTEP (www.castep.org), WIEN2K (www.wien2k.at).

Here we describe the seamless interface between wannier90 and PWSCF, a plane-wave DFT code that comes as part of the quantum-espresso package (see www.quantum-espresso.org or www.pwscf.org). You will need to download and compile PWSCF (i.e., the pw.x code) and the post-processing interface pw2wannier90.x. Please refer to the documentation that comes with the quantum-espresso distribution for instructions.

- 1. Run 'scf'/'nscf' calculation(s) with pw
- 2. Run wannier90 with postproc\_setup = .true. to generate seedname.nnkp
- 3. Run pw2wannier90. First it reads an input file, e.g., seedname.pw2wan, which defines prefix and outdir for the underlying 'scf' calculation, as well as the name of the file seedname.nnkp, and does a consistency check between the direct and reciprocal lattice vectors read from seedname.nnkp and those defined in the files specified by prefix. pw2wannier90 generates seedname.mmn, seedname.amn and seedname.eig
- 4. Run wannier90 with postproc\_setup = .false. to disentangle bands (if required), localise MLWF, and use MLWF for plotting, bandstructures, Fermi surfaces etc.

Examples of how the interface with PWSCF works are given in the wannier90 Tutorial.

# 5.5.1 seedname.pw2wan

A number of keywords may be specified in the pw2wannier90 input file:

- outdir Location to write output files. Default is './'
- prefix Prefix for the PWSCF calculation. Default is ' '

wannier90: User Guide 47

- seedname Seedname for the wannier90 calculation. Default is 'wannier'
- spin\_component Spin component. Takes values 'up', 'down' or 'none' (default).
- wan\_mode Either 'standalone' (default) or 'library'
- write\_unk Set to .true. to write the periodic part of the Bloch functions for plotting in wannier90. Default is .false.
- reduce\_unk Set to .true. to reduce file-size (and resolution) of Bloch functions by a factor of 8. Default is .false. (only relevant if write\_unk=.true.)<sup>1</sup>
- wvfn\_formatted Set to .true. to write formatted wavefunctions. Default is .false. (only relevant if write\_unk=.true.)
- write\_amn Set to .false. if  $A_{mn}^{(\mathbf{k})}$  not required. Default is .true.
- write\_mmn Set to .false. if  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  not required. Default is .true.
- write\_spn Set to .true. to write out the matrix elements of  $S_z$  between Bloch states (non-collinear spin calculation only). Default is .false.
- write\_unkg Set to .true. to write the first few Fourier components of the periodic parts of the Bloch functions.

For examples of use, refer to the wannier90 Tutorial.

<sup>&</sup>lt;sup>1</sup>Note that there is a small bug with this feature in v3.2 (and subsequent patches) of quantum-espresso. Please use a later version (if available) or the CVS version of pw2wannier90.f90, which has been fixed.

# Chapter 6

# wannier90 as a library

This is a description of the interface between any external program and the wannier code. There are two subroutines: wannier\_setup and wannier\_run. Calling wannier\_setup will return information required to construct the  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  overlaps (Ref. [1], Eq. (25)) and  $A_{mn}^{(\mathbf{k})} = \langle \psi_{m\mathbf{k}} | g_n \rangle$  projections (Ref. [1], Eq. (62); Ref. [2], Eq. (22)). Once the overlaps and projection have been computed, calling wannier\_run activates the minimisation and plotting routines in wannier90.

# 6.1 Subroutines

#### 6.1.1 wannier\_setup

- character(len=\*), intent(in) :: seed\_name
  The seedname of the current calculation.
- integer, dimension(3), intent(in) :: mp\_grid The dimensions of the Monkhorst-Pack k-point grid.
- integer, intent(in) :: num\_kpts

  The number of k-points on the Monkhorst-Pack grid.
- real(kind=dp), dimension(3,3), intent(in) :: real\_lattice The lattice vectors in Cartesian co-ordinates in units of Angstrom.
- real(kind=dp), dimension(3,3), intent(in) :: recip\_lattice

  The reciprocal lattice vectors in Cartesian co-ordinates in units of reciprocal Angstrom.

- real(kind=dp), dimension(3,num\_kpts), intent(in) :: kpt\_latt

  The positions of the k-points in fractional co-ordinates relative to the reciprocal lattice vectors.
- integer, intent(in) :: num\_bands\_tot

  The total number of bands in the first-principles calculation (note: including semi-core states).
- integer, intent(in) :: num\_atoms

  The total number of atoms in the system.
- character(len=20), dimension(num\_atoms), intent(in) :: atom\_symbols The elemental symbols of the atoms.
- real(kind=dp), dimension(3,num\_atoms), intent(in) :: atoms\_cart The positions of the atoms in Cartesian co-ordinates in Angstrom.
- logical, intent(in) :: gamma\_only Set to .true. if the underlying electronic structure calculation has been performed with only  $\Gamma$ -point sampling and, hence, if the Bloch eigenstates that are used to construct  $A_{mn}^{(\mathbf{k})}$  and  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  are real.
- logical, intent(in) :: spinors
  Set to .true. if underlying electronic structure calculation has been performed with
  spinor wavefunctions. Note: the only effect this has is that wannier90 will expect half
  the usual number of projections.
- integer, intent(out) :: nntot
  The total number of nearest neighbours for each k-point.
- integer, dimension(num\_kpts,num\_nnmax), intent(out) :: nnlist The list of nearest neighbours for each k-point.
- integer, dimension(3, num\_kpts, num\_nnmax), intent(out) :: nncell The vector, in fractional reciprocal lattice co-ordinates, that brings the  $nn^{th}$  nearest neighbour of k-point nkp to its periodic image that is needed for computing the overlap  $M_{mn}^{(\mathbf{k},\mathbf{b})}$ .
- integer, intent(out) :: num\_bands

  The number of bands in the first-principles calculation used to form the overlap matricies
  (note: excluding eg. semi-core states).
- integer, intent(out) :: num\_wann
  The number of MLWF to be extracted.
- real(kind=dp), dimension(3,num\_bands\_tot), intent(out) :: proj\_site
  Projection function centre in crystallographic co-ordinates relative to the direct lattice
  vectors.
- integer, dimension(num\_bands\_tot), intent(out) :: proj\_1 l specifies the angular part  $\Theta_{lm_r}(\theta,\varphi)$  of the projection function (see Tables 3.1, 3.2 and 3.3).

- integer, dimension(num\_bands\_tot), intent(out) :: proj\_m  $m_{\rm r}$  specifies the angular part  $\Theta_{lm_{\rm r}}(\theta,\varphi)$ , of the projection function (see Tables 3.1, 3.2 and 3.3).
- integer, dimension(num\_bands\_tot), intent(out) :: proj\_radial r specifies the radial part  $R_r(r)$  of the projection function (see Tables 3.1, 3.2 and 3.3).
- real(kind=dp), dimension(3,num\_bands\_tot), intent(out) :: proj\_z Defines the axis from which the polar angle  $\theta$  in spherical polar coordinates is measured. Default is 0.0 0.0 1.0.
- real(kind=dp), dimension(3,num\_bands\_tot), intent(out) :: proj\_x Must be orthogonal to z-axis; default is 1.0 0.0 0.0 or a vector perpendicular to proj\_z if proj\_z is given; defines the axis from with the azimuthal angle  $\varphi$  in spherical polar coordinates is measured.
- real(kind=dp), dimension(num\_bands\_tot), intent(out) :: proj\_zona The value of  $\frac{Z}{a}$  associated with the radial part of the atomic orbital. Units are in reciprocal Angstrom.
- integer, dimension(num\_bands\_tot), intent(out) :: exclude\_bands Kpoints independant list of bands to exclude from the calculation of the MLWF (e.g., semi-core states).

#### Conditions:

```
\star num_kpts = mp_grid(1) \times mp_grid(2) \times mp_grid(3).
```

 $\star$  num\_nnmax = 12

This subroutine returns the information required to determine the required overlap elements  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  and projections  $A_{mn}^{(\mathbf{k})}$ , i.e., M\_matrix and A\_matrix, described in Section 6.1.2.

For the avoidance of doubt, real\_lattice(1,2) is the y-component of the first lattice vector  $\mathbf{A}_1$ , etc.

The list of nearest neighbours of a particular k-point nkp is given by nnlist(nkp,1:nntot).

Additionally, the parameter shell\_list may be specified in the wannier90 input file.

#### 6.1.2 wannier\_run

- character(len=\*), intent(in) :: seed\_name
  The seedname of the current calculation.
- integer, dimension(3), intent(in) :: mp\_grid The dimensions of the Monkhorst-Pack k-point grid.
- integer, intent(in) :: num\_kpts

  The number of k-points on the Monkhorst-Pack grid.
- real(kind=dp), dimension(3,3), intent(in) :: real\_lattice The lattice vectors in Cartesian co-ordinates in units of Angstrom.
- real(kind=dp), dimension(3,3), intent(in) :: recip\_lattice

  The reciprical lattice vectors in Cartesian co-ordinates in units of inverse Angstrom.
- real(kind=dp), dimension(3,num\_kpts), intent(in) :: kpt\_latt

  The positions of the k-points in fractional co-ordinates relative to the reciprocal lattice vectors.
- integer, intent(in) :: num\_bands

  The total number of bands to be processed.
- integer, intent(in) :: num\_wann
  The number of MLWF to be extracted.
- integer, intent(in) :: nntot

  The number of nearest neighbours for each k-point.
- integer, intent(in) :: num\_atoms
  The total number of atoms in the system.
- character(len=20), dimension(num\_atoms), intent(in) :: atom\_symbols The elemental symbols of the atoms.
- real(kind=dp), dimension(3,num\_atoms), intent(in) :: atoms\_cart The positions of the atoms in Cartesian co-ordinates in Angstrom.
- logical, intent(in) :: gamma\_only Set to .true. if the underlying electronic structure calculation has been performed with only  $\Gamma$ -point sampling and, hence, if the Bloch eigenstates that are used to construct  $A_{mn}^{(\mathbf{k})}$  and  $M_{mn}^{(\mathbf{k},\mathbf{b})}$  are real.
- complex(kind=dp), dimension(num\_bands,num\_bands,nntot,num\_kpts), intent(in) :: M\_matrix

  The matrices of overlaps between neighbouring periodic parts of the Bloch eigenstates at each k-point,  $M_{mn}^{((\mathbf{k},\mathbf{b}))}$  (Ref. [1], Eq. (25)).
- complex(kind=dp), dimension(num\_bands,num\_wann,num\_kpts), intent(in) :: A\_matrix

  The matrices describing the projection of num\_wann trial orbitals on num\_bands Bloch states at each k-point,  $A_{mn}^{(k)}$  (Ref. [1], Eq. (62); Ref. [2], Eq. (22)).

- real(kind=dp), dimension(num\_bands,num\_kpts), intent(in) :: eigenvalues The eigenvalues  $\varepsilon_{n\mathbf{k}}$  corresponding to the eigenstates, in eV.
- complex(kind=dp), dimension(num\_wann,num\_wann,num\_kpts),
   intent(out) :: U\_matrix
   The unitary matrices at each k-point (Ref. [1], Eq. (59))
- logical, dimension(num\_bands,num\_kpts), intent(out) :: lwindow
  The element lwindow(nband,nkpt) is .true. if the band nband lies within the outer
  energy window at kpoint nkpt.
- real(kind=dp), dimension(3,num\_wann), intent(out) :: wann\_centres
  The centres of the MLWF in Cartesian co-ordinates in Angstrom.
- real(kind=dp), dimension(num\_wann), intent(out) :: wann\_spreads The spread of each MLWF in  $\mathring{A}^2$ .
- real(kind=dp), dimension(3), intent(out) :: spread The values of  $\Omega$ ,  $\Omega_{\rm I}$  and  $\tilde{\Omega}$  (Ref. [1], Eq. (13)).

#### Conditions:

- ⋆ num\_wann ≤ num\_bands
- $\star \text{ num\_kpts} = \text{mp\_grid(1)} \times \text{mp\_grid(2)} \times \text{mp\_grid(3)}.$

If num\_bands = num\_wann then U\_matrix\_opt is the identity matrix and lwindow=.true.

For the avoidance of doubt, real\_lattice(1,2) is the y-component of the first lattice vector  $\mathbf{A}_1$ , etc.

```
\begin{array}{lcl} \texttt{M\_matrix(m,n,nkp,nn)} &=& \langle u_{m\mathbf{k}} | u_{n\mathbf{k}+\mathbf{b}} \rangle \\ \\ \texttt{A\_matrix(m,n,nkp)} &=& \langle \psi_{m\mathbf{k}} | g_n \rangle \\ \\ \texttt{eigenvalues(n,nkp)} &=& \varepsilon_{n\mathbf{k}} \end{array}
```

where

```
\mathbf{k} = \text{kpt\_latt(1:3,nkp)}

\mathbf{k} + \mathbf{b} = \text{kpt\_latt(1:3,nnlist(nkp,nn))} + \text{nncell(1:3,nkp,nn)}
```

and  $\{|g_n\rangle\}$  are a set of initial trial orbitals. These are typically atom or bond-centred Gaussians that are modulated by appropriate spherical harmonics.

Additional parameters should be specified in the wannier90 input file.

# Chapter 7

# Transport Calculations with wannier90

By setting transport = TRUE, wannier90 will calculate the quantum conductance and density of states of a one-dimensional system. The results will be written to files seedname\_qc.dat and seedname\_dos.dat, respectively.

The system for which transport properties are calculated is determined by the keyword transport\_mode.

# 7.1 transport\_mode = bulk

Quantum conductance and density of states are calculated for a perfectly periodic onedimensional conductor. If tran\_read\_ht = FALSE the transport properties are calculated using the Hamiltonian in the Wannier function basis of the system found by wannier90. Setting tran\_read\_ht = TRUE allows the user to provide an external Hamiltonian matrix file seedname\_htB.dat, from which the properties are found. See Section 2.9 for more details of the keywords required for such calculations.

# 7.2 transport\_mode = lcr

Quantum conductance and density of states are calculated for a system where semi-infinite, left and right leads are connected through a central conductor region. This is known as the *lcr* system. Details of the method is described in Ref. [7].

In wannier90 two options exist for performing such calculations:

• If tran\_read\_ht = TRUE the external Hamiltonian files seedname\_htL.dat, seedname\_htLc.dat, seedname\_htC.dat, seedname\_htC.dat, seedname\_htR.dat are read and used to compute the transport properties.

• If tran\_read\_ht = FALSE, then the transport calculation is performed automatically using the Wannier functions as a basis and the 2c2 geometry described in Section 7.3.

# 7.3 Automated lcr Transport Calculations: The 2c2 Geometry

Calculations using the 2c2 geometry provide a method to calculate the transport properties of an lcr system from a single wannier90 calculation. The Hamiltonian matrices which the five external files provide in the tran\_read\_ht = TRUE case are instead built from the Wannier function basis directly. As such, strict rules apply to the system geometry, which is shown in Figure 7.1. These rules are as follows:

- Left and right leads must be identical and periodic.
- Supercell must contain two principal layers (PLs) of lead on the left, a central conductor region and two principal layers of lead on the right.
- The conductor region must contain enough lead such that the disorder does not affect the principal layers of lead either side.
- A single **k**-point (Gamma) must be used.




Figure 7.1: Schematic illustration of the supercell required for 2c2 lcr calculations, showing where each of the Hamiltonian matrices are derived from. Four principal layers (PLs) are required plus the conductor region.

In order to build the Hamiltonians, Wannier functions are first sorted according to position and then type if a number of Wannier functions exist with a similar centre (eg. d-orbital type Wannier functions centred on a Cu atom). Next, consistent parities of Wannier function are enforced. To distingiush between different types of Wannier function and assertain relative parities, a signature of each Wannier function is computed. The signature is formed of 20 integrals which have different spatial dependence. They are given by:

$$I = \frac{1}{V} \int_{V} g(\mathbf{r}) w(\mathbf{r}) d\mathbf{r}$$
 (7.1)

where V is the volume of the cell,  $w(\mathbf{r})$  is the Wannier function and  $g(\mathbf{r})$  are the set of functions:

$$g(\mathbf{r}) = \left\{ 1, \sin\left(\frac{2\pi(x-x_c)}{L_x}\right), \sin\left(\frac{2\pi(y-y_c)}{L_y}\right), \sin\left(\frac{2\pi(z-z_c)}{L_z}\right), \sin\left(\frac{2\pi(x-x_c)}{L_x}\right) \sin\left(\frac{2\pi(y-y_c)}{L_y}\right), \\ \sin\left(\frac{2\pi(x-x_c)}{L_x}\right) \sin\left(\frac{2\pi(z-z_c)}{L_z}\right), \ldots \right\}$$

$$(7.2)$$

upto third order in powers of sines. Here, the supercell has dimension  $(L_x, L_y, L_z)$  and the Wannier function has centre  $\mathbf{r}_c = (x_c, y_c, z_c)$ . Each of these integrals may be written as linear combinations of the following sums:

$$S_n(\mathbf{G}) = e^{i\mathbf{G}.\mathbf{r}_c} \sum_m U_{mn} \tilde{u}_{m\Gamma}^*(\mathbf{G})$$
(7.3)

where n and m are the Wannier function and band indexes,  $\mathbf{G}$  is a G-vector,  $U_{mn}$  is the unitary matrix that transforms from the Bloch reopresentation of the system to the maximally-localised Wannier function basis and  $\tilde{u}_{m\Gamma}^*(\mathbf{G})$  are the conjugates of the Fourier transforms of the periodic parts of the Bloch states at the  $\Gamma$ -point. The complete set of  $\tilde{u}_{m\mathbf{k}}(\mathbf{G})$  are often outputted by plane-wave DFT codes. However, to calculate the 20 signature integrals, only 32 specific  $\tilde{u}_{m\mathbf{k}}(\mathbf{G})$  are required. These are found in an additional file (seedname.unkg) that should be provided by the interface between the DFT code and wannier90. A detailed description of this file may be found in Section 8.27.

Additionally, the following keywords are also required in the input file:

- tran\_num\_11: The number of Wannier functions in a principal layer.
- tran\_num\_cell\_ll: The number of unit cells in one principal layer of lead

A further parameter related to these calculations is tran\_group\_threshold.

Examples of how 2c2 calculations are preformed can be found in the wannier90 Tutorial.

# Chapter 8

# **Files**

# 8.1 seedname.win

INPUT. The master input file; contains the specification of the system and any parameters for the run. For a description of input parameters, see Chapter 2; for examples, see Section 10.1 and the wannier90 Tutorial.

#### 8.1.1 Units

The following are the dimensional quantities that are specified in the master input file:

- Direct lattice vectors
- Positions (of atomic or projection) centres in real space
- Energy windows
- Positions of k-points in reciprocal space
- Convergence thresholds for the minimisation of  $\Omega$
- zona (see Section 3.1)
- wannier\_plot\_cube: cut-off radius for plotting WF in Gaussian cube format

### Notes:

- The units (either ang (default) or bohr) in which the lattice vectors, atomic positions or projection centres are given can be set in the first line of the blocks unit\_cell\_cart, atoms\_cart and projections, respectively, in seedname.win.
- Energy is always in eV.
- Convergence thresholds are always in  $Å^2$

- Positions of k-points are always in crystallographic coordinates relative to the reciprocal lattice vectors.
- zona is always in reciprocal Angstrom (Å<sup>-1</sup>)
- The keyword length\_unit may be set to ang (default) or bohr, in order to set the units in which the quantities in the output file seedname.wout are written.
- wannier\_plot\_radius is in Angstrom

The reciprocal lattice vectors  $\{\mathbf{B}_1, \mathbf{B}_2, \mathbf{B}_3\}$  are defined in terms of the direct lattice vectors  $\{\mathbf{A}_1, \mathbf{A}_2, \mathbf{A}_3\}$  by the equation

$$\mathbf{B}_1 = \frac{2\pi}{\Omega} \mathbf{A}_2 \times \mathbf{A}_3 \quad \text{etc.}, \tag{8.1}$$

where the cell volume is  $V = \mathbf{A}_1 \cdot (\mathbf{A}_2 \times \mathbf{A}_3)$ .

# 8.2 seedname.mmn

INPUT. Written by the underlying electronic structure code. See Chapter 5 for details.

### 8.3 seedname.amn

INPUT. Written by the underlying electronic structure code. See Chapter 5 for details.

# 8.4 seedname.eig

INPUT. Written by the underlying electronic structure code. See Chapter 5 for details.

# 8.5 seedname.nnkp


OUTPUT. Written by wannier90 when postproc\_setup=.TRUE. (or, alternatively, when wannier90 is run with the -pp command-line option). See Chapter 5 for details.

#### 8.6 seedname.wout

OUTPUT. The master output file. Here we give a description of the main features of the output. The verbosity of the output is controlled by the input parameter iprint. The higher the value, the more detail is given in the output file. The default value is 1, which prints minimal information.

#### 8.6.1 Header

The header provides some basic information about wannier90, the authors, and the execution time of the current run.



# 8.6.2 System information

This part of the output file presents information that wannier90 has read or inferred from the master input file seedname.win. This includes real and reciprocal lattice vectors, atomic positions, k-points, parameters for job control, disentanglement, localisation and plotting.

SYSTEM

----

	Lattice	Vectors (Ar	ng)
a_1	3.938486	0.000000	0.000000
a_2	0.000000	3.938486	0.000000
a_3	0.000000	0.000000	3.938486
Unit	Cell Volume:	61.0925	51 (Ang^3)
	Reciprocal-Spa	ace Vectors	(Ang^-1)
b_1	1.595330	0.000000	0.000000
b_2	0.000000	1.595330	0.000000
b 3	0.000000	0.000000	1.595330

	ite	Fractional Coordinate					n Coordina	O	 
	1		0.00000	0.00000			0.00000	0.00000	I
Ti	1	0.50000	0.50000	0.50000	- 1	1.96924	1.96924	1.96924	
					•				
<b>.</b>					•				

K-POINT GRID

-----

Grid size =  $4 \times 4 \times 4$  Total points = 64

*-	MAIN			*
	Number of Wannier Functions	:	9	1
	Number of input Bloch states	:	9	
	Output verbosity (1=low, 5=high)	:	1	
	Length Unit	:	Ang	- 1
	Post-processing setup (write *.nnkp)	:	F	- 1

•

# 8.6.3 Nearest-neighbour k-points

This part of the output files provides information on the b-vectors and weights chosen to satisfy the condition of Eq. 2.1.

\*-----\*

	Shell	Dist	tance (Ang	^-1)	Multip	olicity
	 1		0.398833			6
	2		0.564034			12
			•			
The b-	-vectors are cho	sen automa	atically			
			1			
THE TO	ollowing shells	are usea.	-			
	ollowing shells					
			# Nearest	 -Neighbours		

# 8.6.4 Disentanglement

Then (if required) comes the part where  $\Omega_{\rm I}$  is minimised to disentangle the optimally-connected subspace of states for the localisation procedure in the next step.

First, a summary of the energy windows that are being used is given:

*		DISEN	TANG	LE		 *
		Energy	Wind	dows		 +
	Outer:	2.81739	to	38.00000	(eV)	
	Inner:	2.81739	to	13.00000	(eV)	
+						 +

Then, each step of the iterative minimisation of  $\Omega_{\rm I}$  is reported.

Extraction	of	optimally-connected	subspace

+-						+< DIS
	Iter	Omega_I(i-1)	Omega_I(i)	Delta (frac.)	Time	< DIS
+-						+< DIS
	1	3.82493590	3.66268867	4.430E-02	0.36	< DIS
	2	3.66268867	3.66268867	6.911E-15	0.37	< DIS

.

```
<<< Delta < 1.000E-10 over 3 iterations >>>
<<< Disentanglement convergence criteria satisfied >>>
```

Final Omega\_I 3.66268867 (Ang^2)

+-----

The first column gives the iteration number. For a description of the minimisation procedure and expressions for  $\Omega_{\rm I}^{(i)}$ , see the original paper [2]. The procedure is considered to be converged when the fractional difference between  $\Omega_{\rm I}^{(i)}$  and  $\Omega_{\rm I}^{(i-1)}$  is less than dis\_conv\_tol over dis\_conv\_window iterations. The final column gives a running account of the wall time (in seconds) so far. Note that at the end of each line of output, there are the characters "<-- DIS". This enables fast searching of the output using, for example, the Unix command grep:

my\_shell> grep DIS wannier.wout | less

#### 8.6.5 Wannierisation

The next part of the input file provides information on the minimisation of  $\widetilde{\Omega}$ . At each iteration, the centre and spread of each WF is reported.

```
*----*
+-----+<-- CONV
| Iter Delta Spread RMS Gradient Spread (Ang^2)
                                        Time |<-- CONV
Initial State
 WF centre and spread 1 ( 0.000000, 1.969243, 1.969243 ) 1.52435832
 WF centre and spread 2 ( 0.000000, 1.969243, 1.969243 ) 1.16120620
      0.29 <-- CONV
    Cycle: 1
 WF centre and spread 1 (0.000000, 1.969243, 1.969243) 1.52414024
 WF centre and spread 2 ( 0.000000, 1.969243, 1.969243)
                                           1.16059775
 Sum of centres and spreads (11.815458, 11.815458, 11.815458) 12.62663472
      -0.313E-02
                0.0697660962 12.6266347170
                                       0.34 <-- CONV
     O_D= 0.0000000 O_OD= 0.1460380 O_TOT= 12.6266347 <-- SPRD
Delta: O_D= -0.4530841E-18 O_OD= -0.3133809E-02 O_TOT= -0.3133809E-02 <-- DLTA
```

```
Cycle:
WF centre and spread
                  1 ( 0.000000, 1.969243, 1.969243 )
                                                   1.52414866
                   2 ( 0.000000, 1.969243, 1.969243 )
WF centre and spread
                                                    1.16052405
 Sum of centres and spreads (11.815458, 11.815458, 11.815458) 12.62646411
                   -0.171E-03
     Delta: O_D= -0.2847260E-18 O_OD= -0.1706115E-03 O_TOT= -0.1706115E-03 <-- DLTA
Final State
WF centre and spread 1 ( 0.000000, 1.969243, 1.969243) 1.52416618
WF centre and spread 2 ( 0.000000, 1.969243, 1.969243 ) 1.16048545
Sum of centres and spreads (11.815458, 11.815458, 11.815458) 12.62645344
                       Omega I
                                 = 12.480596753
      Spreads (Ang^2)
     _____
                       Omega D
                                    0.00000000
                                =
                       Omega OD
                                    0.145856689
                                =
  Final Spread (Ang^2)
                       Omega Total = 12.626453441
```

It looks quite complicated, but things look more simple if one uses grep:

my\_shell> grep CONV wannier.wout

gives

+	Iter	Delta Spread	RMS Gradient	Spread (Ang^2)		- CONV
•	0 1	0.126E+02 -0.313E-02	0.000000000 0.0697660962	12.6297685260 12.6266347170		- CONV
	50	0.000E+00	0.000000694	12.6264534413	2.14 <	- CONV

The first column is the iteration number, the second is the change in  $\Omega$  from the previous iteration, the third is the root-mean-squared gradient of  $\Omega$  with respect to variations in the unitary matrices  $\mathbf{U^{(k)}}$ , and the last is the time taken (in seconds). Depending on the input parameters used, the procedure either runs for num\_iter iterations, or a convergence criterion is applied on  $\Omega$ . See Section 2.8 for details.

Similarly, the command

my\_shell> grep SPRD wannier.wout


gives

O_D=	0.0000000	0.1491718	12.6297685 < SPRD 12.6266347 < SPRD
		•	
O D=	0.0000000 D DD=	0.1458567 O TOT=	12.6264534 < SPRD

which, for each iteration, reports the value of the diagonal and off-diagonal parts of the non-gauge-invariant spread, as well as the total spread, respectively. Recall from Section 1.1 that  $\Omega = \Omega_{\rm I} + \Omega_{\rm D} + \Omega_{\rm OD}$ .

# 8.6.6 Plotting

After WF have been localised, wannier90 enters its plotting routines (if required). For example, if you have specified an interpolated bandstucture:



Calculating interpolated band-structure

# 8.6.7 Summary timings

At the very end of the run, a summary of the time taken for various parts of the calculation is given. The level of detail is controlled by the timing\_level input parameter (set to 1 by default).

*======================================		=====		=======*
I	TIMING INFORMATION			1
*===========				=======*
Tag			Ncalls	Time (s)
kmesh: get		:	1	0.212
overlap: read		:	1	0.060
wann: main		:	1	1.860
plot: main		:	1	0.168
*				*

All done: wannier90 exiting

# 8.7 seedname.chk

INPUT/OUTPUT. Information required to restart the calculation or enter the plotting phase. If we have used disentanglement this file also contains the rectangular matrices  $\mathbf{U}^{\mathrm{dis}(\mathbf{k})}$ .

#### 8.8 seedname.r2mn

OUTPUT. Written if write\_r2mn = true. The matrix elements  $\langle m|r^2|n\rangle$  (where m and n refer to MLWF)

# 8.9 seedname\_band.dat

OUTPUT. Written if bands\_plot=.TRUE.; The raw data for the interpolated band structure.

# 8.10 seedname\_band.gnu

OUTPUT. Written if bands\_plot=.TRUE. and bands\_plot\_format=gnuplot; A gnuplot script to plot the interpolated band structure.

# 8.11 seedname\_band.agr

OUTPUT. Written if bands\_plot=.TRUE. and bands\_plot\_format=xmgrace; A grace file to plot the interpolated band structure.

# 8.12 seedname\_band.kpt

OUTPUT. Written if bands\_plot=.TRUE.; The k-points used for the interpolated band structure, in units of the reciprocal lattice vectors. This file can be used to generate a comparison band structure from a first-principles code.

#### 8.13 seedname.bxsf

OUTPUT. Written if fermi\_surface\_plot=.TRUE.; A Fermi surface plot file suitable for plotting with XCrySDen.

# 8.14 seedname\_w.xsf

OUTPUT. Written if wannier\_plot=.TRUE. and wannier\_plot\_format=xcrysden. Contains the w<sup>th</sup> WF in real space in a format suitable for plotting with XCrySDen or VMD, for example.

# 8.15 seedname\_w.cube

OUTPUT. Written if wannier\_plot=.TRUE. and wannier\_plot\_format=cube. Contains the w<sup>th</sup> WF in real space in Gaussian cube format, suitable for plotting in XCrySDen, VMD, gopenmol etc.

# 8.16 UNKp.s

INPUT. Read if wannier\_plot=.TRUE. and used to plot the MLWF. Read if transport\_mode=lcr and tran\_read\_ht=.FALSE. for use in automated lcr transport calculations.

The periodic part of the Bloch states represented on a regular real space grid, indexed by k-point p (from 1 to num\_kpts) and spin s ('1' for 'up', '2' for 'down').

The name of the wavefunction file is assumed to have the form:

```
write(wfnname,200) p,spin
200 format ('UNK',i5.5,'.',i1)
```

The first line of each file should contain 5 integers: the number of grid points in each direction (ngx, ngy and ngz), the k-point number ik and the total number of bands num\_band in the file. The full file will be read by wannier90 as:

```
read(file_unit) ngx,ngy,ngz,ik,nbnd
do loop_b=1,num_bands
  read(file_unit) (r_wvfn(nx,loop_b),nx=1,ngx*ngy*ngz)
end do
```

The file can be in formatted or unformatted style, this is controlled by the logical keyword wvfn\_formatted.

# 8.17 seedname\_centres.xyz

OUTPUT. Written if write\_xyz=.TRUE.; xyz format atomic structure file suitable for viewing with your favourite visualiser (jmol, gopenmol, vmd, etc.).

# 8.18 seedname\_hr.dat

OUTPUT. Written if hr\_plot=.TRUE.. The first line gives the date and time at which the file was created. The second line states the number of Wannier functions num\_wann. The third line gives the number of Wigner-Seitz grid-points nrpts. The next block of nrpts integers gives the degeneracy of each Wigner-Seitz grid point, with 15 entries per line. Finally, the remaining num\_wann<sup>2</sup> × nrpts lines each contain, respectively, the components of the vector  $\mathbf{R}$  in terms of the lattice vectors  $\{\mathbf{A}_i\}$ , the indices m and n, and the real and imaginary parts of the Hamiltonian matrix element  $H_{mn}^{(\mathbf{R})}$  in the WF basis, e.g.,

```
Created on 24May2007 at 23:32:09
        20
        17
            2
   4
        1
                             1
                                   1
                                               1
        2
   1
   0
        0
           -2
                            -0.001013
                                           0.000000
                  1
                        1
                                           0.000000
   0
        0
           -2
                  2
                        1
                             0.000270
   0
        0
           -2
                  3
                            -0.000055
                                           0.000000
                        1
   0
        0
           -2
                  4
                        1
                             0.000093
                                           0.000000
           -2
                        1
                            -0.000055
                                           0.000000
```

# 8.19 seedname\_qc.dat

OUTPUT. Written if transport = .TRUE.. The first line gives the date and time at which the file was created. In the subsequent lines, the energy value in units of eV is written in the left column, and the quantum conductance in units of  $\frac{2e^2}{h}$  ( $\frac{e^2}{h}$  for a spin-polarized system) is written in the right column.

```
## written on 14Dec2007 at 11:30:17
-3.000000 8.999999
-2.990000 8.999999
-2.980000 8.999999
-2.970000 8.999999
.
```

#### 8.20 seedname\_dos.dat

OUTPUT. Written if transport = .TRUE.. The first line gives the date and time at which the file was created. In the subsequent lines, the energy value in units of eV is written in the left column, and the density of states in an arbitrary unit is written in the right column.

```
## written on 14Dec2007 at 11:30:17
-3.000000 6.801199
-2.990000 6.717692
-2.980000 6.640828
-2.970000 6.569910
.
```

# 8.21 seedname\_htB.dat

INPUT/OUTPUT. Read if transport\_mode = bulk and tran\_read\_ht = .TRUE.. Written if tran\_write\_ht = .TRUE.. The first line gives the date and time at which the file was created. The second line gives tran\_num\_bb. The subsequent lines contain tran\_num\_bb $\times$ tran\_num\_bb  $H_{mn}$  matrix, where the indices m and n span all tran\_num\_bb WFs located at  $0^{th}$  principal layer. Then tran\_num\_bb is recorded again in the new line followed by  $H_{mn}$ , where  $m^{th}$  WF is at  $0^{th}$  principal layer and  $n^{th}$  at  $1^{st}$  principal layer. The  $H_{mn}$  matrix is written in such a way that m is the fastest varying index.

```
written on 14Dec2007 at 11:30:17
  150
  -1.737841
               -2.941054
                             0.052673
                                        -0.032926
                                                      0.010738
                                                                  -0.009515
   0.011737
               -0.016325
                            0.051863
                                        -0.170897
                                                     -2.170467
                                                                   0.202254
  -0.057064
               -0.571967
                           -0.691431
                                         0.015155
                                                     -0.007859
                                                                   0.000474
  -0.000107
               -0.001141
                           -0.002126
                                         0.019188
                                                     -0.686423
                                                                 -10.379876
  150
                            0.000000
   0.000000
                0.000000
                                         0.000000
                                                      0.000000
                                                                   0.000000
   0.000000
                0.000000
                             0.000000
                                         0.000000
                                                      0.000000
                                                                   0.000000
   0.000000
                0.000000
                            0.000000
                                         0.000000
                                                      0.000000
                                                                  -0.001576
   0.000255
               -0.000143
                           -0.001264
                                                      0.00000
                                                                   0.000000
                                         0.002278
```

### 8.22 seedname\_htL.dat

INPUT. Read if transport\_mode = lcr and tran\_read\_ht = .TRUE.. The file must be written in the same way as in seedname\_htB.dat. The first line can be any comment you want. The second line gives tran\_num\_ll. tran\_num\_ll in seedname\_htL.dat must be equal to that in seedname.win. The code will stop otherwise.

Created by a WANNIER user 105								
0.316879	0.000000	-2.762434	0.048956	0.000000	-0.016639			
0.000000	0.000000	0.000000	0.000000	0.000000	-2.809405			
•								
0.000000	0.078188	0.000000	0.000000	-2.086453	-0.001535			
0.007878	-0.545485	-10.525435						
105								
0.000000	0.000000	0.000315	-0.000294	0.000000	0.000085			
0.000000	0.000000	0.000000	0.000000	0.000000	0.000021			
•								
0.000000	0.000000	0.000000	0.000000	0.000000	0.000000			
0.00000	0.000000	0.000000						

#### 8.23 seedname\_htR.dat

INPUT. Read if transport\_mode = lcr and tran\_read\_ht = .TRUE. and tran\_use\_same\_lead = .FALSE.. The file must be written in the same way as in seedname\_htL.dat. tran\_num\_rr in seedname\_htR.dat must be equal to that in seedname.win.

### 8.24 seedname htC.dat

INPUT. Read if transport\_mode = 1cr and tran\_read\_ht = .TRUE.. The first line can be any comment you want. The second line gives tran\_num\_cc. The subsequent lines contain tran\_num\_cc×tran\_num\_cc  $H_{mn}$  matrix, where the indices m and n span all tran\_num\_cc WFs inside the central conductor region. tran\_num\_cc in seedname\_htC.dat must be equal to that in seedname.win.

# Created by a WANNIER user 99 -10.499455 -0.541232 0.007684 -0.001624 -2.067078 -0.412188 0.003217 0.076965 0.000522 -0.000414 0.000419 -2.122184

# 8.25 seedname\_htLC.dat

INPUT. Read if transport\_mode = lcr and tran\_read\_ht = .TRUE.. The first line can be any comment you want. The second line gives tran\_num\_ll and tran\_num\_lc in the given order. The subsequent lines contain tran\_num\_ll×tran\_num\_lc  $H_{mn}$  matrix. The index m spans tran\_num\_ll WFs in the surface principal layer of semi-infinite left lead which is in contact with the conductor region. The index n spans tran\_num\_lc WFs in the conductor region which have a non-negligible interaction with the WFs in the semi-infinite left lead. Note that tran\_num\_lc can be different from tran\_num\_cc.

```
Created by a WANNIER user
  105
   0.000000
                0.000000
                            0.000000
                                         0.000000
                                                      0.000000
                                                                   0.000000
   0.000000
                0.000000
                            0.000000
                                         0.000000
                                                      0.000000
                                                                   0.000000
  -0.000003
                0.000009
                            0.000290
                                         0.000001
                                                     -0.000007
                                                                  -0.000008
   0.000053
               -0.000077
                           -0.000069
```

# 8.26 seedname\_htCR.dat

INPUT. Read if transport\_mode = lcr and tran\_read\_ht = .TRUE.. The first line can be any comment you want. The second line gives tran\_num\_cr and tran\_num\_rr in the given order. The subsequent lines contain tran\_num\_cr×tran\_num\_rr  $H_{mn}$  matrix. The index m spans tran\_num\_cr WFs in the conductor region which have a non-negligible interaction with the WFs in the semi-infinite right lead. The index n spans tran\_num\_rr WFs in the surface principal layer of semi-infinite right lead which is in contact with the conductor region. Note that tran\_num\_cr can be different from tran\_num\_cc.

```
Created by a WANNIER user
99 105
-0.000180 0.000023 0.000133 -0.000001 0.000194 0.000008
-0.000879 -0.000028 0.000672 -0.000257 -0.000102 -0.000029
.
.
```

0.000000	0.000000	0.000000	0.00000	0.000000	0.000000
0.000000	0.000000	0.000000			

# 8.27 seedname.unkg

INPUT. Read if transport\_mode = 1cr and tran\_read\_ht = .FALSE.. The first line is the number of G-vectors at which the  $\tilde{u}_{m\mathbf{k}}(\mathbf{G})$  are subsequently printed. This number should always be 32 since 32 specific  $\tilde{u}_{m\mathbf{k}}$  are required. The following lines contain the following in this order: The band index m, a counter on the number of G-vectors, the integer co-efficient of the G-vector components a, b, c (where  $\mathbf{G} = a\mathbf{b}_1 + b\mathbf{b}_2 + c\mathbf{b}_3$ ), then the real and imaginary parts of the corresponding  $\tilde{u}_{m\mathbf{k}}(\mathbf{G})$  at the  $\Gamma$ -point. We note that the ordering in which the G-vectors and  $\tilde{u}_{m\mathbf{k}}(\mathbf{G})$  are printed is not important, but the specific G-vectors are critical. The following example displays for a single band, the complete set of  $\tilde{u}_{m\mathbf{k}}(\mathbf{G})$  that are required. Note the G-vectors (a, b, c) needed.

	32					
1	1	0	0	0	0.4023306	0.0000000
1	2	0	0	1	-0.0000325	0.0000000
1	3	0	1	0	-0.3043665	0.0000000
1	4	1	0	0	-0.3043665	0.0000000
1	5	2	0	0	0.1447143	0.0000000
1	6	1	-1	0	0.2345179	0.0000000
1	7	1	1	0	0.2345179	0.0000000
1	8	1	0	-1	0.0000246	0.0000000
1	9	1	0	1	0.0000246	0.0000000
1	10	0	2	0	0.1447143	0.0000000
1	11	0	1	-1	0.0000246	0.0000000
1	12	0	1	1	0.0000246	0.0000000
1	13	0	0	2	0.0000338	0.0000000
1	14	3	0	0	-0.0482918	0.0000000
1	15	2	-1	0	-0.1152414	0.0000000
1	16	2	1	0	-0.1152414	0.0000000
1	17	2	0	-1	-0.0000117	0.0000000
1	18	2	0	1	-0.0000117	0.0000000
1	19	1	-2	0	-0.1152414	0.0000000
1	20	1	2	0	-0.1152414	0.0000000
1	21	1	-1	-1	-0.0000190	0.0000000
1	22	1	-1	1	-0.0000190	0.0000000
1	23	1	1	-1	-0.0000190	0.0000000
1	24	1	1	1	-0.0000190	0.0000000
1	25	1	0	-2	-0.0000257	0.0000000
1	26	1	0	2	-0.0000257	0.0000000
1	27	0	3	0	-0.0482918	0.0000000
1	28	0	2	-1	-0.0000117	0.0000000
1	29	0	2	1	-0.0000117	0.0000000

 1
 30
 0
 1
 -2
 -0.0000257
 0.0000000

 1
 31
 0
 1
 2
 -0.0000257
 0.0000000

 1
 32
 0
 0
 3
 0.0000187
 0.0000000

 2
 1
 0
 0
 -0.0000461
 0.0000000

.

# Chapter 9

# Frequently Asked Questions

# 9.1 General Questions

#### 9.1.1 What is wannier 90?

wannier90 is a computer package, written in Fortran90, for obtaining maximally-localised Wannier functions, using them to calculate bandstructures, Fermi surfaces, dielectric properties, sparse Hamiltonians and many things besides.

# 9.1.2 Where can I get wannier90?

The most recent release of wannier90 is always available on our website www.wannier.org.

# 9.1.3 Where can I get the most recent information about wannier90?

The latest news about wannier90 can be followed on our website www.wannier.org.

#### 9.1.4 Is wannier90 free?

Yes! wannier90 is available for use free-of-charge under the GNU General Public Licence. See the file LICENCE that comes with the wannier90 distribution or the GNU hopepage at www.gnu.org.

# 9.1.5 Who wrote wannier90?

wannier90 is written by Arash A. Mostofi (Imperial College London), Jonathan. R. Yates (University of Oxford) and Young-Su Lee (Korea Institute of Science and Technology). wannier90 is based on algorithms written in 1996-7 by Nicola Marzari (Massachusetts Institute of Technology) and David Vanderbilt (Rutgers University), and in 2000-1 by Ivo Souza (Universidad

del Pais Vasco), Nicola Marzari and David Vanderbilt.

The interface to PWSCF was written by Stefano de Gironcoli (SISSA, Trieste).

# 9.2 Getting Help

#### 9.2.1 Is there a Tutorial available for wannier 90?

Yes! The examples directory of the wannier90 distribution contains input files for a number of tutorial calculations. The doc directory contains the accompanying tutorial handout.

# 9.2.2 Where do I get support for wannier90?

There are a number of options:

- 1. The wannier90 User Guide, available in the doc directory of the distribution, and from the webpage (www.wannier.org/user\_guide.html)
- 2. The wannier90 webpage for the most recent announcements (www.wannier.org)
- 3. The wannier90 mailing list (see www.wannier.org/forum.html)

#### 9.2.3 Is there a mailing list for wannier90?

Yes! You need to register: go to www.wannier.org/forum.html and follow the instructions.

# 9.3 Providing Help: Finding and Reporting Bugs

# 9.3.1 I think I found a bug. How do I report it?

- Check and double-check. Make sure it's a bug.
- Check that it is a bug in wannier90 and not a bug in the software interfaced to wannier90.
- Check that you're using the latest version of wannier90.
- Send us an email. Make sure to describe the problem and to attach all input and output files relating to the problem that you have found.

# 9.3.2 I have got an idea! How do I report a wish?

We're always happy to listen to suggestions. Email your idea to the wannier90 developers.

# 9.3.3 I want to help! How can I contribute to wannier90?

Great! There's always plenty of functionality to add. Email us to let us know about the functionality you'd like to contribute.

# 9.3.4 I like wannier90! Should I donate anything to its authors?

Our Swiss bank account number is... just kidding! There is no need to donate anything, please just cite our paper in any publications that arise from your use of wannier90:

[ref] A. A. Mostofi, J. R. Yates, Y.-S. Lee, I. Souza, D. Vanderbilt and N. Marzari, wannier90: A Tool for Obtaining Maximally-Localised Wannier Functions, *Comput. Phys. Commun.*, accepted (2007); http://arxiv.org/abs/0708.0650.

#### 9.4 Installation

#### 9.4.1 How do I install wannier 90?

Follow the instructions in the file README.install in the main directory of the wannier90 distribution.

### 9.4.2 Are there wannier90 binaries available?

Not at present.

# 9.4.3 Is there anything else I need?

Yes. wannier90 works on top of an electronic structure calculation.

At the time of writing there are public, fully functioning, interfaces between wannier90 and PWSCF, ABINIT (www.abinit.org), SIESTA (www.icmab.es/siesta/) and FLEUR (www.fleur.de). Interfaces to other electronic structure codes are in progress, e.g., CASTEP (www.castep.org), WIEN2K (www.wien2k.at).

To use wannier90 in combination with PWSCF code (a plane-wave, pseudopotential, density-functional theory code, which is part of the quantum-espresso package) you will need to download PWSCF from the webpage www.quantum-espresso.org or www.pwscf.org. Then compile PWSCF and the wannier90 interface program pw2wannier90. For instructions, please refer to the documentation that comes with the quantum-espresso distribution.

For examples of how to use PWSCF and wannier90 in conjunction with each other, see the wannier90 Tutorial.

# Chapter 10

# Sample Input Files

# 10.1 Master input file: seedname.win

```
: 4
num_wann
                : 4 4 4
mp_grid
          : 100
num_iter
postproc_setup : true
begin unit_cell_cart
ang
-1.61 0.00 1.61
0.00 1.61 1.61
-1.61 1.61 0.00
end unit_cell_cart
begin atoms_frac
C -0.125 -0.125 -0.125
    0.125 0.125 0.125
end atoms_frac
bands_plot : true
bands_num_points : 100
bands_plot_format : gnuplot
begin kpoint_path
L 0.50000 0.50000 0.50000 G 0.00000 0.00000 0.00000
G 0.00000 0.00000 0.00000 X 0.50000 0.00000 0.50000
X 0.50000 0.00000 0.50000 K 0.62500 0.25000 0.62500
end kpoint_path
begin projections
C:1=0,1=1
```

```
end projections
begin kpoints
0.00 0.00 0.00
0.00 0.00 0.25
0.00 0.50 0.50
0.75 0.75 0.50
0.75 0.75 0.75
end kpoints
10.2
```

# seedname.nnkp

Running wannier90 on the above input file would generate the following nnkp file:

```
File written on 9Feb2006 at 15:13: 9
calc_only_A : F
begin real_lattice
 -1.612340 0.000000 1.612340
  0.000000 1.612340 1.612340
 -1.612340 1.612340 0.000000
end real_lattice
begin recip_lattice
 -1.951300 -1.951300 1.951300
  1.951300 1.951300 1.951300
 -1.951300 1.951300 -1.951300
end recip_lattice
begin kpoints
    64
 0.00000 0.00000
                    0.00000
 0.00000 0.25000 0.00000
 0.00000 0.50000 0.00000
 0.00000 0.75000 0.00000
 0.25000 0.00000
                    0.00000
 0.50000 0.75000 0.75000
```

```
0.75000
           0.00000
                     0.75000
           0.25000
 0.75000
                     0.75000
           0.50000
 0.75000
                     0.75000
 0.75000
           0.75000
                     0.75000
end kpoints
begin projections
  8
 -0.12500
            -0.12500
                       -0.12500
    0.000 0.000 1.000
                          1.000 0.000 0.000
                                                2.00
            -0.12500
                       -0.12500
 -0.12500
                                    1 1 1
    0.000 0.000 1.000
                          1.000
                                0.000 0.000
                                                2.00
 -0.12500
            -0.12500
                       -0.12500
                                    1 2 1
    0.000
          0.000 1.000
                          1.000
                                0.000 0.000
                                                2.00
 -0.12500
            -0.12500
                       -0.12500
                                    1
                                       3 1
    0.000 0.000 1.000
                          1.000
                                0.000 0.000
                                                2.00
  0.12500
             0.12500
                        0.12500
                                    0
                                       1 1
                                0.000 0.000
    0.000 0.000 1.000
                          1.000
                                                2.00
  0.12500
             0.12500
                        0.12500
                                    1
                                       1
                                          1
    0.000 0.000 1.000
                          1.000
                                0.000 0.000
                                                2.00
  0.12500
             0.12500
                        0.12500
                                    1
                                       2 1
          0.000 1.000
                                 0.000 0.000
    0.000
                          1.000
                                                2.00
```

0.12500

1 3 1

2.00

1.000 0.000 0.000

end projections

0.12500

# begin nnkpts

0.12500

0.000 0.000 1.000

64	1	1	1	1
64	16	0	0	1
64	43	0	0	0
64	48	0	0	0
64	52	1	0	0
64	60	0	0	0
64	61	0	1	0
64	63	0	0	0
end	nnkpts			

begin exclude\_bands

end exclude\_bands

# Bibliography

- [1] N. Marzari and D. Vanderbilt, Maximally Localized Generalized Wannier Functions for Composite Energy Bands, *Phys. Rev. B* **56**, 12847 (1997).
- [2] I. Souza, N. Marzari and D. Vanderbilt, Maximally Localized Wannier Functions for Entangled Energy Bands, *Phys. Rev. B* **65**, 035109 (2001).
- [3] Gygi, F., Fattebert, J.-L., and Schwegler, E., Computation of Maximally Localized Wannier Functions using a simultaneous diagonalization algorithm, *Comp. Phys. Commun.* **155**, 1 (2003).
- [4] A. A. Mostofi, J. R. Yates, Y.-S. Lee, I. Souza, D. Vanderbilt and N. Marzari, wannier90: A Tool for Obtaining Maximally-Localized Wannier Functions, *Comput. Phys. Commun.*, 178, 685 (2008); http://arxiv.org/abs/0708.0650.
- [5] D. Vanderbilt, Soft Self-Consistent Pseudopotentials in a Generalized Eigenvalue Formalism, *Phys. Rev. B* **41** (11), 7892 (1990).
- [6] M. Posternak, A. Baldereschi, S. Massidda and N. Marzari, Maximally Localized Wannier Functions in Antiferromagnetic MnO within the FLAPW Formalism, *Phys. Rev. B* 65, 184422 (2002).
- [7] M. Buongiorno Nardelli, Electronic Transport in Extended Systems: Application to Carbon Nanotubes, *Phys. Rev. B* **60** (11), 7828 (1999).