

# **Book For Application Developers**

Release 11.0

**Geant4 Collaboration** 

Rev6.0 - December 10th, 2021

# **CONTENTS**

1	Intro	duction		3
	1.1	How to	use this manual	3
2	Getti		red with Geant4 - Running a Simple Example	5
	2.1		Define the main() Program	5
		2.1.1	A Sample main() Method	5
		2.1.2	G4RunManager	6
		2.1.3	User Initialization and Action Classes	7
		2.1.4	G4UImanager and UI CommandSubmission	8
		2.1.5	G4cout and G4cerr	9
	2.2	How to	Define a Detector Geometry	9
		2.2.1	Basic Concepts	9
		2.2.2	Create a Simple Volume	10
		2.2.3	Choose a Solid	10
		2.2.4	Create a Logical Volume	11
		2.2.5	Place a Volume	11
		2.2.6	Create a Physical Volume	11
		2.2.7		12
	2.3	How to		12
		2.3.1	General Considerations	12
		2.3.2		12
		2.3.3		13
		2.3.4	Define a Mixture by Fractional Mass	13
		2.3.5		13
		2.3.6	Define a Material from the Base Material	14
		2.3.7		14
		2.3.8		14
	2.4	How to		15
		2.4.1		15
		2.4.2		17
	2.5	How to		18
		2.5.1		18
		2.5.2		19
		2.5.3	6 6	19
	2.6			20
		2.6.1		20
		2.6.2		22
	2.7			23
		2.7.1		23
		2.7.2		24
		2.7.2	2	

		2.7.3 2.7.4		27 32
	2.8		Make an Executable Program	33
	2.0	2.8.1	Using CMake to Build Applications	33
		2.8.2		41
	2.9			43
	2.9		1	
		2.9.1		43
		2.9.2	1	43
	2 10	2.9.3	How to Select Interface in Your Applications	45
	2.10		Execute a Program	46
		2.10.1		46
		2.10.2	'Hard-coded' Batch Mode	47
		2.10.3	Batch Mode with Macro File	47
		2.10.4	Interactive Mode Driven by Command Lines	48
		2.10.5	General Case	50
	2.11	How to	Visualize the Detector and Events	52
		2.11.1	Introduction	52
		2.11.2	Visualization Drivers	52
		2.11.3	How to Incorporate Visualization Drivers into an Executable	52
		2.11.4	Writing the main () Method to Include Visualization	53
		2.11.5	Sample Visualization Sessions	54
		2.11.6	For More Information on GEANT4 Visualization	54
3	Toolk		amentals	55
	3.1	Class C	ategories and Domains	55
		3.1.1	What is a class category?	55
		3.1.2	Class categories in GEANT4	55
	3.2	Global	Usage Classes	57
		3.2.1	Signature of GEANT4 classes	57
		3.2.2	The <i>HEPRandom</i> module in CLHEP	58
		3.2.3	The <i>HEPNumerics</i> module	61
		3.2.4	General management classes	61
	3.3	System		63
		3.3.1	Basic units	63
		3.3.2		63
		3.3.3		64
		3.3.4		64
		3.3.5	Print the list of units	65
	3.4	Run		65
		3.4.1	Basic concept of Run	65
		3.4.2	GEANT4 as a state machine	67
		3.4.3	User's hook for state change	68
		3.4.4	Customizing the Run Manager	68
		3.4.5	Managing worker thread	70
	3.5			71
	3.3	3.5.1	Representation of an event	71
		3.5.2	Structure of an event	71
		3.5.3	Mandates of G4EventManager	71
	26	3.5.4	Stacking mechanism	71
	3.6		Semerator Interface	72
		3.6.1	Structure of a primary event	72
		3.6.2	Interface to a primary generator	73
	o =	3.6.3	Event overlap using multiple generators	75
	3.7	Event B	iasing Techniques	75

		3.7.1	Scoring, Geometrical Importance Sampling and Weight Roulette
		3.7.2	Physics Based Biasing
		3.7.3	Adjoint/Reverse Monte Carlo
		3.7.4	Generic Biasing
4	Dete	ctor Defi	nition and Response 99
	4.1	Geomet	ry
		4.1.1	Introduction
		4.1.2	Solids
		4.1.3	Logical Volumes
		4.1.4	Physical Volumes
		4.1.5	Touchables: Uniquely Identifying a Volume
		4.1.6	Creating an Assembly of Volumes
		4.1.7	Reflecting Hierarchies of Volumes
		4.1.8	The Geometry Navigator
		4.1.9	Converting Geometries from Geant3.21
		4.1.10	Detecting Overlapping Volumes
		4.1.11	Dynamic Geometry Setups
		4.1.12	Importing XML Models Using GDML
		4.1.13	Importing ASCII Text Models
		4.1.14	Saving geometry tree objects in binary format
	4.2		1
	1.2	4.2.1	General considerations
		4.2.2	Introduction to the Classes
		4.2.3	Recipes for Building Elements and Materials
		4.2.4	The Tables
	4.3		magnetic Field
	7.5	4.3.1	An Overview of Propagation in a Field
		4.3.2	Practical Aspects
		4.3.3	Spin Tracking
	4.4		
	7.7	4.4.1	Hit
		4.4.2	Sensitive detector
		4.4.3	G4SDManager
		4.4.4	G4MultiFunctionalDetector and G4VPrimitiveScorer
		4.4.5	Concrete classes of G4VPrimitiveScorer
		4.4.6	G4VSDFilter and its derived classes
		4.4.7	Multiple sensitive detectors associated to a single logical-volume
		4.4.8	Utilities
	4.5		tion
	т.Э	4.5.1	Digi
		4.5.2	Digitizer module
	4.6		uenching
	4.7		Persistency
	7.7	4.7.1	Persistency in GEANT4
		4.7.2	Using Root-I/O for persistency of GEANT4 objects
	4.8		Geometries
	7.0	4.8.1	A parallel world
		4.8.2	Defining a parallel world
		4.8.3	Layered mass geometry
	4.9		nd-based scoring
	7.7	4.9.1	Introduction
		4.9.2	Defining a scoring volume in the tracking world
		4.9.3	Defining a scoring world
		1.7.0	

		4.9.4	Defining a scoring probe
		4.9.5	Defining primitive scorers to a scoring volume
		4.9.6	Drawing scores for a scoring mesh
		4.9.7	Writing scores to a file
		4.9.8	Filling 1-D histogram
		4.9.9	List of available primitive scorers
		т.у.у	List of available primitive scorers
5	Tracl	king and	1 Physics 203
	5.1		ng
		5.1.1	Basic Concepts
		5.1.2	Access to Track and Step Information
		5.1.3	Handling of Secondary Particles
		5.1.4	User Actions
		5.1.5	Verbose Outputs
		5.1.6	Trajectory and Trajectory Point
	5.2		Processes
	3.2	5.2.1	Overview
		5.2.1	
			Electromagnetic Interactions
		5.2.3	Hadronic Interactions
		5.2.4	Particle Decay Process
		5.2.5	Gamma-nuclear and Lepto-nuclear Processes
		5.2.6	Optical Photon Processes
		5.2.7	Parameterisation
		5.2.8	Transportation Process
	5.3		270
		5.3.1	Basic concepts
		5.3.2	Definition of a particle
		5.3.3	Dynamic particle
	5.4		tion Threshold versus Tracking Cut
		5.4.1	General considerations
		5.4.2	Set production threshold (SetCut methods)
		5.4.3	Apply cut
		5.4.4	Why produce secondaries below threshold in some processes?
		5.4.5	Cuts in stopping range or in energy?
		5.4.6	Summary
		5.4.7	Special tracking cuts
	5.5	Cuts pe	r Region
		5.5.1	General Concepts
		5.5.2	Default Region
		5.5.3	Assigning Production Cuts to a Region
	5.6	Physics	Table
		5.6.1	General Concepts
		5.6.2	Material-Cuts Couple
		5.6.3	File I/O for the Physics Table
		5.6.4	Building the Physics Table
	5.7		mits
		5.7.1	General Concepts
		5.7.2	Processes co-working with G4UserLimits
	5.8		Error Propagation
	5.0	5.8.1	Physics
		5.8.2	Trajectory state
		5.8.3	Trajectory state error
		5.8.4	Targets
		5.8.5	Managing the track propagation
		2.0.2	171dinging the thek propagation

			ing the step				
	5.9						
			cs				
			ial				
		5.9.3 Geom	etry		 	 	287
	TT	A -40					200
6		Actions					289
	6.1						
	6.2	•	er Actions and Initializations				
			serDetectorConstruction				
			cs Lists				
			Action Initialization				
	6.3		Actions				
		_	e of User Actions				
			g Tracks in User Actions and Energy Conservation				
	6.4		on Classes				
		6.4.1 G4VU	JserEventInformation		 	 	
		6.4.2 G4VU	JserTrackInformation		 	 	299
		6.4.3 G4VU	JserPrimaryVertexInformation and G4VUserPrimaryTrackInformatio	n.	 	 	299
		6.4.4 G4VU	JserRegionInformation		 	 	299
	6.5	Multiple User	Actions		 	 	300
		6.5.1 Excep	otions		 	 	301
		-					
7	Cont						303
	7.1		nands				
	7.2		- Defining New Commands				
			messenger				
			command and its derived classes				
			ample messenger				
		7.2.4 How t	to control the output of G4cout/G4cerr		 	 	311
8	Viene	lization					313
ð			Visualization				
	8.1						
			Can be Visualized				
			ave a Choice of Visualization Drivers				
			se the Driver that Meets Your Needs				
			olling Visualization				
			lization Details				
	8.2	0	ization to Your Executable				
			ling Visualization Drivers				
			to Realize Visualization Drivers in an Executable				
			do wish to write your own subclass				
			fault				
			nally				
		8.2.6 Visua	lization Manager		 	 	318
		8.2.7 How t	to Write the main () Function		 	 	318
	8.3	The Visualizat	ion Drivers		 	 	319
		8.3.1 Availa	ability of drivers on the supported systems		 	 	320
		8.3.2 Open	GL		 	 	320
		-					
			Inventor				
		1	Inventor Extended Viewer				
		1	Inventor Qt Viewer				

	8.3.8	ToolsSG
	8.3.9	Vtk
	8.3.10	HepRepFile
	8.3.11	DAWN 32
	8.3.12	VRML
	8.3.13	RayTracer
	8.3.14	·
		Visualization of detector geometry tree
8.4		lling Visualization from Commands
	8.4.1	Scene, scene handler, and viewer
	8.4.2	Create a scene handler and a viewer: /vis/open command
	8.4.3	Create an empty scene: /vis/scene/create command
	8.4.4	Visualization of a physical volume: /vis/drawVolume command
	8.4.5	Visualization of a logical volume: /vis/drawLogicalVolume command
	8.4.6	Visualization of trajectories: /vis/scene/add/trajectories command
	8.4.7	Visualization of hits: /vis/scene/add/hits command
	8.4.8	Visualization of fields: /vis/scene/add/magneticField command
	8.4.9	Visualization of Scored Data
	8.4.10	Additional attributes for Hits
	8.4.11	Visualization of histograms (plotting)
	8.4.12	Basic camera workings: /vis/viewer/commands
	8.4.13	Declare the end of visualization for flushing: /vis/viewer/flush command
	8.4.14	End of Event Action and End of Run Action: /vis/scene/endOfEventAction and
	0.4.14	/vis/scene/endOfRunAction commands
	8.4.15	HepRep Attributes for Trajectories
	8.4.16	
	8.4.17	How to save a view to an image file
	8.4.18	Culling
	8.4.19	Cut view
	8.4.20	Multithreading commands
8.5		lling Visualization from Compiled Code
0.0	8.5.1	G4VVisManager
	8.5.2	Visualization of detector components
	8.5.3	Visualization of trajectories
	8.5.4 8.5.5	Enhanced trajectory drawing
	8.5.6	
	8.5.7	Visualization of hits       34         HepRep Attributes for Hits       35
		i i
	8.5.8 8.5.9	Visualization of text
		Visualization of polylines and tracking steps
	8.5.10 8.5.11	
	8.5.11	
8.6		Drawing a solid as a cloud of points
8.0		
	8.6.1	Visibility
	8.6.2	Colour
	8.6.3	Forcing attributes
	8.6.4	Other attributes
	8.6.5	Constructors of G4Vis Attributes
	8.6.6	How to assign G4VisAttributes to a logical volume
0.7	8.6.7	Additional User-Defined Attributes
8.7		ed Trajectory Drawing
	8.7.1	Default Configuration
	8.7.2	Trajectory Drawing Models

		8.7.3	Controlling from Commands	364
		8.7.4	Controlling from Compiled Code	
		8.7.5	Drawing by time	366
	8.8	Trajecto	ory Filtering	367
		8.8.1	Controlling from Commands	
		8.8.2	Example commands	
		8.8.3	Hit and Digi Filtering	
	8.9		es, Markers and Text	
	0.7	8.9.1	Polylines	
		8.9.2	Markers	
		8.9.3	Text	
	8.10		a Movie	
	0.10	8.10.1	Using /vis/viewer/interpolate	
		8.10.2	With a macro loop	
		8.10.3	Processing picture files with mpeg2encode	
		8.10.4	Qt	
		8.10.5	DAWNFILE	
		8.10.6	RayTracerX	
	8.11		ring geometry with vis	
		8.11.1	Using advanced vis tools	377
_				
9	Analy	•		381
	9.1		ction	
	9.2	-	s Manager Classes	
		9.2.1	Analysis Manager	
		9.2.2	Files handling	
		9.2.3	Histograms	385
		9.2.4	Profiles	390
		9.2.5	Plotting	393
		9.2.6	Ntuples	394
		9.2.7	Parallel Processing	
		9.2.8	Coexistence of Several Managers	
		9.2.9	Supported Features and Limitations	
	9.3		s Reader Classes	
	,	9.3.1	Analysis Reader	
		9.3.2	File handling	
		9.3.3	Histograms and Profiles	
		9.3.4	Ntuples	
	9.4	Accumi	1	
	9.4			
		9.4.1	G4Accumulable <t></t>	
	0.5	9.4.2	User defined accumulables	
	9.5	g4tools		
		9.5.1	g4tools package	
		9.5.2	User API	405
10	100			405
10	Exam	•		407
		Introduc		407
	10.2		xamples	
		10.2.1	Basic Examples Summary	407
		10.2.2	Basic Examples Macros	410
		10.2.3	Multi-threading	411
		1001	E1- D1	410
		10.2.4	Example B1	
		10.2.4	Example B1	412

	10.2.7 Example B4	414
	10.2.8 Example B5	416
10.3	Extended Examples	417
	10.3.1 Analysis	418
	10.3.2 Biasing	418
	10.3.3 Common	418
	10.3.4 Electromagnetic	418
	10.3.5 Error Propagation	419
	10.3.6 Event Generator	419
	10.3.7 Exotic Physics	420
	10.3.8 Fields	420
	10.3.9 Geant3 to Geant4	420
	10.3.10 Geometry	420
	10.3.11 Hadronic	420
	10.3.12 Medical Applications	421
	10.3.13 Optical Photons	422
	10.3.14 Parallel Computing	422
	10.3.15 Parameterisations	422
	10.3.16 Persistency	430
	10.3.17 Physics lists	430
	10.3.18 Polarisation	430
	10.3.19 Radioactive Decay	431
	10.3.20 Run & Event	431
	10.3.21 Visualization	431
10.4	Advanced Examples	431
10.5	Novice Examples	433
11 App		435
11.1	- ;	435
	11.1.1 Using Geant4Py	435
	11.1.2 Developing Geant4Py	436
11.2		436
	11.2.1 Simple Materials (Elements)	436
	11.2.2 NIST Compounds	438
	11.2.3 HEP and Nuclear Materials	450
	11.2.4 Space (ISS) Materials	451
44.0	11.2.5 Bio-Chemical Materials	451
11.3	1	453
	11.3.1 The challenge of integrating all tracks	453
	11.3.2 Using preset thresholds for killing loopers	454
	11.3.3 Fine grained control of the parameters for killing looping particles	455
Bibliogr	raphy	459

### Scope of this manual

The User's Guide for Application Developers is the first manual the reader should consult when learning about GEANT4 or developing a GEANT4 -based detector simulation program. This manual is designed to:

- introduce the first-time user to the GEANT4 object-oriented detector simulation toolkit,
- provide a description of the available tools and how to use them, and
- supply the practical information required to develop and run simulation applications which may be used in real experiments.

This manual is intended to be an overview of the toolkit, rather than an exhaustive treatment of it. Related physics discussions are not included unless required for the description of a particular tool. Detailed discussions of the physics included in GEANT4 can be found in the Physics Reference Manual. Details of the design and functionality of the GEANT4 classes can be found in the User's Guide for Toolkit Developers.

GEANT4 is a detector simulation toolkit written in the C++ language. The reader is assumed to have a basic knowledge of object-oriented programming using C++. Although GEANT4 is a fairly complicated software system, only a relatively small part of it needs to be understood in order to begin developing detector simulation applications. An understanding of radiation physics and associated processes is beneficial.

CONTENTS 1

2 CONTENTS

**CHAPTER** 

ONE

# INTRODUCTION

# 1.1 How to use this manual

A very basic introduction to GEANT4 is presented in Section *Getting Started with Geant4 - Running a Simple Example*. It is a recipe for writing and running a simple GEANT4 application program. New users of GEANT4 should read this chapter first. It is strongly recommended that this chapter be read in conjunction with a GEANT4 system installed and running on your computer. It is helpful to run the provided examples as they are discussed in the manual. To install the GEANT4 system on your computer, please refer to the Installation Guide for Setting up Geant4 in Your Computing Environment.

Section *Toolkit Fundamentals* discusses general GEANT4 issues such as class categories and the physical units system. It goes on to discuss runs and events, which are the basic units of a simulation.

Section *Detector Definition and Response* describes how to construct a detector from customized materials and geometric shapes, and embed it in electromagnetic fields. It also describes how to make the detector sensitive to particles passing through it and how to store this information.

How particles are propagated through a material is treated in Section *Tracking and Physics*. The GEANT4 "philosophy" of particle tracking is presented along with summaries of the physics processes provided by the toolkit. The definition and implementation of GEANT4 particles is discussed and a list of particle properties is provided.

Section *User Actions* is a description of the "user hooks" by which the simulation code may be customized to perform special tasks.

Section *Control* provides a summary of the commands available to the user to control the execution of the simulation. After Chapter 2, Chapters 6 and 7 are of foremost importance to the new application developer.

The display of detector geometry, tracks and events may be incorporated into a simulation application by using the tools described in Section *Visualization*.

Section *Examples* provides a set of basic, novice, extended and advanced simulation codes which may be compiled and run "as is" from the GEANT4 source code. These examples may be used as educational tools or as base code from which more complex applications are developed.

# **GETTING STARTED WITH GEANT4 - RUNNING A SIMPLE EXAMPLE**

# 2.1 How to Define the main() Program

# 2.1.1 A Sample main() Method

The contents of main() will vary according to the needs of a given simulation application and therefore must be supplied by the user. The GEANT4 toolkit does not provide a main() method, but a sample is provided here as a guide to the beginning user. Listing 2.1 is the simplest example of main() required to build a simulation program.

Listing 2.1: Simplest example of main()

```
#include "G4RunManagerFactory.hh"
#include "G4UImanager.hh"
#include "ExG4DetectorConstruction01.hh"
#include "ExG4PhysicsList00.hh"
#include "ExG4ActionInitialization01.hh"
int main()
  // construct the default run manager
 auto runManager = G4RunManagerFactory::CreateRunManager();
  // set mandatory initialization classes
  runManager->SetUserInitialization(new ExG4DetectorConstruction01);
  runManager->SetUserInitialization(new ExG4PhysicsList00);
  runManager->SetUserInitialization(new ExG4ActionInitialization01);
  // initialize G4 kernel
  runManager->Initialize();
  // get the pointer to the UI manager and set verbosities
  G4UImanager* UI = G4UImanager::GetUIpointer();
 UI->ApplyCommand("/run/verbose 1");
 UI->ApplyCommand("/event/verbose 1");
 UI->ApplyCommand("/tracking/verbose 1");
  int numberOfEvent = 3;
  runManager->BeamOn(numberOfEvent);
 delete runManager;
 return 0:
```

The main () method is implemented by two toolkit classes, G4RunManager and G4UImanager, and three classes, ExG4DetectorConstruction01, ExG4PhysicsList00 and ExG4ActionInitialization01, which

are derived from toolkit classes. Each of these are explained in the following sections.

### 2.1.2 G4RunManager

The first thing main () must do is create an instance of the G4RunManager class. This is the only manager class in the GEANT4 kernel which should be explicitly constructed in the user's main (). It controls the flow of the program and manages the event loop(s) within a run. G4RunManagerFactory::CreateRunManager() instantiates a G4RunManager object whose concrete type is:

- G4MTRunManager if Geant4 library was built with multithreading support
- G4RunManager otherwise

The concrete type chosen may be overridden at application runtime without recompilation by setting the environment variable G4RUN\_MANAGER\_TYPE, whose value can be set to either Serial, MT, Tasking or TBB. For Geant4 version 10.7, options Tasking and TBB are provided as beta-release. The traditional style of direct instantiation of G4RunManager (sequential mode) or G4MTRunMabager (multithreaded mode) is also available.

When G4RunManager is created, the other major manager classes are also created. They are deleted automatically when G4RunManager is deleted. The run manager is also responsible for managing initialization procedures, including methods in the user initialization classes. Through these the run manager must be given all the information necessary to build and run the simulation, including

- 1. how the detector should be constructed,
- 2. all the particles and all the physics processes to be simulated,
- 3. how the primary particle(s) in an event should be produced, and
- 4. any additional requirements of the simulation.

In the sample main () the lines

```
runManager->SetUserInitialization(new ExG4DetectorConstruction01);
runManager->SetUserInitialization(new ExG4PhysicsList00);
runManager->SetUserInitialization(new ExG4ActionInitialization01);
```

create objects which specify the detector geometry, physics processes and primary particle, respectively, and pass their pointers to the run manager. ExG4DetectorConstruction01 is an example of a user initialization class which is derived from G4VUserDetectorConstruction. This is where the user describes the entire detector setup, including

- its geometry,
- the materials used in its construction,
- · a definition of its sensitive regions and
- the readout schemes of the sensitive regions.

Similarly ExG4PhysicsList01 is derived from G4VUserPhysicsList and requires the user to define

- the particles to be used in the simulation,
- all the physics processes to be simulated.

User can also override the default implementation for

• the range cuts for these particles and

Also ExG4ActionInitialization01 is derived from G4VUserActionInitialization and requires the user to define

- so-called user action classes (see next section) that are invoked during the simulation,
- which includes one mandatory user action to define the primary particles.

The next instruction

```
runManager->Initialize();
```

performs the detector construction, creates the physics processes, calculates cross sections and otherwise sets up the run. The final run manager method in main ()

```
int numberOfEvent = 3;
runManager->beamOn(numberOfEvent);
```

begins a run of three sequentially processed events. The beamOn() method may be invoked any number of times within main() with each invocation representing a separate run. Once a run has begun neither the detector setup nor the physics processes may be changed. They may be changed between runs, however, as described in *Customizing the Run Manager*. More information on G4RunManager in general is found in *Run*.

As mentioned above, other manager classes are created when the run manager is created. One of these is the user interface manager, G4UImanager. In main () a pointer to the interface manager must be obtained

```
G4UImanager* UI = G4UImanager::getUIpointer();
```

in order for the user to issue commands to the program. In the present example the applyCommand() method is called three times to direct the program to print out information at the run, event and tracking levels of simulation. A wide range of commands is available which allows the user detailed control of the simulation. A list of these commands can be found in *Built-in Commands*.

### 2.1.3 User Initialization and Action Classes

### **User Classes**

There are two kinds of user classes, user initialization classes and user action classes. User initialization classes are used during the initialization phase, while user action classes are used during the run. User initialization classes should be directly set to G4RunManager through SetUserInitialization() method, while user action classes should be defined in G4VUserActionInitialization class.

### **User Initialization Classes**

All three user initialization classes are mandatory. They must be derived from the abstract base classes provided by GEANT4:

- G4VUserDetectorConstruction
- G4VUserPhysicsList
- G4VUserActionInitialization

GEANT4 does not provide default behavior for these classes. G4RunManager checks for the existence of these mandatory classes when the Initialize() and BeamOn() methods are invoked.

As mentioned in the previous section, G4VUserDetectorConstruction requires the user to define the detector and G4VUserPhysicsList requires the user to define the physics. Detector definition will be discussed in Sections *How to Define a Detector Geometry* and *How to Specify Materials in the Detector*. Physics definition will be discussed in *How to Specify Particles* and *How to Specify Physics Processes*. The user action G4VUserPrimaryGeneratorAction requires that the initial event state be defined. Primary event generation will be discussed in *How to Make an Executable Program*.

G4VUserActionInitialization should include at least one mandatory user action class G4VUserPrimaryGeneratorAction. All user action classes are described in the next section.

Listing 2.2: Simplest example of ExG4ActionInitialization01

```
#include "ExG4ActionInitialization01.hh"
#include "ExG4PrimaryGeneratorAction01.hh"

void ExG4ActionInitialization01::Build() const
{
   SetUserAction(new ExG4PrimaryGeneratorAction01);
}
```

#### **User Action Classes**

G4VUserPrimaryGeneratorAction is a mandatory class the user has to provide. It creates an instance of a primary particle generator. ExG4PrimaryGeneratorAction01 is an example of a user action class which is derived from G4VUserPrimaryGeneratorAction. In this class the user must describe the initial state of the primary event. This class has a public virtual method named GeneratePrimaries() which will be invoked at the beginning of each event. Details will be given in *How to Generate a Primary Event*. Note that GEANT4 does not provide any default behavior for generating a primary event.

GEANT4 provides additional five user hook classes:

- G4UserRunAction
- G4UserEventAction
- G4UserStackingAction
- G4UserTrackingAction
- G4UserSteppingAction

These optional user action classes have several virtual methods which allow the specification of additional procedures at all levels of the simulation application. Details of the user initialization and action classes are provided in *User Actions*.

### 2.1.4 G4UImanager and UI CommandSubmission

GEANT4 provides a category named **intercoms**. G4UImanager is the manager class of this category. Using the functionalities of this category, you can invoke **set** methods of class objects of which you do not know the pointer. In Listing 2.3, the verbosities of various GEANT4 manager classes are set. Detailed mechanism description and usage of **intercoms** will be given in the next chapter, with a list of available commands. Command submission can be done all through the application.

Listing 2.3: An example of main() using interactive terminal.

```
#include "G4RunManager.hh"
#include "G4UIExecutive.hh"

#include "ExG4DetectorConstruction01.hh"
#include "ExG4PhysicsList00.hh"
#include "ExG4PrimaryGeneratorAction01.hh"

int main()
{
    // construct the default run manager
    G4RunManager* runManager = new G4RunManager;

    // set mandatory initialization classes
    runManager->SetUserInitialization(new ExG4DetectorConstruction01);
```

(continues on next page)

(continued from previous page)

```
runManager->SetUserInitialization(new ExG4PhysicsList00);
// set mandatory user action class
runManager->SetUserAction(new ExG4PrimaryGeneratorAction01);
// initialize G4 kernel
runManager->Initialize();
// Get the pointer to the User Interface manager
G4UImanager* UImanager = G4UImanager::GetUIpointer();
if ( argc == 1 ) {
    interactive mode : define UI session
 G4UIExecutive* ui = new G4UIExecutive(argc, argv);
 UImanager->ApplyCommand("/control/execute init.mac");
 ui->SessionStart():
 delete ui;
else {
 G4String command = "/control/execute ";
 G4String fileName = argv[1];
 UImanager->ApplyCommand(command+fileName);
// job termination
delete runManager;
return 0:
```

### 2.1.5 G4cout and G4cerr

Although not yet included in the above examples, output streams will be needed. G4cout and G4cerr are **iostream** objects defined by GEANT4. The usage of these objects is exactly the same as the ordinary *cout* and *cerr*, except that the output streams will be handled by G4UImanager. Thus, output strings may be displayed on another window or stored in a file. Manipulation of these output streams will be described in *How to control the output of G4cout/G4cerr*. These objects should be used instead of the ordinary *cout* and *cerr*.

# 2.2 How to Define a Detector Geometry

# 2.2.1 Basic Concepts

A detector geometry in GEANT4 is made of a number of volumes. The largest volume is called the **World** volume. It must contain, with some margin, all other volumes in the detector geometry. The other volumes are created and placed inside previous volumes, included in the World volume. The most simple (and efficient) shape to describe the World is a box.

Each volume is created by describing its shape and its physical characteristics, and then placing it inside a containing volume.

When a volume is placed within another volume, we call the former volume the daughter volume and the latter the mother volume. The coordinate system used to specify where the daughter volume is placed, is the coordinate system of the mother volume.

To describe a volume's shape, we use the concept of a solid. A solid is a geometrical object that has a shape and specific values for each of that shape's dimensions. A cube with a side of 10 centimeters and a cylinder of radius 30 cm and length 75 cm are examples of solids.

To describe a volume's full properties, we use a logical volume. It includes the geometrical properties of the solid, and adds physical characteristics: the material of the volume; whether it contains any sensitive detector elements; the magnetic field; etc.

We have yet to describe how to position the volume. To do this you create a physical volume, which places a copy of the logical volume inside a larger, containing, volume.

# 2.2.2 Create a Simple Volume

What do you need to do to create a volume?

- · Create a solid.
- Create a logical volume, using this solid, and adding other attributes.

Each of the volume types (solid, logical, and physical) has an associated registry (*VolumeStore*) which contains a list of all the objects of that type constructed so far. The registries will automatically delete those objects when requested; users should not deleted geometry objects manually.

### 2.2.3 Choose a Solid

To create a simple box, you only need to define its name and its extent along each of the Cartesian axes.

Listing 2.4: Creating a box.

```
G4double world_hx = 3.0*m;
G4double world_hy = 1.0*m;
G4double world_hz = 1.0*m;

G4Box* worldBox
= new G4Box("World", world_hx, world_hy, world_hz);
```

This creates a box named "World" with the extent from -3.0 meters to +3.0 meters along the X axis, from -1.0 to 1.0 meters in Y, and from -1.0 to 1.0 meters in Z. Note that the G4Box constructor takes as arguments the halves of the total box size.

It is also very simple to create a cylinder. To do this, you can use the G4Tubs class.

Listing 2.5: Creating a cylinder.

This creates a full cylinder, named "Tracker", of radius 60 centimeters and length 50 cm (the hz parameter represents the half length in Z).

# 2.2.4 Create a Logical Volume

To create a logical volume, you must start with a solid and a material. So, using the box created above, you can create a simple logical volume filled with argon gas (see *How to Specify Materials in the Detector*) by entering:

This logical volume is named "World".

Similarly we create a logical volume with the cylindrical solid filled with aluminium

```
G4LogicalVolume* trackerLog = new G4LogicalVolume(trackerTube, Al, "Tracker");
```

and named "Tracker".

### 2.2.5 Place a Volume

How do you place a volume? You start with a logical volume, and then you decide the already existing volume inside of which to place it. Then you decide where to place its center within that volume, and how to rotate it. Once you have made these decisions, you can create a physical volume, which is the placed instance of the volume, and embodies all of these attributes.

# 2.2.6 Create a Physical Volume

You create a physical volume starting with your logical volume. A physical volume is simply a placed instance of the logical volume. This instance must be placed inside a mother logical volume. For simplicity it is unrotated:

Listing 2.6: A simple physical volume.

```
G4double pos_x = -1.0 \times meter;
G4double pos_y = 0.0*meter;
G4double pos_z = 0.0*meter;
G4VPhysicalVolume* trackerPhys
                                            // no rotation
  = new G4PVPlacement(0,
                      G4ThreeVector(pos_x, pos_y, pos_z),
                                               // translation position
                                               // its logical volume
                      trackerLog,
                      "Tracker",
                      worldLog,
                                               // its mother (logical) volume
                                                // no boolean operations
                      false,
                                               // its copy number
                      0);
```

This places the logical volume trackerLog at the origin of the mother volume worldLog, shifted by one meter along X and unrotated. The resulting physical volume is named "Tracker" and has a copy number of 0.

An exception exists to the rule that a physical volume must be placed inside a mother volume. That exception is for the World volume, which is the largest volume created, and which contains all other volumes. This volume obviously cannot be contained in any other. Instead, it must be created as a G4PVPlacement with a null mother pointer. It also must be unrotated, and it must be placed at the origin of the global coordinate system.

Generally, it is best to choose a simple solid as the World volume, the G4Box solid type is used in all basic examples.

# 2.2.7 Coordinate Systems and Rotations

In GEANT4, the rotation matrix associated to a placed physical volume represents the rotation of the reference system of this volume with respect to its mother.

A rotation matrix is normally constructed as in CLHEP, by instantiating the identity matrix and then applying a rotation to it. This is also demonstrated in Example B3.

# 2.3 How to Specify Materials in the Detector

### 2.3.1 General Considerations

In nature, general materials (chemical compounds, mixtures) are made of elements, and elements are made of isotopes. Therefore, these are the three main classes designed in GEANT4. Each of these classes has a table as a static data member, which is for keeping track of the instances created of the respective classes. All three objects automatically register themselves into the corresponding table on construction, and should never be deleted in user code.

The G4Element class describes the properties of the atoms:

- · atomic number.
- number of nucleons,
- · atomic mass,
- shell energy,
- as well as quantities such as cross sections per atom, etc.

The G4Material class describes the macroscopic properties of matter:

- · density,
- state,
- · temperature,
- pressure,
- as well as macroscopic quantities like radiation length, mean free path, dE/dx, etc.

The G4Material class is the one which is visible to the rest of the toolkit, and is used by the tracking, the geometry, and the physics. It contains all the information relative to the eventual elements and isotopes of which it is made, at the same time hiding the implementation details.

# 2.3.2 Define a Simple Material

In the example below, liquid argon is created, by specifying its name, density, mass per mole, and atomic number.

Listing 2.7: Creating liquid argon.

```
G4double z, a, density;

density = 1.390*g/cm3;

a = 39.95*g/mole;

G4Material* lAr = new G4Material(name="liquidArgon", z=18., a, density);
```

The pointer to the material, *lAr*, will be used to specify the matter of which a given logical volume is made:

```
G4LogicalVolume* myLbox = new G4LogicalVolume(aBox,lAr,"Lbox",0,0,0);
```

### 2.3.3 Define a Molecule

In the example below, the water, H2O, is built from its components, by specifying the number of atoms in the molecule.

Listing 2.8: Creating water by defining its molecular components.

```
G4double z, a, density;
G4String name, symbol;
G4int ncomponents, natoms;

a = 1.01*g/mole;
G4Element* elH = new G4Element(name="Hydrogen", symbol="H" , z= 1., a);

a = 16.00*g/mole;
G4Element* elO = new G4Element(name="Oxygen" , symbol="O" , z= 8., a);

density = 1.000*g/cm3;
G4Material* H2O = new G4Material(name="Water", density, ncomponents=2);
H2O->AddElement(elH, natoms=2);
H2O->AddElement(elO, natoms=1);
```

# 2.3.4 Define a Mixture by Fractional Mass

In the example below, air is built from nitrogen and oxygen, by giving the fractional mass of each component.

Listing 2.9: Creating air by defining the fractional mass of its components.

```
G4double z, a, fractionmass, density;
G4String name, symbol;
G4int ncomponents;

a = 14.01*g/mole;
G4Element* elN = new G4Element(name="Nitrogen", symbol="N" , z= 7., a);

a = 16.00*g/mole;
G4Element* elO = new G4Element(name="Oxygen" , symbol="O" , z= 8., a);

density = 1.290*mg/cm3;
G4Material* Air = new G4Material(name="Air ", density, ncomponents=2);
Air->AddElement(elN, fractionmass=70*perCent);
Air->AddElement(elO, fractionmass=30*perCent);
```

### 2.3.5 Define a Material from the GEANT4 Material Database

In the example below, air and water are accessed via the GEANT4 material database.

Listing 2.10: Defining air and water from the internal GEANT4 database.

```
G4NistManager* man = G4NistManager::Instance();

G4Material* H2O = man->FindOrBuildMaterial("G4_WATER");
G4Material* Air = man->FindOrBuildMaterial("G4_AIR");
```

### 2.3.6 Define a Material from the Base Material

It is possible to build new material on base of an existing "base" material. This feature is useful for electromagnetic physics allowing to peak up for the derived material all correction data and precomputed tables of stopping powers and cross sections of the base material. In the example below, two methods how to create water with unusual density are shown.

Listing 2.11: Defining water with user defined density on base of G4 WATER.

```
G4double density;

density = 1.05*mg/cm3;
G4Material* water1 = new G4Material("Water_1.05", density, "G4_WATER");

density = 1.03*mg/cm3;
G4NistManager* man = G4NistManager::Instance();
G4Material* water2 = man->BuildMaterialWithNewDensity("Water_1.03", "G4_WATER", density);
```

### 2.3.7 Print Material Information

Listing 2.12: Printing information about materials.

```
G4cout << H2O;  \\ print a given material G4cout << *(G4Material::GetMaterialTable()); \\ print the list of materials
```

In GEANT4 examples you all possible ways to build a material.

### 2.3.8 Access to GEANT4 material database

Listing 2.13: GEANT4 material database may be accessed via UI commands.

```
/material/nist/printElement Fe \\ print element by name \\material/nist/printElementZ 13 \\ print element by atomic number \\material/nist/listMaterials type \\ print materials type = [simple | compound | hep | all] \\material/g4/printElement elmName \\ print instantiated element by name \\material/g4/printMaterial matName \\ print instantiated material by name
```

In GEANT4 examples you with find all possible ways to build a material.

# 2.4 How to Specify Particles

G4VUserPhysicsList is one of the mandatory user base classes described in *How to Define the main() Program*. Within this class all particles and physics processes to be used in your simulation must be defined. The range cut-off parameter should also be defined in this class.

The user must create a class derived from G4VuserPhysicsList and implement the following pure virtual methods:

```
ConstructParticle(); // construction of particles
ConstructProcess(); // construct processes and register them to particles
```

The user may also want to override the default implementation of the following virtual method:

```
SetCuts(); // setting a range cut value for all particles
```

This section provides some simple examples of the ConstructParticle() and SetCuts() methods. For information on ConstructProcess() methods, please see *How to Specify Physics Processes*.

### 2.4.1 Particle Definition

GEANT4 provides various types of particles for use in simulations:

- ordinary particles, such as electrons, protons, and gammas
- resonant particles with very short lifetimes, such as vector mesons and delta baryons
- nuclei, such as deuteron, alpha, and heavy ions (including hyper-nuclei)
- · quarks, di-quarks, and gluon

Each particle is represented by its own class, which is derived from G4ParticleDefinition. (Exception: G4Ions represents all heavy nuclei. Please see *Particles*.) Particles are organized into six major categories:

- lepton,
- · meson,
- baryon,
- boson,
- · shortlived and
- ion

each of which is defined in a corresponding sub-directory under geant4/source/particles. There is also a corresponding granular library for each particle category.

#### The G4ParticleDefinition Class

G4ParticleDefinition has properties which characterize individual particles, such as, name, mass, charge, spin, and so on. Most of these properties are "read-only" and can not be changed directly. G4ParticlePropertyTable is used to retrieve (load) particle property of G4ParticleDefinition into (from) G4ParticlePropertyData.

#### How to Access a Particle

Each particle class type represents an individual particle type, and each class has a single object. This object can be accessed by using the static method of each class. There are some exceptions to this rule; please see *Particles* for details.

For example, the class G4Electron represents the electron and the member G4Electron::theInstance points its only object. The pointer to this object is available through the static methods G4Electron::ElectronDefinition().G4Electron::Definition().

More than 100 types of particles are provided by default, to be used in various physics processes. In normal applications, users will not need to define their own particles.

The unique object for each particle class is created when its static method to get the pointer is called at the first time. Because particles are dynamic objects and should be instantiated before initialization of physics processes, you must explicitly invoke static methods of all particle classes required by your program at the initialization step. (NOTE: The particle object was static and created automatically before 8.0 release)

### **Dictionary of Particles**

The G4ParticleTable class is provided as a dictionary of particles. Various utility methods are provided, such as:

```
FindParticle(G4String name); // find the particle by name
FindParticle(G4int PDGencoding) // find the particle by PDG encoding .
```

G4ParticleTable is defined as a singleton object, and the static method G4ParticleTable::GetParticleTable() provides its pointer.

As for heavy ions (including hyper-nuclei), objects are created dynamically by requests from users and processes. The G4ParticleTable class provides methods to create ions, such as:

Particles are registered automatically during construction. The user has no control over particle registration.

### **Constructing Particles**

ConstructParticle() is a pure virtual method, in which the static member functions for all the particles you require should be called. This ensures that objects of these particles are created.

**Warning:** You must define "ALL PARTICLE TYPES" which are used in your application, except for heavy ions. "ALL PARTICLE TYPES" means not only primary particles, but also all other particles which may appear as secondaries generated by physics processes you use. Beginning with GEANT4 version 8.0, you should keep this rule strictly because all particle definitions are revised to "non-static" objects.

For example, suppose you need a proton and a geantino, which is a virtual particle used for simulation and which does not interact with materials. The ConstructParticle() method is implemented as below:

Listing 2.14: Construct a proton and a geantino.

```
void MyPhysicsList::ConstructParticle()
{
   G4Proton::ProtonDefinition();
   G4Geantino::GeantinoDefinition();
}
```

Due to the large number of pre-defined particles in GEANT4, it is cumbersome to list all the particles by this method. If you want all the particles in a GEANT4 particle category, there are six utility classes, corresponding to each of the particle categories, which perform this function:

- G4BosonConstructor
- G4LeptonConstructor
- G4MesonConstructor
- G4BaryonConstructor
- G4IonConstructor
- G4ShortlivedConstructor.

An example of this is shown in ExNO5PhysicsList, listed below.

Listing 2.15: Construct all leptons.

```
void ExN05PhysicsList::ConstructLeptons()
{
    // Construct all leptons
    G4LeptonConstructor pConstructor;
    pConstructor.ConstructParticle();
}
```

# 2.4.2 Range Cuts

To avoid infrared divergence, some electromagnetic processes require a threshold below which no secondary will be generated. Because of this requirement, gammas, electrons and positrons require production threshold. This threshold should be defined as a distance, or range cut-off, which is internally converted to an energy for individual materials. The range threshold should be defined in the initialization phase using the SetCuts() method of G4VUserPhysicsList. *Cuts per Region* discusses threshold and tracking cuts in detail.

### Setting the cuts

Production threshold values should be defined in SetCuts() which is a virtual method of the G4VUserPhysicsList. Construction of particles, materials, and processes should precede the invocation of SetCuts(). G4RunManager takes care of this sequence in usual applications.

This range cut value is converted threshold energies for each material and for each particle type (i.e. electron, positron and gamma) so that the particle with threshold energy stops (or is absorbed) after traveling the range cut distance. In addition, from the 9.3 release ,this range cut value is applied to the proton as production thresholds of nuclei for hadron elastic processes. In this case, the range cut value does not means the distance of traveling. Threshold energies are calculated by a simple formula from the cut in range.

Note that the upper limit of the threshold energy is defined as 10 GeV. If you want to set higher threshold energy, you can change the limit by using "/cuts/setMaxCutEnergy" command before setting the range cut.

The idea of a "unique cut value in range" is one of the important features of GEANT4 and is used to handle cut values in a coherent manner. For most applications, users need to determine only one cut value in range, and apply this value to gammas, electrons and positrons alike. (and proton too)

The default implementation of SetCuts() method provides a defaultCutValue member as the unique range cut-off value for all particle types. The defaultCutValue is set to 1.0 mm by default. User can change this value by SetDefaultCutValue() The "/run/setCut" command may be used to change the default cut value interactively.

Warning: DO NOT change cut values inside the event loop. Cut values may however be changed between runs.

It is possible to set different range cut values for gammas, electrons and positrons by using SetCutValue() methods (or using "/run/setCutForAGivenParticle" command). However, user must be careful with physics outputs because GEANT4 processes (especially energy loss) are designed to conform to the "unique cut value in range" scheme.

Beginning with GEANT4 version 5.1, it is now possible to set production thresholds for each geometrical region. This new functionality is described in *Cuts per Region*.

# 2.5 How to Specify Physics Processes

# 2.5.1 Physics Processes

Physics processes describe how particles interact with materials. GEANT4 provides seven major categories of processes:

- · electromagnetic,
- · hadronic,
- transportation,
- · decay,
- optical,
- photolepton\_hadron, and
- parameterisation.

All physics processes are derived from the G4VProcess base class. Its virtual methods

- AtRestDoIt,
- AlongStepDoIt, and
- PostStepDoIt

and the corresponding methods

- AtRestGetPhysicalInteractionLength,
- AlongStepGetPhysicalInteractionLength, and
- PostStepGetPhysicalInteractionLength

describe the behavior of a physics process when they are implemented in a derived class. The details of these methods are described in *Physics Processes*.

The following are specialized base classes to be used for simple processes:

G4VAtRestProcess Processes with only AtRestDoIt
G4VContinuousProcess Processes with only AlongStepDoIt
G4VDiscreteProcess processes with only PostStepDoIt

Another 4 virtual classes, such as G4VContinuousDiscreteProcess, are provided for complex processes.

# 2.5.2 Managing Processes

The G4ProcessManager class contains a list of processes that a particle can undertake. It has information on the order of invocation of the processes, as well as which kind of DoIt method is valid for each process in the list. A G4ProcessManager object corresponds to each particle and is attached to the G4ParticleDefiniton class.

In order to validate processes, they should be registered with the particle's G4ProcessManager. Process ordering information is included by using the AddProcess() and SetProcessOrdering() methods. For registration of simple processes, the AddAtRestProcess(), AddContinuousProcess() and AddDiscreteProcess() methods may be used.

G4ProcessManager is able to turn some processes on or off during a run by using the ActivateProcess() and InActivateProcess() methods. These methods are valid only after process registration is complete, so they must not be used in the *PreInit* phase.

The G4VUserPhysicsList class creates and attaches G4ProcessManager objects to all particle classes defined in the ConstructParticle () method.

# 2.5.3 Specifying Physics Processes

G4VUserPhysicsList is the base class for a "mandatory user class" (see *How to Define the main() Program*), in which all physics processes and all particles required in a simulation must be registered. The user must create a class derived from G4VUserPhysicsList and implement the pure virtual method ConstructProcess().

For example, if just the G4Geantino particle class is required, only the transportation process need be registered. The ConstructProcess() method would then be implemented as follows:

Listing 2.16: Register processes for a geantino.

```
void MyPhysicsList::ConstructProcess()
{
    // Define transportation process
    AddTransportation();
}
```

Here, the AddTransportation() method is provided in the G4VUserPhysicsList class to register the G4Transportation class with all particle classes. The G4Transportation class (and/or related classes) describes the particle motion in space and time. It is the mandatory process for tracking particles.

In the ConstructProcess() method, physics processes should be created and registered with each particle's instance of G4ProcessManager.

An example of process registration is given in the G4VUserPhysicsList::AddTransportation() method.

Registration in G4ProcessManager is a complex procedure for other processes and particles because the relations between processes are crucial for some processes. In order to ease registration procedures, G4PhysicsListHelper is provided. Users do not care about type of processes (i.e. AtRest and/or Discrete and/or Continuous ) or ordering parameters.

An example of electromagnetic process registration for the gamma is shown below

Listing 2.17: Register processes for a gamma.

```
void MyPhysicsList::ConstructProcess()
{
    // Define transportation process
    AddTransportation();
    // electromagnetic processes
    ConstructEM();
```

(continues on next page)

(continued from previous page)

```
void MyPhysicsList::ConstructEM()
{
    // Get pointer to G4PhysicsListHelper
    G4PhysicsListHelper* ph = G4PhysicsListHelper::GetPhysicsListHelper();

    // Get pointer to gamma
    G4ParticleDefinition* particle = G4Gamma::GammaDefinition();

    // Construct and register processes for gamma
    ph->RegisterProcess(new G4PhotoElectricEffect(), particle);
    ph->RegisterProcess(new G4ComptonScattering(), particle);
    ph->RegisterProcess(new G4GammaConversion(), particle);
    ph->RegisterProcess(new G4RayleighScattering(), particle);
}
```

# 2.6 How to Generate a Primary Event

# 2.6.1 Generating Primary Events

G4VuserPrimaryGeneratorAction is one of the mandatory classes available for deriving your own concrete class. In your concrete class, you have to specify how a primary event should be generated. Actual generation of primary particles will be done by concrete classes of G4VPrimaryGenerator, explained in the following subsection. Your G4VUserPrimaryGeneratorAction concrete class just arranges the way primary particles are generated.

Listing 2.18: ExG4PrimaryGeneratorAction01: An example of a G4VUserPrimaryGeneratorAction concrete class using G4ParticleGun. For the usage of G4Particle Gun refer to the next subsection.

```
// ExG4PrimaryGeneratorAction01.hh
#ifndef ExG4PrimaryGeneratorAction01_h
#define ExG4PrimaryGeneratorAction01_h 1
#include "G4VUserPrimaryGeneratorAction.hh"
#include "G4ThreeVector.hh"
#include "globals.hh"
class G4ParticleGun;
class G4Event;
class ExG4PrimaryGeneratorAction01 : public G4VUserPrimaryGeneratorAction
 public:
   ExG4PrimaryGeneratorAction01(
     const G4String& particleName = "geantino",
     G4double energy = 1.*MeV,
     G4ThreeVector position= G4ThreeVector(0,0,0),
     G4ThreeVector momentumDirection = G4ThreeVector(0,0,1));
   ~ExG4PrimaryGeneratorAction01();
   virtual void GeneratePrimaries(G4Event*);
  private:
```

(continues on next page)

(continued from previous page)

```
// data members
    G4ParticleGun* fParticleGun; //pointer a to G4 service class
};
#endif
// ExG4PrimaryGeneratorAction01.cc
#include "ExG4PrimaryGeneratorAction01.hh"
#include "G4Event.hh"
#include "G4ParticleGun.hh"
#include "G4ParticleTable.hh"
#include "G4ParticleDefinition.hh"
ExG4PrimaryGeneratorAction01::ExG4PrimaryGeneratorAction01(
                                 const G4String @ particleName,
                                 G4double energy,
                                 G4ThreeVector position,
                                 G4ThreeVector momentumDirection)
  : G4VUserPrimaryGeneratorAction(),
    fParticleGun(0)
  G4int nofParticles = 1;
  fParticleGun = new G4ParticleGun(nofParticles);
  // default particle kinematic
 G4ParticleTable* particleTable = G4ParticleTable::GetParticleTable();
 {\tt G4ParticleDefinition} * {\tt particle}
    = particleTable->FindParticle(particleName);
  fParticleGun->SetParticleDefinition(particle);
  fParticleGun->SetParticleEnergy(energy);
  fParticleGun->SetParticlePosition(position);
  fParticleGun->SetParticleMomentumDirection (momentumDirection);
{\tt ExG4PrimaryGeneratorAction01::} {\tt \sim} {\tt ExG4PrimaryGeneratorAction01()}
 delete fParticleGun;
void ExG4PrimaryGeneratorAction01::GeneratePrimaries(G4Event* anEvent)
 // this function is called at the beginning of event
  fParticleGun->GeneratePrimaryVertex(anEvent);
```

### Selection of the generator

In the constructor of your G4VUserPrimaryGeneratorAction, you should instantiate the primary generator(s). If necessary, you need to set some initial conditions for the generator(s).

In *ExG4PrimaryGeneratorAction01*, G4ParticleGun is constructed to use as the actual primary particle generator. Methods of G4ParticleGun are described in the following section. Please note that the primary generator object(s) you construct in your G4VUserPrimaryGeneratorAction concrete class must be deleted in your destructor.

#### Generation of an event

G4VUserPrimaryGeneratorAction has a pure virtual method named generatePrimaries(). This method is invoked at the beginning of each event. In this method, you have to invoke the G4VPrimaryGenerator concrete class you instantiated via the generatePrimaryVertex() method.

You can invoke more than one generator and/or invoke one generator more than once. Mixing up several generators can produce a more complicated primary event.

# 2.6.2 G4VPrimaryGenerator

GEANT4 provides three G4VPrimaryGenerator concrete classes. Among these G4ParticleGun and G4GeneralParticleSource will be discussed here. The third one is G4HEPEvtInterface, which will be discussed in *Event Generator Interface*.

#### **G4ParticleGun**

G4ParticleGun is a generator provided by GEANT4. This class generates primary particle(s) with a given momentum and position. It does not provide any sort of randomizing. The constructor of G4ParticleGun takes an integer which causes the generation of one or more primaries of exactly same kinematics. It is a rather frequent user requirement to generate a primary with randomized energy, momentum, and/or position. Such randomization can be achieved by invoking various set methods provided by G4ParticleGun. The invocation of these methods should be implemented in the generatePrimaries() method of your concrete G4VUserPrimaryGeneratorAction class before invoking generatePrimaryVertex() of G4ParticleGun. GEANT4 provides various random number generation methods with various distributions (see Global Usage Classes).

#### Public methods of G4ParticleGun

The following methods are provided by G4ParticleGun, and all of them can be invoked from the generatePrimaries() method in your concrete G4VUserPrimaryGeneratorAction class.

- void SetParticleDefinition(G4ParticleDefinition\*)
- void SetParticleMomentum(G4ParticleMomentum)
- void SetParticleMomentumDirection(G4ThreeVector)
- void SetParticleEnergy(G4double)
- void SetParticleTime(G4double)
- void SetParticlePosition(G4ThreeVector)
- void SetParticlePolarization(G4ThreeVector)
- void SetNumberOfParticles(G4int)

### **G4GeneralParticleSource**

For many applications G4ParticleGun is a suitable particle generator. However if you want to generate primary particles in more sophisticated manner, you can utilize G4GeneralParticleSource, the GEANT4 General Particle Source module (GPS), discussed in the next section ( *General Particle Source*).

# 2.7 GEANT4 General Particle Source

### 2.7.1 Introduction

The G4GeneralParticleSource (GPS) is part of the GEANT4 toolkit for Monte-Carlo, high-energy particle transport. Specifically, it allows the specifications of the spectral, spatial and angular distribution of the primary source particles. An overview of the GPS class structure is presented here. *Configuration* covers the configuration of GPS for a user application, and *Macro Commands* describes the macro command interface. *Example Macro File* gives an example input file to guide the first time user.

G4GeneralParticleSource is used exactly the same way as G4ParticleGun in a GEANT4 application. In existing applications one can simply change your PrimaryGeneratorAction by globally replacing G4ParticleGun with G4GeneralParticleSource. GPS may be configured via command line, or macro based, input. The experienced user may also hard-code distributions using the methods and classes of the GPS that are described in more detail in a technical note<sup>1</sup>.

The class diagram of GPS is shown in Fig. 2.1. As of version 10.01, a split-class mechanism was introduced to reduce memory usage in multithreaded mode. The G4GeneralParticleSourceData class is a thread-safe singleton which provides access to the source information for the G4GeneralParticleSource class. The G4GeneralParticleSourceData class can have multiple instantiations of the G4SingleParticleSource class, each with independent positional, angular and energy distributions as well as incident particle types. To the user, this change should be transparent.




Fig. 2.1: The class diagram of G4GeneralParticleSource.

<sup>&</sup>lt;sup>1</sup> General purpose Source Particle Module for GEANT4/SPARSET: Technical Note, UoS-GSPM-Tech, Issue 1.1, C Ferguson, February 2000.

# 2.7.2 Configuration

GPS allows the user to control the following characteristics of primary particles:

- Spatial sampling: on simple 2D or 3D surfaces such as discs, spheres, and boxes.
- Angular distribution: unidirectional, isotropic, cosine-law, beam or arbitrary (user defined).
- Spectrum: linear, exponential, power-law, Gaussian, blackbody, or piece-wise fits to data.
- Multiple sources: multiple independent sources can be used in the same run.

As noted above, G4GeneralParticleSource is used exactly the same way as G4ParticleGun in a GEANT4 application, and may be substituted for the latter by "global search and replace" in existing application source code.

### **Position Distribution**

The position distribution can be defined by using several basic shapes to contain the starting positions of the particles. The easiest source distribution to define is a point source. One could also define planar sources, where the particles emanate from circles, annuli, ellipses, squares or rectangles. There are also methods for defining 1D or 2D accelerator beam spots. The five planes are oriented in the x-y plane. To define a circle one gives the radius, for an annulus one gives the inner and outer radii, and for an ellipse, a square or a rectangle one gives the half-lengths in x and y.

More complicated still, one can define surface or volume sources where the input particles can be confined to either the surface of a three dimensional shape or to within its entire volume. The four 3D shapes used within G4GeneralParticleSource are sphere, ellipsoid, cylinder and parallelepiped. A sphere can be defined simply by specifying the radius. Ellipsoids are defined by giving their half-lengths in x, y and z. Cylinders are defined such that the axis is parallel to the z-axis, the user is therefore required to give the radius and the z half-length. Parallelepipeds are defined by giving x, y and z half-lengths, plus the angles  $\alpha$ ,  $\theta$ , and  $\phi$  (Fig. 2.2).




Fig. 2.2: The angles used in the definition of a Parallelepiped.

To allow easy definition of the sources, the planes and shapes are assumed to be orientated in a particular direction to the coordinate axes, as described above. For more general applications, the user may supply two vectors (x' and a vector in the plane x'-y') to rotate the co-ordinate axes of the shape with respect to the overall co-ordinate system (Fig. 2.3). The rotation matrix is automatically calculated within G4GeneralParticleSource. The starting points of particles are always distributed homogeneously over the 2D or 3D surfaces, although biasing can change this.




Fig. 2.3: An illustration of the use of rotation matrices. A cylinder is defined with its axis parallel to the z-axis (black lines), but the definition of 2 vectors can rotate it into the frame given by x', y', z' (red lines).

### **Angular Distribution**

The angular distribution is used to control the directions in which the particles emanate from/incident upon the source point. In general there are three main choices, isotropic, cosine-law or user-defined. In addition there are options for specifying parallel beam as well as diverse accelerator beams. The isotropic distribution represents what would be seen from a uniform  $4\pi$  flux. The cosine-law represents the distribution seen at a plane from a uniform  $2\pi$  flux.

It is possible to bias (*Biasing*) both  $\theta$  and  $\phi$  for any of the predefined distributions, including setting lower and upper limits to  $\theta$  and  $\phi$ . User-defined distributions cannot be additionally biased (any bias should obviously be incorporated into the user definition).

Incident with zenith angle  $\theta = 0$  means the particle is travelling along the -z axis. It is important to bear this in mind when specifying user-defined co-ordinates for angular distributions. The user must be careful to rotate the co-ordinate axes of the angular distribution if they have rotated the position distribution (Fig. 2.3).

The user defined distribution requires the user to enter a histogram in either  $\theta$  or  $\phi$  or both. The user-defined distribution may be specified either with respect to the coordinate axes or with respect to the surface-normal of a shape or volume. For the surface-normal distribution,  $\theta$  should only be defined between 0 and  $\pi/2$ , not the usual 0 to  $\pi$  range.

The top-level /gps/direction command uses direction cosines to specify the primary particle direction, as follows:

$$P_x = -\sin\theta\cos\phi$$

$$P_y = -\sin\theta\sin\phi$$

$$P_z = -\cos\theta$$
(2.1)

### **Energy Distribution**

The energy of the input particles can be set to follow several built-in functions or a user-defined one, as shown in Table 2.1. The user can bias any of the pre-defined energy distributions in order to speed up the simulation (user-defined distributions are already biased, by construction).

Spectrum	Abbreviation	Functional Form	User Parameters
mono-energetic	Mono	$I \propto \delta(E - E_0)$	Energy $E_0$
linear	Lin	$I \propto I_0 + m \times E$	Intercept $I_0$ , slope $m$
exponential	Exp	$I \propto \exp(-E/E_0)$	Energy scale-height $E_0$
power-law	Pow	$I \propto E^{\alpha}$	Spectral index $\alpha$
Gaussian	Gauss	$I = (2\pi\sigma)^{-\frac{1}{2}} \exp[-(E/E_0)^2/\sigma^2]$	Mean energy $E_0$ , standard
			deviation $\sigma$
bremsstrahlung	Brem	$I = \int 2E^2 [h^2 c^2 (\exp(-E/kT) - 1)]^{-1}$	Temperature $T$
black body	Bbody	$I \propto (kT)^{\frac{1}{2}} E \exp(-E/kT)$	Temperature $T$ (see text)
cosmic diffuse	Cdg	$I \propto [(E/E_b)^{\alpha_1} + (E/E_b)^{\alpha_2}]^{-1}$	Energy range $E_{\min}$ to $E_{\max}$ ;
gamma ray			energy $E_b$ and indices $\alpha_1$
			and $\alpha_2$ are fixed (see text)

Table 2.1: Energy distribution commands.

There is also the option for the user to define a histogram in energy ("User") or energy per nucleon ("Epn") or to give an arbitrary point-wise spectrum ("Arb") that can be fit with various simple functions. The data for histograms or point spectra must be provided in ascending bin (abscissa) order. The point-wise spectrum may be differential (as with a binned histogram) or integral (a cumulative distribution function). If integral, the data must satisfy  $s(e1) \geq s(e2)$  for e1 < e2 when entered; this is not validated by the GPS code. The maximum energy of an integral spectrum is defined by the last-but-one data point, because GPS converts to a differential spectrum internally.

Unlike the other spectral distributions it has proved difficult to integrate indefinitely the black-body spectrum and this has lead to an alternative approach. Instead it has been decided to use the black-body formula to create a 10,000 bin histogram and then to produce random energies from this.

Similarly, the broken power-law for cosmic diffuse gamma rays makes generating an indefinite integral CDF problematic. Instead, the minimum and maximum energies specified by the user are used to construct a definite-integral CDF from which random energies are selected.

### **Biasing**

The user can bias distributions by entering a histogram. It is the random numbers from which the quantities are picked that are biased and so one only needs a histogram from 0 to 1. Great care must be taken when using this option, as the way a quantity is calculated will affect how the biasing works, as discussed below. Bias histograms are entered in the same way as other user-defined histograms.

When creating biasing histograms it is important to bear in mind the way quantities are generated from those numbers. For example let us compare the biasing of a  $\theta$  distribution with that of a  $\phi$  distribution. Let us divide the  $\theta$  and  $\phi$  ranges up into 10 bins, and then decide we want to restrict the generated values to the first and last bins. This gives a new  $\phi$  range of 0 to 0.628 and 5.655 to 6.283. Since  $\phi$  is calculated using  $\phi = 2\pi \times \text{RNDM}$ , this simple biasing will work correctly.

If we now look at  $\theta$ , we expect to select values in the two ranges 0 to 0.314 (for  $0 \le \text{RNDM} \le 0.1$ ) and 2.827 to 3.142 (for  $0 \le \text{RNDM} \le 0.9$ ). However, the polar angle  $\theta$  is calculated from the formula  $\theta = \arccos(1-2\times \text{RNDM})$ . From this, we see that 0.1 gives a  $\theta$  of 0.644 and a RNDM of 0.9 gives a  $\theta$  of 2.498. This means that the above will not bias the distribution as the user had wished. The user must therefore take into account the method used to generate random quantities when trying to apply a biasing scheme to them. Some quantities such as x, y, z and  $\phi$  will be relatively easy to bias, but others may require more thought.

## **User-Defined Histograms**

The user can define histograms for several reasons: angular distributions in either  $\theta$  or  $\phi$ ; energy distributions; energy per nucleon distributions; or biasing of x, y, z,  $\theta$ ,  $\phi$ , or energy. Even though the reasons may be different the approach is the same.

To choose a histogram the command /gps/hist/type is used (*Macro Commands*). If one wanted to enter an angular distribution one would type "theta" or "phi" as the argument. The histogram is loaded, one bin at a time, by using the /gps/hist/point command, followed by its two arguments the upper boundary of the bin and the weight (or area) of the bin. Histograms are therefore differential functions.

Currently histograms are limited to 1024 bins. The first value of each user input data pair is treated as the upper edge of the histogram bin and the second value is the bin content. The exception is the very first data pair the user input whose first value is the treated as the lower edge of the first bin of the histogram, and the second value is not used. This rule applies to all distribution histograms, as well as histograms for biasing.

The user has to be aware of the limitations of histograms. For example, in general  $\theta$  is defined between 0 and  $\pi$  and  $\phi$  is defined between 0 and  $2\pi$ , so histograms defined outside of these limits may not give the user what they want (see also *Biasing*).

### 2.7.3 Macro Commands

G4GeneralParticleSource can be configured by typing commands from the /gps command directory tree, or including the /gps commands in a g4macro file.

## G4ParticleGun equivalent commands

	14010 2	3.2. Off after of court equivalent communities.
Command	Arguments	Description and restrictions
/gps/List		List available incident particles
/gps/particle	name	Defines the particle type [default geantino], using GEANT4 naming con-
		vention.
/gps/direction	Px Py Pz	Set the momentum direction [default (1,0,0)] of generated particles us-
		ing (2.1)
/gps/energy	E unit	Sets the energy [default 1 MeV] for mono-energetic sources. The units
		can be eV, keV, MeV, GeV, TeV or PeV. (NB: it is recommended to use
		/gps/ene/mono instead.)
/gps/position	X Y Z unit	Sets the centre co-ordinates $(X,Y,Z)$ of the source [default $(0,0,0)$ cm].
		The units can be micron, mm, cm, m or km. (NB: it is recommended to
		use /gps/pos/centre instead.)
/gps/ion	ZAQE	After /gps/particle ion, sets the properties (atomic number Z,
		atomic mass A, ionic charge Q, excitation energy E in keV) of the ion.
/gps/ionLvl	Z A Q lvl	After /gps/particle ion, sets the properties (atomic number Z,
		atomic mass A, ionic charge Q, Number of metastable state excitation
		level (0-9) of the ion.
/gps/time	t0 unit	Sets the primary particle (event) time [default 0 ns]. The units can be
		ps, ns, us, ms, or s.
/gps/polarization	Px Py Pz	Sets the polarization vector of the source, which does not need to be a
		unit vector.
/gps/number	N	Sets the number of particles [default 1] to simulate on each event.
/gps/verbose	level	Control the amount of information printed out by the GPS code. Larger
		values produce more detailed output.

Table 2.2: G4ParticleGun equivalent commands.

# **Multiple source specification**

Table 2.3: Multiple source specification.

Command	Arguments	Description and restrictions
/gps/source/add	intensity	Add a new particle source with the specified intensity
/gps/source/list		List the particle sources defined.
/gps/source/clear		Remove all defined particle sources.
/gps/source/show		Display the current particle source
/gps/source/set	index	Select the specified particle source as the current one.
/gps/source/delete	index	Remove the specified particle source.
/gps/source/ multiplevertex	flag	Specify <i>true</i> for simultaneous generation of multiple vertices, one from
		each specified source. False [default] generates a single vertex, choos-
		ing one source randomly.
/gps/source/ intensity	intensity	Reset the current source to the specified intensity
/gps/source/ flatsampling	flag	Set to True to allow biased sampling among the sources. Setting to True
		will ignore source intensities. The default is False.

# Source position and structure

Table 2.4: Source position and structure.

gps/pos/tshape   dist   Sets the source positional distribution type: Point [default], Plane, Beam, Surface, Volume.	Command	Arguments	Description and restrictions
Sets the source shape type, after / gps/pos/type has been used. For a Plane this can be Circle, Annulus, Ellipse, Square, Rectangle. For both Surface or Volume sources this can be Sphere, Ellipsoid, Cylinder, Para (parallelepiped).    Sets the centre co-ordinates (X,Y,Z) of the source [default (0,0,0) cm]. The units can only be micron, mm, cm, m or km.    Sets the centre co-ordinates (X,Y,Z) of the source [default (0,0,0) cm]. The units can only be micron, mm, cm, m or km.    Sets the second vector R1 [default (1,0,0)], which does not need to be a unit vector, and is used together with / gps/pos/rot2 coeate the rotation matrix of the shape defined with / gps/pos/rot1 to create the rotation matrix of the shape defined with / gps/pos/rot1 to create the rotation matrix of the shape defined with / gps/pos/halfx   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Sets the half-length in z [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Sets the half-length in z [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Sets the alfise default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Sets the alfise default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Sets the rains default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    Sets the rains default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    Sets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km.    Sets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km.    Sets deviated to the surface of the face at to the centre of the face at to the	/gps/pos/type	dist	Sets the source positional distribution type: Point [default], Plane,
a Plane this can be Circle, Annulus, Ellipse, Square, Rectangle. For both Surface or Volume sources this can be Sphere. Ellipsoid. Cylinder, Para (parallelepiped).  /gps/pos/centre X Y Z unit Sets the centre co-ordinates (X,Y,Z) of the source [default (0,0,0) cm]. The units can only be micron, mm, cm, m or km.  /gps/pos/rot1 R1 <sub>x</sub> R1 <sub>y</sub> R1 <sub>z</sub> Defines the first (x' direction) vector R1 [default (1,0,0)], which does not need to be a unit vector, and is used together with /gps/pos/shape.  /gps/pos/rot2 R2 <sub>x</sub> R2 <sub>y</sub> R2 <sub>z</sub> Defines the second vector R2 in the xy plane [default (0,1,0)], which does not need to be a unit vector, and is used together with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/pos/shape.  /gps/pos/halfx len unit Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.  /gps/pos/halfz len unit Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.  /gps/pos/radius len unit Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.  /gps/pos/sigma_r sigma unit Sets the inner radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.  /gps/pos/sigma_x sigma unit Sets the inner radius [default 0 cm] of post post post post post post post post			Beam, Surface, Volume.
both Surface or Volume sources this can be Sphere, Ellipsoid, Cylinder, Para (parallelepiped).	/gps/pos/shape	shape	Sets the source shape type, after /gps/pos/type has been used. For
Para (parallelepiped).   Sets the centre co-ordinates (X,Y,Z) of the source [default (0,0,0) cm]. The units can only be micron, mm, cm, m or km.			a Plane this can be Circle, Annulus, Ellipse, Square, Rectangle. For
/gps/pos/centre         X Y Z unit         Sets the centre co-ordinates (X, Y, Z) of the source [default (0,0,0) cm]. The units can only be micron, mm, cm, m or km.           /gps/pos/rot1         R1 <sub>x</sub> R1 <sub>y</sub> R1 <sub>z</sub> Defines the first (x' direction) vector R1 [default (1,0,0)], which does not need to be a unit vector, and is used together with /gps/pos/shape.           /gps/pos/rot2         R2 <sub>x</sub> R2 <sub>y</sub> R2 <sub>z</sub> Defines the second vector R2 in the xy plane [default (0,1,0)], which does not need to be a unit vector, and is used together with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/pos/ps/ps/ps/ps/ps/ps/ps/ps/ps/ps/ps/ps/ps			both Surface or Volume sources this can be Sphere, Ellipsoid, Cylinder,
The units can only be micron, mm, cm, m or km.			Para (parallelepiped).
gps/pos/rot1   R1x R1y R1z   Defines the first (x' direction) vector R1 [default (1,0,0)], which does not need to be a unit vector, and is used together with /qps/pos/shape.	/gps/pos/centre	X Y Z unit	Sets the centre co-ordinates $(X,Y,Z)$ of the source [default $(0,0,0)$ cm].
not need to be a unit vector, and is used together with /gps/pos/rot2 to create the rotation matrix of the shape defined with /gps/shape.    Pags/pos/rot2   R2x R2y R2z   Defines the second vector R2 in the xy plane [default (0,1,0)], which does not need to be a unit vector, and is used together with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/pos/hape.    Pags/pos/halfx   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Pags/pos/halfy   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Pags/pos/halfz   len unit   Sets the half-length in z [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Pags/pos/radius   len unit   Sets the half-length in z [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    Pags/pos/radius   len unit   Sets the radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    Pags/pos/sigma_r   sigma unit   Sets the transverse (radial) standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km.    Pags/pos/sigma_y   sigma unit   Sets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km.    Pags/pos/paralp   alpha unit   Sets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km.    Pags/pos/paralp   alpha unit   Sets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be deg or rad.    Pags/pos/paralp   Alpha unit   Sets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be deg or rad.    Pags/pos/paralp   Alpha unit   Sets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be de			The units can only be micron, mm, cm, m or km.
gps/pos/rot2   R2x R2y R2z   Defines the second vector R2 in the xy plane [default (0,1,0)], which does not need to be a unit vector, and is used together with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/pos/pos/halfx   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.	/gps/pos/rot1	$R1_x R1_y R1_z$	Defines the first (x' direction) vector R1 [default (1,0,0)], which does
Shape.   Defines the second vector R2 in the xy plane [default (0,1,0)], which does not need to be a unit vector, and is used together with /gps/pos/rctl to create the rotation matrix of the shape defined with /gps/pos/halfx   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.		-	not need to be a unit vector, and is used together with /gps/pos/
gps/pos/rot2   R2x R2y R2z   Defines the second vector R2 in the xy plane [default (0,1,0)], which does not need to be a unit vector, and is used together with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/pos/halfx   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.			rot2 to create the rotation matrix of the shape defined with /gps/
does not need to be a unit vector, and is used together with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/shape.    does not need to be a unit vector, and is used together with /gps/pos/rot1 to create the rotation matrix of the shape defined with /gps/pos/halfx   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.    default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km.    default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km.    default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km.    default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km.    default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km.    default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km.    defaul			shape.
pos/rot1 to create the rotation matrix of the shape defined with / gps/pos/halfx   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.	/gps/pos/rot2	R2 <sub>x</sub> R2 <sub>y</sub> R2 <sub>z</sub>	Defines the second vector R2 in the xy plane [default (0,1,0)], which
gps/pos/halfx   len unit   Sets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km.		j	does not need to be a unit vector, and is used together with /gps/
/gps/pos/halfxlen unitSets the half-length in x [default 0 cm] of the source. The units can only be micron, mm, cm, m or km./gps/pos/halfylen unitSets the half-length in y [default 0 cm] of the source. The units can only be micron, mm, cm, m or km./gps/pos/halfzlen unitSets the half-length in z [default 0 cm] of the source. The units can only be micron, mm, cm, m or km./gps/pos/radiuslen unitSets the radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km./gps/pos/inner_radiuslen unitSets the inner radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km./gps/pos/sigma_rsigma unitSets the transverse (radial) standard deviation [default 0 cm] of beam position profile. The units can only be micron, mm, cm, m or km./gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/pos/pos/paralpsigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/pos/pos/parphitheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] φ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/confinephi unitUsed with a Parallelepiped. The azimuth			pos/rot1 to create the rotation matrix of the shape defined with /
be micron, mm, cm, m or km.			gps/shape.
/gps/pos/halfylen unitSets the half-length in y [default 0 cm] of the source. The units can only be micron, mm, cm, m or km./gps/pos/halfzlen unitSets the half-length in z [default 0 cm] of the source. The units can only be micron, mm, cm, m or km./gps/pos/radiuslen unitSets the radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km./gps/pos/sipner_radiuslen unitSets the inner radius [default 0 cm] for annuli. The units can only be micron, mm, cm, m or km./gps/pos/sigma_rsigma unitSets the transverse (radial) standard deviation [default 0 cm] of beam position profile. The units can only be micron, mm, cm, m or km./gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/pos/paralpsigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/pos/parphitheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/confinephi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.	/gps/pos/halfx	len unit	Sets the half-length in x [default 0 cm] of the source. The units can only
be micron, mm, cm, m or km.			be micron, mm, cm, m or km.
/gps/pos/halfzlen unitSets the half-length in z [default 0 cm] of the source. The units can only be micron, mm, cm, m or km./gps/pos/radiuslen unitSets the radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km./gps/pos/inner_radiuslen unitSets the inner radius [default 0 cm] for annuli. The units can only be micron, mm, cm, m or km./gps/pos/sigma_rsigma unitSets the inner radius [default 0 cm] for annuli. The units can only be micron, mm, cm, m or km./gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/sigma_ysigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parphitheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] φ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/pos/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confineAllows the user to confine the source to the physical volume name [de-	/gps/pos/halfy	len unit	Sets the half-length in y [default 0 cm] of the source. The units can only
be micron, mm, cm, m or km.  /gps/pos/radius  len unit  Sets the radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km.  /gps/pos/sigma_r sigma unit  /gps/pos/sigma_x sigma unit  /gps/pos/sigma_y sigma unit  /gps/pos/pos/paralp alpha unit  /gps/pos/paralp theta unit  /gps/pos/confine theta unit  /gps/pos/confine theta unit			be micron, mm, cm, m or km.
/gps/pos/radiuslen unitSets the radius [default 0 cm] of the source or the outer radius for annuli. The units can only be micron, mm, cm, m or km./gps/pos/inner_radiuslen unitSets the inner radius [default 0 cm] for annuli. The units can only be micron, mm, cm, m or km./gps/pos/sigma_rsigma unitSets the transverse (radial) standard deviation [default 0 cm] of beam position profile. The units can only be micron, mm, cm, m or km./gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/sigma_ysigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parphiUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/confineUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confineAllows the user to confine the source to the physical volume name [de-	/gps/pos/halfz	len unit	Sets the half-length in z [default 0 cm] of the source. The units can only
The units can only be micron, mm, cm, m or km.  /gps/pos/inner_radius len unit /gps/pos/sigma_r sigma unit /gps/pos/sigma_x sigma unit /gps/pos/sigma_x sigma unit /gps/pos/sigma_y sigma unit /gps/pos/pos/paralp alpha unit /gps/pos/paralp theta unit /gps/pos/confine phi unit /gps/pos/confine Allows the user to confine the source to the physical volume name [de-			
/gps/pos/inner_radiuslen unitSets the inner radius [default 0 cm] for annuli. The units can only be micron, mm, cm, m or km./gps/pos/sigma_rsigma unitSets the transverse (radial) standard deviation [default 0 cm] of beam position profile. The units can only be micron, mm, cm, m or km./gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/sigma_ysigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parthetheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confineAllows the user to confine the source to the physical volume name [de-	/gps/pos/radius	len unit	Sets the radius [default 0 cm] of the source or the outer radius for annuli.
/gps/pos/sigma_rsigma unitSets the transverse (radial) standard deviation [default 0 cm] of beam position profile. The units can only be micron, mm, cm, m or km./gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/sigma_ysigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parthetheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confineAllows the user to confine the source to the physical volume name [de-			The units can only be micron, mm, cm, m or km.
/gps/pos/sigma_rsigma unitSets the transverse (radial) standard deviation [default 0 cm] of beam position profile. The units can only be micron, mm, cm, m or km./gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/sigma_ysigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parthetheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confineAllows the user to confine the source to the physical volume name [de-	/gps/pos/inner_radius	len unit	Sets the inner radius [default 0 cm] for annuli. The units can only be
position profile. The units can only be micron, mm, cm, m or km.			micron, mm, cm, m or km.
/gps/pos/sigma_xsigma unitSets the standard deviation [default 0 cm] of beam position profile in x-direction. The units can only be micron, mm, cm, m or km./gps/pos/sigma_ysigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parthetheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confinenameAllows the user to confine the source to the physical volume name [de-	/gps/pos/sigma_r	sigma unit	Sets the transverse (radial) standard deviation [default 0 cm] of beam
x-direction. The units can only be micron, mm, cm, m or km.  Sets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km.  /gps/pos/paralp  alpha unit  Used with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad.  /gps/pos/parthe  theta unit  Used with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad.  /gps/pos/parphi  phi unit  Used with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.  /gps/pos/confine  Allows the user to confine the source to the physical volume name [de-			
/gps/pos/sigma_ysigma unitSets the standard deviation [default 0 cm] of beam position profile in y-direction. The units can only be micron, mm, cm, m or km./gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] α formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parthetheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confinenameAllows the user to confine the source to the physical volume name [de-	/gps/pos/sigma_x	sigma unit	Sets the standard deviation [default 0 cm] of beam position profile in
y-direction. The units can only be micron, mm, cm, m or km.  /gps/pos/paralp  alpha unit  Used with a Parallelepiped. The angle [default 0 rad] $\alpha$ formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad.  /gps/pos/parthe  theta unit  Used with a Parallelepiped. Polar angle [default 0 rad] $\theta$ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad.  /gps/pos/parphi  phi unit  Used with a Parallelepiped. The azimuth angle [default 0 rad] $\phi$ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.  /gps/pos/confine  Allows the user to confine the source to the physical volume name [de-			x-direction. The units can only be micron, mm, cm, m or km.
/gps/pos/paralpalpha unitUsed with a Parallelepiped. The angle [default 0 rad] $\alpha$ formed by the y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad./gps/pos/parthetheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] $\theta$ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] $\phi$ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confinenameAllows the user to confine the source to the physical volume name [de-	/gps/pos/sigma_y	sigma unit	Sets the standard deviation [default 0 cm] of beam position profile in
y-axis and the plane joining the centre of the faces parallel to the zx plane at y and +y. The units can only be deg or rad.  /gps/pos/parthe theta unit Used with a Parallelepiped. Polar angle [default 0 rad] $\theta$ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad.  /gps/pos/parphi phi unit Used with a Parallelepiped. The azimuth angle [default 0 rad] $\phi$ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.  /gps/pos/confine name Allows the user to confine the source to the physical volume name [de-			y-direction. The units can only be micron, mm, cm, m or km.
plane at y and +y. The units can only be deg or rad.  /gps/pos/parthe  theta unit  Used with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad.  /gps/pos/parphi  phi unit  Used with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.  /gps/pos/confine  name  Allows the user to confine the source to the physical volume name [de-	/gps/pos/paralp	alpha unit	
/gps/pos/parthetheta unitUsed with a Parallelepiped. Polar angle [default 0 rad] θ of the line connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad./gps/pos/parphiphi unitUsed with a Parallelepiped. The azimuth angle [default 0 rad] φ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad./gps/pos/confinenameAllows the user to confine the source to the physical volume name [de-			y-axis and the plane joining the centre of the faces parallel to the zx
connecting the centre of the face at z to the centre of the face at +z. The units can only be deg or rad.  /gps/pos/parphi  phi unit  Used with a Parallelepiped. The azimuth angle [default 0 rad] $\phi$ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.  /gps/pos/confine  name  Allows the user to confine the source to the physical volume <i>name</i> [de-			plane at y and +y. The units can only be deg or rad.
$\begin{array}{cccccccccccccccccccccccccccccccccccc$	/gps/pos/parthe	theta unit	
/gps/pos/parphi phi unit Used with a Parallelepiped. The azimuth angle [default 0 rad] $\phi$ of the line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.  /gps/pos/confine name Allows the user to confine the source to the physical volume name [de-			
line connecting the centre of the face at z with the centre of the face at +z. The units can only be deg or rad.  /gps/pos/confine name Allows the user to confine the source to the physical volume <i>name</i> [de-			
+z. The units can only be deg or rad.  /gps/pos/confine name Allows the user to confine the source to the physical volume <i>name</i> [de-	/gps/pos/parphi	phi unit	
/gps/pos/confine name Allows the user to confine the source to the physical volume name [de-			
fault NULL].	/gps/pos/confine	name	
			fault NULL].

# Source direction and angular distribution

Table 2.5: Source direction and angular distribution.

Command	Arguments	Description and restrictions
/gps/ang/type	AngDis	Sets the angular distribution type (iso [default], cos, planar, beam1d,
		beam2d, focused, user) to either isotropic, cosine-law or user-defined.
/gps/ang/rot1	AR1 <sub>x</sub> AR1 <sub>y</sub> AR1 <sub>z</sub>	Defines the first (x' direction) rotation vector AR1 [default (1,0,0)] for
		the angular distribution and is not necessarily a unit vector. Used with
		/gps/ang/rot2 to compute the angular distribution rotation matrix.
/gps/ang/rot2	AR2 <sub>x</sub> AR2 <sub>y</sub> AR2 <sub>z</sub>	Defines the second rotation vector AR2 in the xy plane [default $(0,1,0)$ ]
		for the angular distribution, which does not necessarily have to be a unit
		vector. Used with /gps/ang/rot2 to compute the angular distribu-
		tion rotation matrix.
/gps/ang/mintheta	MinTheta unit	Sets a minimum value [default 0 rad] for the $\theta$ distribution. Units can
		be deg or rad.
/gps/ang/maxtheta	MaxTheta unit	Sets a maximum value [default $\pi$ rad] for the $\theta$ distribution. Units can
		be deg or rad.
/gps/ang/minphi	MinPhi unit	Sets a minimum value [default 0 rad] for the $\phi$ distribution. Units can
		be deg or rad.
/gps/ang/maxphi	MaxPhi unit	Sets a maximum value [default $2\pi$ rad] for the $\phi$ distribution. Units can
		be deg or rad.
/gps/ang/sigma_r	sigma unit	Sets the standard deviation [default 0 rad] of beam directional profile in
		radial. The units can only be deg or rad.
/gps/ang/sigma_x	sigma unit	Sets the standard deviation [default 0 rad] of beam directional profile in
		x-direction. The units can only be deg or rad.
/gps/ang/sigma_y	sigma unit	Sets the standard deviation [default 0 rad] of beam directional profile in
		y-direction. The units can only be deg or rad.
/gps/ang/focuspoint	X Y Z unit	Set the focusing point $(X,Y,Z)$ for the beam [default $(0,0,0)$ cm]. The
		units can only be micron, mm, cm, m or km.
/gps/ang/user_coor	bool	Calculate the angular distribution with respect to the user defined co-
		ordinate system ( <i>true</i> ), or with respect to the global co-ordinate system
		(false, default).
/gps/ang/surfnorm	bool	Allows user to choose whether angular distributions are with respect
		to the co-ordinate system (false, default) or surface normals (true) for
		user-defined distributions.

# **Energy spectra**

Table 2.6: Source energy spectra.

Command	Arguments	Description and restrictions
/gps/ene/type	EnergyDis	Sets the energy distribution type to one of (see Table Table 2.1): <i>Mono</i>
		(mono-energetic, default), Lin (linear), Pow (power-law), Exp (ex-
		ponential), Gaussian), Brem (bremsstrahlung), Bbody (black-
		body), Cdg (cosmic diffuse gamma-ray), User (user-defined his-
		togram), Arb (point-wise spectrum), Epn (energy-per-nucleon his-
		togram)
/gps/ene/min	Emin unit	Sets the minimum [default 0 keV] for the energy distribution. The units
		can be eV, keV, MeV, GeV, TeV or PeV.
/gps/ene/max	Emax unit	Sets the maximum [default 0 keV] for the energy distribution. The units
		can be eV, keV, MeV, GeV, TeV or PeV.
/gps/ene/mono	E unit	Sets the energy [default 1 MeV] for mono-energetic sources. The units
		can be eV, keV, MeV, GeV, TeV or PeV.
/gps/ene/sigma	sigma unit	Sets the standard deviation [default 0 keV] in energy for Gaussian or
		Mono energy distributions. The units can be eV, keV, MeV, GeV, TeV
		or PeV.
/gps/ene/alpha	alpha	Sets the exponent $\alpha$ [default 0] for a power-law distribution.
/gps/ene/temp	T	Sets the temperature in kelvins [default 0] for black body and
		bremsstrahlung spectra.
/gps/ene/ezero	E0	Sets scale E <sub>0</sub> [default 0] for exponential distributions.
/gps/ene/gradient	gradient	Sets the gradient (slope) [default 0] for linear distributions.
/gps/ene/intercept	intercept	Sets the Y-intercept [default 0] for the linear distributions.
/gps/ene/biasAlpha	alpha	Sets the exponent $\alpha$ [default 0] for a biased power-law distribution. Bias
		weight is determined from the power-law probability distribution.
/gps/ene/calculate		Prepares integral PDFs for the internally-binned cosmic diffuse gamma
		ray $(Cdg)$ and black body $(Bbody)$ distributions.
/gps/ene/emspec	bool	Allows user to specify distributions are in momentum (false) or energy
		(true, default). Only valid for User and Arb distributions.
/gps/ene/diffspec	bool	Allows user to specify whether a point-wise spectrum is integral (false)
		or differential (true, default). The integral spectrum is only usable for
		<i>Arb</i> distributions.

# User-defined histograms and interpolated functions

		1
Command	Arguments	Description and restrictions
/gps/hist/type	type	Set the histogram type: predefined biasx [default], biasy, biasz, biast
		(angle $\theta$ , biasp (angle $\phi$ ), biaspt (position $\theta$ , biaspp (position $\phi$ ), bi-
		ase; user-defined histograms theta, phi, energy, arb (point-wise), epn
		(energy per nucleon).
/gps/hist/reset	type	Re-set the specified histogram: biasx [default], , biasy, biasz, biast, bi-
		asp, biaspt, biaspp, biase, theta, phi, energy, arb, epn.
/gps/hist/point	E <sub>hi</sub> Weight	Specify one entry (with contents Weight) in a histogram (where Ehi
		is the bin upper edge) or point-wise distribution (where $E_{hi}$ is the ab-
		scissa). The abscissa E <sub>hi</sub> must be in GEANT4 default units (MeV for
		energy, rad for angle).
/gps/hist/file	HistFile	Import an arbitrary energy histogram in an ASCII file. The format
		should be one $E_{hi}$ Weight pair per line of the file, following the detailed
		instructions in User-defined histograms and interpolated functions For
		histograms, E <sub>hi</sub> is the bin upper edge, for point-wise distributions E <sub>hi</sub> is
		the abscissa. The abscissa E <sub>hi</sub> must be in GEANT4 default units (MeV
		for energy, rad for angle).
/gps/hist/inter	type	Sets the interpolation type (Lin linear, Log logarithmic, Exp exponen-
		tial, <i>Spline</i> cubic spline) for point-wise spectra. This command <b>must</b> be
		issued immediately after the last data point.

Table 2.7: User defined histograms and interpolated functions.

# 2.7.4 Example Macro File

```
# Macro test2.g4mac
/control/verbose 0
/tracking/verbose 0
/event/verbose 0
/gps/verbose 2
/gps/particle gamma
/gps/pos/type Plane
/gps/pos/shape Square
/gps/pos/centre 1 2 1 cm
/gps/pos/halfx 2 cm
/gps/pos/halfy 2 cm
/gps/ang/type cos
/gps/ene/type Lin
/gps/ene/min 2 MeV
/gps/ene/max 10 MeV
/gps/ene/gradient 1
/qps/ene/intercept 1
/run/beamOn 10000
```

The above macro defines a planar source, square in shape, 4 cm by 4 cm and centred at (1,2,1) cm. By default the normal of this plane is the z-axis. The angular distribution is to follow the cosine-law. The energy spectrum is linear, with gradient and intercept equal to 1, and extends from 2 to 10 MeV. 10,000 primaries are to be generated.

The standard GEANT4 output should show that the primary particles start from between 1, 0, 1 and 3, 4, 1 (in cm) and have energies between 2 and 10 MeV, as shown in Fig. 2.4, in which we plotted the actual energy, position and angular distributions of the primary particles generated by the above macro file.




Fig. 2.4: Energy, position and angular distributions of the primary particles as generated by the macro file shown above.

# 2.8 How to Make an Executable Program

The code for the user examples in Geant4 is placed in the subdirectory examples of the main Geant4 source package. This directory is installed to the share/Geant4-G4VERSION/examples (where G4VERSION is the Geant4 version number) subdirectory under the installation prefix. In the following section, a quick overview will be given on how to build a concrete example, "ExampleB1", which is part of the Geant4 distribution, using CMake.

# 2.8.1 Using CMake to Build Applications

Geant4 installs a file named Geant4Config.cmake located in

```
+- CMAKE_INSTALL_PREFIX
+- lib/
+- Geant4-G4VERSION/
+- Geant4Config.cmake
```

which is designed for use with the CMake find\_package command. Building a Geant4 application using CMake therefore involves writing a CMakeLists.txt script using this and other CMake commands to locate Geant4 and describe the build of your client application. Whilst it requires a bit of effort to write the script, CMake provides a very friendly yet powerful tool, especially if you are working on multiple platforms. It is therefore the method we recommend for building Geant4 applications.

We'll use Basic Example B1, which you may find in the Geant4 source directory under examples/basic/B1, to demonstrate the use of CMake to build a Geant4 application. You'll find links to the latest CMake documentation for the commands used throughout, so please follow these for further information. The application sources and scripts are arranged in the following directory structure:

```
+- B1/
+- CMakeLists.txt
+- exampleB1.cc
+- include/

(continues on next page)
```

(continued from previous page)

```
| ... headers.hh ...
+- src/
... sources.cc ...
```

Here, exampleB1.cc contains main() for the application, with include/ and src/ containing the implementation class headers and sources respectively. This arrangement of source files is not mandatory when building with CMake, apart from the location of the CMakeLists.txt file in the root directory of the application.

The text file CMakeLists.txt is the CMake script containing commands which describe how to build the exampleB1 application

```
cmake_minimum_required(VERSION 3.16...3.21)
project (B1)
option (WITH_GEANT4_UIVIS "Build example with Geant4 UI and Vis drivers" ON)
if (WITH_GEANT4_UIVIS)
  find_package(Geant4 REQUIRED ui_all vis_all)
else()
 find_package(Geant4 REQUIRED)
endif()
include(${Geant4_USE_FILE})
include_directories(${PROJECT_SOURCE_DIR}/include)
file(GLOB sources ${PROJECT_SOURCE_DIR}/src/*.cc)
file(GLOB headers ${PROJECT_SOURCE_DIR}/include/*.hh)
add_executable(exampleB1 exampleB1.cc ${sources} ${headers})
target_link_libraries(exampleB1 ${Geant4_LIBRARIES})
set (EXAMPLEB1_SCRIPTS
 exampleB1.in
  exampleB1.out
  init_vis.mac
  run1.mac
  run2.mac
  vis.mac
foreach(_script ${EXAMPLEB1_SCRIPTS})
  configure_file(
    ${PROJECT_SOURCE_DIR}/${_script}
${PROJECT_BINARY_DIR}/${_script}
    )
endforeach()
install (TARGETS exampleB1 DESTINATION bin)
```

For clarity, the above listing has stripped out the main comments (CMake comments begin with a "#") you'll find in the actual file to highlight each distinct task:

#### 1. Basic Configuration

The <code>cmake\_minimum\_required</code> command and <code>if</code> block simply ensures we're using a suitable version of CMake and that it has been setup appropriately. The <code>project</code> command sets the name of the project and enables and configures C and C++ compilers.

2. Find and Configure Geant4

The aforementioned find\_package command is used to locate and configure Geant4 (we'll see how to specify the location later when we run CMake), the REQUIRED argument being supplied so that CMake will fail with an error if it cannot find Geant4. The option command specifies a boolean variable which defaults to ON, and which can be set when running CMake via a -D command line argument, or toggled in the CMake GUI interfaces. We wrap the calls to find\_package in a conditional block on the option value. This allows us to configure the use of Geant4 UI and Visualization drivers by exampleB1 via the ui\_all vis\_all "component" arguments to find\_package. An overview of available components is provided *Use of Geant4Config.cmake with find package in CMake* with a full listing at the top of the installed Geant 4Config.cmake file.

3. Configure the Project to Use Geant4 and B1 Headers

To automatically configure the header path, and force setting of compiler flags and compiler definitions needed for compiling against Geant4, we use the include command to load a CMake script supplied by Geant4. The CMake variable named Geant4\_USE\_FILE is set to the path to this module when Geant4 is located by find\_package. We use the include\_directories command to add the B1 header directory to the compiler's header search path. The CMake variable PROJECT\_SOURCE\_DIR points to the top level directory of the project and is set by the earlier call to the project command.

4. List the Sources to Build the Application

Use the globbing functionality of the file command to prepare lists of the B1 source and header files.

Note however that CMake globbing is only used here as a convenience. The expansion of the glob *only happens when CMake is run*, so if you later add or remove files, the generated build scripts will not know a change has taken place. Kitware strongly recommend listing sources explicitly as CMake automatically makes the build depend on the CMakeLists.txt file. This means that if you explicitly list the sources in CMakeLists.txt, any changes you make will be automatically picked up when you rebuild. This is also useful when you are working on a project with sources under version control and multiple contributors to ensure traceability and consistent builds.

5. Define and Link the Executable

The add\_executable command defines the build of an application, outputting an executable named by its first argument, with the sources following. Note that we add the headers to the list of sources so that they will appear in IDEs like Xcode.

After adding the executable, we use the target\_link\_libraries command to link it with the Geant4 libraries. The Geant4\_LIBRARIES variable is set by find\_package when Geant4 is located, and is a list of all the libraries needed to link against to use Geant4.

6. Copy any Runtime Scripts to the Build Directory

Because we want to support out of source builds so that we won't mix CMake generated files with our actual sources, we copy any scripts used by the B1 application to the build directory. We use foreach to loop over the list of scripts we constructed, and configure file to perform the actual copy.

Here, the CMake variable PROJECT\_BINARY\_DIR is set by the earlier call to the project command and points to the directory where we run CMake to configure the build.

7. If Required, Install the Executable

Use the install command to create an install target that will install the executable to a bin directory under CMAKE\_INSTALL\_PREFIX.

If you don't intend your application to be installable, i.e. you only want to use it locally when built, you can leave this out.

This sequence of commands is the most basic needed to compile and link an application with Geant4, and is easily extendable to more involved use cases such as platform specific configuration or using other third party packages (via find\_package).

With the CMake script in place, using it to build an application is a two step process. First CMake is run to generate buildscripts to describe the build. By default, these will be Makefiles on Unix platforms, and Visual Studio solutions on Windows, but you can generate scripts for other tools like Xcode and Eclipse if you wish. Second, the buildscripts are run by the chosen build tool to compile and link the application.

A key concept with CMake is that we generate the buildscripts and run the build in a separate directory, the so-called *build directory*, from the directory in which the sources reside, the so-called *source directory*. This is the exact same technique we used when building Geant4 itself. Whilst this may seem awkward to begin with, it is a very useful

technique to employ. It prevents mixing of CMake generated files with those of your application, and allows you to have multiple builds against a single source without having to clean up, reconfigure and rebuild.

We'll illustrate this configure and build process on Linux/macOS using Makefiles, and on Windows using Visual Studio. The example script and Geant4's Geant4Config.cmake script are vanilla CMake, so you should be able to use other Generators (such as Xcode and Eclipse) without issue.

### **Building ExampleB1 with CMake on Unix with Makefiles**

We'll assume, for illustration only, that you've copied the exampleB1 sources into a directory under your home area so that we have:

```
+- /home/you/B1/
+- CMakeLists.txt
+- exampleB1.cc
+- include/
+- src/
+- ...
```

Here, our source directory is /home/you/B1, in other words the directory holding the CMakeLists.txt file.

Let's also assume that you have already installed Geant4 in your home area under, for illustration only, /home/you/geant4-install.

Our first step is to create a *build directory* in which build the example. We will create this alongside our B1 *source directory* as follows:

```
$ cd $HOME
$ mkdir B1-build
```

We now change to this *build directory* and run CMake to generate the Makefiles needed to build the B1 application. We pass CMake two arguments

```
$ cd $HOME/B1-build
$ cmake -DGeant4_DIR=/home/you/geant4-install/lib64/Geant4-G4VERSION $HOME/B1
```

Here, the first argument points CMake to our install of Geant4. Specifically, it is the directory holding the Geant4Config.cmake file that Geant4 installs to help CMake find and use Geant4. You should of course adapt the value of this variable to the location of your actual Geant4 install. This provides the most specific way to point CMake to the Geant4 install you want to use. You may also use the CMAKE\_PREFIX\_PATH variable, e.g.

```
$ cd $HOME/B1-build
$ cmake -DCMAKE_PREFIX_PATH=/home/you/geant4-install $HOME/B1
```

This is most useful for system integrators as it may be extended via the environment or command line with paths to the install prefixes of additional required software packages.

The second argument to CMake is the path to the *source directory* of the application we want to build. Here it's just the B1 directory as discussed earlier. You should of course adapt the value of that variable to where you copied the B1 source directory.

CMake will now run to configure the build and generate Makefiles and you will see output similar to

```
$ cmake -DGeant4_DIR=/home/you/geant4-install/lib64/Geant4-G4VERSION $HOME/B1
-- The C compiler identification is GNU 9.3.0
-- The CXX compiler identification is GNU 9.3.0
-- Check for working C compiler: /usr/bin/gcc-9
-- Check for working C compiler: /usr/bin/gcc-9 -- works
-- Detecting C compiler ABI info
-- Detecting C compiler ABI info - done
```

(continues on next page)

(continued from previous page)

```
-- Detecting C compile features
-- Detecting C compile features - done
-- Check for working CXX compiler: /usr/bin/g++-9
-- Check for working CXX compiler: /usr/bin/g++-9 -- works
-- Detecting CXX compiler ABI info
-- Detecting CXX compiler ABI info - done
-- Detecting CXX compile features
-- Detecting CXX compile features - done
-- Configuring done
-- Generating done
-- Build files have been written to: /home/you/B1-build
```

The exact output will depend on the UNIX variant, compiler, and CMake version but the last three lines should be identical to within the exact path used.

If you now list the contents of you build directory, you can see the files generated:

```
$ 1s

CMakeCache.txt exampleB1.in Makefile vis.mac

CMakeFiles exampleB1.out run1.mac

cmake_install.cmake init_vis.mac run2.mac
```

Note the Makefile and that all the scripts for running the exampleB1 application we're about to build have been copied across. With the Makefile available, we can now build by simply running make:

```
$ make -jN
```

CMake generated Makefiles support parallel builds, so N can be set to the number of cores on your machine (e.g. on a dual core processor, you could set N to 2). When make runs, you should see the output:

```
$ make

Scanning dependencies of target exampleB1

[ 12%] Building CXX object B1/CMakeFiles/exampleB1.dir/exampleB1.cc.o

[ 25%] Building CXX object B1/CMakeFiles/exampleB1.dir/src/ActionInitialization.cc.o

[ 37%] Building CXX object B1/CMakeFiles/exampleB1.dir/src/DetectorConstruction.cc.o

[ 50%] Building CXX object B1/CMakeFiles/exampleB1.dir/src/EventAction.cc.o

[ 62%] Building CXX object B1/CMakeFiles/exampleB1.dir/src/PrimaryGeneratorAction.cc.o

[ 75%] Building CXX object B1/CMakeFiles/exampleB1.dir/src/RunAction.cc.o

[ 87%] Building CXX object B1/CMakeFiles/exampleB1.dir/src/SteppingAction.cc.o

[ 100%] Linking CXX executable exampleB1

[ 100%] Built target exampleB1
```

CMake Unix Makefiles are quite terse, but you can make them more verbose by adding the VERBOSE argument to make:

```
$ make VERBOSE=1
```

If you now list the contents of your build directory you will see the example B1 application executable has been created:

```
$ ls

CMakeCache.txt exampleB1 init_vis.mac run2.mac

CMakeFiles exampleB1.in Makefile vis.mac

cmake_install.cmake exampleB1.out run1.mac
```

You can now run the application in place:

(continues on next page)

(continued from previous page)

Note that the exact output shown will depend on how both Geant4 and your application were configured. Further output and behaviour beyond the Registering graphics systems... line will depend on what UI and Visualization drivers your Geant4 install supports. If you recall the use of the ui\_all vis\_all in the find\_package command, this results in all available UI and Visualization drivers being activated in your application. If you didn't want any UI or Visualization, you could rerun CMake in your build directory with arguments:

```
$ cmake -DWITH_GEANT4_UIVIS=OFF .
```

This would switch the option we set up to false, and result in find\_package not activating any UI or Visualization for the application. You can easily adapt this pattern to provide options for your application such as additional components or features.

Once the build is configured, you can edit code for the application in its *source directory*. You only need to rerun make in the corresponding *build directory* to pick up and compile the changes. However, note that due to the use of CMake globbing to create the source file list, if you add or remove files, you must remember to rerun CMake to pick up the changes. This is another reason why Kitware recommend listing the sources explicitly.

### Building ExampleB1 with CMake on Windows with Visual Studio

As with building Geant4 itself, the simplest system to use for building applications on Windows is a Visual Studio Developer Command Prompt, which can be started from  $Start \rightarrow Visual\ Studio\ 2017 \rightarrow Developer\ Command\ Prompt$  for VS2017 (similarly for VS2015)

We'll assume, for illustration only, that you've copied the exampleB1 sources into a directory C:\Users\YourUsername\B1 so that we have:

```
+- C:\Users\YourUsername\B1
+- CMakeLists.txt
+- exampleB1.cc
+- include\
+- src\
+- ...
```

Here, our *source directory* is C:\Users\YourUsername\B1, in other words the directory holding the CMakeLists.txt file.

Let's also assume that you have already installed Geant4 in your home area under, for illustration only, C:\Users\YourUsername\Geant4-install.

Our first step is to create a *build directory* in which build the example. We will create this alongside our B1 *source directory* as follows, working from the Visual Studio Developer Command Prompt:

```
> cd %HOMEPATH%
> mkdir B1-build
```

We now change to this *build directory* and run CMake to generate the Visual Studio solution needed to build the B1 application. We pass CMake two arguments

Here, the first argument points CMake to our install of Geant4. Specifically, it is the directory holding the Geant4Config.cmake file that Geant4 installs to help CMake find and use Geant4. You should of course adapt the value of this variable to the location of your actual Geant4 install. As with the examples above, you can also use the CMAKE\_PREFIX\_PATH variable. The second argument is the path to the *source directory* of the application we want to build. Here it's just the B1 directory as discussed earlier. You should of course adapt it to where you copied the B1 source directory. In both cases the arguments are quoted in case of the paths containing spaces.

CMake will now run to configure the build and generate Visual Studio solutions and you will see output similar to

```
Building for: Visual Studio 15 2017
-- The C compiler identification is MSVC 19.11.25547.0
-- The CXX compiler identification is MSVC 19.11.25547.0
-- Check for working C compiler: C:/Program Files (x86)/Microsoft Visual Studio/2017/Community/
\rightarrow VC/Tools/MSVC/14.11.25503/bin/Hostx86/x86/cl.exe
  Check for working C compiler: C:/Program Files (x86)/Microsoft Visual Studio/2017/Community/
→VC/Tools/MSVC/14.11.25503/bin/Hostx86/x86/cl.exe -- works
-- Detecting C compiler ABI info
-- Detecting C compiler ABI info - done
 Check for working CXX compiler: C:/Program Files (x86)/Microsoft Visual Studio/2017/Community/
→VC/Tools/MSVC/14.11.25503/bin/Hostx86/x86/cl.exe
-- Check for working CXX compiler: C:/Program Files (x86)/Microsoft Visual Studio/2017/Community/
→VC/Tools/MSVC/14.11.25503/bin/Hostx86/x86/cl.exe -- works
-- Detecting CXX compiler ABI info
  Detecting CXX compiler ABI info

    done

-- Detecting CXX compile features
-- Detecting CXX compile features - done
-- Configuring done
-- Generating done
  Build files have been written to: C:/Users/YourUsername/B1-build
```

If you now list the contents of you build directory, you can see the files generated:

```
> dir /B
ALL_BUILD.vcxproj
ALL_BUILD.vcxproj.filters
B1.sln
B1.vcxproj
B1.vcxproj.filters
CMakeCache.txt
CMakeFiles
cmake_install.cmake
exampleB1.in
exampleB1.out
exampleB1.vcxproj
exampleB1.vcxproj.filters
init_vis.mac
INSTALL.vcxproj
INSTALL.vcxproj.filters
run1.mac
run2.mac
vis.mac
ZERO_CHECK.vcxproj
ZERO_CHECK.vcxproj.filters
```

Note the B1.sln solution file and that all the scripts for running the exampleB1 application we're about to build have been copied across. With the solution available, we can now build by running cmake to drive MSBuild:

```
> cmake --build . --config Release
```

Solution based builds are quite verbose, but you should not see any errors at the end. In the above, we have built the B1 program in Release mode, meaning that it is optimized and has no debugging symbols. As with building Geant4 itself, this is chosen to provide optimum performance. If you require debugging information for your application, simply change the argument to RelWithDebInfo. Note that in both cases you must match the configuration of your application with that of the Geant4 install, i.e. if you are building the application in Release mode, then ensure it uses a Release build of Geant4. Link and/or runtime errors may result if mixed configurations are used.

After running the build, if we list the contents of the build directory again we see:

```
ALL_BUILD.vcxproj
ALL_BUILD.vcxproj.filters
B1.sln
B1.vcxproj
B1.vcxproj.filters
CMakeCache.txt
CMakeFiles
cmake_install.cmake
exampleB1.dir
exampleB1.in
exampleB1.out
exampleB1.vcxproj
exampleB1.vcxproj.filters
init_vis.mac
INSTALL.vcxproj
INSTALL.vcxproj.filters
Release
run1.mac
run2.mac
vis.mac
Win32
ZERO_CHECK.vcxproj
ZERO_CHECK.vcxproj.filters
> dir /B Release
exampleB1.exe
```

Here, the Release subdirectory contains the executable, and the main build directory contains all the .mac scripts for running the program. If you build in different modes, the executable for that mode will be in a directory named for that mode, e.g. RelWithDebInfo/exampleB1.exe. You can now run the application in place:

Note that the exact output shown will depend on how both Geant4 and your application were configured. Further output and behaviour beyond the Registering graphics systems... line will depend on what UI and Visualization drivers your Geant4 install supports.

Whilst the Visual Studio Developer Command prompt provides the simplest way to build an application, the generated Visual Studio Solution file (B1.sln in the above example) may also be opened directly in the Visual Studio IDE. This provides a more comprehensive development and debugging environment, and you should consult its documentation if you wish to use this.

One key CMake related item to note goes back to our listing of the *headers* for the application in the call to add\_executable. Whilst CMake will naturally ignore these for configuring compilation of the application, it will add them to the Visual Studio Solution. If you do not list them, they will not be editable in the Solution in the Visual Studio IDE.

# 2.8.2 Use of Geant4Config.cmake with find\_package in CMake

The Geant 4Config.cmake file installed by Geant 4 is designed to be used with CMake's find\_package command. CMake will search for the file using the Geant 4\_DIR variable described above, plus a standard set of paths used by find\_package.

When found, it sets several CMake variables and provides a mechanism for checking and activating optional features of Geant4 if your application requires these. The simplest possible usage of find\_package and these variables to configure an application or library requiring Geant4 is:

The Geant 4\_LIBRARIES variable holds the list of CMake Imported Targets for the Geant4 libraries. These set and propagate all Usage Requirements of Geant4 to the consuming target(s) (the myq4app executable in the above).

The minimal example just requires that a Geant4 install be found. A version number may be supplied to search for an install *greater than or equal to* the supplied version, e.g.

```
find_package(Geant4 10.0 REQUIRED)
```

makes CMake search for a Geant4 install whose version number is greater than or equal to 10.0. An exact version number may also be specified:

```
find_package(Geant4 10.4.0 EXACT REQUIRED)
```

In both cases, CMake will fail with an error if a Geant4 install meeting these version requirements is not found.

Geant4 can be installed with many optional components, and the presence of these can also be required and activated by passing extra "component" arguments. For example, to require that Geant4 is found *and* that it has support for gdml and Ot:

```
find_package(Geant4 REQUIRED gdml qt)
```

which will fail if the found install was not built with these options. If you want to activate components only if they exist, you can use the pattern

```
find_package (Geant 4 REQUIRED)
find_package (Geant 4 QUIET OPTIONAL_COMPONENTS qt)
```

which will require CMake to locate a core install of Geant4, and then check for and activate Qt support if the install provides it, continuing without error otherwise. A key thing to note here is that you can call find\_package multiple times to append configuration of components. If you use this pattern and need to check if a component was found, you can use the Geant 4\_<COMPONENTNAME>\_FOUND variables which are set after the call to find\_package.

Some components are "passive" in that they just indicate support is available, others are "active" in that they indicate support for and activate use of the component in the application linking to the targets in Geant 4\_LIBRARIES. A

partial list of the most useful components and their behaviour is given below, but for a full list, please see the listing in the installed Geant 4 Config. cmake file.

• multithreaded

Geant4\_multithreaded\_FOUND is TRUE if the install of Geant4 was built with multithreading support. Note that this is a passive option and only indicates availability of multithreading support! Multithreading in your application code requires creation and usage of the appropriate C++ objects and interfaces as described in this guide.

• qdml

Geant 4\_gdml\_FOUND is TRUE if the install of Geant 4 was built with GDML support. Note that this is a passive option, and indicates support for GDML is available in the found install.

• ni all

Activates **all** available UI drivers. Does not set any variables, and never causes CMake to fail. *It is recommended to use this over specific UI drivers unless your application has strong requirements*.

• vis all

Activates **all** available Visualization drivers. Does not set any variables, and never causes CMake to fail. *It is recommended to use this over specific Vis drivers unless your application has strong requirements*.

• ui\_tcsh

Geant4\_ui\_tcsh\_FOUND is TRUE if the install of Geant4 provides the TCsh command line User Interface. Using this component activates and allows use of the TCsh command line interface in the linked application.

• ui win32

Geant4\_ui\_win32\_FOUND is TRUE if the install of Geant4 provides the Win32 command line User Interface. Using this component activates and allows use of the Win32 command line interface in the linked application.

• motif

Geant4\_motif\_FOUND is TRUE if the install of Geant4 provides the Motif(Xm) User Interface and Visualization driver. Using this component activates and allows use of the Motif User Interface and Visualization Driver in the linked application.

• qt

Geant 4\_qt\_FOUND is TRUE if the install of Geant4 provides the Qt User Interface and Visualization driver. Using this component activates and allows use of the Qt User Interface and Visualization Driver in the linked application.

• vis\_raytracer\_x11

Geant4\_vis\_raytracer\_x11\_FOUND is TRUE if the install of Geant4 provides the X11 interface to the RayTracer Visualization driver. Using this component activates and allows use of the RayTracer X11 Visualization Driver in the linked application.

• vis\_opengl\_x11

Geant4\_vis\_opengl\_x11\_FOUND is TRUE if the install of Geant4 provides the X11 interface to the OpenGL Visualization driver. Using this component activates and allows use of the X11 OpenGL Visualization Driver in the linked application.

• vis opengl win32

Geant 4\_vis\_openg1\_win32\_FOUND is TRUE if the install of Geant 4 provides the Win32 interface to the OpenGL Visualization driver. Using this component activates and allows use of the Win32 OpenGL Visualization Driver in the linked application.

• vis\_openinventor

Geant4\_vis\_openinventor\_FOUND is TRUE if the install of Geant4 provides the OpenInventor Visualization driver. Using this component activates and allows use of the OpenInventor Visualization Driver in the linked application.

• vis\_toolssq\_x11\_gles

Geant4\_vis\_toolssg\_x11\_gles\_FOUND is TRUE if the install of Geant4 provides the ToolsSG visualization driver with X11 backend. Using this component allows use of the ToolsSG Visualization Driver in the linked application.

• vis\_toolssg\_xt\_gles Geant4\_vis\_toolssg\_xt\_gles\_FOUND is TRUE if the install of Geant4 provides the ToolsSG visualization driver with Motif backend. Using this component allows use of the ToolsSG Visualization Driver in the linked application.

- vis\_toolssg\_qt\_gles
  Geant4\_vis\_toolssg\_qt\_gles\_FOUND is TRUE if the install of Geant4 provides the ToolsSG visualization driver with Qt5 backend. Using this component allows use of the ToolsSG Visualization Driver in the
  linked application.
- vis\_toolssg\_windows\_gles
  Geant4\_vis\_toolssg\_windows\_gles\_FOUND is TRUE if the install of Geant4 provides the ToolsSG
  visualization driver with Windows backend. Using this component allows use of the ToolsSG Visualization
  Driver in the linked application.
- vis\_Vtk Geant4\_vis\_Vtk\_FOUND is TRUE if the install of Geant4 provides the Vtk visualization driver. Using this component allows use of the Vtk Visualization Driver in the linked application.

# 2.9 How to Set Up an Interactive Session

## 2.9.1 Introduction

### Roles of the "intercoms" category

The "intercoms" category provides an expandable command interpreter. It is the key mechanism of GEANT4 to realize secure user interactions across categories without being annoyed by dependencies among categories. GEANT4 commands can be used in an interactive session, a batch mode with a macro file, or a direct C++ call.

#### User Interfaces to drive the simulation

GEANT4 can be controlled by a series of GEANT4 UI commands. The "intercoms" category provides the abstract class G4UIsession that processes interactive commands. The concrete implementations of (graphical) user interface are provided in the "interfaces" category. The strategy realize to adopt various user interface tools, and allows GEANT4 to utilize the state-of-the-art GUI tools such as Motif, Qt, and Java etc. The following interfaces is currently available;

- 1. Command-line terminal (dumb terminal and tcsh-like terminal)
- 2. Xm, Qt, Win32, variations of the above terminal by using a Motif, Qt, Windows widgets
- 3. GAG, a fully graphical user interface and its network extension GainServer of the client/server type.

Implementation of the user sessions (1 and 2) is included in the <code>source/interfaces/basic</code> directory. As for GAG, the front-end class is included in the <code>source/interfaces/GAG</code> directory, while its partner GUI package MOMO.jar is available under the <code>environments/MOMO</code> directory. MOMO.jar, Java archive file, contains not only GAG, but also GGE and other helper packages.

## 2.9.2 A Short Description of Available Interfaces

## **G4UIterminal**

This interface opens a session on a command-line terminal. G4UIterminal runs on all supported platforms. There are two kinds of shells, G4UIcsh and G4UItcsh. G4UItcsh supports tesh-like readline features (cursor and command completion) and works on Linux on Mac, while G4UIcsh is a plain standard input (cin) shell that works on all platforms. The following built-in commands are available in G4UIterminal;

cd, pwd change, display the current command directory.

**ls**, **lc** list commands and subdirectories in the current directory.

history show previous commands.

!historyID reissue previous command.

**?command** show current parameter values of the command.

help command show command help.

exit terminate the session.

G4UItcsh supports user-friendly key bindings a-la-tcsh. G4UItcsh runs on Linux and Mac. The following keybindings are supported;

- ^A move cursor to the top
- **^B** backward cursor ([LEFT] cursor)
- **^C** (except Windows terminal) abort a run ( soft abort ) during event processing. A program will be terminated while accepting a user command.
- ^D delete/exit/show matched list
- ^E move cursor to the end
- **^F** forward cursor ([RIGHT] cursor)
- ^K clear after the cursor
- ^N next command ([DOWN] cursor)
- **^P** previous command ([UP] cursor)
- TAB command completion
- **DEL** backspace
- BS backspace

The example below shows how to set a user's prompt.

```
G4UItcsh* tcsh = new G4UItcsh();
tcsh-> SetPrompt("%s>");
```

The following strings are supported as substitutions in a prompt string.

%s current application status

%/ current working directory

%h history number

Command history in a user's session is saved in a file \$(HOME)/.g4\_hist that is automatically read at the next session, so that command history is available across sessions.

#### G4UIXm, G4UIQt and G4UIWin32 classes

These interfaces are versions of G4UIterminal implemented over libraries Motif, Qt and WIN32 respectively. G4UIXm uses the Motif XmCommand widget, G4UIQt the Qt dialog widget, and G4UIWin32 the Windows "edit" component to do the command capturing. These interfaces are useful if working in conjunction with visualization drivers that use the Xt library, Qt library or the WIN32 one.

A command box is at disposal for entering or recalling GEANT4 commands. Command completion by typing "TAB" key is available in the command box. The shell commands "exit, cont, help, ls, cd..." are also supported. A menu bar can be customized through the *AddMenu* and *AddButton* method. Ex:

/gui/addMenu test Test

/gui/addButton test Init /run/initialize

/gui/addButton test "Set gun" "/control/execute gun.g4m"

/gui/addButton test "Run one event" "/run/beamOn 1"

G4UIXm runs on Unix/Linux with Motif. G4UIQt run everywhere with Qt. G4UIWin32 runs on Windows.

#### G4UIGAG and G4UIGainServer classes

They are front-end classes of GEANT4 which make connections with their respective graphical user interfaces, GAG (GEANT4 Adaptive GUI) via pipe, and Gain (GEANT4 adaptive interface for network) via sockets. While GAG must run on the same system (Windows or Unixen) as a GEANT4 application, Gain can run on a remote system (Windows, Linux, etc.) in which JRE (Java Runtime Environment) is installed. A GEANT4 application is invoked on a Unix (Linux) system and behaves as a network server. It opens a port, waiting the connection from the Gain. Gain has capability to connect to multiple GEANT4 "servers" on Unixen systems at different hosts.

Client GUIs, GAG and Gain have almost similar look-and-feel. So, GAG's functionalities are briefly explained here. Please refer to the URL previously mentioned for details.

Using GAG, user can select a command, set its parameters and execute it. It is adaptive, in the sense that it reflects the internal states of GEANT4 that is a state machine. So, GAG always provides users with the GEANT4 commands which may be added, deleted, enabled or disabled during a session. GAG does nothing by itself but to play an intermediate between user and an executable simulation program via pipes. GEANT4's front-end class G4UIGAG must be instantiated to communicate with GAG. GAG runs on Linux and Windows. MOMO.jar is supplied in the GEANT4 source distribution and can be run by a command:

```
%java -jar /path/to/geant4.10.00/environments/MOMO/MOMO.jar
```

GAG has following functions.

- **GAG Menu:** The menus are to choose and run a GEANT4 executable file, to kill or exit a GEANT4 process and to exit GAG. Upon the normal exit or an unexpected death of the GEANT4 process, GAG window are automatically reset to run another GEANT4 executable.
- GEANT4 Command tree: Upon the establishment of the pipe connection with the GEANT4 process, GAG displays the command menu, using expandable tree browser whose look and feel is similar to a file browser. Disabled commands are shown in opaque. GAG doesn't display commands that are just below the root of the command hierarchy. Direct type-in field is available for such input. Guidance of command categories and commands are displayed upon focusing. GAG has a command history function. User can re-execute a command with old parameters, edit the history, or save the history to create a macro file.
- Command Parameter panel: GAG's parameter panel is the user-friendliest part. It displays parameter name, its guidance, its type(s) (integer, double, Boolean or string), omittable, default value(s), expression(s) of its range and candidate list(s) (for example, of units). Range check is done by intercoms and the error message from it is shown in the pop-up dialog box. When a parameter component has a candidate list, a list box is automatically displayed. When a file is requested by a command, the file chooser is available.
- **Logging:** Log can be redirected to the terminal (xterm or cygwin window) from which GAG is invoked. It can be interrupted as will, in the middle of a long session of execution. Log can be saved to a file independent of the above redirection. GAG displays warning or error messages from GEANT4 in a pop-up warning widget.

# 2.9.3 How to Select Interface in Your Applications

To choose an interface (G4UIxxx where xxx = terminal, Xm, Win32, Qt, GAG, GainServer) in your programs, there are two ways.

• Calling G4UIxxx directly:

```
#include "G4Uixxx.hh"

G4UIsession* session = new G4UIxxx;
session-> SessionStart();

delete session;
```

**Note:** For using a tesh session, G4UIterminal is instantiated like:

```
G4UIsession* session = new G4UIterminal(new G4UItcsh);
```

If the user wants to deactivate the default signal handler (soft abort) raised by "Ctr-C", the false flag can be set in the second argument of the G4UIterminal constructor like

```
G4UIsession* session = new G4UIterminal(new G4UItcsh, false).
```

• Using G4UIExecutive This is more convenient way for choosing a session type, that can select a session at run-time according to a rule described below.

```
#include "G4UIExecutive.hh"

G4UIExecutive* ui = new G4UIExecutive(argc, argv);
ui->SessionStart();

delete ui;
```

G4UIExecutive has several ways to choose a session type. A session is selected in the following rule. Note that session types are identified by a case-insensitive characters ("qt", "xm", "win32", "gag", "tcsh", "csh").

- 1. Check the argument of the constructor of G4UIExecutive. You can specify a session like new G4UIExecutive(argc, argv, "qt");
- 2. Check environment variables, G4UI\_USE\_XX (XX= QT, XM, WIN32, GAG, TCSH). Select a session if the corresponding environment variable is defined. Variables are checked in the order of QT, XM, WIN32, GAG, TCSH if multiple variables are set.
- 3. Check ~/.g4session . You can specify the default session type and a session type by each application in that file. The below shows a sample of .g4session.

```
tcsh # default session
exampleN03 Qt # (application name / session type)
myapp tcsh
hoge csh
```

4. Guess the best session type according to build session libraries. The order of the selection is Qt, tcsh, Xm.

In any cases, G4UIExecutive checks if a specified session is build or not. If not, it goes the next step. A terminal session with csh is the fallback session. If none of specified session is available, then it will be selected.

# 2.10 How to Execute a Program

### 2.10.1 Introduction

A GEANT4 application can be run either in

- 'purely hard-coded' batch mode
- batch mode, but reading a macro of commands
- interactive mode, driven by command lines
- interactive mode via a Graphical User Interface

The last mode will be covered in *How to Set Up an Interactive Session*. The first three modes are explained here.

## 2.10.2 'Hard-coded' Batch Mode

Below is a modified main program of the basic example B1 to represent an application which will run in batch mode.

Listing 2.19: An example of the main() routine for an application which will run in batch mode.

```
using namespace B1;
int main()
{
    // Construct the default run manager
    auto runManager = G4RunManagerFactory::CreateRunManager();

    // Set mandatory initialization classes
    runManager->SetUserInitialization(new DetectorConstruction);
    runManager->SetUserInitialization(new QGSP_BIC_EMY);
    runManager->SetUserInitialization(new ActionInitialization);

// Initialize G4 kernel
    runManager->Initialize();

// start a run
    int numberOfEvent = 1000;
    runManager->BeamOn(numberOfEvent);

// job termination
delete runManager;
    return 0;
}
```

Even the number of events in the run is 'frozen'. To change this number you must at least recompile main ().

### 2.10.3 Batch Mode with Macro File

Below is a modified main program of the basic example B1 to represent an application which will run in batch mode, but reading a file of commands.

Listing 2.20: An example of the main() routine for an application which will run in batch mode, but reading a file of commands.

```
using namespace B1;
int main(int argc,char** argv)
{
    // Construct the default run manager
    auto runManager = G4RunManagerFactory::CreateRunManager();

    // Set mandatory initialization classes
    runManager->SetUserInitialization (new DetectorConstruction);
    runManager->SetUserInitialization (new QGSP_BIC_EMY);
    runManager->SetUserInitialization (new ActionInitialization);

// Initialize G4 kernel
    runManager->Initialize();

//read a macro file of commands
G4UImanager* UI = G4UImanager::GetUIpointer();
G4String command = "/control/execute ";
G4String fileName = argv[1];
UI->ApplyCommand(command+fileName);
```

(continues on next page)

(continued from previous page)

```
// job termination
delete runManager;
return 0;
}
```

This example will be executed with the command:

```
> exampleB1 run1.mac
```

where exampleB1 is the name of the executable and run1.mac is a macro of commands located in the current directory, which could look like:

Listing 2.21: A typical command macro.

```
# Macro file for myProgram
#
# set verbose level for this run
#
/run/verbose 2
/event/verbose 0
/tracking/verbose 1
#
# Set the initial kinematic and run 100 events
# electron 1 GeV to the direction (1.,0.,0.)
#
/gun/particle e-
/gun/energy 1 GeV
/run/beamOn 100
```

Indeed, you can re-execute your program with different run conditions without recompiling anything.

**Note:** many G4 category of classes have a verbose flag which controls the level of 'verbosity'.

Usually verbose=0 means silent. For instance

- /run/verbose is for the RunManager
- /event/verbose is for the EventManager
- /tracking/verbose is for the TrackingManager
- ...etc...

# 2.10.4 Interactive Mode Driven by Command Lines

Below is an example of the main program for an application which will run interactively, waiting for command lines entered from the keyboard.

Listing 2.22: An example of the main() routine for an application which will run interactively, waiting for commands from the keyboard.

```
using namespace B1;
int main(int argc, char** argv)
{
    // Construct the default run manager
    G4RunManager* runManager = new G4RunManager;
    // Set mandatory initialization classes
```

(continues on next page)

(continued from previous page)

```
runManager->SetUserInitialization(new DetectorConstruction);
runManager->SetUserInitialization(new QGSP_BIC_EMY);
runManager->SetUserInitialization(new ActionInitialization);

// Initialize G4 kernel
runManager->Initialize();

// Define UI terminal for interactive mode
G4UIsession * session = new G4UIterminal;
session->SessionStart();
delete session;

// job termination
delete runManager;
return 0;
}
```

This example will be executed with the command:

```
> exampleB1
```

where exampleB1 is the name of the executable.

The G4 kernel will prompt:

```
Idle>
```

and you can start your session. An example session could be:

Run 5 events:

```
Idle> /run/beamOn 5
```

Switch on tracking/verbose and run one more event:

```
Idle> /tracking/verbose 1
Idle> /run/beamOn 1
```

Change primary particle type an run more events:

```
Idle> /gun/particle mu+
Idle> /gun/energy 10 GeV
Idle> /run/beamOn 1
Idle> /gun/particle proton
Idle> /gun/energy 100 MeV
Idle> /run/beamOn 3
Idle> exit
```

For the meaning of the machine state Idle, see as a state machine.

This mode is useful for running a few events in debug mode and visualizing them. How to include visualization will be shown in the next, general case, example.

## 2.10.5 General Case

All basic examples in the examples/basic subdirectory of the GEANT4 source distribution have the following main() structure. The application can be run either in batch or interactive mode.

Listing 2.23: The typical main () routine from the examples directory.

```
using namespace B1;
int main(int argc,char** argv)
  // Detect interactive mode (if no arguments) and define UI session
 G4UIExecutive* ui = 0;
  if ( argc == 1 ) {
  ui = new G4UIExecutive(argc, argv);
  // Optionally: choose a different Random engine...
  // G4Random::setTheEngine(new CLHEP::MTwistEngine);
  // Construct the default run manager
  G4RunManager* runManager = new G4RunManager;
  // Set mandatory initialization classes
  // Detector construction
  runManager->SetUserInitialization(new DetectorConstruction());
  G4VModularPhysicsList* physicsList = new QBBC;
  physicsList->SetVerboseLevel(1);
  runManager->SetUserInitialization(physicsList);
  // User action initialization
  runManager->SetUserInitialization(new ActionInitialization());
  // Initialize visualization
  G4VisManager* visManager = new G4VisExecutive;
  // G4VisExecutive can take a verbosity argument - see /vis/verbose guidance.
  // G4VisManager* visManager = new G4VisExecutive("Quiet");
  visManager->Initialize();
  // Get the pointer to the User Interface manager
 G4UImanager * UImanager = G4UImanager::GetUIpointer();
  if (! ui ) {
   // batch mode
   G4String command = "/control/execute ";
   G4String fileName = argv[1];
   UImanager->ApplyCommand(command+fileName);
  } else {
    // interactive mode
   UImanager->ApplyCommand("/control/execute init_vis.mac");
   ui->SessionStart();
   delete ui;
  // Job termination
  // Free the store: user actions, physics_list and detector_description are
  // owned and deleted by the run manager, so they should not be deleted
  // in the main() program !
  delete visManager;
  delete runManager;
```

## Listing 2.24: The init.mac macro

```
# Macro file for the initialization phase of example B1
# when running in interactive mode without visualization
#
# Set some default verbose
/control/verbose 2
/control/saveHistory
/run/verbose 2
```

The init\_vis.mac macro has just added a line with a call to vis.mac:

```
# Macro file for the initialization phase of example B1
# when running in interactive mode with visualization
#
# Set some default verbose
#
/control/verbose 2
/control/saveHistory
/run/verbose 2
#
# Visualization setting
/control/execute vis.mac
```

The vis.mac macro defines a minimal setting for drawing volumes and trajectories accumulated for all events of a given run:

```
# Macro file for the visualization setting in the initialization phase
# of the B1 example when running in interactive mode
# Use this open statement to create an OpenGL view:
/vis/open OGL 600x600-0+0
# Draw geometry:
/vis/drawVolume
# Specify view angle:
/vis/viewer/set/viewpointThetaPhi 90. 180.
# Draw smooth trajectories at end of event, showing trajectory points
# as markers 2 pixels wide:
/vis/scene/add/trajectories smooth
# To superimpose all of the events from a given run:
/vis/scene/endOfEventAction accumulate
# Re-establish auto refreshing and verbosity:
/vis/viewer/set/autoRefresh true
/vis/verbose warnings
# For file-based drivers, use this to create an empty detector view:
#/vis/viewer/flush
```

Also, this example demonstrates that you can read and execute a macro from another macro or interactively:

```
Idle> /control/execute mySubMacro.mac
```

# 2.11 How to Visualize the Detector and Events

#### 2.11.1 Introduction

This section briefly explains how to perform GEANT4 Visualization. The description here is based on the sample program examples/basic/B1. More details are given in *Visualization*.

### 2.11.2 Visualization Drivers

The GEANT4 visualization system was developed in response to a diverse set of requirements:

- 1. Quick response to study geometries, trajectories and hits
- 2. High-quality output for publications
- 3. Flexible camera control to debug complex geometries
- 4. Tools to show volume overlap errors in detector geometries
- 5. Interactive picking to get more information on visualized objects

No one graphics system is ideal for all of these requirements, and many of the large software frameworks into which GEANT4 has been incorporated already have their own visualization systems, so GEANT4 visualization was designed around an abstract interface that supports a diverse family of graphics systems. Some of these graphics systems use a graphics library compiled with GEANT4, such as OpenGL, Qt or OpenInventor, while others involve a separate application, such as HepRApp or DAWN.

You need not use all visualization drivers. You can select those suitable to your purposes. In the following, for simplicity, we assume that the GEANT4 libraries are built with the Qt driver.

If you build GEANT4 using the standard CMake procedure, you include Qt by setting GEANT4\_USE\_QT to ON.

In order to use the the Qt driver, you need the OpenGL library, which is installed in many platforms by default and CMake will find it. (If you wish to "do-it-yourself", see *Installing Visualization Drivers*.) The makefiles then set appropriate C-pre-processor flags to select appropriate code at compilation time.

If you are using multithreaded mode, from GEANT4 version 10.2 event drawing is performed by a separate thread and you may need to optimise this with special /vis/multithreading commands - see *Multithreading commands*.

## 2.11.3 How to Incorporate Visualization Drivers into an Executable

Most GEANT4 examples already incorporate visualization drivers. If you want to include visualization in your own GEANT4 application, you need to instantiate and initialize a subclass of G4VisManager that implements the pure virtual function RegisterGraphicsSystems().

The provided class G4VisExecutive can handle all of this work for you. G4VisExecutive is sensitive to the G4VIS\_... variables (that you either set by hand or that are set for you by GNUMake or CMake configuration). See any of the GEANT4 examples for how to use G4VisExecutive.

If you really want to write your own subclass, rather than use G4VisExecutive, you may do so. You will see how to do this by looking at G4VisExecutive.icc. This subclass must be compiled in the user's domain to force the loading of appropriate libraries in the right order. A typical extract is:

```
RegisterGraphicsSystem (new G4DAWNFILE);
...
#ifdef G4VIS_USE_OPENGLX
RegisterGraphicsSystem (new G4OpenGLImmediateX);
RegisterGraphicsSystem (new G4OpenGLStoredX);
#endif
...
```

The G4VisExecutive takes ownership of all registered graphics systems, and will delete them when it is deleted at the end of the user's job (see below).

If you wish to use G4VisExecutive but register an additional graphics system, XXX say, you may do so either before or after initializing:

```
visManager->RegisterGraphicsSytem(new XXX);
visManager->Initialize();
```

An example of a typical main () function is given below.

# 2.11.4 Writing the main () Method to Include Visualization

Now we explain how to write a visualization manager and the main() function for GEANT4 visualization. In order that your GEANT4 executable is able to perform visualization, you must instantiate and initialize *your* Visualization Manager in the main() function. The typical main() function available for visualization is written in the following style:

Listing 2.25: The typical main () routine available for visualization.

```
#include "G4VisExecutive.hh"
....
int main(int argc, char** argv) {
....
// Initialize visualization
G4VisManager* visManager = new G4VisExecutive;
// G4VisExecutive can take a verbosity argument - see /vis/verbose guidance.
// G4VisManager* visManager = new G4VisExecutive("Quiet");
visManager->Initialize();
....
// Job termination
delete visManager;
....
return 0;
}
```

Note that we are here recommending that all jobs instantiate a Visualization Manager. Even in batch mode you may generate an image using one of the file-writing drivers - DAWNFILE, VRML2FILE, HepRepFile, RayTracer.

Note also that it is your responsibility to delete the Visualization Manager. A good example of a main () function is examples/basic/B1/exampleB1.cc.

# 2.11.5 Sample Visualization Sessions

Most GEANT4 examples include a vis.mac. Run that macro to see a typical visualization. Read the comments in the macro to learn a little bit about some visualization commands. The vis.mac also includes commented-out optional visualization commands. By uncommenting some of these you can see additional visualization features.

# 2.11.6 For More Information on GEANT4 Visualization

See the Visualization part of this user guide.

## TOOLKIT FUNDAMENTALS

# 3.1 Class Categories and Domains

# 3.1.1 What is a class category?

In the design of a large software system such as GEANT4, it is essential to partition it into smaller logical units. This makes the design well organized and easier to develop. Once the logical units are defined independent to each other as much as possible, they can be developed in parallel without serious interference.

In object-oriented analysis and design methodology by Grady Booch [Booch1994], class categories are used to create logical units. They are defined as "clusters of classes that are themselves cohesive, but are loosely coupled relative to other clusters." This means that a class category contains classes which have a close relationship (for example, the "has-a" relation). However, relationships between classes which belong to different class categories are weak, i.e., only limited classes of these have "uses" relations. The class categories and their relations are presented by a class category diagram. The class category diagram designed for GEANT4 is shown in the figure below (Fig. 3.1). Each box in the figure represents a class category, and a "uses" relation by a straight line. The circle at an end of a straight line means the class category which has this circle uses the other category.

The file organization of the GEANT4 codes follows basically the structure of this class category. This *User's Manual* is also organized according to class categories.

In the development and maintenance of GEANT4, one software team will be assigned to a class category. This team will have a responsibility to develop and maintain all classes belonging to the class category.

# 3.1.2 Class categories in GEANT4

The following is a brief summary of the role of each class category in GEANT4.

#### 1. Run and Event

These are categories related to the generation of events, interfaces to event generators, and any secondary particles produced. Their roles are principally to provide particles to be tracked to the Tracking Management.

## 2. Tracking and Track

These are categories related to propagating a particle by analyzing the factors limiting the step and applying the relevant physics processes. The important aspect of the design was that a generalized GEANT4 physics process (or interaction) could perform actions, along a tracking step, either localized in space, or in time, or distributed in space and time (and all the possible combinations that could be built from these cases).

#### 3. Geometry and Magnetic Field

These categories manage the geometrical definition of a detector (solid modeling) and the computation of distances to solids (also in a magnetic field). The GEANT4 geometry solid modeler is based on the ISO STEP standard and it is fully compliant with it. A key feature of the GEANT4 geometry is that the volume definitions are independent of the solid representation. By this abstract interface for the G4 solids, the tracking component works identically for various representations. The treatment of the propagation in the presence of fields




Fig. 3.1: Class categories in GEANT4.

has been provided within specified accuracy. An OO design allows to exchange different numerical algorithms and/or different fields (not only B-field), without affecting any other component of the toolkit.

#### 4. Particle Definition and Matter

These two categories manage the the definition of materials and particles.

### 5. Physics

This category manages all physics processes participating in the interactions of particles in matter. The abstract interface of physics processes allows multiple implementations of physics models per interaction or per channel. Models can be selected by energy range, particle type, material, etc. Data encapsulation and polymorphism make it possible to give transparent access to the cross sections (independently of the choice of reading from an ascii file, or of interpolating from a tabulated set, or of computing analytically from a formula). Electromagnetic and hadronic physics were handled in a uniform way in such a design, opening up the physics to the users.

## 6. Hits and Digitization

These two categories manage the creation of hits and their use for the digitization phase. The basic design and implementation of the Hits and Digi had been realized, and also several prototypes, test cases and scenarios had been developed before the alpha-release. Volumes (not necessarily the ones used by the tracking) are aggregated in sensitive detectors, while hits collections represent the logical read out of the detector. Different ways of creating and managing hits collections had been delivered and tested, notably for both single hits and calorimetry hits types. In all cases, hits collections had been successfully stored into and retrieved from an Object Data Base Management System.

#### 7. Visualization

This manages the visualization of solids, trajectories and hits, and interacts with underlying graphical libraries (the Visualization class category). The basic and most frequently used graphics functionality had been implemented already by the alpha-release. The OO design of the visualization component allowed us to develop several drivers independently, such as for OpenGL, Qt and OpenInventor (for X11 and Windows), DAWN, Postscript (via DAWN) and VRML.

#### 8. Interfaces

This category handles the production of the graphical user interface (GUI) and the interactions with external software (OODBMS, reconstruction etc.).

# 3.2 Global Usage Classes

The "global" category in GEANT4 collects all classes, types, structures and constants which are considered of general use within the GEANT4 toolkit. This category also defines the interface with third-party software libraries (CLHEP, STL, etc.) and system-related types, by defining, where appropriate, typedefs according to the GEANT4 code conventions.

## 3.2.1 Signature of GEANT4 classes

In order to keep an homogeneous naming style, and according to the GEANT4 coding style conventions, each class part of the GEANT4 kernel has its name beginning with the prefix G4, e.g., G4VHit, G4GeometryManager, G4ProcessVector, etc. Instead of the raw C types, G4 types are used within the GEANT4 code. For the basic numeric types (int, float, double, etc.), different compilers and different platforms provide different value ranges. In order to assure portability, the use of G4int, G4float, G4double, G4bool, globally defined, is preferable. G4 types implement the right generic type for a given architecture.

### **Basic types**

The basic types in GEANT4 are considered to be the following:

- G4int,
- G4long,
- G4float,
- G4double,
- G4bool.
- G4complex,
- G4String.

which currently consist of simple typedefs to respective types defined in the **CLHEP**, **STL** or system libraries. Most definitions of these basic types come with the inclusion of a single header file, globals.hh. This file also provides inclusion of required system headers, as well as some global utility functions needed and used within the GEANT4 kernel.

## Typedefs to CLHEP classes and their usage

The following classes are typedefs to the corresponding classes of the CLHEP (Computing Library for High Energy Physics) distribution. For more detailed documentation please refer to the CLHEP documentation.

- G4ThreeVector, G4RotationMatrix, G4LorentzVector and G4LorentzRotation: Vector classes: defining 3-component (x,y,z) vector entities, rotation of such objects as 3x3 matrices, 4-component (x,y,z,t) vector entities and their rotation as 4x4 matrices.
- G4Plane3D, G4Transform3D, G4Normal3D, G4Point3D, G4Scale3D, and G4Vector3D: Geometrical classes: defining geometrical entities and transformations in 3D space.

### 3.2.2 The HEPRandom module in CLHEP

The *HEPRandom* module, originally part of the GEANT4 kernel, and now distributed as a module of **CLHEP**, has been designed and developed starting from the *Random* class of MC++, the original **CLHEP**'s *HepRandom* module and the **Rogue Wave** approach in the **Math.h++** package. For detailed documentation on the *HEPRandom* classes see the CLHEP documentation.

Information written in this manual is extracted from the original manifesto distributed with the HEPRandom package.

The *HEPRandom* module consists of classes implementing different random engines and different random distributions. A distribution associated to an engine constitutes a random generator. A distribution class can collect different algorithms and different calling sequences for each method to define distribution parameters or range-intervals. An engine implements the basic algorithm for pseudo-random numbers generation.

There are 3 different ways of shooting random values:

- 1. Using the static generator defined in the *HepRandom* class: random values are shot using static methods shoot () defined for each distribution class. The static generator will use, as default engine, a *MixMaxRng* object, and the user can set its properties or change it with a new instantiated engine object by using the static methods defined in the *HepRandom* class.
- 2. Skipping the static generator and specifying an engine object: random values are shot using static methods shoot (\*HepRandomEngine) defined for each distribution class. The user must instantiate an engine object and give it as argument to the shoot method. The generator mechanism will then be by-passed by using the basic flat () method of the specified engine. The user must take care of the engine objects he/she instantiates.
- 3. Skipping the static generator and instantiating a distribution object: random values are shot using fire() methods (NOT static) defined for each distribution class. The user must instantiate a distribution object giving as argument to the constructor an engine by pointer or by reference. By doing so, the engine will be associated to the distribution object and the generator mechanism will be by-passed by using the basic flat() method of that engine.

In this guide, we'll only focus on the static generator (point 1.), since the static interface of *HEPRandom* is the only one used within the GEANT4 toolkit.

#### **HEPRandom** engines

The class *HepRandomEngine* is the abstract class defining the interface for each random engine. It implements the getSeed() and getSeeds() methods which return the initial seed value and the initial array of seeds (if any) respectively. Many concrete random engines can be defined and added to the structure, simply making them inheriting from *HepRandomEngine*. Several different engines are currently implemented in *HepRandom*, we describe here five of them:

- HepJamesRandom
  - It implements the algorithm described in *F.James*, *Comp. Phys. Comm.* 60 (1990) 329 for pseudo-random number generation.
- DRand48Engine
  - Random engine using the drand48() and srand48() system functions from C standard library to implement the flat() basic distribution and for setting seeds respectively. *DRand48Engine* uses the seed48() function from C standard library to retrieve the current internal status of the generator, which is represented by 3 short values. *DRand48Engine* is the only engine defined in *HEPRandom* which intrinsically works in 32 bits precision. Copies of an object of this kind are not allowed.
- MixMaxRng
  - Random number engine implementing the MixMax Matrix Generator of Pseudorandom Numbers generator proposed by N.Z.Akopov, G.K.Saviddy and N.G.Ter-Arutyunian, J.Compt.Phy. 97, (1991) 573 and G.Savvidy and N.Savvidy, J.Comput.Phys. 97 (1991) 566. This is the default random engine for the static generator; it will be invoked by each distribution class unless the user sets a different one.

#### RanluxEngine

The algorithm for *RanluxEngine* has been taken from the original implementation in FORTRAN77 by Fred James, part of the **MATHLIB HEP** library. The initialisation is carried out using a Multiplicative Congruential generator using formula constants of L'Ecuyer as described in *F.James, Comp. Phys. Comm.* 60 (1990) 329-344. The engine provides five different luxury levels for quality of random generation. When instantiating a *RanluxEngine*, the user can specify the luxury level to the constructor (if not, the default value 3 is taken). For example:

```
RanluxEngine theRanluxEngine(seed,4);
// instantiates an engine with `seed' and the best luxury-level
... or
RanluxEngine theRanluxEngine;
// instantiates an engine with default seed value and luxury-level
...
```

The class provides a getLuxury () method to get the engine luxury level.

The SetSeed() and SetSeeds() methods to set the initial seeds for the engine, can be invoked specifying the luxury level. For example:

#### • RanecuEngine

The algorithm for *RanecuEngine* is taken from the one originally written in FORTRAN77 as part of the **MATH-LIB HEP** library. The initialisation is carried out using a Multiplicative Congruential generator using formula constants of L'Ecuyer as described in *F.James, Comp. Phys. Comm.* 60 (1990) 329-344. Handling of seeds for this engine is slightly different than the other engines in *HEPRandom*. Seeds are taken from a seed table given an index, the <code>getSeed()</code> method returns the current index of seed table. The <code>setSeeds()</code> method will set seeds in the local <code>SeedTable</code> at a given position index (if the index number specified exceeds the table's size, <code>[index%size]</code> is taken). For example:

```
// static interface
const G4long* table_entry;
table_entry = HepRandom::getTheSeeds();
// it returns a pointer `table_entry' to the local SeedTable
// at the current `index' position. The couple of seeds
// accessed represents the current `status' of the engine itself !
...
G4int index=n;
G4long seeds[2];
HepRandom::setTheSeeds(seeds,index);
// sets the new `index' for seeds and modify the values inside
// the local SeedTable at the `index' position. If the index
// is not specified, the current index in the table is considered.
...
```

The setSeed() method resets the current `status' of the engine to the original seeds stored in the static table of seeds in *HepRandom*, at the specified index.

Except for the *RanecuEngine*, for which the internal status is represented by just a couple of longs, all the other engines have a much more complex representation of their internal status, which currently can be obtained only through the methods <code>saveStatus()</code>, <code>restoreStatus()</code> and <code>showStatus()</code>, which can also be statically called from <code>HepRandom</code>. The status of the generator is needed for example to be able to reproduce a run or an event in a run at a given stage of the simulation.

RanecuEngine is probably the most suitable engine for this kind of operation, since its internal status can be fetched/reset by simply using getSeeds()/setSeeds()/setTheSeeds()/setTheSeeds() for the static interface in HepRandom).

### The static interface in the HepRandom class

HepRandom a singleton class and using a MixMaxRng engine as default algorithm for pseudo-random number generation. HepRandom defines a static private data member, theGenerator, and a set of static methods to manipulate it. By means of theGenerator, the user can change the underlying engine algorithm, get and set the seeds, and use any kind of defined random distribution. The static methods setTheSeed() and getTheSeed() will set and get respectively the initial seed to the main engine used by the static generator. For example:

Only one random engine can be active at a time, the user can decide at any time to change it, define a new one (if not done already) and set it. For example:

```
RanecuEngine theNewEngine;
HepRandom::setTheEngine(&theNewEngine);
...
```

or simply setting it to an old instantiated engine (the old engine status is kept and the new random sequence will start exactly from the last one previously interrupted). For example:

```
HepRandom::setTheEngine(&myOldEngine);
```

Other static methods defined in this class are:

- void setTheSeeds(const G4long\* seeds, G4int)
- const G4long\* getTheSeeds()

To set/get an array of seeds for the generator, in the case of a *RanecuEngine* this corresponds also to set/get the current status of the engine.

• HepRandomEngine\* getTheEngine()

To get a pointer to the current engine used by the static generator.

#### **HEPRandom** distributions

A distribution-class can collect different algorithms and different calling sequences for each method to define distribution parameters or range-intervals; it also collects methods to fill arrays, of specified size, of random values, according to the distribution. This class collects either static and not static methods. A set of distribution classes are defined in *HEPRandom*. Here is the description of some of them:

- RandFlat Class to shoot flat random values (integers or double) within a specified interval. The class provides also methods to shoot just random bits.
- RandExponential Class to shoot exponential distributed random values, given a mean (default mean = 1)
- RandGauss Class to shoot Gaussian distributed random values, given a mean (default = 0) or specifying also a deviation (default = 1). Gaussian random numbers are generated two at the time, so every other time a number is shot, the number returned is the one generated the time before.
- RandBreitWigner Class to shoot numbers according to the Breit-Wigner distribution algorithms (plain or mean^2).

• RandPoisson Class to shoot numbers according to the Poisson distribution, given a mean (default = 1) (Algorithm taken from W.H.Press et al., Numerical Recipes in C, Second Edition).

### 3.2.3 The HEPNumerics module

A set of classes implementing numerical algorithms has been developed in GEANT4. Most of the algorithms and methods have been implemented mainly based on recommendations given in the books:

- B.H. Flowers, An introduction to Numerical Methods In C++, Clarendon Press, Oxford 1995.
- M. Abramowitz, I. Stegun, *Handbook of mathematical functions*, DOVER Publications INC, New York 1965; chapters 9, 10, and 22.

This set of classes includes:

- G4ChebyshevApproximation Class creating the Chebyshev approximation for a function pointed by
  fFunction data member. The Chebyshev polynomial approximation provides an efficient evaluation of the minimax polynomial, which (among all polynomials of the same degree) has the smallest maximum deviation from
  the true function.
- G4DataInterpolation Class providing methods for data interpolations and extrapolations: Polynomial, Cubic Spline, ...
- G4GaussChebyshevQ
- G4GaussHermiteQ
- G4GaussJacobiQ
- G4GaussLaguerreQ Classes implementing the Gauss-Chebyshev, Gauss-Hermite, Gauss-Jacobi, Gauss-Laguerre and Gauss-Legendre quadrature methods. Roots of orthogonal polynomials and corresponding weights are calculated based on iteration method (by bisection Newton algorithm).
- G4Integrator Template class collecting integrator methods for generic functions (Legendre, Simpson, Adaptive Gauss, Laguerre, Hermite, Jacobi).
- G4SimpleIntegration Class implementing simple numerical methods (Trapezoidal, MidPoint, Gauss, Simpson, Adaptive Gauss, for integration of functions with signature: double f(double).

# 3.2.4 General management classes

The global category defines also a set of utility classes generally used within the kernel of GEANT4. These classes include:

• G4Allocator

A class for fast allocation of objects to the heap through paging mechanism. It's meant to be used by associating it to the object to be allocated and defining for it new and delete operators via MallocSingle() and FreeSingle() methods of G4Allocator.

**Note:** G4Allocator assumes that objects being allocated have all the same size for the type they represent. For this reason, classes which are handled by G4Allocator should *avoid* to be used as base-classes for others. Similarly, base-classes of sub-classes handled through G4Allocator should not define their (eventually empty) virtual destructors inlined; such measure is necessary in order also to prevent bad aliasing optimisations by compilers which may potentially lead to crashes in the attempt to free allocated chunks of memory when using the base-class pointer or not.

The list of allocators implicitly defined and used in GEANT4 is reported here:

- events (G4Event): anEventAllocator
- tracks (G4Track): aTrackAllocator
- stacked tracks (G4StackedTrack): aStackedTrackAllocator
- primary particles (G4PrimaryParticle): aPrimaryParticleAllocator
- primary vertices (G4PrimaryVertex): aPrimaryVertexAllocator

- decay products (G4DecayProducts): aDecayProductsAllocator
- digits collections of an event (G4DCofThisEvent): anDCoTHAllocator
- digits collections (G4DigiCollection): aDCAllocator
- hits collections of an event (G4HCofThisEvent): anHCoTHAllocator
- hits collections (G4HitsCollection): anHCAllocator
- touchable histories (G4TouchableHistory): aTouchableHistoryAllocator
- trajectories (G4Trajectory): aTrajectoryAllocator
- trajectory points (G4TrajectoryPoint): aTrajectoryPointAllocator
- trajectory containers (G4TrajectoryContainer): aTrajectoryContainerAllocator
- navigation levels (G4NavigationLevel): aNavigationLevelAllocator
- navigation level nodes (G4NavigationLevelRep): aNavigLevelRepAllocator
- reference-counted handles (G4ReferenceCountedHandle<X>): aRCHAllocator
- counted objects (G4CountedObject<X>): aCountedObjectAllocator
- HEPEvt primary particles (G4HEPEvtParticle): aHEPEvtParticleAllocator
- electron occupancy objects(G4ElectronOccupancy): aElectronOccupancyAllocator
- "rich" trajectories (G4RichTrajectory): aRichTrajectoryAllocator
- "rich" trajectory points (G4RichTrajectoryPoint): aRichTrajectoryPointAllocator
- "smooth" trajectories (G4SmoothTrajectory): aSmoothTrajectoryAllocator
- "smooth" trajectory points (G4SmoothTrajectoryPoint): aSmoothTrajectoryPointAllocator
- "ray" trajectories (G4RayTrajectory): G4RayTrajectoryAllocator
- "ray" trajectory points (G4RayTrajectoryPoint): G4RayTrajectoryPointAllocator

For each of these allocators, accessible from the global namespace, it is possible to monitor the allocation in their memory pools or force them to release the allocated memory (for example at the end of a run):

```
// Return the size of the total memory allocated for tracks
//
aTrackAllocator.GetAllocatedSize();

// Return allocated storage for tracks to the free store
//
aTrackAllocator.ResetStorage();
```

• G4ReferenceCountedHandle

Template class acting as a smart pointer and wrapping the type to be counted. It performs the reference counting during the life-time of the counted object.

• G4FastVector

Template class defining a vector of pointers, not performing boundary checking.

• G4PhysicsVector

Defines a physics vector which has values of energy-loss, cross-section, and other physics values of a particle in matter in a given range of the energy, momentum, etc. This class serves as the base class for a vector having various energy scale, for example like 'log' (G4PhysicsLogVector) 'linear' (G4PhysicsLinearVector), 'free' (G4PhysicsFreeVector), etc.

• G4LPhysicsFreeVector

Implements a free vector for low energy physics cross-section data. A subdivision method is used to find the energylmomentum bin.

• G4PhysicsOrderedFreeVector

A physics ordered free vector inherits from G4PhysicsVector. It provides, in addition, a method for the user to insert energy/value pairs in sequence. Methods to retrieve the max and min energies and values from the vector are also provided.

• G4Timer

Utility class providing methods to measure elapsed user/system process time. Uses <sys/times.h> and <unistd.h> - POSIX.1.

• G4UserLimits

Class collecting methods for get and set any kind of step limitation allowed in GEANT4.

• G4UnitsTable

Placeholder for the system of units in GEANT4.

# 3.3 System of units

## 3.3.1 Basic units

GEANT4 offers the user the possibility to choose and use the preferred units for any quantity. In fact, GEANT4 takes care of the units. Internally a consistent set on units based on the HepSystemOfUnits is used:

```
millimeter
                         (mm)
nanosecond
                         (ns)
Mega electron Volt
                         (MeV)
positron charge
                         (eplus)
degree Kelvin
                         (kelvin)
the amount of substance (mole)
luminous intensity
                         (candela)
radian
                         (radian)
steradian
                         (steradian)
```

All other units are defined from the basic ones.

For instance:

```
millimeter = mm = 1;
meter = m = 1000*mm;
...
m3 = m*m*m;
...
```

In the file \$CLHEP\_BASE\_DIR/include/CLHEP/Units/SystemOfUnits.h from the CLHEP installation, one can find all units definitions.

One can also change the system of units to be used by the kernel.

# 3.3.2 Input your data

#### Avoid 'hard coded' data

The user **must** give the units for the data to introduce:

```
G4double Size = 15*km, KineticEnergy = 90.3*GeV, density = 11*mg/cm3;
```

GEANT4 assumes that these specifications for the units are respected, in order to assure independence from the units chosen in the client application.

If units are not specified in the client application, data are implicitly treated in internal GEANT4 system units; this practice is however strongly discouraged.

If the data set comes from an array or from an external file, it is strongly recommended to set the units as soon as the data are read, before any treatment. For instance:

```
for (int j=0, j<jmax, j++) CrossSection[j] *= millibarn;
...
my calculations
...</pre>
```

#### Interactive commands

Some built-in commands from the User Interface (UI) also require units to be specified.

For instance:

```
/gun/energy 15.2 keV
/gun/position 3 2 -7 meter
```

If units are not specified, or are not valid, the command is refused.

# 3.3.3 Output your data

You can output your data with the wished units. To do so, it is sufficient to **divide** the data by the corresponding unit:

```
G4cout << KineticEnergy/keV << " keV";
G4cout << density/(g/cm3) << " g/cm3";
```

Of course, G4cout << KineticEnergy will print the energy in the internal units system.

There is another way to output the data. Let GEANT4 choose the most appropriate units for the actual numerical value of the data. It is sufficient to specify to which category the data belong to (Length, Time, Energy, etc.). For example:

```
G4cout << G4BestUnit(StepSize, "Length");
```

StepSize will be printed in km, m, mm, fermi, etc. depending of its actual value.

## 3.3.4 Introduce new units

If wished to introduce new units, there are two methods:

• You can extend the file SystemOfUnits.h

```
#include "SystemOfUnits.h"
static const G4double inch = 2.54*cm;
```

Using this method, it is not easy to define composed units. It is better to do the following:

• Instantiate an object of the class G4UnitDefinition. These objects are owned by the global G4UnitsTable at construction, and must not be deleted by the user.

```
new G4UnitDefinition ( name, symbol, category, value )
```

For example: define a few units for speed

```
new G4UnitDefinition ( "km/hour" , "km/h", "Speed", km/(3600*s) );
new G4UnitDefinition ( "meter/ns", "m/ns", "Speed", m/ns );
```

The category "Speed" does not exist by default in G4UnitsTable, but it will be created automatically. The class G4UnitDefinition is defined in source/global/management/G4UnitsTable.hh.

## 3.3.5 Print the list of units

You can print the list of units with the static function: G4UnitDefinition::PrintUnitsTable(); or with the interactive command: /units/list

## 3.4 Run

# 3.4.1 Basic concept of Run

In GEANT4, *Run* is the largest unit of simulation. A run consists of a sequence of events. Within a run, the detector geometry, the set up of sensitive detectors, and the physics processes used in the simulation should be kept unchanged. A run is represented by a G4Run class object. A run starts with BeamOn () method of G4RunManager.

#### Representation of a run

G4Run represents a run. It has a run identification number, which should be set by the user, and the number of events simulated during the run. Please note that the run identification number is not used by the GEANT4 kernel, and thus can be arbitrarily assigned at the user's convenience.

G4Run has pointers to the tables G4VHitsCollection and G4VDigiCollection. These tables are associated in case *sensitive detectors* and *digitizer modules* are simulated, respectively. The usage of these tables will be mentioned in *Hits* and *Digitization*.

G4Run has two virtual methods, and thus you can extend G4Run class. In particular if you use GEANT4 in multithreaded mode and need to accumulate values, these two virtual method must be overwritten to specify how such values should be collected firstly for a worker thread, and then for the entire run. These virtual methods are the following.

- virtual void RecordEvent (const G4Event\*) Method to be overwritten by the user for recording events in this (thread-local) run. At the end of the implementation, G4Run base-class method for must be invoked for recording data members in the base class.
- void Merge (const G4Run\*) Method to be overwritten by the user for merging local Run object to the global Run object. At the end of the implementation, G4Run base-class method for must be invoked for merging data members in the base class.

#### Manage the run procedures

G4RunManager manages the procedures of a run. In the constructor of G4RunManager, all of the manager classes in GEANT4 kernel, except for some static managers, are constructed. These managers are deleted in the destructor of G4RunManager. G4RunManager must be a singleton created in the user's main() program; the pointer to this singleton object can be obtained by other code using the GetRunManager() static method.

As already mentioned in *How to Define the main() Program*, all of the *user initialization* classes defined by the user should be assigned to G4RunManager before starting initialization of the GEANT4 kernel. The assignments of these user classes are done by SetUserInitialization() methods. All user classes defined by the GEANT4 kernel will be summarized in *User Actions*.

G4RunManager has several public methods, which are listed below.

Initialize () All initializations required by the GEANT4 kernel are triggered by this method. Initializations are:

- construction of the detector geometry and set up of sensitive detectors and/or digitizer modules,
- construction of particles and physics processes,
- calculation of cross-section tables.

3.4. Run 65

This method is thus mandatory before proceeding to the first run. This method will be invoked automatically for the second and later runs in case some of the initialized quantities need to be updated.

- **BeamOn (G4int numberOfEvent)** This method triggers the actual simulation of a run, that is, an event loop. It takes an integer argument which represents the number of events to be simulated.
- **GetRunManager** () This static method returns the pointer to the G4RunManager singleton object.
- **GetCurrentEvent ()** This method returns the pointer to the G4Event object which is currently being simulated. This method is available only when an event is being processed. At this moment, the application state of GEANT4, which is explained in the following sub-section, is "EventProc". When GEANT4 is in a state other than "EventProc", this method returns null. Please note that the return value of this method is const G4Event \* and thus you cannot modify the contents of the object.
- **SetNumberOfEventsToBeStored (G4int nPrevious)** When simulating the "pile up" of more than one event, it is essential to access more than one event at the same moment. By invoking this method, G4RunManager keeps nPrevious G4Event objects. This method must be invoked before proceeding to BeamOn().
- **GetPreviousEvent (G4int i\_thPrevious)** The pointer to the i\_thPrevious G4Event object can be obtained through this method. A pointer to a const object is returned. It is inevitable that i\_thPrevious events must have already been simulated in the same run for getting the i\_thPrevious event. Otherwise, this method returns null.
- **AbortRun ()** This method should be invoked whenever the processing of a run must be stopped. It is valid for GeomClosed and EventProc states. Run processing will be safely aborted even in the midst of processing an event. However, the last event of the aborted run will be incomplete and should not be used for further analysis.

### Run manager classes for multi-threading mode

G4MTRunManager is the replacement of G4RunManager for multi-threading mode. At the very end of Initialize() method, G4MTRunManager creates and starts worker threads. The event each thread is tasked is in first-come-first-served basis, so that event numbers each thread has are not sequential.

G4WorkerRunManager is the local RunManager automatically instantiated by G4MTRunManager to take care of initialization and event handling of a thread. Both G4MTRunManager and G4WorkerRunManager are derived classes of G4RunManager base class.

The static method G4RunManager::GetRunManager() returns the following pointer.

- It returns the pointer to the G4WorkerRunManager of the local thread when it is invoked from thread-local object.
- It returns the pointer to the G4MTRunManager when it is invoked from shared object.
- It returns the pointer to the base G4RunManager if it is used in the sequential mode.

G4RunManager has a method GetRunManagerType() that returns an enum named RMType to indicate what kind of RunManager it is. RMType is defined as { sequentialRM, masterRM, workerRM }. From the thread-local object, a static method G4MTRunManager::GetMasterRunManager() is available to access to G4MTRunManager. From a worker thread, the user may access to, for example, detector construction (it is a shared class) through this GetMasterRunManager() method.

#### G4UserRunAction

G4UserRunAction is one of the *user action* classes from which you can derive your own concrete class. This base class has three virtual methods as follows:

**GenerateRun ()** This method is invoked at the beginning of the BeamOn() method but after confirmation of the conditions of the GEANT4 kernel. This method should be used to instantiate a user-specific run class object.

**BeginOfRunAction ()** This method is invoked at the beginning of the BeamOn() method but after confirmation of the conditions of the GEANT4 kernel. Likely uses of this method include:

- setting a run identification number,
- · booking histograms,
- setting run specific conditions of the sensitive detectors and/or digitizer modules (e.g., dead channels).

**EndOfRunAction ()** This method is invoked at the very end of the BeamOn() method. Typical use cases of this method are

- · store/print histograms,
- manipulate run summaries.

#### 3.4.2 GEANT4 as a state machine

GEANT4 is designed as a state machine. Some methods in GEANT4 are available for only a certain state(s). G4RunManager controls the state changes of the GEANT4 application. States of GEANT4 are represented by the enumeration G4ApplicationState. It has six states through the life cycle of a GEANT4 application.

- **G4State\_PreInit state** A GEANT4 application starts with this state. The application needs to be initialized when it is in this state. The application occasionally comes back to this state if geometry, physics processes, and/or cut-off have been changed after processing a run.
- **G4State\_Init state** The application is in this state while the Initialize() method of G4RunManager is being invoked. Methods defined in any user initialization classes are invoked during this state.
- **G4State\_Idle state** The application is ready for starting a run.
- **G4State\_GeomClosed state** When BeamOn() is invoked, the application proceeds to this state to process a run. Geometry, physics processes, and cut-off cannot be changed during run processing.
- **G4State\_EventProc state** A GEANT4 application is in this state when a particular event is being processed. GetCurrentEvent() and GetPreviousEvent() methods of G4RunManager are available only at this state.
- **G4State\_Quit state** When the destructor of G4RunManager is invoked, the application comes to this "dead end" state. Managers of the GEANT4 kernel are being deleted and thus the application cannot come back to any other state.
- **G4State\_Abort state** When a G4Exception occurs, the application comes to this "dead end" state and causes a core dump. The user still has a hook to do some "safe" operations, e.g. storing histograms, by implementing a user concrete class of G4VStateDependent. The user also has a choice to suppress the occurrence of G4Exception by a UI command /control/suppressAbortion. When abortion is suppressed, you will still get error messages issued by G4Exception, and there is NO guarantee of a correct result after the G4Exception error message.

G4StateManager belongs to the intercoms category.

3.4. Run 67

# 3.4.3 User's hook for state change

In case the user wants to do something at the moment of state change of GEANT4, the user can create a concrete class of the G4VStateDependent base class. For example, the user can store histograms when G4Exception occurs and GEANT4 comes to the *Abort* state, but before the actual core dump.

The following is an example user code which stores histograms when GEANT4 becomes to the *Abort* state. This class object should be made in, for example main(), by the user code. This object will be automatically registered to G4StateManager at its construction.

Listing 3.1: Header file of UserHookForAbortState

```
#ifndef UserHookForAbortState_H
#define UserHookForAbortState_H 1

#include "G4VStateDependent.hh"

class UserHookForAbortState : public G4VStateDependent
{
   public:
    UserHookForAbortState(); // constructor
   ~UserHookForAbortState(); // destructor

   virtual G4bool Notify(G4ApplicationState requiredState);
};
```

Listing 3.2: Source file of UserHookForAbortState

```
#include "UserHookForAbortState.hh"

UserHookForAbortState::UserHookForAbortState() {;}
UserHookForAbortState::~UserHookForAbortState() {;}

G4bool UserHookForAbortState::Notify(G4ApplicationState requiredState)
{
   if(requiredState!=Abort) return true;

   // Do book keeping here
   return true;
}
```

## 3.4.4 Customizing the Run Manager

#### Virtual Methods in the Run Manager

G4RunManager is a concrete class with a complete set of functionalities for managing the GEANT4 kernel. It is the only manager class in the GEANT4 kernel which must be constructed in the main() method of the user's application. Thus, instead of constructing the G4RunManager provided by GEANT4, you are free to construct your own RunManager. It is recommended, however, that your RunManager inherit G4RunManager. For this purpose, G4RunManager has various virtual methods which provide all the functionalities required to handle the GEANT4 kernel. Hence, your customized run manager need only override the methods particular to your needs; the remaining methods in G4RunManager base class can still be used. A summary of the available methods is presented here:

```
public: virtual void Initialize(); main entry point of GEANT4 kernel initialization
protected: virtual void InitializeGeometry(); geometry construction
protected: virtual void InitializePhysics(); physics processes construction
public: virtual void BeamOn(G4int n_event); main entry point of the event loop
```

```
protected: virtual G4bool ConfirmBeamOnCondition(); check the kernel conditions for the
    event loop

protected: virtual void RunInitialization(); prepare a run

protected: virtual void DoEventLoop(G4int n_events); manage an event loop

protected: virtual G4Event* GenerateEvent(G4int i_event); generation of G4Event object

protected: virtual void AnalyzeEvent(G4Event* anEvent); storage/analysis of an event

protected: virtual void RunTermination(); terminate a run

public: virtual void DefineWorldVolume(G4VPhysicalVolume * worldVol); set the
    world volume to G4Navigator

public: virtual void AbortRun(); abort the run
```

## **Customizing the Event Loop**

In G4RunManager the event loop is handled by the virtual method DoEventLoop (). This method is implemented by a for loop consisting of the following steps:

- 1. construct a G4Event object and assign to it primary vertex(es) and primary particles. This is done by the virtual GeneratePrimaryEvent () method.
- 2. send the G4Event object to G4EventManager for the detector simulation. *Hits* and *trajectories* will be associated with the G4Event object as a consequence.
- 3. perform bookkeeping for the current G4Event object. This is done by the virtual AnalyzeEvent () method.

DoEventLoop() performs the entire simulation of an event. However, it is often useful to split the above three steps into isolated application programs. If, for example, you wish to examine the effects of changing discriminator thresholds, ADC gate widths and/or trigger conditions on simulated events, much time can be saved by performing steps 1 and 2 in one program and step 3 in another. The first program need only generate the hit/trajectory information once and store it, perhaps in a database. The second program could then retrieve the stored G4Event objects and perform the digitization (analysis) using the above threshold, gate and trigger settings. These settings could then be changed and the digitization program re-run without re-generating the G4Events.

#### **Changing the Detector Geometry**

The detector geometry defined in your G4VUserDetectorConstruction concrete class can be changed during a run break (between two runs). Two different cases are considered.

The first is the case in which you want to delete the entire structure of your old geometry and build up a completely new set of volumes. For this case, you need to delete them by yourself, and let *RunManager* invokes Construct() and ConstructSDandField() methods of your detector construction once again when RunManager starts the next run.

```
G4RunManager* runManager = G4RunManager::GetRunManager();
runManager->ReinitializeGeometry();
```

If this ReinitializeGeometry() is invoked, GeometryHasBeenModified() (discussed next) is automatically invoked. Presumably this case is rather rare. The second case is more frequent for the user.

The second case is the following. Suppose you want to move and/or rotate a particular piece of your detector component. This case can easily happen for a beam test of your detector. It is obvious for this case that you need not change the world volume. Rather, it should be said that your world volume (experimental hall for your beam test) should be big enough for moving/rotating your test detector. For this case, you can still use all of your detector geometries, and just use a Set method of a particular physical volume to update the transformation vector as you want. Thus, you don't need to re-set your world volume pointer to *RunManager*.

If you want to change your geometry for every run, you can implement it in the BeginOfRunAction() method of G4UserRunAction class, which will be invoked at the beginning of each run, or, derive the

3.4. Run 69

RunInitialization() method. Please note that, for both of the above mentioned cases, you need to let *Run-Manager* know "the geometry needs to be closed again". Thus, you need to invoke

```
runManager->GeometryHasBeenModified();
```

before proceeding to the next run. An example of changing geometry is given in a GEANT4 tutorial in GEANT4 Training kit #2.

### Switch physics processes

In the InitializePhysics () method, G4VUserPhysicsList::Construct is invoked in order to define particles and physics processes in your application. Basically, you can not add nor remove any particles during execution, because particles are static objects in GEANT4 (see *How to Specify Particles* and *Particles* for details). In addition, it is very difficult to add and/or remove physics processes during execution, because registration procedures are very complex, except for experts (see *How to Specify Physics Processes* and *Physics Processes*). This is why the initializePhysics () method is assumed to be invoked at once in GEANT4 kernel initialization.

However, you can switch on/off physics processes defined in your G4VUserPhysicsList concrete class and also change parameters in physics processes during the run break.

You can use ActivateProcess() and InActivateProcess() methods of G4ProcessManager anywhere outside the event loop to switch on/off some process. You should be very careful to switch on/off processes inside the event loop, though it is not prohibited to use these methods even in the *EventProc* state.

It is a likely case to change cut-off values in a run. You can change defaultCutValue in G4VUserPhysicsList during the *Idle* state. In this case, all cross section tables need to be recalculated before the event loop. You should use the CutOffHasBeenModified() method when you change cut-off values so that the SetCuts method of your *PhysicsList* concrete class will be invoked.

## 3.4.5 Managing worker thread

G4UserWorkerInitialization is an additional user initialization class to be used only for the multi-threaded mode. The object of this class can be set to G4MTRunManager, but not to G4RunManager. G4UserWorkerInitialization class has five virtual methods as the user hooks which are invoked at several occasions of the life cycle of each thread.

- virtual void WorkerInitialize() const This method is called after the tread is created but before the G4WorkerRunManager is instantiated.
- **virtual void WorkerStart() const** This method is called once at the beginning of simulation job when kernel classes and user action classes have already instantiated but geometry and physics have not been yet initialized. This situation is identical to "PreInit" state in the sequential mode.
- **virtual void WorkerStartRun () const** This method is called before an event loop. Geometry and physics have already been set up for the thread. All threads are synchronized and ready to start the local event loop. This situation is identical to "Idle" state in the sequential mode.
- virtual void WorkerRunEnd() const This method is called for each thread when the local event loop is done, but before the synchronization over all worker threads.
- virtual void WorkerStop() const This method is called once at the end of simulation job.

# 3.5 Event

# 3.5.1 Representation of an event

G4Event represents an event. An object of this class contains all inputs and outputs of the simulated event. This class object is constructed in G4RunManager and sent to G4EventManager. The event currently being processed can be obtained via the getCurrentEvent () method of G4RunManager.

## 3.5.2 Structure of an event

A G4Event object has four major types of information. Get methods for this information are available in G4Event.

**Primary vertexes and primary particles** Details are given in *Event Generator Interface*.

**Trajectories** Trajectories are stored in G4TrajectoryContainer class objects and the pointer to this container is stored in G4Event. The contents of a trajectory are given in *Trajectory and Trajectory Point*.

**Hits collections** Collections of hits generated by *sensitive detectors* are kept in G4HCofThisEvent class object and the pointer to this container class object is stored in G4Event. See *Hits* for the details.

**Digits collections** Collections of digits generated by *digitizer modules* are kept in G4DCofThisEvent class object and the pointer to this container class object is stored in G4Event. See *Digitization* for the details.

# 3.5.3 Mandates of G4EventManager

G4EventManager is the manager class to take care of one event. It is responsible for:

- converting G4PrimaryVertex and G4PrimaryParticle objects associated with the current G4Event object to G4Track objects. All of G4Track objects representing the primary particles are sent to G4StackManager.
- Pop one G4Track object from G4StackManager and send it to G4TrackingManager. The current G4Track object is deleted by G4EventManager after the track is simulated by G4TrackingManager, if the track is marked as "killed".
- In case the primary track is "suspended" or "postponed to next event" by G4TrackingManager, it is sent back to the G4StackManager. Secondary G4Track objects returned by G4TrackingManager are also sent to G4StackManager.
- When G4StackManager returns NULL for the "pop" request, G4EventManager terminates the current processing event.
- invokes the user-defined methods beginOfEventAction() and endOfEventAction() from the G4UserEventAction class. See *User Information Classes* for details.

# 3.5.4 Stacking mechanism

G4StackManager has three stacks, named *urgent*, *waiting* and *postpone-to-next-event*, which are objects of the G4TrackStack class. By default, all G4Track objects are stored in the *urgent* stack and handled in a "last in first out" manner. In this case, the other two stacks are not used. However, tracks may be routed to the other two stacks by the user-defined G4UserStackingAction concrete class.

If the methods of G4UserStackingAction have been overridden by the user, the *postpone-to-next-event* and waiting stacks may contain tracks. At the beginning of an event, G4StackManager checks to see if any tracks left over from the previous event are stored in the *postpone-to-next-event stack*. If so, it attempts to move them to the *urgent* stack. But first the PrepareNewEvent() method of G4UserStackingAction is called. Here tracks may be re-classified by the user and sent to the *urgent* or *waiting* stacks, or deferred again to the *postpone-to-next-event* stack. As the event is processed G4StackManager pops tracks from the *urgent* stack until it is empty. At this point

3.5. Event 71

the NewStage () method of G4UserStackingAction is called. In this method tracks from the *waiting* stack may be sent to the *urgent* stack, retained in the *waiting* stack or postponed to the next event.

Details of the user-defined methods of G4UserStackingAction and how they affect track stack management are given in *User Information Classes*.

## 3.6 Event Generator Interface

# 3.6.1 Structure of a primary event

#### Primary vertex and primary particle

The G4Event class object should have a set of primary particles when it is sent to G4EventManager via processOneEvent() method. It is the mandate of your G4VUserPrimaryGeneratorAction concrete class to send primary particles to the G4Event object.

The G4PrimaryParticle class represents a primary particle with which GEANT4 starts simulating an event. This class object has information on particle type and its three momenta. The positional and time information of primary particle(s) are stored in the G4PrimaryVertex class object and, thus, this class object can have one or more G4PrimaryParticle class objects which share the same vertex. Primary vertexes and primary particles are associated with the G4Event object by a form of linked list.

A concrete class of G4VPrimaryGenerator, the G4PrimaryParticle object is constructed with either a pointer to G4ParticleDefinition or an integer number which represents P.D.G. particle code. For the case of some artificial particles, e.g., geantino, optical photon, etc., or exotic nuclear fragments, which the P.D.G. particle code does not cover, the G4PrimaryParticle should be constructed by G4ParticleDefinition pointer. On the other hand, elementary particles with very short life time, e.g., weak bosons, or quarks/gluons, can be instantiated as G4PrimaryParticle objects using the P.D.G. particle code. It should be noted that, even though primary particles with such a very short life time are defined, GEANT4 will simulate only the particles which are defined as G4ParticleDefinition class objects. Other primary particles will be simply ignored by G4EventManager. But it may still be useful to construct such "intermediate" particles for recording the origin of the primary event.

#### Forced decay channel

The G4PrimaryParticle class object can have a list of its daughter particles. If the parent particle is an "intermediate" particle, which GEANT4 does not have a corresponding G4ParticleDefinition, this parent particle is ignored and daughters are assumed to start from the vertex with which their parent is associated. For example, a Z boson is associated with a vertex and it has positive and negative muons as its daughters, these muons will start from that vertex.

There are some kinds of particles which should fly some reasonable distances and, thus, should be simulated by GEANT4, but you still want to follow the decay channel generated by an event generator. A typical case of these particles is B meson. Even for the case of a primary particle which has a corresponding G4ParticleDefinition, it can have daughter primary particles. GEANT4 will trace the parent particle until it comes to decay, obeying multiple scattering, ionization loss, rotation with the magnetic field, etc. according to its particle type. When the parent comes to decay, instead of randomly choosing its decay channel, it follows the "pre-assigned" decay channel. To conserve the energy and the momentum of the parent, daughters will be Lorentz transformed according to their parent's frame.

# 3.6.2 Interface to a primary generator

#### **G4HEPEvtInterface**

Unfortunately, almost all event generators presently in use, commonly are written in FORTRAN. For GEANT4, it was decided to not link with any FORTRAN program or library, even though the C++ language syntax itself allows such a link. Linking to a FORTRAN package might be convenient in some cases, but we will lose many advantages of object-oriented features of C++, such as robustness. Instead, GEANT4 provides an ASCII file interface for such event generators.

G4HEPEvtInterface is one of G4VPrimaryGenerator concrete class and thus it can be used in your G4VUserPrimaryGeneratorAction concrete class. G4HEPEvtInterface reads an ASCII file produced by an event generator and reproduces G4PrimaryParticle objects associated with a G4PrimaryVertex object. It reproduces a full production chain of the event generator, starting with primary quarks, etc. In other words, G4HEPEvtInterface converts information stored in the /HEPEVT/ common block to an object-oriented data structure. Because the /HEPEVT/ common block is commonly used by almost all event generators written in FORTRAN, G4HEPEvtInterface can interface to almost all event generators currently used in the HEP community. The constructor of G4HEPEvtInterface takes the file name. Listing 3.3 shows an example how to use G4HEPEvtInterface. Note that an event generator is not assumed to give a place of the primary particles, the interaction point must be set before invoking GeneratePrimaryVertex() method.

Listing 3.3: An example code for G4HEPEvtInterface

```
#ifndef ExN04PrimaryGeneratorAction_h
#define ExN04PrimaryGeneratorAction_h 1
#include "G4VUserPrimaryGeneratorAction.hh"
#include "globals.hh"
class G4VPrimaryGenerator;
class G4Event;
class ExNO4PrimaryGeneratorAction : public G4VUserPrimaryGeneratorAction
 public:
   ExN04PrimaryGeneratorAction();
    ~ExN04PrimaryGeneratorAction();
   void GeneratePrimaries(G4Event* anEvent);
 private:
    G4VPrimaryGenerator* HEPEvt;
#endif
#include "ExN04PrimaryGeneratorAction.hh"
#include "G4Event.hh"
#include "G4HEPEvtInterface.hh"
ExN04PrimaryGeneratorAction::ExN04PrimaryGeneratorAction()
  HEPEvt = new G4HEPEvtInterface("pythia_event.data");
ExN04PrimaryGeneratorAction::~ExN04PrimaryGeneratorAction()
  delete HEPEvt;
```

(continues on next page)

(continued from previous page)

```
void ExN04PrimaryGeneratorAction::GeneratePrimaries(G4Event* anEvent)
{
   HEPEvt->SetParticlePosition(G4ThreeVector(0.*cm,0.*cm,0.*cm));
   HEPEvt->GeneratePrimaryVertex(anEvent);
}
```

#### Format of the ASCII file

An ASCII file, which will be fed by G4HEPEvtInterface should have the following format.

- The first line of each primary event should be an integer which represents the number of the following lines of primary particles.
- Each line in an event corresponds to a particle in the /HEPEVT/ common. Each line has ISTHEP, IDHEP, JDAHEP(1), JDAHEP(2), PHEP(1), PHEP(2), PHEP(3), PHEP(5). Refer to the /HEPEVT/ manual for the meanings of these variables.

Listing 3.4 shows an example FORTRAN code to generate an ASCII file.

Listing 3.4: A FORTRAN example using the /HEPEVT/ common.

```
SUBROUTINE HEP2G4
* Convert /HEPEVT/ event structure to an ASCII file
 to be fed by G4HEPEvtInterface
      PARAMETER (NMXHEP=2000)
      COMMON/HEPEVT/NEVHEP, NHEP, ISTHEP (NMXHEP), IDHEP (NMXHEP),
     >JMOHEP (2,NMXHEP), JDAHEP (2,NMXHEP),PHEP (5,NMXHEP),VHEP (4,NMXHEP)
      DOUBLE PRECISION PHEP, VHEP
      WRITE (6, *) NHEP
      DO IHEP=1, NHEP
      WRITE (6,10)
     > ISTHEP (IHEP), IDHEP (IHEP), JDAHEP (1, IHEP), JDAHEP (2, IHEP),
     > PHEP (1, IHEP), PHEP (2, IHEP), PHEP (3, IHEP), PHEP (5, IHEP)
      FORMAT (4I10, 4 (1X, D15.8))
      ENDDO
      RETURN
      END
```

## Future interface to the new generation generators

Several activities have already been started for developing object-oriented event generators. Such new generators can be easily linked and used with a GEANT4 based simulation. Furthermore, we need not distinguish a primary generator from the physics processes used in GEANT4. Future generators can be a kind of physics process plugged-in by inheriting G4VProcess.

# 3.6.3 Event overlap using multiple generators

Your G4VUserPrimaryGeneratorAction concrete class can have more than one G4VPrimaryGenerator concrete class. Each G4VPrimaryGenerator concrete class can be accessed more than once per event. Using these class objects, one event can have more than one primary event.

One possible use is the following. Within an event, a G4HEPEvtInterface class object instantiated with a minimum bias event file is accessed 20 times and another G4HEPEvtInterface class object instantiated with a signal event file is accessed once. Thus, this event represents a typical signal event of LHC overlapping 20 minimum bias events. It should be noted that a simulation of event overlapping can be done by merging hits and/or digits associated with several events, and these events can be simulated independently. Digitization over multiple events will be mentioned in *Digitization*.

# 3.7 Event Biasing Techniques

# 3.7.1 Scoring, Geometrical Importance Sampling and Weight Roulette

GEANT4 provides event biasing techniques which may be used to save computing time in such applications as the simulation of radiation shielding. These are *geometrical splitting* and *Russian roulette* (also called geometrical importance sampling), and *weight roulette*. Scoring is carried out by G4MultiFunctionalDetector (see *G4MultiFunctionalDetector and G4VPrimitiveScorer* and *Concrete classes of G4VPrimitiveScorer*) using the standard GEANT4 scoring technique. Biasing specific scorers have been implemented and are described within G4MultiFunctionalDetector documentation. In this chapter, it is assumed that the reader is familiar with both the usage of GEANT4 and the concepts of importance sampling. More detailed documentation may be found in the documents 'Scoring, geometrical importance sampling and weight roulette'.

A detailed description of different use-cases which employ the sampling and scoring techniques can be found in the document 'Use cases of importance sampling and scoring in Geant4'.

The purpose of importance sampling is to save computing time by sampling less often the particle histories entering "less important" geometry regions, and more often in more "important" regions. Given the same amount of computing time, an importance-sampled and an analogue-sampled simulation must show equal mean values, while the importance-sampled simulation will have a decreased variance.

The implementation of scoring is independent of the implementation of importance sampling. However both share common concepts. *Scoring and importance sampling apply to particle types chosen by the user*, which should be borne in mind when interpreting the output of any biased simulation.

Examples on how to use scoring and importance sampling may be found in examples/extended/biasing.

#### Geometries

The kind of scoring referred to in this note and the importance sampling apply to spatial cells provided by the user.

A **cell** is a physical volume (further specified by it's replica number, if the volume is a replica). Cells may be defined in two kinds of geometries:

- 1. mass geometry: the geometry setup of the experiment to be simulated. Physics processes apply to this geometry.
- 2. **parallel-geometry**: a geometry constructed to define the physical volumes according to which scoring and/or importance sampling is applied.

The user has the choice to score and/or sample by importance the particles of the chosen type, according to mass geometry or to parallel geometry. It is possible to utilize several parallel geometries in addition to the mass geometry. This provides the user with a lot of flexibility to define separate geometries for different particle types in order to apply scoring or/and importance sampling.

**Note:** Parallel geometries should be constructed using the implementation as described in *Parallel Geometries*. There are a few conditions for parallel geometries:

- The world volume for parallel and mass geometries must be identical copies.
- Scoring and importance cells must not share boundaries with the world volume.

### **Changing the Sampling**

Samplers are higher level tools which perform the necessary changes of the GEANT4 sampling in order to apply importance sampling and weight roulette.

Variance reduction (and scoring through the G4MultiFunctionalDetector) may be combined arbitrarily for chosen particle types and may be applied to the mass or to parallel geometries.

The G4GeometrySampler can be applied equally to mass or parallel geometries with an abstract interface supplied by G4VSampler. G4VSampler provides Prepare... methods and a Configure method:

```
class G4VSampler
  public:
  G4VSampler();
  virtual ~G4VSampler();
  virtual void PrepareImportanceSampling(G4VIStore *istore,
                                          const G4VImportanceAlgorithm
                                           *ialg = 0) = 0;
   virtual void PrepareWeightRoulett(G4double wsurvive = 0.5,
                                    G4double wlimit = 0.25,
                                     G4double isource = 1) = 0;
   virtual void PrepareWeightWindow(G4VWeightWindowStore *wwstore,
                                    G4VWeightWindowAlgorithm *wwAlg = 0,
                                    G4PlaceOfAction placeOfAction =
                                    onBoundary) = 0;
   virtual void Configure() = 0;
   virtual void ClearSampling() = 0;
   virtual G4bool IsConfigured() const = 0;
};
```

The methods for setting up the desired combination need specific information:

- Importance sampling: message PrepareImportanceSampling with a G4VIStore and optionally a G4VImportanceAlgorithm
- Weight window: message PrepareWeightWindow with the arguments:
  - \*wwstore: a G4VWeightWindowStore for retrieving the lower weight bounds for the energy-space cells
  - \*wwAlg: a G4VWeightWindowAlgorithm if a customized algorithm should be used
  - placeOfAction: a G4PlaceOfAction specifying where to perform the biasing
- Weight roulette: message PrepareWeightRoulett with the optional parameters:
  - wsurvive: survival weight
  - wlimit: minimal allowed value of weight \* source importance / cell importance
  - *isource*: importance of the source cell

Each object of a sampler class is responsible for one particle type. The particle type is given to the constructor of the sampler classes via the particle type name, e.g. "neutron". Depending on the specific purpose, the Configure () of a sampler will set up specialized processes (derived from G4VProcess) for transportation in the parallel geometry, importance sampling and weight roulette for the given particle type. When Configure () is invoked the sampler places the processes in the correct order independent of the order in which user invoked the Prepare... methods.

#### Note:

- The Prepare...() functions may each only be invoked once.
- To configure the sampling the function Configure () must be called *after* the G4RunManager has been initialized and the PhysicsList has been instantiated.

The interface and framework are demonstrated in the examples/extended/biasing directory, with the main changes being to the G4GeometrySampler class and the fact that in the parallel case the WorldVolume is a copy of the Mass World. The parallel geometry now has to inherit from G4VUserParallelWorld which also has the GetWorld() method in order to retrieve a copy of the mass geometry WorldVolume.

```
class B02ImportanceDetectorConstruction : public G4VUserParallelWorld
ghostWorld = GetWorld();
```

The constructor for G4GeometrySampler takes a pointer to the physical world volume and the particle type name (e.g. "neutron") as arguments. In a single mass geometry the sampler is created as follows:

```
G4GeometrySampler mgs(detector->GetWorldVolume(), "neutron");
mgs.SetParallel(false);
```

Whilst the following lines of code are required in order to set up the sampler for the parallel geometry case:

```
G4VPhysicalVolume* ghostWorld = pdet->GetWorldVolume();
G4GeometrySampler pgs(ghostWorld, "neutron");
pgs.SetParallel(true);
```

Also note that the preparation and configuration of the samplers has to be carried out *after* the instantiation of the UserPhysicsList. With the modular reference PhysicsList the following set-up is required (first is for biasing, the second for scoring):

```
physicsList->RegisterPhysics(new G4ImportanceBiasing(&pgs,parallelName));
physicsList->RegisterPhysics(new G4ParallelWorldPhysics(parallelName));
```

If the a UserPhysicsList is being implemented, then the following should be used to give the pointer to the GeometrySampler to the PhysicsList:

```
physlist->AddBiasing(&pgs,parallelName);
```

Then to instantiate the biasing physics process the following should be included in the UserPhysicsList and called from ConstructProcess():

(continues on next page)

(continued from previous page)

```
fGeomSampler->AddProcess();
#else
  G4cout << " Running in singlethreaded mode!!! " << G4endl;
#endif</pre>
```

```
pgs.PrepareImportanceSampling(G4IStore::GetInstance(pdet->GetName()), 0);
pgs.Configure();
```

Due to the fact that biasing is a process and has to be inserted after all the other processes have been created.

## Importance Sampling

Importance sampling acts on particles crossing boundaries between "importance cells". The action taken depends on the importance values assigned to the cells. In general a particle history is either split or Russian roulette is played if the importance increases or decreases, respectively. A weight assigned to the history is changed according to the action taken.

The tools provided for importance sampling require the user to have a good understanding of the physics in the problem. This is because the user has to decide which particle types require importance sampled, define the cells, and assign importance values to the cells. If this is not done properly the results cannot be expected to describe a real experiment.

The assignment of importance values to a cell is done using an importance store described below.

An "importance store" with the interface G4VIStore is used to store importance values related to cells. In order to do importance sampling the user has to create an object (e.g. of class G4IStore) of type G4VIStore. The samplers may be given a G4VIStore. The user fills the store with cells and their importance values. The store is now a singleton class so should be created using a GetInstance method:

```
G4IStore *aIstore = G4IStore::GetInstance();
```

Or if a parallel world is used:

```
G4IStore *aIstore = G4IStore::GetInstance(pdet->GetName());
```

An importance store has to be constructed with a reference to the world volume of the geometry used for importance sampling. This may be the world volume of the mass or of a parallel geometry. Importance stores derive from the interface G4VIStore:

```
class G4VIStore
{
  public:
    G4VIStore();
    virtual ~G4VIStore();
    virtual G4double GetImportance(const G4GeometryCell &gCell) const = 0;
    virtual G4bool IsKnown(const G4GeometryCell &gCell) const = 0;
    virtual const G4VPhysicalVolume &GetWorldVolume() const = 0;
};
```

A concrete implementation of an importance store is provided by the class G4VStore. The *public* part of the class is:

```
class G4IStore : public G4VIStore
{
  public:
    explicit G4IStore(const G4VPhysicalVolume &worldvolume);
    virtual ~G4IStore();
    virtual G4double GetImportance(const G4GeometryCell &gCell) const;
    virtual G4bool IsKnown(const G4GeometryCell &gCell) const;
```

(continues on next page)

(continued from previous page)

The member function AddImportanceGeometryCell() enters a cell and an importance value into the importance store. The importance values may be returned either according to a physical volume and a replica number or according to a G4GeometryCell. The user must be aware of the interpretation of assigning importance values to a cell. If scoring is also implemented then this is attached to logical volumes, in which case the physical volume and replica number method should be used for assigning importance values. See examples/extended/biasing B01 and B02 for examples of this.

**Note:** An importance value must be assigned to every cell.

The different cases:

- · Cell is not in store
  - Not filling a certain cell in the store will cause an exception.
- *Importance value = zero* 
  - Tracks of the chosen particle type will be killed.
- importance values > 0
  - Normal allowed values
- Importance value smaller zero
  - Not allowed!

## The Importance Sampling Algorithm

Importance sampling supports using a customized importance sampling algorithm. To this end, the sampler interface *Changing the Sampling* may be given a pointer to the interface G4VImportanceAlgorithm:

The method Calculate () takes the arguments:

- ipre, ipost: importance of the previous cell and the importance of the current cell, respectively.
- *init\_w*: the particle's weight

It returns the struct:

```
class G4Nsplit_Weight
{
  public:
    G4int fN;
    G4double fW;
};
```

- fN: the calculated number of particles to exit the importance sampling
- fW: the weight of the particles

The user may have a customized algorithm used by providing a class inheriting from G4VImportanceAlgorithm.

If no customized algorithm is given to the sampler the default importance sampling algorithm is used. This algorithm is implemented in G4ImportanceAlgorithm.

#### The Weight Window Technique

The weight window technique is a weight-based alternative to importance sampling:

- applies splitting and Russian roulette depending on space (cells) and energy
- user defines weight windows in contrast to defining importance values as in importance sampling

In contrast to importance sampling this technique is not weight blind. Instead the technique is applied according to the particle weight with respect to the current energy-space cell.

Therefore the technique is convenient to apply in combination with other variance reduction techniques such as cross-section biasing and implicit capture.

A weight window may be specified for every cell and for several energy regions: space-energy cell.




Fig. 3.2: Weight window concept

#### Weight window concept

The user specifies a *lower weight bound W\_L* for every space-energy cell.

• The upper weight bound W\_U and the survival weight W\_S are calculated as:

```
W_U = C_U W_L and W_S = C_S W_L.
```

- The user specifies C\_S and C\_U once for the whole problem.
- The user may give different sets of energy bounds for every cell or one set for all geometrical cells
- Special case: if C\_S = C\_U = 1 for all energies then weight window is equivalent to importance sampling
- The user can choose to apply the technique: at boundaries, on collisions or on boundaries and collisions

The energy-space cells are realized by G4GeometryCell as in importance sampling. The cells are stored in a weight window store defined by G4VWeightWindowStore:

A concrete implementation is provided:

```
class G4WeightWindowStore: public G4VWeightWindowStore {
public:
  explicit G4WeightWindowStore(const G4VPhysicalVolume &worldvolume);
  virtual ~G4WeightWindowStore();
  virtual G4double GetLowerWeitgh(const G4GeometryCell &gCell,
                                   G4double partEnergy) const;
   virtual G4bool IsKnown(const G4GeometryCell &gCell) const;
  virtual const G4VPhysicalVolume &GetWorldVolume() const;
  void AddLowerWeights (const G4GeometryCell &gCell,
                       const std::vector<G4double> &lowerWeights);
   void AddUpperEboundLowerWeightPairs(const G4GeometryCell &qCell,
                                       const G4UpperEnergyToLowerWeightMap&
                                       enWeMap);
   void SetGeneralUpperEnergyBounds(const
      std::set<G4double, std::less<G4double> > & enBounds);
private::
};
```

The user may choose equal energy bounds for all cells. In this case a set of upper energy bounds must be given to the store using the method SetGeneralUpperEnergyBounds. If a general set of energy bounds have been set AddLowerWeights can be used to add the cells.

Alternatively, the user may chose different energy regions for different cells. In this case the user must provide a mapping of upper energy bounds to lower weight bounds for every cell using the method AddUpperEboundLowerWeightPairs.

Weight window algorithms implementing the interface class G4VWeightWindowAlgorithm can be used to define a customized algorithm:

A concrete implementation is provided and used as a default:

The constructor takes three parameters which are used to: calculate the upper weight bound (upperLimitFaktor), calculate the survival weight (survivalFaktor), and introduce a maximal number (maxNumberOfSplits) of copies to be created in one go.

In addition, the inverse of the maxNumberOfSplits is used to specify the minimum survival probability in case of Russian roulette.

#### The Weight Roulette Technique

Weight roulette (also called weight cutoff) is usually applied if importance sampling and implicit capture are used together. Implicit capture is not described here but it is useful to note that this procedure reduces a particle weight in every collision instead of killing the particle with some probability.

Together with importance sampling the weight of a particle may become so low that it does not change any result significantly. Hence tracking a very low weight particle is a waste of computing time. Weight roulette is applied in order to solve this problem.

#### The weight roulette concept

Weight roulette takes into account the importance "Ic" of the current cell and the importance "Is" of the cell in which the source is located, by using the ratio "R=Is/Ic".

Weight roulette uses a relative minimal weight limit and a relative survival weight. When a particle falls below the weight limit Russian roulette is applied. If the particle survives, tracking will be continued and the particle weight will be set to the survival weight.

The weight roulette uses the following parameters with their default values:

- wsurvival: 0.5 wlimit: 0.25
- isource: 1

The following algorithm is applied:

If a particle weight "w" is lower than R\*wlimit:

- the weight of the particle will be changed to "ws = wsurvival\*R"
- the probability for the particle to survive is "p = w/ws"

# 3.7.2 Physics Based Biasing

GEANT4 supports physics based biasing through a number of general use, built in biasing techniques. A utility class, G4WrapperProcess, is also available to support user defined biasing.

#### **Built in Biasing Options**

### **Primary Particle Biasing**

Primary particle biasing can be used to increase the number of primary particles generated in a particular phase space region of interest. The weight of the primary particle is modified as appropriate. A general implementation is provided through the G4GeneralParticleSource class. It is possible to bias position, angular and energy distributions.

G4GeneralParticleSource is a concrete implementation of G4VPrimaryGenerator. To use, instantiate G4GeneralParticleSource in the G4VUserPrimaryGeneratorAction class, as demonstrated below.

```
MyPrimaryGeneratorAction::MyPrimaryGeneratorAction() {
    generator = new G4GeneralParticleSource;
}

void
MyPrimaryGeneratorAction::GeneratePrimaries(G4Event*anEvent) {
    generator->GeneratePrimaryVertex(anEvent);
}
```

The biasing can be configured through interactive commands, as described in *General Particle Source*. Examples are also distributed with the GEANT4 distribution in **examples/extended/eventgenerator/exgps**.

#### **Hadronic Leading Particle Biasing**

One hadronic leading particle biasing technique is implemented in the G4HadLeadBias utility. This method keeps only the most important part of the event, as well as representative tracks of each given particle type. So the track with the highest energy as well as one of each of Baryon, pi0, mesons and leptons. As usual, appropriate weights are assigned to the particles. Setting the **SwitchLeadBiasOn** environmental variable will activate this utility.

#### **Hadronic Cross Section Biasing**

Cross section biasing artificially enhances/reduces the cross section of a process. This may be useful for studying thin layer interactions or thick layer shielding. The built in hadronic cross section biasing applies to photon inelastic, electron nuclear and positron nuclear processes.

The biasing is controlled through the **BiasCrossSectionByFactor** method in G4HadronicProcess, as demonstrated below.

```
void MyPhysicsList::ConstructProcess()
{
    ...
    G4ElectroNuclearReaction * theElectroReaction =
        new G4ElectroNuclearReaction;

G4ElectronNuclearProcess theElectronNuclearProcess;
    theElectronNuclearProcess.RegisterMe(theElectroReaction);
    theElectronNuclearProcess.BiasCrossSectionByFactor(100);

pManager->AddDiscreteProcess(&theElectronNuclearProcess);
```

(continues on next page)

(continued from previous page)

```
...
```

# **Radioactive Decay Biasing**

The G4RadioactiveDecay (GRDM) class simulates the decay of radioactive nuclei and implements the following biasing options:

- Increase the sampling rate of radionuclides within observation times through a user defined probability distribution function
- Nuclear splitting, where the parent nuclide is split into a user defined number of nuclides
- Branching ratio biasing where branching ratios are sampled with equal probability

G4RadioactiveDecay is a process which must be registered with a process manager, as demonstrated below.

```
void MyPhysicsList::ConstructProcess()
{
    ...
    G4RadioactiveDecay* theRadioactiveDecay =
        new G4RadioactiveDecay();

G4ProcessManager* pmanager = ...
    pmanager ->AddProcess(theRadioactiveDecay);
    ...
}
```

Biasing can be controlled either in compiled code or through interactive commands. Radioactive decay biasing examples are also distributed with the GEANT4 distribution in **examples/extended/radioactivedecay/exrdm**.

To select biasing as part of the process registration, use

```
theRadioactiveDecay->SetAnalogueMonteCarlo(false);
```

or the equivalent macro command:

```
/grdm/analogeMC [true|false]
```

In both cases, true specifies that the unbiased (analogue) simulation will be done, and false selects biasing.

#### **Limited Radionuclides**

Radioactive decay may be restricted to only specific nuclides, in order (for example) to avoid tracking extremely long-lived daughters in decay chains which are not of experimental interest. To limit the range of nuclides decayed as part of the process registration (above), use

```
G4NucleusLimits limits(aMin, aMax, zMin, zMax);
theRadioactiveDecay->SetNucleusLimits(limits);
```

or via the macro command

```
/grdm/nucleusLimits [aMin] [aMax] [zMin] [zMax]
```

#### **Geometric Biasing**

Radioactive decays may be generated throughout the user's detector model, in one or more specified volumes, or nowhere. The detector geometry must be defined before applying these geometric biases.

Volumes may be selected or deselected programmatically using

or with the equivalent macro commands

```
/grdm/allVolumes
/grdm/noVolumes
/grdm/selectVolume [logicalVolume]
/grdm/deselectVolume [logicalVolume]
```

In macro commands, the volumes are specified by name, and found by searching the G4LogicalVolumeStore.

## **Decay Time Biasing**

The decay time function (normally an exponential in the natural lifetime) of the primary particle may be replaced with a *time profile* F(t), as discussed in Section 40.6 of the *Physics Reference Manual*. The profile function is represented as a two-column ASCII text file with up to 100 time points (first column) with fractions (second column).

```
theRadioactiveDecay->SetSourceTimeProfile(fileName);
theRadioactiveDecay->SetDecayBias(fileName);

/grdm/sourceTimeProfile [fileName]
```

## **Branching Fraction Biasing**

/grdm/decayBiasProfile [fileName]

Radionuclides with rare decay channels may be biased by forcing all channels to be selected uniformly (BRBias = *true* below), rather than according to their natural branching fractions (*false*).

```
theRadioactiveDecay->SetBRBias(true);
/grdm/BRbias [true|false]
```

## **Nuclear Splitting**

The statistical efficiency of generated events may be increased by generating multiple "copies" of nuclei in an event, each of which is decayed independently, with an assigned weight of 1/Nsplit. Scoring the results of tracking the decay daughters, using their corresponding weights, can improve the statistical reach of a simulation while preserving the shape of the resulting distributions.

```
theRadioactiveDecay->SetSplitNuclei(Nsplit);
```

```
/grdm/splitNucleus [Nsplit]
```

#### **G4WrapperProcess**

G4WrapperProcess can be used to implement user defined event biasing. G4WrapperProcess, which is a process itself, wraps an existing process. By default, all function calls are forwarded to the wrapped process. It is a non-invasive way to modify the behaviour of an existing process.

To use this utility, first create a derived class inheriting from G4WrapperProcess. Override the methods whose behaviour you would like to modify, for example, PostStepDoIt, and register the derived class in place of the process to be wrapped. Finally, register the wrapped process with G4WrapperProcess. The code snippets below demonstrate its use.

# 3.7.3 Adjoint/Reverse Monte Carlo

Another powerful biasing technique available in GEANT4 is the Reverse Monte Carlo (RMC) method, also known as the Adjoint Monte Carlo method. In this method particles are generated on the external boundary of the sensitive part of the geometry and then are tracked backward in the geometry till they reach the external source surface, or exceed an energy threshold. By this way the computing time is focused only on particle tracks that are contributing to the tallies. The RMC method is much rapid than the Forward MC method when the sensitive part of the geometry is small compared to the rest of the geometry and to the external source, that has to be extensive and not beam like. At the moment the RMC method is implemented in GEANT4 only for some electromagnetic processes (see *Reverse processes*). An example illustrating the use of the Reverse MC method in GEANT4 is distributed within the GEANT4 toolkit in **examples/extended/biasing/ReverseMC01**.

#### Treatment of the Reverse MC method in GEANT4

Different G4Adjoint classes have been implemented into the GEANT4 toolkit in order to run an adjoint/reverse simulation in a GEANT4 application. This implementation is illustrated in Fig. 3.3. An adjoint run is divided in a series of alternative adjoint and forward tracking of adjoint and normal particles. One GEANT4 event treats one of this tracking phase.




Fig. 3.3: Schematic view of an adjoint/reverse simulation in GEANT4.

#### Adjoint tracking phase

Adjoint particles (adjoint\_e-, adjoint\_gamma,...) are generated one by one on the so called adjoint source with random position, energy (1/E distribution) and direction. The adjoint source is the external surface of a user defined volume or of a user defined sphere. The adjoint source should contain one or several sensitive volumes and should be small compared to the entire geometry. The user can set the minimum and maximum energy of the adjoint source. After its generation the adjoint primary particle is tracked backward in the geometry till a user defined external surface (spherical or boundary of a volume) or is killed before if it reaches a user defined upper energy limit that represents the maximum energy of the external source. During the reverse tracking, reverse processes take place where the adjoint particle being tracked can be either scattered or transformed in another type of adjoint particle. During the reverse tracking the G4AdjointSimulationManager replaces the user defined primary, run, stepping, ... actions, by its own actions. A reverse tracking phase corresponds to one GEANT4 event.

## Forward tracking phase

When an adjoint particle reaches the external surface its weight, type, position, and direction are registered and a normal primary particle, with a type equivalent to the last generated primary adjoint, is generated with the same energy, position but opposite direction and is tracked in the forward direction in the sensitive region as in a forward MC simulation. During this forward tracking phase the event, stacking, stepping, tracking actions defined by the user for his forward simulation are used. By this clear separation between adjoint and forward tracking phases, the code of the user developed for a forward simulation should be only slightly modified to adapt it for an adjoint simulation (see *How to update a G4 application to use the reverse Monte Carlo mode*). Indeed the computation of the signals is done by the same actions or classes that the one used in the forward simulation mode. A forward tracking phase corresponds to one G4 event.

#### **Reverse processes**

During the reverse tracking, reverse processes act on the adjoint particles. The reverse processes that are at the moment available in GEANT4 are the:

- Reverse discrete ionization for e-, proton and ions
- · Continuous gain of energy by ionization and bremsstrahlung for e- and by ionization for protons and ions
- Reverse discrete e- bremsstrahlung
- Reverse photo-electric effect
- · Reverse Compton scattering
- Approximated multiple scattering (see comment in *Reverse multiple scattering*)

It is important to note that the electromagnetic reverse processes are cut dependent as their equivalent forward processes. The implementation of the reverse processes is based on the forward processes implemented in the G4 standard electromagnetic package.

### Nb of adjoint particle types and nb of G4 events of an adjoint simulation

The list of type of adjoint and forward particles that are generated on the adjoint source and considered in the simulation is a function of the adjoint processes declared in the physics list. For example if only the e- and gamma electromagnetic processes are considered, only adjoint e- and adjoint gamma will be considered as primaries. In this case an adjoint event will be divided in four G4 event consisting in the reverse tracking of an adjoint e-, the forward tracking of its equivalent forward e-, the reverse tracking of an adjoint gamma, and the forward tracking of its equivalent forward gamma. In this case a run of 100 adjoint events will consist into 400 GEANT4 events. If the proton ionization is also considered adjoint and forward protons are also generated as primaries and 600 GEANT4 events are processed for 100 adjoint events.

## How to update a G4 application to use the reverse Monte Carlo mode

Some modifications are needed to an existing GEANT4 application in order to adapt it for the use of the reverse simulation mode (see also the G4 example examples/extended/biasing/ReverseMC01). It consists into the:

- Creation of the adjoint simulation manager in the main code
- Optional declaration of user actions that will be used during the adjoint tracking phase
- Use of a special physics lists that combine the adjoint and forward processes
- Modification of the user analysis part of the code

#### Creation of G4AdjointSimManager in the main

The class G4AdjointSimManager represents the manager of an adjoint simulation. This static class should be created somewhere in the main code. The way to do that is illustrated below

```
int main(int argc,char** argv) {
    ...
    G4AdjointSimManager* theAdjointSimManager = G4AdjointSimManager::GetInstance();
    ...
}
```

By doing this the G4 application can be run in the reverse MC mode as well as in the forward MC mode. It is important to note that G4AdjointSimManager is not a new G4RunManager and that the creation of G4RunManager in the main and the declaration of the geometry, physics list, and user actions to G4RunManager is still needed. The definition of the adjoint and external sources and the start of an adjoint simulation can be controlled by G4UI commands in the directory /adjoint.

#### Optional declaration of adjoint user actions

During an adjoint simulation the user stepping, tracking, stacking and event actions declared to G4RunManager are used only during the G4 events dedicated to the forward tracking of normal particles in the sensitive region, while during the events where adjoint particles are tracked backward the following happen concerning these actions:

• The user stepping action is replaced by G4AdjointSteppingAction that is responsible to stop an adjoint track when it reaches the external source, exceed the maximum energy of the external source, or cross the adjoint source surface. If needed the user can declare its own stepping action that will be called by G4AdjointSteppingAction after the check of stopping track conditions. This stepping action can be different that the stepping action used for the forward simulation. It is declared to G4AdjointSimManager by the following lines of code:

```
G4AdjointSimManager* theAdjointSimManager = G4AdjointSimManager::GetInstance(); theAdjointSimManager->SetAdjointSteppingAction(aUserDefinedSteppingAction);
```

• No stacking, tracking and event actions are considered by default. If needed the user can declare to G4AdjointSimManager stacking, tracking and event actions that will be used only during the adjoint tracking phase. The following lines of code show how to declare these adjoint actions to G4AdjointSimManager:

```
G4AdjointSimManager* theAdjointSimManager = G4AdjointSimManager::GetInstance(); theAdjointSimManager->SetAdjointEventAction(aUserDefinedEventAction); theAdjointSimManager->SetAdjointStackingAction(aUserDefinedStackingAction); theAdjointSimManager->SetAdjointTrackingAction(aUserDefinedTrackingAction);
```

By default no user run action is considered in an adjoint simulation but if needed such action can be declared to G4AdjointSimManager as such:

```
G4AdjointSimManager* theAdjointSimManager = G4AdjointSimManager::GetInstance(); theAdjointSimManager->SetAdjointRunAction(aUserDefinedRunAction);
```

## Physics list for reverse and forward electromagnetic processes

To run an adjoint simulation a specific physics list should be used where existing G4 adjoint electromagnetic processes and their forward equivalent have to be declared. An example of such physics list is provided by the class G4AdjointPhysicsLits in the G4 example **extended/biasing/ReverseMC01**.

## Modification in the analysis part of the code

The user code should be modified to normalize the signals computed during the forward tracking phase to the weight of the last adjoint particle that reaches the external surface. This weight represents the statistical weight that the last full adjoint tracks (from the adjoint source to the external source) would have in a forward simulation. If multiplied by a signal and registered in function of energy and/or direction the simulation results will give an answer matrix of this signal. To normalize it to a given spectrum it has to be furthermore multiplied by a directional differential flux corresponding to this spectrum The weight, direction, position, kinetic energy and type of the last adjoint particle that reaches the external source, and that would represents the primary of a forward simulation, can be gotten from G4AdjointSimManager by using for example the following line of codes

```
G4AdjointSimManager* theAdjointSimManager = G4AdjointSimManager::GetInstance();
G4String particle_name = theAdjointSimManager->GetFwdParticleNameAtEndOfLastAdjointTrack();
G4int PDGEncoding= theAdjointSimManager->GetFwdParticlePDGEncodingAtEndOfLastAdjointTrack();
G4double weight = theAdjointSimManager->GetWeightAtEndOfLastAdjointTrack();
G4double Ekin = theAdjointSimManager->GetEkinAtEndOfLastAdjointTrack();
G4double Ekin_per_nuc=theAdjointSimManager->GetEkinNucAtEndOfLastAdjointTrack();
// for ions
G4ThreeVector dir = theAdjointSimManager->GetDirectionAtEndOfLastAdjointTrack();
G4ThreeVector pos = theAdjointSimManager->GetPositionAtEndOfLastAdjointTrack();
```

In order to have a code working for both forward and adjoint simulation mode, the extra code needed in user actions or analysis manager for the adjoint simulation mode can be separated to the code needed only for the normal forward simulation by using the following public method of G4AdjointSimManager:

```
G4bool GetAdjointSimMode();
```

that returns true if an adjoint simulation is running and false if not.

The following code example shows how to normalize a detector signal and compute an answer matrix in the case of an adjoint simulation.

Listing 3.5: Normalization in the case of an adjoint simulation. The detector signal S computed during the forward tracking phase is normalized to a primary source of e- with a differential directional flux given by the function F. An answer matrix of the signal is also computed.

```
G4double S = ...; // signal in the sensitive volume computed during a forward tracking phase
//Normalization of the signal for an adjoint simulation
G4AdjointSimManager* theAdjSimManager = G4AdjointSimManager::GetInstance();
if (theAdjSimManager->GetAdjointSimMode()) {
 G4double normalized_S=0.; //normalized to a given e- primary spectrum
 G4double S_for_answer_matrix=0.; //for e- answer matrix
 if (theAdjSimManager->GetFwdParticleNameAtEndOfLastAdjointTrack() == "e-") {
   G4double ekin_prim = theAdjSimManager->GetEkinAtEndOfLastAdjointTrack();
   G4ThreeVector dir_prim = theAdjointSimManager->GetDirectionAtEndOfLastAdjointTrack();
   G4double weight_prim = theAdjSimManager->GetWeightAtEndOfLastAdjointTrack();
   S_for_answer_matrix = S*weight_prim;
   normalized_S = S_for_answer_matrix*F(ekin_prim,dir);
    // F(ekin_prim, dir_prim) gives the differential directional flux of primary e-
  //follows the code where normalized_S and S_for_answer_matrix are registered or whatever
//analysis/normalization code for forward simulation
else {
}
```

#### Control of an adjoint simulation

The G4UI commands in the directory /adjoint. allow the user to:

- Define the adjoint source where adjoint primaries are generated
- Define the external source till which adjoint particles are tracked
- · Start an adjoint simulation

#### Known issues in the Reverse MC mode

#### Occasional wrong high weight in the adjoint simulation

In rare cases an adjoint track may get a wrong high weight when reaching the external source. While this happens not often it may corrupt the simulation results significantly. This happens in some tracks where both reverse photo-electric and bremsstrahlung processes take place at low energy. We still need some investigations to remove this problem at the level of physical adjoint/reverse processes. However this problem can be solved at the level of event actions or analysis in the user code by adding a test on the normalized signal during an adjoint simulation. An example of such test has been implemented in the GEANT4 example **extended/biasing/ReverseMC01**. In this implementation an event is rejected when the relative error of the computed normalized energy deposited increases during one event by more than 50% while the computed precision is already below 10%.

#### Reverse bremsstrahlung

A difference between the differential cross sections used in the adjoint and forward bremsstrahlung models is the source of a higher flux of >100 keV gamma in the reverse simulation compared to the forward simulation mode. In principle the adjoint processes/models should make use of the direct differential cross section to sample the adjoint secondaries and compute the adjoint cross section. However due to the way the effective differential cross section is considered in the forward model G4eBremsstrahlungModel this was not possible to achieve for the reverse bremsstrahlung. Indeed the differential cross section used in G4AdjointeBremstrahlungModel is obtained by the numerical derivation over the cut energy of the direct cross section provided by G4eBremsstrahlungModel. This would be a correct procedure if the distribution of secondary in G4eBremsstrahlungModel would match this differential cross section. Unfortunately it is not the case as independent parameterization are used in G4eBremsstrahlungModel for both the cross sections and the sampling of secondaries. (It means that in the forward case if one would integrate the effective differential cross section considered in the simulation we would not find back the used cross section). In the future we plan to correct this problem by using an extra weight correction factor after the occurrence of a reverse bremsstrahlung. This weight factor should be the ratio between the differential CS used in the adjoint simulation and the one effectively used in the forward processes. As it is impossible to have a simple and direct access to the forward differential CS in G4eBremsstrahlungModel we are investigating the feasibility to use the differential CS considered in G4Penelope models.

#### Reverse multiple scattering

For the reverse multiple scattering the same model is used than in the forward case. This approximation makes that the discrepancy between the adjoint and forward simulation cases can get to a level of  $\sim 10$ -15% relative differences in the test cases that we have considered. In the future we plan to improve the adjoint multiple scattering models by forcing the computation of multiple scattering effect at the end of an adjoint step.

## 3.7.4 Generic Biasing

The generic biasing scheme provides facilities for:

- physics-based biasing, to alter the behavior of existing physics processes:
  - biasing of physics process interaction occurrence,
  - biasing of physics process final state production;
- non-physics-based biasing, to introduce or remove particles in the simulation but without affecting the existing physics processes, with techniques like, but not limited to
  - splitting,
  - Russian roulette (killing).

Decisions on what techniques to apply are taken on a step by step and intra-step basis, hence providing a lot of flexibility.

The scheme has been introduced in 10.0, with new features and some non-backward compatible changes introduced in 10.1 and 10.2; these are documented in *Changes from 10.0 to 10.1* and *Changes from 10.1 to 10.2*. Parallel geometry capability has been introduced in 10.3.

#### Overview

The generic biasing scheme relies on two abstract classes, that are meant to model the biasing problems. You have to inherit from them to create your own concrete classes, or use some of the concrete instances provided (see *Existing biasing operations, operator and interaction laws*), if they respond to your case. A dedicated process provides the interface between these biasing classes and the tracking. In case of parallel geometry usage, an other process handles the navigation in these geometries.

The two abstract classes are:

- G4VBiasingOperation: which represents a simple, or "atomic" biasing operation, like changing a process interaction occurrence probability, or changing its final state production, or making a splitting operation, etc. For the occurrence biasing case, the biasing is handled with an other class, "G4VBiasingInteractionLaw", which holds the properties of the biased interaction law. An object of this class type must be provided by the occurrence biasing operation returned.
- G4VBiasingOperator: which purpose is to make decisions on the above biasing operations to be applied. It is attached to a G4LogicalVolume and is the pilot of the biasing in this volume. An operator may decide to delegate to other operators. An operator acts only in the G4LogicalVolume it is attached to. In volumes with no biasing operator attached, the usual tracking is applied.

The process acting as interface between the biasing classes and the tracking is:

- G4BiasingProcessInterface: it is a concrete G4VProcess implementation. It interrogates the current biasing operator, if any, for biasing operations to be applied. The G4BiasingProcessInterface can either:
  - hold a physics process that it wraps and controls: in this case it asks the operator for physics-based biasing operations (only) to be applied to the wrapped process,
  - not hold a physics process: in this case it asks the operator for non-physics-based biasing operations (only): splitting, killing, etc.
- The G4BiasingProcessInterface class provides many information that can be used by the biasing operator. Each G4BiasingProcessInterface provides its identity to the biasing operator it calls, so that the operator has this information but also information of the underneath wrapped physics process, if it is the case.
  - The G4BiasingProcessInterface can be asked for all other G4BiasingProcessInterface instances at play on the current track. In particular, this allows the operator to get all cross-sections at the current point (feature available since 10.1). The code is organized in such a way that these cross-sections are all available at the first call to the operator in the current step.
- To make G4BiasingProcessInterface instances wrapping physics processes, or to insert instances not holding a physics process, the physics list has to be modified -the generic biasing approach is hence invasive to the physics list. The way to configure your physics list and related helper tools are described below.

The process handling parallel geometries is:

- G4ParallelGeometriesLimiterProcess, it is a concrete G4VProcess implementation, which takes care of limiting the step on the boundaries of parallel geometries.
- A single instance of G4ParallelGeometriesLimiterProcess handles all parallel geometries to be considered for a particle type. It collects these geometries by means of myLimiterProcess->AddParallelWorld("myParallelGeometry") calls.

  Given such a process is attached to a particle type, parallel geometries are hence specified per particle type.

• Attaching an instance of this process to a given particle type, and specifying the parallel geometries to be considered is eased by the helper tools as explained below.

#### **Getting Started**

#### **Examples**

Seven "Generic Biasing (GB)" examples are proposed (they have been introduced in 10.0, 10.1, 10.3 and 10.6):

- examples/extended/biasing/GB01:
  - which shows how biasing of process cross-section can be done.
  - This example uses the physics-based biasing operation G4BOptnChangeCrossSection defined in geant4/source/processes/biasing/generic. This operation performs the actual process cross-section change. In the example a first G4VBiasingOperator, GB01BOptrChangeCrossSection, configures and selects this operation. This operator applies to only one particle type.
  - To allow several particle types to be biased, a second G4VBiasingOperator, GB01BOptrMultiParticleChangeCrossSection, is implemented, and which holds a GB01BOptrChangeCrossSection operator for each particle type to be biased. This second operator then delegates to the first one the handling of the biasing operations.
- examples/extended/biasing/GB02:
  - which shows how a "force collision" scheme very close to the MCNP one can be activated.
  - This second example has a quite similar approach than the GB01 one, with a G4VBiasingOperator, QGB02BOptrMultiParticleForceCollision, that holds as many operators than particle types to be biased, this operators being of G4BOptrForceCollision type.
  - This G4BOptrForceCollision operator is defined in source/processes/biasing/generic. It combines several biasing operations to build-up the needed logic (see *Setting up the application*). It can be in particular looked at to see how it collects and makes use of physics process cross-sections.
- examples/extended/biasing/GB03:
  - which implements a kind of importance geometry biasing, using the generic biasing classes.
  - The example uses a simple sampling calorimeter. On the boundary of the absorber parts, it does splitting (killing) if the track is moving forward (backward). As the splitting can be too strong in some cases, falling into an over-splitting situation, even with a splitting by a factor 2, a technique is introduced to alleviate the problem: a probability to apply the splitting (killing) is introduced, and with proper tuning of this probability, the over-splitting can be avoided.
- examples/extended/biasing/GB04:
  - which implements a bremsstrahlung splitting. Bremsstrahlung splitting exists in the EM package. In the present example, it is shown how to implement a similar technique, using the generic biasing classes.
  - A biasing operator, GB04BOptrBremSplitting, sends a final state biasing operation, GB04BOptnBremSplitting, for the bremsstrahlung process. Splitting factor, and options to control the biasing are available through command line.
- examples/extended/biasing/GB05:
  - which illustrates a technique that uses physics cross-sections to determine the splitting[killing] rate in a shielding problem, it is applied to neutrons. This technique is supposed to be an invention, to illustrate a technique combining physics-based information with splitting/killing.
  - In the classical treatment of the shielding problem, the shield is divided in slices at the boundaries of which particles are splitted[killed] if moving forward[backward]. In the present technique, we collect the cross-sections of "absorbing/destroying" processes: decay, capture, inelastic. We then use the generic biasing facilities to create an equivalent of a splitting process, that has a "cross-section" which is the sum of the previous ones. This process is competing with other processes, as a regular one. When this process wins the competition, it splits the track, with a splitting factor 2. This splitting is hence occurring at the same rate than the absorption, resulting in an expected maintained (unweighted) flux.

- GB05BOptrSplitAndKillByCrossSection and GB05BOptnSplitAndKillByCrossSection are respectively the biasing operator and operation. The operator collects the absorbing cross-sections at the beginning of the step, passes them to the operation, requests it to sample the distance to its next interaction, and returns this operation to the calling G4BiasingProcessInterface as the operation to be applied in the step.
- The operation interaction distance is then proposed by the calling G4BiasingProcessInterface and, if being the shortest of the interaction distances, the operation final state generation (the splitting) is applied by the process.
- examples/extended/biasing/GB06:
  - which demonstrates the use of parallel geometries in generic biasing, on a classical shield problem, using geometry-based importance biasing.
  - The mass geometry consists of a single block of concrete; it is overlayed by a parallel geometry defining the slices used for splitting/killing.
  - The navigation capability in the parallel geometry is activated in the main program, by means of the physics list constructor.
- examples/extended/biasing/GB07:
  - which demonstrates the use of the leading particle biasing technique in generic biasing.
  - The mass geometry consists of a block of concrete in which the biasing is applied. A thin volume then follows to score (simple printing) the particles leaving the block of concrete.

## Setting up the application

For making an existing G4VBiasingOperator used by your application, you have to do two things:

1. Attach the operator to the G4LogicalVolume where the biasing should take place: You have to make this attachment in your ConstructSDandField() method (to make your application both sequential and MT-compliant):

Listing 3.6: Attachment of a G4BiasingOperator to a G4LogicalVolume. We assume such a volume has been created with name "volumeWithBiasing", and we assume that a biasing operator class MyBiasingOperator has been created, inheriting from G4VBiasingOperator:

- 2. Setup the physics list you use to properly include the needed G4BiasingProcessInterface instances. You have several options for this.
  - The easiest way is if you use a pre-packaged physics list (e.g. FTFP\_BERT, QGSP...). As such a physics list is of G4VModularPhysicsList type, you can alter it with a G4VPhysicsConstructor. The constructor G4GenericBiasingPhysics is meant for this. It can be used, typically in your main program, as:

Listing 3.7: Use of the G4GenericBiasingPhysics physics constructor to setup a pre-packaged physics list (of G4VModularPhysicsList type). Here we assume the FTFP\_BERT physics list, and we assume that runManager is a pointer on a created G4RunManager or G4RMTunManager object.

```
// Instantiate the physics list:
FTFP_BERT* physicsList = new FTFP_BERT;
// Create the physics constructor for biasing:
G4GenericBiasingPhysics* biasingPhysics = new G4GenericBiasingPhysics();
// Tell what particle types have to be biased:
biasingPhysics->Bias("gamma");
biasingPhysics->Bias("neutron");
// Register the physics constructor to the physics list:
physicsList->RegisterPhysics(biasingPhysics);
// Set this physics list to the run manager:
runManager->SetUserInitialization(physicsList);
```

Doing so, all physics processes will be wrapped, and, for example, the gamma conversion process, "conv", will appear as "biasWrapper(conv)" when dumping the processes (/particle/process/dump). An additional "biasWrapper(0)" process, for non-physics-based biasing is also inserted.

Other methods to specifically chose some physics processes to be biased or to insert only G4BiasingProcessInterface instances for non-physics-based biasing also exist.

• The second way is useful if you write your own physics list, and if this one is not a modular physics list, but inherits directly from the lowest level abstract class G4VUserPhysicsList. In this case, the above solution with G4GenericBiasingPhysics does not apply. Instead you can use the G4BiasingHelper utility class (this one is indeed used by G4GenericBiasingPhysics).

Listing 3.8: Use of the G4BiasingHelper utility class to setup a physics list for biasing in case this physics list is not of G4VModularPhysicsList type but inherits directly from G4VUserPhysicsList.

```
// Get physics list helper:
G4PhysicsListHelper* ph = G4PhysicsListHelper::GetPhysicsListHelper();
...
// Assume "particle" is a pointer on a G4ParticleDefinition object
G4String particleName = particle->GetParticleName();
if (particleName == "gamma")
{
ph->RegisterProcess(new G4PhotoElectricEffect , particle);
ph->RegisterProcess(new G4ComptonScattering , particle);
ph->RegisterProcess(new G4GammaConversion , particle);
G4ProcessManager* pmanager = particle->GetProcessManager();
G4BiasingHelper::ActivatePhysicsBiasing(pmanager, "phot");
G4BiasingHelper::ActivatePhysicsBiasing(pmanager, "compt");
G4BiasingHelper::ActivatePhysicsBiasing(pmanager, "conv");
G4BiasingHelper::ActivateNonPhysicsBiasing(pmanager);
}
```

• A last way to setup the physics list is by direct insertion of the G4BiasingProcessInterface instances, but this requires solid expertise in physics list creation.

In case you also use parallel geometries, you have to make the generic biasing sensitive to these. Assuming you have created three parallel geometries with names "parallelWorld1", "parallelWorld2" and "parallelWorld3" that you want to be active for neutrons, the additional calls you have to make compared to example *EvtBias.GenericBiasing.Overview.UsePhysConstructor* above are simply:

Listing 3.9: Calls to activate parallel geometry navigation

```
// -- activate parallel geometries for neutrons:
biasingPhysics->AddParallelGeometry("neutron", "parallelWorld1");
biasingPhysics->AddParallelGeometry("neutron", "parallelWorld2");
biasingPhysics->AddParallelGeometry("neutron", "parallelWorld3");
```

It is also possible, even though less convenient, to use the G4BiasingHelper utility class making calls to the static method limiter = G4BiasingHelper::AddLimiterProcess(pmanager, "limiterProcessName") in addition to the ones of example <code>EvtBias.GenericBiasing.Overview.UseBiasingHelper</code> above. This call returns a pointer limiter on the constructed G4ParallelGeometriesLimiterProcess process, setting its name as "limiterProcessName", this pointer has then to be used to specify the parallel geometries to the process: limiter->AddParallelWorld("parallelWorld1")...

#### Existing biasing operations, operator and interaction laws

Below are the set of available concrete biasing operations, operators and interaction laws. These are defined in source/processes/biasing/generic. Please note that several examples (*Examples*) also implement dedicated operators and operations.

- Concrete implementation classes of G4VBiasingOperation:
  - G4BOptnCloning: a non-physics-based biasing operation that clones the current track. Each of the two copies is given freely a weight.
  - G4BOptnChangeCrossSection: a physics-based biasing operation to change one process crosssection
  - G4BOptnForceFreeFlight: a physics-based biasing operation to force a flight with no interaction through the current volume. This operation is better said a "silent flight": the flight is conducted under a zero weight, and the track weight is restored at the end of the free flight, taking into account the cumulative weight change for the non-interaction flight. This special feature is because this class in used in the MCNP-like force collision scheme G4BOptrForceCollision.
  - G4BOptnForceCommonTruncatedExp: a physics-based biasing operation to force a collision inside the current volume. It is "common" as several processes may be forced together, driving the related interaction law by the sum of these processes cross-section. The relative natural occurrence of processes is conserved. This operation makes use of a "truncated exponential" law, which is the exponential law limited to a segment [0,L], where L is the distance to exit the current volume.
  - G4BOptnLeadingParticle: a non-physics-based biasing operation that implements a Leading Particle Biasing scheme. The technique can be applied to hadronic, electromagnetic et decay processes. At each interaction point, are kept:
    - \* the leading particle (highest energy track),
    - \* one particle of each species (considering particles and anti-particles as of same species, and all particles with  $Z \ge 2$  as one species).

A Russian roulette is additionnally played on the surviving non-leading tracks. This is specially of interest for electromagnetic processes as these have low multiplicities, making unaffected the final state if applying the above algorithm. The default killing probability is 2/3, but can be changed by the void SetFurtherKillingProbability (G4double p) method.

- Concrete implementation class of G4VBiasingOperator:
  - G4BOptrForceCollision: a biasing operator that implements a force collision scheme quite close to the one provided by MCNP. It handles the scheme though the following sequence:
    - 1. The operator starts by using a G4BOptnCloning cloning operation, making a copy of the primary entering the volume. The primary is given a zero weight.
    - 2. The primary is then transported through to the volume, without interactions. This is done with the operator requesting forced free flight G4BOptnForceFreeFlight operations to all physics processes. The weight is zero to prevent the primary to contribute to scores. This flight purpose is to accumulate the probability to fly through the volume without interaction. When the primary reaches

the volume boundary, the first free flight operation restores the primary weight to its initial weight and all operations multiply this weight by their weight for non-interaction flight. The operator then abandons here the primary track, letting it back to normal tracking.

- 3. The copy of the primary track starts and the track is forced to interact in the volume, using the G4BOptnForceCommonTruncatedExp operation, itself using the total cross-section to compute the forced interaction law (exponential law limited to path length in the volume). One of the physics processes is randomly selected (on the basis of cross-section values) for the interaction.
- 4. Other processes are receiving a forced free flight operation, from the operator.
- 5. The copy of the primary is transported up to its interaction point. With these operations configured, the G4BiasingProcessInterface instances have all needed information to automatically compute the weight of the primary track and of its interaction products.

As this operation starts on the volume boundary, a single force interaction occurs: if the track survives the interaction (e.g Compton process), as it moved apart the boundary, the operator does not consider it further.

- G4VBiasingInteractionLaw classes. These classes describe the interaction law in term of a non-interaction probability over a segment of length l, and an "effective" cross-section for an interaction at distance l (see Physics Reference Manual, section generic biasing). An interaction law can also be sampled.
  - G4InteractionLawPhysical: the usual exponential law, driven by a cross-section constant over a step. The effective cross-section is the cross-section.
  - G4ILawForceFreeFlight: an "interaction" law for, precisely, a non-interacting track, with non-interaction probability always 1, and zero effective cross-section. It is a limit case of the modeling.
  - G4ILawTruncatedExp: an exponential interaction law limited to a segment [0,L]. The non-interaction probability and effective cross-section depend on l, the distance travelled, and become zero and infinite, respectively, at l=L.

## Changes from 10.0 to 10.1

The G4VBiasingOperation class has been evolved to simplify the interface. The changes regard physics-based biasing (occurrence biasing and final state biasing) and are:

- Suppression of the method virtual G4ForceCondition ProposeForceCondition(const G4ForceCondition wrappedProcessCondition)
  - The functionality has been kept, absorbing the ProposeForceCondition(...) method by the ProvideOccurenceBiasingInteractionLaw(...) one, which has now the signature:

```
virtual const G4VBiasingInteractionLaw*
ProvideOccurenceBiasingInteractionLaw ( const
G4BiasingProcessInterface* callingProcess, G4ForceCondition&
proposeForceCondition) = 0;
```

- The value of proposeForceCondition passed to the method is the G4ForceCondition value of the wrapped process, as this was the case with deprecated method ProposeForceCondition(...)
- Suppression of the virtual method "G4bool DenyProcessPostStepDoIt(const G4BiasingProcessInterface\* callingProcess, const G4Track\* track, const G4Step\* step, G4double& proposedTrackWeight)":
  - This method was used to prevent the wrapped process hold by callingProcess to have its PostStepDoIt(...) called, providing a weight for this non-call.
  - The method has been removed, but the functionality still exists, and has been merged and generalized with the change of the pure virtual ApplyFinalStateBiasing (...) described just after.
- Extra argument G4bool& forceBiasedFinalState added as last argument of virtual G4VParticleChange\* ApplyFinalStateBiasing(const G4BiasingProcessInterface\* callingProcess, const G4Track\* track, const G4Step\* step, G4bool& forceBiasedFinalState) = 0
  - This method is meant to return a final state interaction through the G4VParticleChange. The final state may be the analog wrapped process one, or a biased one, which comes with its weight correction

for biasing the final state. If an occurrence biasing is also at play in the same step, the weight correction for this biasing is applied to the final state before this one is returned to the stepping. This is the default behavior. This behavior can be controlled by forceBiasedFinalState:

- \* If forceBiasedFinalState is left false, the above default behavior is applied.
- \* If forceBiasedFinalState is set to true, the G4VParticleChange final state will be returned as is to the stepping, and that, regardless there is an occurrence at play. Hence, when setting forceBiasedFinalState to true, the biasing operation takes full responsibility for the total weight (occurrence + final state) calculation.
- Deletion of G4ILawCommonTruncatedExp, which could be eliminated after better implementation of G4BOptnForceCommonTruncatedExp operation.

#### Changes from 10.1 to 10.2

Changes in 10.2 derive from the introduction of the track feature G4VAuxiliaryTrackInformation. They regard essentially the force collision operator G4BOptrForceCollision and related features. These changes are transparent to the user if using G4BOptrForceCollision and following examples/extended/biasing/GB02. The information below are provided for developers of biasing classes.

The G4VAuxiliaryTrackInformation functionality allows to extend the G4Track attributes with an instance of a concrete class deriving from G4VAuxiliaryTrackInformation. Such an object is registered to the G4Track using an ID that has to be previously obtained from the G4PhysicsModelCatalog. The G4VBiasingOperator class defines two new virtual methods, Configure () and ConfigureForWorker (), to help with the creation of these ID's at the proper time (see G4BOptrForceCollision as an example).

Before 10.2, the G4BOptrForceCollision class was using state variables to make the bookkeeping of the tracks handled by the scheme. Now this bookkeeping is handled using a G4VAuxiliaryTrackInformation, G4BOptrForceCollisionTrackData.

To help with the bookkeeping, the base class G4VBiasingOperator was defining a set of methods (GetBirthOperation(..)), RememberSecondaries(..), ForgetTrack(..)), these have been removed in 10.2 and are easy to overpass with a dedicated G4VAuxiliaryTrackInformation.

**CHAPTER** 

**FOUR** 

## **DETECTOR DEFINITION AND RESPONSE**

# 4.1 Geometry

## 4.1.1 Introduction

The detector definition requires the representation of its geometrical elements, their materials and electronics properties, together with visualization attributes and user defined properties. The geometrical representation of detector elements focuses on the definition of solid models and their spatial position, as well as their logical relations to one another, such as in the case of containment.

GEANT4 uses the concept of "Logical Volume" to manage the representation of detector element properties. The concept of "Physical Volume" is used to manage the representation of the spatial positioning of detector elements and their logical relations. The concept of "Solid" is used to manage the representation of the detector element solid modeling. Volumes and solids must be dynamically allocated using 'new' in the user program; they must not be declared as local objects. Volumes and solids are automatically registered on creation to dedicated stores; these stores will delete all objects at the end of the job.

## 4.1.2 Solids

The GEANT4 geometry modeller implements Constructive Solid Geometry (CSG) representations for geometrical primitives. CSG representations are easy to use and normally give superior performance.

All solids must be allocated using 'new' in the user's program; they get registered to a G4SolidStore at construction, which will also take care to deallocate them at the end of the job, if not done already in the user's code.

All constructed solids can stream out their contents via appropriate methods and streaming operators.

For all solids it is possible to estimate the geometrical volume and the surface area by invoking the methods:

```
G4double GetCubicVolume()
G4double GetSurfaceArea()
```

which return an estimate of the solid volume and total area in internal units respectively. For elementary solids the functions compute the exact geometrical quantities, while for composite or complex solids an estimate is made using Monte Carlo techniques.

For all solids it is also possible to generate pseudo-random points lying on their surfaces, by invoking the method

```
G4ThreeVector GetPointOnSurface() const
```

which returns the generated point in local coordinates relative to the solid. To be noted that this function is not meant to provide a uniform distribution of points on the surfaces of the solids.

Since release 10.3, solids can be scaled in their dimensions along the Cartesian axes X, Y or Z, by providing a scale transformation associated to the original solid.


**Note:** GEANT4 does not impose any restriction on the name assigned to solids; names can be shared. It is however good practice to specify unique names for each constructed solid, to allow for easier retrivial from stores for post-processing use.

## Constructed Solid Geometry (CSG) Solids

CSG solids are defined directly as three-dimensional primitives. They are described by a minimal set of parameters necessary to define the shape and size of the solid. CSG solids are Boxes, Tubes and their sections, Cones and their sections, Spheres, Wedges, and Toruses.

#### Box:

To create a **box** one can use the constructor:



by giving the box a name and its half-lengths along the X, Y and Z axis:


This will create a box that extends from -pX to +pX in X, from -pY to +pY in Y, and from -pZ to +pZ in Z.

For example to create a box that is 2 by 6 by 10 centimeters in full length, and called BoxA one should use the following code:

```
G4Box* aBox = new G4Box("BoxA", 1.0*cm, 3.0*cm, 5.0*cm);
```

### **Cylindrical Section or Tube:**

Similarly to create a cylindrical section or tube, one would use the constructor:




giving its name pName and its parameters which are:

pRMin	Inner radius	pRMax	Outer radius
pDz	Half length in Z	pSPhi	Starting phi angle in radians
pDPhi	Angle of the segment in radians		

### **Cylindrical Cut Section or Cut Tube:**

A cut in Z can be applied to a cylindrical section to obtain a **cut tube**. The following constructor should be used:




giving its name pName and its parameters which are:

pRMin	Inner radius	pRMax	Outer radius
pDz	Half length in Z	pSPhi	Starting phi angle in radians
pDPhi	Angle of the segment in radians	pLowNorm	Outside Normal at -Z
pHighNorm	Outside Normal at +Z		

### **Cone or Conical section:**

Similarly to create a cone, or conical section, one would use the constructor




giving its name pName, and its parameters which are:

pRmin1	inside radius at -pDz	pRmax1	outside radius at -pDz
pRmin2	inside radius at +pDz	pRmax2	outside radius at +pDz
pDz	half length in Z	pSPhi	starting angle of the segment in radians
pDPhi	the angle of the segment in radians		

## Parallelepiped:

A parallelepiped is constructed using:




giving its name pName and its parameters which are:

dx, dy,	Half-length in x,y,z
dz	
alpha	Angle formed by the Y axis and by the plane joining the centre of the faces <i>parallel</i> to the Z-X plane
	at -dy and +dy
theta	Polar angle of the line joining the centres of the faces at -dz and +dz in Z
phi	Azimuthal angle of the line joining the centres of the faces at -dz and +dz in Z

## Trapezoid:

To construct a trapezoid use:




to obtain a solid with name pName and parameters

dx1	Half-length along X at the surface positioned at -dz
dx2	Half-length along X at the surface positioned at +dz
dy1	Half-length along Y at the surface positioned at -dz
dy2	Half-length along Y at the surface positioned at +dz
dz	Half-length along Z axis

## Generic Trapezoid:

To build a **generic trapezoid**, the G4Trap class is provided. G4Trap is a solid with six trapezoidal faces, it has two bases parallel to the XY-plane and four lateral faces. The bases are located at the same distance from the XY-plane, but on opposite sides from it. Each of the bases has two edges parallel the X-axis. Let's call the line joining middle point of these edges - *the centre line of the base*, and the middle point of this line - *the centre of the base*. An important property of G4Trap is that the line joining the centres of the bases goes through the origin of the local coordinate system.

G4Trap has three main constructors; for a Right Angular Wedge, for a general trapezoid and a constructor from eight points:



to obtain a Right Angular Wedge with name pName and parameters:

pΖ	Length along Z
рҮ	Length along Y
рХ	Length along X at the wider side
pLTX	Length along X at the narrower side ( $plTX \le pX$ )

The angle between the Y-axis and the centre lines of the bases in case of Right Angular Wedge is defined by the following expression:

$$tan(alpha) = 0.5 * (pLTX - pX) / pY$$

or, to obtain the general trapezoid:

pDz	Half Z length - distance from the origin to the bases
pTheta	Polar angle of the line joining the centres of the bases at -/+pDz
pPhi	Azimuthal angle of the line joining the centre of the base at -pDz to the centre of the base at +pDz
pDy1	Half Y length of the base at -pDz
pDy2	Half Y length of the base at +pDz
pDx1	Half X length at smaller Y of the base at -pDz
pDx2	Half X length at bigger Y of the base at -pDz
pDx3	Half X length at smaller Y of the base at +pDz
pDx4	Half X length at bigger y of the base at +pDz
pAlp1	Angle between the Y-axis and the centre line of the base at -pDz (lower endcap)
pAlp2	Angle between the Y-axis and the centre line of the base at +pDz (upper endcap)

**Note:** The angle pAlph1 and pAlph2 have to be the same due to the planarity condition.

or, to obtain from eight points with name pName:


pt   Coordinates of the vertices
pt[0], pt[1]   Edge with smaller Y of the base at -z
pt [2], pt [3]   Edge with bigger Y of the base at -z
pt[4], pt[5]   Edge with smaller Y of the base at +z
pt[6], pt[7]   Edge with bigger Y of the base at +z

Array of vertices is given as a sequence of four edges parallel to the X-axis, first two edges define the base at -z, next two edges define the base at +z. First point in edge should have smaller X.

**Note:** The following properties of G4Trap should be respected: (a) Lateral faces should be planar; (b) The line joining the centers of the bases should go through the origin

### **Sphere or Spherical Shell Section:**

To build a sphere, or a spherical shell section, use:




to obtain a solid with name pName and parameters:

pRmin	Inner radius
pRmax	Outer radius
pSPhi	Starting Phi angle of the segment in radians
pDPhi	Delta Phi angle of the segment in radians
pSTheta	Starting Theta angle of the segment in radians
pDTheta	Delta Theta angle of the segment in radians

### **Full Solid Sphere:**

To build a **full solid sphere** use:




The Orb can be obtained from a Sphere with: pRmin = 0, pSPhi = 0,  $pDPhi = 2 * \pi$ , pSTheta = 0,  $pDTheta = \pi$ 

pRmax	Outer radius
L	

## **Torus:**

To build a **torus** use:



to obtain a solid with name pName and parameters:


pRmin	Inside radius
pRmax	Outside radius
pRtor	Swept radius of torus
pSPhi	Starting Phi angle in radians (fSPhi+fDPhi<=2PI, fSPhi>-2PI)
pDPhi	Delta angle of the segment in radians

In addition, the GEANT4 Design Documentation shows in the Solids Class Diagram the complete list of CSG classes.

### **Specific CSG Solids**

## **Polycons:**

Polycons (PCON) are implemented in GEANT4 through the G4Polycone class:



where:

phiStart	Initial Phi starting angle
phiTotal	Total Phi angle
numZPlanes	Number of Z planes
numRZ	Number of corners in r,Z space
zPlane	Position of Z planes, with Z in increasing order
rInner	Tangent distance to inner surface
r0uter	Tangent distance to outer surface
r	r coordinate of corners
Z	Z coordinate of corners

A Polycone where Z planes position can also decrease is implemented through the G4GenericPolycone class:


```
G4GenericPolycone(const G4String& pName,
G4double phiStart,
G4double phiTotal,
G4int numRZ,
const G4double r[],
const G4double z[])
```

where:

phiStart	Initial Phi starting angle
phiTotal	Total Phi angle
numRZ	Number of corners in r,Z space
r	r coordinate of corners
Z	Z coordinate of corners

## Polyhedra (PGON):

Polyhedra (PGON) are implemented through G4Polyhedra:





where:

phiStart	Initial Phi starting angle
phiTotal	Total Phi angle
numSide	Number of sides
numZPlanes	Number of Z planes
numRZ	Number of corners in r,Z space
zPlane	Position of Z planes
rInner	Tangent distance to inner surface
rOuter	Tangent distance to outer surface
r	r coordinate of corners
Z	Z coordinate of corners

## Tube with an elliptical cross section:


A tube with an elliptical cross section (ELTU) can be defined as follows:





## General Ellipsoid:

The general **ellipsoid** with possible cut in  $\mathbb{Z}$  can be defined as follows:



A general (or triaxial) ellipsoid is a quadratic surface which is given in Cartesian coordinates by:


```
1.0 = (x/pxSemiAxis)**2 + (y/pySemiAxis)**2 + (z/pzSemiAxis)**2
```

where:

pxSemiAxis	Semiaxis in X
pySemiAxis	Semiaxis in Y
pzSemiAxis	Semiaxis in Z
pzBottomCut	lower cut plane level, Z
pzTopCut	upper cut plane level, Z

## **Cone with Elliptical Cross Section:**

A cone with an elliptical cross section can be defined as follows:



where:

xSemiAxis	A scalar value, it defines the scaling along X-axis	
ySemiAxis	A scalar value, it defines the scaling along Y-axis	
zHeight	Z-coordinate if the apex	
zTopCut	Upper cut plane level	

Value of zTopCut cannot exceed zHeight; the bases of an elliptical cone are located at -zTopCut and +zTopCut.

The lateral surface of an elliptical cone is described by the equation:


$$(x/xSemiAxis)**2 + (y/ySemiAxis)**2 = (zHeight - z)**2$$


Values of xSemiAxis and ySemiAxis can be figured out from the equations for the semimajor axes of the elliptical section at z=0:

dx = xSemiAxis \* zHeight dy = ySemiAxis \* zHeight

### Paraboloid, a solid with parabolic profile:


A solid with parabolic profile and possible cuts along the Z axis can be defined as follows:





## **Tube with Hyperbolic Profile:**

A **tube with a hyperbolic profile** (HYPE) can be defined as follows:



G4Hype is shaped with curved sides parallel to the Z-axis, has a specified half-length along the Z axis about which it is centred, and a given minimum and maximum radius.


A minimum radius of 0 defines a filled Hype (with hyperbolic inner surface), i.e. inner radius = 0 AND inner stereo angle = 0.

The inner and outer hyperbolic surfaces can have different stereo angles. A stereo angle of 0 gives a cylindrical surface:

innerRadius	Inner radius
outerRadius	Outer radius
innerStereo	Inner stereo angle in radians
outerStereo	Outer stereo angle in radians
halfLenZ	Half length in Z

## Tetrahedra:

A **tetrahedra** solid can be defined as follows:




The solid is defined by 4 points in space:

anchor	Anchor point
p2	Point 2
р3	Point 3
p4	Point 4
degeneracyFlag	Flag indicating degeneracy of points

## **Extruded Polygon:**

The extrusion of an arbitrary polygon (**extruded solid**) with fixed outline in the defined Z sections can be defined as follows (in a general way, or in a simplified construct with only two Z sections). G4ExtrudedSolid is constructed by moving a 2D polygonal contour along a 3D polyline. During movement the polygonal contour can be scaled.



The Z-sides of the solid are the scaled versions of the same polygon.


polygon 2D polygonal contour; the vertices of the outlined polygon defined in clock-	
zsections	3D polyline with scale factors; the Z-sections defined by Z position in increasing order
halfZ Half length in Z; distance from the origin to the sections	
off1, scale1	(X, Y) position of the polygon and scale factor at -halfZ
off2, scale2	(X, Y) position of the polygon and scale factor at +halfZ

Each node in the 3D polyline is defined as a ZSection object:

Very often an **extruded solid** is constructed by shifting a polygon in the perpendicular direction to its plane. In such case off1, off2 should be specified as G4TwoVector(0,0) and scale1, scale2 should be equal to 1.

## **Box Twisted:**

A **box twisted** along one axis can be defined as follows:




G4TwistedBox is a box twisted along the z-axis. The twist angle cannot be greater than 90 degrees:

twistedangle	Twist angle
pDx	Half x length
pDy	Half y length
pDz	Half z length

## **Trapezoid Twisted along One Axis:**

trapezoid twisted along one axis can be defined as follows:



The first constructor of G4TwistedTrap produces a regular trapezoid twisted along the Z-axis, where the caps of the trapezoid are of the same shape and size.


The second constructor produces a generic trapezoid with polar, azimuthal and tilt angles.

The twist angle cannot be greater than 90 degrees:

twistedangle	Twisted angle
pDx1	Half X length at y=-pDy
pDx2	Half X length at y=+pDy
pDy	Half Y length
pDz	Half Z length
pTheta	Polar angle of the line joining the centres of the faces at -/+pDz
pDy1	Half Y length at -pDz
pDx1	Half X length at -pDz, y=-pDy1
pDx2	Half X length at -pDz, y=+pDy1
pDy2	Half Y length at +pDz
pDx3	Half X length at +pDz, y=-pDy2
pDx4	Half X length at +pDz, y=+pDy2
pAlph	Angle with respect to the Y axis from the centre of the side

## Twisted Trapezoid with X and Y dimensions varying along Z:

A **twisted trapezoid** with the X and Y dimensions **varying along** Z can be defined as follows:




where:

pDx1	Half X length at the surface positioned at -dz
pDx2	Half X length at the surface positioned at +dz
pDy1	Half Y length at the surface positioned at -dz
pDy2	Half Y length at the surface positioned at +dz
pDz	Half Z length
twistedangle	Twisted angle

## Generic trapezoid with optionally collapsing vertices:


An **arbitrary trapezoid** with up to 8 vertices standing on two parallel planes perpendicular to the  $\mathbb Z$  axis can be defined as follows:

```
G4GenericTrap(const G4String& pName,
G4double pDz,
const std::vector<G4TwoVector>& vertices)
```




## *In the picture*:

pDz = 25vertices =  $\{-30, -30\}$ ,  $\{-30, 30\}$ ,  $\{30, 30\}$ ,  $\{30, -30\}$   $\{-5, -20\}$ ,  $\{-20, 20\}, \{20, 20\}, \{20, -20\}$ 



#### *In the picture:*

pDz = 25 vertices =  $\{-30, -30\}$ ,  $\{-30, 30\}$ ,  $\{30, 30\}$ ,  $\{30, -30\}$   $\{-20, -20\}$ ,  $\{-20, -20\}$ 20}, {20,20}, {20, 20}



#### *In the picture*:

 $pDz = 25 \text{ vertices} = \{-30, -30\}, \{-30, 30\}, \{30, 30\}, \{30, -30\}, \{0, 0\},$ 0), {0,0}

where:

pDz	Half Z length	
vertices	The $(X,Y)$ coordinates of vertices	

The order of specification of the coordinates for the vertices in G4GenericTrap is important. The first four points are the vertices sitting on the -hz plane; the last four points are the vertices sitting on the +hz plane.


The order of defining the vertices of the solid is the following:

```
point 0 is connected with points 1,3,4
point 1 is connected with points 0,2,5
point 2 is connected with points 1,3,6
point 3 is connected with points 0,2,7
point 4 is connected with points 0,5,7
point 5 is connected with points 1,4,6
point 6 is connected with points 2,5,7
point 7 is connected with points 3,4,6
```

Points can be identical in order to create shapes with less than 8 vertices; the only limitation is to have at least one triangle at +hz or -hz; the lateral surfaces are not necessarily planar. Not planar lateral surfaces are represented by a surface that linearly changes from the edge on -hz to the corresponding edge on +hz; it represents a *sweeping* surface with twist angle linearly dependent on Z, but it is not a real twisted surface mathematically described by equations as for the other *twisted* solids described in this chapter.

## **Tube Section Twisted along Its Axis:**

A tube section twisted along its axis can be defined as follows:



G4TwistedTubs is a sort of twisted cylinder which, placed along the Z-axis and divided into phi-segments is shaped like an hyperboloid, where each of its segmented pieces can be tilted with a stereo angle.

It can have inner and outer surfaces with the same stereo angle:

twistedangle	Twisted angle
endinnerrad	Inner radius at endcap
endouterrad	Outer radius at endcap
halfzlen	Half Z length
dphi	Phi angle of a segment

Additional constructors are provided, allowing the shape to be specified either as:

- the number of segments in phi and the total angle for all segments, or
- a combination of the above constructors providing instead the inner and outer radii at z=0 with different Z-lengths along negative and positive Z-axis.

### Solids made by Boolean operations

Simple solids can be combined using Boolean operations. For example, a cylinder and a half-sphere can be combined with the union Boolean operation.

Creating such a new Boolean solid, requires:

- · Two solids
- A Boolean operation: union, intersection or subtraction.
- Optionally a transformation for the second solid.

The solids used should be either CSG solids (for examples a box, a spherical shell, or a tube) or another Boolean solid: the product of a previous Boolean operation. An important purpose of Boolean solids is to allow the description of solids with peculiar shapes in a simple and intuitive way, still allowing an efficient geometrical navigation inside them.

**Note:** The constituent solids of a Boolean operation should possibly *avoid* be composed by sharing all or part of their surfaces. This precaution is necessary in order to avoid the generation of 'fake' surfaces due to precision loss, or errors in the final visualization of the Boolean shape. In particular, if any one of the *subtractor* surfaces is coincident with a surface of the *subtractee*, the result is undefined. Moreover, the final Boolean solid should represent a single 'closed' solid, i.e. a Boolean operation between two solids which are disjoint or far apart each other, is *not* a valid Boolean composition.

**Note:** The tracking cost for navigating in a Boolean solid is proportional to the number of constituent solids. So care must be taken to avoid extensive, unnecessary use of Boolean solids in performance-critical areas of a geometry description, where each solid is created from Boolean combinations of many other solids.

Examples of the creation of the simplest Boolean solids are given below:

where the union, intersection and subtraction of a box and cylinder are constructed.

The more useful case where one of the solids is displaced from the origin of coordinates also exists. In this case the second solid is positioned relative to the coordinate system (and thus relative to the first). This can be done in two ways:

- Either by giving a rotation matrix and translation vector that are used to transform the coordinate system of the second solid to the coordinate system of the first solid. This is called the *passive* method.
- Or by creating a transformation that moves the second solid from its desired position to its standard position, e.g., a box's standard position is with its centre at the origin and sides parallel to the three axes. This is called the *active* method.

In the first case, the translation is applied first to move the origin of coordinates. Then the rotation is used to rotate the coordinate system of the second solid to the coordinate system of the first.

```
G4RotationMatrix* yRot = new G4RotationMatrix; // Rotates X and Z axes only
yRot->rotateY(M_PI/4.*rad); // Rotates 45 degrees

G4ThreeVector zTrans(0, 0, 50);

G4UnionSolid* unionMoved =
    new G4UnionSolid("Box+CylinderMoved", box, cyl, yRot, zTrans);

//
// The new coordinate system of the cylinder is translated so that
// its centre is at +50 on the original Z axis, and it is rotated
// with its X axis halfway between the original X and Z axes.

// Now we build the same solid using the alternative method
//
G4RotationMatrix invRot = yRot->invert();
G4Transform3D transform(invRot, zTrans);
G4UnionSolid* unionMoved =
    new G4UnionSolid("Box+CylinderMoved", box, cyl, transform);
```

Note that the first constructor that takes a pointer to the rotation-matrix (G4RotationMatrix\*), does NOT copy it. Therefore once used a rotation-matrix to construct a Boolean solid, it must NOT be modified.

In contrast, with the alternative method shown, a G4Transform3D is provided to the constructor by value, and its transformation is stored by the Boolean solid. The user may modify the G4Transform3D and eventually use it again.

When positioning a volume associated to a Boolean solid, the relative center of coordinates considered for the positioning is the one related to the *first* of the two constituent solids.

### **Multi-Union Structures**

Since release 10.4, the possibility to define multi-union structures is part of the standard set of constructs in GEANT4. A G4MultiUnion structure allows for the description of a Boolean union of many displaced solids at once, therefore representing volumes with the same associated material. An example on how to define a simple MultiUnion structure is given here:

```
#include "G4MultiUnion.hh"
// Define two -G4Box- shapes
G4Box*box1 = new G4Box("Box1", 5.*mm, 5.*mm, 10.*mm);
G4Box*box2 = new G4Box("Box2", 5.*mm, 5.*mm, 10.*mm);
// Define displacements for the shapes
G4RotationMatrix rotm = G4RotationMatrix();
G4ThreeVector position1 = G4ThreeVector(0.,0.,1.);
G4ThreeVector position2 = G4ThreeVector(0.,0.,2.);
G4Transform3D tr1 = G4Transform3D(rotm, position1);
G4Transform3D tr2 = G4Transform3D(rotm,position2);
// Initialise a MultiUnion structure
G4MultiUnion* munion_solid = new G4MultiUnion("Boxes_Union");
// Add the shapes to the structure
munion solid->AddNode(*box1,tr1);
munion_solid->AddNode(*box2,tr2);
// Finally close the structure
munion_solid->Voxelize();
```

(continues on next page)

(continued from previous page)

Fast detection of intersections in tracking is assured by the adoption of a specialised optimisation applied to the 3D structure itself and generated at initialisation.

### **Tessellated Solids**

In GEANT4 it is also implemented a class G4TessellatedSolid which can be used to generate a generic solid defined by a number of facets (G4VFacet). Such constructs are especially important for conversion of complex geometrical shapes imported from CAD systems bounded with generic surfaces into an approximate description with facets of defined dimension (see Fig. 4.1).




Fig. 4.1: Example of geometries imported from CAD system and converted to tessellated solids.

They can also be used to generate a solid bounded with a generic surface made of planar facets. It is important that the supplied facets shall form a fully enclosed space to represent the solid, and that adjacent facets always share a complete edge (no vertex on one facet can lie between vertices on an adjacent facet).

Two types of facet can be used for the construction of a G4TessellatedSolid: a triangular facet (G4TriangularFacet) and a quadrangular facet (G4QuadrangularFacet).

An example on how to generate a simple tessellated shape is given below.

Listing 4.1: Example of geometries imported from CAD system and converted to tessellated solids.

```
// First declare a tessellated solid
//
G4TessellatedSolid solidTarget = new G4TessellatedSolid("Solid_name");

// Define the facets which form the solid
//
G4double targetSize = 10*cm;
```

(continues on next page)

(continued from previous page)

```
G4TriangularFacet *facet1 = new
G4TriangularFacet (G4ThreeVector(-targetSize,-targetSize,
                                                               0.0).
                  G4ThreeVector(+targetSize,-targetSize,
                  G4ThreeVector( 0.0,
                                             0.0,+targetSize),
                 ABSOLUTE);
G4TriangularFacet *facet2 = new
G4TriangularFacet (G4ThreeVector(+targetSize,-targetSize,
                                                               0.0).
                  G4ThreeVector(+targetSize,+targetSize,
                                                               0.0).
                                      0.0,
                                             0.0, +targetSize),
                  G4ThreeVector(
                 ABSOLUTE);
G4TriangularFacet *facet3 = new
G4TriangularFacet (G4ThreeVector(+targetSize,+targetSize,
                                                               0.0).
                  G4ThreeVector(-targetSize,+targetSize,
                  G4ThreeVector( 0.0, 0.0, +targetSize),
                  ABSOLUTE):
G4TriangularFacet *facet4 = new
G4TriangularFacet (G4ThreeVector(-targetSize,+targetSize,
                                                               0.0),
                  G4ThreeVector(-targetSize,-targetSize,
                  G4ThreeVector(
                                      0.0, 0.0, +targetSize),
                 ABSOLUTE);
G4QuadrangularFacet *facet5 = new
G4QuadrangularFacet (G4ThreeVector(-targetSize,-targetSize,
                                                                 0.0),
                                                                 0.0),
                    G4ThreeVector(-targetSize,+targetSize,
                    G4ThreeVector(+targetSize,+targetSize,
                                                                 0.0),
                    G4ThreeVector(+targetSize,-targetSize,
                                                                 0.0),
                    ABSOLUTE);
// Now add the facets to the solid
solidTarget->AddFacet((G4VFacet*) facet1);
solidTarget->AddFacet((G4VFacet*) facet2);
solidTarget->AddFacet((G4VFacet*) facet3);
solidTarget->AddFacet((G4VFacet*) facet4);
solidTarget->AddFacet((G4VFacet*) facet5);
Finally declare the solid is complete
solidTarget->SetSolidClosed(true);
```

The G4TriangularFacet class is used for the construction of G4TessellatedSolid. It is defined by three vertices, which shall be supplied in *anti-clockwise order* looking from the outside of the solid where it belongs. Its constructor looks like:

i.e., it takes 4 parameters to define the three vertices:

G4FacetVertexType	ABSOLUTE in which case Pt0, vt1 and vt2 are the three vertices in anti-clockwise
	order looking from the outside.
G4FacetVertexType	RELATIVE in which case the first vertex is Pt0, the second vertex is Pt0+vt1
	and the third vertex is Pt0+vt2, all in anti-clockwise order when looking from the
	outside.

The G4QuadrangularFacet class can be used for the construction of G4TessellatedSolid as well. It is defined by four vertices, which shall be in the same plane and be supplied in *anti-clockwise order* looking from the outside of the solid where it belongs. Its constructor looks like:

i.e., it takes 5 parameters to define the four vertices:

G4FacetVertexType	ABSOLUTE in which case Pt0, vt1, vt2 and vt3 are the four vertices required in
	anti-clockwise order when looking from the outside.
G4FacetVertexType	RELATIVE in which case the first vertex is Pt0, the second vertex is Pt0+vt, the
	third vertex is Pt0+vt2 and the fourth vertex is Pt0+vt3, in anti-clockwise order
	when looking from the outside.

## Importing CAD models as tessellated shapes

Tessellated solids can also be used to import geometrical models from CAD systems (see *fig-geom-solid-1*). In order to do this, it is required to convert first the CAD shapes into tessellated surfaces. A way to do this is to save the shapes in the geometrical model as STEP files and convert them to tessellated (faceted surfaces) solids, using a tool which allows such conversion. This strategy allows to import any shape with some degree of approximation; the converted CAD models can then be imported through GDML (Geometry Description Markup Language) into GEANT4 and be represented as G4TessellatedSolid shapes.

Tools which can be used to generate meshes to be then imported in GEANT4 as tessellated solids are:

- FASTRAD 3D tool for radiation shielding analysis; exports meshes to GDML.
- InStep A free STL to GDML conversion tool.
- SALOME Open-source software allowing to import STEP/BREP/IGES/STEP/ACIS formats, mesh them and export to STL.
- ESABASE2 Space environment analysis CAD, basic modules free for academic non-commercial use. Can import STEP files and export to GDML shapes or complete geometries.
- CADMesh Tool based on the VCG Library to read STL files and import in GEANT4.
- Cogenda Commercial TCAD software for generation of 3D meshes through the module *Gds2Mesh* and final export to GDML.
- EDGE A commercial GDML editor, able to import/export STEP/STL geometries.
- CadMC Tool to convert FreeCAD geometries to Geant4 (tessellated and CSG shapes).

#### **Unified Solids**

An alternative implementation for most of the cited geometrical primitives is provided since release 10.0 of GEANT4. With release 10.6, all primitives shapes except the twisted specific solids, can be replaced.

The code for the new geometrical primitives originated as part of the AIDA Unified Solids Library and is now integrated in the VecGeom library (the vectorized geometry library for particle-detector simulation); it is provided as alternative use and can be activated in place of the original primitives defined in GEANT4, by selecting the appropriate compilation flag when configuring the GEANT4 libraries installation. The installation allows to build against an external system installation of the VecGeom library, therefore the appropriate installation path must also be provided during the installation configuration:

```
-DGEANT4_USE_USOLIDS="all" // to replace all available shapes
-DGEANT4_USE_USOLIDS="box; tubs" // to replace only individual shapes
```

The original API for all geometrical primitives is preserved.

# 4.1.3 Logical Volumes

The Logical Volume manages the information associated with detector elements represented by a given Solid and Material, independently from its physical position in the detector.

G4LogicalVolumes must be allocated using 'new' in the user's program; they get registered to a G4LogicalVolumeStore at construction, which will also take care to deallocate them at the end of the job, if not done already in the user's code.

A Logical Volume knows which physical volumes are contained within it. It is uniquely defined to be their mother volume. A Logical Volume thus represents a hierarchy of unpositioned volumes whose positions relative to one another are well defined. By creating Physical Volumes, which are placed instances of a Logical Volume, this hierarchy or tree can be repeated.

A Logical Volume also manages the information relative to the Visualization attributes (*Visualization Attributes*) and user-defined parameters related to tracking, electro-magnetic field or cuts (through the G4UserLimits interface).

By default, tracking optimization of the geometry (voxelization) is applied to the volume hierarchy identified by a logical volume. It is possible to change the default behavior by choosing not to apply geometry optimization for a given logical volume. This feature does not apply to the case where the associated physical volume is a parameterised volume; in this case, optimization is always applied.

**Note:** GEANT4 does not impose any restriction on the name assigned to logical volumes; names can be shared. It is however good practice to specify unique names for each logical volume, to allow for easier retrivial from stores for post-processing use.

Through the logical volume it is also possible to *tune* the granularity of the optimisation algorithm to be applied to the sub-tree of volumes represented. This is possible using the methods:

```
G4double GetSmartless() const void SetSmartless(G4double s)
```

The default *smartless* value is 2 and controls the average number of slices per contained volume which are used in the optimisation. The smaller the value, the less fine grained optimisation grid is generated; this will translate in a possible reduction of memory consumed for the optimisation of that portion of geometry at the price of a slight CPU time increase at tracking time. Manual tuning of the optimisation is in general not required, since the optimal granularity level is computed automatically and adapted to the specific geometry setup; however, in some cases (like geometry portions with 'dense' concentration of volumes distributed in a non-uniform way), it may be necessary to adopt manual tuning for helping the optimisation process in dealing with the most critical areas. By setting the verbosity to 2 through the following UI run-time command:

```
/run/verbose 2
```

a statistics of the memory consumed for the allocated optimisation nodes will be displayed volume by volume, allowing to easily identify the critical areas which may eventually require manual intervention.

The logical volume provides a way to estimate the *mass* of a tree of volumes defining a detector or sub-detector. This can be achieved by calling the method:

```
G4double GetMass(G4bool forced=false)
```

The mass of the logical volume tree is computed from the estimated geometrical volume of each solid and material associated with the logical volume and its daughters. Note that this computation may require a considerable amount of time, depending on the complexity of the geometry tree. The returned value is cached by default and can be used for successive calls, unless recomputation is forced by providing true for the Boolean argument forced in input. Computation should be forced if the geometry setup has changed after the previous call.

Finally, the Logical Volume manages the information relative to the Envelopes hierarchy required for fast Monte Carlo parameterisations (*Parameterisation*).

### **Sub-detector Regions**

In complex geometry setups, such as those found in large detectors in particle physics experiments, it is useful to think of specific Logical Volumes as representing parts (sub-detectors) of the entire detector setup which perform specific functions. In such setups, the processing speed of a real simulation can be increased by assigning specific production *cuts* to each of these detector parts. This allows a more detailed simulation to occur only in those regions where it is required.

The concept of detector *Region* is introduced to address this need. Once the final geometry setup of the detector has been defined, a region can be specified by constructing it with:

```
G4Region( const G4String& rName )
```

where:

```
rName String identifier for the detector region
```

G4Regions must be allocated using 'new' in the user's program; they get registered to a G4RegionStore at construction, which will also take care to deallocate them at the end of the job, if not done already in the user's code.

A G4Region must then be assigned to a logical volume, in order to make it a Root Logical Volume:

```
G4Region* emCalorimeter = new G4Region("EM-Calorimeter");
emCalorimeterLV->SetRegion(emCalorimeter);
emCalorimeter->AddRootLogicalVolume(emCalorimeterLV);
```

A root logical volume is the first volume at the top of the hierarchy to which a given region is assigned. Once the region is assigned to the root logical volume, the information is automatically propagated to the volume tree, so that each daughter volume shares the same region. Propagation on a tree branch will be interrupted if an already existing root logical volume is encountered.

**Note:** It is recommended to assign unique names to logical volumes specified as root logical volumes, as this will guarantee proper retrievial from the store for post-processing use in persistency. The same applies for names assigned to regions.

A specific Production Cut can be assigned to the region, by defining and assigning to it a G4ProductionCut object

```
emCalorimeter->SetProductionCuts(emCalCuts);
```

Set production threshold (SetCut methods) describes how to define a production cut. The same region can be assigned to more than one root logical volume, and root logical volumes can be removed from an existing region. A logical volume can have only *one* region assigned to it. Regions will be automatically registered in a store which will take care of destroying them at the end of the job. A default region with a default production cut is automatically created and assigned to the world volume.

Regions can also become 'envelopes' for fast-simulation; can be assigned user-limits or generic user-information (G4VUserRegionInformation); can be associated to specific stepping-actions (G4UserSteppingAction) or have assigned a local magnetic-field (local fields specifically associated to logical volumes take precedence anyhow).

## 4.1.4 Physical Volumes

Physical volumes represent the spatial positioning of the volumes describing the detector elements. Several techniques can be used. They range from the simple placement of a single copy to the repeated positioning using either a simple linear formula or a user specified function.

Any physical volume must be allocated using 'new' in the user's program; they get registered to a G4PhysicalVolumeStore at construction, which will also take care to deallocate them at the end of the job, if not done already in the user's code.

The simple placement involves the definition of a transformation matrix for the volume to be positioned. Repeated positioning is defined using the number of times a volume should be replicated at a given distance along a given direction. Finally it is possible to define a parameterised formula to specify the position of multiple copies of a volume. Details about these methods are given below.

**Note:** For geometries which vary between runs and for which components of the old geometry setup are explicitly -deleted-, it is required to consider the proper order of deletion (which is the exact inverse of the actual construction, i.e., first delete physical volumes and then logical volumes). Deleting a logical volume does NOT delete its daughter volumes.

It is not necessary to delete the geometry setup at the end of a job, the system will take care to free the volume and solid stores at the end of the job. The user has to take care of the deletion of any additional transformation or rotation matrices allocated dynamically in his/her own application.

**Note:** GEANT4 does not impose any restriction on the name assigned to volumes; names can be shared. It is however good practice to specify unique names for each physical node in a tree, to allow for easier retrivial from stores for post-processing use.

## Placements: single positioned copy

In this case, the Physical Volume is created by associating a Logical Volume with a Transformation that defines the position of the current volume in the mother volume. The solid itself is moved by rotating and translating it to bring it into the system of coordinates of the mother volume. The decomposition of the Transformation must contain only rotation and translation (reflection and scaling are not allowed).

To create a Placement one must construct it using:

```
G4PVPlacement(
G4Transform3D solidTransform,
G4LogicalVolume* pCurrentLogical,
pName,
G4LogicalVolume* pMotherLogical,
G4bool pMany,
G4int pCopyNo,
G4bool pSurfChk=false)
```

where:

solidTransform	Position in its mother volume	
pCurrentLogical	The associated Logical Volume	
pName	String identifier for this placement	
pMotherLogical	The associated mother volume	
pMany	For future use. Can be set to false	
рСоруNо	Integer which identifies this placement	
pSurfChk	if true activates check for overlaps with existing volumes	

Currently Boolean operations are not implemented at the level of physical volume. So pMany must be false. However, an alternative implementation of Boolean operations exists. In this approach a solid can be created from the union, intersection or subtraction of two solids. See *Solids made by Boolean operations* above for an explanation of this.

The mother volume must be specified for all volumes *except* the world volume.

An alternative way to specify a Placement is to use a Rotation Matrix and a Translation Vector. If compared with the previous construct, the Rotation Matrix is the inverse of the rotation from the decomposition of the transformation, but the Translation Vector is the same. The Rotation Matrix represents the rotation of the reference frame of the considered volume relatively to its mother volume's reference frame. The Translation Vector represents the translation of the current volume in the reference frame of its mother volume. This *passive* method can be utilized using the following constructor:

```
G4PVPlacement( G4RotationMatrix* pRot,
const G4ThreeVector& tlate,
G4LogicalVolume* pCurrentLogical,
const G4String& pName,
G4LogicalVolume* pMotherLogical,
G4bool pMany,
G4int pCopyNo,
G4bool pSurfChk=false)
```

where:

pRot	Rotation with respect to its mother volume	
tlate	Translation with respect to its mother volume	
pCurrentLogical	The associated Logical Volume	
pName	String identifier for this placement	
pMotherLogical	The associated mother volume	
pMany	For future use. Can be set to false	
рСоруNо	Integer which identifies this placement	
pSurfChk	if true activates check for overlaps with existing volumes	

Care must be taken because the rotation matrix is not copied by a G4PVPlacement. So the user must not modify it after creating a Placement that uses it. However the same rotation matrix can be re-used for many volumes.

An alternative method to specify the mother volume is to specify its placed physical volume. It can be used in either of the above methods of specifying the placement's position and rotation. The effect will be exactly the same as for using the mother logical volume.

Note that a Placement Volume can still represent multiple detector elements. This can happen if several copies exist of the mother logical volume. Then different detector elements will belong to different branches of the tree of the hierarchy of geometrical volumes.

An example demonstrating various ways of placement and constructing the rotation matrix is provided in examples/extended/geometry/transforms.

### Repeated volumes

In this case, a single Physical Volume represents multiple copies of a volume within its mother volume, allowing to save memory. This is normally done when the volumes to be positioned follow a well defined rotational or translational symmetry along a Cartesian or cylindrical coordinate. The Repeated Volumes technique is available for most volumes described by CSG solids.

## **Replicas**

Replicas are *repeated volumes* in the case when the multiple copies of the volume are all identical. The coordinate axis and the number of replicas need to be specified for the program to compute at run time the transformation matrix corresponding to each copy.

#### where:

pName	String identifier for the replicated volume	
pCurrentLogical	The associated Logical Volume	
pMotherLogical	The associated mother volume	
pAxis	The axis along with the replication is applied	
nReplicas	The number of replicated volumes	
width	The width of a single replica along the axis of replication	
offset	Possible offset associated to mother offset along the axis of replication	

G4PVReplica represents nReplicas volumes differing only in their positioning, and completely **filling** the containing mother volume. Consequently if a G4PVReplica is 'positioned' inside a given mother it **MUST** be the mother's only daughter volume. Replica's correspond to divisions or slices that completely fill the mother volume and have no offsets. For Cartesian axes, slices are considered perpendicular to the axis of replication.

The replica's positions are calculated by means of a linear formula. Replication may occur along:

- Cartesian axes (kXAxis, kYAxis, kZAxis)
  The replications, of specified width have coordinates of form (-width\*(nReplicas-1)\*0.
  5+n\*width,0,0) where n=0.. nReplicas-1 for the case of kXAxis, and are unrotated.
- Radial axis (cylindrical polar) (kRho)
  - The replications are cons/tubs sections, centred on the origin and are unrotated.
- They have radii of width\*n+offset to width\*(n+1)+offset where n=0..nReplicas-1
- Phi axis (cylindrical polar) (kPhi)
  - The replications are *phi sections* or *wedges*, and of cons/tubs form.
  - They have phi of offset+n\*width to offset+(n+1)\*width where n=0..nReplicas-1

The coordinate system of the replicas is at the centre of each replica for the Cartesian axis. For the radial case, the coordinate system is unchanged from the mother. For the phi axis, the new coordinate system is rotated such that the X axis bisects the angle made by each wedge, and Z remains parallel to the mother's Z axis.

The solid associated via the replicas' logical volume should have the dimensions of the first volume created and must be of the correct symmetry/type, in order to assist in good visualisation.

ex. For X axis replicas in a box, the solid should be another box with the dimensions of the replications. (same Y & Z dimensions as mother box, X dimension = mother's X dimension/nReplicas).

Replicas may be placed inside other replicas, provided the above rule is observed. Normal placement volumes may be placed inside replicas, provided that they do not intersect the mother's or any previous replica's boundaries. Parameterised volumes may not be placed inside.

Because of these rules, it is not possible to place any other volume inside a replication in radius.

The world volume *cannot* act as a replica, therefore it cannot be sliced.

During tracking, the translation + rotation associated with each G4PVReplica object is modified according to the currently 'active' replication. The solid is not modified and consequently has the wrong parameters for the cases of phi and r replication and for when the cross-section of the mother is not constant along the replication.

Example

Listing 4.2: An example of simple replicated volumes with G4PVReplica.

```
G4PVReplica repX("Linear Array",
                 pRepLogical,
                 pContainingMotherBox,
                  kXAxis, 5, 10 *mm);
G4PVReplica repR("RSlices",
                 pRepRLogical,
                 pContainingMotherTub,
                  kRho, 5, 10 * mm, 0);
G4PVReplica repZ("ZSlices",
                 pRepZLogical,
                 pContainingMotherTub,
                 kZAxis, 5, 10 ⋅mm);
G4PVReplica repPhi("PhiSlices",
                   pRepPhiLogical,
                   pContainingMotherTub,
                    kPhi, 4, M_PI*0.5*rad, 0);
```

RepX is an array of 5 replicas of width 10\*mm, positioned inside and completely filling the volume pointed by pContainingMotherBox. The mother's X length must be 5\*10\*mm=50\*mm (for example, if the mother's solid were a Box of half lengths [25,25,25] then the replica's solid must be a box of half lengths [25,25,5]).

If the containing mother's solid is a tube of radius 50\*mm and half Z length of 25\*mm, RepR divides the mother tube into 5 cylinders (hence the solid associated with pRepRLogical must be a tube of radius 10\*mm, and half Z length 25\*mm); repZ divides the tube into 5 shorter cylinders (the solid associated with pRepZLogical must be a tube of radius 10\*mm, and half Z length 5\*mm); finally, repPhi divides the tube into 4 tube segments with full angle of 90 degrees (the solid associated with pRepPhiLogical must be a tube segment of radius 10\*mm, half Z length 5\*mm and delta phi of M\_PI\*0.5\*rad).

No further volumes may be placed inside these replicas. To do so would result in intersecting boundaries due to the r replications.

### **Parameterised Volumes**

Parameterised Volumes are *repeated volumes* in the case in which the multiple copies of a volume can be different in size, solid type, or material. The solid's type, its dimensions, the material and the transformation matrix can all be parameterised in function of the copy number, both when a strong symmetry exist and when it does not. The user implements the desired parameterisation function and the program computes and updates automatically at run time the information associated to the Physical Volume.

An example of creating a parameterised volume (by dimension and position) exists in basic example B2b. The implementation is provided in the two classes B2b::DetectorConstruction and B2b::ChamberParameterisation.

To create a parameterised volume, one must first create its logical volume like trackerChamberLV below. Then one must create his own parameterisation class (*B2b::ChamberParameterisation*) and instantiate an object of this class (chamberParam). We will see how to create the parameterisation below.

Listing 4.3: An example of Parameterised volumes.

```
// Tracker segments
// An example of Parameterised volumes
// Dummy values for G4Tubs -- modified by parameterised volume
G4Tubs* chamberS
  = new G4Tubs("tracker",0, 100*cm, 100*cm, 0.*deg, 360.*deg);
fLogicChamber
  = new G4LogicalVolume(chamberS,fChamberMaterial, "Chamber", 0, 0, 0);
G4double firstPosition = -trackerSize + chamberSpacing;
G4double firstLength = trackerLength/10;
G4double lastLength = trackerLength;
G4VPVParameterisation* chamberParam
 new ChamberParameterisation(NbOfChambers,  // NoChambers
                                 firstPosition, // Z of center of first
                                 chamberSpacing, // Z spacing of centers
                                 chamberWidth, // chamber width
                                 firstLength,  // initial length
lastLength);  // final length
// dummy value : kZAxis -- modified by parameterised volume
new G4PVParameterised("Chamber",
                       ("Chamber", // their name
fLogicChamber, // their logical volume
trackerLV, // Mother logical volume
                        kZAxis,
                                          // Are placed along this axis
                        NbOfChambers, // Number of chambers chamberParam, // The parametrisation
                        fCheckOverlaps); // checking overlaps
```

### The general constructor is:

Note that for a parameterised volume the user must always specify a mother volume. So the world volume can *never* be a parameterised volume, nor it can be sliced. The mother volume can be specified either as a physical or a logical volume.

pAxis specifies the tracking optimisation algorithm to apply: if a valid axis (the axis along which the parameterisation is performed) is specified, a simple one-dimensional voxelisation algorithm is applied; if "kUndefined" is specified instead, the default three-dimensional voxelisation algorithm applied for normal placements will be activated. In the latter case, more voxels will be generated, therefore a greater amount of memory will be consumed by the optimisation algorithm.

pSurfChk if true activates a check for overlaps with existing volumes or paramaterised instances.

The parameterisation mechanism associated to a parameterised volume is defined in the parameterisation class and its methods. Every parameterisation must create two methods:

- ComputeTransformation defines where one of the copies is placed,
- ComputeDimensions defines the size of one copy, and
- a constructor that initializes any member variables that are required.

An example is B2b:: ChamberParameterisation that parameterises a series of tubes of different sizes

Listing 4.4: An example of Parameterised tubes of different sizes.

These methods works as follows:

The ComputeTransformation method is called with a copy number for the instance of the parameterisation under consideration. It must compute the transformation for this copy, and set the physical volume to utilize this transformation:

```
void ChamberParameterisation::ComputeTransformation
(const G4int copyNo, G4VPhysicalVolume *physVol) const
{
    // Note: copyNo will start with zero!
    G4double Zposition = fStartZ + copyNo * fSpacing;
    G4ThreeVector origin(0,0,Zposition);
    physVol->SetTranslation(origin);
    physVol->SetRotation(0);
}
```

Note that the translation and rotation given in this scheme are those for the frame of coordinates (the *passive* method). They are **not** for the *active* method, in which the solid is rotated into the mother frame of coordinates.

Similarly the ComputeDimensions method is used to set the size of that copy.

```
void ChamberParameterisation::ComputeDimensions
(G4Tubs& trackerChamber, const G4int copyNo, const G4VPhysicalVolume*) const
{
    // Note: copyNo will start with zero!
    G4double rmax = fRmaxFirst + copyNo * fRmaxIncr;
    trackerChamber.SetInnerRadius(0);
    trackerChamber.SetOuterRadius(rmax);
    (continues on next page)
```

(continued from previous page)

```
trackerChamber.SetZHalfLength(fHalfWidth);
trackerChamber.SetStartPhiAngle(0.*deg);
trackerChamber.SetDeltaPhiAngle(360.*deg);
}
```

The user must ensure that the type of the first argument of this method (in this example G4Tubs &) corresponds to the type of object the user give to the logical volume of parameterised physical volume.

More advanced usage allows the user:

- to change the type of solid by creating a ComputeSolid method, or
- to change the material of the volume by creating a ComputeMaterial method. This method can also utilise information from a parent or other ancestor volume (see the Nested Parameterisation below.)

for the parameterisation.

Example examples/extended/runAndEvent/RE02 shows a simple parameterisation by material. A more complex example is provided in examples/extended/medical/DICOM, where a phantom grid of cells is built using a parameterisation by material defined through a map.

**Note:** Currently for many cases it is not possible to add daughter volumes to a parameterised volume. Only parameterised volumes all of whose solids have the same size are allowed to contain daughter volumes. When the size or type of solid varies, adding daughters is not supported. So the full power of parameterised volumes can be used only for "leaf" volumes, which contain no other volumes.

**Note:** A hierarchy of volumes included in a parameterised volume cannot vary. Therefore, it is not possible to implement a parameterisation which can modify the hierarchy of volumes included inside a specific parameterised copy.

**Note:** For parameterisations of tubes or cons, where the starting Phi and its DeltaPhi angles vary, it is possible to optimise the regeneration of the trigonometric parameters of the shape, by invoking SetStartPhiAngle(newPhi, false); SetDeltaPhiAngle (newDPhi), i.e. by specifying with false flag to skip the computation of the parameters which will be later on properly initialised with the call for DeltaPhi.

**Note:** Parameterisations of composed solids like Boolean, Reflected or Displaced solids are not recommended, given the complexity in handling transformations that this might imply, and limitations in making persistent representations (i.e. GDML) of the geometry itself.

**Note:** For multi-threaded applications, one must be careful in the implementation of the parameterisation functions for the geometrical objects being created in the parameterisation. In particular, when parameterising by the type of a solid, it is assumed that the solids being parameterised are being declared thread-local in the user's parameterisation class and allocated just once.

### Advanced parameterisations for 'nested' parameterised volumes

A different type of parameterisation enables a user to have the daughter's material also depend on the copy number of the parent when a parameterised volume (daughter) is located inside another (parent) repeated volume. The parent volume can be a replica, a parameterised volume, or a division if the key feature of modifying its contents is utilised. (Note: a 'nested' parameterisation inside a placement volume is not supported, because all copies of a placement volume must be identical at all levels.)

In such a "nested" parameterisation, the user must provide a ComputeMaterial method that utilises the new argument that represents the touchable history of the parent volume:

The implementation of the method can utilise any information from a parent or other ancestor volume of its parameterised physical volume, but typically it will use only the copy number:

```
G4Material*
SampleNestedParameterisation::ComputeMaterial (G4VPhysicalVolume *currentVol, const G4int no_lev, const G4VTouchable *parentTouchable)

{
    G4Material *material=0;

    // Get the information about the parent volume
    G4int no_parent= parentTouchable->GetReplicaNumber();
    G4int no_total= no_parent + no_lev;

    // A simple 'checkerboard' pattern of two materials
    if( no_total / 2 == 1 ) material= material1;
    else material= material2;

    // Set the material to the current logical volume
    G4LogicalVolume* currentLogVol= currentVol->GetLogicalVolume();
    currentLogVol->SetMaterial( material );
    return material;
}
```

Nested parameterisations are suitable for the case of regular, 'voxel' geometries in which a large number of 'equal' volumes are required, and their only difference is in their material. By creating two (or more) levels of parameterised physical volumes it is possible to divide space, while requiring only limited additional memory for very fine-level optimisation. This provides fast navigation. Alternative implementations, taking into account the regular structure of such geometries in navigation are under study.

#### **Divisions of Volumes**

Divisions in GEANT4 are repeated volumes and are implemented as a specialized type of parameterised volumes.

They serve to divide a volume into identical copies along one of its axes, providing the possibility to define an *offset*, and without the limitation that the daughters have to fill the mother volume as it is the case for the replicas. In the case, for example, of a tube divided along its radial axis, the copies are not strictly identical, but have increasing radii, although their widths are constant.

To divide a volume it will be necessary to provide:

- 1. the axis of division, and
- 2. either
  - the number of divisions (so that the width of each division will be automatically calculated), or
  - the division width (so that the number of divisions will be automatically calculated to fill as much of the mother as possible), or
  - both the number of divisions and the division width (this is especially designed for the case where the copies do not fully fill the mother).

An *offset* can be defined so that the first copy will start at some distance from the mother wall. The dividing copies will be then distributed to occupy the rest of the volume.

There are three constructors, corresponding to the three input possibilities described above:

• Giving only the number of divisions:

```
G4PVDivision( const G4String& pName,
G4LogicalVolume* pCurrentLogical,
G4LogicalVolume* pMotherLogical,
const EAxis pAxis,
const G4int nDivisions,
const G4double offset )
```

• Giving only the division width:

```
G4PVDivision( const G4String& pName,
G4LogicalVolume* pCurrentLogical,
G4LogicalVolume* pMotherLogical,
const EAxis pAxis,
const G4double width,
const G4double offset )
```

• Giving the number of divisions and the division width:

where:

pName	String identifier for the replicated volume	
pCurrentLogical	The associated Logical Volume	
pMotherLogical	The associated mother Logical Volume	
pAxis	The axis along which the division is applied	
nDivisions	The number of divisions	
width	The width of a single division along the axis	
offset	Possible offset associated to the mother along the axis of division	

The parameterisation is calculated automatically using the values provided in input. Therefore the dimensions of the solid associated with pCurrentLogical will not be used, but recomputed through the G4VParameterisation::ComputeDimension() method.

Since G4VPVParameterisation may have different ComputeDimension() methods for each solid type, the user must provide a solid that is of the same type as of the one associated to the mother volume.

As for any replica, the coordinate system of the divisions is related to the centre of each division for the Cartesian axis. For the radial axis, the coordinate system is the same of the mother volume. For the phi axis, the new coordinate system is rotated such that the X axis bisects the angle made by each wedge, and Z remains parallel to the mother's Z axis.

As divisions are parameterised volumes with constant dimensions, they may be placed inside other divisions, except in the case of divisions along the radial axis.

It is also possible to place other volumes inside a volume where a division is placed.

The list of volumes that currently support divisioning and the possible division axis are summarised below:

G4Box	kXAxis, kYAxis, kZAxis
G4Tubs	kRho, kPhi, kZAxis
G4Cons	kRho, kPhi, kZAxis
G4Trd	kXAxis, kYAxis, kZAxis
G4Para	kXAxis, kYAxis, kZAxis
G4Polycone	kRho, kPhi, kZAxis
G4Polyhedra	kRho, kPhi, kZAxis(*)

#### (\*)-G4Polyhedra:

• kPhi - the number of divisions has to be the same as solid sides, (i.e. numSides), the width will *not* be taken into account.

In the case of division along kRho of G4Cons, G4Polycone, G4Polyhedra, if width is provided, it is taken as the width at the -Z radius; the width at other radii will be scaled to this one.

Examples are given below in listings Listing 4.3 and Listing 4.5.

Listing 4.5: An example of a box division along different axes, with or without offset.

- divBox1 is a division of a box along its X axis in 5 equal copies. Each copy will have a dimension in meters of [0.2, 1., 1.].
- divBox2 is a division of the same box along its X axis with a width of 0.1 meters and an offset of 0.5 meters. As the mother dimension along X of 1 meter (0.5\*m of halflength), the division will be sized in total 1 0.45 = 0.55 meters. Therefore, there's space for 5 copies, the first extending from -0.05 to 0.05 meters in the mother's frame and the last from 0.35 to 0.45 meters.

divBox3 is a division of the same box along its X axis in 3 equal copies of width 0.1 meters and an offset of 0.5 meters. The first copy will extend from 0.1 meters in the mother's frame and the last from 0.2 to 0.3 meters.

Listing 4.6: An example of division of a polycone.

```
G4double* zPlanem = new G4double[3];
          zPlanem[0] = -1.*m;
          zPlanem[1] = -0.25 * m;
         zPlanem[2] = 1.*m;
G4double* rInnerm = new G4double[3];
          rInnerm[0]=0.;
          rInnerm[1]=0.1\starm;
          rInnerm[2]=0.5*m;
G4double* rOuterm = new G4double[3];
         rOuterm[0]=0.2 \pm m;
          rOuterm[1]=0.4\starm;
          rOuterm[2]=1.*m;
G4Polycone * motherSolid = new G4Polycone ("motherSolid", 20.*deg, 180.*deg,
                                          3, zPlanem, rInnerm, rOuterm);
G4LogicalVolume* motherLog = new G4LogicalVolume(motherSolid, material, "mother", 0, 0, 0);
G4double* zPlaned = new G4double[3];
          zPlaned[0] = -3.*m;
          zPlaned[1] = -0.*m;
          zPlaned[2] = 1.*m;
G4double* rInnerd = new G4double[3];
          rInnerd[0]=0.2;
          rInnerd[1]=0.4\timesm;
          rInnerd[2]=0.5\starm;
G4double* rOuterd = new G4double[3];
          rOuterd[0]=0.5\starm;
          rOuterd[1]=0.8\pmm;
          rOuterd[2]=2.*m;
G4Polycone * divSolid = new G4Polycone ("divSolid", 0.*deg, 10.*deg,
                                       3, zPlaned, rInnerd, rOuterd);
G4LogicalVolume* childLog = new G4LogicalVolume(divSolid, material, "child",0,0,0);
G4PVDivision divPconePhiW("division along phi giving width and offset",
                           childLog, motherLog, kPhi, 30.*deg, 60.*deg);
G4PVDivision divPconeZN("division along Z giving nDiv and offset",
                            childLog, motherLog, kZAxis, 2, 0.1*m);
```

- divPconePhiW is a division of a polycone along its phi axis in equal copies of width 30 degrees with an offset of 60 degrees. As the mother extends from 0 to 180 degrees, there's space for 4 copies. All the copies have a starting angle of 20 degrees (as for the mother) and a phi extension of 30 degrees. They are rotated around the Z axis by 60 and 30 degrees, so that the first copy will extend from 80 to 110 and the last from 170 to 200 degrees.
- divPconeZN is a division of the same polycone along its Z axis. As the mother polycone has two sections, it will be divided in two one-section polycones, the first one extending from -1 to -0.25 meters, the second from -0.25 to 1 meters. Although specified, the offset will not be used.

## **Replicated Slices**

A special kind of divided volume is represented by G4ReplicatedSlice, a division allowing for gaps inbetween divided volumes.

Three constructors, corresponding to three input possibilities are provided:

• Giving only the number of divisions:

• Giving only the division width:

• Giving the number of divisions and the division width:

where:

pName	String identifier for the replicated volume
pCurrentLogical	The associated Logical Volume
pMotherLogical	The associated mother Logical Volume
pAxis	The axis along which the division is applied
nDivisions	The number of divisions
width	The width of a single division along the axis
half_gap	The half width of the gap to be considered inbetween division slices
offset	Possible offset associated to the mother along the axis of division

As for G4PVDivision, the parameterisation is calculated automatically using the values provided in input.

# 4.1.5 Touchables: Uniquely Identifying a Volume

#### **Introduction to Touchables**

A *touchable* for a volume serves the purpose of providing a unique identification for a detector element. This can be useful for description of the geometry alternative to the one used by the GEANT4 tracking system, such as a Sensitive Detectors based read-out geometry, or a parameterised geometry for fast Monte Carlo. In order to create a *touchable volume*, several techniques can be implemented: for example, in GEANT4 touchables are implemented as solids associated to a transformation-matrix in the global reference system, or as a hierarchy of physical volumes up to the root of the geometrical tree.

A touchable is a geometrical entity (volume or solid) which has a unique placement in a detector description. It is represented by an abstract base class which can be implemented in a variety of ways. Each way must provide the capabilities of obtaining the transformation and solid that is described by the touchable.

#### What can a Touchable do?

All G4VTouchable implementations must respond to the two following "requests", where in all cases, by depth it is meant the number of levels *up* in the tree to be considered (the default and current one is 0):

- 1. GetTranslation (depth)
- 2. GetRotation (depth)

that return the components of the volume's transformation.

Additional capabilities are available from implementations with more information. These have a default implementation that causes an exception.

Several capabilities are available from touchables with physical volumes:

- 1. GetSolid(depth) gives the solid associated to the touchable.
- 2. GetVolume (depth) gives the physical volume.
- 3. GetReplicaNumber (depth) or GetCopyNumber (depth) which return the copy number of the physical volume (replicated or not).

Touchables that store volume hierarchy (history) have the whole stack of parent volumes available. Thus it is possible to add a little more state in order to extend its functionality. We add a "pointer" to a level and a member function to move the level in this stack. Then calling the above member functions for another level the information for that level can be retrieved.

The top of the history tree is, by convention, the world volume.

- 1. GetHistoryDepth() gives the depth of the history tree.
- 2. MoveUpHistory (num) moves the current pointer inside the touchable to point num levels up the history tree. Thus, e.g., calling it with num=1 will cause the internal pointer to move to the mother of the current volume.

**Warning:** this function changes the state of the touchable and can cause errors in tracking if applied to Pre/Post step touchables.

These methods are valid only for the touchable-history type, as specified also below.

An update method, with different arguments is available, so that the information in a touchable can be updated:

1. UpdateYourself(vol, history) takes a physical volume pointer and can additionally take a NavigationHistory pointer.

#### Touchable history holds stack of geometry data

As shown in Sections *Logical Volumes* and *Physical Volumes*, a logical volume represents unpositioned detector elements, and a physical volume can represent multiple detector elements. On the other hand, touchables provide a unique identification for a detector element. In particular, the GEANT4 transportation process and the tracking system exploit touchables as implemented in G4TouchableHistory. The touchable history is the minimal set of information required to specify the full genealogy of a given physical volume (up to the root of the geometrical tree). These touchable volumes are made available to the user at every step of the GEANT4 tracking in G4VUserSteppingAction.

To create/access a G4TouchableHistory the user must message G4Navigator which provides the method CreateTouchableHistoryHandle():

```
G4TouchableHistoryHandle CreateTouchableHistoryHandle() const;
```

this will return a handle to the touchable.

The methods that differentiate the touchable-history from other touchables (since they have meaning only for this type...), are:

```
G4int GetHistoryDepth() const;
G4int MoveUpHistory( G4int num_levels = 1 );
```

The first method is used to find out how many levels deep in the geometry tree the current volume is. The second method asks the touchable to eliminate its deepest level.

As mentioned above, MoveUpHistory (num) significantly modifies the state of a touchable.

# 4.1.6 Creating an Assembly of Volumes

G4AssemblyVolume is a helper class which allows several logical volumes to be combined together in an arbitrary way in 3D space. The result is a placement of a normal logical volume, but where final physical volumes are many.

However, an *assembly* volume does not act as a real mother volume, being an envelope for its daughter volumes. Its role is over at the time the placement of the logical assembly volume is done. The physical volume objects become independent copies of each of the assembled logical volumes.

This class is particularly useful when there is a need to create a regular pattern in space of a complex component which consists of different shapes and can't be obtained by using replicated volumes or parametrised volumes (see also Fig. 4.2. Careful usage of G4AssemblyVolume must be considered though, in order to avoid cases of "proliferation" of physical volumes all placed in the same mother.




Fig. 4.2: Examples of assembly of volumes.

### Filling an assembly volume with its "daughters"

Participating logical volumes are represented as a triplet of <logical volume, translation, rotation> (G4AssemblyTriplet class).

The adopted approach is to place each participating logical volume with respect to the assembly's coordinate system, according to the specified translation and rotation.

### Assembly volume placement

An assembly volume object is composed of a set of logical volumes; imprints of it can be made inside a mother logical volume.

Since the assembly volume class generates physical volumes during each imprint, the user has no way to specify identifiers for these. An internal counting mechanism is used to compose uniquely the names of the physical volumes created by the invoked MakeImprint (...) method(s).

The name for each of the physical volume is generated with the following format:

```
av_WWW_impr_XXX_YYY_ZZZ
```

#### where:

```
WWW - assembly volume instance number

XXX - assembly volume imprint number

YYY - the name of the placed logical volume

ZZZ - the logical volume index inside the assembly volume
```

It is however possible to access the constituent physical volumes of an assembly and eventually customise ID and copy-number.

The setting of the copy-numbers can be complex, depending on how complex is the structure being built. Each assembly (G4AssemblyVolume) instance gets automatically assigned a number, assemblyID, which starts from zero and gets incremented based on the number of imprints being made. Each assembly is being stored in a G4AssemblyStore and can always been retrieved at any time. G4AssemblyVolume allows to define a base copy-number for each imprint (call to MakeImprint ()), by specifying it as a parameter, copyNumBase, which is set to zero by default. The computation of the effective copy-number of each volume in the assembly is done using such parameter, i.e. based on the number of triplets (number of volumes added in the assembly), each volume copy number is assigned as:

```
numberOfDaughters + i
```

where i goes from zero to the number of volumes in the assembly; numberOfDaughters is either set to the number of daughter volumes in the mother where the assembly must be placed (if copyNumBase is zero, i.e. not being specified at the time the imprint is made), or the specified copyNumBase.

In case the assembly includes another assembly inside, the call to makeImprint() is made recursively, and the base copy-number in this case is being set to:

```
i*100+copyNumBase
```

so, shifted by 100 times the index of the triplet in the original assembly.

### Destruction of an assembly volume

At destruction all the generated physical volumes and associated rotation matrices of the imprints will be destroyed. A list of physical volumes created by MakeImprint() method is kept, in order to be able to cleanup the objects when not needed anymore. This requires the user to keep the assembly objects in memory during the whole job or during the life-time of the G4Navigator, logical volume store and physical volume store may keep pointers to physical volumes generated by the assembly volume.

The MakeImprint () method will operate correctly also on transformations including reflections and can be applied also to recursive assemblies (i.e., it is possible to generate imprints of assemblies including other assemblies). Giving true as the last argument of the MakeImprint () method, it is possible to activate the volumes overlap check for the assembly's constituents (the default is false).

Each assembly structure is registered at construction in a specialised store, G4AssemblyStore, which can then be used to identify all structures defined in a geometry setup, as well as the volumes belonging to each imprint.

At destruction of a G4AssemblyVolume, all its generated physical volumes and rotation matrices will be automatically freed.

#### **Example**

This example shows how to use the G4AssemblyVolume class. It implements a layered detector where each layer consists of 4 plates.

In the code below, at first the world volume is defined, then solid and logical volume for the plate are created, followed by the definition of the assembly volume for the layer.

The assembly volume for the layer is then filled by the plates in the same way as normal physical volumes are placed inside a mother volume.

Finally the layers are placed inside the world volume as the imprints of the assembly volume (see Listing 4.7).

Listing 4.7: An example of usage of the G4AssemblyVolume class.

```
static unsigned int layers = 5;
void TstVADetectorConstruction::ConstructAssembly()
  // Define world volume
 G4Box* WorldBox = new G4Box( "WBox", worldX/2., worldY/2., worldZ/2.);
 G4LogicalVolume* worldLV = new G4LogicalVolume( WorldBox, selectedMaterial,
                                                    "WLog", 0, 0, 0);
 G4VPhysicalVolume* worldVol = new G4PVPlacement( 0, G4ThreeVector(), "WPhys", worldLV,
                                                  0, false, 0);
  // Define a plate
  G4Box* PlateBox = new G4Box( "PlateBox", plateX/2., plateY/2., plateZ/2.);
  G4LogicalVolume* plateLV = new G4LogicalVolume( PlateBox, Pb, "PlateLV", 0, 0, 0 );
  // Define one layer as one assembly volume
  G4AssemblyVolume* assemblyDetector = new G4AssemblyVolume();
  // Rotation and translation of a plate inside the assembly
  G4RotationMatrix Ra;
  G4ThreeVector Ta;
  G4Transform3D Tr;
  // Rotation of the assembly inside the world
  G4RotationMatrix Rm;
  // Fill the assembly by the plates
  Ta.setX( caloX/4. ); Ta.setY( caloY/4. ); Ta.setZ( 0. );
```

(continues on next page)

```
Tr = G4Transform3D(Ra, Ta);
assemblyDetector->AddPlacedVolume( plateLV, Tr );
Ta.setX( -1*caloX/4.); Ta.setY( caloY/4.); Ta.setZ( 0.);
Tr = G4Transform3D(Ra, Ta);
assemblyDetector->AddPlacedVolume( plateLV, Tr );
Ta.setX(-1*caloX/4.); Ta.setY(-1*caloY/4.); Ta.setZ(0.);
Tr = G4Transform3D(Ra, Ta);
assemblyDetector->AddPlacedVolume( plateLV, Tr );
Ta.setX( caloX/4.); Ta.setY( -1*caloY/4.); Ta.setZ( 0.);
Tr = G4Transform3D(Ra, Ta);
assemblyDetector->AddPlacedVolume( plateLV, Tr );
// Now instantiate the layers
for( unsigned int i = 0; i < layers; i++ )</pre>
  // Translation of the assembly inside the world
 G4ThreeVector Tm( 0,0,i*(caloZ + caloCaloOffset) - firstCaloPos );
 Tr = G4Transform3D(Rm, Tm);
 assemblyDetector->MakeImprint( worldLV, Tr );
```

The resulting detector will look as in Fig. 4.3.

# 4.1.7 Reflecting Hierarchies of Volumes

Hierarchies of placed or replicated volumes can be reflected by means of the G4ReflectionFactory class and G4ReflectedSolid, which implements a solid that has been shifted from its original reference frame to a new 'reflected' one. The reflection transformation is applied as a decomposition into rotation and translation transformations.

The factory is a singleton object which provides the following methods:

```
G4PhysicalVolumesPair Place(const G4Transform3D& transform3D,
                          const G4String&
                                               name,
                               G4LogicalVolume* LV,
                               G4LogicalVolume* motherLV,
                               G4bool
                                               isMany,
                                               copyNo,
                                G4int
                                G4bool
                                               surfCheck=false)
G4PhysicalVolumesPair Replicate(const G4String&
                                   G4LogicalVolume* LV,
                                   G4LogicalVolume* motherLV,
                                                   axis,
                                                  nofReplicas,
                                   G4int
                                   G4double
G4double
                                                   width,
                                                   offset=0)
G4PhysicalVolumesPair Divide(const G4String&
                                G4LogicalVolume* LV,
                                G4LogicalVolume* motherLV,
                                 EAxis
                                                axis,
                                G4int
                                                nofDivisions,
                                G4double
                                              width,
                                G4double offset);
```

The method Place () used for placements, evaluates the passed transformation. In case the transformation contains a reflection, the factory will act as follows:

1. Performs the transformation decomposition.




Fig. 4.3: The geometry corresponding to the Listing 4.7.

- Creates a new reflected solid and logical volume, or retrieves them from a map if the reflected object was already created.
- 3. Transforms the daughters (if any) and place them in the given mother.

If successful, the result is a pair of physical volumes, where the second physical volume is a placement in a reflected mother. Optionally, it is also possible to force the overlaps check at the time of placement, by activating the surfCheck flag.

The method Replicate () creates replicas in the given mother. If successful, the result is a pair of physical volumes, where the second physical volume is a replica in a reflected mother.

The method Divide () creates divisions in the given mother. If successful, the result is a pair of physical volumes, where the second physical volume is a division in a reflected mother. There exists also two more variants of this method which may specify or not width or number of divisions.

**Note:** In order to reflect hierarchies containing divided volumes, it is necessary to explicitly instantiate a concrete *division* factory -before- applying the actual reflection: (i.e. - G4PVDivisionFactory::GetInstance();).

**Note:** Reflection of generic parameterised volumes is currently not possible.

Listing 4.8: An example of usage of the G4ReflectionFactory class.

```
#include "G4ReflectionFactory.hh"
// Calor placement with rotation
G4double calThickness = 100 * cm;
G4double Xpos = calThickness*1.5;
G4RotationMatrix* rotD3 = new G4RotationMatrix();
rotD3->rotateY(10.*deg);
G4VPhysicalVolume* physiCalor =
                                                   // rotation
    new G4PVPlacement (rotD3,
                      G4ThreeVector(Xpos, 0., 0.), // at (Xpos, 0, 0)
                       logicCalor, // its logical volume (defined elsewhere)
                       "Calorimeter", // its name
                       false,
                       0);
// Calor reflection with rotation
G4Translate3D translation(-Xpos, 0., 0.);
G4Transform3D rotation = G4Rotate3D(*rotD3);
G4ReflectX3D reflection;
G4Transform3D transform = translation*rotation*reflection;
G4ReflectionFactory::Instance()
         ->Place(transform, // the transformation with reflection
                  "Calorimeter", // the actual name
                 logicCalor, // the logical volume
logicHall, // the mother volume
false, // no boolean operation
1, // copy number
false); // no overlap check triggered
// Replicate layers
G4ReflectionFactory::Instance()
        ->Replicate("Layer", // layer name
```

(continues on next page)

```
logicLayer, // layer logical volume (defined elsewhere)
logicCalor, // its mother
kXAxis, // axis of replication
5, // number of replica
20*cm); // width of replica
```

# 4.1.8 The Geometry Navigator

Navigation through the geometry at tracking time is implemented by the class G4Navigator. The navigator is used to locate points in the geometry and compute distances to geometry boundaries. At tracking time, the navigator is intended to be the only point of interaction with tracking.

Internally, the G4Navigator has several private helper/utility classes:

- **G4NavigationHistory** stores the compounded transformations, replication/parameterisation information, and volume pointers at each level of the hierarchy to the current location. The volume types at each level are also stored whether normal (placement), replicated or parameterised.
- **G4NormalNavigation** provides location & distance computation functions for geometries containing 'placement' volumes, with no voxels.
- G4VoxelNavigation provides location and distance computation functions for geometries containing 'placement' physical volumes with voxels. Internally a stack of voxel information is maintained. Private functions allow for isotropic distance computation to voxel boundaries and for computation of the 'next voxel' in a specified direction.
- **G4ParameterisedNavigation** provides location and distance computation functions for geometries containing parameterised volumes with voxels. Voxel information is maintained similarly to G4VoxelNavigation, but computation can also be simpler by adopting voxels to be one level deep only (*unrefined*, or 1D optimisation)
- G4ReplicaNavigation provides location and distance computation functions for replicated volumes.
- G4RegularNavigation provides location and distance computation functions for fast navigation in volumes
  containing a regular parameterisation. If two contiguous voxels have the same material, navigation does not stop
  at the surface.

In addition, the navigator maintains a set of flags for exiting/entry optimisation. A navigator is not a singleton class; this is mainly to allow a design extension in future (e.g. geometrical event biasing).

# **Navigation and Tracking**

The main functions required for tracking in the geometry are described below. Additional functions are provided to return the net transformation of volumes and for the creation of touchables. None of the functions implicitly requires that the geometry be described hierarchically.

#### SetWorldVolume()

Sets the first volume in the hierarchy. It must be unrotated and untranslated from the origin.

## • LocateGlobalPointAndSetup()

Locates the volume containing the specified global point. This involves a traverse of the hierarchy, requiring the computation of compound transformations, testing replicated and parameterised volumes (etc). To improve efficiency this search may be performed relative to the last, and this is the recommended way of calling the function. A 'relative' search may be used for the first call of the function which will result in the search defaulting to a search from the root node of the hierarchy. Searches may also be performed using a G4TouchableHistory.

#### • LocateGlobalPointAndUpdateTouchableHandle()

First, search the geometrical hierarchy like the above method LocateGlobalPointAndSetup(). Then use the volume found and its navigation history to update the touchable.

# • ComputeStep()

Computes the distance to the next boundary intersected along the specified unit direction from a specified point. The point must be have been located prior to calling ComputeStep ().

When calling ComputeStep(), a proposed physics step is passed. If it can be determined that the first intersection lies at or beyond that distance then kInfinity is returned. In any case, if the returned step is greater than the physics step, the physics step must be taken.

# • SetGeometricallyLimitedStep()

Informs the navigator that the last computed step was taken in its entirety. This enables entering/exiting optimisation, and should be called prior to calling LocateGlobalPointAndSetup().

#### • CreateTouchableHistory()

Creates a G4TouchableHistory object, for which the caller has deletion responsibility. The 'touchable' volume is the volume returned by the last Locate operation. The object includes a copy of the current NavigationHistory, enabling the efficient relocation of points in/close to the current volume in the hierarchy.

As stated previously, the navigator makes use of utility classes to perform location and step computation functions. The different navigation utilities manipulate the G4NavigationHistory object.

In LocateGlobalPointAndSetup () the process of locating a point breaks down into three main stages - optimisation, determination that the point is contained with a subtree (mother and daughters), and determination of the actual containing daughter. The latter two can be thought of as scanning first 'up' the hierarchy until a volume that is guaranteed to contain the point is found, and then scanning 'down' until the actual volume that contains the point is found.

In ComputeStep () three types of computation are treated depending on the current containing volume:

- The volume contains normal (placement) daughters (or none)
- The volume contains a single parameterised volume object, representing many volumes
- The volume is a replica and contains normal (placement) daughters

### Using the navigator to locate points

More than one navigator object can be created inside an application; these navigators can act independently for different purposes. The main navigator which is *activated* automatically at the startup of a simulation program is the navigator used for the *tracking* and attached the world volume of the main tracking (or *mass*) geometry.

The navigator for tracking can be retrieved at any state of the application by messaging the G4TransportationManager:

```
G4Navigator* tracking_navigator = G4TransportationManager::GetInstance()->GetNavigatorForTracking();
```

This also allows to retrieve at any time a pointer to the world volume assigned for tracking:

```
G4VPhysicalVolume* tracking_world = tracking_navigator->GetWorldVolume();
```

The navigator for tracking also retains all the information of the current history of volumes traversed at a precise moment of the tracking during a run. Therefore, if the navigator for tracking is used during tracking for locating a generic point in the tree of volumes, the actual particle gets also -relocated- in the specified position and tracking will be of course affected!

In order to avoid the problem above and provide information about location of a point without affecting the tracking, it is suggested to either use an alternative G4Navigator object (which can then be assigned to the world-volume), or access the information through the step.

If the user instantiates an alternative G4Navigator, ownership is retained by the user's code, and the navigator object should be deleted by that code.

#### Using the 'step' to retrieve geometrical information

During the tracking run, geometrical information can be retrieved through the touchable handle associated to the current step. For example, to identify the exact copy-number of a specific physical volume in the mass geometry, one should do the following:

```
// Given the pointer to the step object ...
//
G4Step* aStep = ..;

// ... retrieve the 'pre-step' point
//
G4StepPoint* preStepPoint = aStep->GetPreStepPoint();

// ... retrieve a touchable handle and access to the information
//
G4TouchableHandle theTouchable = preStepPoint->GetTouchableHandle();
G4int copyNo = theTouchable->GetCopyNumber();
G4int motherCopyNo = theTouchable->GetCopyNumber(1);
```

To determine the exact position in global coordinates in the mass geometry and convert to local coordinates (local to the current volume):

### Using an alternative navigator to locate points

In order to know (when in the idle state of the application) in which physical volume a given point is located in the detector geometry, it is necessary to create an alternative navigator object first and assign it to the world volume:

```
G4Navigator* aNavigator = new G4Navigator();
aNavigator->SetWorldVolume(worldVolumePointer);
```

Then, locate the point myPoint (defined in global coordinates), retrieve a *touchable handle* and do whatever you need with it:

If outside of the tracking run and given a generic local position (local to a given volume in the geometry tree), it is -not- possible to determine a priori its global position and convert it to the global coordinates system. The reason for this is rather simple, nobody can guarantee that the given (local) point is located in the right -copy- of the physical volume! In order to retrieve this information, some extra knowledge related to the absolute position of the physical volume is required first, i.e. one should first determine a global point belonging to that volume, eventually making a dedicated scan of the geometry tree through a dedicated G4Navigator object and then apply the method above after having created the touchable for it.

### **Navigation in parallel geometries**

Since release 8.2 of GEANT4, it is possible to define geometry trees which are parallel to the tracking geometry and having them assigned to navigator objects that transparently communicate in sync with the normal tracking geometry.

Parallel geometries can be defined for several uses (fast shower parameterisation, geometrical biasing, particle scoring, readout geometries, etc ...) and can *overlap* with the mass geometry defined for the tracking. The parallel transportation will be activated only after the registration of the parallel geometry in the detector description setup; see Section *Parallel Geometries* for how to define a parallel geometry and register it to the run-manager.

The G4TransportationManager provides all the utilities to verify, retrieve and activate the navigators associated to the various parallel geometries defined.

### Fast navigation in regular patterned geometries and phantoms

Since release 9.1 of GEANT4, a specialised navigation algorithm has been introduced to allow for optimal memory use and extremely efficient navigation in geometries represented by a regular pattern of volumes and particularly three-dimensional grids of boxes. A typical application of this kind is the case of DICOM phantoms for medical physics studies.

The class G4RegularNavigation is used and automatically activated when such geometries are defined. It is required to the user to implement a parameterisation of the kind G4PhantomParameterisation and place the parameterised volume containing it in a container volume, so that all cells in the three-dimensional grid (*voxels*) completely fill the container volume. This way the location of a point inside a voxel can be done in a fast way, transforming the position to the coordinate system of the container volume and doing a simple calculation of the kind:

```
copyNo_x = (localPoint.x()+fVoxelHalfX*fNoVoxelX) / (fVoxelHalfX*2.)
```

where fVoxelHalfX is the half dimension of the voxel along X and fNoVoxelX is the number of voxels in the X dimension. Voxel 0 will be the one closest to the corner (fVoxelHalfX\*fNoVoxelX, fVoxelHalfZ\*fNoVoxelZ).

Having the voxels filling completely the container volume allows to avoid the lengthy computation of ComputeStep() and ComputeSafety methods required in the traditional navigation algorithm. In this case, when a track is inside the parent volume, it has always to be inside one of the voxels and it will be only necessary to calculate the distance to the walls of the current voxel.

#### Skipping borders of voxels with same material

Another speed optimisation can be provided by skipping the frontiers of two voxels which the same material assigned, so that bigger steps can be done. This optimisation may be not very useful when the number of materials is very big (in which case the probability of having contiguous voxels with same material is reduced), or when the physical step is small compared to the voxel dimensions (very often the case of electrons). The optimisation can be switched off in such cases, by invoking the following method with argument skip = 0:

### Phantoms with only one material

If you want to describe a phantom of a unique material, you may spare some memory by not filling the set of indices of materials of each voxel. If the method SetMaterialIndices() is not invoked, the index for all voxels will be 0, that is the first (and unique) material in your list.

```
G4RegularParameterisation::SetSkipEqualMaterials( G4bool skip );
```

#### **Example**

To use the specialised navigation, it is required to first create an object of type G4PhantomParameterisation:

```
G4PhantomParameterisation* param = new G4PhantomParameterisation();
```

Then, fill it with the all the necessary data:

```
// Voxel dimensions in the three dimensions
G4double halfX = ...;
G4double halfY = ...;
G4double halfZ = ...;
param->SetVoxelDimensions( halfX, halfY, halfZ );
// Number of voxels in the three dimensions
G4int nVoxelX = ...;
G4int nVoxelY = ...;
G4int nVoxelZ = ...;
param->SetNoVoxel( nVoxelX, nVoxelY, nVoxelZ );
// Vector of materials of the voxels
std::vector < G4Material* > theMaterials;
theMaterials.push_back( new G4Material( ...
theMaterials.push_back( new G4Material( ...
param->SetMaterials (theMaterials);
// List of material indices
// For each voxel it is a number that correspond to the index of its
// material in the vector of materials defined above;
size_t* mateIDs = new size_t[nVoxelX*nVoxelY*nVoxelZ];
mateIDs[0] = n0;
mateIDs[1] = n1;
param->SetMaterialIndices( mateIDs );
```

Then, define the volume that contains all the voxels:

(continues on next page)

```
false, // No op. bool.
1); // Copy number
```

The physical volume should be assigned as the container volume of the parameterisation:

```
param->BuildContainerSolid(cont_phys);
// Assure that the voxels are completely filling the container volume
param->CheckVoxelsFillContainer( cont_solid->GetXHalfLength(),
                                    cont_solid->GetyHalfLength(),
                                    cont_solid->GetzHalfLength() );
// The parameterised volume which uses this parameterisation is placed
// in the container logical volume
G4PVParameterised * patient_phys =
 new G4PVParameterised("Patient",
                                                 // name
                       patient_logic,
                                                // mother volume
            kXAxis,
                                     // optimisation hint
                        nVoxelX*nVoxelY*nVoxelZ, // number of voxels
                                                  // parameterisation
                        param);
// Indicate that this physical volume is having a regular structure
patient_phys->SetRegularStructureId(1);
```

An example showing the application of the optimised navigation algorithm for phantoms geometries is available in examples/extended/medical/DICOM. It implements a real application for reading DICOM images and convert them to GEANT4 geometries with defined materials and densities, allowing for different implementation solutions to be chosen (non-optimised, classical 3D optimisation, nested parameterisations and use of G4PhantomParameterisation).

#### **Run-time commands**

When running in *verbose* mode (i.e. the default, G4VERBOSE set while installing the GEANT4 kernel libraries), the navigator provides a few commands to control its behavior. It is possible to select different verbosity levels (up to 5), with the command:

```
geometry/navigator/verbose [verbose_level]
```

or to force the navigator to run in *check* mode:

```
geometry/navigator/check_mode [true/false]
```

The latter will force more strict and less tolerant checks in step/safety computation to verify the correctness of the solids' response in the geometry.

By combining *check\_mode* with verbosity level-1, additional verbosity checks on the response from the solids can be activated.

### **Setting Geometry Tolerance to be relative**

The tolerance value defining the accuracy of tracking on the surfaces is by default set to a reasonably small value of *10E-9 mm*. Such accuracy may be however redundant for use on simulation of detectors of big size or macroscopic dimensions. Since release 9.0, it is possible to specify the surface tolerance to be relative to the extent of the world volume defined for containing the geometry setup.

The class G4GeometryManager can be used to activate the computation of the surface tolerance to be relative to the geometry setup which has been defined. It can be done this way:

```
G4GeometryManager::GetInstance()->SetWorldMaximumExtent(WorldExtent);
```

where, WorldExtent is the actual maximum extent of the world volume used for placing the whole geometry setup.

Such call to G4GeometryManager must be done before defining any geometrical component of the setup (solid shape or volume), and can be done only **once**!

The class G4GeometryTolerance is to be used for retrieving the actual values defined for tolerances, surface (Cartesian), angular or radial respectively:

```
G4GeometryTolerance::GetInstance()->GetSurfaceTolerance();
G4GeometryTolerance::GetInstance()->GetAngularTolerance();
G4GeometryTolerance::GetInstance()->GetRadialTolerance();
```

# 4.1.9 Converting Geometries from Geant3.21

### **Approach**

G3toG4 is the GEANT4 facility to convert GEANT 3.21 geometries into GEANT4. This is done in two stages:

- 1. The user supplies a GEANT 3.21 RZ-file (.rz) containing the initialization data structures. An executable rztog4 reads this file and produces an ASCII *call list* file containing instructions on how to build the geometry. The source code of rztog4 is FORTRAN.
- 2. A call list interpreter (G4BuildGeom.cc) reads these instructions and builds the geometry in the user's client code for GEANT4.

#### Importing converted geometries into GEANT4

Two examples of how to use the call list interpreter are supplied in the directory examples/extended/g3tog4:

- 1. cltog4 is a simple example which simply invokes the call list interpreter method G4BuildGeom from the G3toG4DetectorConstruction class, builds the geometry and exits.
- 2. clGeometry, is more complete and is patterned as for the basic GEANT4 examples. It also invokes the call list interpreter, but in addition, allows the geometry to be visualized and particles to be tracked.

To compile and build the G3toG4 libraries, you need to have enabled GEANT4\_USE\_G3TOG4 at the build configuration of GEANT4. The G3toG4 libraries are not built by default.

#### **Current Status**

The package has been tested with the geometries from experiments like: BaBar, CMS, Atlas, Alice, Zeus, L3, and Opal.

Here is a comprehensive list of features supported and not supported or implemented in the current version of the package:

- Supported shapes: all GEANT 3.21 shapes except for GTRA, CTUB.
- PGON, PCON are built using the *specific* solids G4Polycone and G4Polyhedra.
- GEANT 3.21 MANY feature is only partially supported. MANY positions are resolved in the G3toG4MANY() function, which has to be processed before G3toG4BuildTree() (it is not called by default). In order to resolve MANY, the user code has to provide additional info using G4gsbool(G4String volName, G4String manyVolName) function for all the overlapping volumes. Daughters of overlapping volumes are then resolved automatically and should not be specified via Gsbool.

**Limitation**: a volume with a MANY position can have only this one position; if more than one position is needed a new volume has to be defined (gsvolu()) for each position.

- GSDV\* routines for dividing volumes are implemented, using G4PVReplicas, for shapes:
  - BOX, TUBE, TUBS, PARA all axes;
  - CONE, CONS axes 2, 3;
  - TRD1, TRD2, TRAP axis 3;
  - PGON, PCON axis 2;
  - PARA -axis 1; axis 2,3 for a special case
- GSPOSP is implemented via individual logical volumes for each instantiation.
- GSROTM is implemented. Reflections of hierarchies based on plain CSG solids are implemented through the G3Division class.
- Hits are not implemented.
- Conversion of GEANT 3.21 magnetic field is currently not supported. However, the usage of magnetic field has to be turned on.

# 4.1.10 Detecting Overlapping Volumes

#### The problem of overlapping volumes

Volumes are often positioned within other volumes with the intent that one is fully contained within the other. If, however, a volume extends beyond the boundaries of its mother volume, it is defined as overlapping. It may also be intended that volumes are positioned within the same mother volume such that they do not intersect one another. When such volumes do intersect, they are also defined as overlapping.

The problem of detecting overlaps between volumes is bounded by the complexity of the solid model description. Hence it requires the same mathematical sophistication which is needed to describe the most complex solid topology, in general. However, a tunable accuracy can be obtained by approximating the solids via first and/or second order surfaces and checking their intersections.

In general, the most powerful clash detection algorithms are provided by CAD systems, treating the intersection between the solids in their topological form.

#### **Detecting overlaps at construction**

The GEANT4 geometry modeler provides the ability to detect overlaps of placed volumes (normal placements or parameterised) at the time of construction. This check is optional and can be activated when instantiating a placement (see G4PVPlacement constructor in *Placements: single positioned copy*) or a parameterised volume (see G4PVParameterised constructor in *Repeated volumes*).

The positioning of that specific volume will be checked against all volumes in the same hierarchy level and its mother volume. Depending on the complexity of the geometry being checked, the check may require considerable CPU time; it is therefore suggested to use it only for debugging the geometry setup and to apply it only to the part of the geometry setup which requires debugging.

The classes G4PVPlacement and G4PVParameterised also provide a method:

```
G4bool CheckOverlaps(G4int res=1000, G4double tol=0., G4bool verbose=true, G4int maxErr=1)
```

which will force the check for the specified volume, and can be therefore used to verify for overlaps also once the geometry is fully built. The check verifies if each placed or parameterised instance is overlapping with other instances or with its mother volume. A default resolution for the number of points to be generated and verified is provided. The method returns true if an overlap occurs. It is also possible to specify a "tolerance" by which overlaps not exceeding such quantity will not be reported and a maximum of overlaps errors for the volume; by default, one overlap per volume is reported.

#### Detecting overlaps: built-in kernel commands

Built-in run-time commands to activate verification tests for the user-defined geometry are also provided

```
geometry/test/run
--> to start verification of geometry for overlapping regions
   recursively through the volumes tree.
geometry/test/recursion_start [int]
--> to set the starting depth level in the volumes tree from where
   checking overlaps. Default is level '0' (i.e. the world volume).
   The new settings will then be applied to any recursive test run.
geometry/test/recursion_depth [int]
 -> to set the total depth in the volume tree for checking overlaps.
   Default is '-1' (i.e. checking the whole tree).
   Recursion will stop after having reached the specified depth (the
   default being the full depth of the geometry tree).
   The new settings will then be applied to any recursive test run.
geometry/test/tolerance [double] [unit]
--> to define tolerance by which overlaps should not be reported.
   Default is '0'.
geometry/test/verbosity [bool]
--> to set verbosity mode. Default is 'true'.
geometry/test/resolution [int]
--> to establish the number of points on surface to be generated
   and checked for each volume. Default is '10000'.
geometry/test/maximum_errors [int]
--> to fix the threshold for the number of errors to be reported
   for a single volume. By default, for each volume, reports stop
   after the first error reported.
```

To detect overlapping volumes, the built-in UI commands use the random generation of points on surface technique described above. It allows to detect with high level of precision any kind of overlaps, as depicted below. For example, consider Fig. 4.4:

Here we have a line intersecting some physical volume (large, black rectangle). Belonging to the volume are four daughters: A, B, C, and D. Indicated by the dots are the intersections of the line with the mother volume and the four daughters.




Fig. 4.4: Different cases of placed volumes overlapping each other.

This example has two geometry errors. First, volume A sticks outside its mother volume (this practice, sometimes used in GEANT3.21, is not allowed in GEANT4). This can be noticed because the intersection point (leftmost magenta dot) lies outside the mother volume, as defined by the space between the two black dots.

The second error is that daughter volumes A and B overlap. This is noticeable because one of the intersections with A (rightmost magenta dot) is inside the volume B, as defined as the space between the red dots. Alternatively, one of the intersections with B (leftmost red dot) is inside the volume A, as defined as the space between the magenta dots.

Another difficult issue is roundoff error. For example, daughters C and D lie precisely next to each other. It is possible, due to roundoff, that one of the intersections points will lie just slightly inside the space of the other. In addition, a volume that lies tightly up against the outside of its mother may have an intersection point that just slightly lies outside the mother.

Finally, notice that no mention is made of the possible daughter volumes of A, B, C, and D. To keep the code simple, only the immediate daughters of a volume are checked at one pass. To test these "granddaughter" volumes, the daughters A, B, C, and D each have to be tested themselves in turn. To make this automatic, a recursive algorithm is applied; it first tests the target volume, then it loops over all daughter volumes and calls itself.

Note: for a complex geometry, checking the entire volume hierarchy can be extremely time consuming.

### Using built-in visualisation features

See Debugging geometry with vis.

#### Using the visualization tool DAVID

The GEANT4 visualization offers also a debugging tool for detecting potential intersections of physical volumes. The GEANT4 DAVID visualization tool can automatically detect the overlaps between the volumes defined in GEANT4 and converted to a graphical representation for visualization purposes. The accuracy of the graphical representation can be tuned onto the exact geometrical description. In the debugging, physical-volume surfaces are automatically decomposed into 3D polygons, and intersections of the generated polygons are investigated. If a polygon intersects with another one, physical volumes which these polygons belong to are visualized in color (red is the default). The Fig. 4.5 figure below is a sample visualization of a detector geometry with intersecting physical volumes highlighted:

At present physical volumes made of the following solids can be debugged: G4Box, G4Cons, G4Para, G4Sphere, G4Trd, G4Trap, G4Tubs. (Existence of other solids is harmless.)

Visual debugging of physical-volume surfaces is performed with the DAWNFILE driver defined in the visualization category and with the two application packages, i.e. Fukui Renderer "DAWN" and a visual intersection debugger




Fig. 4.5: A geometry with overlapping volumes highlighted by DAVID.

"DAVID".

How to compile GEANT4 with the DAWNFILE driver incorporated is described in *The Visualization Drivers*.

If the DAWNFILE driver, DAWN and DAVID are all working well in your host machine, the visual intersection debugging of physical-volume surfaces can be performed as follows:

Run your GEANT4 executable, invoke the DAWNFILE driver, and execute visualization commands to visualize your detector geometry:

```
Idle> /vis/open DAWNFILE
.....(setting camera etc)...
Idle> /vis/drawVolume
Idle> /vis/viewer/update
```

Then a file "g4.prim", which describes the detector geometry, is generated in the current directory and DAVID is invoked to read it. (The description of the format of the file g4.prim can be found from the DAWN web site documentation.)

If DAVID detects intersection of physical-volume surfaces, it automatically invokes DAWN to visualize the detector geometry with the intersected physical volumes highlighted (See the above sample visualization).

If no intersection is detected, visualization is skipped and the following message is displayed on the console:

```
!!! Number of intersected volumes : 0 !!!
!!! Congratulations ! \(^o^)/ !!!
```

If you always want to skip visualization, set an environmental variable as follows beforehand:

```
% setenv DAVID_NO_VIEW 1
```

To control the precision associated to computation of intersections (default precision is set to 9), it is possible to use the environmental variable for the DAWNFILE graphics driver, as follows:

```
% setenv G4DAWNFILE_PRECISION 10
```

If necessary, re-visualize the detector geometry with intersected parts highlighted. The data are saved in a file "g4david.prim" in the current directory. This file can be re-visualized with DAWN as follows:

```
% dawn g4david.prim
```

It is also helpful to convert the generated file g4david.prim into a VRML-formatted file and perform interactive visualization of it with your WWW browser. The file conversion tool prim2wrml can be downloaded from the DAWN web site.

# 4.1.11 Dynamic Geometry Setups

GEANT4 can handle geometries which vary in time (e.g. a geometry varying between two runs in the same job).

It is considered a change to the geometry setup, whenever for the same physical volume:

- the shape or dimension of its related solid is modified;
- the positioning (translation or rotation) of the volume is changed;
- the volume (or a set of volumes, tree) is removed/replaced or added.

Whenever such a change happens, the geometry setup needs to be first "opened" for the change to be applied and afterwards "closed" for the optimisation to be reorganised.

In the general case, in order to notify the GEANT4 system of the change in the geometry setup, the G4RunManager has to be messaged once the new geometry setup has been finalised:

```
G4RunManager::GeometryHasBeenModified();
```

The above notification needs to be performed also if a material associated to a *positioned* volume is changed, in order to allow for the internal materials/cuts table to be updated. However, for relatively complex geometries the re-optimisation step may be extremely inefficient, since it has the effect that the whole geometry setup will be re-optimised and re-initialised. In cases where only a limited portion of the geometry has changed, it may be suitable to apply the re-optimisation only to the affected portion of the geometry (subtree).

Since release 7.1 of the GEANT4 toolkit, it is possible to apply re-optimisation local to the subtree of the geometry which has changed. The user will have to explicitly "open/close" the geometry providing a pointer to the top physical volume concerned:

Listing 4.9: Opening and closing a portion of the geometry without notifying the G4RunManager.

```
#include "G4GeometryManager.hh"

// Open geometry for the physical volume to be modified ...

//
G4GeometryManager::OpenGeometry(physCalor);

// Modify dimension of the solid ...

//
physCalor->GetLogicalVolume()->GetSolid()->SetXHalfLength(12.5*cm);

// Close geometry for the portion modified ...

//
G4GeometryManager::CloseGeometry(physCalor);
```

If the existing geometry setup is modified locally in more than one place, it may be convenient to apply such a technique only once, by specifying a physical volume on top of the hierarchy (subtree) containing all changed portions of the setup.

An alternative solution for dealing with dynamic geometries is to specify NOT to apply optimisation for the subtree affected by the change and apply the general solution of invoking the G4RunManager. In this case, a performance penalty at run-time may be observed (depending on the complexity of the not-optimised subtree), considering that, without optimisation, intersections to all volumes in the subtree will be explicitly computed each time.

Note: in multi-threaded runs, dynamic geometries are only allowed for runs consisting only of one event.

# 4.1.12 Importing XML Models Using GDML

Geometry Description Markup Language (GDML) is a markup language based on XML and suited for the description of detector geometry models. It allows for easy exchange of geometry data in a *human-readable* XML-based description and structured formatting.

The GDML parser is a component of GEANT4 which can be built and installed as an optional choice. It allows for importing and exporting GDML files, following the schema specified in the GDML documentation. The installation of the plugin is optional and requires the installation of the XercesC DOM parser.

Examples of how to import and export a detector description model based on GDML, and also how to extend the GDML schema, are provided and can be found in examples/extended/persistency/gdml.

# 4.1.13 Importing ASCII Text Models

Since release 9.2 of GEANT4, it is also possible to import geometry setups based on a plain text description, according to a well defined syntax for identifying the different geometrical entities (solids, volumes, materials and volume attributes) with associated parameters. An example showing how to define a geometry in plain text format and import it in a GEANT4 application is shown in examples/extended/persistency/P03. The example also covers the case of associating a sensitive detector to one of the volumes defined in the text geometry, the case of mixing C++ and text geometry definitions and the case of defining new tags in the text format so that regions and cuts by region can be defined in the text file. It also provides an example of how to write a geometry text file from the in-memory GEANT4 geometry. For the details on the format see the dedicated manual.

# 4.1.14 Saving geometry tree objects in binary format

The GEANT4 geometry tree can be stored in the Root binary file format using the *Root-I/O* technique provided by in Root. Such a binary file can then be used to quickly load the geometry into the memory or to move geometries between different GEANT4 applications.

See Object Persistency for details and references.

# 4.2 Material

#### 4.2.1 General considerations

In nature, materials (chemical compounds, mixtures) are made of elements, and elements are made of isotopes. GEANT4 has three main classes designed to reflect this organization. Each of these classes has a table, which is a static data member, used to keep track of the instances of the respective classes created.

**G4Isotope** This class describes the properties of atoms: atomic number, number of nucleons, mass per mole, etc. **G4Element** This class describes the properties of elements: effective atomic number, effective number of nucleons, effective mass per mole, number of isotopes, shell energy, and quantities like cross section per atom, etc.

**G4Material** This class describes the macroscopic properties of matter: density, state, temperature, pressure, and macroscopic quantities like radiation length, mean free path, dE/dx, etc.

Only the G4Material class is visible to the rest of the toolkit and used by the tracking, the geometry and the physics. It contains all the information relevant to its constituent elements and isotopes, while at the same time hiding their implementation details.

#### 4.2.2 Introduction to the Classes

#### **G4Isotope**

A G4Isotope object has a name, atomic number, number of nucleons, mass per mole, and an index in the table. The constructor automatically stores "this" isotope in the isotopes table, which will assign it an index number. The G4Isotope objects are owned by the isotopes table, and must not be deleted by user code.

4.2. Material 157

#### **G4Element**

A G4Element object has a name, symbol, effective atomic number, effective number of nucleons, effective mass of a mole, an index in the elements table, the number of isotopes, a vector of pointers to such isotopes, and a vector of relative abundances referring to such isotopes (where relative abundance means the number of atoms per volume). In addition, the class has methods to add, one by one, the isotopes which are to form the element.

The constructor automatically stores "this" element in the elements table, which will assign it an index number. The G4Element objects are owned by the elements table, and must not be deleted by user code.

A G4Element object can be constructed by directly providing the effective atomic number, effective number of nucleons, and effective mass of a mole, if the user explicitly wants to do so. Alternatively, a G4Element object can be constructed by declaring the number of isotopes of which it will be composed. The constructor will "new" a vector of pointers to G4Isotopes and a vector of doubles to store their relative abundances. Finally, the method to add an isotope must be invoked for each of the desired (pre-existing) isotope objects, providing their addresses and relative abundances. At the last isotope entry, the system will automatically compute the effective atomic number, effective number of nucleons and effective mass of a mole, and will store "this" element in the elements table.

A few quantities, with physical meaning or not, which are constant in a given element, are computed and stored here as "derived data members".

Using the internal GEANT4 database, a G4Element can be accessed by atomic number or by atomic symbol ("Al", "Fe", "Pb"...). In that case G4Element will be found from the list of existing elements or will be constructed using data from the GEANT4 database, which is derived from the NIST database of elements and isotope compositions. Thus, the natural isotope composition can be built by default. The same element can be created as using the NIST database with the natural composition of isotopes and from scratch in user code with user defined isotope composition.

#### **G4Material**

A G4Material object has a name, density, physical state, temperature and pressure (by default the standard conditions), the number of elements and a vector of pointers to such elements, a vector of the fraction of mass for each element, a vector of the atoms (or molecules) numbers of each element, and an index in the materials table. In addition, the class has methods to add, one by one, the elements which will comprise the material.

The constructor automatically stores "this" material in the materials table, which will assign it an index number. The G4Material objects are owned by the materials table, and must not be deleted by user code.

A G4Material object can be constructed by directly providing the resulting effective numbers, if the user explicitly wants to do so (an underlying element will be created with these numbers). Alternatively, a G4Material object can be constructed by declaring the number of elements of which it will be composed. The constructor will "new" a vector of pointers to G4Element and a vector of doubles to store their fraction of mass. Finally, the method to add an element must be invoked for each of the desired (pre-existing) element objects, providing their addresses and mass fractions. At the last element entry, the system will automatically compute the vector of the number of atoms of each element per volume, the total number of electrons per volume, and will store "this" material in the materials table. In the same way, a material can be constructed as a mixture of other materials and elements.

It should be noted that if the user provides the number of atoms (or molecules) for each element comprising the chemical compound, the system automatically computes the mass fraction. A few quantities, with physical meaning or not, which are constant in a given material, are computed and stored here as "derived data members".

Some materials are included in the internal GEANT4 database, which were derived from the NIST database of material properties. Additionally a number of materials frequently used in HEP is included in the database. Materials are interrogated or constructed by their *names* ( *Material Database*). There are UI commands for the material category, which provide an interactive access to the database. If material is created using the NIST database by it will consist by default of elements with the natural composition of isotopes.

#### **Final Considerations**

The classes will automatically decide if the total of the mass fractions is correct, and perform the necessary checks. The main reason why a fixed index is kept as a data member is that many cross section and energy tables will be built in the physics processes "by rows of materials (or elements, or even isotopes)". The tracking gives the physics process the address of a material object (the material of the current volume). If the material has an index according to which the cross section table has been built, then direct access is available when a number in such a table must be accessed. We get directly to the correct row, and the energy of the particle will tell us the column. Without such an index, every access to the cross section or energy tables would imply a search to get to the correct material's row. More details will be given in the section on processes.

Isotopes, elements and materials must be instantiated dynamically in the user application; they are automatically registered in internal stores and the system takes care to free the memory allocated at the end of the job.

# 4.2.3 Recipes for Building Elements and Materials

The Listing 4.10 illustrates the different ways to define materials.

Listing 4.10: A program which illustrates the different ways to define materials.

```
#include "G4Isotope.hh"
#include "G4Element.hh"
#include "G4Material.hh"
#include "G4UnitsTable.hh"
int main() {
                                 // a=mass of a mole;
G4String name, symbol;
G4double a, z, density;
                                  // z=mean number of protons;
                                   // iz=nb of protons in an isotope;
G4int iz, n;
                                   // n=nb of nucleons in an isotope;
G4int ncomponents, natoms;
G4double abundance, fractionmass;
G4double temperature, pressure;
G4UnitDefinition::BuildUnitsTable();
// define Elements
a = 1.01 * g/mole;
G4Element* elH = new G4Element(name="Hydrogen", symbol="H", z= 1., a);
a = 12.01 * g/mole;
G4Element* elC = new G4Element(name="Carbon", symbol="C", z= 6., a);
a = 14.01 \times g/mole:
G4Element* elN = new G4Element(name="Nitrogen", symbol="N", z= 7., a);
a = 16.00 * g/mole;
G4Element* el0 = new G4Element(name="Oxygen" , symbol="0" , z= 8., a);
a = 28.09 * q/mole;
G4Element* elSi = new G4Element(name="Silicon", symbol="Si", z=14., a);
a = 55.85 * g/mole;
G4Element* elFe = new G4Element(name="Iron" , symbol="Fe", z=26., a);
a = 183.84 * g/mole;
G4Element * elW = new G4Element (name="Tungsten", symbol="W", z=74., a);
a = 207.20 * q/mole;
G4Element * elPb = new G4Element (name="Lead"
                                               ,symbol="Pb", z=82., a);
```

(continues on next page)

4.2. Material 159

```
// define an Element from isotopes, by relative abundance
G4Isotope* U5 = new G4Isotope(name="U235", iz=92, n=235, a=235.01*g/mole);
G4Isotope* U8 = new G4Isotope(name="U238", iz=92, n=238, a=238.03*g/mole);

G4Element* elU = new G4Element(name="enriched Uranium", symbol="U", ncomponents=2);
elU->AddIsotope(U5, abundance= 90.*perCent);
elU->AddIsotope(U8, abundance= 10.*perCent);

G4cout << *(G4Isotope::GetIsotopeTable()) << G4endl;
G4cout << *(G4Element::GetElementTable()) << G4endl;</pre>
```

```
// define simple materials
density = 2.700*g/cm3;
a = 26.98 * g/mole;
G4Material* Al = new G4Material(name="Aluminum", z=13., a, density);
density = 1.390*q/cm3;
a = 39.95 * g/mole;
G4Material* lAr = new G4Material(name="liquidArgon", z=18., a, density);
density = 8.960 \times g/cm3;
a = 63.55 * g/mole;
G4Material* Cu = new G4Material(name="Copper" , z=29., a, density);
// define a material from elements. case 1: chemical molecule
density = 1.000*g/cm3;
G4Material* H2O = new G4Material(name="Water", density, ncomponents=2);
H2O->AddElement(elH, natoms=2);
H2O->AddElement(elO, natoms=1);
density = 1.032 \times g/cm3;
G4Material* Sci = new G4Material (name="Scintillator", density, ncomponents=2);
Sci->AddElement(elC, natoms=9);
Sci->AddElement(elH, natoms=10);
density = 2.200*g/cm3;
G4Material* SiO2 = new G4Material(name="quartz", density, ncomponents=2);
SiO2->AddElement(elSi, natoms=1);
SiO2->AddElement(elO , natoms=2);
density = 8.280*g/cm3;
G4Material* PbWO4= new G4Material(name="PbWO4", density, ncomponents=3);
PbWO4->AddElement(elO , natoms=4);
PbWO4->AddElement(elW , natoms=1);
PbWO4->AddElement(elPb, natoms=1);
// define a material from elements. case 2: mixture by fractional mass
density = 1.290 \times mg/cm3;
G4Material* Air = new G4Material(name="Air", density, ncomponents=2);
Air->AddElement(elN, fractionmass=0.7);
Air->AddElement(elO, fractionmass=0.3);
// define a material from elements and/or others materials (mixture of mixtures)
density = 0.200 \times g/cm3;
G4Material* Aerog = new G4Material(name="Aerogel", density, ncomponents=3);
Aerog->AddMaterial(SiO2, fractionmass=62.5*perCent);
Aerog->AddMaterial(H2O , fractionmass=37.4*perCent);
Aerog->AddElement (elC , fractionmass= 0.1*perCent);
```

```
// examples of gas in non STP conditions
density = 27.*mg/cm3;
pressure = 50.*atmosphere;
temperature = 325.*kelvin;
G4Material* CO2 = new G4Material(name="Carbonic gas", density, ncomponents=2,
```

(continues on next page)

```
kStateGas, temperature, pressure);
CO2->AddElement(elC, natoms=1);
CO2->AddElement(elO, natoms=2);
density
           = 0.3 \times mg/cm3;
pressure = 2.*atmosphere;
temperature = 500.*kelvin;
G4Material* steam = new G4Material(name="Water steam", density, ncomponents=1,
                                       kStateGas, temperature, pressure);
steam->AddMaterial(H2O, fractionmass=1.);
// What about vacuum ? Vacuum is an ordinary gas with very low density
density = universe_mean_density;
pressure = 1.e-19*pascal;
temperature = 0.1*kelvin;
new G4Material(name="Galactic", z=1., a=1.01*g/mole, density,
                   kStateGas, temperature, pressure);
density
           = 1.e-5*g/cm3;
pressure = 2.e-2*bar;
temperature = STP_Temperature;
                                                      //from PhysicalConstants.h
G4Material* beam = new G4Material(name="Beam", density, ncomponents=1,
                                       kStateGas, temperature, pressure);
beam->AddMaterial(Air, fractionmass=1.);
// print the table of materials
G4cout << *(G4Material::GetMaterialTable()) << G4endl;
return EXIT_SUCCESS;
```

As can be seen in the later examples, a material has a state: solid (the default), liquid, or gas. The constructor checks the density and automatically sets the state to gas below a given threshold (10 mg/cm3).

In the case of a gas, one may specify the temperature and pressure. The defaults are STP conditions defined in PhysicalConstants.hh.

An element must have the number of nucleons  $\geq$  number of protons  $\geq$  1.

A material must have non-zero values of density, temperature and pressure.

Materials can also be defined using the internal GEANT4 database. Listing 4.11 illustrates how to do this for the same materials used in Listing 4.10. There are also UI commands which allow the database to be accessed. *The list of currently available material names (Material Database)* is extended permanently.

Listing 4.11: A program which shows how to define materials from the internal database.

```
#include "globals.hh"
#include "G4Material.hh"
#include "G4NistManager.hh"

int main() {
   G4NistManager* man = G4NistManager::Instance();
   man->SetVerbose(1);

   // define elements
   G4Element* C = man->FindOrBuildElement("C");
   G4Element* Pb = man->FindOrBuildMaterial("Pb");

   // define pure NIST materials
   G4Material* Al = man->FindOrBuildMaterial("G4_Al");
   G4Material* Cu = man->FindOrBuildMaterial("G4_Cu");

   (continues on next page)
```

4.2. Material 161

```
// define NIST materials
G4Material* H2O = man->FindOrBuildMaterial("G4_WATER");
G4Material* Sci = man->FindOrBuildMaterial("G4_PLASTIC_SC_VINYLTOLUENE");
G4Material* SiO2 = man->FindOrBuildMaterial("G4_SILICON_DIOXIDE");
G4Material* Air = man->FindOrBuildMaterial("G4_AIR");

// HEP materials
G4Material* PbWO4 = man->FindOrBuildMaterial("G4_AIR");
G4Material* lAr = man->FindOrBuildMaterial("G4_IAr");
G4Material* vac = man->FindOrBuildMaterial("G4_Galactic");

// define gas material at non STP conditions (T = 120K, P=0.5atm)
G4Material* coldAr = man->ConstructNewGasdMaterial("ColdAr", "G4_Ar", 120.*kelvin, 0.

$\times 5*\text{atmosphere}$;

// print the table of materials
G4cout << *(G4Material::GetMaterialTable()) << G4endl;

return EXIT_SUCCESS;
}</pre>
```

# 4.2.4 The Tables

### Print a constituent

The following shows how to print a constituent:

```
G4cout << elU << G4endl;
G4cout << Air << G4endl;
```

#### Print the table of materials

The following shows how to print the table of materials:

```
G4cout << *(G4Material::GetMaterialTable()) << G4endl;
```

# 4.3 Electromagnetic Field

# 4.3.1 An Overview of Propagation in a Field

GEANT4 is capable of describing and propagating in a variety of fields. Magnetic fields, electric fields, electromagnetic fields, and gravity fields, uniform or non-uniform, can specified for a GEANT4 setup. The propagation of tracks inside them can be performed to a user-defined accuracy.

In order to propagate a track inside a field, the equation of motion of the particle in the field is integrated. In general, this is done using a Runge-Kutta method for the integration of ordinary differential equations. However, for specific cases where an analytical solution is known, it is possible to utilize this instead. Several Runge-Kutta methods are available, suitable for different conditions. In specific cases (such as a uniform field where the analytical solution is known) different solvers can also be used. In addition, when an approximate analytical solution is known, it is possible to utilize it in an iterative manner in order to converge to the solution to the precision required. This latter method is currently implemented and can be used particularly well for magnetic fields that are almost uniform.

Once a method is chosen that calculates the track's propagation in a specific field, the curved path is broken up into linear chord segments. These chord segments are determined so that they closely approximate the curved path. The

chords are then used to interrogate the Navigator as to whether the track has crossed a volume boundary. Several parameters are available to adjust the accuracy of the integration and the subsequent interrogation of the model geometry.

How closely the set of chords approximates a curved trajectory is governed by a parameter called the *miss distance* (also called the *chord distance*). This is an upper bound for the value of the sagitta - the distance between the 'real' curved trajectory and the approximate linear trajectory of the chord. By setting this parameter, the user can control the precision of the volume interrogation. Every attempt has been made to ensure that all volume interrogations will be made to an accuracy within this *miss distance*.




Fig. 4.6: The curved trajectory will be approximated by chords, so that the maximum estimated distance and chord is less than the *miss distance*.

In addition to the *miss distance* there are two more parameters which the user can set in order to adjust the accuracy (and performance) of tracking in a field. In particular these parameters govern the accuracy of the intersection with a volume boundary and the accuracy of the integration of other steps. As such they play an important role for tracking.

The *delta intersection* parameter is the accuracy to which an intersection with a volume boundary is calculated. If a candidate boundary intersection is estimated to have a precision better than this, it is accepted. This parameter is especially important because it is used to limit a bias that our algorithm (for boundary crossing in a field) exhibits. This algorithm calculates the intersection with a volume boundary using a chord between two points on the curved particle trajectory. As such, the intersection point is always on the 'inside' of the curve. By setting a value for this parameter that is much smaller than some acceptable error, the user can limit the effect of this bias on, for example, the future estimation of the reconstructed particle momentum.

The *delta one step* parameter is the accuracy for the endpoint of 'ordinary' integration steps, those which do not intersect a volume boundary. This parameter is a limit on the estimated error of the endpoint of each physics step. It can be seen as akin to a statistical uncertainty and is not expected to contribute any systematic behavior to physical quantities. In contrast, the bias addressed by *delta intersection* is clearly correlated with potential systematic errors in the momentum of reconstructed tracks. Thus very strict limits on the intersection parameter should be used in tracking detectors or wherever the intersections are used to reconstruct a track's momentum.

Delta intersection and delta one step are parameters of the Field Manager; the user can set them according to the demands of his application. Because it is possible to use more than one field manager, different values can be set for different detector regions.

Note that reasonable values for the two parameters are strongly coupled: it does not make sense to request an accuracy of 1 nm for *delta intersection* and accept 100  $\mu$ m for the *delta one step* error value. Nevertheless *delta intersection* is the more important of the two. It is recommended that these parameters should not differ significantly - certainly not by more than an order of magnitude.




Fig. 4.7: The distance between the calculated chord intersection point C and a computed curve point D is used to determine whether C is an accurate representation of the intersection of the curved path ADB with a volume boundary. Here CD is likely too large, and a new intersection on the chord AD will be calculated.

# 4.3.2 Practical Aspects

### Creating a Magnetic Field for a Detector

The simplest way to define a field for a detector involves the following steps:

1. create a field. It can be uniform

```
#include "G4SystemOfUnits.hh"

G4MagneticField *magField;
magField = new G4UniformMagField(G4ThreeVector(0.,0.,3.0*kilogauss));
```

or non-uniform:

```
magField = new G4QuadrupoleMagField( 1.*tesla/(1.*meter) );
```

2. set it as the default field:

```
G4FieldManager* fieldMgr
= G4TransportationManager::GetTransportationManager()
    ->GetFieldManager();
fieldMgr->SetDetectorField(magField);
```

3. create the objects which calculate the trajectory for a pure magnetic field,:

```
fieldMgr->CreateChordFinder(magField);
```

This is a short cut, which creates all the equation of motion, a method for integration (Runge-Kutta stepper) and the driver which controls the integration and limits its estimated error.

#### Creating a Uniform Magnetic Field with user commands

Since 10.0 version, it is also possible to create a uniform magnetic field and perform the other two steps above the G4GlobalMagFieldMessenger class:

```
G4ThreeVector fieldValue = G4ThreeVector(0.,0.,fieldValue);
fMagFieldMessenger = new G4GlobalMagFieldMessenger(fieldValue);
fMagFieldMessenger->SetVerboseLevel(1);
```

The messenger creates the global uniform magnetic field, which is activated (set to the G4TransportationManager object) only when the fieldValue is non zero vector. The messenger class setter functions can be then used to change the field value (and activate or inactivate the field again) or the level of output messages. The messenger also takes care of deleting the field.

As its class name suggests, the messenger creates also UI commands which can be used to change the field value and the verbose level interactively or from a macro:

```
/globalField/setValue vx vy vz unit
/globalField/verbose level
```

#### Creating a Field for a Part of the Volume Hierarchy

It is possible to create a field for a part of the detector. In particular it can describe the field (with pointer pEmField, for example) inside a logical volume and all its daughters. This can be done by simply creating a G4FieldManager and attaching it to a logical volume (with pointer, logicVolumeWithField, for example) or set of logical volumes.

```
G4bool allLocal = true;
logicVolumeWithField->SetFieldManager(localFieldManager, allLocal);
```

Using the second parameter to SetFieldManager you choose whether daughter volumes of this logical volume will also be given this new field. If it has the value true, the field will be assigned also to its daughters, and all their sub-volumes. Else, if it is false, it will be copied only to those daughter volumes which do not have a field manager already, and recursively to their sub-volumes without a field manager.

# Creating an Electric or Electromagnetic Field

The design and implementation of the *Field* category allows and enables the use of an electric or combined electromagnetic field. These fields can also vary with time, as can magnetic fields.

Source listing Listing 4.12 shows how to define a uniform electric field for the whole of a detector.

Listing 4.12: How to define a uniform electric field for the whole of a detector, extracted from example in examples/extended/field/field02.

```
// in the header file (or first)
#include "G4EqMagElectricField.hh"
#include "G4UniformElectricField.hh"
#include "G4DormandPrince745.hh"
G4ElectricField* pEMfield;
G4EqMagElectricField* pEquation;
                       pChordFinder ;
G4ChordFinder*
// in the source file
  pEMfield = new G4UniformElectricField(
               G4ThreeVector(0.0,100000.0*kilovolt/cm,0.0));
  // Create an equation of motion for this field
  pEquation = new G4EqMagElectricField(pEMfield);
  G4int nvar = 8;
  // Create the Runge-Kutta 'stepper' using the efficient 'DoPri5' method
  auto pStepper = new G4DormandPrince745( pEquation, nvar );
  // Get the global field manager
  auto fieldManager= G4TransportationManager::GetTransportationManager()->
       GetFieldManager();
  // Set this field to the global field manager
  fieldManager->SetDetectorField( pEMfield );
  G4double minStep
                    = 0.010*mm ; // minimal step of 10 microns
  // The driver will ensure that integration is control to give
  // acceptable integration error
  auto pIntgrationDriver =
     new G4IntegrationDriver<G4DormandPrince745> (minStep,
                                                  pStepper,
                                                  nvar);
```

(continues on next page)

```
pChordFinder = new G4ChordFinder(pIntgrationDriver);
fieldManager->SetChordFinder( pChordFinder );
}
```

An example with an electric field is examples/extended/field/field02, where the class F02ElectricFieldSetup demonstrates how to set these and other parameters, and how to choose different Integration Steppers. An example with a uniform gravity field (G4UniformGravityField) is examples/extended/field/field06.

Note that using gravity since Geant4 10.6 it is necessary to enable it in the transportation process(es) used in the simulation. (This is in order to enable optimisations which are possible only in its absence.)

The user can also create their own type of field, inheriting from G4VField, and an associated Equation of Motion class (inheriting from G4EqRhs) to simulate other types of fields.

### How to Adjust the Accuracy of hitting a volume

Straight-line chord segments are used to detect volume boundary crossing. The curved trajectory is broken up into such segments using an accuracy parameter <code>DeltaChord</code>. Segments much be chosene so that their 'sagitta', the maximum distance between the curve and chord, is smaller than <code>DeltaChord</code>. So effectively this is the maximum distance by which a volume that should be intersected could be missed.

To change the accuracy of the approximation of the curved trajectory by linear segments, use the SetDeltaChord method:

```
fieldMgr->GetChordFinder()->SetDeltaChord( dcLength ); // Units: length
```

Geant4 propagation will seek ensure that any volume within dcLenght from the curved trajectory will be intersected.

## **How to Adjust the Integration Accuracy**

In order to obtain a particular accuracy in tracking particles through an electromagnetic field, it is necessary to adjust the parameters of the field propagation module. In the following section, some of these additional parameters are discussed.

When integration is used to calculate the trajectory, it is necessary to determine an acceptable level of numerical imprecision in order to get performant simulation with acceptable errors. The parameters in GEANT4 tell the field module what level of integration inaccuracy is acceptable.

In all quantities which are integrated (position, momentum, energy) there will be errors. Here, however, we focus on the error in two key quantities: the position and the momentum. (The error in the energy will come from the momentum integration).

Three parameters exist which are relevant to the integration accuracy. DeltaOneStep is a distance and is roughly the position error which is acceptable in an integration step. Since many integration steps may be required for a single physics step, DeltaOneStep should be a fraction of the average physics step size. The next two parameters impose a further limit on the relative error of the position/momentum inaccuracy. EpsilonMin and EpsilonMax impose a minimum and maximum on this relative error - and take precedence over DeltaOneStep. (Note: if you set EpsilonMin=EpsilonMax=your-value, then all steps will be made to this relative precision.

Listing 4.13: How to set accuracy parameters for the 'global' field of the setup.

We note that the relevant parameters above limit the inaccuracy in each step. The final inaccuracy due to the full trajectory will accumulate!

The exact point at which a track crosses a boundary is also calculated with finite accuracy. To limit this inaccuracy, a parameter called DeltaIntersection is used. This is a maximum for the inaccuracy of a single boundary crossing. Thus the accuracy of the position of the track after a number of boundary crossings is directly proportional to the number of boundaries.

# Full control of integration method for a magnetic field

You can instead specify explicitly the full set of classes for propagating in a magnetic field. This provides full control over the method of integration, and allows the choice of higher or lower order methods. It also all you to select the use of methods which used to be the default choice in the past (e.g. G4ClassicalRungeRK4 or G4DormandPrince745 without using interpolation.)

**The classes required are the equation of motion::** auto pEquation = new G4Mag\_UsualEqRhs(magField); G4int nVar= pEquation->GetNumberOfVariables();

the method of integration (stepper):: auto pStepper = new G4DormandPrince745( pEquation ); the driver to control the accuracy of integration::

auto driver= G4InterpolationDriver<G4DormandPrince745>(minStep,pStepper, nvar);

or alternatively a driver without interpolation::

auto driver= G4IntegrationDriver<typeof(pStepper)>(minStep,pStepper, nvar);
and the chord finder:: auto chordFinder = new G4ChordFinder( driver );

#### **Choosing a Stepper**

Runge-Kutta integration is used to compute the motion of a charged track in a general field. There are many general steppers from which to choose, of low and high order, and specialized steppers for pure magnetic fields. By default, GEANT4 uses the established stepper of Dormand and Prince Runge-Kutta stepper, which is general purpose, efficient and robust. It is a 5th order method which provides an error estimate directly, and requires fewer evaluations of the derivative (and field) than the previous default, the classical 4th order method (for which an error estimate required multiple sub-steps).

For somewhat smooth fields, which change smoothly over the length scales of typical physics steps, there is choice between fifth order steppers (such as the default G4DormandPrince745):

```
G4int nvar = 8; // To integrate time & energy
// in addition to position, momentum

G4EqMagElectricField* pEquation= new G4EqMagElectricField(pEMfield);

auto doPri5stepper = new G4DormandPrince745( pEquation, nvar );
// The recommended stepper, well suited for reasonably smooth fields
// and intermediate accuracy requirements ( 10^-4 to 10^-7 )
```

Alternative fifth order embedded steppers beside the recommended and default G4DormandPrince745 which requires 7 field evaluations (stages) include the older G4CashKarpRKF45 which requires fewer field evaluations (6 'stages')

```
auto CK45stepper = new G4CashKarpRKF45( pEquation, nvar );
   // Alternative 4/5th order stepper for reasonably smooth fields
```

The newest experimental classes G4BogackiShampine45 or G4TsitourasRK45 implement some of the most efficient fifth order methods in the literature, but require an additional derivative (field evaluation) per step.:

```
auto BS45stepper = new G4BogackiShampine45( pEquation, nvar );
    // Alternative 4/5th order stepper with 8 stages (evaluations).
```

If there are particularly challenging accuracy demands (better than 1e-7) it may be worth to investigate higher order steppers. Alternatively, if the field is known to have specific properties, lower or higher order steppers can be used to obtain the results of the necessary accuracy using fewer computing cycles.

Since Geant4 10.5 it is recommended to use the templated driver G4IntegrationDriver together with the stepper:

```
auto dp45driver =
  new G4IntegrationDriver<G4DormandPrince745>(stepMin, doPri5stepper, nvar);
```

### Steppers for rough fields

Sometimes the field changes greatly over short distances, and is estimated in ways that do not ensure that its derivatives are smooth. These can present a challenge for fourth or fifth order Runge-Kutta methods.

What matters is the variation of the field in geometrical regions in which a large fraction of particles are tracked. In particular, if the field is calculated from a field map and it varies significantly and in a non-smooth way over short distances in important regions, it is suggested to investigate a lower order stepper.

Steppers of reduced order are also suitable when lower accuracy is required, such as errors of order 10<sup>-3</sup>. Such accuracy could be suitable for the least important tracks, such as low energy electrons near the end of their trajectory (but still inside material.)

Steppers of reduced order require fewer derivative evaluations per step. The choice of lower order steppers includes the third order embedded stepper G4BogackiShampine23, which provides a direct error estimate.:

```
auto stepper = new G4BogackiShampine23( pEquation, nvar );
// 3rd order embbedded stepper
// Suitable for lower accuracy needs (<~ 10^-3) and/or 'rough' fields</pre>
```

Older type steppers, which do not provide a direct error estimate, offer an alternative for the roughest fields. ( Note: these methods estimate the error in a step by subdividing it into two smaller steps and using the difference between the new estimate and the estimate for the whole step as the estimated error. )

The recommended ones are the fourth order G4ClassicalRK4, which was the default in releases of GEANT4 up to 10.3, and is very robust:

```
pStepper = new ClassicalRK4( pEquation, nvar );
    // 4th order, the old default - a robust alternative
```

the third order stepper G4SimpleHeum, and the second order steppers G4ImplicitEuler and G4SimpleRunge.:

```
pStepper = new G4SimpleHeum( pEquation, nvar );
    // 3rd order robust alternative for low accuracy and/or rought fields

pStepper = new G4SimpleRunge( pEquation, nvar );
    // 2nd order, for very rough (non-smooth) fields
```

A first order stepper is not recommended, but may be used only for the roughest fields, as a cross check for other higher performance methods.

For somewhat smooth fields (intermediate), the choice between a fifth order stepper (such as the default G4DormandPrince745):

```
pStepper = new G4DormandPrince745( pEquation, nvar );
   // The recommended stepper, well suited for reasonably smooth fields
```

embedded third, the older type second or third order steppers, or the established fourth order G4ClassicalRK4 or should be made by trial and error.

Trying a few different types of steppers for a particular field or application is suggested if maximum performance is a goal.

The choice of stepper depends on the type of field: magnetic or general. A general field can be an electric or electromagnetic field, it can be a magnetic field or a user-defined field (which requires a user-defined equation of motion.)

For a general field all the above steppers are potential alternatives to the recommended / default G4DormandPrince745.

But specialized steppers for pure magnetic fields are also available. The G4NystromRK4 stepper is a fourth order method which estimates the integration error in a step directly from the variation of the field at the initial point, the midpoint and near the endpoint of the step. Thus it requires no additional evaluations (stages.):

```
G4Mag_UsualEqRhs*
    pEquation = new G4Mag_UsualEqRhs(fMagneticField);
pStepper = new G4NystromRK4( pEquation );
```

Others take into account the fact that a local trajectory in a slowly varying field will not vary significantly from a helix. Combining this in with a variation the Runge-Kutta method can provide higher accuracy at lower computational cost when large steps are possible.

```
pStepper = new G4HelixImplicitEuler( pEquation );
// Note that for magnetic field that do not vary with time,
// the default number of variables suffices.

// or ..
pStepper = new G4HelixExplicitEuler( pEquation );
pStepper = new G4HelixSimpleRunge( pEquation );
```

A new stepper for propagation in magnetic field is available in release 9.3. Choosing the G4NystromRK4 stepper provides accuracy near that of G4ClassicalRK4 (4th order) with a significantly reduced cost in field evaluation. Using a novel analytical expression for estimating the error of a proposed step and the Nystrom reuse of the mid-point field value, it requires only 2 additional field evaluations per attempted step, in place of 10 field evaluations of ClassicalRK4 (which uses the general midpoint method for estimating the step error.)

```
G4Mag_UsualEqRhs*
   pMagFldEquation = new G4Mag_UsualEqRhs(fMagneticField);
pStepper = new G4NystromRK4( pMagFldEquation );
```

It is proposed as an alternative stepper in the case of a pure magnetic field. It is not applicable for the simulation of electric or full electromagnetic or other types of field. For a pure magnetic field, results should be fully compatible with the results of ClassicalRK4 in nearly all cases. (The only potential exceptions are large steps for tracks with small momenta - which cannot be integrated well by any RK method except the Helical extended methods.)

You can choose an alternative stepper either when the field manager is constructed or later. At the construction of the ChordFinder it is an optional argument:

To change the stepper at a later time use

### Increasing efficiency with interpolation and FSAL stepper

Often a significant fraction of CPU time is spent in integrating the motion of charged particles in field. This is particularly the case when the cost of evaluating the field at a location (and possibly time) is significant. To improve on this developments over the past years have introduced methods that require fewer field evaluations for the same overall accuracy.

New in GEANT4 10.6 is the ability to full use of the newest RK methods, which have an interpolation capability. Such Runge-Kutta methods provide an interpolation polynomial which can be evaluated to estimate the values of all integrated variables at an arbitrary intermediate length in the integration interval.

Both these interpolation capabilities are harnessed by the new type of integration driver G4InterpolationDriver. Currently this combination is available only with the G4DormandPrince745 stepper.

GEANT4 10.4 introduced the capability to use RK methods with the 'First Same as Last' (FSAL) property. Embedded steppers with this property evaluate the field and the derivative in the equation of motion at the endpoint of each step, as an intrinsic part of the method. As a result, after a successful integration step, (one in which the estimated error was acceptable) the derivative at the start of the next step is already available. So one evaluation of the field is saved for every successive integration interval after the first one in each tracking/physical step.

Since GEANT4 10.6 an FSAL capable stepper can be selected for magnetic fields simply by requesting it when constructing a G4ChordFinder:

```
G4MagneticField * pMagField;
G4double stepMinimum = 0.03 * millimeter;
G4int useFSALstp= 1;

auto pChordFinder= new G4ChordFinder( pMagField, stepMinimum, nullptr, useFSALstp );
fieldManager->SetChordFinder( pChordFinder);
```

#### Handling very long steps by switching to helix based stepper

Very long steps of lower energy charged particles can cause excessive simulation time when regular Runge-Kutta methods are used – as these can integrate only a limited angle of a helical track in a single integration step.

This can be a problem for setups in which there is a significant fraction of tracks of low-energy charged particles in a volume with vaccum or a thin gas. In addition integration slowdown or abandoned tracks can occur when muons are tracked in a large air volume with even a fringe magnetic field.

For these setups an alternative type of driver specialised for pure magnetic fields was created. It combines an Interpolation stepper / driver for 'shorter' steps, and a helix-based method for 'long' steps.

It samples the magnetic field at the start of a step, and selects the 'long' step integration method if the helix angle exceed the threshold, currently fixed at 2 pi.

This type of driver G4BFieldIntegrationDriver was the default driver created by G4ChordFinder in Geant4 10.6 for pure magnetic fields.

```
G4MagneticField * pMagField;

G4double stepMinimum = 0.03 * millimeter;

G4bool useFSALstp= false;

auto pChordFinder= new G4ChordFinder( pMagField, stepMinimum, nullptr, useFSALstp );

fieldManager->SetChordFinder( pChordFinder);
```

In Geant4 10.7 the default has changed to use an interpolation driver with templated steppers (see next subsection).

As a result, to select it G4BFieldIntegrationDriver in Geant4 10.7 a user must use:

```
G4int driverId = 3; // B-Field driver = 3
auto pChordFinder= new G4ChordFinder( pMagField, stepMinimum, nullptr, driverId );
fieldManager->SetChordFinder( pChordFinder );
```

It can also be created directly

#### Speeding up using steppers templated on equation

To reduce the CPU time of field propagation in Geant4 10.7 an equation class for magnetic fields and some templated stepper classes were created.

The first optimisation is that the templated equation knows the type of the field class:

```
using Equation_t = G4TMagFieldEquation<Field_class_type>;
Equation_t* equation= new Equation_t(field_object);
```

Given the field class' type, the equation will invoke the field without a virtual call. The relevant include files are:

```
#include "G4TMagFieldEquation.hh"
#include "G4TDormandPrince45.hh"

// For field definition
#include "G4SystemOfUnits.hh"
#include "G4QuadrupoleMagField.hh"
```

To create the templated equation it is simpler to declare each class' type first:

```
using Field_t = G4QuadrupoleMagField;
using Equation_t = G4TMagFieldEquation<Field_t>;

Field_t* quadMagField = new G4QuadrupoleMagField(1.*tesla/(1.*meter));

Equation_t* equation = new Equation_t (quadMagField);
```

but it can also be created directly such as

```
auto equation= new G4TMagFieldEquation<G4QuadrupoleMagField>(quadMagField);
```

The second optimisation makes the type of the equation known to the templated stepper. This avoid a virtual call from the stepper to the equation.

```
using TemplatedStepper_t = G4TDormandPrince45<Equation_t>;

TemplatedStepper_t* dopri5_stepper=
   new G4TDormandPrince45<Equation_t>( equation );
```

Here G4TDormandPrince45 is the templated version of the recommended G4DormandPrince745 stepper that implements the well known 4th/5th order embedded Runge-Kutta method of Dormand and Prince.

Alternative methods which have a templated stepper from Geant4 10.7 include the embedded method of Cash and Karp (G4TCashKarpRKF45), and a number of methods which use bisection for error estimatios: the original method of Runge and Kutta (G4TClassicalRK4) which used to be the default before Geant4 release 10.4, and two lower order methods, the 2nd order G4TSimpleRunge and the third order G4TSimpleHeum.

As a further optimisation, it can also be used with a templated driver

```
double stepMin= 0.1 * CLHEP::millimeter;
auto dp45driver =
   new G4IntegrationDriver<TemplatedStepper_t>(stepMin, dopri5_stepper);
auto interpolatingDrv =
   new G4InterpolationDriver<TemplatedStepper_t>(stepMin, dopri5_stepper);
```

which is simplified greatly by using a name for the type of the templated stepper.

Note that the templated stepper class also can be used without using an equation templated on the type of field. This could be preferable in the case of complex field classes in which a large amount of code calculates the value of the field.

A templated stepper also using an alternative type of field. We demonstrate using a full electromagnetic field (which in practice will be a derived class for a user's application) and its equation G4EqMagElectricField:

```
#include "G4EqMagElectricField.hh"

using Equation_t = G4EqMagElectricField;
constexpr nvar= 8; // Equation integrates over x, p, t

using TemplatedDoPri5_t = G4TDormandPrince45<Equation_t,nvar>;

(continues on next page)
```

(continued from previous page)

```
MyElectroMagneticField *emField= ...; // deriving from
auto emEquation= new G4EqMagElectricField(emField);
TemplatedDoPri5_t* pStepperTDP45 = new TemplatedDoPri5_t( emEquation, nvar );
auto ck45Stepper = new G4TCashKarpRKF45<Equation_t,nvar>( emEquation, nvar );
```

### Using different FSAL steppers - without interpolation

A different method which only has the FSAL property can be used for a magnetic field by adding a flag to the constructor of G4ChordFinder:

```
G4MagneticField * pMagField;
G4double stepMinimum = 0.03 * millimeter;
G4bool useFSALstp= true;
auto pChordF= new G4ChordFinder( pMagField, stepMinimum, nullptr, useFSALstp );
```

#### This uses the constructor ::

**G4ChordFinder::G4ChordFinder( G4MagneticField\* theMagField,** G4double G4MagIntegratorStepper\* pItsStepper, G4bool useFSALstepper);

stepMinimum,

Steppers of this type can also be created directly:

```
#include "G4RK547FEq1.hh"
#include "G4SystemsOfUnits.hh"

using FsalStepperType = G4RK547FEq1;
G4double stepMinimum= 0.1 * millimeter; // Minimum size of step (for driver)
int nvar= 6; // or 8 to include time, Energy

auto fsalStepper= new FsalStepperType(pEquation, nvar);
```

They must then be coupled to a new type of driver G4FSALIntegrationDriver in order to be used in integration. (This is a derived class of the new base class for drivers G4VIntegrationDriver.)

This also demonstrates one of a new family of (FSAL) steppers G4RK547FEq1 (others are G4RK547FEq2 and G4RK547FEq3) which were created to provide an improved equilibrium in integration. When a integration step fails due to an error above threshold, for some setups there can be oscillations in step size that cause multiple bounces between a successful and a failed step. The coefficients of these steppers were optimised to reduce these oscillations, and thus increase the success rate of steps. Initial tests demonstrated a small potential (1.0-2.5%) performance advantage.

### Further reducing the number of field calls to speed-up simulation

An additional method to reduce the number of field evaluations is to avoid recalculating the field value inside a sphere of a given radius distConst from the previously evaluated location.

This can be done by utilising the class G4CachedMagneticField class, for the case of pure magnetic fields which do not vary with time.

This is not recommended if there are locations in the setup in which large variations occur in the field vector. In those cases it is best to rely on advanced integration method. In particular the Interpolation capabilities introduced in Geant4 10.6 greatly reduced the number of field calls already.

#### Choosing different accuracies for the same volume

It is possible to create a G4FieldManager which has different properties for particles of different momenta (or depending on other parameters of a track). This is useful, for example, in obtaining high accuracy for 'important' tracks (e.g. muons) and accept less accuracy in tracking other tracks (e.g. electrons). To use this, you must create your own field manager class, derived from G4FieldManager which implements the method

```
void ConfigureForTrack( const G4Track * ) override final;
```

and uses it to configure itself using the parameters of the current track.

For example to choose different values for the relative accuracy of integration for particles with energy below or above 2.5 MeV, this could be achieve as follows:

```
class MyFieldManager : G4FieldManager
{
    MyFieldManager() = default;
    ~MyFieldManager() = default;

    void ConfigureForTrack( const G4Track * ) override final;
};

void MyFieldManager::ConfigureForTrack( const G4Track *pTrack)
{
    const G4double lowEepsMin= 1.0e-5, lowEepsMax= 1.0e-4;
    const G4double hiEepsMin= 2.5e-6, hiEepsMax= 1.0e-5;

    if( pTrack->GetKineticEnergy() < 2.5 * MeV ) {
        SetMinimumEpsilonStep( lowEepsMin );
        SetMaximumEpsilonStep( lowEepsMax ); // Max relative accuracy
} else {
        SetMinimumEpsilonStep( hiEepsMin );
        SetMaximumEpsilonStep( hiEepsMax ); // Max relative accuracy
}
}</pre>
```

#### Parameters that must scale with problem size

The default settings of this module are for problems with the physical size of a typical high energy physics setup, that is, distances smaller than about one kilometer. A few parameters are necessary to carry this information to the magnetic field module, and must typically be rescaled for problems of vastly different sizes in order to get reasonable performance and robustness. Two of these parameters are the maximum acceptable step and the minimum step size.

The **maximum acceptable step** should be set to a distance larger than the biggest reasonable step. If the apparatus in a setup has a diameter of two meters, a likely maximum acceptable steplength would be 10 meters. A particle could then take large spiral steps, but would not attempt to take, for example, a 1000-meter-long step in the case of a very low-density material. Similarly, for problems of a planetary scale, such as the earth with its radius of roughly 6400 km, a maximum acceptable steplength of a few times this value would be reasonable.

An upper limit for the size of a step is a parameter of G4PropagatorInField, and can be set by calling its SetLargestAcceptableStep method.

The **minimum step size** is used during integration to limit the amount of work in difficult cases. It is possible that strong fields or integration problems can force the integrator to try very small steps; this parameter stops them from becoming unnecessarily small.

Trial steps smaller than this parameter will be treated with less accuracy, and may even be ignored, depending on the situation.

The minimum step size is a parameter of the MagInt\_Driver, but can be set in the constructor of G4ChordFinder, as in the source listing above.

#### **Known Issues**

For most integration method it is computationally expensive to change the *miss distance* to very small values, as it causes tracks to be limited to curved sections whose 'sagitta' is smaller than this value. (The sagitta is the distance of the mid-point from the chord between endpoints see e.g. <a href="https://en.wikipedia.org/wiki/Sagitta\_%28geometry%29">https://en.wikipedia.org/wiki/Sagitta\_%28geometry%29</a>).) For tracks with small curvature (typically low momentum particles in strong fields) this can cause a large number of steps

- even in areas where there are no volumes to intersect (where the safety could be utilized to partially alleviate this limitation)
- especially in a region near a volume boundary (in which case it is necessary in order to discover whether a track might intersect a volume for only a short distance.)

Requiring such precision for the intersection of all potential volumes is clearly expensive, and in some cases it is not possible to reduce expense greatly.

By contrast, changing the intersection parameter *delta intersection* is less computationally expensive. It causes further calculation for only a fraction of the steps, those that intersect a volume boundary.

# 4.3.3 Spin Tracking

The effects of a particle's motion on the precession of its spin angular momentum in slowly varying external fields are simulated. The relativistic equation of motion for spin is known as the BMT equation. The equation demonstrates a remarkable property; in a purely magnetic field, in vacuum, and neglecting small anomalous magnetic moments, the particle's spin precesses in such a manner that the longitudinal polarization remains a constant, whatever the motion of the particle. But when the particle interacts with electric fields of the medium and multiple scatters, the spin, which is related to the particle's magnetic moment, does not participate, and the need thus arises to propagate it independent of the momentum vector. In the case of a polarized muon beam, for example, it is important to predict the muon's spin direction at decay-time in order to simulate the decay electron (Michel) distribution correctly.

In order to track the spin of a particle in a magnetic field, you need to code the following:

#### 1. in your DetectorConstruction

### 2. in your PrimaryGenerator

```
particleGun->SetParticlePolarization(G4ThreeVector p)
```

#### for example:

where you set the initial spin direction.

While the G4Mag\_SpinEqRhs class constructor

```
G4Mag_SpinEqRhs::G4Mag_SpinEqRhs( G4MagneticField* MagField )
    : G4Mag_EqRhs( MagField )
{
    anomaly = 1.165923e-3;
}
```

sets the muon anomaly by default, the class also comes with the public method:

```
inline void SetAnomaly(G4double a) { anomaly = a; }
```

with which you can set the magnetic anomaly to any value you require.

The code has been rewritten (in Release 9.5) such that field tracking of the spin can now be done for charged and neutral particles with a magnetic moment, for example spin tracking of ultra cold neutrons. This requires the user to set <code>EnableUseMagneticMoment</code>, a method of the <code>G4Transportation</code> process. The force resulting from the term, MUSDOTNABLAB, is not yet implemented in <code>GEANT4</code> (for example, simulated trajectory of a neutral hydrogen atom trapped by its magnetic moment in a gradient B-field.)

### 4.4 Hits

### 4.4.1 Hit

A hit is a snapshot of the physical interaction of a track in the sensitive region of a detector. In it you can store information associated with a G4Step object. This information can be

- the position and time of the step,
- the momentum and energy of the track,
- the energy deposition of the step,
- geometrical information,

or any combination of the above.

4.4. Hits 177

#### **G4VHit**

G4VHit is an abstract base class which represents a hit. You must inherit this base class and derive your own concrete hit class(es). The member data of your concrete hit class can be, and should be, your choice.

As with G4THitsCollection, authors of subclasses must declare templated G4Allocators for their class. They must also implement *operator new()* and *operator delete()* which use these allocators.

G4VHit has two virtual methods, Draw() and Print(). To draw or print out your concrete hits, these methods should be implemented. How to define the drawing method is described in *Polylines, Markers and Text*.

#### **G4THitsCollection**

G4VHit is an abstract class from which you derive your own concrete classes. During the processing of a given event, represented by a G4Event object, many objects of the hit class will be produced, collected and associated with the event. Therefore, for each concrete hit class you must also prepare a concrete class derived from G4VHitsCollection, an abstract class which represents a vector collection of user defined hits.

G4THitsCollection is a template class derived from G4VHitsCollection, and the concrete hit collection class of a particular G4VHit concrete class can be instantiated from this template class. Each object of a hit collection must have a unique name for each event.

G4Event has a G4HCofThisEvent class object, that is a container class of collections of hits. Hit collections are stored by their pointers, whose type is that of the base class.

### An example of a concrete hit class

Listing 4.14 shows an example of a concrete hit class.

Listing 4.14: An example of a concrete hit class.

```
//======== header file ==============
#ifndef B2TrackerHit_h
#define B2TrackerHit_h 1
#include "G4VHit.hh"
#include "G4THitsCollection.hh"
#include "G4Allocator.hh"
#include "G4ThreeVector.hh"
#include "tls.hh"
namespace B2
/// Tracker hit class
/// It defines data members to store the trackID, chamberNb, energy deposit,
/// and position of charged particles in a selected volume:
/// - fTrackID, fChamberNB, fEdep, fPos
class TrackerHit : public G4VHit
 public:
    TrackerHit();
    TrackerHit(const TrackerHit&) = default;
    ~TrackerHit() override;
    // operators
    TrackerHit& operator=(const TrackerHit&) = default;
    G4bool operator == (const TrackerHit&) const;
   inline void* operator new(size_t);
    inline void operator delete(void*);
    // methods from base class
    void Draw() override;
    void Print() override;
    // Set methods
   void SetTrackID (G4int track) { fTrackID = track; };
void SetChamberNb(G4int chamb) { fChamberNb = chamb; };
void SetEdep (G4double de) { fEdep = de; };
    void SetEdep (G4double de)
    void SetPos
                      (G4ThreeVector xyz) { fPos = xyz; };
    G4int GetTrackID() const
                                  { return fTrackID; };
    G4int GetChamberNb() const { return fChamberNb; };
G4double GetEdep() const { return fEdep; };
    G4ThreeVector GetPos() const { return fPos; };
  private:
    G4int
                   fTrackID = -1;
    G4int
                   fChamberNb = -1;
    G4double
                   fEdep = 0.;
    G4ThreeVector fPos;
typedef G4THitsCollection<TrackerHit> TrackerHitsCollection;
extern G4ThreadLocal G4Allocator<TrackerHit>* TrackerHitAllocator;
                                                                                          (continues on next page)
```

4.4. Hits 179

(continued from previous page)

G4Allocator is a class for fast allocation of objects to the heap through the paging mechanism. For details of G4Allocator, refer to *General management classes*. Use of G4Allocator is not mandatory, but it is recommended, especially for users who are not familiar with the C++ memory allocation mechanism or alternative tools of memory allocation. On the other hand, note that G4Allocator is to be used **only** for the concrete class that is **not** used as a base class of any other classes. For example, do **not** use the G4Trajectory class as a base class for a customized trajectory class, since G4Trajectory uses G4Allocator.

#### G4THitsMap

G4THitsMap is an alternative to G4THitsCollection. G4THitsMap does not demand G4VHit, but instead any variable which can be mapped with an integer key. Typically the key is a copy number of the volume, and the mapped value could for example be a double, such as the energy deposition in a volume. G4THitsMap is convenient for applications which do not need to output event-by-event data but instead just accumulate them. All the G4VPrimitiveScorer classes discussed in G4MultiFunctionalDetector and G4VPrimitiveScorer use G4THitsMap.

G4THitsMap is derived from the G4VHitsCollection abstract base class and all objects of this class are also stored in G4HCofThisEvent at the end of an event. How to access a G4THitsMap object is discussed in the following section (G4MultiFunctionalDetector and G4VPrimitiveScorer).

### 4.4.2 Sensitive detector

#### G4VSensitiveDetector

G4VSensitiveDetector is an abstract base class which represents a detector. The principal mandate of a sensitive detector is the construction of hit objects using information from steps along a particle track. The ProcessHits() method of G4VSensitiveDetector performs this task using G4Step objects as input. The second argument of ProcessHits() method, i.e. G4TouchableHistory, is obsolete and not used. If user needs to define an artificial second geometry, use *Parallel Geometries*.

ProcessHits() method has a return type of G4bool. This return value is not used by Geant4 kernel. This return value may be used by the user's use-case where one sensitive detector dispatches ProcessHits() to some subsequent (i.e. child) sensitive detectors, and to avoid double-counting, one of these child detector may return true or false.

Your concrete detector class should be instantiated with the unique name of your detector. The name can be associated with one or more global names with "/" as a delimiter for categorizing your detectors. For example

```
myEMcal = new MyEMcal("/myDet/myCal/myEMcal");
```

where myEMcal is the name of your detector. The detector must be constructed in G4VUserDetectorConstruction::ConstructSDandField() method. It must be assigned to one or more G4LogicalVolume objects to set the sensitivity of these volumes. Such assignment must be made in the same G4VUserDetectorConstruction::ConstructSDandField() method. The pointer should also be registered to G4SDManager, as described in G4SDManager.

G4VSensitiveDetector has three major virtual methods.

- ProcessHits() This method is invoked by G4SteppingManager when a step is composed in the G4LogicalVolume which has the pointer to this sensitive detector. The first argument of this method is a G4Step object of the current step. The second argument is a G4TouchableHistory object for the Readout geometry described in the next section. The second argument is NULL if Readout geometry is not assigned to this sensitive detector. In this method, one or more G4VHit objects should be constructed if the current step is meaningful for your detector.
- Initialize() This method is invoked at the beginning of each event. The argument of this method is an object of the G4HCofThisEvent class. Hit collections, where hits produced in this particular event are stored, can be associated with the G4HCofThisEvent object in this method. The hit collections associated with the G4HCofThisEvent object during this method can be used for during the event processing digitization.
- **EndOfEvent ()** This method is invoked at the end of each event. The argument of this method is the same object as the previous method. Hit collections occasionally created in your sensitive detector can be associated with the G4HCofThisEvent object.

4.4. Hits 181

### 4.4.3 G4SDManager

G4SDManager is the singleton manager class for sensitive detectors.

#### Activation/inactivation of sensitive detectors

The user interface commands activate and inactivate are available to control your sensitive detectors. For example:

```
/hits/activate detector_name
/hits/inactivate detector_name
```

where detector\_name can be the detector name or the category name.

For example, if your EM calorimeter is named

```
/myDet/myCal/myEMcal
/hits/inactivate myCal
```

will inactivate all detectors belonging to the myCal category.

#### Access to the hit collections

Hit collections are accessed for various cases.

- · Digitization
- Event filtering in G4VUserStackingAction
- "End of event" simple analysis
- · Drawing / printing hits

The following is an example of how to access the hit collection of a particular concrete type:

```
G4SDManager* fSDM = G4SDManager::GetSDMpointer();
G4RunManager* fRM = G4RunManager::GetRunManager();
G4int collectionID = fSDM->GetCollectionID("collection_name");
const G4Event* currentEvent = fRM->GetCurrentEvent();
G4HCofThisEvent* HCofEvent = currentEvent->GetHCofThisEvent();
MyHitsCollection* myCollection = (MyHitsCollection*) (HCOfEvent->GetHC(collectionID));
```

### 4.4.4 G4MultiFunctionalDetector and G4VPrimitiveScorer

G4MultiFunctionalDetector is a concrete class derived from G4VSensitiveDetector. Instead of implementing a user-specific detector class, G4MultiFunctionalDetector allows the user to register G4VPrimitiveScorer classes to build up the sensitivity. G4MultiFunctionalDetector should be instantiated in the users detector construction with its unique name and should be assigned to one or more G4LogicalVolumes.

G4VPrimitiveScorer is an abstract base class representing a class to be registered to G4MultiFunctionalDetector that creates a G4THitsMap object of one physics quantity for an event. GEANT4 provides many concrete primitive scorer classes listed in *Concrete classes of G4VPrimitiveScorer*, and the user can also implement his/her own primitive scorers. Each primitive scorer object must be instantiated with a name that must be unique among primitive scorers registered in a G4MultiFunctionalDetector. Please note that a primitive scorer object must **not** be shared by more than one G4MultiFunctionalDetector object.

As mentioned in *Hit*, each G4VPrimitiveScorer generates one G4THitsMap object per event. The name of the map object is the same as the name of the primitive scorer. Each of the concrete primitive scorers listed in

Concrete classes of G4VPrimitiveScorer generates a G4THitsMap<G4double> that maps a G4double value to its key integer number. By default, the key is taken as the copy number of the G4LogicalVolume to which G4MultiFunctionalDetector is assigned. In case the logical volume is uniquely placed in its mother volume and the mother is replicated, the copy number of its mother volume can be taken by setting the second argument of the G4VPrimitiveScorer constructor, "depth" to 1, i.e. one level up. Furthermore, in case the key must consider more than one copy number of a different geometry hierarchy, the user can derive his/her own primitive scorer from the provided concrete class and implement the GetIndex (G4Step\*) virtual method to return the unique key.

Listing 4.15 shows an example of primitive sensitivity class definitions.

Listing 4.15: An example of defining primitive sensitivity classes taken from RE06DetectorConstruction.

```
void RE06DetectorConstruction::SetupDetectors()
 G4String filterName, particleName;
 G4SDParticleFilter* gammaFilter =
   new G4SDParticleFilter(filterName="gammaFilter",particleName="gamma");
 G4SDParticleFilter* electronFilter =
   new G4SDParticleFilter(filterName="electronFilter",particleName="e-");
 G4SDParticleFilter* positronFilter =
   new G4SDParticleFilter(filterName="positronFilter",particleName="e+");
 G4SDParticleFilter* epFilter = new G4SDParticleFilter(filterName="epFilter");
 epFilter->add(particleName="e-");
  epFilter->add(particleName="e+");
  for (G4int i=0; i<3; i++)</pre>
  for (G4int j=0; j<2; j++)</pre>
   // Loop counter j = 0 : absorber
   G4String detName = fCalName[i];
   if(j==0)
    { detName += "_abs"; }
   else
    { detName += "_gap"; }
   G4MultiFunctionalDetector* det = new G4MultiFunctionalDetector(detName);
   // The second argument in each primitive means the "level" of geometrical hierarchy,
    // the copy number of that level is used as the key of the G4THitsMap.
    // For absorber (j = 0), the copy number of its own physical volume is used.
    // For gap (j = 1), the copy number of its mother physical volume is used, since there
    // is only one physical volume of gap is placed with respect to its mother.
   G4VPrimitiveScorer* primitive;
   primitive = new G4PSEnergyDeposit("eDep",j);
   det->RegisterPrimitive(primitive);
   primitive = new G4PSNofSecondary("nGamma", j);
   primitive->SetFilter(gammaFilter);
   det->RegisterPrimitive(primitive);
   primitive = new G4PSNofSecondary("nElectron", j);
   primitive->SetFilter(electronFilter);
   det->RegisterPrimitive(primitive);
   primitive = new G4PSNofSecondary("nPositron", j);
   primitive->SetFilter(positronFilter);
   det->RegisterPrimitive(primitive);
   primitive = new G4PSMinKinEAtGeneration("minEkinGamma", j);
   primitive->SetFilter(gammaFilter);
   det->RegisterPrimitive(primitive);
   primitive = new G4PSMinKinEAtGeneration("minEkinElectron", j);
   primitive->SetFilter(electronFilter);
   det->RegisterPrimitive(primitive);
   primitive = new G4PSMinKinEAtGeneration("minEkinPositron", j);
```

(continues on next page)

4.4. Hits 183

(continued from previous page)

```
primitive->SetFilter(positronFilter);
  det->RegisterPrimitive(primitive);
  primitive = new G4PSTrackLength("trackLength",j);
  primitive->SetFilter(epFilter);
  det->RegisterPrimitive(primitive);
  primitive = new G4PSNofStep("nStep",j);
  primitive->SetFilter(epFilter);
  det->RegisterPrimitive(primitive);

G4SDManager::GetSDMpointer()->AddNewDetector(det);
  if(j==0)
  { layerLogical[i]->SetSensitiveDetector(det); }
  else
  { gapLogical[i]->SetSensitiveDetector(det); }
}
}
```

Each G4THitsMap object can be accessed from G4HCofThisEvent with a unique collection ID number. This ID number can be obtained from G4SDManager::GetCollectionID() with a name of G4MultiFunctionalDetector and G4VPrimitiveScorer connected with a slush ("/"). G4THitsMap has a [] operator taking the key value as an argument and returning **the pointer** of the value. Please note that the [] operator returns **the pointer** of the value. If you get zero from the [] operator, it does **not** mean the value is zero, but that the provided key does not exist. The value itself is accessible with an asterisk ("\*"). It is advised to check the validity of the returned pointer before accessing the value. G4THitsMap also has a += operator in order to accumulate event data into run data. Listing 4.16 shows the use of G4THitsMap.

Listing 4.16: An example of accessing to G4THitsMap objects.

```
#include "Run.hh"
#include "G4RunManager.hh"
#include "G4Event.hh"
#include "G4SDManager.hh"
#include "G4HCofThisEvent.hh"
#include "G4THitsMap.hh"
#include "G4SystemOfUnits.hh"
namespace B3b
Run::Run()
Run::~Run()
{ }
void Run::RecordEvent (const G4Event * event)
  if ( fCollID_cryst < 0 ) {</pre>
   fCollID_cryst
     = G4SDManager::GetSDMpointer()->GetCollectionID("crystal/edep");
    //G4cout << " fCollID_cryst: " << fCollID_cryst << G4endl;
  if (fCollID_patient < 0 ) {</pre>
```

(continues on next page)

(continued from previous page)

```
fCollID_patient
     = G4SDManager::GetSDMpointer()->GetCollectionID("patient/dose");
   //G4cout << " fCollID_patient: " << fCollID_patient << G4endl;
 G4int evtNb = event->GetEventID();
  if (evtNb%fPrintModulo == 0) {
   G4cout << G4endl << "---> end of event: " << evtNb << G4endl;
  //Hits collections
  G4HCofThisEvent* HCE = event->GetHCofThisEvent();
  if(!HCE) return;
  //Energy in crystals : identify 'good events'
  const G4double eThreshold = 500*keV;
  G4int nbOfFired = 0;
 G4THitsMap<G4double>* evtMap =
    static_cast<G4THitsMap<G4double>*>(HCE->GetHC(fCollID_cryst));
  std::map<G4int,G4double*>::iterator itr;
  for (itr = evtMap->GetMap()->begin(); itr != evtMap->GetMap()->end(); itr++) {
   G4double edep = *(itr->second);
   if (edep > eThreshold) nbOfFired++;
    ///G4int copyNb = (itr->first);
    ///G4cout << G4endl << " cryst" << copyNb << ": " << edep/keV << " keV ";
  if (nbOfFired == 2) fGoodEvents++;
  //Dose deposit in patient
 G4double dose = 0.;
 evtMap = static_cast<G4THitsMap<G4double>*>(HCE->GetHC(fCollID_patient));
  for (itr = evtMap->GetMap()->begin(); itr != evtMap->GetMap()->end(); itr++) {
   ///G4int copyNb = (itr->first);
   dose = *(itr->second);
  fSumDose += dose;
 fStatDose += dose;
 G4Run::RecordEvent(event);
void Run::Merge(const G4Run* aRun)
 const Run* localRun = static_cast<const Run*>(aRun);
 fGoodEvents += localRun->fGoodEvents;
 fSumDose += localRun->fSumDose;
fStatDose += localRun->fStatDose;
 G4Run::Merge(aRun);
```

4.4. Hits 185

### 4.4.5 Concrete classes of G4VPrimitiveScorer

With GEANT4 version 8.0, several concrete primitive scorer classes are provided, all of which are derived from the G4VPrimitiveScorer abstract base class and which are to be registered to G4MultiFunctionalDetector. Each of them contains one G4THitsMap object and scores a simple double value for each key.

#### Track length scorers

- **G4PSTrackLength** The track length is defined as the sum of step lengths of the particles inside the cell. By default, the track weight is not taken into account, but could be used as a multiplier of each step length if the Weighted () method of this class object is invoked.
- **G4PSPassageTrackLength** The passage track length is the same as the track length in G4PSTrackLength, except that only tracks which pass through the volume are taken into account. It means newly-generated or stopped tracks inside the cell are excluded from the calculation. By default, the track weight is not taken into account, but could be used as a multiplier of each step length if the Weighted () method of this class object is invoked.

### **Deposited energy scorers**

- **G4PSEnergyDeposit** This scorer stores a sum of particles' energy deposits at each step in the cell. The particle weight is multiplied at each step.
- **G4PSDoseDeposit** In some cases, dose is a more convenient way to evaluate the effect of energy deposit in a cell than simple deposited energy. The dose deposit is defined by the sum of energy deposits at each step in a cell divided by the mass of the cell. The mass is calculated from the density and volume of the cell taken from the methods of G4VSolid and G4LogicalVolume. The particle weight is multiplied at each step.

#### **Current and flux scorers**

There are two different definitions of a particle's flow for a given geometry. One is a current and the other is a flux. In our scorers, the current is simply defined as the number of particles (with the particle's weight) at a certain surface or volume, while the flux takes the particle's injection angle to the geometry into account. The current and flux are usually defined at a surface, but volume current and volume flux are also provided.

- **G4PSFlatSurfaceCurrent** Flat surface current is a surface based scorer. The present implementation is limited to scoring only at the -Z surface of a G4Box solid. The quantity is defined by the number of tracks that reach the surface. The user must choose a direction of the particle to be scored. The choices are fCurrent\_In, fCurrent\_Out, or fCurrent\_InOut, one of which must be entered as the second argument of the constructor. Here, fCurrent\_In scores incoming particles to the cell, while fCurrent\_Out scores only outgoing particles from the cell. fCurrent\_InOut scores both directions. The current is multiplied by particle weight and is normalized for a unit area.
- **G4PSSphereSurfaceCurrent** Sphere surface current is a surface based scorer, and similar to the G4PSFlatSurfaceCurrent. The only difference is that the surface is defined at the **inner surface** of a G4Sphere solid.
- **G4PSPassageCurrent** Passage current is a volume-based scorer. The current is defined by the number of tracks that pass through the volume. A particle weight is applied at the exit point. A passage current is defined for a volume.
- G4PSFlatSurfaceFlux Flat surface flux is a surface based flux scorer. The surface flux is defined by the number of tracks that reach the surface. The expression of surface flux is given by the sum of W/cos(t)/A, where W, t and A represent particle weight, injection angle of particle with respect to the surface normal, and area of the surface. The user must enter one of the particle directions, fFlux\_In, fFlux\_Out, or fFlux\_InOut in the constructor. Here, fFlux\_In scores incoming particles to the cell, while fFlux\_Out scores outgoing particles from the cell. fFlux\_InOut scores both directions.

- **G4PSCellFlux** Cell flux is a volume based flux scorer. The cell flux is defined by a track length (L) of the particle inside a volume divided by the volume (V) of this cell. The track length is calculated by a sum of the step lengths in the cell. The expression for cell flux is given by the sum of (W\*L)/V, where W is a particle weight, and is multiplied by the track length at each step.
- **G4PSPassageCellFlux** Passage cell flux is a volume based scorer similar to G4PSCellFlux. The only difference is that tracks which pass through a cell are taken into account. It means generated or stopped tracks inside the volume are excluded from the calculation.

#### Other scorers

- **G4PSMinKinEAtGeneration** This scorer records the minimum kinetic energy of secondary particles at their production point in the volume in an event. This primitive scorer does not integrate the quantity, but records the minimum quantity.
- **G4PSNofSecondary** This class scores the number of secondary particles generated in the volume. The weight of the secondary track is taken into account.

**G4PSNofStep** This class scores the number of steps in the cell. A particle weight is not applied.

**G4PSCellCharge** This class scored the total charge of particles which has stopped in the volume.

### 4.4.6 G4VSDFilter and its derived classes

G4VSDFilter is an abstract class that represents a track filter to be associated with G4VSensitiveDetector or G4VPrimitiveScorer. It defines a virtual method

```
G4bool Accept(const G4Step*)
```

that should return *true* if this particular step should be scored by the G4VSensitiveDetector or G4VPrimitiveScorer.

While the user can implement his/her own filter class, GEANT4 version 8.0 provides the following concrete filter classes:

**G4SDChargedFilter** All charged particles are accepted.

**G4SDNeutralFilter** All neutral particles are accepted.

**G4SDParticleFilter** Particle species which are registered to this filter object by Add("particle\_name") are accepted. More than one species can be registered.

**G4SDKineticEnergyFilter** A track with kinetic energy greater than or equal to EKmin and smaller than EKmin is accepted. EKmin and EKmax should be defined as arguments of the constructor. The default values of EKmin and EKmax are zero and DBL MAX.

**G4SDParticleWithEnergyFilter** Combination of G4SDParticleWithEnergyFilter.

The use of the G4SDParticleFilter class is demonstrated in Listing 4.15, where filters which accept gamma, electron, positron and electron/positron are defined.

4.4. Hits 187

## 4.4.7 Multiple sensitive detectors associated to a single logical-volume

From GEANT4 Version 10.3 it is possible to attach multiple sensitive detectors to a single geometrical element. This is achieved via the use of a special proxy class, to which multiple child sensitive detectors are attached: G4MultiSensitiveDetector. The kernel still sees a single sensitive detector associated to any given logical-volume, but the proxy will dispatch the calls from kernel to all the attached child sensitive detectors.

When using the G4VUserDetectorConstruction::SetSensitiveDetector(...) utility method the handling of multiple sensitive detectors is done automatically. Multiple calls to the method passing the same logical volume will trigger the creation and setup of an instance of G4MultiSensitiveDetector.

For more complex use cases it may be necessary to manually instantiate and setup an instance of G4MultiSensitiveDetector. For this advanced use case you can refer to the implementation of the G4VUserDetectorConstruction::SetSensitiveDetector(G4LogicalVolume\* logVol, G4VSensitiveDetector\* aSD) utility method.

Listing 4.17: An example of the use of G4MultiSensitiveDetector.

```
void MyDetectorConstruction::ConstructSDandField()
{
   auto sdman = G4SDManager::GetSDMpointer();
   //...
   auto mySD = new mySD1("/SD1");
   sdman->AddNewDetector(mySD);//Note we explicitly add the SD to the manager
   SetSensitiveDetector("LogVolName", mySD);
   auto mySD2 = new MySD2("/SD2");
   sdman->AddNewDetector(mySD2);
   //This will trigger automatic creation and setup of proxy
   SetSensitiveDetector("LogVolName", mySD2);
   //...
}
```

# 4.4.8 Utilities

### **UI-command base scoring**

Command-based scoring functionality offers the user a possibility to define a scoring-mesh and various scorers for commonly-used physics quantities such as dose, flux, etc. via UI commands.

Due to small performance overhead, it does not come by default. To use this functionality, G4ScoringManager has to be activated after the instantiation of G4RunManager in the main () function, see Listing 4.18. This will create the UI commands in /score directory.

Listing 4.18: Activation of UI-command base scoring in main ()

```
#include "G4ScoringManager.hh"
int main()
{
    // ...
    G4RunManager* runManager = new G4RunManager;
    G4ScoringManager::GetScoringManager();
    // ...
}
```

An example of a macro creating a scoring mesh of box type with two scorers and a filter is given below:

```
# Define scoring mesh
/score/create/boxMesh boxMesh_1
(continues on next page)
```

(continued from previous page)

```
/score/mesh/boxSize 100. 100. 100. cm
/score/mesh/nBin 30 30 30

# Define scoring quantity
/score/quantity/energyDeposit boxMash keV

# Define a filter
/score/filter/charged

# Close mesh
/score/close
```

Detailed usage of command-based scoring is given in the section Command-based scoring.

G4ScoringManager provides also a default score writer which dumps every entry of one quantity of a mesh for all quantities of the mesh one by one in CSV format. To alternate the file format the user can implement his/her own score writer deriving from G4VUserScoreWriter base class and set it to G4ScoringManager. To demonstrate this, RE03UserScoreWriter is included in the extended RE03 example in the runAndEvent category.

### **Score Ntuple Writer**

It is also possible to save the scorers hits using Geant4 analysis tools. This functionality is assured by the G4VScoreNtupleWriter interface (since 10.5) and the G4TScoreNtupleWriter and G4TScoreNtupleWriterMessenger classes (since 10.6).

This feature is demonstrated in the basic examples B3 and B4d. The example of activating the score ntuple writer is given below:

```
#include "G4AnalysisManager.hh"
#include "G4TScoreNtupleWriter.hh"

// Activate score ntuple writer
G4TScoreNtupleWriter<G4AnalysisManager> scoreNtupleWriter;
scoreNtupleWriter.SetVerboseLevel(1);
```

The Geant4 UI commands defined in G4TScoreNtupleWriterMessenger can be used to choose the output file name and the level of verbosity:

```
/score/ntuple/writerFileName name
/score/ntuple/writerVerbose 1
```

# 4.5 Digitization

# 4.5.1 Digi

A hit is created by a sensitive detector when a step goes through it. Thus, the sensitive detector is associated to the corresponding G4LogicalVolume object(s). On the other hand, a digit is created using information of hits and/or other digits by a digitizer module. The digitizer module is not associated with any volume, and you have to implicitly invoke the Digitize() method of your concrete G4VDigitizerModule class.

Typical usages of digitizer module include:

- simulate ADC and/or TDC
- · simulate readout scheme
- generate raw data
- · simulate trigger logics

4.5. Digitization 189

• simulate pile up

#### **G4VDigi**

G4VDigi is an abstract base class which represents a digit. You have to inherit this base class and derive your own concrete digit class(es). The member data of your concrete digit class should be defined by yourself. G4VDigi has two virtual methods, Draw() and Print().

As with G4VHit, authors of subclasses must declare templated G4Allocators for their digit class. They must also implement *operator new()* and *operator delete()* which use these allocators.

#### **G4TDigiCollection**

G4TDigiCollection is a template class for digits collections, which is derived from the abstract base class G4VDigiCollection. G4Event has a G4DCofThisEvent object, which is a container class of collections of digits. The usages of G4VDigi and G4TDigiCollection are almost the same as G4VHit and G4THitsCollection, respectively, explained in the previous section.

As with G4THitsCollection, authors of subclasses must declare templated G4Allocators for their collection class. They must also implement *operator new()* and *operator delete()* which use these allocators.

## 4.5.2 Digitizer module

#### G4VDigitizerModule

G4VDigitizerModule is an abstract base class which represents a digitizer module. It has a pure virtual method, Digitize(). A concrete digitizer module must have an implementation of this virtual method. The GEANT4 kernel classes do not have a "built-in" invocation to the Digitize() method. You have to implement your code to invoke this method of your digitizer module.

In the Digitize() method, you construct your G4VDigi concrete class objects and store them to your G4TDigiCollection concrete class object(s). Your collection(s) should be associated with the G4DCofThisEvent object.

#### G4DigiManager

G4DigiManager is the singleton manager class of the digitizer modules. All of your concrete digitizer modules should be registered to G4DigiManager with their unique names.

```
G4DigiManager * fDM = G4DigiManager::GetDMpointer();
MyDigitizer * myDM = new MyDigitizer( "/myDet/myCal/myEMdigiMod" );
fDM->AddNewModule(myDM);
```

Your concrete digitizer module can be accessed from your code using the unique module name.

```
G4DigiManager * fDM = G4DigiManager::GetDMpointer();
MyDigitizer * myDM = fDM->FindDigitizerModule( "/myDet/myCal/myEMdigiMod" );
myDM->Digitize();
```

Also, G4DigiManager has a Digitize () method which takes the unique module name.

```
G4DigiManager * fDM = G4DigiManager::GetDMpointer();
MyDigitizer * myDM = fDM->Digitize( "/myDet/myCal/myEMdigiMod" );
```

#### How to get hitsCollection and/or digiCollection

G4DigiManager has the following methods to access to the hits or digi collections of the currently processing event or of previous events.

First, you have to get the collection ID number of the hits or digits collection.

```
G4DigiManager * fDM = G4DigiManager::GetDMpointer();
G4int myHitsCollID = fDM->GetHitsCollectionID( "hits_collection_name");
G4int myDigiCollID = fDM->GetDigiCollectionID( "digi_collection_name");
```

Then, you can get the pointer to your concrete G4THitsCollection object or G4TDigiCollection object of the currently processing event.

```
MyHitsCollection * HC = fDM->GetHitsCollection( myHitsCollID );
MyDigiCollection * DC = fDM->GetDigiCollection( myDigiCollID );
```

In case you want to access to the hits or digits collection of previous events, add the second argument.

```
MyHitsCollection * HC = fDM->GetHitsCollection( myHitsCollID, n );
MyDigiCollection * DC = fDM->GetDigiCollection( myDigiCollID, n );
```

where, n indicates the hits or digits collection of the n<sup>th</sup> previous event.

# 4.6 Birks Quenching

The current versions of hadronic string models (FTF & QGS) produce hadronic showers with (a few percent) higher energy response than the stable released (as used in LHC productions) version of these models. Test-beam and collider data seem to indicate lower energy response in hadronic showers than currently provided by Geant4 simulations. This is the main reason why the development versions of the string models were not released in two previous public versions of Geant4 (10.3 and 10.4), in spite of providing an overall better description of thin-target data. We think that the main reason why the simulation overshot the data regarding the energy response of hadronic showers is in fact due to an incorrect treatment of the quenching of the signal - the conversion from the energy deposited by ionizing particles in a sensitive detector to the observed electronic (readout) signal is not linear, with proportionally less signal for higher densities of deposited energy, for both scintillation light and ionization electron-hole/ion pairs. This quenching effect is traditionally described by the simple, phenomenological "law" suggested many years ago by Birks. Its main parameter is fitted from experimental data under the assumption that the observed energy is related to the incident particle energy loss. This does not consider delta-ray production which will result in lower energy deposit (density). As a result of this approximation, the density of deposited energy is overestimated, which implies that the Birks coefficient, as fitted from the experimental data, gets underestimated. Using this Birks coefficient in simulations where delta rays are emitted (and considered discretely), as in practice for all simulations of high-energy experiments, results in underestimating the quenching effect, and therefore predicting larger signals than in reality. The correct Birks coefficient to be used in a simulation depends on the production threshold which is chosen in the simulation, with lower thresholds producing a larger delta-ray component and therefore reducing the density of the energy deposition along the ionizing track, and hence requiring an even higher Birks coefficient. We suggest the following pragmatic approach to incorporating Birks quenching: The calibration of a calorimeter - i.e. the conversion from the electronic signal produced by a shower and the energy of the primary particle that initiates the shower - is typically done for test beam data with an electron of a given energy, e.g. 20 GeV. We suggest to add an extra step to this calibration, in which the Birks coefficient used in the simulation is tuned to reproduce the ratio of the energy response of a hadron (typically a charged pion or a proton) and the energy response of an electron of the same energy (this ratio is indicated as "h/e"). It is natural to consider the same beam energy used for the calibration, e.g. 20 GeV, but in principle it could be a different one; note also that the tuning of the Birks coefficient is idependent from the calibration constant, given that the latter cancels out from the ratio h/e. Of course, with the tuning of the Birks coefficient as suggested above we compensate also for some of the intrinsic inaccuracies in the modelling of hadronic interactions; however, this effect is valid uniquely at the energy where the tuning is done (e.g. 20 GeV), and limited only to the energy response. For other observables (energy resolution, longitudinal and lateral shower shapes), and for all other energies, this procedure has a minimal impact, i.e. should not reduce the prediction-power of the simulation.

# 4.7 Object Persistency

## 4.7.1 Persistency in GEANT4

Object persistency is provided by GEANT4 as an optional functionality.

When a usual (transient) object is created in C++, the object is placed onto the application heap and it ceases to exist when the application terminates. Persistent objects, on the other hand, live beyond the termination of the application process and may then be accessed by other processes (in some cases, by processes on other machines).




Fig. 4.8: Persistent object.

C++ does not have, as an intrinsic part of the language, the ability to store and retrieve persistent objects. GEANT4 provides an abstract framework for persistency of hits, digits and events.

Two examples demonstrating an implementation of object persistency using one of the tools accessible through the available interface, is provided in examples/extended/persistency.

# 4.7.2 Using Root-I/O for persistency of GEANT4 objects

Object persistency of GEANT4 objects is also possible by using the Root-I/O features through Root (since release v6.04/08).

The basic steps that one needs to do in order to use Root-I/O for arbitrary C++ classes is:

- 1. Generate the dictionary for the given classes from Root (this usually is done by adding the appropriate command to the makefile)
- 2. Add initialization of Root-I/O and loading of the generated dictionary for the given classes in the appropriate part of the code
- 3. Whenever the objects to be persistified are available, call the WriteObject method of TFile with the pointer to the appropriate object as argument (usually it is some sort of container, like std::vector containing the collection of objects to be persistified)

The two examples (P01 and P02) provided in examples/extended/persistency demonstrate how to perform object persistency using the Root-I/O mechanism for storing hits and geometry description.

# 4.8 Parallel Geometries

# 4.8.1 A parallel world

Occasionally, it is not straightforward to define geometries for sensitive detectors, importance geometries or envelopes for shower parameterization to be coherently assigned to volumes in the tracking (mass) geometry. The parallel navigation functionality introduced since release 8.2 of GEANT4, allows the user to define more than one world simultaneously. The G4CoupledTransportation process will see all worlds simultaneously; steps will be limited by every boundaries of the mass and parallel geometries. G4Transportation is automatically replaced G4CoupledTransportation.

In a parallel world, the user can define volumes in arbitrary manner with sensitivity, regions, shower parameterization setups, and/or importance weight for biasing. Volumes in different worlds may overlap.

Any kind of G4VSensitiveDetector object can be defined in volumes in a parallel world, exactly at the same manner for the mass geometry. G4Step object given as an argument of ProcessHit() method contains geometrical information of the associated world.

Here are restrictions to be considered for the parallel geometry:

- Production thresholds and EM field are used only from the mass geometry. Even if such *physical* quantities are defined in a parallel world, they do not affect to the simulation.
- Although all worlds will be comprehensively taken care by the G4CoupledTransportation process for the navigation, each parallel world must have its own unique object of G4ParallelWorldProcess process (for instance created with G4ParallelWorldPhysics constructor registered to a modular physics list).
- Volumes in a parallel world may have materials. Such materials overwrite the materials defined in the mass geometry if the "layered mass geometry" switch of the G4ParallelWorldProcess constructor is set.

# 4.8.2 Defining a parallel world

A parallel world should be defined in the Construct() virtual method of the user's class derived from the abstract base class G4VUserParallelWorld. If needed, sensitive detectors must be defined in the ConstructSD() method of the same derived class. Please note that EM field cannot be defined in a parallel world.

Listing 4.19: An example header file of a concrete user parallel world class.

```
#ifndef MyParallelWorld_h
#define MyParallelWorld_h 1

#include "globals.hh"
#include "G4VUserParallelWorld.hh"

class MyParallelWorld : public G4VUserParallelWorld
{
   public:
        MyParallelWorld(G4String worldName);
        virtual ~MyParallelWorld();

   public:
        virtual void Construct();
        virtual void ConstructSD();
};

#endif
```

A parallel world must have its unique name, which should be set to the G4VUserParallelWorld base class as an argument of the base class constructor.

The world physical volume of the parallel world is provided by the G4RunManager as a clone of the mass geometry. In the Construct () virtual method of the user's class, the pointer to this cloned world physical volume is available through the GetWorld() method defined in the base class. The user should fill the volumes in the parallel world by using this provided world volume. For a logical volume in a parallel world, the material pointer can be nullptr. Even if specified a valid material pointer, unless "layered mass geometry" switch of the G4ParallelWorldProcess constructor is set, it will not be taken into account by any physics process.

Listing 4.20: An example source code of a concrete user parallel world class.

```
#include "MyParallelWorld.hh"
#include "G4LogicalVolume.hh"
#include "G4VPhysicalVolume.hh"
#include "G4Box.hh"
#include "G4PVPlacement.hh"
MyParallelWorld::MyParallelWorld(G4String worldName)
:G4VUserParallelWorld(worldName)
MyParallelWorld::~MyParallelWorld()
void MyParallelWorld::Construct()
 G4VPhysicalVolume* ghostWorld = GetWorld();
 G4LogicalVolume* worldLogical = ghostWorld->GetLogicalVolume();
  // place volumes in the parallel world here. For example ...
 G4Box * ghostSolid = new G4Box("GhostdBox", 60.*cm, 60.*cm, 60.*cm);
 G4LogicalVolume * ghostLogical
        = new G4LogicalVolume(ghostSolid, 0, "GhostLogical", 0, 0, 0);
 new G4PVPlacement(0, G4ThreeVector(), ghostLogical,
                    "GhostPhysical", worldLogical, 0, 0);
```

In case the user needs to define more than one parallel worlds, each of them must be implemented through its dedicated class. Each parallel world should be registered to the mass geometry class using the method RegisterParallelWorld() available through the class G4VUserDetectorConstruction. The registration must be done before the mass world is registered to the G4RunManager. Each parallel world should also have its own G4ParallelWorldPhysics constructor registered to the physics list using the method RegisterPhysics() available through the class G4VModularPhysicsList.

Listing 4.21: Typical implementation in the main () to define a parallel world.

```
// RunManager construction
//
G4RunManager* runManager = new G4RunManager;

// mass world
//
MyDetectorConstruction* massWorld = new MyDetectorConstruction;

// parallel world
//
G4String paraWorldName = "ParallelWorld";
massWorld->RegisterParallelWorld(new MyParallelWorld(paraWorldName));
```

(continues on next page)

(continued from previous page)

```
// set mass world to run manager
//
runManager->SetUserInitialization(massWorld);

// physics list
//
G4VModularPhysicsList* physicsList = new FTFP_BERT;
physicsList->RegisterPhysics(new G4ParallelWorldPhysics(paraWorldName));
runManager->SetUserInitialization(physicsList);
```

## 4.8.3 Layered mass geometry

If "layered mass geometry" switch of the G4ParallelWorldProcess constructor is set, that parallel world is conceptually layered on top of the mass geometry. If more than one parallel worlds are defined, later-defined world comes on top of others. A track will see the material of the top layer, if it is nullptr, then one layer beneath. Thus, user has to make sure volumes in a parallel world should have nullptr as their materials except for volumes he/she really wants to overwrite.

Listing 4.22: Typical implementation in the main () to define a layered mass geometry.

```
// RunManager construction
//
G4RunManager* runManager = new G4RunManager;

// mass world
//
MyDetectorConstruction* massWorld = new MyDetectorConstruction;

// parallel world
//
G4String paraWorldName = "ParallelWorld";
massWorld->RegisterParallelWorld(new MyParallelWorld(paraWorldName));

// set mass world to run manager
//
runManager->SetUserInitialization(massWorld);

// physics list
//
G4VModularPhysicsList* physicsList = new FTFP_BERT;
physicsList->RegisterPhysics(new G4ParallelWorldPhysics(paraWorldName,true));
runManager->SetUserInitialization(physicsList);
```

For an information to advanced users, instead of using G4ParallelWorldPhysics physics constructor, once can define G4ParallelWorldProcess in his/her physics list and assign it only to some selected kind of particle types. In this case, this parallel world will be seen only by these kinds of particles.

# 4.9 Command-based scoring

#### 4.9.1 Introduction

Command-based scoring in GEANT4 defines G4MultiFunctionalDetector to a volume that is either defined in the tracking volume or created in a dedicated parallel world utilizing parallel navigation as described in the previous sections. The parallel world volume can be a scoring mesh or a scoring probe.

Once a scoring volume is defined, through interactive commands, the user can define arbitrary number of primitive scorers to score physics quantities and filters to be associated to each primitive scorer.

After scoring (i.e. a run), the user can dump scores into a file. Scores are automatically merged over worker threads. Also, for scoring mesh, scores can be visualized as well. All available UI commands are listed in List of built-in commands.

Command-based scoring is an optional functionality and the user has to explicitly define its use in the main(). To do this, the method G4ScoringManager::GetScoringManager() must be invoked right after the instantiation of G4RunManager. The scoring manager is a singleton object, and the pointer accessed above should not be deleted by the user.

Listing 4.23: A user main () to use the command-based scoring

```
#include "G4RunManager.hh"
#include "G4ScoringManager.hh"

int main(int argc,char** argv)
{
    // Construct the run manager
    G4RunManager * runManager = new G4RunManager;

    // Activate command-based scorer
    G4ScoringManager::GetScoringManager();
...
}
```

## 4.9.2 Defining a scoring volume in the tracking world

Scoring volume can be declared as a logical volume that is already defined as a part of the mass geometry through /score/create/realWorldLogVol <LV\_name> <anc\_lvl> command, where <LV\_name> is the name of G4LogicalVolume defined in the tracking world. If there are more than one physical volumes that share the same logical volume, scores are made for each individual physical volumes separately. Copy number of the physical volume is the index. If the physical volume is placed only once in its mother volume, but its (grand-)mother volume is duplicated, use the <anc\_lvl> parameter to indicate the ancestor level where the copy number should be taken as the index of the score.

## 4.9.3 Defining a scoring mesh

To define a scoring mesh, the user has to specify the following.

- Shape and name of the 3D scoring mesh. Currently, box and cylinder are the only available shapes.
- Size of the scoring mesh. Mesh size must be specified as "half width" similar to the arguments of G4Box or G4Tubs, respectively.
- Number of bins for each axes. Note that too high number causes immense memory consumption.
- Optionally, position and rotation of the mesh. If not specified, the mesh is positioned at the center of the world volume without rotation.

The following sample UI commands define a scoring mesh named boxMesh\_1, size of which is 2 m \* 2 m \* 2 m, and sliced into 30 cells along each axes.

Listing 4.24: UI commands to define a scoring mesh

```
#
# define scoring mesh
#
/score/create/boxMesh boxMesh_1
/score/mesh/boxSize 100. 100. 100. cm
/score/mesh/nBin 30 30 30
```

# 4.9.4 Defining a scoring probe

User may locate scoring "probes" at arbitrary locations. A "probe" is a virtual cube, the size of which has to be specified as "half width". Given probes are located in an artificial "parallel world", probes may overlap to the volumes defined in the mass geometry, as long as probes themselves are not overlapping to each other or protruding from the world volume.

In addition, the user may optionally set a material to the probe. Once a material is set to the probe, it overwrites the material(s) defined in the tracking geometry when a track enters the probe cube. This material has to be already instantiated in user's detector construction class or defined in G4NISTmanager.

Because of this overwriting, physics quantities that depend on material or density, e.g. energy deposition or dose, would be measured according to the specified material. Please note that this overwriting material obviously affects to the simulation results, so the size and number of probes should be reasonably small to avoid significant side effects.

If probes are placed more than once, all probes have the same scorers but score individually.

The following sample UI commands define a scoring probe named Probes, size of which is 10 cm \* 10 cm \* 10 cm, filled by G4\_Water, and located at three positions.

Listing 4.25: UI commands to define a scoring probe

```
#
# define scoring probe
#
/score/create/probe Probes 5. cm
/score/probe/material G4_WATER
/score/probe/locate 0. 0. 0. cm
/score/probe/locate 25. 0. 0. cm
/score/probe/locate 0. 25. 0. cm
```

# 4.9.5 Defining primitive scorers to a scoring volume

Once the scoring volume is defined, the user can define arbitrary scoring quantities and filters.

For a scoring volume the user may define arbitrary number primitive scorers to score for each physical volume (each cell for scoring mesh and each probe for scoring probe). For each scoring quantity, the use can set one filter. Please note that /score/filter commad affects on the immediately preceding scorer.

Names of scorers and filters must be unique for the scoring volume. It is possible to define more than one scorers of same kind with different names and, likely, with different filters. The list of available primitive scorers can be found at Table 4.1.

Defining a scoring volume and primitive scores should terminate with the /score/close command. The following sample UI commands define a scoring mesh named boxMesh\_1, size of which is 2 m \* 2 m \* 2 m, and sliced into 30 cells along each axes. For each cell energy deposition, number of steps of gamma, number of steps of electron and number of steps of positron are scored.

Listing 4.26: UI commands to define a scoring mesh and scorers

```
#
# define scoring mesh
#
/score/create/boxMesh boxMesh_1
/score/mesh/boxSize 100. 100. 100. cm
/score/mesh/nBin 30 30 30
#
# define scorers and filters
#
/score/quantity/energyDeposit eDep
/score/quantity/nOfStep nOfStepGamma
/score/filter/particle gammaFilter gamma
/score/quantity/nOfStep nOfStepEMinus
/score/quantity/nOfStep nOfStepEMinus
/score/filter/particle eMinusFilter e-
/score/quantity/nOfStep nOfStepEPlus
/score/filter/particle ePlusFilter e+
#
/score/close
#
```

# 4.9.6 Drawing scores for a scoring mesh

Once scores assigned to a scoring mesh are filled, it is possible to visualize these scores. The score is drawn on top of the mass geometry with the current visualization settings.




Fig. 4.9: Drawing scores in slices (left) and projection (right).

Scored data can be visualized using the commands /score/drawProjection and /score/drawColumn. For details, see examples/extended/runAndEvent/RE03.

By default, entries are linearly mapped to colors (gray - blue - green - red). This color mapping is implemented in G4DefaultLinearColorMap class, and registered to G4ScoringManager with the color map name "defaultLinearColorMap". The user may alternate color map by implementing a customised color map class derived from G4VScoreColorMap and register it to G4ScoringManager. Then, for each draw command, one can specify the preferred color map.

This drawing funactionality is available only for scoring mesh.

### 4.9.7 Writing scores to a file

It is possible to dump a score in a mesh (/score/dumpQuantityToFile command) or all scores in a mesh (/score/dumpAllQuantitiesToFile command) to a file. The default file format is the simple CSV. To alternate the file format, one should overwrite G4VScoreWriter class and register it to G4ScoringManager. The scoring manager takes ownership of the registered writer, and will delete it at the end of the job.

Please refer to /examples/extended/runAndEvent/RE03 for details.

# 4.9.8 Filling 1-D histogram

Through the template interface class G4TScoreHistFiller a primitive scorer can directly fill a 1-D histogram defined by G4Analysis module. Track-by-track or step-by-step filling allows command-based histogram such as energy spectrum. G4TScoreHistFiller template class must be instantiated in the user's code (e.g. in the constructor of user run action) with his/her choice of analysis data format.

Listing 4.27: Instantiation of G4TScoreHistFiller

```
#include "g4csv.hh"
#include "G4TScoreHistFiller.hh"

auto histFiller = new G4TScoreHistFiller<G4AnalysisManager>;
```

/score/fill1D <histID> <volName> <primName> <copNo> command defines the histogram <histID> to be filled by <primName> primitive scorer assigned to <volName> scoring volume. If scoring volume in tracking world or probe is placed more than once, fill1D command should be issued for each individual

copy number <copNo>.. Histogram <histID> must be defined through /analysis/h1/create command in advance to setting it to a primitive scorer. Scoring volume <volName> (either tracking world scorer or probe scorer) as well as the primitive scorer <primName> must be defined in advance, as well. This ifilling 1-D histogram functionality is not available for mesh scorer due to memory consumption concern. The list of primitive scorers available for 1-D histogram can be found at Table 4.1.

The following UI commands define a scoring probe named Probes, size of which is 10 cm \* 10 cm \* 10 cm, with two volume flux primitive scorers (one for total flux and the other for proton flux), and fill 1-D histograms of these two fluxes.

Listing 4.28: Filling 1-D histograms

```
#
# define scoring probe
#
/score/create/probe Probes 5. cm
/score/probe/locate 0. 0. 0. cm
#
# define flux scorers and filter
#
/score/quantity/volumeFlux volFlux
/score/quantity/volumeFlux protonFlux
/score/filter/particle protonFilter proton
/score/close
#
# define histograms
#
/analysis/h1/create volFlux Probes_volFlux 100 0.01 2000. MeV ! log
/analysis/h1/create protonFlux Probes_protonFlux 100 0.01 2000. MeV ! log
# filling histograms
#
/score/fill1D 1 Probes volFlux
/score/fill1D 2 Probes protonFlux
```

# 4.9.9 List of available primitive scorers

A primitive scorer is assigned to the scoring volume by /score/quantity/xxxxx <primName> <unit> where xxxxx is the name of primitive scorer listed below. Some of these primitive scorers can fill 1-D histogram described in the previous section.




Fig. 4.10: Histograms of total flux (top) and proton flux (bottom)

Table 4.1: List of primitive scorers.

	Table 4.1: List of	of primitive score	rs.	
Name of primitive	Description	Default unit	x-axis of 1-D	y-axis of 1-D
scorer	1 1 1		histogram	histogram
cellCharge	deposited charge in the volume	e+	n/a	n/a
cellFlux	sum of track length divided by the vol- ume	$cm^{-2}$	Ek in MeV	weighted cell flux
doseDeposit	deposited dose in the volume	Gy	dose per step in Gy	track weight
energyDeposit	deposited energy in the volume	MeV	eDep per step in MeV	track weight
flatSurfaceCurrent	surface current on - z surface to be used only for Box	$cm^{-2}$	Ek in MeV	weighted cur- rent
flatSurfaceFlux	surface flux (1/cos(theta)) on -z surface to be used only for Box	$cm^{-2}$	Ek in MeV	weighted flux
nOfCollision	number of steps made by physics interaction	n/a	n/a	n/a
nOfSecondary	number od secondary tracks generated in the volume	n/a	Ek in MeV	track weight
nOfStep	number of steps in the volume	n/a	step length in mm	entry (un- weighted)
nOfTerminatedTrack	numver of tracks terminated in the volume (due to de- cay, interaction, stop, etc.)	n/a	n/a	n/a
nOfTrack	number of tracks in the volume (includ- ing both passing and terminated tracks)	n/a	Ek in MeV	track weight
passageCellCurrent	number of tracks that pass through the volume	n/a	Ek in MeV	track weight
passageCellFlux	sum of track length divided by the vol- ume counted only for tracks that pass through the volume	$cm^{-2}$	Ek in MeV	weighted cell flux
passageTrackLength	sum of track length in the volume for tracks that pass through the volume	mm	track length in mm	entry (un- weighted)
population	number of tracks in the volume that are unique in an event	n/a	n/a	n/a
trackLength	total track length in the volume (includ- ing both passing and	mm	n/a	n/a
volumeFlux	number of tracks get- ting into the volume	Chapter n/a	4. Detector Det Ek in MeV	finition and Res track weight

## TRACKING AND PHYSICS

# 5.1 Tracking

## 5.1.1 Basic Concepts

### Philosophy of Tracking

All GEANT4 processes, including the transportation of particles, are treated generically. In spite of the name "tracking", particles are not transported in the tracking category. G4TrackingManager is an interface class which brokers transactions between the event, track and tracking categories. An instance of this class handles the message passing between the upper hierarchical object, which is the event manager, and lower hierarchical objects in the tracking category. The event manager is a singleton instance of the G4EventManager class.

The tracking manager receives a track from the event manager and takes the actions required to finish tracking it. G4TrackingManager aggregates the pointers to G4SteppingManager, G4Trajectory and G4UserTrackingAction. Also there is a "use" relation to G4Track and G4Step.

G4SteppingManager plays an essential role in tracking the particle. It takes care of all message passing between objects in the different categories relevant to transporting a particle (for example, geometry and interactions in matter). Its public method Stepping () steers the stepping of the particle. The algorithm to handle one step is given below.

- 1. If the particle stop (i.e. zero kinetic energy), each active AtRest process proposes a step length in time based on the interaction it describes. And the process proposing the smallest step length will be invoked.
- 2. Each active discrete or continuous process must propose a step length based on the interaction it describes. The smallest of these step lengths is taken.
- 3. The geometry navigator calculates "Safety", the distance to the next volume boundary. If the minimum physical-step-length from the processes is shorter than "Safety", the physical-step-length is selected as the next step length. In this case, no further geometrical calculations will be performed.
- 4. If the minimum physical-step-length from the processes is longer than "Safety", the distance to the next boundary is re-calculated.
- 5. The smaller of the minimum physical-step-length and the geometric step length is taken.
- 6. All active continuous processes are invoked. Note that the particle's kinetic energy will be updated only after all invoked processes have completed. The change in kinetic energy will be the sum of the contributions from these processes.
- 7. The current track properties are updated before discrete processes are invoked. In the same time, the secondary particles created by processes are stored in SecondaryList. The updated properties are:
  - the kinetic energy of the current track particle (note that 'sumEnergyChange' is the sum of the energy difference before and after each process invocation)
  - position and time
- 8. The kinetic energy of the particle is checked to see whether or not it has been terminated by a continuous process. If the kinetic energy goes down to zero, AtRest processes will be applied at the next step if applicable.
- 9. The discrete process is invoked. After the invocation,
  - the energy, position and time of the current track particle are updated, and

- the secondaries are stored in SecondaryList.
- 10. The track is checked to see whether or not it has been terminated by the discrete process.
- 11. "Safety" is updated.
- 12. If the step was limited by the volume boundary, push the particle into the next volume.
- 13. Handle hit information.
- 14. Invoke the user intervention G4UserSteppingAction.
- 15. Save data to Trajectory.
- 16. Update the mean free paths of the discrete processes.
- 17. If the parent particle is still alive, reset the maximum interaction length of the discrete process which has occurred.
- 18. One step completed.

#### What is a Process?

Only processes can change information of G4Track and add secondary tracks via ParticleChange. G4VProcess is a base class of all processes and it has 3 kinds of DoIt and GetPhysicalInteraction methods in order to describe interactions generically. If a user want to modify information of G4Track, he (or she) SHOULD create a special process for the purpose and register the process to the particle.

#### What is a Track?

G4Track keeps 'current' information of the particle. (i.e. energy,momentum, position ,time and so on) and has 'static' information (i.e. mass, charge, life and so on) also. Note that G4Track keeps information at the beginning of the step while the AlongStepDoIts are being invoked for the step in progress. After finishing all AlongStepDoIts, G4Track is updated. On the other hand, G4Track is updated after each invocation of a PostStepDoIt.

### What is a Step?

G4Step stores the transient information of a step. This includes the two endpoints of the step, PreStepPoint and PostStepPoint, which contain the points' coordinates and the volumes containing the points. G4Step also stores the change in track properties between the two points. These properties, such as energy and momentum, are updated as the various active processes are invoked.

#### What is a ParticleChange?

Processes do NOT change any information of G4Track directly in their DoIt. Instead, they proposes changes as a result of interactions by using ParticleChange. After each DoIt, ParticleChange updates PostStepPoint based on proposed changes. Then, G4Track is updated after finishing all AlongStepDoIts and after each PostStepDoIt.

# 5.1.2 Access to Track and Step Information

#### **How to Get Track Information**

Track information may be accessed by invoking various Get methods provided in the G4Track class. For details, see the G4Track.hh header file in \$G4INCLUDE. Typical information available includes:

- (x,y,z)
- Global time (time since the event was created)
- Local time (time since the track was created)
- Proper time (time in its rest frame since the track was created)
- Momentum direction ( unit vector )
- Kinetic energy
- · Accumulated geometrical track length
- · Accumulated true track length
- Pointer to dynamic particle
- Pointer to physical volume
- Track ID number

- Track ID number of the parent
- Current step number
- · Track status
- (x,y,z) at the start point (vertex position) of the track
- Momentum direction at the start point (vertex position) of the track
- Kinetic energy at the start point (vertex position) of the track
- Pointer to the process which created the current track

#### **How to Get Step Information**

Step and step-point information can be retrieved by invoking various Get methods provided in the G4StepPoint classes..

#### Information in G4Step includes:

- Pointers to PreStep and PostStepPoint
- Geometrical step length (step length before the correction of multiple scattering)
- True step length (step length after the correction of multiple scattering)
- Increment of position and time between PreStepPoint and PostStepPoint
- Increment of momentum and energy between PreStepPoint and PostStepPoint. (Note: to get the energy deposited in the step, you cannot use this 'Delta energy'. You have to use 'Total energy deposit' as below.)
- Pointer to G4Track
- Total energy deposited during the step this is the sum of
  - the energy deposited by the energy loss process, and
  - the energy lost by secondaries which have NOT been generated because each of their energies was below the cut threshold
- Energy deposited not by ionization during the step
- Secondary tracks created during tracking for the current track.
  - NOTE: all secondaries are included. NOT only secondaries created in the CURRENT step.

Information in G4StepPoint (PreStepPoint and PostStepPoint) includes:

- (x, y, z, t)
- (px, py, pz, Ek)
- Momentum direction (unit vector)
- Pointers to physical volumes
- Safety
- Beta, gamma
- Polarization
- Step status
- Pointer to the physics process which defined the current step and its DoIt type
- Pointer to the physics process which defined the previous step and its DoIt type
- · Total track length
- Global time (time since the current event began)
- Local time (time since the current track began)
- Proper time

### How to Get "particle change"

Particle change information can be accessed by invoking various Get methods provided in the G4ParticleChange class. Typical information available includes:

- final momentum direction of the parent particle
- final kinetic energy of the parent particle
- final position of the parent particle
- final global time of the parent particle
- final proper time of the parent particle

5.1. Tracking 205

- final polarization of the parent particle
- status of the parent particle (G4TrackStatus)
- true step length (this is used by multiple scattering to store the result of the transformation from the geometrical step length to the true step length)
- local energy deposited this consists of either
  - energy deposited by the energy loss process, or
  - the energy lost by secondaries which have NOT been generated because each of their energies was below the cut threshold.
- number of secondaries particles
- list of secondary particles (list of G4Track)

## 5.1.3 Handling of Secondary Particles

Secondary particles are passed as G4Tracks from a physics process to tracking. G4ParticleChange provides the following four methods for a physics process:

```
    AddSecondary( G4Track* aSecondary )
    AddSecondary( G4DynamicParticle* aSecondary )
    AddSecondary( G4DynamicParticle* aSecondary, G4ThreeVector position )
    AddSecondary( G4DynamicParticle* aSecondary, G4double time)
```

In all but the first, the construction of G4Track is done in the methods using information given by the arguments.

### 5.1.4 User Actions

There are two classes which allow the user to intervene in the tracking. These are:

- G4UserTrackingAction, and
- G4UserSteppingAction.

Each provides methods which allow the user access to the GEANT4 kernel at specific points in the tracking.

**Note:** Users SHOULD NOT (and CAN NOT) change G4Track in UserSteppingAction. The only exception is the TrackStatus.

**Note:** Users have to be cautious to implement an unnatural/unphysical action in these user actions. See the section *Killing Tracks in User Actions and Energy Conservation* for more details.

## 5.1.5 Verbose Outputs

The verbose information output flag can be turned on or off. The amount of information printed about the track/step, from brief to very detailed, can be controlled by the value of the verbose flag, for example,

```
G4UImanager* UI = G4UImanager::GetUIpointer();
UI->ApplyCommand("/tracking/verbose 1");
```

# 5.1.6 Trajectory and Trajectory Point

## G4Trajectory and G4TrajectoryPoint

G4Trajectory and G4TrajectoryPoint are default concrete classes provided by GEANT4, which are derived from the G4VTrajectory and G4VTrajectoryPoint base classes, respectively. A G4Trajectory class object is created by G4TrackingManager when a G4Track is passed from the G4EventManager. G4Trajectory has the following data members:

- ID numbers of the track and the track's parent
- particle name, charge, and PDG code
- a collection of G4TrajectoryPoint pointers

G4TrajectoryPoint corresponds to a step point along the path followed by the track. Its position is given by a G4ThreeVector. A G4TrajectoryPoint class object is created in the AppendStep() method of G4Trajectory and this method is invoked by G4TrackingManager at the end of each step. The first point is created when the G4Trajectory is created, thus the first point is the original vertex.

The creation of a trajectory can be controlled by invoking G4TrackingManager::SetStoreTrajectory (G4bool). The UI command /tracking/storeTrajectory \_bool\_ does the same. The user can set this flag for each individual track from his/her G4UserTrackingAction::PreUserTrackingAction() method.

**Note:** The user should not create trajectories for secondaries in a shower due to the large amount of memory consumed.

All the created trajectories in an event are stored in G4TrajectoryContainer class object and this object will be kept by G4Event. To draw or print trajectories generated in an event, the user may invoke the DrawTrajectory() or ShowTrajectory() methods of G4VTrajectory, respectively, from his/her G4UserEventAction::EndOfEventAction(). The geometry must be drawn before the trajectory drawing. The color of the drawn trajectory depends on the particle charge:

negative: redneutral: greenpositive: blue

**Note:** Due to improvements in G4Navigator, a track can execute more than one turn of its spiral trajectory without being broken into smaller steps as long as the trajectory does not cross a geometrical boundary. Thus a drawn trajectory may not be circular.

## **Customizing trajectory and trajectory point**

G4Track and G4Step are transient classes; they are not available at the end of the event. Thus, the concrete classes G4VTrajectory and G4VTrajectoryPoint are the only ones a user may employ for end-of-event analysis or for persistency. As mentioned above, the default classes which GEANT4 provides, i.e. G4Trajectory and G4TrajectoryPoint, have only very primitive quantities. The user can customize his/her own trajectory and trajectory point classes by deriving directly from the respective base classes.

To use the customized trajectory, the user must construct a concrete trajectory class object in the G4UserTrackingAction::PreUserTrackingAction() method and make its pointer available to G4TrackingManager by using the SetTrajectory() method. The customized trajectory point class object must be constructed in the AppendStep() method of the user's implementation of the trajectory class. This AppendStep() method will be invoked by G4TrackingManager.

5.1. Tracking 207

To customize trajectory drawing, the user can override the DrawTrajectory () method in his/her own trajectory class.

When a customized version of G4Trajectory declares any new class variables, *operator new* and *operator delete* must be provided. It is also useful to check that the allocation size in *operator new* is equal to <code>sizeof(G4Trajectory)</code>. These two points do not apply to G4VTrajectory because it has no *operator new* or *operator delete*.

# **5.2 Physics Processes**

#### 5.2.1 Overview

Physics processes describe how particles interact with a material. Seven major categories of processes are provided by GEANT4:

- 1. electromagnetic,
- 2. hadronic,
- 3. decay,
- 4. photolepton-hadron,
- 5. optical,
- 6. parameterization, and
- 7. transportation.

The generalization and abstraction of physics processes is a key issue in the design of GEANT4. All physics processes are treated in the same manner from the tracking point of view. The GEANT4 approach enables anyone to create a process and assign it to a particle type. This openness should allow the creation of processes for novel, domain-specific or customised purposes by individuals or groups of users.

Each process has two groups of methods which play an important role in tracking, GetPhysicalInteractionLength (GPIL) and DoIt. The GPIL method gives the step length from the current space-time point to the next space-time point. It does this by calculating the probability of interaction based on the process's cross section information. At the end of this step the DoIt method should be invoked. The DoIt method implements the details of the interaction, changing the particle's energy, momentum, direction and position, and producing secondary tracks if required. These changes are recorded as G4VParticleChange objects (see Particle change).

#### **G4VProcess**

G4VProcess is the base class for all physics processes. Each physics process must implement virtual methods of G4VProcess which describe the interaction (DoIt) and determine when an interaction should occur (GPIL). In order to accommodate various types of interactions G4VProcess provides three DoIt methods:

- G4VParticleChange\* AlongStepDoIt( const G4Track& track, const G4Step& stepData )
  - This method is invoked while G4SteppingManager is transporting a particle through one step. The corresponding AlongStepDoIt for each defined process is applied for every step regardless of which process produces the minimum step length. Each resulting change to the track information is recorded and accumulated in G4Step. After all processes have been invoked, changes due to AlongStepDoIt are applied to G4Track, including the particle relocation and the safety update. Note that after the invocation of AlongStepDoIt, the endpoint of the G4Track object is in a new volume if the step was limited by a geometric boundary. In order to obtain information about the old volume, G4Step must be accessed, since it contains information about both endpoints of a step.
- G4VParticleChange\* PostStepDoIt( const G4Track& track, const G4Step& stepData )

This method is invoked at the end point of a step, only if its process has produced the minimum step length, or if the process is forced to occur. G4Track will be updated after each invocation of PostStepDoIt, in contrast to the AlongStepDoIt method.

• G4VParticleChange\* AtRestDoIt( const G4Track& track, const G4Step& stepData )

This method is invoked only for stopped particles, and only if its process produced the minimum step length or the process is forced to occur.

For each of the above DoIt methods G4VProcess provides a corresponding pure virtual GPIL method:

• PostStepGetPhysicalInteractionLength

This method generates the step length allowed by its process. It also provides a flag to force the interaction to occur regardless of its step length.

• AlongStepGetPhysicalInteractionLength

```
G4double AlongStepGetPhysicalInteractionLength(const G4Track& track,
G4double previousStepSize,
G4double currentMinimumStep,
G4double& proposedSafety,
G4GPILSelection* selection)
```

This method generates the step length allowed by its process.

• AtRestGetPhysicalInteractionLength

```
G4double AtRestGetPhysicalInteractionLength(const G4Track& track, G4ForceCondition* condition)
```

This method generates the step length in time allowed by its process. It also provides a flag to force the interaction to occur regardless of its step length.

Other pure virtual methods in G4VProcess follow:

- virtual G4bool IsApplicable(const G4ParticleDefinition&) returns true if this process object is applicable to the particle type.
- virtual void PreparePhysicsTable(const G4ParticleDefinition&) and
- virtual void BuildPhysicsTable(const G4ParticleDefinition&) is messaged by the process manager, whenever cross section tables should be prepared and rebuilt due to changing cut-off values. It is not mandatory if the process is not affected by cut-off values.
- virtual void StartTracking() and
- virtual void EndTracking()

are messaged by the tracking manager at the beginning and end of tracking the current track.

#### Other base classes for processes

Specialized processes may be derived from seven additional virtual base classes which are themselves derived from G4VProcess. Three of these classes are used for simple processes:

**G4VRestProcess** Processes using only the AtRestDoIt method.

example: neutron capture

**G4VDiscreteProcess** Processes using only the PostStepDoIt method.

example: Compton scattering, hadron inelastic interaction

The other four classes are provided for rather complex processes:

**G4VContinuousDiscreteProcess** Processes using both AlongStepDoIt and PostStepDoIt methods. example: transportation, ionisation(energy loss and delta ray)

**G4VRestDiscreteProcess** Processes using both AtRestDoIt and PostStepDoIt methods. example: positron annihilation, decay (both in flight and at rest)

G4VRestContinuousProcess Processes using both AtRestDoIt and AlongStepDoIt methods.

G4VRestContinuousDiscreteProcess Processes using AtRestDoIt, AlongStepDoIt and PostStepDoIt methods.

### Particle change

G4VParticleChange and its descendants are used to store the final state information of the track, including secondary tracks, which has been generated by the DoIt methods. The instance of G4VParticleChange is the only object whose information is updated by the physics processes, hence it is responsible for updating the step. The stepping manager collects secondary tracks and only sends requests via particle change to update G4Step.

G4VParticleChange is introduced as an abstract class. It has a minimal set of methods for updating G4Step and handling secondaries. A physics process can therefore define its own particle change derived from G4VParticleChange. Three pure virtual methods are provided,

- virtual G4Step\* UpdateStepForAtRest( G4Step\* step),
- virtual G4Step\* UpdateStepForAlongStep( G4Step\* step ), and
- virtual G4Step\* UpdateStepForPostStep( G4Step\* step),

which correspond to the three DoIt methods of G4VProcess. Each derived class should implement these methods.

# **5.2.2 Electromagnetic Interactions**

This section summarizes the electromagnetic (EM) physics processes which are provided with GEANT4. Extended information are available at EM web pages. For details on the implementation of these processes please refer to the Physics Reference Manual.

To use the electromagnetic physics data files are needed. The user should set the environment variable G4LEDATA to the directory with this files. These files are distributed together with GEANT4 and can be obtained via the GEANT4 download web page.

#### **Electromagnetic Processes**

The following is a summary of the electromagnetic processes available in GEANT4.

- Photon processes
  - Gamma conversion (also called pair production, class name G4GammaConversion)
  - Photo-electric effect (class name G4PhotoElectricEffect)
  - Compton scattering (class name G4ComptonScattering)
  - Rayleigh scattering (class name G4RayleighScattering)
  - Muon pair production (class name G4GammaConversionToMuons)
  - General gamma process (class name G4GeneralGammaProcess)
- Electron/positron processes
  - Ionisation and delta ray production (class name G4eIonisation)
  - Bremsstrahlung (class name G4eBremsstrahlung)
  - e+e-pair production (class name G4ePairProduction)
  - Multiple scattering (class name G4eMultipleScattering)
  - Positron annihilation into two gammas (class name G4eplusAnnihilation)
  - Positron annihilation into two muons (class name G4AnnihiToMuPair)
  - Positron annihilation into hadrons (class name G4eeToHadrons)
- Muon processes
  - Ionisation and delta ray production (class name G4MuIonisation)

- Bremsstrahlung (class name G4MuBremsstrahlung)
- e+e-pair production (class name G4MuPairProduction)
- Multiple scattering (class name G4MuMultipleScattering)
- Hadron/ion processes
  - Ionisation (class name G4hIonisation)
  - Ionisation for ions (class name G4ionIonisation)
  - Ionisation for heavy exotic particles (class name G4hhIonisation)
  - Ionisation for classical magnetic monopole (class name G4mplIonisation)
  - Multiple scattering (class name G4hMultipleScattering)
  - Bremsstrahlung (class name G4hBremsstrahlung)
  - e+e-pair production (class name G4hPairProduction)
- Coulomb scattering processes
  - Alternative process for simulation of single Coulomb scattering of all charged particles (class name G4CoulombScattering)
  - Alternative process for simulation of single Coulomb scattering of ions (class name G4ScreenedNuclearRecoil)
- Processes for simulation of polarized electron and gamma beams
  - Compton scattering of circularly polarized gamma beam on polarized target (class name G4PolarizedCompton)
  - Pair production induced by circularly polarized gamma beam (class name G4PolarizedGammaConversion)
  - Photo-electric effect induced by circularly polarized gamma beam (class name G4PolarizedPhotoElectricEffect)
  - Bremsstrahlung of polarized electrons and positrons (class name G4ePolarizedBremsstrahlung)
  - Ionisation of polarized electron and positron beam (class name G4ePolarizedIonisation)
  - Annihilation of polarized positrons (class name G4eplusPolarizedAnnihilation)
- Processes for simulation of X-rays and optical protons production by charged particles
  - Synchrotron radiation (class name G4SynchrotronRadiation)
  - Transition radiation (class name G4TransitionRadiation)
  - Cerenkov radiation (class name G4Cerenkov)
  - Scintillations (class name G4Scintillation)
- The processes described above use physics model classes, which may be combined according to particle energy. It is possible to change the energy range over which different models are valid, and to apply other models specific to particle type, energy range, and G4Region. Models, which are used in the default EM Physics List, are mainly from the standard EM sub-library:
  - Photoelectric effect (class name G4LivermorePhotoElectricModel)
  - Compton scattering (class name G4KleinNishinaCompton)
  - Electron/positron pair production (class name G4PairProductionRelModel)
  - Rayleigh scattering (class name G4LivermoreRayleighModel)
  - Multiple scattering (class name G4UrbanMscModel)
  - Multiple scattering (class name G4WentzelVIModel)
  - Single Coulomb scattering (class name G4eCoulombScatteringModel)
  - Electron ionisation (class name G4MollerBhabhaModel)
  - Electron/positron bremsstrahlung (class name G4SeltzerBergerModel)
  - Electron/positron bremsstrahlung (class name G4eBremsstrahlungRelModel)
  - Positron annihilation into 2 gamma (class name G4eeToTwoGammaModel)
  - Muon and hadron low-energy ionisation (class name G4BraggModel)
  - Ion low-energy ionisation (class name G4BraggIonModel)
  - Anti-particle low-energy ionisation (class name G4ICRU73Q0Model)
  - Muon and hadron ionisation (class name G4BetheBlochModel)
  - Muon ionisation (class name G4MuBetheBlochModel)
  - Muon bremsstrahlung (class name G4MuBremsstrahlungModel)
  - Hadron bremsstrahlung (class name G4hBremsstrahlungModel)
  - Muon e+e- pair production (class name G4MuPairProductionModel)

- Hadron e+e- pair production (class name G4hPairProductionModel)
- The following alternative models are available in the standard EM sub-library:
  - Ionisation in thin absorbers (class name G4PAIModel)
  - Ionisation in thin absorbers (class name G4PAIPhotModel)
  - Ionisation in low-density media (class name G4BraggIonGasModel)
  - Ionisation in low-density media (class name G4BetheBlochIonGasModel)
  - Ionisation of relativistic ions (class name G4AtimaEnergyLossModel)
  - Ionisation of ions (class name G4LindhardSorensenIonModel)
  - Electron/positron pair production (class name G4BetheHeitlerModel)
  - Electron/positron pair production (class name G4BetheHeitler5DModel)
  - Positron annihilation into 2 or 3 gamma (class name G4eplusTo2GammaOKVIModel)
  - Multiple scattering (class name G4GoudsmitSaundersonMscModel)
  - Multiple scattering (class name G4LowEWentzelVIModel)
  - Single scattering (class name G4eSingleCoulombScatteringModel)
  - Single scattering (class name G4hCoulombScatteringModel)
  - Single scattering (class name G4IonCoulombScatteringModel)

In the low-energy sub-library there are alternative models (more detailes see below):

- Photoelectric effect (class name G4PenelopePhotoElectricModel)
- Compton scattering (class name G4PenelopeComptonModel)
- Compton scattering (class name G4LivermoreComptonModel)
- Compton scattering (class name G4LivermorePolarizedComptonModel)
- Compton scattering (class name G4LowEPComptonModel)
- Compton scattering (class name G4LowEPPolarizedComptonModel)
- Gamma conversion to e+e- pair (class name G4LivermoreGammaConversionModel)
- Gamma conversion to e+e- pair (class name G4LivermoreGammaConversion5DModel)
- Gamma conversion to e+e- pair (class name G4PenelopeGammaConversionModel)
- Rayleigh scattering (class name G4JAEAElasticScatteringModel)
- Rayleigh scattering (class name G4JAEAPolarizedElasticScatteringModel)
- Rayleigh scattering (class name G4LivermorePolarizedRayleighModel)
- Rayleigh scattering (class name G4PenelopeRayleighModel)
- Electron ionisation (class name G4LivermoreIonisationModel)
- Electron and positron ionisation (class name G4PositronIonisationModel)
- Ion ionisation (class name G4IonParametrisedLossModel)
- Electron, proton, alpha, and ion ionisation (class name G4MicroElecInelastic)
- Electron, proton, alpha, and ion elastic scattering (class name G4MicroElecElastic)

It is recommended to use physics constructor classes provided with reference physics lists (in subdirectory source/physics\_lists/constructors/electromagnetic of the GEANT4 source distribution):

- default EM physics, multiple scattering is simulated with "UseSafety" type of step limitation by combined G4WentzelVIModel and G4eCoulombScatteringModel for all particle types, for of e+- below 100 MeV G4UrbanMscModel is used, G4LivermorePhotoElectricModel is used for simulation of the photo-electric effect, the Rayleigh scattering process is enabled below 1 MeV, physics tables are built from 100 eV to 100 TeV, 7 bins per energy decade of physics tables are used (class name G4EmStandardPhysics),
- optional EM physics providing fast but less accurate electron transport due to "Minimal" method of step limitation by multiple scattering, RangeFactor = 0.2, Rayleigh scattering is disabled, photo-electric effect is using G4PEEffectFluoModel, and enabled "ApplyCuts" option (class name G4EmStandardPhysics\_option1),
- optional EM physics providing fast but less accurate electron transport due to "Minimal" method of step limitation by multiple scattering, RangeFactor = 0.2, "Simple" method of step limitation by multiple scattering, Rayleigh scattering is disabled, and photo-electric effect is using G4PEEffectFluoModel (class name G4EmStandardPhysics\_option2)
- EM physics for simulation with high accuracy due to "UseDistanceToBoundary" multiple scattering step limitation and usage of G4UrbanMscModel for all charged particles, reduced *finalRange* parameter of stepping function optimized per particle type, alternative model G4KleinNishinaModel for Comp-

ton scattering, enabled fluorescence, enabled nuclear stopping, G4Generator2BS angular generator for bremsstrahlung, G4IonParameterisedLossModel for ion ionisation, G4ePairProduction for electron/positron, 20 bins energy decade of physics tables, and 10 eV low-energy limit for tables (class name G4EmStandardPhysics\_option3)

- Combination of EM models for simulation with high accuracy includes multiple scattering with "UseSafety-Plus" type of step limitation by combined G4WentzelVIModel and G4eCoulombScatteringModel for all particle types, for of e+- below 100 MeV G4GoudsmitSaundersonMscModel is used, RangeFactor = 0.08, Scin = 3 (error free stepping near geometry boundaries), reduced finalRange parameter of stepping function optimized per particle type, enabled fluorescence, enabled nuclear stopping, enable accurate angular generator for ionisation models, G4LowEPComptonModel below 20 MeV and G4KleinNishinaModel above, G4BetheHeitler5DModel for gamma conversion, G4LivermoreIonisationModel for electrons and positrons below 100 keV, G4IonParameterisedLossModel for ion ionisation, G4Generator2BS angular generator for bremsstrahlung, G4ePairProduction for electron/positron, and 20 bins per energy decade of physics tables, (class name G4EmStandardPhysics\_option4)
- Models based on Livermore data bases for electrons and gamma, enabled Rayleigh scattering, enabled fluorescence, G4BetheHeitler5DModel is used for gamma conversion, enabled nuclear stopping, enable accurate angular generator for ionisation models, G4IonParameterisedLossModel for ion ionisation, for of e+- below 100 MeV G4GoudsmitSaundersonMscModel is used with "UseSafetyPlus" multiple scattering step limitation, RangeFactor = 0.08, Scin = 3 (error free stepping near geometry boundaries), G4Generator2BS angular generator for bremsstrahlung, G4ePairProduction for electron/positron, and 20 bins per energy decade of physics tables, (G4EmLivermorePhysics);
- Models based on Livermore data bases and new model for Compton scattering G4LowEPComptonModel, G4BetheHeitler5DModel is used for gamma conversion, low-energy model of multiple scattering G4LowEWenzelMscModel, and G4LindhardSorensenIonModel, G4hBremsstrahlung and G4hPairProduction for ions (G4EmLowEPPhysics);
- Penelope2008 models for electrons, positrons and gamma, enabled Rayleigh scattering, enabled fluorescence, enabled nuclear stopping, enable accurate angular generator for ionisation models, G4IonParameterisedLossModel for ion ionisation, for of e+- below 100 MeV G4GoudsmitSaundersonMscModel is used with "UseSafetyPlus" multiple scattering step limitation, RangeFactor = 0.08, Scin = 3 (error free stepping near geometry boundaries), and 20 bins per energy decade of physics tables, (G4EmPenelopePhysics);
- Experimental physics with multiple scattering below 100 MeV simulated G4GoudsmitSaundersonMscModel done default is top of the physics (G4EmStandardPhysicsGS);
- Experimental physics is done on top of the default EM physics with multiple scattering of e+- below 100 MeV simulated by a combination of G4UrbanMscModel below 1 MeV and G4WentzelVIModel, G4eCoulombScatteringModel, and for ions G4LindhardSorensenIonModel (G4EmStandardPhysicsWVI);
- Experimental physics with single scattering models instead of multiple scattering is done on top of the default EM physics, for all leptons and hadrons G4eCoulombScatteringModel is used, for ions G4IonCoulombScatteringModel (G4EmStandardPhysicsSS);
- Low-energy GEANT4-DNA physics (G4EmDNAPhysics).
- Alternative low-energy GEANT4-DNA physics constructors (G4EmDNAPhysics\_optionX, where X is 1 to 8). Refer to GEANT4-DNA section.

Examples of the registration of these physics constructor and construction of alternative combinations of options are shown in basic, extended and advanced examples, which can be found in the subdirectories examples/basic, examples/extended/electromagnetic, examples/medical, examples/advanced, and of the GEANT4 source distribution. Examples illustrating the use of electromagnetic processes are available as part of the GEANT4 release.

**Options** are available for steering of electromagnetic processes. These options may be invoked either by UI commands or by the new C++ interface class G4EmParameters. The interface G4EmParameters::Instance() is thread safe, EM parameters are shared between threads, and parameters are shared between all EM processes. Parameters may be modified at G4State PreInit or G4State Idle states of GEANT4. Note, that when any of EM physics constructor

is instantiated a default set of EM parameters for this EM physics configuration is defined. So, parameters modification should be applied only after. This class has the following public methods:

- Dump()
- StreamInfo(std::ostream&)
- SetDefaults()
- SetLossFluctuations(G4bool)
- SetBuildCSDARange(G4bool)
- SetLPM(G4bool)
- SetUseCutAsFinalRange(G4bool)
- SetApplyCuts(G4bool)
- SetFluo(G4bool val)
- SetBeardenFluoDir(G4bool val)
- SetANSTOFluoDir(G4bool val)
- SetAuger(G4bool val)
- SetPixe(G4bool val)
- SetDeexcitationIgnoreCut(G4bool val)
- SetLateralDisplacement(G4bool val)
- SetLateralDisplacementAlg96(G4bool val)
- SetMuHadLateralDisplacement(G4bool val)
- ActivateAngularGeneratorForIonisation(G4bool val)
- SetUseMottCorrection(G4bool val)
- SetBirksActive(G4bool val)
- SetUseICRU90Data(G4bool val)
- SetDNAFast(G4bool val)
- SetDNAStationary(G4bool val)
- SetDNAElectronMsc(G4bool val)
- SetGeneralProcessActive(G4bool val)
- SetEnableSamplingTable(G4bool val)
- SetEnablePolarisation(G4bool val)
- SetDirectionalSplitting(G4bool val)
- SetQuantumEntanglement(G4bool val)
- SetRetrieveMuDataFromFile(G4bool val)
- SetOnIsolated(G4bool val)
- ActivateDNA(G4bool val)
- SetIsPrintedFlag(G4bool val);
- SetMinEnergy(G4double)
- SetMaxEnergy(G4double)
- SetMaxEnergyForCSDARange(G4double)
- SetLowestElectronEnergy(G4double)
- SetLowestMuHadEnergy(G4double)
- SetLowestTripletEnergy(G4double)
- SetLinearLossLimit(G4double)
- SetBremsstrahlungTh(G4double)
- SetMuHadBremsstrahlungTh(G4double val)
- SetLambdaFactor(G4double)
- SetFactorForAngleLimit(G4double)
- SetMscThetaLimit(G4double)
- SetMscEnergyLimit(G4double)
- SetMscRangeFactor(G4double)
- SetMscMuHadRangeFactor(G4double)
- SetMscGeomFactor(G4double)
- SetMscSafetyFactor(G4double)
- SetMscLambdaLimit(G4double)

- SetMscSkin(G4double)
- SetScreeningFactor(G4double)
- SetMaxNIELEnergy(G4double)
- SetMaxEnergyFor5DMuPair(G4double)
- SetStepFunction(G4double, G4double)
- SetStepFunctionMuHad(G4double, G4double)
- SetStepFunctionLightIons(G4double, G4double);
- SetStepFunctionIons(G4double, G4double);
- SetDirectionalSplittingRadius(G4double)
- SetDirectionalSplittingTarget(const G4ThreeVector&)
- SetNumberOfBinsPerDecade(G4int)
- SetVerbose(G4int)
- SetWorkerVerbose(G4int)
- SetMscStepLimitType(G4MscStepLimitType val)
- SetMscMuHadStepLimitType(G4MscStepLimitType val)
- SetSingleScatteringType(G4eSingleScatteringType val)
- SetNuclearFormFactorType(G4NuclearFormFactorType val)
- SetDNAeSolvationSubType(G4DNAModelSubType val)
- SetConversionType(G4int val)
- SetPIXECrossSectionModel(const G4String&)
- SetPIXEElectronCrossSectionModel(const G4String&)
- SetLivermoreDataDir(const G4String&)
- AddPAIModel(const G4String& particle, const G4String& region, const G4String& type)
- AddMicroElec(const G4String& region)
- AddDNA(const G4String& region, const G4String& type)
- AddPhysics(const G4String& region, const G4String& physics type)
- SetSubCutRegion(const G4String& region)
- SetDeexActiveRegion(const G4String& region, G4bool, G4bool, G4bool)
- SetProcessBiasingFactor(const G4String& process, G4double, G4bool)
- ActivateForcedInteraction(const G4String& process, const G4String& region, G4double, G4bool)
- ActivateSecondaryBiasing(const G4String& process, const G4String& region, G4double, G4double)
- SetEmSaturation(G4EmSaturation\*)

The corresponding UI command can be accessed in the UI subdirectories "/process/eLoss", "/process/em", and "/process/msc". The following types of step limitation by multiple scattering are available:

- fMinimal simplified step limitation (used in \_EMV and \_EMX Physics Lists)
- fUseSafety default
- fUseDistanceToBoundary advance method of step limitation used in EM examples, required parameter skin > 0, should be used for setup without magnetic field
- fUseSafetyPlus advanced method may be used with magnetic field

**G4EmCalculator** is a class which provides access to cross sections and stopping powers. This class can be used anywhere in the user code provided the physics list has already been initialised (G4State\_Idle). G4EmCalculator has "Get" methods which can be applied to materials for which physics tables are already built, and "Compute" methods which can be applied to any material defined in the application or existing in the GEANT4 internal database. The public methods of this class are:

- GetDEDX(kinEnergy,particle,material,const G4Region\* r=nullptr)
- GetRangeFromRestrictedDEDX(kinEnergy,particle,material,const G4Region\* r=nullptr)
- GetCSDARange(kinEnergy,particle,material,const G4Region\* r=nullptr)
- GetRange(kinEnergy,particle,material,const G4Region\* r=nullptr)
- GetKinEnergy(range,particle,material,const G4Region\* r=nullptr)
- GetCrossSectionPerVolume(kinEnergy,particle,material,const G4Region\* r=nullptr)
- GetShellIonisationCrossSectionPerAtom(particle,Z,shell,kinEnergy)
- GetMeanFreePath(kinEnergy,particle,material,const G4Region\* r=nullptr)

- PrintDEDXTable(particle)
- PrintRangeTable(particle)
- PrintInverseRangeTable(particle)
- ComputeDEDX(kinEnergy,particle,process,material,cut=DBL\_MAX)
- ComputeElectronicDEDX(kinEnergy,particle,material,cut=DBL MAX)
- ComputeDEDXForCutInRange(kinEnergy,particle,material,cut=DBL\_MAX)
- ComputeNuclearDEDX(kinEnergy,particle,material,cut=DBL MAX)
- ComputeTotalDEDX(kinEnergy,particle,material,cut=DBL\_MAX)
- ComputeCrossSectionPerVolume(kinEnergy,particle,process,material,cut=nullptr)
- ComputeCrossSectionPerAtom(kinEnergy,particle,process,Z,A,cut=nullptr)
- ComputeCrossSectionPerShell(kinEnergy,particle,process,Z,shellIdx,cut=nullptr)
- ComputeGammaAttenuationLength(kinEnergy,material)
- ComputeShellIonisationCrossSectionPerAtom(particle,Z,shell,kinEnergy)
- ComputeMeanFreePath(kinEnergy,particle,process,material,cut=nullptr)
- ComputeEnergyCutFromRangeCut(range,particle,material)
- FindParticle(const G4String&)
- FindIon(G4int Z, G4int A)
- FindMaterial(const G4String&)
- FindRegion(const G4String&)
- FindCouple(const G4Material\*, const const G4Region\* r=nullptr)
- FindProcess(particle, const G4String& processName)
- SetVerbose(G4int)

For these interfaces, particles, materials, or processes may be pointers (const G4ParticleDefinition\*, const G4Material\*) or strings with names (const G4String&).

**G4NIELCalculator** is a class which provides computation of NIEL energy loss at a step independently on cuts and tracking. G4NIELCalculator has follow methods:

- ComputeNIEL(const G4Step\*)
- RecoilEnergy(const G4Step\*)
- AddEmModel(G4VEmModel\*)

the last method allows customisation of NIEL model.

#### Low Energy Electromagnetic Library

A physical interaction is described by a process class which can handle physics models, described by model classes. The following is a summary of the Low Energy Electromagnetic physics models available in GEANT4. Further information is available in the web pages of the GEANT4 Low Energy Electromagnetic Physics Working Group, accessible from the GEANT4 web site, "who we are" section, then "working groups".

The physics content of these models is documented in the GEANT4 Physics Reference Manual. They are based on the Livermore data library, on the ICRU73 data tables or on the Penelope2008 Monte Carlo code. They adopt the same software design as the "standard" GEANT4 electromagnetic models.

Examples of the registration of physics constructor with low-energy electromagnetic models are shown in GEANT4 extended examples (examples/extended/electromagnetic and examples/extended/medical in the GEANT4 source distribution). Advanced examples (examples/advanced in the GEANT4 source distribution) illustrate alternative instantiation of these processes. Both are available as part of the GEANT4 release.

#### **Production Cuts**

Remember that production cuts for secondaries can be specified as range cuts, which are converted at initialisation time into energy thresholds for secondary gamma, electron, positron and proton production. The cut for proton is applied by elastic scattering processes to all recoil ions.

A range cut value is set by default to 0.7 mm in GEANT4 reference physics lists. This value can be specified in the optional SetCuts() method of the user Physics list or via UI commands. For e.g. to set a range cut of 10 micrometers, one can use

```
/run/setCut 0.01 mm
```

or, for a given particle type (for e.g. electron),

```
/run/setCutForAGivenParticle e- 0.01 mm
```

If a range cut equivalent to an energy lower than 990 eV is specified, the energy cut is still set to 990 eV. In order to decrease this value (for e.g. down to 250 eV, in order to simulate low energy emission lines of the fluorescence spectrum), one may use the following UI command before the "/run/initialize" command

```
/cuts/setLowEdge 100 eV
```

or alternatively directly in the user Physics list, in the optional SetCuts() method, using:

```
G4ProductionCutsTable::GetProductionCutsTable()->SetEnergyRange(100*eV, 1*GeV);
```

A command is also available in order to disable usage of production threshold for fluorescence and Auger electron production

```
/process/em/deexcitationIgnoreCut true
```

## **Angular Generators**

For part of EM processes it is possible to factorise out sampling of secondary energy and direction. Using an interface G4VEmModel base class SetAngularDistribution (G4VEmAngularDistribution\*) it is possible to substitute default angular generator of a model. Angular generators in standard and lowenergy sub-packages follow the same abstract interface.

For photoelectric models several angular generators are available:

- G4SauterGavrilaAngularDistribution (default);
- G4PhotoElectricAngularGeneratorSauterGavrila;
- G4PhotoElectricAngularGeneratorPolarized.

For bremsstrahlung and pair production models following angular generators are available:

- G4ModifiedTsai (default for electrons and positrons);
- G4ModifiedMephi (default for muons and hadrons);
- G4DipBustGenerator;
- G4Generator2BS (recommended for electrons and positrons);
- G4Generator2BN;
- G4PenelopeBremsstrahlungAngular.

For gamma conversion models following angular generators are available:

- G4ModifiedTsai (default);
- G4DipBustGenerator.

For models of ionisation a new optional angular generator is available:

• G4DeltaAngle.

### **Electromagnetics secondary biasing**

It may be useful to create more than one secondary at an interaction. For example, electrons incident on a target in a medical linac produce photons through bremsstrahlung. The variance reduction technique of bremsstrahlung splitting involves choosing *N* photons from the expected distribution, and assigning each a weight of 1/*N*.

Similarly, if the secondaries are not important, one can kill them with a survival probability of 1/N. The weight of the survivors is increased by a factor N. This is known as Russian roulette.

Neither biasing technique is applied if the resulting daughter particles would have a weight below 1/N, in the case of brem splitting, or above 1, in the case of Russian roulette.

These techniques can be enabled in GEANT4 electromagnetics with the macro commands

```
/process/em/setSecBiasing processName Region factor energyLimit energyUnit
```

where: *processName* is the name of the process to apply the biasing to; *Region* is the region in which to apply biasing; *factor* is the inverse of the brem splitting or Russian roulette factor (1/N); *energyLimit energyUnit* is the high energy limit. If the first secondary has energy above this limit, no biasing is applied.

For example,

```
/process/em/setSecBiasing eBrem target 10 100 MeV
```

will result in electrons undergoing bremsstrahlung in the target region being split 10 times (if the first photon sampled has an energy less than 100 MeV).

Note that the biasing needs to be specified for each process individually. To apply Russian Roulette to daughter electrons from interactions of photons, issue the macro command for the processes phot, compt, conv.

### **Directional splitting**

This biasing may be enabled based on the direction of the outgoing particles ("directional splitting"). The user may specify a spherical volume of interest by giving the center and radius of the volume. In an interaction, if the incident particle has high weight, the outgoing particles are split. *N* particles from the distribution are created, each with weight 1/*N*. For each particle, if it is not directed towards the volume of interest, Russian Roulette is played. Typically one will want directional splitting to take place for all interactions.

For example,

```
/process/em/setDirectionalSplitting true
/process/em/setDirectionalSplittingTarget 1000 0 0 mm # x, y, z components of center
/process/em/setDirectionalSplittingRadius 10 cm
/process/em/setSecBiasing eBrem world 100 100 MeV
/process/em/setSecBiasing Rayl world 100 100 MeV
/process/em/setSecBiasing phot world 100 100 MeV
/process/em/setSecBiasing compt world 100 100 MeV
/process/em/setSecBiasing annihil world 100 100 MeV
```

Reference: BEAMnrc Users Manual, D.W.O Rogers, B. Walters, I. Kawrakow. NRCC Report PIRS-0509(A)revL, available at http://www.irs.inms.nrc.ca/inms/irs/BEAM/beamhome.html

#### **Livermore Data Based Models**

#### Photon models

- Photo-electric effect (class G4LivermorePhotoElectricModel)
- Polarized Photo-electric effect (class G4LivermorePolarizedPhotoElectricModel)
- Compton scattering (class G4LivermoreComptonModel)
- Compton scattering (class G4LowEPComptonModel)
- Polarized Compton scattering (class G4LivermorePolarizedComptonModel)
- Rayleigh scattering (class G4LivermoreRayleighModel)
- Polarized Rayleigh scattering (class G4LivermorePolarizedRayleighModel)
- Gamma conversion (also called pair production, class G4LivermoreGammaConversionModel)
- Nuclear gamma conversion (class G4LivermoreNuclearGammaConversionModel)
- Polarized gamma conversion (class G4LivermorePolarizedGammaConversionModel)

#### Electron models

- Bremsstrahlung (class G4LivermoreBremsstrahlungModel)
- Ionisation and delta ray production (class G4LivermoreIonisationModel)

#### **ICRU73 Based Ion Model**

Ionisation and delta ray production (class G4IonParametrisedLossModel)

The ion model uses data files initially converted from the ICRU 73 report. Later authors of the ICRU 73 report provided GEANT4 recomputed tables for more combinations of projectile and target ions. In 2015 newer calculation results were provided. The algorithm of selection of ion stopping powers applying following condition: if a projectile/target combination exists in the data base and the projectile energy is below 1 GeV/nucleon then tabulated data is used, otherwise applies a Bethe-Bloch based formalism. For compounds, ICRU 73 stopping powers are employed if the material name coincides with the name of GEANT4 NIST materials (e.g. G4\_WATER). Elemental materials are matched to the corresponding ICRU 73 stopping powers by means of the atomic number of the material. The material name may be arbitrary in this case. For a list of applicable materials, the user is referred to the ICRU 73 report.

The model requires data files to be copied by the user to his/her code repository. These files are distributed together with the GEANT4 release. The user should set the environment variable G4LEDATA to the directory where he/she has copied the files.

Alternative model (class G4LinhardSorensenIonModel) use ICRU73 and ICRU90 data, G4BraggIonModel, G4BetheBlochModel and the parameterisation based on original relativistic model (*J. Lindhard & A.H. Sorensen, Phys. Rev. A* 53 (1996) 2443-2455).

Both models are dedicated to be used with the G4ionIonisation process and its applicability is restricted to G4GenericIon particles.

## Penelope2008 Based Models

#### · Photon models

- Compton scattering (class G4PenelopeComptonModel)
- Rayleigh scattering (class G4PenelopeRayleighModel)
- Gamma conversion (also called pair production, class G4PenelopeGammaConversionModel)
- Photo-electric effect (class G4PenelopePhotoElectricModel)

## • Electron models

- Bremsstrahlung (class G4PenelopeBremsstrahlungModel)
- Ionisation and delta ray production (class G4PenelopeIonisationModel)

#### · Positron models

- Bremsstrahlung (class G4PenelopeBremsstrahlungModel)
- Ionisation and delta ray production (class G4PenelopeIonisationModel)

- Positron annihilation (class G4PenelopeAnnihilationModel)

All Penelope models can be applied up to a maximum energy of 100 GeV, although it is advisable not to use them above a few hundreds of MeV.

Options are available in the all Penelope Models, allowing to set (and retrieve) the verbosity level of the model, namely the amount of information which is printed on the screen.

- SetVerbosityLevel(G4int)
- GetVerbosityLevel()

The default verbosity level is 0 (namely, no textual output on the screen). The default value should be used in general for normal runs. Higher verbosity levels are suggested only for testing and debugging purposes.

The verbosity scale defined for all Penelope processes is the following:

- 0 = no printout on the screen (default)
- 1 = issue warnings only in the case of energy non-conservation in the final state (should never happen)
- 2 = reports full details on the energy budget in the final state
- 3 = writes also information on cross section calculation, data file opening and sampling of atoms
- 4 = issues messages when entering in methods

## Very Low energy Electromagnetic Processes (GEANT4-DNA extension)

The GEANT4 low energy electromagnetic Physics package has been extended down to energies of a few electron Volts suitable for the simulation of radiation effects in liquid water for applications in micro/nanodosimetry at the cellular and sub-cellular level. These developments take place in the framework of the on-going GEANT4-DNA project (see more in the Geant4-DNA web pages or in the EM web pages of the Geant4 Electromagnetic Physics Working Group).

The GEANT4 -DNA process and model classes apply to electrons, protons, hydrogen, alpha particles and their charge states, in liquid water ("G4\_WATER" material).

#### **Electron processes and models**

- Elastic scattering:
  - process class is G4DNAElastic
  - four alternative model classes are: G4DNAScreenedRutherfordElasticModel or G4DNAChampionElasticModel (default) or G4DNAUeharaScreenedRutherfordElasticModel or G4DNACPA100ElasticModel
- Excitation
  - process class is G4DNAExcitation
  - model class is G4DNABornExcitationModel (default) or G4DNAEmfietzoglouExcitationModel or G4DNACPA100ExcitationModel
- Ionisation
  - process class is G4DNAIonisation
  - model class is G4DNABornIonisationModel (default) or G4DNAEmfietzoglouIonisationModel or G4DNACPA100IonisationModel
- Attachment
  - process class is G4DNAAttachment
  - model class is G4DNAMeltonAttachmentModel
- Vibrational excitation
  - process class is G4DNAVibExcitation
  - model class is G4DNASancheExcitationModel

#### Proton processes and models

- · Elastic scattering:
  - process class is G4DNAElastic
  - G4DNAIonElasticModel

- Excitation
  - process class is G4DNAExcitation
  - two complementary model classes are G4DNAMillerGreenExcitationModel (below 500 keV) and G4DNABornExcitationModel (above)
- Ionisation
  - process class is G4DNAIonisation
  - two complementary model classes are G4DNARuddIonisationModel (below 500 keV) and G4DNABornIonisationModel (above)
- · Charge decrease
  - process class is G4DNAChargeDecrease
  - model class is G4DNADingfelderChargeDecreaseModel

## Hydrogen processes and models

- Elastic scattering:
  - process class is G4DNAElastic
  - G4DNAIonElasticModel
- Excitation
  - process class is G4DNAExcitation
  - model class is G4DNAMillerGreenExcitationModel
- Ionisation
  - process class is G4DNAIonisation
  - model class is G4DNARuddIonisationModel
- · Charge increase
  - process class is G4DNAChargeIncrease
  - model class is G4DNADingfelderChargeIncreaseModel

## Helium (neutral) processes and models

- Elastic scattering:
  - process class is G4DNAElastic
  - G4DNAIonElasticModel
- Excitation
  - process class is G4DNAExcitation
  - model class is G4DNAMillerGreenExcitationModel
- Ionisation
  - process class is G4DNAIonisation
  - model class is G4DNARuddIonisationModel
- Charge increase
  - process class is G4DNAChargeIncrease
  - model class is G4DNADingfelderChargeIncreaseModel

#### Helium+ (ionized once) processes and models

- Elastic scattering:
  - process class is G4DNAElastic
  - G4DNAIonElasticModel
- Excitation
  - process class is G4DNAExcitation
  - model class is G4DNAMillerGreenExcitationModel
- Ionisation
  - process class is G4DNAIonisation
  - model classes is G4DNARuddIonisationModel
- · Charge increase
  - process class is G4DNAChargeIncrease
  - model classes is G4DNADingfelderChargeIncreaseModel
- · Charge decrease

- process class is G4DNAChargeDecrease
- model classes is G4DNADingfelderChargeDecreaseModel

#### Helium++ (ionised twice) processes and models

- Elastic scattering:
  - process class is G4DNAElastic
  - G4DNAIonElasticModel
- Excitation
  - process class is G4DNAExcitation
  - model classes is G4DNAMillerGreenExcitationModel
- Ionisation
  - process class is G4DNAIonisation
  - model classes is G4DNARuddIonisationModel
- · Charge decrease
  - process class is G4DNAChargeDecrease
  - model classes is G4DNADingfelderChargeDecreaseModel

#### Li, Be, B, C, N, O, Si, Fe processes and models

- Ionisation
  - process class is G4DNAIonisation
  - model class is G4DNARuddIonisationExtendedModel

Examples of the registration of these processes in a physics list are given in the G4EmDNAPhysics\* constructors (in source/physics\_lists/constructors/electromagnetic in the GEANT4 source distribution). An example of the usage of these constructors in a physics list is given in the "dnaphysics" extended example, which explains how to extract basic information from GEANT4-DNA Physics processes.

GEANT4-DNA physics constructors are described at the Geant4-DNA website.

The "microdosimetry" extended example illustrates how to combine GEANT4-DNA processes with Standard electromagnetic processes (combination of discrete and condensed history GEANT4 electromagnetic processes at different scales).

A set of GEANT4-DNA models applicable to biological materials is available since release 10.4. These models are named G4DNAPTBElasticModel, G4DNAPTBExcitationModel, G4DNAPTBIonisationModel and G4DNAPTBAugerModel. They can be used for electrons in THF, PY, PU, TMP precursors and in backbone, cytosine, thymine, adenine, guanine materials of DNA. The G4DNAPTBIonisationModel can also be used with protons in THF, PY and TMP. Their usage is illustrated in the "icsd" extended example.

Since GEANT4 release 11.0, GEANT4-DNA can be used to describe electron interactions down to 10 eV in gold using a tracking structure approach. Electron processes and models include:

- · Elastic scattering
  - process class is G4DNAElastic
  - model class is G4DNAELSEPAElasticModel
- Ionization
  - process class is G4DNAIonisation
  - model class is G4DNARelativisticIonisationModel
- Excitation
  - process class is G4DNAExcitation
  - model class is G4DNADiracRMatrixExcitationModel
- Plasmon excitation
  - process class is G4DNAPlasmonExcitation
  - model class is G4DNAQuinnPlasmonExcitationModel

See more details on these physics models in:

D. Sakata et al., An implementation of discrete electron transport models for gold in the Geant4 simulation toolkit, Journal of Applied Physics, 120, 244901, 2016.

Since GEANT4 release 10.1, GEANT4-DNA can also be used for the modelling of water radiolysis (physico-chemistry and chemistry stages). Three extended examples, "chem1", "chem2", "chem3" and "chem4" illustrate this. More information is available from the Geant4-DNA website.

To run the GEANT4-DNA extension, data files need to be copied by the user to his/her code repository. These files are distributed together with the GEANT4 release. The user should set the environment variable G4LEDATA to the directory where he/she has copied the files.

A full list of publications regarding GEANT4-DNA is directly available from the Geant4-DNA website or from the Geant4@IN2P3 web site).

#### **Atomic Deexcitation**

A unique interface named G4VAtomicDeexcitation is available in GEANT4 for the simulation of atomic deexcitation using Standard, Low Energy and Very Low Energy electromagnetic processes. Atomic deexcitation includes fluorescence and Auger electron emission induced by photons, electrons and ions (PIXE); see more details in:

A. Mantero et al., PIXE Simulation in Geant4, X-Ray Spec., 40, 135-140, 2011.

It can be activated for processes producing vacancies in atomic shells. Currently these processes are the photoelectric effect, ionization and Compton scattering.

#### Activation of atomic deexcitation

The activation of atomic deexcitation in continuous processes in a user physics list can be done through the following G4EmParameters class methods described above or via UI commands

```
/process/em/deexcitation region true true
/process/em/fluo true
/process/em/auger true
/process/em/pixe true
```

One can define parameters in the G4State\_PreInit or G4State\_Idle states. Fluorescence from photons and electrons is activated by default in Option3, Option4, Livermore and Penelope physics constructors, while Auger production and PIXE are not.

The alternative set of data by Bearden et al. (1967) for the modelling of fluorescence lines had been added to the G4LEDATA archive. This set can be selected via UI command

```
/process/em/fluoBearden true
```

The alternative set of ANSTO data had been added to the G4LEDATA archive. This set can be selected via UI command

```
/process/em/fluoANSTO true
```

Another important UI commands enable simulation of the full Auger and/or fluorescence cascade

```
/process/em/deexcitationIgnoreCut true
```

#### How to change ionisation cross section models?

The user can also select which cross section model to use in order to calculate shell ionisation cross sections for generating PIXE

```
/process/em/pixeXSmodel name
/process/em/pixeElecXSmodel name
```

where the name can be "Empirical", "ECPSSR\_FormFactor", "ECPSSR\_Analytical" or "ECPSSR\_ANSTO" corresponds to different PIXE cross sections. Following shell cross sections models are available: "ECPSSR\_Analytical" models derive from an analytical calculation of the ECPSSR theory (see *A. Mantero et al., X-Ray Spec.40 (2011) 135-140*) and it reproduces K and L shell cross sections over a wide range of energies; "ECPSSR\_FormFactor" models derive from A. Taborda et al. calculations (see *A. Taborda et al., X-Ray Spec. 40 (2011) 127-134*) of ECPSSR values directly form Form Factors and it covers K, L shells on the range 0.1-100 MeV and M shells in the range 0.1-10 MeV; the "empirical" models are from Paul "reference values" (for protons and alphas for K-Shell) and Orlic empirical model for L shells (only for protons and ions with Z>2). The later ones are the models used by default. Out of the energy boundaries, "ECPSSR\_Analytical" model is used. We recommend to use default settings if not sure what to use. "ECPSSR\_ANSTO" models are ECPSSR calculations based on state of the art recommendations documented in D. Cohen et al., K, L, and M shell datasets for PIXE spectrum fitting and analysis, NIM B, 363, 7-18, 2015.

#### **Example**

The **TestEm5 extended/electromagetic example** shows how to simulate atomic deexcitation (see for e.g. the pixe.mac and pixe\_ANSTO macros).

# Very Low energy Electromagnetic Processes in Silicon for microelectronics application (GEANT4-MuElec extension)

(Previously named GEANT4-MuElec)

The GEANT4 low energy electromagnetic Physics package has been extended down to energies of a few electron Volts suitable for the simulation of radiation effects in highly integrated microelectronic components.

The GEANT4-MicroElec process and model classes apply to electrons, protons and heavy ions in silicon.

#### Electron processes and models

- Elastic scattering :
  - process class is G4MicroElastic
  - model class is G4MicroElecElasticModel
- Ionization
  - process class is G4MicroElecInelastic
  - model class is G4MicroElecInelasticModel

## Proton processes and models

- Ionisation
  - process class is G4MicroElecInelastic
  - model class is G4MicroElecInelasticModel

#### Heavy ion processes and models

- Ionization
  - process class is G4MicroElecInelastic
  - model class is G4MicroElecInelasticModel

A full list of publications regarding GEANT4-MicroElec is directly available from the Geant4-MicroElec website.

### New Compton model by Monash U., Australia

A new Compton scattering model for unpolarised photons has been developed in the relativistic impulse approximation. The model was developed as an alternative to low energy electromagnetic Compton scattering models developed from Ribberfors' Compton scattering framework (Livermore, Penelope Compton models). The model class is named named G4LowEPComptonModel.

G4LowEPComptonModel has been added to the physics constructor G4EmStandardPhysics\_option4, containing the most accurate models from the Standard and Low Energy Electromagnetic physics working groups.

#### **Multi-scale Processes**

## **Hadron Impact Ionisation and PIXE**

The **G4hImpactIonisation** process deals with ionisation by impact of hadrons and alpha particles, and the following generation of **PIXE** (Particle Induced X-ray Emission). This process and related classes can be found in *source/processes/electromagnetic/pii*.

Further documentation about PIXE simulation with this process is available here.

A detailed description of the related physics features can be found in:

```
M. G. Pia et al., PIXE Simulation with Geant4, IEEE Trans. Nucl. Sci., vol. 56, no. 6, pp. 3614-3649, 2009.
```

A brief summary of the related physics features can be found in the GEANT4 Physics Reference Manual.

An example of how to use this process is shown below. A more extensive example is available in the eRosita GEANT4 advanced example (see *examples/advanced/eRosita* in your GEANT4 installation source).

```
#include "G4hImpactIonisation.hh"
[...]
void eRositaPhysicsList::ConstructProcess()
[...]
  theParticleIterator->reset():
  while( (*theParticleIterator)() )
     G4ParticleDefinition* particle = theParticleIterator->value();
      G4ProcessManager* processManager = particle->GetProcessManager();
     G4String particleName = particle->GetParticleName();
      if (particleName == "proton")
             Instantiate the G4hImpactIonisation process
          G4hImpactIonisation* hIonisation = new G4hImpactIonisation();
          // Select the cross section models to be applied for K, L and M shell vacancy creation
            (here the ECPSSR model is selected for K, L and M shell; one can mix and match
          // different models for each shell)
          hIonisation->SetPixeCrossSectionK("ecpssr");
          hIonisation->SetPixeCrossSectionL("ecpssr");
          hIonisation->SetPixeCrossSectionM("ecpssr");
          // Register the process with the processManager associated with protons
          processManager -> AddProcess(hIonisation, -1, 2, 2);
     }
```

### Available cross section model options

The following cross section model options are available:

```
protons

    K shell

        * ecpssr (based on the ECPSSR theory)
        * ecpssr hs (based on the ECPSSR theory, with Hartree-Slater correction)
        * ecpssr_ua (based on the ECPSSR theory, with United Atom Hartree-Slater correction)
        * ecpssr_he (based on the ECPSSR theory, with high energy correction)
        * pwba (plane wave Born approximation)
        * paul (based on the empirical model by Paul and Sacher)
         * kahoul (based on the empirical model by Kahoul et al.)
    - L shell
        * ecpssr
        * ecpssr_ua
        * pwba
        * miyaqawa (based on the empirical model by Miyagawa et al.)
        * orlic (based on the empirical model by Orlic et al.)
        * sow (based on the empirical model by Sow et al.)

    M shell

        * ecpssr
         * pwba
· alpha particles
    - K shell
        * ecpssr
        * ecpssr_hs
        * pwba
        * paul (based on the empirical model by Paul and Bolik)
    L shell
        * ecpssr
         * pwba
    - M shell
        * ecpssr
```

## PIXE data library

\* pwba

The G4hImpactIonisation process uses a PIXE Data Library.

The PIXE Data Library is distributed in the GEANT4 **G4PII** data set, which must be downloaded along with GEANT4 source code.

The **G4PIIDATA** environment variable must be defined to refer to the location of the G4PII PIXE data library in your filesystem; for instance, if you use a c-like shell

```
setenv G4PIIDATA path_to_where_G4PII_has_been_downloaded
```

Further documentation about the PIXE Data Library is available here.

## 5.2.3 Hadronic Interactions

This section briefly introduces the hadronic physics processes installed in GEANT4. For details of the implementation of hadronic interactions available in GEANT4, please refer to the Physics Reference Manual.

#### **Treatment of Cross Sections**

#### **Cross section data sets**

Each hadronic process object (derived from G4HadronicProcess) may have one or more cross section data sets associated with it. The term "data set" is meant, in a broad sense, to be an object that encapsulates methods and data for calculating total cross sections for a given process. The methods and data may take many forms, from a simple equation using a few hard-wired numbers to a sophisticated parameterisation using large data tables. Cross section data sets are derived from the abstract class G4VCrossSectionDataSet, and are required to implement the following methods:

```
G4bool IsApplicable( const G4DynamicParticle*, const G4Element*)
```

This method must return True if the data set is able to calculate a total cross section for the given particle and material, and False otherwise.

```
G4double GetCrossSection( const G4DynamicParticle*, const G4Element*)
```

This method, which will be invoked only if True was returned by IsApplicable, must return a cross section, in GEANT4 default units, for the given particle and material.

```
void BuildPhysicsTable( const G4ParticleDefinition& )
```

This method may be invoked to request the data set to recalculate its internal database or otherwise reset its state after a change in the cuts or other parameters of the given particle type.

```
void DumpPhysicsTable( const G4ParticleDefinition& )
```

This method may be invoked to request the data set to print its internal database and/or other state information, for the given particle type, to the standard output stream.

#### Cross section data store

Cross section data sets are used by the process for the calculation of the physical interaction length. A given cross section data set may only apply to a certain energy range, or may only be able to calculate cross sections for a particular type of particle. The class G4CrossSectionDataStore has been provided to allow the user to specify, if desired, a series of data sets for a process, and to arrange the priority of data sets so that the appropriate one is used for a given energy range, particle, and material. It implements the following public method:

```
G4double ComputeCrossSection( const G4DynamicParticle*, const G4Material*)
G4double GetCrossSection( const G4DynamicParticle*, const G4Element*, const G4Material*)
```

For a given particle and material, this method returns a cross section value provided by one of the collection of cross section data sets listed in the data store object. If there are no known data sets, a G4Exception is thrown and DBL\_MIN is returned. Otherwise, each data set in the list is queried, in reverse list order, by invoking its IsApplicable method for the given particle and material. The first data set object that responds positively will then be asked to return a cross section value via its GetCrossSection method. If no data set responds positively, a G4Exception is thrown and DBL\_MIN is returned.

```
void AddDataSet( G4VCrossSectionDataSet* aDataSet )
```

This method adds the given cross section data set to the end of the list of data sets in the data store. For the evaluation of cross sections, the list has a LIFO (Last In First Out) priority, meaning that data sets added later to the list will have priority over those added earlier to the list. Another way of saying this, is that the data store, when given a GetCrossSection request, does the IsApplicable queries in the reverse list order, starting with the last data set in the list and proceeding to the first, and the first data set that responds positively is used to calculate the cross section.

```
void BuildPhysicsTable( const G4ParticleDefinition& aParticleType )
```

This method may be invoked to indicate to the data store that there has been a change in the cuts or other parameters of the given particle type. In response, the data store will invoke the BuildPhysicsTable of each of its data sets.

```
void DumpPhysicsTable( const G4ParticleDefinition& )
```

This method may be used to request the data store to invoke the DumpPhysicsTable method of each of its data sets.

#### **Default cross sections**

The default cross section for main hadrons:

```
- G4BGGNucleonInelasticXS and G4BGGNucleonElasticXS for protons
- G4NeutronInelasticXS, G4NeutronElasticXS, G4NeutronCaptureXS
- G4BGGPionInelasticXS and G4BGGPionElasticXS for pions
- G4GammaNuclearXS for gamma-nuclear
```

For other hadrons and ions cross section is provided by generic classes:

```
- G4CrosssectionInelastic
- G4CrossSectionElastic
```

which require concrete cross section implementation via the interface G4VComponentCrossSection. Following main components are used:

```
- G4ComponentGGHadronNucleusXsc for hadrons
- G4ComponentAntiNuclNuclearXS for anti-protons and anti light ions
- G4ComponentGGNuclNuclXsc for ions
```

The default cross sections can be overridden in whole or in part by the user. To this end, the base class G4HadronicProcess has a get method:

```
G4CrossSectionDataStore* GetCrossSectionDataStore()
```

which gives public access to the data store for each process. The user's cross section data sets can be added to the data store according to the following framework:

```
G4Hadron...Process aProcess(...)

MyCrossSectionDataSet myDataSet(...)

aProcess.GetCrossSectionDataStore()->AddDataSet(&MyDataSet)
```

The added data set will override the default cross section data whenever so indicated by its IsApplicable method. In addition to the get method, G4HadronicProcess also has the method

#### void SetCrossSectionDataStore( G4CrossSectionDataStore\* )

which allows the user to completely replace the default data store with a new data store.

It should be noted that a process does not send any information about itself to its associated data store (and hence data set) objects. Thus, each data set is assumed to be formulated to calculate cross sections for one and only one type of process. Of course, this does not prevent different data sets from sharing common data and/or calculation methods, as in the case of the G4HadronCrossSections class mentioned above. Indeed, G4VCrossSectionDataSet specifies only the abstract interface between physics processes and their data sets, and leaves the user free to implement whatever sort of underlying structure is appropriate.

### Cross-sections for low energy neutron transport

The cross section data for low energy neutron transport are organized in a set of files that are read in by the corresponding data set classes at time zero. Hereby the file system is used, in order to allow highly granular access to the data. The ``root" directory of the cross-section directory structure is accessed through an environment variable, G4NEUTRONHPDATA, which is to be set by the user. The classes accessing the total cross-sections of the individual processes, i.e., the cross-section data set classes for low energy neutron transport, are G4NeutronHPElasticData, G4NeutronHPCaptureData, G4NeutronHPFissionData, and G4NeutronHPInelasticData.

For detailed descriptions of the low energy neutron total cross-sections, they may be registered by the user as described above with the data stores of the corresponding processes for neutron interactions.

It should be noted that using these total cross section classes does not require that the neutron\_hp models also be used. It is up to the user to decide whether this is desirable or not for his particular problem.

The compact version of neutron cross sections derived from HP database are provided with classes G4NeutronInelasticXS, G4NeutronElasticXS, and G4NeutronCaptureXS. Using low-energy data for protons, deuterons, tritons, alpha, and He3 the data for the class G4ParticleInelasticXS are obtained. Gamma-nuclear cross section is extracted from the IAEA Evaluated Photonuclear Data Library (IAEA/PD-2019) https://www-nds.iaea.org/photonuclear/`\_\_.

These cross-sections for n, p, d, t, He3, He4, and gamma are accessed through an environment variable G4PARTICLEXSDATA.

#### Cross-sections for low-energy charged particle transport

The cross-section data for low-energy charged particle transport are organized in a set of files that are read at initialization, similarly to the case of low-energy neutron transport. The "root" directory of the cross-section directory structure is accessed through an environment variable, G4PARTICLEHPDATA, which has to be set by the user. This variable has to point to the directory where the low-energy charged particle data have been installed, e.g. G4TENDL1. 4 for the GEANT4 release 10.7 (note that the download of this data library from the GEANT4 web site is not done automatically, i.e. it must be done manually by the user):

```
export G4PARTICLEHPDATA=/your/path/G4TENDL1.4/
```

It is expected that the directory \$G4PARTICLEHPDATA has the following five subdirectories, corresponding to the charged particles that can be handled by the low-energy charged particle transport: Proton/, Deuteron/, Triton/, He3/, Alpha/. It is possible for the user to overwrite the default directory structure with individual environment variables pointing to custom data libraries for each particle type. This is considered an advanced/expert user feature. These directories are set by the following environment variables: G4PROTONHPDATA, for proton; G4DEUTERONHPDATA, for deuteron; G4TRITONHPDATA, for triton; G4HE3HPDATA, for He3; G4ALPHAHPDATA, for alpha. Note that if any of these variables is not defined explicitly, e.g. G4TRITONHPDATA, then the corresponding data library is expected to be a subdirectory of \$G4PARTICLEHPDATA/, e.g. \$G4PARTICLEHPDATA/Triton/.

If instead all the above five environmental variables are set, then G4PARTICLEHPDATA does not need to be specified; even if it is set, then its value will be ignored (because the per-particle ones take precedence).

#### **Hadrons at Rest**

## List of implemented "Hadron at Rest" processes

The following process classes have been implemented:

- $\pi^-, K^-, \sigma^-, \xi^-, \omega^-$  absorption (class name G4HadronicAbsorptionBertini)
- neutron capture (class name G4NeutronCaptureProcess)
- anti-proton, anti- $\sigma^+$ , anti-deuteron, anti-triton, anti-alpha, anti-He3 annihilation (class name G4HadronicAbsorptionFritiof)
- mu-capture (class name G4MuonMinusCapture)

Capture of low-energy negatively charged particles is a complex process involving formation of mesonic atoms, X-ray cascade and Auger cascade, nuclear interaction. In the case of mu-there is also a probability to decay from K-shell of mesonic atom. To handle this a base process class G4HadronicStoppingProcess is used.

For the case of neutrons, GEANT4 offer simulation down to thermal energies. The capture cross section generally increases when neutron energy decreases and there are many nuclear resonances. In GEANT4 neutron capture cross sections are parameterized using ENDF database.

### **Hadrons in Flight**

## What processes do you need?

For hadrons in motion, there are four physics process classes. Table 5.1 shows each process and the particles for which it is relevant.

Table 5.1: Hadronic processes and relevant particles.

G4HadronElasticProcess	$\pi^+,\pi^-,K^+,K^0_S,K^0_L,K^-,p,\bar{p},n,\bar{n},\lambda,\bar{\lambda},\Sigma^+,\Sigma^-,\bar{\Sigma}^+,\bar{\Sigma}^-,\Xi^0,\Xi^-,\bar{\Xi}^0$	$ ,\bar{\Xi}^-$
G4HadronInelasticProcess	$\pi^{+}, \pi^{-}, K^{+}, K_{S}^{\bar{0}}, K_{L}^{\bar{0}}, K^{-}, p, \bar{p}, n, \bar{n}, \lambda, \bar{\lambda}, \Sigma^{+}, \Sigma^{-}, \bar{\Sigma}^{+}, \bar{\Sigma}^{-}, \Xi^{0}, \Xi^{-}, \bar{\Xi}^{0}$	$ ,\bar{\Xi}^- $
G4NeutronFissionProcess	neutron	
G4NeutronCaptureProcess	neutron	

## **How to register Models**

To register an inelastic process model for a particle, a proton for example, first get the pointer to the particle's process manager:

```
G4ParticleDefinition *theProton = G4Proton::ProtonDefinition();
G4ProcessManager *theProtonProcMan = theProton->GetProcessManager();
```

Create an instance of the particle's inelastic process:

```
G4HadronicProcess *theProcess = new G4HadronicProcess();
```

Create an instance of the model which determines the secondaries produced in the interaction, and calculates the momenta of the particles, for instance the Bertini cascade model:

```
G4CascadeInterface *theCascade = new G4CascadeInterface();
```

Register the model with the particle's inelastic process:

```
theProcess->RegisterMe( theCascade );
```

Finally, add the particle's inelastic process to the list of discrete processes:

```
theProcessManager->AddDiscreteProcess( theProcess );
```

The particle's inelastic process class, G4HadronInelasticProcess may be used, which is equivalent to G4HadronicProcess class. The G4HadronicProcess class derives from the G4VDiscreteProcess class. The inelastic, elastic, capture, and fission processes derive from the G4HadronicProcess class. This pure virtual class also provides the energy range manager object and the RegisterMe access function.

In-flight, final-state hadronic models derive, directly or indirectly, from the G4InelasticInteraction class, which is an abstract base class since the pure virtual function ApplyYourself is not defined there. G4InelasticInteraction itself derives from the G4HadronicInteraction abstract base class. This class is the base class for all the model classes. It sorts out the energy range for the models and provides class utilities. The G4HadronicInteraction class provides the Set/GetMinEnergy and the Set/GetMaxEnergy functions which determine the minimum and maximum energy range for the model. An energy range can be set for a specific element, a specific material, or for general applicability:

```
void SetMinEnergy( G4double anEnergy, G4Element *anElement )
void SetMinEnergy( G4double anEnergy, G4Material *aMaterial )
void SetMinEnergy( const G4double anEnergy)
void SetMaxEnergy( G4double anEnergy, G4Element *anElement )
void SetMaxEnergy( G4double anEnergy, G4Material *aMaterial )
void SetMaxEnergy( const G4double anEnergy )
```

## Which models are there, and what are the defaults

In GEANT4, any model can be run together with any other model without the need for the implementation of a special interface, or batch suite, and the ranges of applicability for the different models can be steered at initialisation time. This way, highly specialised models (valid only for one material and particle, and applicable only in a very restricted energy range) can be used in the same application, together with more general code, in a coherent fashion.

Each model has an intrinsic range of applicability, and the model chosen for a simulation depends very much on the use-case. Consequently, there are no "defaults". However, physics lists are provided which specify sets of models for various purposes.

Two types of hadronic shower models have been implemented: data driven models and theory driven models.

- Data driven models are available for the transport of low energy neutrons in matter in sub-directory hadronics/models/neutron\_hp. The modeling is based on the data formats of ENDF/6, and all distributions of this standard data format are implemented. The data sets used are selected from data libraries that conform to these standard formats. The file system is used in order to allow granular access to, and flexibility in, the use of the cross sections for different isotopes, and channels. The energy coverage of these models is from thermal energies to 20 MeV.
- Theory driven models are available for inelastic scattering in a first implementation, covering the full energy range of LHC experiments. They are located in sub-directory hadronics/models/generator. The current philosophy implies the usage of parton string models at high energies, of intra-nuclear transport models at intermediate energies, and of statistical break-up models for de-excitation.

## **High-precision neutron interactions (NeutronHP)**

Nuclear models fail (sometimes catastrophically) at predicting with reasonable accuracies the nuclear cross sections of neutrons (and other particles). For this reason, all physical quantities relevant for an accurate modeling of nuclear reactions in Monte Carlo simulations need to be provided as a database which includes, ideally:

- · cross sections
- angular distributions of the emitted particles
- energy spectra of the emitted particles
- energy-angle correlated spectrum (double-differential cross sections, DDX)
- neutrons per fission
- fission spectra
- fission product yields
- photo production data

For the case of neutron induced reactions, such databases are called "evaluated data", in the sense that they contain recommended values for different quantities that rely on compilations of experimental nuclear data and usually completed with theoretical predictions, benchmarked against available experimental data (i.e. integral and differential experiments) when possible. It should be noticed that the information available varies from isotope to isotope and can be incomplete or totally missing.

The G4NeutronHP package in GEANT4 allows using evaluated nuclear data libraries in the G4NDL format. GEANT4 users should know that any simulation involving neutrons with energies below 20 MeV and not using the G4NeutronHP package can lead to unreliable results. GEANT4 users are therefore encouraged to use it, although they should be aware of the limitations of using evaluated nuclear data libraries.

An example about how to implement the G4NeutronHP package into physics list in a GEANT4 application can be found in the example case (among others distributed with GEANT4) extended/radioactivedecay/rdecay02. Three different processes are included in that example: elastic, capture and inelastic. The inelastic reactions in G4NeutronHP are all reactions except elastic, capture and fission, so fission should also be included in the physics list, if needed, and it is done in the same way as it is done for the other three.

The G4NeutronHP package must be used together with evaluated nuclear data libraries. They are available on the GEANT4 download page and from the IAEA nuclear data web site where a larger set of different libraries, including isotopes with Z > 92, is available.

The evaluated nuclear data libraries do differ and thus the results of the Monte Carlo simulations will depend on the library used. It is a safe practice to perform simulations with (at least) two different libraries for estimating the uncertainties associated to the nuclear data.

Together with a good implementation of the physics list, users must be very careful with the definition of the materials performed in a Monte Carlo simulation when low energy neutron transport is relevant. In contrast to other kind of simulations, the isotopic composition of the elements which compose the different materials can strongly affect the obtained simulation results. Because of this, it is strongly recommended to define specifically the isotopic composition of each element used in the simulation, as it is described in the GEANT4 user's manual. In principle, such a practice is not mandatory if natural isotopic compositions are used, since GEANT4 contains them in their databases. However, by defining them explicitly some unexpected problems may be avoided and a better control of the simulation will be achieved.

It is highly recommended or mandatory to set the following UNIX environment variable and UI commands when running a GEANT4 application:

**G4NEUTRONHPDATA** [path to the G4NDL format data libraries] (mandatory).

/process/had/particle\_hp/skip\_missing\_isotopes true This UI commands sets to zero the cross section of the isotopes which are not present in the neutron library. If GEANT4 doesn't find an isotope, then it looks for the natural composition data of that element. Only if the element is not found then the cross section is set to zero. On the contrary, if this variable is not defined, GEANT4 looks then for the neutron data of another

isotope close in Z and A, which will have completely different nuclear properties and lead to incorrect results (highly recommended).

/process/had/particle\_hp/do\_not\_adjust\_final\_state true Without this UI command, a GEANT4 model that attempts to satisfy the energy and momentum conservation in some nuclear reactions, by generating artificial gamma rays. By setting such a variable one avoids the correction and leads to the result obtained with the ENDF-6 libraries. Even though energy and momentum conservation are desirable, the ENDF-6 libraries do not provide the necessary correlations between secondary particles for satisfying them in all cases. On the contrary, ENDF-6 libraries intrinsically violate energy and momentum conservation for several processes and have been built for preserving the overall average quantities such as average energy releases, average number of secondaries... (highly recommended).

The G4NDL format libraries are based on the ENDF-6 format libraries, which contain evaluated (i.e. recommended) nuclear data prepared for their use in transport codes. These data are essentially nuclear reaction cross sections together with the distribution in energy and angle of the secondary reaction products. As a consequence of how the data is written in the ENDF files, there are some features that may be or may be not expected in the results of a Monte Carlo calculation.

The information concerning the creation of the reaction products can be incomplete and/or uncorrelated, in the sense that is described below:

#### 1. Incomplete information.

This applies when there is no information about how to generate a secondary particle. As an example, it is possible to have only the cross section data of an (n,p) reaction, without any information concerning the energy and angle of the secondary proton. In this case GEANT4 will produce the proton considering that it is emitted isotropically in the center of mass frame, with an energy which is deduced from assuming that the residual nucleus is in its ground state.

#### 2. Uncorrelated information.

This applies when:

- 1. The energy and angle distributions of a reaction product may be uncorrelated. As a consequence, the reaction products can be generated with an unphysical energy-angle relationship.
- 2. The energy-angle distributions of different reaction products of a certain reaction are always uncorrelated. As an example, consider that in a (n, 2p) reaction at a certain neutron energy both resulting protons can be emitted with energies ranging from 0 to 5MeV. In this case the energy and angle of each proton will be sampled independently of the energy and angle of the other proton, so there will be events in which both protons will be emitted with energies close to 5 MeV and there will also be events in which both protons will be emitted with energies close to 0 MeV. As a consequence, energy and angular momentum won't be conserved event by event. However, energy will be conserved in average and the resulting proton energy spectrum will be correctly produced.

#### 3. Concatenated reactions.

There are some cases where several nuclear reactions are put together as if they were a single reaction (MT=5 reaction, in ENDF-6 format nomenclature). In those cases the information consists in a cross section, which is the sum of all of them, plus a reaction product yield and energy-angle distributions for each secondary particle. In this case the amount of each secondary particle produced has to be sampled every time the reaction occurs, and it is done independently of the amount of the other secondary particles produced.

Thus, in this case neither the energy and angular momentum nor the number of nucleons is conserved event by event, but all the quantities should be conserved in average. As a consequence, it is also not possible to deduce which are the residual nuclei produced, since no information is available concerning what are the specific nuclear reactions which take place. It has to be said that sometimes ENDF libraries include the residual nuclei as an outgoing particle. However, GEANT4 does not manage that information, at present. This situation is quite uncommon in neutron data libraries up to 20 MeV. However, it is quite common to find it in charged particle libraries below 20 MeV or in neutron libraries above 20 MeV.

As a consequence of what has been presented above, some general features can be expected in the results of a Monte Carlo calculation performed with the G4NeutronHP package:

• The neutron transport, which means how the neutron looses energy in the collisions, when and how it is ab-

sorbed..., is quite trustable, since the main purpose of the ENDF neutron libraries is to perform this neutron transport.

- The production of neutrons due to neutron induced nuclear reactions is usually trustable, with the exception of the energy-angle correlations when several neutrons are produced in the same nuclear reaction.
- The results concerning the production of charged particles have to be always questioned. A look into the ENDF format library used can indicate which results are trustable and which are not. This can be done, for example, in http://t2.lanl.gov/nis/data.html, among other websites.
- The results concerning the production of  $\gamma$ -rays have to be questioned always. For example, the information on the number and energies of  $\gamma$ -rays emitted in the neutron capture process is incomplete for almost all the nuclei and is frequently also uncorrelated. When the information is available, it will be used, but one can obtain results which are quite far from reality on an event by event basis: the total energy of the cascade won't be correct in many cases and only some specific  $\gamma$ -rays which are stored in the neutron databases will be emitted. If there isn't any information concerning these  $\gamma$ -rays, GEANT4 will use a simple a model instead which is generally missing the relevant spectroscopic information. The results concerning the generation of residual nuclei (for example, in activation calculations) are usually trustable, with the exception of libraries with MT=5 reactions, as described above (*uncorrelated*).

As a general conclusion, users should always be critical with the results obtained with Monte Carlo simulation codes, and this also applies to GEANT4. They have to anticipate which results can be trusted and which results should be questioned. For the particular case of the a closer look into the underlying evaluated nuclear data in the ENDF format libraries will allow to check what is the information available in a certain library for some specific isotope and a certain reaction. There are several public nuclear data sites like http://t2.lanl.gov/nis/data.html.

The transport of very low energy neutrons (below 5 eV) has to be performed using the thermal neutron data libraries. At these energies, the fact that the nuclei are in atoms which form part of a certain molecule inside a material (crystal lattice, liquid, plastic...) plays an important role, since there can be a transference of momentum between the neutron and the whole structure of the material, not only with the nucleus. This is of particular importance for material used as neutron moderators, i.e., materials with low A (mass number) used to decrease the incident neutron energy in only a few collisions. Since the property is related to the nucleus in the material, as an example, there is the need for having different thermal libraries for Hydrogen in polyethylene, Hydrogen in water and so on.

If neutron collisions at these energies are relevant for the problem to be simulated, thermal libraries should be used for the materials if they are available. If they are not, the results obtained from the simulation will not be trustable in the neutron energy range below 5 eV, especially when using low mass elements in the simulation.

To use the thermal libraries the following lines should be included in the physics list:

```
G4HadronElasticProcess* theNeutronElasticProcess = new G4HadronElasticProcess;
// Cross Section Data set
G4NeutronHPElasticData* theHPElasticData = new G4NeutronHPElasticData:
theNeutronElasticProcess->AddDataSet(theHPElasticData);
G4NeutronHPThermalScatteringData* theHPThermalScatteringData = new,
→G4NeutronHPThermalScatteringData;
theNeutronElasticProcess->AddDataSet(theHPThermalScatteringData);
G4NeutronHPElastic* theNeutronElasticModel = new G4NeutronHPElastic;
theNeutronElasticModel->SetMinEnergy(4.0*eV);
theNeutronElasticProcess->RegisterMe (theNeutronElasticModel);
\texttt{G4NeutronHPThermalScattering} \star \ \texttt{theNeutronThermalElasticModel} \ = \ \textbf{new} \ \texttt{G4NeutronHPThermalScattering} ;
theNeutronThermalElasticModel->SetMaxEnergy(4.0 *eV);
theNeutronElasticProcess->RegisterMe(theNeutronThermalElasticModel);
// Apply Processes to Process Manager of Neutron
G4ProcessManager* pmanager = G4Neutron::Neutron()->GetProcessManager();
pmanager->AddDiscreteProcess(theNeutronElasticProcess);
```

And the materials should be defined with a specific name. For example, to use the thermal library for Hydrogen in water, the water should be defined as:

```
G4Element* elTSHW = new G4Element("TS_H_of_Water", "H_WATER", 1.0, 1.0079*g/mole);
G4Material* matH2O_TS = new G4Material("Water_TS", density=1.0*g/cm3, ncomponents=2);
matH2O_TS->AddElement(elTSHW, natoms=2);
matH2O_TS->AddElement(elO, natoms=1);
```

where the important thing is the name "TS\_H\_of\_Water", which is a specific name used by G4NeutronHP. In order to see which thermal libraries are available, they can be found in the G4NDL4.0/ThermalScattering folder (or equivalent, for other neutron libraries). Then, one has to look into the G4NeutronHPThermalScatteringNames.cc source file, under source/processes/hadronic/models/neutron\_hp/src. There are some lines similar to:

```
names.insert(std::pair<G4String,G4String>("TS_H_of_Water", "h_water"));
```

where "TS\_H\_of\_Water" means Hydrogen in water. Names similar to "TS\_H\_of\_Water" like "TS\_C\_of\_Graphite" or "TS\_H\_of\_Polyethylene" can be found and used in the same way as described above.

### **High-precision charged particle interactions (ParticleHP)**

By default in ParticleHP the final state is adjusted to ensure better conservation laws (for charge, energy, momentum, baryon number). However, projectile charged particles can be improved by using the following UI command: /process/had/particle\_hp/do\_not\_adjust\_final\_state true

The adjustment of the final state is recommended for realistic detector response in the case of neutron interactions. For the use-case of reactor physics and dosimetry, where *average* quantities are important, not adjusting the final state (i.e. setting the above environment variable) improves accuracy.

Note that, for the time being, the UI command /process/had/particle\_hp/do\_not\_adjust\_final\_state true affects both primary neutrons and charged particles, so be careful which is the use-case and observable quantity you are interested in.

#### Switching statistical nuclear de-excitation models

Nuclear reactions at intermediate energies (from a few MeV to a few GeV) are typically modelled in two stages. The first, fast reaction stage is described by a dynamical model (quantum molecular dynamics, intranuclear cascade, pre-compound, etc.) and often results in the production of one or several excited nuclei. The second reaction stage describes the de-excitation of the excited nuclei and it is usually handled by statistical de-excitation models. The models for the two reaction stages can in principle be chosen independently, but the current design of the GEANT4 hadronics framework makes it difficult to do this at the physics-list level. However, another solution exists.

GEANT4 provides several nuclear de-excitation modules. The default one is G4ExcitationHandler, which is described in detail in the Physics Reference Manual. The Bertini-style G4CascadeInterface uses an internal de-excitation model. The ABLA V3 model is also available.

**Options** are available for steering of the pre-compound model and the de-excitation module. These options may be invoked by the new C++ interface class G4DeexPrecoParameters. The interface G4NuclearLevelData::Instance()->GetParameters() is thread safe, parameters are shared between threads, and parameters are shared between all de-excitation and pre-compound classes. Parameters may be modified at G4State\_PreInit state of GEANT4. This class has the following public methods:

- Dump()
- StreamInfo(std::ostream&)
- SetLevelDensity(G4double)
- SetR0(G4double)
- SetTransitionsR0(G4double)
- SetFBUEnergyLimit(G4double)

- SetFermiEnergy(G4double)
- SetPrecoLowEnergy(G4double)
- SetPrecoHighEnergy(G4double)
- SetPhenoFactor(G4double)
- SetMinExcitation(G4double)
- SetMaxLifeTime(G4double)
- SetMinExPerNucleounForMF(G4double)
- SetMinEForMultiFrag(G4double)
- SetMinZForPreco(G4int)
- SetMinAForPreco(G4int)
- SetPrecoModelType(G4int)
- SetDeexModelType(G4int)
- SetTwoJMAX(G4int)
- SetVerbose(G4int)
- SetNeverGoBack(G4bool)
- SetUseSoftCutoff(G4bool)
- SetUseCEM(G4bool)
- SetUseGNASH(G4bool)
- SetUseHETC(G4bool)
- SetUseAngularGen(G4bool)
- SetPrecoDummy(G4bool)
- SetCorrelatedGamma(G4bool)
- SetStoreICLevelData(G4bool)
- SetInternalConversionFlag(G4bool)
- SetLevelDensityFlag(G4bool)
- SetDiscreteExcitationFlag(G4bool)
- SetIsomerProduction(G4bool)
- SetDeexChannelType(G4DeexChannelType)

It is possible to replace the default de-excitation model with *ABLA V3* for any intranuclear-cascade model in GEANT4 except G4CascadeInterface. The easiest way to do this is to call the SetDeExcitation() method of the relevant intranuclear-cascade-model interface. This can be done even if you are using one of the reference physics lists. The technique is the following.

For clarity's sake, assume you are using the FTFP\_INCLXX physics list, which uses INCL++, the Liege Intranuclear Cascade model (G4INCLXXInterface) at intermediate energies. You can couple INCL++ to ABLA V3 by adding a run action (Usage of User Actions) and adding the following code snippet to BeginOfRunAction().

Listing 5.1: Coupling the INCL++ model to ABLA V3

```
#include "G4HadronicInteraction.hh"
#include "G4HadronicInteractionRegistry.hh"
#include "G4INCLXXInterface.hh"
#include "G4AblaInterface.hh"
void MyRunAction::BeginOfRunAction(const G4Run*)
  // Get hold of pointers to the INCL++ model interfaces
 std::vector<G4HadronicInteraction *> interactions = G4HadronicInteractionRegistry::Instance()
    ->FindAllModels(G4INCLXXInterfaceStore::GetInstance()->getINCLXXVersionName());
  for(std::vector<G4HadronicInteraction *>::const_iterator iInter=interactions.begin(),_
⇒e=interactions.end():
     iInter!=e; ++iInter) {
   G4INCLXXInterface *theINCLInterface = static_cast<G4INCLXXInterface*>(*iInter);
   if(theINCLInterface) {
       // Instantiate the ABLA model
     G4HadronicInteraction *interaction = G4HadronicInteractionRegistry::Instance()->FindModel(
→"ABLA");
```

(continues on next page)

(continued from previous page)

```
G4AblaInterface *theAblaInterface = static_cast<G4AblaInterface*>(interaction);
if(!theAblaInterface)
    theAblaInterface = new G4AblaInterface;
// Couple INCL++ to ABLA
G4cout << "Coupling INCLXX to ABLA" << G4endl;
theINCLInterface->SetDeExcitation(theAblaInterface);
}
}
}
```

This technique may be applied to any intranuclear-cascade model (i.e. models that inherit from G4VIntraNuclearTransportModel), except G4CascadeInterface. For example, if your physics list relies on the *Binary-Cascade* model (e.g. *FTF\_BIC*), you'll need to do

```
// Get hold of a pointer to the Binary-Cascade model interface
std::vector<G4HadronicInteraction *> interactions = G4HadronicInteractionRegistry::Instance()
    ->FindAllModels("Binary Cascade");
for(std::vector<G4HadronicInteraction *>::const_iterator iInter=interactions.begin(),
    ->e=interactions.end();
    iInter!=e; ++iInter) {
    G4BinaryCascade *theBICInterface = static_cast<G4BinaryCascade*>(*iInter);
    if(theBICInterface) {

        // Instantiate ABLA V3 as in the example above
        // [...]

        // Couple BIC to ABLA
        theBICInterface->SetDeExcitation(theAblaInterface);
    }
}
```

# 5.2.4 Particle Decay Process

This section briefly introduces decay processes installed in GEANT4. For details of the implementation of particle decays, please refer to the Physics Reference Manual.

#### **Particle Decay Class**

GEANT4 provides a G4Decay class for both at rest and in flight particle decays. G4Decay can be applied to all particles except:

```
massless particles, i.e., G4ParticleDefinition::thePDGMass <= 0
particles with "negative" life time, i.e., G4ParticleDefinition::thePDGLifeTime < 0
shortlived particles, i.e., G4ParticleDefinition::fShortLivedFlag = True
```

Decay for some particles may be switched on or off by using G4ParticleDefinition::SetPDGStable() as well as ActivateProcess() and InActivateProcess() methods of G4ProcessManager.

G4Decay proposes the step length (or step time for AtRest) according to the lifetime of the particle unless PreAssignedDecayProperTime is defined in G4DynamicParticle.

The G4Decay class itself does not define decay modes of the particle. GEANT4 provides two ways of doing this:

- using G4DecayChannel in G4DecayTable, and
- $\bullet \ using \ {\tt thePreAssignedDecayProducts} \ of \ {\tt G4DynamicParticle}$

The G4Decay class calculates the PhysicalInteractionLength and boosts decay products created by G4VDecayChannel or event generators. See below for information on the determination of the decay modes.

An object of G4Decay can be shared by particles. Registration of the decay process to particles in the ConstructPhysics method of *PhysicsList* (see *How to Specify Physics Processes*) is shown in Listing 5.2.

Listing 5.2: Registration of the decay process to particles in the ConstructPhysics method of *PhysicsList*.

```
#include "G4Decay.hh"
void MyPhysicsList::ConstructGeneral()
{
    // Add Decay Process
    G4Decay* theDecayProcess = new G4Decay();
    theParticleIterator->reset();
    while( (*theParticleIterator)() ) {
        G4ParticleDefinition* particle = theParticleIterator->value();
        G4ProcessManager* pmanager = particle->GetProcessManager();
        if (theDecayProcess->IsApplicable(*particle)) {
            pmanager ->AddProcess(theDecayProcess);
            // set ordering for PostStepDoIt and AtRestDoIt
            pmanager ->SetProcessOrdering(theDecayProcess, idxPostStep);
            pmanager ->SetProcessOrdering(theDecayProcess, idxAtRest);
        }
    }
}
```

## **Decay Table**

Each particle has its G4DecayTable, which stores information on the decay modes of the particle. Each decay mode, with its branching ratio, corresponds to an object of various "decay channel" classes derived from G4VDecayChannel. Default decay modes are created in the constructors of particle classes. For example, the decay table of the neutral pion has G4PhaseSpaceDecayChannel and G4DalitzDecayChannel as follows:

```
// create a decay channel
G4VDecayChannel* mode;
// pi0 -> gamma + gamma
mode = new G4PhaseSpaceDecayChannel("pi0",0.988,2,"gamma","gamma");
table->Insert(mode);
// pi0 -> gamma + e+ + e-
mode = new G4DalitzDecayChannel("pi0",0.012,"e-","e+");
table->Insert(mode);
```

Decay modes and branching ratios defined in GEANT4 are listed in *Definition of a particle*.

Branching ratios and life time can be set in tracking time.

```
// set lifetime
G4Neutron::Neutron()->SetPDGLifeTime(885.7*second);
// allow neutron decay
G4Neutron::Neutron()->SetPDGStable(false);
```

Branching ratios and life time can be modified by using user commands, also.

#### Example: Set 100% br for dalitz decay of pi0

## **Pre-assigned Decay Modes by Event Generators**

Decays of heavy flavor particles such as B mesons are very complex, with many varieties of decay modes and decay mechanisms. There are many models for heavy particle decay provided by various event generators and it is impossible to define all the decay modes of heavy particles by using G4VDecayChannel. In other words, decays of heavy particles cannot be defined by the GEANT4 decay process, but should be defined by event generators or other external packages. GEANT4 provides two ways to do this: pre-assigned decay mode and external decayer.

In the latter approach, the class G4VExtDecayer is used for the interface to an external package which defines decay modes for a particle. If an instance of G4VExtDecayer is attached to G4Decay, daughter particles will be generated by the external decay handler.

In the former case, decays of heavy particles are simulated by an event generator and the primary event contains the decay information. G4VPrimaryGenerator automatically attaches any daughter particles to the parent particle as the PreAssignedDecayProducts member of G4DynamicParticle. G4Decay adopts these pre-assigned daughter particles instead of asking G4VDecayChannel to generate decay products.

In addition, the user may assign a pre-assigned decay time for a specific track in its rest frame (i.e. decay time is defined in the proper time) by using the G4PrimaryParticle::SetProperTime() method. G4VPrimaryGenerator sets the PreAssignedDecayProperTime member of G4DynamicParticle. G4Decay uses this decay time instead of the life time of the particle type.

# 5.2.5 Gamma-nuclear and Lepto-nuclear Processes

Gamma-nuclear and lepto-nuclear reactions are handled in GEANT4 as hybrid processes which typically require both electromagnetic and hadronic models for their implementation. While neutrino-induced reactions are not currently provided, the GEANT4 hadronic framework is general enough to include their future implementation as a hybrid of weak and hadronic models.

The general scheme followed is to factor the full interaction into an electromagnetic (or weak) vertex, in which a virtual particle is generated, and a hadronic vertex in which the virtual particle interacts with a target nucleus. In most cases the hadronic vertex is implemented by an existing GEANT4 model which handles the intra-nuclear propagation.

The cross sections for these processes are parameterizations, either directly of data or of theoretical distributions determined from the integration of lepton-nucleon cross sections double differential in energy loss and momentum transfer.

Electro-nuclear reactions in GEANT4 are handled by the classes G4ElectronNuclearProcess and G4PositronNuclearProcess, which are both implmented by G4ElectroVDNuclearModel. This model consists of three sub-models: code which generates the virtual photon from the lepton-nucleus vertex, the Bertini-style cascade to handle the low and medium energy photons, and the FTFP model to handle the high energy photons.

Muon-nuclear reactions are handled similarly. The process G4MuonNuclearProcess can be assigned the G4MuonVDNuclearModel which in turn is implemented by three sub-models: virtual gamma generation code, Bertini-style cascade and the FTFP model.

#### **Resonance effects**

Note that the model that generates secondary particles does not take resonance effects into account. This may be particularly important in the region of the giant dipole resonance, at ~20MeV for high-Z materials (an important region for shielding in some medical applications.) Here, about 2/3 of photonuclear interactions may not produce neutrons.

In order to obtain correct photonuclear production in this regime, the user should use a LEND, data-driven model. Alternatively, if the environment variable G4CASCADE\_CHECK\_PHOTONUCLEAR is set, the model will ensure that, for incident energies less than 50 MeV, the mass of the nucleus changes during the interaction.

## 5.2.6 Optical Photon Processes

A photon is considered to be *optical* when its wavelength is much greater than the typical atomic spacing. In GEANT4 optical photons are treated as a class of particle distinct from their *gamma* cousins. Optical photons have different processes than gamma particles. An important use case for optical photons is that they interact with boundaries between volumes, undergoing reflection, refraction, etc.

**Note:** There is no transition between the optical photon and gamma particle classes: a *gamma* will never become an *optical photon*.

Optical photons are generated in GEANT4 by

- Cerenkov effect (class G4Cerenkov)
- Scintillation (class G4Scintillation)

The source code for these classes is in the source/processes/electromagnetic/xrays directory.

Optical photons interact through the processes

- Absorption (class G4OpAbsorption)
- Rayleigh scattering (class G40pRayleigh)
- Mie scattering (class G40pMieHG)
- Wave-length shifting (classes G40pWLS and G40pWLS2)
- Boundary scattering (class G40pBoundary)

The source code for these classes is in the source/processes/optical directory.

Optical photons are generated in GEANT4 without regard to energy conservation and their energy must therefore not be tallied as part of the energy balance of an event.

The are several steps to simulate optical photons in GEANT4.

- The optical photon and optical processes must be defined and configured
- Optical properties need to be assigned to relevant materials and surfaces
- If an optical photon is a primary particle, its polarization should be set

### Defining optical processes: G4OpticalPhysics constructor

The most straightforward way of using optical physics is to use the G4OpticalPhysics constructor in main(), as in the extended optical examples. This automatically includes all the optical physics processes and provides a default configuration. The configuration is stored in the class G4OpticalParameters, and can be accessed via the class G4OpticalParametersMessenger. Both macro commands and C++ methods are available.

An example of using G4OpticalPhysics is shown in Listing 5.3.

Listing 5.3: An example of using the G4OpticalPhysics constructor in main().

```
#include "G4OpticalPhysics.hh"
...

G4VModularPhysicsList* physicsList = new FTFP_BERT; // for example
G4OpticalPhysics* opticalPhysics = new G4OpticalPhysics();

physicsList->RegisterPhysics(opticalPhysics);
runManager->SetUserInitialization(physicsList);

// to set parameters in code, if wanted
auto opticalParams = G4OpticalParameters::Instance();
opticalParams->SetWLSTimeProfile("delta");
```

See the sections for each process for details on process-specific commands in the class G4OpticalParametersMessenger. There are two general commands:

- 1. /process/optical/verbose int sets the verbosity of all processes to the given value. 0 is silent, 1 is printing during initialization only, 2 is printing during tracking
- 2. /process/optical/processActivation name bool is used to deactivate individual processes. name may be one of Cerenkov, Scintillation, OpAbsorption, OpRayleigh, OpMieHG, OpBoundary, OpWLS, OWLS2. By default, all the processes are activated.

The optical parameters can be printed by invoking G4OpticalParameters::Instance()->Dump().

**Note:** In version 10.7, redundant commands were marked as deprecated, but were still available. In version 11, these commands have been removed.

## Setting the polarization

For the simulation of optical photons to work correctly in GEANT4, they must have a linear polarization. This is unlike most other particles in GEANT4 but is automatically and correctly done for optical photons that are generated as secondaries by existing processes in GEANT4. If the user wishes to start optical photons as primary particles, they must set the linear polarization using particle gun methods, the General Particle Source, or their PrimaryGeneratorAction. For an unpolarized source, the linear polarization should be sampled randomly for each new primary photon. See the extended optical examples for methods to set the polarization.

## **Defining material properties**

The optical properties of the medium which are key to the implementation of these types of processes are stored as entries in a G4MaterialPropertiesTable which is a private data member of the G4Material class.

Each entry in the G4MaterialPropertiesTable consists of a *key* and *value* pair. The key is used to retrieve the corresponding value. Keys are defined in two enums (and thus are G4ints). Keys are also available as G4Strings. Properties are added using the G4String key, but may be accessed by either the G4String key or the G4int key. Material property names are listed in tables for each process, below.

These properties may be independent of photon energy (denoted "Constant" or "Const") or they may be expressed as a function of the photon's energy. In the case of Constant parameters, the value is a G4double. Methods to access the Constant parameters have "Const" in their names.

In the case of energy-dependent properties, the value is a G4MaterialPropertyVector (which is a typedef to G4PhysicsFreeVector). Energy dependent properties may be added by specifying a G4MaterialPropertyVector, or by passing two std::vectors of type G4double. The first vector is the energy and the second vector is the property value at that energy. The numbers of elements in the two vectors must be the same (if std::vectors are used, GEANT4 will check that the numbers of elements in the two vectors are the same).

For backwards compatibility, energy dependent properties may also be created by specifying two C arrays of doubles. In this case, it is up to the user to ensure that both arrays have the same number of values, and the number of values must be passed as an argument.

Typically, a user only needs to add properties. Authors of processes that need these properties will need to access the values. Methods to add properties are:

- void AddConstProperty(const G4String& key, G4double PropertyValue)
- void AddConstProperty(const char\* key, G4double PropertyValue)
- G4MaterialPropertyVector\* AddProperty(const G4String& key, const std::vector<G4double>& photonEnergies, const std::vector<G4double>& propertyValues, G4bool createNewKey = false, G4bool spline = false)
- G4MaterialPropertyVector\* AddProperty(const char\* key, G4double\* PhotonEnergies, G4double\* PropertyValues, G4int NumEntries, G4bool createNewKey = false, G4bool spline = false)
- void AddProperty(const G4String& key, G4MaterialPropertyVector\* opv, G4bool createNewKey = false)
- void AddProperty(const char\* key, G4MaterialPropertyVector\* opv, G4bool createNewKey = false)
- void AddProperty(const G4String& key, const G4String& mat)

The createNewKey argument, if false, will check that the key string is one of the default keys. See *User-defined* properties for more information. The spline argument enables spline interpolation of the data.

An example of adding material properties to a material is shown in Listing 5.4. In this example the interpolation of the G4MaterialPropertyVector is to be done by a spline fit. The default is a linear interpolation.

Listing 5.4: Example of optical properties added to a G4MaterialPropertiesTable and linked to a G4Material

```
G4Material* scintillator = new G4Material(/*...*/);

std::vector<G4double> energy = {2.034*eV, 3.*eV, 4.136*eV};

std::vector<G4double> rindex = {1.3435, 1.351, 1.3608};

std::vector<G4double> absorption = {344.8*cm, 850.*cm, 1450.0*cm};

G4MaterialPropertiesTable* MPT = new G4MaterialPropertiesTable();

// property independent of energy
```

(continues on next page)

(continued from previous page)

```
MPT->AddConstProperty("SCINTILLATIONYIELD", 100./MeV);

// properties that depend on energy
MPT->AddProperty("RINDEX", energy, rindex);
MPT->AddProperty("ABSLENGTH", energy, absorption);
scintillator->SetMaterialPropertiesTable(MPT);
```

**Note:** Starting in version 11.0, GEANT4 will check that the property name is in the list of pre-defined properties. This avoids errors due to spelling mistakes. If you want to define a new property name, see *User-defined properties*.

**Note:** Digitized data of refractive indices for many materials can be accessed for instance at https://refractiveindex.info.

#### **Pre-defined properties**

Starting in version 11.0, some optical material properties are defined in GEANT4. Currently, these are the refractive indices for "Air", "Water", "PMMA", and "Fused Silica". The precise values are found in source/materials/include/G4OpticalMaterialProperties.hh.

To use them, add them to the material properties table as follows:

```
G4MaterialPropertiesTable* MT = new G4MaterialPropertiesTable();
MT->AddProperty("RINDEX", "Fused Silica");
```

#### **User-defined properties**

One may create their own properties, for example, for use in custom processes. To facilitate this, the various AddProperty()/AddConstProperty() methods have a default argument createNewKey. Set this to true to allow a new key name.

```
myMPT->AddConstProperty("USERDEFINEDCONST", 3.14, true);
```

This value may accessed by the string name:

```
G4double val = myMPT->GetConstProperty("USERDEFINEDCONST");
```

but there is a potential speed-up. Material properties are stored internally in a vector. To access a material property, first find the index of the property (e.g. at initialization), then use the index during the event loop.

```
G4int index = myMPT->GetConstPropertyIndex("USERDEFINEDCONST");
...
G4double val = myMPT->GetConstProperty(index);
```

It is possible to test if a property has been defined. In the case of constant properties, the methods ConstPropertyExists(const G4String& key), ConstPropertyExists(const char\* key), ConstPropertyExists(const G4int index) return true if the property is defined, false otherwise. For energy-dependent properties, the GetProperty(...) methods return nullptr if the property has not been defined.

#### **Cerenkov Effect**

The radiation of Cerenkov light occurs when a charged particle moves through a dispersive medium faster than the group velocity of light in that medium. Photons are emitted on the surface of a cone, whose opening angle with respect to the particle's instantaneous direction decreases as the particle slows down. At the same time, the frequency of the photons emitted increases, and the number produced decreases. When the particle velocity drops below the local speed of light, the radiation ceases and the emission cone angle collapses to zero. The photons produced by this process have an inherent polarization perpendicular to the cone's surface at production.

To generate Cerenkov optical photons in a material, refractive index must be specified using the material property name RINDEX.

The flux, spectrum, polarization and emission of Cerenkov radiation in the AlongStepDoIt method of the class G4Cerenkov follow well-known formulae, with two inherent computational limitations. The first arises from stepwise simulation, and the second comes from the requirement that numerical integration calculate the average number of Cerenkov photons per step. The process makes use of a G4PhysicsTable which contains incremental integrals to expedite this calculation.

The time and position of Cerenkov photon emission are calculated from quantities known at the beginning of a charged particle's step. The step is assumed to be rectilinear even in the presence of a magnetic field. The user may limit the step size by specifying a maximum (average) number of Cerenkov photons created during the step, using the setMaxPhotons command. The actual number generated will necessarily be different due to the Poissonian nature of the production. In the present implementation, the production density of photons is distributed evenly along the particle's track segment, even if the particle has slowed significantly during the step. The step can also be limited with the setMaxBetaChange command, where the argument is the allowed change in percent.

The large number of optical photons that can be produced (about 300/cm in water) can fill the available memory. GEANT4 by default will track the Cerenkov photons produced in a step before continuing to track the primary particle. This may be changed using the setTrackSecondariesFirst command.

#### Configuration

Material property names used in the process are given in the following table.

Table 5.2: Material properties for the Cerenkov process.

Name	Туре	Description	Unit Category
RINDEX	Energy-dependent	Refractive index	Unitless

These parameters are available to configure the process.

- Set the step size to limit the number of photons produced (on average) to a given value (an integer N)
  - macro command: /process/optical/cerenkov/setMaxPhotons N
  - C++ statement: G4OpticalParameters::Instance()->SetMaxNumPhotonsPerStep(G4int);
  - default value: 100
- Set the maximum change in  $\beta = v/c$  in a step, expressed in percent.
  - macro command: /process/optical/cerenkov/setMaxBetaChange X.X
  - C++ statement: G4OpticalParameters::Instance()->SetMaxBetaChangePerStep(G4double);
  - default value: 10.0
- Specify whether to add Cerenkov photons to the stack, and track them.
  - macro command: /process/optical/cerenkov/setStackPhotons true
  - C++ statement: G4OpticalParameters::Instance()->SetCerenkovStackPhotons(G4bool);
  - default value: true
- Specify whether to track secondaries produced in the step before continuing with primary.
  - macro command: /process/optical/cerenkov/setTrackSecondariesFirst true
  - C++ statement: G4OpticalParameters::Instance()->SetCerenkovTrackSecondariesFirst(G4bool);

- default value: true
- Set the verbosity of the process. 0 = silent; 1 = initialisation; 2 = during tracking
  - macro command: /process/optical/cerenkov/verbose
  - C++ statement: G4OpticalParameters::Instance()->SetCerenkovVerbosity(G4int);
  - default value: 0

#### **Scintillation**

A scintillating material is characterised by the number of optical photons produced (the yield), their spectrum, and the distribution of emission times. The yield may be dependent on the type of primary particle. The distribution of emission times can be characterised by an exponential rise time, and a decay with one or more time constants. Starting with GEANT4 version 10.7, it is possible to specify up to three decay time constants, for particle-independent and particle-dependent yields. This new method uses different material property names than used in previous versions. The method used in previous versions is no longer available in GEANT4 version 11.0. All of the capabilities of the previous method are available with the new method.

The scintillation yield may depend on the type of primary particle. In this case, the material parameter names are modified from the case where the yield is independent of primary particle.

Each photon's frequency is sampled from the empirical spectrum. The photons originate evenly along the track segment and are emitted uniformly into the  $4\pi$  solid angle with a random linear polarization perpendicular to their momentum direction, and an emission time characteristic for the scintillation component.

**Important:** Starting in GEANT4 version 11.0, only the new method (called "enhanced" in version 10.7) is available to specify decay time constants. It is no longer necessary to set the optical parameter setEnhancedTimeConstants to true.

#### Scintillation independent of particle type

If the scintillation yield is independent of particle type, the yield is specified using the material constant property SCINTILLATIONYIELD. The mean number of optical photons in a step is calculated as the SCINTILLATIONYIELD property, times the yield factor, times either the VisibleEnergyDepositAtAStep (if Birks' saturation is used) or the total energy deposit (otherwise). (Note the yield factor is redundant here and should not be used. See the description of the old scintillation methods for its use.) The property SCINTILLATIONYIELD is expressed in number per energy.

If the calculated mean number of optical photons for the step is less than or equal to 10, the actual number is determined from a Poisson distribution with that mean, then converted to an integer. If the mean number of photons is greater than 10, the number of photons is chosen from a Gaussian distribution with that mean, and a sigma equal to the square root of the the mean times a factor called the resolution scale. This factor is set using the material constant property RESOLUTIONSCALE. A resolution scale of zero produces no fluctuation.

There may be 1 to 3 decay component with independent spectra and rise and decay time constants.

If there is one component, specify the decay time constant with the material constant property SCINTILLATIONTIMECONSTANT1. If a non-zero rise time is wanted, set the optical parameter setFiniteRiseTime to true, and set the material constant property SCINTILLATIONRISETIME1 to the desired value. The creation time of the photon is chosen from a distribution with these characteristics.

The energy spectrum of the emitted photons is specified using the energy-dependent material property SCINTILLATIONCOMPONENT1.

If there are 2 or 3 decay component, the time constant, rise time, and spectrum must be specified for the additional component. The property names are the same as for the first component, with the "1" at the end of the property name

replaced with "2" or "3". Additionally, the fraction of photons in each component must be specified. Set the material constant properties SCINTILLATIONYIELD1, SCINTILLATIONYIELD2, and SCINTILLATIONYIELD3 (if there are three components) to the relative amount of photons produced in each component. The values will be automatically normalized. The spectra are specified using the material properties SCINTILLATIONCOMPONENT2 and SCINTILLATIONCOMPONENT3. The values of the time constants do not need to be ordered (i.e., SCINTILLATIONTIMECONSTANT1).

#### Scintillation dependent on particle type

The scintillation yield, and the strength of each component, may depend on particle type. If so, set the optical parameter <code>setByParticleType</code> true, and specify a yield vector for each particle type using material property names such as <code>ALPHASCINTILLATIONYIELD</code>. The mean number of photons produced in the step is calculated as the difference in the value of the yield vector at the pre-step kinetic energy of the primary particle, and the value of the yield vector at the pre-step kinetic energy minus the energy deposit in the step:

```
ScintillationYield = yieldVector->Value(PreStepKineticEnergy)
- yieldVector->Value(PreStepKineticEnergy - StepEnergyDeposit);
```

The relative amounts of photons produced in each component are specified using the material constant properties with key names such as ALPHASCINTILLATIONYIELD1, etc. If there is only one component for a primary particle, it is not necessary to specify the per-component yield e.g. ALPHASCINTILLATIONYIELD1.

The rise and decay time constants and the emission spectra are not dependent on particle type. These are specified in the same way as for the scintillation yield independent of particle type. RESOLUTIONSCALE also is equivalent.

Listing 5.5: Specification of scintillation properties in DetectorConstruction using enhanced time constants (from extended example LXe).

```
//Liquid Xenon
fLXe = new G4Material("LXe", z=54., a=131.29*g/mole, density=3.020*g/cm3);
std::vector<G4double> lxe_Energy = {7.0*eV, 7.07*eV, 7.14*eV};
std::vector<G4double> lxe_SCINT = {0.1, 1.0, 0.1};
std::vector<G4double> lxe_RIND = {1.59, 1.57, 1.54};
std::vector<G4double> lxe_ABSL = {35.*cm, 35.*cm, 35.*cm};
fLXe_mt = new G4MaterialPropertiesTable();
fLXe_mt->AddProperty("SCINTILLATIONCOMPONENT1", lxe_Energy, lxe_SCINT);
fLXe_mt->AddProperty("SCINTILLATIONCOMPONENT2", lxe_Energy, lxe_SCINT);
fLXe_mt->AddProperty("RINDEX",
                                      lxe_Energy, lxe_RIND);
fLXe_mt->AddProperty("ABSLENGTH",
                                     lxe_Energy, lxe_ABSL);
fLXe_mt->AddConstProperty("SCINTILLATIONYIELD", 12000./MeV);
fLXe_mt->AddConstProperty("RESOLUTIONSCALE", 1.0);
fLXe_mt->AddConstProperty("SCINTILLATIONTIMECONSTANT1", 20.*ns);
fLXe_mt->AddConstProperty("SCINTILLATIONTIMECONSTANT2", 45.*ns);
fLXe_mt->AddConstProperty("SCINTILLATIONYIELD1", 1.0);
fLXe_mt->AddConstProperty("SCINTILLATIONYIELD2", 0.0);
fLXe->SetMaterialPropertiesTable(fLXe_mt);
// Set the Birks Constant for the LXe scintillator
fLXe->GetIonisation()->SetBirksConstant(0.126*mm/MeV);
```

### Configuration

These parameters are available to configure the scintillation process.

- Use enhanced time constants (the new method allowing more decay components)
  - macro command: /process/optical/scintillation/setEnhancedTimeConstants true
  - C++ statement: G4OpticalParameters::Instance()->SetScintEnhancedTimeConstants(G4bool)
  - default value: false
- Multiply the yield by a constant factor. Used when more than one scintillation process is defined in the user's physics list.
  - macro command: /process/optical/scintillation/setYieldFactor
  - C++ statement: G4OpticalParameters::Instance()->SetScintYieldFactor(G4double val)
  - default value: 1.0
- Set the ratio of emitted photons of the fast and slow decay components. Used when more than one scintillation process is defined in the user's physics list.
  - macro command: /process/optical/scintillation/setExcitationRatio
  - C++ statement: G4OpticalParameters::Instance()->SetScintExcitationRatio(G4double val)
  - default value: 1.0
- Enable particle-dependent yields
  - macro command: /process/optical/scintillation/setByParticleType
  - C++ statement: G4OpticalParameters::Instance()->SetScintByParticleType(G4bool val)
  - default value: false
- · Record track information
  - macro command: /process/optical/scintillation/setTrackInfo
  - C++ statement: G4OpticalParameters::Instance()->SetScintTrackInfo(G4bool val)
  - default value: false
- Whether to track secondaries before resuming tracking of primary particle
  - macro command: /process/optical/scintillation/setTrackSecondariesFirst
  - C++ statement: G4OpticalParameters::Instance()->SetScintTrackSecondariesFirst(G4bool val)
  - default value: true
- Whether to use a finite rise time for the secondary emission time
  - macro command: /process/optical/scintillation/setFiniteRiseTime
  - C++ statement: G4OpticalParameters::Instance()->SetScintFiniteRiseTime(G4bool val)
  - default value: false
- Whether to add produced optical photons to the stack (the alternative is to kill them)
  - macro command: /process/optical/scintillation/setStackPhotons
  - C++ statement: G4OpticalParameters::Instance()->SetScintStackPhotons(G4bool val)
  - default value: true
- Set the verbosity level. 0 = silent, 1 = initialisation, 2 = during tracking
  - macro command: /process/optical/scintillation/verbose
  - C++ statement: G4OpticalParameters::Instance()->SetScintVerboseLevel(G4int val)
  - default value: 0

Table 5.3: Material properties for the optical scintillation process.

Name	Туре	Description	Unit category
ALPHASCINTILLATIONYIELD	Energy-	Yield vector for alphas	1/Energy
	dependent		
ALPHASCINTILLATIONYIELD1	Constant	Relative yield of component	Unitless
		1 for alphas	
ALPHASCINTILLATIONYIELD2	Constant	Relative yield of component	Unitless
		2 for alphas	

continues on next page

Table 5.3 – continued from previous page

		Unit category
		Unitless
Constant		Cintiess
Energy-		1/Energy
	Tield vector for dedictions	17 Energy
	Relative yield of component	Unitless
Constant		Cintiess
Constant	1	Unitless
Constant		Cintiess
Constant	1	Unitless
Energy-	1	1/Energy
		i, znergj
•	Relative yield of component	Unitless
Constant	1	Unitless
Constant	1	Unitless
	3 for electrons	
Energy-	Yield vector for ions	1/Energy
	Relative yield of component	Unitless
Constant	1	Unitless
Constant	1	Unitless
Energy-		1/Energy
	1	
Constant	Relative yield of component	Unitless
	1 for protons	
Constant	Relative yield of component	Unitless
	2 for protons	
Constant	Relative yield of component	Unitless
	3 for protons	
Constant	Factor to vary width of yield	Unitless
	distribution	
Energy-	Energy spectrum for decay	Unitless
dependent	component 1	
Energy-	Energy spectrum for decay	Unitless
dependent	component 2	
Energy-	Energy spectrum for decay	Unitless
dependent	component 3	
Constant	Rise time for component 1	Time
Constant	Rise time for component 2	Time
Constant	Rise time for component 3	Time
Constant	Time constant for compo-	Time
	nent 1	
Constant	Time constant for compo-	Time
	nent 2	
	Type Constant  Energy- dependent Constant  Constant  Energy- dependent Constant  Energy- dependent Constant  Constant	Constant  Relative yield of component 3 for alphas  Energy- dependent  Constant  Relative yield of component 1 for deuterons  Constant  Relative yield of component 2 for deuterons  Constant  Relative yield of component 3 for deuterons  Energy- dependent  Constant  Relative yield of component 1 for electrons  Energy- dependent  Constant  Relative yield of component 2 for electrons  Constant  Relative yield of component 2 for electrons  Constant  Relative yield of component 3 for electrons  Energy- dependent  Constant  Relative yield of component 1 for ions  Constant  Relative yield of component 2 for ions  Constant  Relative yield of component 2 for ions  Constant  Relative yield of component 2 for ions  Constant  Relative yield of component 3 for ions  Constant  Relative yield of component 1 for protons  Constant  Relative yield of component 2 for protons  Constant  Relative yield of component 1 for protons  Constant  Relative yield of component 2 for protons  Constant  Relative yield of component 1 for protons  Constant  Relative yield of component 2 for protons  Constant  Relative yield of component 2 for protons  Constant  Relative yield of component 1 for protons  Constant  Relative yield of component 2 for protons  Constant  Relative yield of component 3 for protons  Constant  R

continues on next page

Name	Type	Description	Unit category
SCINTILLATIONTIMECONSTANT3	Constant	Time constant for compo-	Time
		nent 3	
SCINTILLATIONYIELD	Constant	Mean yield (number of par-	1/Energy
		ticle produce per energy)	
SCINTILLATIONYIELD1	Constant	Relative yield of component	Unitless
		1	
SCINTILLATIONYIELD2	Constant	Relative yield of component	Unitless
		2	
SCINTILLATIONYIELD3	Constant	Relative yield of component	Unitless
		3	
TRITONSCINTILLATIONYIELD	Energy-	Yield vector for tritons	1/Energy
	dependent		
TRITONSCINTILLATIONYIELD1	Constant	Relative yield of component	Unitless
		1 for tritons	
TRITONSCINTILLATIONYIELD2	Constant	Relative yield of component	Unitless
		2 for tritons	
TRITONSCINTILLATIONYIELD3	Constant	Relative yield of component	Unitless
		3 for tritons	

Table 5.3 – continued from previous page

### **Absorption**

The implementation of optical photon bulk absorption, G4OpAbsorption, is trivial in that the process merely kills the particle. The procedure requires the user to fill the relevant G4MaterialPropertiesTable with empirical data for the absorption length, using ABSLENGTH as the property key. The absorption length is the average distance traveled by a photon before being absorbed by the medium; i.e., it is the mean free path returned by the GetMeanFreePath method.

Table 5.4: Material properties for the optical absorption process.

Name	Туре	Description	Unit category
ABSLENGTH	Energy-dependent	Absorption length	Length

This G4OpticalParameters command can be used to configure the process.

- Set the verbosity of the absorption process. 0 = silent; 1 = initialisation; 2 = during tracking.
  - macro command: /process/optical/absorption/verbose 1
  - C++ statement: G4OpticalParameters::Instance()->SetAbsorptionVerboseLevel(G4int verboseLevel);
  - default value: 0

### **Rayleigh Scattering**

The differential cross section in Rayleigh scattering,  $d\sigma/d\Omega$ , is proportional to  $1+\cos^2\theta$ , where  $\theta$  is the angle of the new polarization vector with respect to the old polarization vector. The G40pRayleigh scattering process samples this angle accordingly and then calculates the scattered photon's new direction by requiring that it be perpendicular to the photon's new polarization in such a way that the final direction, initial and final polarizations are all in one plane. This process thus depends on the particle's polarization (spin). A photon which does not have a polarization will not be Rayleigh scattered.

The process requires Rayleigh scattering attenuation length data. The Rayleigh scattering attenuation length is the average distance traveled by a photon before it is Rayleigh scattered in the medium and it is the distance returned by the GetMeanFreePath method. The attenuation length may be provided by the user filling a G4MaterialPropertiesTable with key RAYLEIGH.

The G40pRayleigh class provides a method which can be used to calculate the attenuation coefficient of a medium following the Einstein-Smoluchowski formula. The derivation of this formula requires the use of statistical mechanics, includes temperature, and depends on the isothermal compressibility of the medium. This function is convenient when the Rayleigh attenuation length is not known from measurement but may be calculated from first principles using the above material constants. If the material property RAYLEIGH is not set, the attenuation coefficient will be calculated if either the material name is "Water", or the material's isothermal compressibility is provided using the material property ISOTHERMAL\_COMPRESSIBILITY. For the material "Water", a temperature of 10°C and isothermal compressibility of 7.658 x 10<sup>-23</sup> m³/MeV is used. For other materials, the temperature is determined by calling them material's GetTemperature(). The calculated attenuation length may be scaled by provided a material property RS\_SCALE\_FACTOR.

Name	Туре	Description	Unit cate-
			gory
ISOTHER-	Constant	Isothermal compressibility. Can be used to calcu-	Vol-
MAL_COMPRESSIBILITY		late mean free path	ume/Energy
RAYLEIGH	Energy-	Attenuation length	Length
	dependent		
RS_SCALE_FACTOR	Constant	If set, multiply the calculated mean free path by	Unitless
		this factor	

Table 5.5: Material properties for the optical Rayleigh scattering process.

This G4OpticalParameters command can be used to configure the process.

- Set the verbosity of the Rayleigh scattering process. 0 = silent; 1 = initialisation; 2 = during tracking.
  - macro command: /process/optical/rayleigh/verbose 1
  - C++ statement: G4OpticalParameters::Instance()->SetRayleighVerboseLevel(G4int verboseLevel);
  - default value: 0

### Wavelength Shifting

Wavelength shifting (WLS) fibers are used in many high-energy particle physics experiments. They absorb light at one wavelength and re-emit light at a different wavelength and are used for several reasons. For one, they tend to decrease the self-absorption of the detector so that as much light reaches the PMTs as possible. WLS fibers are also used to match the emission spectrum of the detector with the input spectrum of the PMT.

A WLS material is characterized by its photon absorption and photon emission spectrum and by a possible time delay between the absorption and re-emission of the photon. Wavelength Shifting may be simulated by specifying these empirical parameters for each WLS material in the simulation. It is sufficient to specify a relative spectral distribution as a function of photon energy for the WLS material. WLSABSLENGTH is the absorption length of the material as a function of the photon's energy. WLSCOMPONENT is the relative emission spectrum of the material as a function of the photon's energy, and WLSTIMECONSTANT accounts for any time delay which may occur between absorption and re-emission of the photon. An example is shown in the Listing 5.6.

Listing 5.6: Specification of WLS properties in DetectorConstruction.

(continues on next page)

(continued from previous page)

The way the WLSTIMECONSTANT is used depends on the time profile method chosen by the user. If the "exponential" option is set, the time delay between absorption and re-emission of the photon is sampled from an exponential distribution, with the decay term equal to WLSTIMECONSTANT. If, on the other hand, the "delta" option is chosen, the time delay is a delta function and equal to WLSTIMECONSTANT. The default is "delta".

The number of secondaries emitted may be configured. By default, each WLS interaction generates one secondary. If the material property WLSMEANNUMBERPHOTONS is set, the number of secondaries is chosen from a Poisson distribution with mean equal to WLSMEANNUMBERPHOTONS.

**Important:** New in GEANT4 version 10.7: definition of two WLS processes.

It is possible to have a material with two WLS processes. The G4OpticalPhysics constructor builds two processes by default, named OpWLS and OpWLS2. Usage of the second process is analogous to the first. The material property names for the OpWLS2 process are the same as for OpWLS, with a "2" appended. The time profile may be chosen to be "exponential" or "delta" using macro or C++ commands. In order to activate the OpWLS2 process in a material, the user needs to define the material properties.

Material properties are shown in Table 5.6.

Name	Туре	Description	Unit cate-
			gory
WLSABSLENGTH	Energy-	Absorption length of first WLS process	Length
	dependent		
WLSABSLENGTH2	Energy-	Absorption length of second WLS process	Length
	dependent		
WLSCOMPONENT	Energy-	Emission spectrum of first WLS process	Unitless
	dependent		
WLSCOMPONENT2	Energy-	Emission spectrum of second WLS process	Unitless
	dependent		
WLSMEANNUMBER-	Constant	Mean number of photons emitted per interaction, for	Unitless
PHOTONS		first WLS process	
WLSMEANNUMBER-	Constant	Mean number of photons emitted per interaction, for	Unitless
PHOTONS2		second WLS process	
WLSTIMECONSTANT	Constant	Time constant for emission, for first WLS process	Time
WLSTIMECONSTANT2	Constant	Time constant for emission, for second WLS process	Time

Table 5.6: Material properties for WLS processes.

These parameters are available to configure the process:

- Set the time profile of the first WLS process to be either "delta" or "exponential":
  - macro command: /process/optical/wls/setTimeProfile value

- C++ statement: G4OpticalParameters::Instance()->SetWLSTimeProfile(const G4String& val);
- default value: delta
- Set the verbosity of the first WLS process. 0 = silent; 1 = initialisation; 2 = during tracking.
  - macro command: /process/optical/wls/verbose 1
  - C++ statement: G4OpticalParameters::Instance()->SetWLSVerboseLevel(G4int verboseLevel);
  - default value: 0
- Set the time profile of the second WLS process to be either "delta" or "exponential":
  - macro command: /process/optical/wls/setTimeProfile value
  - C++ statement: G4OpticalParameters::Instance()->SetWLSTimeProfile(const G4String& val);
  - default value: delta
- Set the verbosity of the second WLS process. 0 = silent; 1 = initialisation; 2 = during tracking.
  - macro command: /process/optical/wls/verbose 1
  - C++ statement: G4OpticalParameters::Instance()->SetWLSVerboseLevel(G4int verboseLevel);
  - default value: 0

#### Mie Scattering

Mie Scattering (or Mie solution) is an analytical solution of Maxwell's equations for scattering of optical photons by spherical particles. It is significant only when the radius of the scattering object is of order of the wave length. The analytical expressions for Mie Scattering are complicated since they are a series sum of Bessel functions. One common approximation made is called *Henyey-Greenstein (HG)*. The implementation in GEANT4 follows the HG approximation (for details see the Physics Reference Manual) and the treatment of polarization and momentum are similar to that of Rayleigh scattering. We require the final polarization direction to be perpendicular to the momentum direction. We also require the final momentum, initial polarization, and final polarization to be in the same plane.

The process requires a G4MaterialPropertiesTable to be filled by the user with Mie scattering length data (entered with the name MIEHG) analogous to Rayleigh scattering. The Mie scattering attenuation length is the average distance traveled by a photon before it is Mie scattered in the medium and it is the distance returned by the GetMean-FreePath method. In practice, the user not only needs to provide the attenuation length of Mie scattering, but also needs to provide the constant parameters of the approximation  $g_f$ ,  $g_b$ , and  $r_f$ , with AddConstProperty and with the names MIEHG\_FORWARD, MIEHG\_BACKWARD, and MIEHG\_FORWARD\_RATIO, respectively; see extended example optical/OpNovice.

Name	Type	Description	Unit cate-
			gory
MIEHG	Energy- dependent	Attenuation length	Length
MIEHG_BACKWARD	Constant	Parameter used in sampling of scattering direc-	Unitless
		tion	
MIEHG_FORWARD	Constant	Parameter used in sampling of scattering direc-	Unitless
		tion	
MIEHG_FORWARD_RATIO	Constant	Parameter used in sampling of scattering direc-	Unitless
		tion	

Table 5.7: Material properties for the optical Mie scattering process.

This G4OpticalParameters command can be used to configure the process.

- Set the verbosity of the Mie scattering process. 0 = silent; 1 = initialisation; 2 = during tracking.
  - macro command: /process/optical/mie/verbose 1
  - C++ statement: G4OpticalParameters::Instance()->SetMieVerboseLevel(G4int verboseLevel);
  - default value: 0

#### **Boundary Process**

Optical photons interact with boundaries between volumes, for example, to reflect or refract. There are various methods of specifying a surface and assigning properties to it.

Reference: E. Hecht and A. Zajac, Optics [Hecht1974]

When a photon arrives at a medium boundary its behavior depends on the nature of the two materials that join at that boundary. Medium boundaries may be formed between two dielectric materials or a dielectric and a metal.

In the case of an interface between a dielectric and a metal, the photon can be absorbed by the metal or reflected back into the dielectric. If the photon is absorbed it can be detected according to the photoelectron efficiency of the metal.

As expressed in Maxwell's equations, Fresnel reflection and refraction are intertwined through their relative probabilities of occurrence. Therefore neither of these processes, nor total internal reflection, are viewed as individual processes deserving separate class implementation. Nonetheless, an attempt was made to adhere to the abstraction of having independent processes by splitting the code into different methods where practicable.

The program defaults to the GLISUR model and *polished* surface finish when no specific model and surface finish is specified by the user. In the case of a dielectric-metal interface, or when the GLISUR model is specified, the only surface finish options available are *polished* or *ground*. For dielectric-metal surfaces, the G40pBoundaryProcess also defaults to unit reflectivity and zero detection efficiency. In cases where the user specifies the UNIFIED model (Fig. 5.1), but does not otherwise specify the model reflection probability constants, the default becomes Lambertian reflection.

When an optical photon arrives at a boundary it is absorbed if the medium of the volume being left behind has no index of refraction defined. A photon is also absorbed in case of a dielectric-dielectric polished or ground surface when the medium about to be entered has no index of refraction. It is absorbed for backpainted surfaces when the surface has no index of refraction.

#### Specifying the surface

The physical surface object specifies which model the boundary process should use to simulate interactions with that surface. In addition, the physical surface can have a material property table all its own. The usage of this table allows all specular constants to be wavelength dependent. In case the surface is painted or wrapped (but not a cladding), the table may include the thin layer's index of refraction. This allows the simulation of boundary effects at the intersection between the medium and the surface layer, as well as the Lambertian reflection at the far side of the thin layer. This occurs within the process itself and does not invoke the G4Navigator. Combinations of surface finish properties, such as *polished* or *ground* and *front painted* or *back painted*, enumerate the different situations which can be simulated.

There are three methods of specifying an optical surface.

- 1. For the simple case of a perfectly smooth interface between two dielectric materials, all the user needs to provide are the refractive indices (RINDEX) of the two materials stored in their respective G4MaterialPropertiesTables.
- 2. A *skin surface* is the surface entirely surrounding a logical volume. This is useful where a volume is coated with a reflector and placed into many different mother volumes. A limitation is that the skin surface can only have one and the same optical property for all of the enclosed volume's sides. An optical surface is created and defined using G4OpticalSurface. This surface is assigned to a logical volume using the class G4LogicalSkinSurface.
- 3. A border surface is defined by specifying the ordered pair of physical volumes touching at the surface. Because the pair of physical volumes is ordered, the user may specify different optical properties for photons arriving from the reverse side of the same interface. For the optical boundary process to use a border surface, the two volumes must have been positioned with G4PVPlacement. The ordered combination can exist at many places in the simulation. An optical surface is created and defined using G4OpticalSurface. This surface is assigned to the ordered pair of physical volumes using the class G4LogicalBorderSurface.

If the geometry boundary has a *border surface* this surface takes precedence, otherwise the program checks for *skin surfaces*. The *skin surface* of the daughter volume is taken if a daughter volume is entered, or else the program checks for a *skin surface* of the current volume. When the optical photon leaves a volume without entering a daughter volume the *skin surface* of the current volume takes precedence over that of the volume about to be entered.

Listing 5.7: Defining border and skin surfaces (from extended example OpNovice).

```
#include "G4LogicalBorderSurface.hh"
#include "G4LogicalSkinSurface.hh"
#include "G4OpticalSurface.hh"
// The experimental Hall
G4Box* expHall_box = new G4Box("World", fExpHall_x, fExpHall_y, fExpHall_z);
G4LogicalVolume* expHall_log =
 new G4LogicalVolume(expHall_box, air, "World", 0, 0, 0);
G4VPhysicalVolume* expHall_phys =
 new G4PVPlacement(0, G4ThreeVector(), expHall_log, "World", 0, false, 0);
// The Water Tank
G4Box* waterTank_box = new G4Box("Tank", fTank_x, fTank_y, fTank_z);
G4LogicalVolume* waterTank_log =
 new G4LogicalVolume(waterTank_box, water, "Tank", 0, 0, 0);
G4VPhysicalVolume* waterTank_phys = new G4PVPlacement(
 0, G4ThreeVector(), waterTank_log, "Tank", expHall_log, false, 0);
// The Air Bubble
G4Box* bubbleAir_box = new G4Box("Bubble", fBubble_x, fBubble_y, fBubble_z);
G4LogicalVolume* bubbleAir_log =
 new G4LogicalVolume(bubbleAir_box, air, "Bubble", 0, 0, 0);
new G4PVPlacement(0, G4ThreeVector(0., 2.5 * m, 0.), bubbleAir_log, "Bubble",
                 waterTank_log, false, 0);
G4OpticalSurface* opWaterSurface = new G4OpticalSurface("WaterSurface");
opWaterSurface->SetType(dielectric_LUTDAVIS);
opWaterSurface->SetFinish(Rough_LUT);
opWaterSurface->SetModel(DAVIS);
G4LogicalBorderSurface * waterSurface = new G4LogicalBorderSurface(
 "WaterSurface", waterTank_phys, expHall_phys, opWaterSurface);
G4OpticalSurface* opAirSurface = new G4OpticalSurface("AirSurface");
opAirSurface->SetType (dielectric_dielectric);
opAirSurface->SetFinish(polished);
opAirSurface->SetModel(glisur);
G4LogicalSkinSurface * airSurface =
 new G4LogicalSkinSurface("AirSurface", bubbleAir_log, opAirSurface);
```

#### Surface models: Defining the boundary properties

There are several models to describe the interactions of optical photons at a surface. These are defined in an emum:

Listing 5.8: Optical surface models.

The model is specified by calling the SetModel (G4int model) method of the surface.

#### No surface defined

In the special case where no surface has been defined, but the two volumes defining the surface have the refractive index defined using the material property RINDEX, the surface is taken to be perfectly smooth, and both materials are taken to be dielectric. The photon can undergo total internal reflection, refraction or reflection, depending on the photon's wavelength, angle of incidence, and the refractive indices on both sides of the boundary. Furthermore, reflection and transmission probabilities are sensitive to the state of linear polarization.

#### The UNIFIED model

One implementation of the G4OpBoundaryProcess class employs the UNIFIED model [Levin1996] of the DE-TECT program [Knoll1988]. It applies to dielectric-dielectric interfaces and tries to provide a realistic simulation, which deals with all aspects of surface finish and reflector coating. The surface may be assumed as smooth and covered with a metallized coating representing a specular reflector with given reflection coefficient, or painted with a diffuse reflecting material where Lambertian reflection occurs. The surfaces may or may not be in optical contact with another component and most importantly, one may consider a surface to be made up of micro-facets with normal vectors that follow given distributions around the nominal normal for the volume at the impact point. For very rough surfaces, it is possible for the photon to inversely aim at the same surface again after reflection of refraction and so multiple interactions with the boundary are possible within the process itself and without the need for relocation by G4Navigator.

The UNIFIED model (Fig. 5.1) provides for a range of different reflection mechanisms. The specular lobe constant (material property name SPECULARLOBECONSTANT) represents the reflection probability about the normal of a micro facet. The specular spike constant (material property name SPECULARSPIKECONSTANT), in turn, illustrates the probability of reflection about the average surface normal. The diffuse lobe constant is for the probability of internal Lambertian reflection, and finally the back-scatter spike constant (material property name BACKSCATTERCONSTANT) is for the case of several reflections within a deep groove with the ultimate result of exact back-scattering. The four probabilities add up to one, with the diffuse lobe constant being calculated by the code from other other three values that the user entered. The reader may consult the reference for a thorough description of the model.

It is possible to specify that a given fraction of photons are absorbed at the surface, or transmitted without change in direction or polarization. This is applicable for dielectric\_dielectric interfaces that are not backpainted. The material properties REFLECTIVITY and TRANSMISSION are used. By default, REFLECTIVITY equals 1 and TRANSMISSION equals 0. At a surface interaction, a random number is chosen. If the random number is greater than the sum of the values of REFLECTIVITY and TRANSMISSION at the photon energy, the photon is absorbed. Otherwise, if the random number is greater than the REFLECTIVITY value, the photon is transmitted. Otherwise, the usual calculation of scattering takes place.

#### Dielectric dielectric Polished Front Painted GroundBackPainted GroundFrontPainted PolishedBackPainted Only Reflection or Reflectivity is used to The Polished refers to the wrapping. It implies the wrapping is a perfectly smooth mirror with only specular spike reflection Absorption; No refraction; The Ground refers to the wrapping. It implies the wrapping is a ground mirror determine whether Only Reflection or Absorption; No photon is absorbed ( Strictly speaking here lection probability set refraction; with only Lambertian reflection taking Snell's Law is applied taking place. Reflection off the wrapper set by Reflectivity Reflection probability set by Reflectivity. Only Lambertian reflection by Reflectivity. If reflected, then it is place. Reflection off the wrapper set by based on Refractive reflectivity is not the index of the two media But Before this reflection coefficient, it is 1 minus the Specular Spike reflection Reflectivity. The Sigma Alpha value specified refers to the The Sigma Alpha value specified refers to the crystal-air gap interface. Snell's law is applied after sampling the FacetNormal, crystal-air gap interface. Snell's law is applied after sampling the FacetNormal, and if absorption Reflectivity is used to determine whether coefficient) reflection takes place, one of the four and if reflection takes place, one of the four (specular spike, specular lobe, (specular spike, specular lobe, backscatter lambertian) takes place with respect to photon is absorbed ( First, FacetNormal is Strictly speaking here reflectivity is not the sampled using Sigma Alpha backscatter, lambertian) takes place with FacetNormal according to assigned respect to FacetNormal according to reflection coefficient, probabilities assigned probabilities it is 1 minus the absorption coefficient) Dielectric metal Polished Ground Now. Snell's Law is applied with respect to this facet normal Only Reflection or Absorption; No refraction; Reflection probability set by Reflectivity. If reflected, one of the four specular spike, backscatter, lambertian, or specular lobe reflection with respect to a FacetNormal, takes If Snell's law results in reflection, then one of the four (specular spike, place according to assigned probabilities. specular lobe, backscatter, lambertian) takes place with respect to FacetNormal

**UNIFIED MODEL FOR OPTICAL SURFACES** 

Fig. 5.1: Diagram of the UNIFIED Model for Optical Surfaces (courtesy A. Shankar)

NOTE: Applying Snell's Law includes applying Fresnel's equations of reflection and refraction, and these combined

may result in Fresnel Refraction or Total Internal Reflection o Fresnel Reflection

according to assigned probabilities

If a photon is absorbed at the boundary, it may by detected—that is, its status set to "Detect" and its energy deposited locally. The material property EFFICIENCY is used to specify the fraction of photons detected.

The sigma\_alpha parameter allows sepcification of the surface roughness. The facet normal is chosen from a Gaussian distribution with this sigma, with a maximum of the lower of 1 and 4 times sigma\_alpha.

Listing 5.9: Dielectric-dielectric surface properties defined via the G4OpticalSurface.

```
G4VPhysicalVolume* volume1;
G4VPhysicalVolume* volume2;
G4OpticalSurface * OpSurface = new G4OpticalSurface("name");
G4LogicalBorderSurface* Surface = new
 G4LogicalBorderSurface("name", volume1, volume2, OpSurface);
OpSurface->SetType (dielectric_dielectric);
OpSurface->SetModel(unified);
OpSurface->SetFinish(groundbackpainted);
OpSurface->SetSigmaAlpha(0.1);
std::vector<G4double> pp = \{2.038 \pm eV, 4.144 \pm eV\};
std::vector<G4double> specularlobe = {0.3, 0.3};
std::vector<G4double> specularspike = {0.2, 0.2};
std::vector<G4double> backscatter = {0.1, 0.1};
std::vector<G4double> rindex = {1.35, 1.40};
std::vector<G4double> reflectivity = {0.3, 0.5};
std::vector<G4double> efficiency = {0.8, 0.1};
G4MaterialPropertiesTable * SMPT = new G4MaterialPropertiesTable();
SMPT->AddProperty("RINDEX", pp, rindex);
SMPT->AddProperty("SPECULARLOBECONSTANT", pp, specularlobe);
SMPT->AddProperty("SPECULARSPIKECONSTANT", pp, specularspike);
SMPT->AddProperty("BACKSCATTERCONSTANT", pp, backscatter);
SMPT->AddProperty("REFLECTIVITY", pp, reflectivity);
SMPT->AddProperty("EFFICIENCY", pp, efficiency);
OpSurface->SetMaterialPropertiesTable(SMPT);
```

#### The Glisur model

The original GEANT3.21 implementation of this process is also available via the GLISUR methods flag, as shown in Listing 5.10. Note that there is considerable overlap of the Glisur and UNIFIED models in the code. The surface roughness is specified with the polish parameter.

Listing 5.10: Dielectric metal surface properties defined via the G4OpticalSurface.

```
G4LogicalVolume* volume_log;

G4OpticalSurface* OpSurface = new G4OpticalSurface("name");

G4LogicalSkinSurface* Surface = new
  G4LogicalSkinSurface("name", volume_log, OpSurface);

OpSurface->SetType(dielectric_metal);
OpSurface->SetFinish(ground);
OpSurface->SetFolish(ground);
OpSurface->SetPolish(0.8);
(continues on next page)
```

(continued from previous page)

```
G4MaterialPropertiesTable* OpSurfaceProperty = new G4MaterialPropertiesTable();

OpSurfaceProperty->AddProperty("REFLECTIVITY", pp, reflectivity);

OpSurfaceProperty->AddProperty("EFFICIENCY", pp, efficiency);

OpSurface->SetMaterialPropertiesTable(OpSurfaceProperty);
```

#### LBNL look-up tables (LUT)

Janecek and Moses [Janecek2010] built an instrument for measuring the angular reflectivity distribution inside of BGO crystals with common surface treatments and reflectors applied. These results have been incorporated into the GEANT4 code. A third class of reflection type besides dielectric\_metal and dielectric\_dielectric is added: dielectric\_LUT. The distributions have been converted to 21 look-up-tables (LUT); so far for 1 scintillator material (BGO) x 3 surface treatments x 7 reflector materials. The modified code allows the user to specify the surface treatment (rough-cut, chemically etched, or mechanically polished), the attached reflector (Lumirror, Teflon, ESR film, Tyvek, or TiO2 paint), and the bonding type (air-coupled or glued). The glue used is MeltMount, and the ESR film used is VM2000. Each LUT consists of measured angular distributions with 4° by 5° resolution in theta and phi, respectively, for incidence angles from 0° to 90°, in 1°-steps. The code might in the future be updated by adding more LUTs, for instance, for other scintillating materials (such as LSO or NaI). To use these LUT the user has to download them from Geant4 Software Download and set an environment variable, G4REALSURFACEDATA, to the directory of geant4/data/RealSurface2.2.

The enumeration G4OpticalSurfaceFinish includes:

```
polishedlumirrorair,
                                            // mechanically polished surface, with lumirror
polishedlumirrorglue, // mechanically polished surface, with lumirror & meltmount polishedteflonair, // mechanically polished surface, with tellon polishedticair // mechanically polished surface, with tio paint
polishedtioair,
                                           // mechanically polished surface, with tio paint
polishedtyvekair,
                                    // mechanically polished surface, with tyvek
// mechanically polished surface, with esr film
// mechanically polished surface, with esr film & meltmount
// chemically etched surface, with lumirror
// chemically etched surface, with lumirror & meltmount
// chemically etched surface, with teflon
                                            // mechanically polished surface, with tyvek
polishedvm2000air,
polishedvm2000glue,
etchedlumirrorair,
etchedlumirrorglue,
etchedteflonair,
etchedtioair,
                                            // chemically etched surface, with tio paint
                                          // chemically etched surface, with tyvek
etchedtyvekair,
                                       // chemically etched surface, with tyvek

// chemically etched surface, with esr film

// chemically etched surface, with esr film & meltmount

// rough-cut surface, with lumirror & meltmount
etchedvm2000air,
groundlumirrorair,
groundlumirrorglue,
groundteflonair,
groundtioair
                                            // rough-cut surface, with lumirror & meltmount
                                          // rough-cut surface, with teflon
                                           // rough-cut surface, with tio paint
groundtyvekair,
                                            // rough-cut surface, with tyvek
groundvm2000air.
                                             // rough-cut surface, with esr film
                                            // rough-cut surface, with esr film & meltmount
groundvm2000glue
```

To use an LBNL look-up-table, all the user needs to specify for an G4OpticalSurface is: SetType(dielectric\_LUT), SetModel(LUT) and for example, SetFinish(polishedtyvekair).

Note that the LBNL look-up tables were the first optical surface LUT implemented in GEANT4. Where the term "LUT" is used, it often refers to the LBNL LUT.

#### Davis look-up tables (LUTDAVIS)

Another model for optical surface interactions is called the LUT Davis model [RoncaliCherry2013], [Stockhoff2017], [Roncali2017]. The model is based on measured surface data and allows the user to choose from a list of available surface finishes. Provided are a rough and a polished L(Y)SO surface that can be used without reflector, or in combination with a specular reflector (e.g. ESR) or a Lambertian reflector (e.g. Teflon). The specular reflector can be coupled to the crystal with air or optical grease. Teflon tape is wrapped around the crystal with 4 layers.

	Table 5.8: Surface nam	nes of available LUTs.	
Dava	Toflon	CCD . Aim	

	Bare	Teflon	ESR + Air	ESR + Optical Grease
Rough	Rough_LUT	RoughTeflon_LUT	RoughESR_LUT	RoughESRGrease_LUT
Polished	Polished_LUT	PolishedTeflon_LUT	PolishedESR_LUT	PolishedESRGrease_LUT

In the LUT database, typical roughness parameters obtained from the measurements are provided to characterize the type of surface modelled:

ROUGH : 
$$R_a = 0.48 \mu \text{m}, \sigma = 0.57 \mu \text{m}, R_{pv} = 3.12 \mu \text{m}$$
  
POLISHED :  $R_a = 20.8 \text{ nm}, \sigma = 26.2 \text{ nm}, R_{pv} = 34.7 \text{ nm}$  (5.1)

with  $R_a$  = average roughness;  $\sigma$  = rms roughness,  $R_{pv}$  = peak-to-valley ratio.

The detector surface, called <code>Detector\_LUT</code>, defines a polished surface coupled to a photodetector with optical grease or a glass interface (similar index of refraction 1.5). To use <code>Detector\_LUT</code>, the surface property <code>EFFICIENCY</code> must be greater than 0. Any surface can be used as a detector surface when the <code>EFFICIENCY</code> is set to 1.

To enable the LUT Davis Model, the user needs to specify for a G4OpticalSurface: SetType(dielectric\_LUTDAVIS), SetModel(DAVIS) and also, for example, SetFinish(Rough\_LUT). The user also has to download data files from Geant4 Software Download and set an environment variable, G4REALSURFACEDATA, to the directory of geant4/data/RealSurface2.2.

#### Background

The crystal topography is obtained with atomic force microscopy (AFM). From the AFM data, the probability of reflection (1) and the reflection directions (2) are computationally determined, for incidence angles ranging from 0° to 90°. Each LUT is computed for a given surface and reflector configuration. The reflection probability in the LUT combines two cases: directly reflected photons from the crystal surface and photons that are transmitted to the reflector surface and later re-enter the crystal. The key operations of the reflection process are the following: The angle between the incident photon (Old Momentum) and the surface normal are calculated. The probability of reflection is extracted from the first LUT. A Bernoulli test determines whether the photon is reflected or transmitted. In case of reflection two angles are drawn from the reflection direction LUT.

#### Complex index of refraction

The reflectivity off a metal surface can also be calculated by way of a complex index of refraction. Instead of storing the REFLECTIVITY directly, the user stores the real part (REALRINDEX) and the imaginary part (IMAGINARYRINDEX) as a function of photon energy separately in the G4MaterialPropertyTable. GEANT4 then calculates the reflectivity depending on the incident angle, photon energy, degree of TE and TM polarization, and this complex refractive index.

If it is desired that photons are not absorbed at the surface, but instead are transmitted into the material, the user can set the transmittance (TRANSMITTANCE) to 1. If this setting is used together with a ground finish and a non-zero value of sigma\_alpha, some photons are still absorbed at the surface. If the absorption at the surface should be completely prevented, sigma\_alpha must be zero or a polished finish needs to be used. Additionally, the absorption length (ABSLENGTH) should be defined for the material, otherwise the material would be fully transparent. Note




Fig. 5.2: Old Momentum to New Momentum. The old momentum is the unit vector that describes the incident photon. The reflected/transmitted photon is the New Momentum described by two angles  $\phi$  and  $\theta$ .

that Geant4 does not calculate the absorption length, which is a material property, from the imaginary part of the refractive index, which is a surface property. The user needs to provide both properties individually. The macro complexRindex.mac (below) in the example OpNovice2 demonstrates the usage of the complex refractive index.

Listing 5.11: A macro for use with OpNovice2 demonstrating the usage of the complex index of refraction.

```
/control/verbose 2
/tracking/verbose 0
/run/verbose 0
/process/optical/verbose 1
/control/cout/ignoreThreadsExcept 0
/opnovice2/worldMaterial G4_Al
/opnovice2/worldProperty GROUPVEL 0.000002 299.792
                                                       0.000008 299.792
                                                       0.000004 0.28
                                                                            0.000006 0.13
/opnovice2/worldProperty RINDEX 0.000002 1.38
→ 0.000008 0.077
/opnovice2/worldProperty ABSLENGTH 0.000002 6.75e-9
                                                       0.000004 6.65e-9
                                                                            0.000006 6.96e-9
→ 0.000008 7.45e-9
/opnovice2/boxMaterial G4_AIR
                                                 0.000008 1.01
/opnovice2/boxProperty RINDEX 0.000002 1.01
/opnovice2/boxProperty ABSLENGTH 0.000002 1000000 0.000005 2000000 0.000008 3000000
/opnovice2/surfaceModel unified
/opnovice2/surfaceType dielectric_metal
/opnovice2/surfaceFinish polished
/opnovice2/surfaceSigmaAlpha 0 # only relevant for ground finish
/opnovice2/surfaceProperty REALRINDEX
                                               0.000002 1.38
                                                                 0.000004 0.28
                                                                                   0.000006 0.
        0.000008 0.077
/opnovice2/surfaceProperty IMAGINARYRINDEX
                                               0.000002 7.31
                                                                 0.000004 3.71
                                                                                   0.000006 2.
      0.000008 1.71
                                                                 0.000006 1
/opnovice2/surfaceProperty TRANSMITTANCE
                                                                 0.000006 1 # only relevant for_
/opnovice2/surfaceProperty SPECULARLOBECONSTANT 0.000002 1
→ground finish
/run/initialize
/gun/particle opticalphoton
/gun/energy 4 eV
```

(continues on next page)

(continued from previous page)

```
/gun/position 90 0 0 cm
/gun/direction 1 0 0
/opnovice2/gun/optPhotonPolar 0. deg
/opnovice2/gun/randomDirection true

/analysis/setFileName complexRindex_0
/analysis/h1/set 20 90 0 90 # deg
/analysis/h1/set 21 90 0 90 # deg
/run/printProgress 100000

/analysis/setFileName complexRindex_90
/opnovice2/gun/optPhotonPolar 90. deg
/run/beamOn 500000
```

### **Dichroic filter**

A dielectric-dichroic boundary may be specified by supplying a dichroic vector to the optical surface.

### Configuration

Table 5.9: Material and surface properties for the optical boundary scattering process.

Name	Туре	Mate-	Description	Unit
		rial or		cate-
		surface		gory
BACKSCAT-	Energy-	Surface	Unified model	Unit-
TERCON-	dependent			less
STANT				
EFFICIENCY	Energy-	Surface	Chance of an absorbed photon to be detected	Unit-
	dependent			less
GROUPVEL	Energy-	Material	If specified, set the photon velocity to this value on entering	Unit-
	dependent		the material, if undergoing Fresnel refraction or transmis-	less
			sion	
IMAGI-	Energy-	Either	Imaginary part of complex refractive index	Unit-
NARYRINDEX	dependent			less
REFLECTIV-	Energy-	Surface	1 minus the absorption coefficient	Unit-
ITY	dependent			less
REALRINDEX	Energy-	Either	Real part of complex refractive index	Unit-
	dependent			less
RINDEX	Energy-	Either	Refractive index	Unit-
	dependent			less
SPECULAR-	Energy-	Surface	Unified model	Unit-
LOBECON-	dependent			less
STANT				
SPECULAR-	Energy-	Surface	Unified model	Unit-
SPIKECON-	dependent			less
STANT				
SURFACER-	Constant	Surface	Parameter to express surface roughness for dielec-	Unit-
OUGHNESS			tric_dielectric surfaces, leading to Lambertian scattering	less
TRANSMIT-	Energy-	Surface	For dielectric_dielectric surfaces	Unit-
TANCE	dependent			less

These G4OpticalParameters commands can be used to configure the process.

- Set the verbosity of the boundary scattering process. 0 = silent; 1 = initialisation; 2 = during tracking.
  - macro command: /process/optical/boundary/verbose 1
  - C++ statement: G4OpticalParameters::Instance()->SetBoundaryVerboseLevel(G4int verboseLevel);
  - default value: 0
- Call the sensitive detector automatically.
  - macro command: /process/optical/boundary/setInvokeSD
  - C++ statement: G4OpticalParameters::Instance()->SetBoundaryInvokeSD(G4bool val)
  - default value: false

#### 5.2.7 Parameterisation

In this section we describe how to use the parameterisation or "fast simulation" facilities of GEANT4. Examples are provided in the **examples/extended/parameterisations** directory.

#### **Generalities:**

The GEANT4 parameterisation facilities allow you to shortcut the detailed simulation in a given volume and for given particle types in order for you to provide your own implementation of the physics and of the detector response. This allows to make an alternative modelling of the physics processes, usually approximate and faster than the detailed simulation.

Overtaking the detailed GEANT4 simulation (tracking) requires the user to specify 3 main components of the parameterisation:

- 1. Where the particles are parameterised;
- 2. Which particles are parameterised:
  - static conditions (particle type, PDG, charge, ...)
  - dynamic conditions (energy, direction, ...)
- 3. What happens instead of the detailed simulation:
  - where the particle is moved
  - what are the created secondaries
  - is the primary particle killed
  - what (and where) energy is deposited

Note: It is user responsibility to invoke Hit method of the sensitive detector

#### 1. Where

Parameterisations are bound to a G4Region object, which, in the case of fast simulation can be called an **envelope**. A G4Region has a G4LogicalVolume object (or a series of G4LogicalVolume objects) as a root, and the G4Region is attached to this volume and all its ancestors:

```
G4Region(const G4String&) // constructor also registers to G4RegionStore void G4Region::AddRootLogicalVolume (G4LogicalVolume*) // attach root volume to region
```

Envelopes often correspond to the outer volumes of (sub-)detectors: electromagnetic calorimeters, tracking chambers, etc.

With GEANT4 it is also possible to define envelopes by overlaying a parallel ("ghost") geometry as discussed in *Parameterisation Using Ghost/Parallel Geometries*.

#### 2. Which particles

Parameterisation is usually specified only for certain particles. Those particles must have attached G4FastSimulationManagerProcess to their list of processes. For users of modular physics lists (G4VModularPhysicsList) — from which reference physics lists (FTFP\_BERT, QGSP\_BIC,...) are derived — it is enough to use the helper class G4FastSimulationPhysics and activate the parameterisation for each particle type:

GEANT4 will take into account the parameterisation process at tracking for any step that starts in any root G4LogicalVolume of the G4Region that has been declared as an envelope. It will proceed by first asking the available parameterisation models for that particle (models with static conditions fulfilled by that particle). Existing models will be checked (in the order they were added) if one of them (and only one) wants to issue a trigger (meaning the dynamic conditions are met). If yes, it will invoke its parameterisation. In this case, the tracking and physics (detailed simulation) will not apply be applied to the particle in the step. In case no trigger is issued, the simulation continues as usual, with other processes being taken into account.

Parameterisations resembles a "user stepping action" but are more advanced because:

- parameterisation code is considered only in the G4Region to which it is bound;
- parameterisation code is considered anywhere in the G4Region, that is, any volume in which the track is located (mother, daughter, sub-daughter, ...);
- GEANT4 will provide information to your parameterisation code about the current root volume of the G4Region in which the track is travelling.

### 3. What happens

Implementation of the parameterisation must be made deriving from the G4VFastSimulationModel abstract class. Models are attached to the G4Region and will be considered only if particle meets the selection criteria and is within the geometrical hierarchy tree of the root logical volume of the G4Region. The G4Region is specified in the model constructor, together with the model name:

```
// constructor adds this model to G4FastSimulationManager of given envelope G4VFastSimulationModel(const G4String&, G4Region*)
```

Selection criteria are to be defined in G4VFastSimulationModel implementation:

```
// specify the static conditions (particle type, PDG, charge, ...)
virtual G4bool G4VFastSimulationModel::IsApplicable (const G4ParticleDefinition&) = 0
// specify the dynamic conditions (momentum, direction, position, distance to boundary, ...)
virtual G4bool G4VFastSimulationModel::ModelTrigger (const G4FastTrack&) = 0
```

As particle is not transported by GEANT4, it is therefore responsibility of the model to describe what happens to the particle in place of the standard simulation: where the particle goes to (or to kill it), how its momentum is changed, what is the deposited energy (user needs to register manually all deposits in the sensitive detector or use helper class G4FastSimHitMaker), and what secondary particles are created. Those details should be implemented within:

```
// input information: G4FastTrack
// output information: G4FastStep
virtual G4bool G4VFastSimulationModel::DoIt(const G4FastTrack&, G4FastStep&) = 0
```

GEANT4 contains an implementation of the Gflash parameterisation model (see more in *Gflash Parameterisation*) and several examples in extended/parameterisations directory.

#### **Overview of Parameterisation Components**

The GEANT4 components which allow the implementation and control of parameterisations are:

- **G4VFastSimulationModel** This is the abstract class for the implementation of parameterisations. You must inherit from it to implement your concrete parameterisation model.
- **G4Region** As mentioned before, an envelope of parameterisation in GEANT4 is a G4Region. The parameterisation is bound to the G4Region by setting a G4FastSimulationManager pointer to it.
  - Fig. 5.3 shows how the G4VFastSimulationModel and G4FastSimulationManager objects are bound to the G4Region. Then for all root G4LogicalVolume's held by the G4Region, the fast simulation code is active.




Fig. 5.3: G4VFastSimulationModel and G4FastSimulationManager objects.

- **G4FastSimulationManager** The G4VFastSimulationModel objects are attached to the G4Region through a G4FastSimulationManager. This object will manage the list of models and will message them at tracking time.
- **G4FastSimulationManagerProcess** This is an implementation of G4VProcess. It invokes the parameterisation models if trigger conditions are met (particle is within an envelope, of certain type, etc.). It must be set in the process list of the particles you want to parameterise (e.g. using physics constructor G4FastSimulationPhysics on top of any modular physics list since 10.3 release). If added manually, one must remember that in presence of the parallel world, the ordering of processes matters.
- **G4GlobalFastSimulationManager** This a singleton class which provides the management of the G4FastSimulationManager objects and some ghost facilities.
- G4FastSimHitMaker This is a helper class that can be employed in the fast simulation models. It allows to deposit energy at given position (G4FastHit), provided it is located within the sensitive detector that derives from G4VFastSimSensitiveDetector base class. An extended example extended/parameterisations/Par03 demonstrates how to use G4FastSimHitMaker to create multiple deposits from the fast simulation model. Such model should create energy deposits, and for each one call the method G4FastSimHitMaker::make(const G4FastHit& aHit, const G4FastTrack& aTrack) so that sensitive detector can be located, and hits stored in hit collection, as implemented in the sensitive detector class user implementation.
- **G4VFastSimSensitiveDetector** This is a base class for a sensitive detector that allows to easily store hits created in the fast simulation models. It must me used in addition to inheritance from the usual base class *G4VSensitiveDetector* for processing of energy deposited in G4Step. ProcessHits(...) method must be implemented and describe how hits should be saved in the hit collections. It is invoked by Hit method

which is public and can be called directly in the fast simulation model (if sensitive detector is known to the model), or via the helper class G4FastSimHitMaker that will locate appropriate volume and retrieve its sensitive detector. An extended example extended/parameterisations/Par03 demonstrates how to use G4VFastSimSensitiveDetector to deposit energy from fast simulation and compare it to the detailed simulation.

#### The G4VFastSimulationModel Abstract Class

#### **Constructors**

The G4VFastSimulationModel class has two constructors.

- G4VFastSimulationModel(const G4String& aName): Here aName identifies the parameterisation model
- G4VFastSimulationModel (const G4String& aName, G4Region\*, G4bool IsUnique=false):
  In addition to the model name, this constructor accepts a G4Region pointer. The needed G4FastSimulationManager object is constructed if necessary, passing to it the G4Region pointer and the Boolean value. If it already exists, the model is simply added to this manager. Note that the G4VFastSimulationModel object will not keep track of the G4Region passed in the constructor. The Boolean argument is there for optimisation purposes: if you know that the G4Region has a unique root G4LogicalVolume, uniquely placed, you can set the Boolean value to true.

#### Virtual methods

The G4VFastSimulationModel has pure virtual methods which must be overridden in your concrete class:

- **G4VFastSimulationModel(const G4String& aName):** Here aName identifies the parameterisation model.
- G4bool ModelTrigger (const G4FastTrack&): You must return true when the dynamic conditions to trigger your parameterisation are fulfilled. G4FastTrack provides access to the current G4Track, gives simple access to the current root G4LogicalVolume related features (its G4VSolid, and G4AffineTransform references between the global and the root G4LogicalVolume local coordinates systems) and simple access to the position and momentum expressed in the root G4LogicalVolume coordinate system. Using these quantities and the G4VSolid methods, you can for example easily check how far you are from the root G4LogicalVolume boundary, or if the particle is entering or escaping the volume.
- G4bool IsApplicable (const G4ParticleDefinition&): In your implementation, you must return true when your model is applicable to the G4ParticleDefinition passed to this method. The G4ParticleDefinition provides all intrinsic particle information (mass, charge, spin, name...). If you want to implement a model which is valid only for certain particle types, it is recommended for efficiency that you use the static pointer of the corresponding particle classes.

As an example, in a model valid for gammas only, the IsApplicable () method should take the form:

```
#include "G4Gamma.hh"

G4bool MyGammaModel::IsApplicable(const G4ParticleDefinition& partDef)
{
   return &partDef == G4Gamma::GammaDefinition();
}
```

void DoIt (const G4FastTrack&, G4FastStep&): The details of your parameterisation will be implemented in this method. The G4FastTrack reference provides the input information, and the final state of the particles after parameterisation must be returned through the G4FastStep reference (what is the changed energy and position, what are the secondaries, which particles are killed). Tracking for the final state secondary particles is requested after your parameterisation has been invoked.

#### The G4FastSimulationManager Class

G4FastSimulationManager functionalities regarding the use of ghost volumes are explained in *Parameterisation Using Ghost/Parallel Geometries*.

#### Constructor

G4FastSimulationManager (G4Region \*anEnvelope, G4bool IsUnique=false): This is the only constructor. You specify the G4Region by providing its pointer. The G4FastSimulationManager object will bind itself to this G4Region. If you know that this G4Region has a single root G4LogicalVolume, placed only once, you can set the IsUnique boolean to true to allow some optimisation.

Note that if you choose to use the G4VFastSimulationModel(const G4String&, G4Region\*, G4bool) constructor for your model, the G4FastSimulationManager will be constructed using the given G4Region\* and G4bool values of the model constructor.

#### Management of parameterisation models

The following two methods provide the usual management functions.

- void AddFastSimulationModel( G4VFastSimulationModel\*)
- void RemoveFastSimulationModel( G4VFastSimulationModel\*)

#### Messenger

To ease the communication with G4FastSimulationManager a messenger class was introduced. List of available commands:

### The G4FastSimulationManagerProcess Class

This G4VProcess serves as an interface between the tracking and the parameterisation. You usually don't need to set it up directly, as you can conveniently rely on the helper tool G4FastSimulationPhysics (see Section 2. Which particles) for this. At tracking (stepping) time, it collaborates with the G4FastSimulationManager of the current volume, if any, to allow the models to trigger. If no manager exists or if no model issues a trigger, the tracking goes on normally.

#### Parallel/Ghost Geometry

In order to register G4FastSimulationManagerProcess operating on the regions from the parallel geometry, it must be constructed passing the world name. Otherwise, the mass geometry is used (and its navigator).

Moreover, G4FastSimulationManagerProcess must be registered to G4ProcessManager as continuous and discrete process, as it provides navigation in the ghost world to limit the step on ghost boundaries. Hence it is important to maintain the ordering of the along-step execution:

```
[n-3] ...
[n-2] Multiple Scattering
[n-1] G4FastSimulationManagerProcess
[ n ] G4Transportation
```

Since 10.3 release it is convenient to use G4FastSimulationPhysics on top of a modular physics list. To use fast simulation in the parallel geometry (register G4FastSimulationManagerProcess) one can do (from ParO1 example):

```
// -- PhysicsList and fast simulation activation:
// -- Create a physics list (note : FTFP BERT is a G4VModularPhysicsList
// -- which allows to use the subsequent G4FastSimulationPhysics tool to
// -- activate the fast simulation):
FTFP_BERT* physicsList = new FTFP_BERT;
// -- Create helper tool, used to activate the fast simulation:
G4FastSimulationPhysics + fastSimulationPhysics = new G4FastSimulationPhysics();
fastSimulationPhysics->BeVerbose();
   -- activation of fast simulation for particles having fast simulation models
// -- attached in the mass geometry:
fastSimulationPhysics->ActivateFastSimulation("e-");
fastSimulationPhysics->ActivateFastSimulation("e+");
fastSimulationPhysics->ActivateFastSimulation("gamma");
// -- activation of fast simulation for particles having fast simulation models
// -- attached in the parallel geometry:
fastSimulationPhysics->ActivateFastSimulation("pi+", "pionGhostWorld");
fastSimulationPhysics->ActivateFastSimulation("pi-", "pionGhostWorld");
// -- Attach the fast simulation physics constructor to the physics list:
physicsList->RegisterPhysics( fastSimulationPhysics );
// -- Finally passes the physics list to the run manager:
runManager->SetUserInitialization(physicsList);
```

If you wish to register manually G4FastSimulationManagerProcess to all the particles as a discrete and continuous process:

```
void MyPhysicsList::addParameterisation()
{
    G4FastSimulationManagerProcess*
        theFastSimulationManagerProcess = new G4FastSimulationManagerProcess();
    theParticleIterator->reset();
    while( (*theParticleIterator)() )
    {
        G4ParticleDefinition* particle = theParticleIterator->value();
        G4ProcessManager* pmanager = particle->GetProcessManager();
        pmanager->AddProcess(theFastSimulationManagerProcess, -1, 0, 0);
    }
}
```

#### The G4GlobalFastSimulationManager Singleton Class

This class is a singleton which can be accessed as follows:

```
#include "G4GlobalFastSimulationManager.hh"
...
G4GlobalFastSimulationManager* globalFSM;
globalFSM = G4GlobalFastSimulationManager::getGlobalFastSimulationManager();
...
...
```

Presently, you will mainly need to use the G4GlobalFastSimulationManager if you use ghost geometries.

#### Parameterisation Using Ghost/Parallel Geometries

In some cases, volumes of the tracking geometry do not allow envelopes to be defined. This may be the case with a geometry coming from a CAD system. Since such a geometry is flat, a parallel geometry must be used to define the envelopes.

Another interesting case involves defining an envelope which groups the electromagnetic and hadronic calorimeters of a detector into one volume. This may be useful when parameterising the interaction of charged pions. You will very likely not want electrons to see this envelope, which means that ghost geometries have to be organised by particle flavours.

Using ghost geometries implies some more overhead in the parameterisation mechanism for the particles sensitive to ghosts, since navigation is provided in the ghost geometry by the G4FastSimulationManagerProcess. Usually, however, only a few volumes will be placed in this ghost world, so that the geometry computations will remain rather cheap.

For details on how to use fast simulation with the parallel/world geometry please consult *The G4FastSimulationManagerProcess Class*.

#### **Gflash Parameterisation**

This section describes how to use the Gflash parameterisation. Gflash is a concrete implementation based on the equations and parameters of the original Gflash package from H1(hep-ex/0001020, Grindhammer & Peters, see physics manual) and uses the fast simulation facilities of GEANT4 described above. Briefly, whenever a e-/e+ particle enters the calorimeter, it is parameterised if it has a minimum energy and the shower is expected to be contained in the calorimeter (or 'parameterisation envelope'). If this is fulfilled the particle is killed, no secondaries are created, and instead the energy is deposited according to the Gflash equations. Examples, provided in examples/extended/parametrisation/gflash/, show how to interface Gflash to your application. The simulation time is measured, so the user can immediately see the speed increase resulting from the use of Gflash.

#### **Using the Gflash Parameterisation**

To use Gflash 'out of the box' the following steps are necessary:

• The user must add the fast simulation process:

```
G4VModularPhysicsList* physicsList = new FTFP_BERT();
G4FastSimulationPhysics* fastSimulationPhysics = new G4FastSimulationPhysics();
fastSimulationPhysics->ActivateFastSimulation("e-");
physicsList->RegisterPhysics( fastSimulationPhysics );
```

• The envelope in which the parameterisation should be performed must be created and specified (below: G4Region\* fRegion) and the GFlashShowerModel must be assigned to this region. Furthermore, the classes GFlashParticleBounds (which provides thresholds for the parameterisation like minimal energy etc.), GflashHitMaker (a helper class to generate hits in the sensitive detector) and GFlashHomoShowerParameterisation (which does the computations) must be constructed and attached to the GFlashShowerModel:

```
G4Material* pbW04 = nistManager->FindOrBuildMaterial("G4_pbW04");
fFastShowerModel = new GFlashShowerModel("fFastShowerModel", fRegion);
fParameterisation = new GFlashHomoShowerParameterisation(pbW04);
fFastShowerModel->SetParameterisation(*fParameterisation);
fParticleBounds = new GFlashParticleBounds();
fFastShowerModel->SetParticleBounds(*fParticleBounds);
fHitMaker = new GFlashHitMaker();
fFastShowerModel->SetHitMaker(*fHitMaker);
```

The user must set the material of the calorimeter, since the computation depends on the material.

• It is mandatory to use G4VGFlashSensitiveDetector as (additional) base class for the sensitive detector:

Here it is necessary to implement a separate interface, where the Gflash spots are processed:

```
virtual G4bool ProcessHits(G4GFlashSpot*aSpot,G4TouchableHistory*);
```

A separate interface is used, because the Gflash spots naturally contain less information than the full simulation.

Since the parameters in the Gflash package are taken from fits to full simulations with Geant3, with limited number of materials, and on specific range of electron energy, some re-tuning might be necessary for good agreement with GEANT4 showers. Such parameterisation may be moreover made independent on material (currently atomic number Z) reducing the number of parameters. The tuning procedure is described in hep-ex/0001020 and there is on-going work to automate that procedure and make available in GEANT4. For the moment, the only way to alter the parameters is to provide an implementation of **GVFlashHomoShowerTuning** class and pass it to the class that calculates the showers profiles, etc.:

```
 \textit{GFlashHomoShowerParameterisation} \ (\textit{G4Material} \ * \ \textit{aMat}, \ \textit{GVFlashHomoShowerTuning} \ * \ \textit{aPar} \ = \ \textit{0}) \ ;
```

For information, there is also a preliminary (still not validated) implementation of a parameterisation for sampling calorimeters. The user must specify the active and passive material, as well as the thickness of the active and passive layer. The sampling structure of the calorimeter is taken into account by using an "effective medium" to compute the shower shape.

All material properties needed are calculated automatically. If tuning is required, the user can pass his own parameter set in the class **GFlashSamplingShowerTuning**. Here the user can also set his calorimeter resolution.

All in all the constructor looks the following:

```
GFlashSamplingShowerParamterisation(G4Material * Mat1, G4Material * Mat2,G4double d1,G4double d2,GVFlashSamplingShowerTuning * aPar = 0);
```

### **5.2.8 Transportation Process**

A Transportation process is required for every particle which is tracked in a simulation. The GEANT4 transportation processes are responsible for several key functions for tracking:

- polling the Geometry Modeller via G4Navigator to obtain the distance to the next boundary for uncharged particles or charged particles in a volume / region without an electromagnetic field;
- handing off the tracking of charged particles in an EM field to G4PropagatorInField which finds either the endpoint of integration of the equations of motion of the particle or the state of the particle at the location in which it intersects with the next volume boundary;
- updating the time of flight of the particle, using the full step length (not the geometrical step length, which is reduced by multiple scattering.)
- killing tracks which are found to loop inside a (magnetic) field, without making adequate progress after O(thousand) integration steps. A description of this is provided below.

Transportation comes in two flavours:

- the 'standard' G4Transportation process, used for most applications, and
- the G4CoupledTransportation process, which is activated when multiple geometries are active.

Multiple geometries can be created in order to cope with different use cases:

- when a mass overlay geometry is used to overlap a set of 'top' volume onto a complex existing geometry,
- when the GEANT4 scoring and/or biasing capabilities are activated.

The registration of the relevant Transportation process is handled by the G4PhysicsListHelper, which chooses the correct type depending on whether any of the features which require parallel geometries have been used.

In brief there is one main difference between G4Transportation and G4CoupledTransportation. The G4Transportation process uses the G4Navigator of the Geant4 Geometry Modeller to obtain the distance to the next boundary along a straight line (for a neutral particle, or a charged particle in zero field). The G4CoupledTransportation process uses the G4PathFinder class to obtain the shortest length to a boundary amongst the geometries registered for the current particle - in effect multiplexing the different geometries.

In addition the transportation processes estimates the time of flight for the current step. For a neutral particle or a charged particle inside a pure magnetic field, this is estimated from the initial and final velocity of the particle. This taking into account roughly the effect of energy loss from ionisation. Since the full path length is used (rather than the geometrical one) the path lengthening due to multiple scattering is also taken into account.

For a charged particle in an EM field with a non-zero electric component, or a gravity field, the time of flight is calculated taking into account the change in velocity.

For the propagation in an external field, electromagnetic or other, the Transportation processes rely on the capabilities of G4PropagatorInField and the integration methods detailed in the subsection ElectroMagnetic Field

Note that the integration currently is done without taking into account either energy loss along the trajectory of motion or multiple scattering, which is applied independently at the endpoint (if it is not on a boundary.)

Further details about the caveats and control of transportation within a magnetic field are given in the Appendix: *Transportation in Magnetic Field - Further Details*.

### 5.3 Particles

### 5.3.1 Basic concepts

There are three levels of classes to describe particles in GEANT4.

G4ParticleDefinition defines a particle
G4DynamicParticle describes a particle interacting with materials
G4Track describes a particle traveling in space and time

G4ParticleDefinition aggregates information to characterize a particle's properties, such as name, mass, spin, life time, and decay modes. G4DynamicParticle aggregates information to describe the dynamics of particles, such as energy, momentum, polarization, and proper time, as well as "particle definition" information. G4Track (see *Tracking*) includes all information necessary for tracking in a detector simulation, such as time, position, and step, as well as "dynamic particle" information.

### 5.3.2 Definition of a particle

There are a large number of elementary particles and nuclei. GEANT4 provides the G4ParticleDefinition class to represent particles, and various particles, such as the electron, proton, and gamma have their own classes derived from G4ParticleDefinition.

We do not need to make a class in GEANT4 for every kind of particle in the world. There are more than 100 types of particles defined in GEANT4 by default. Which particles should be included, and how to implement them, is determined according to the following criteria. (Of course, the user can define any particles he wants. Please see the User's Guide: For ToolKit Developers).

#### **Particle List in GEANT4**

This list includes all particles in GEANT4 and you can see properties of particles such as

- · PDG encoding
- · mass and width
- electric charge
- · spin, isospin and parity
- magnetic moment
- · quark contents
- · life time and decay modes

Here is a list of particles in GEANT4. This list is generated automatically by using GEANT4 functionality, so listed values are same as those in your GEANT4 application (as far as you do not change source codes).

#### Categories

- gluon / quarks / di-quarks
- leptons
- · mesons
- baryons
- ions
- others

#### Classification of particles

1. elementary particles which should be tracked in GEANT4 volumes

All particles that can fly a finite length and interact with materials in detectors are included in this category. In addition, some particles with a very short lifetime are included for user's convenience.

1. stable particles

Stable means that the particle can not decay, or has a very small possibility to decay in detectors, e.g., gamma, electron, proton, and neutron.

2. **long life** (>10<sup>-14</sup>sec) particles

Particles which may travel a finite length, e.g., muon, charged pions.

3. **short life** particles that decay immediately in GEANT4

For example, pi<sup>0</sup>, eta

4. K<sup>0</sup> system

 $K^0$  "decays" immediately into  $K^0_S$  or  $K^0_L$ , and then  $K^0_S/K^0_L$  decays according to its life time and decay modes.

#### 5. optical photon

Gamma and optical photon are distinguished in the simulation view, though both are the same particle (photons with different energies). For example, optical photon is used for Cerenkov light and scintillation light.

### 6. geantino/charged geantino

Geantino and charged geantino are virtual particles for simulation which do not interact with materials and undertake transportation processes only.

#### 2. nuclei

Any kinds of nucleus can be used in GEANT4, such as alpha(He-4), uranium-238 and excited states of carbon-14. In addition, GEANT4 provides hyper-nuclei. Nuclei in GEANT4 are divided into two groups from the viewpoint of implementation.

### 1. light nuclei

Light nuclei frequently used in simulation, e.g., alpha, deuteron, He3, triton.

2. **heavy nuclei** (including hyper-nuclei)

Nuclei other than those defined in the previous category.

3. light anti-nuclei

5.3. Particles 271

Light anti-nuclei, for example, anti-alpha.

#### 4. light hyper-nuclei

Light hyper-nuclei and anti-hyper-nuclei, for example hyper-alpha and anti-hyper-alpha

Note that G4ParticleDefinition represents nucleus state and G4DynamicParticle represents atomic state with some nucleus. Both alpha particle with charge of +2e and helium atom with no charge aggregates the same "particle definition" of G4Alpha, but different G4DynamicParticle objects should be assigned to them. (Details can be found below)

#### 3. short-lived particles

Particles with very short life time decay immediately and are never tracked in the detector geometry. These particles are usually used only inside physics processes to implement some models of interactions. G4VShortLivedParticle is provided as the base class for these particles. All classes related to particles in this category can be found in shortlived sub-directory under the particles directory.

- 1. quarks/di-quarks: For example, all 6 quarks.
- 2. gluon
- 3. baryon excited states with very short life: For example, spin 3/2 baryons and anti-baryons
- 4. meson excited states with very short life: For example, spin 1 vector bosons

#### Implementation of particles

Single object created in the initialization: Categories a, b-1

These particles are frequently used for tracking in GEANT4. An individual class is defined for each particle in these categories. The object in each class is unique. The user can get pointers to these objects by using static methods in their own classes. The unique object for each class is created when its static method is called in the "initialization phase:.

On-the-fly creation: Category b-2

Ions will travel in a detector geometry and should be tracked, however, the number of ions which may be used for hadronic processes is so huge that ions are dynamically created by requests from processes (and users). Each ion corresponds to one object of the G4Ions class. G4IonTable class is a dictionary for ions. G4IonTable::GetIon() method to create ions on the fly. (G4IonTable::FIndIon() method returns pointer to the specified ion. If the ion does not exists, it returns zero without creating any ion.

G4NucleiPropertiesTableAME03 contains a table of measured mass values of about 3100 stable nuclei (ground states). G4NucleiPropertiesTheoreticalTable theoretical mass values of about 8000 nuclei (ground states). G4IsotopeTable describes properties of ions (exited energy, decay modes, life time and magnetic moments), which are used to create ions. G4NuclideTable is provided as a list of nuclei in GEANT4. It contains about 2900 ground states and 4000 excited states. Users can register his/her G4IsotopeTable to the G4IonTable.

Processes attached to heavy ions are same as those for G4GenericIon class. In other words, you need to create G4GenericIon and attach processes to it if you want to use heavy ions.

G4ParticleGun can shoot any heavy ions with /gun/ions command after ion is selected by /gun/particle command.

Dynamic creation by processes: Category c

Particle types in this category are are not created by default, but will only be created by request from processes or directly by users. Each shortlived particle corresponds to one object of a class derived from G4VshortLivedParticle, and it will be created dynamically during the initialization phase.

#### **G4ParticleDefinition**

The G4ParticleDefinition class has "read-only" properties to characterize individual particles, such as name, mass, charge, spin, and so on. These properties are set during initialization of each particle. Methods to get these properties are listed in Table 5.10.

G4String GetParticleName() particle name G4double GetPDGMass() mass G4double GetPDGWidth() decay width G4double GetPDGCharge() electric charge G4double GetPDGSpin() spin G4double GetPDGMagneticMoment() magnetic moment (0: not defined or no magnetic moment) G4int GetPDGiParity() parity (0:not defined) charge conjugation (0:not defined) G4int GetPDGiConjugation() G4double GetPDGIsospin() iso-spin 3<sup>rd</sup>-component of iso-spin G4double GetPDGIsospin3() G-parity (0:not defined) G4int GetPDGiGParity() G4String GetParticleType() particle type particle sub-type G4String GetParticleSubType() G4int GetLeptonNumber() lepton number G4int GetBaryonNumber() baryon number particle encoding number by PDG G4int GetPDGEncoding() encoding for anti-particle of this particle G4int GetAntiPDGEncoding()

Table 5.10: Methods to get particle properties.

Table 5.11 shows the methods of G4ParticleDefinition for getting information about decay modes and the life time of the particle.

Table 5.11: Methods to get particle decay modes and life time.

G4bool GetPDGStable()	stable flag
G4double GetPDGLifeTime()	life time
G4DecayTable* GetDecayTable()	decay table

Users can modify these properties, though the other properties listed above can not be change without rebuilding the libraries.

Each particle has its own G4ProcessManger object that manages a list of processes applicable to the particle.(see *Managing Processes*)

### 5.3.3 Dynamic particle

The G4DynamicParticle class has kinematics information for the particle and is used for describing the dynamics of physics processes. The properties in G4DynamicParticle are listed in the Table 5.12.

5.3. Particles 273

G4double theDynamicalMass	dynamical mass
G4ThreeVector theMomentumDirection	normalized momentum vector
G4ParticleDefinition*	definition of particle
theParticleDefinition	
G4double theDynamicalSpin	dynamical spin (i.e. total angular momentum as a ion/atom)
G4ThreeVector thePolarization	polarization vector
G4double theMagneticMoment	dynamical magnetic moment (i.e. total magnetic moment
	as a ion/atom )
G4double theKineticEnergy	kinetic energy
G4double theProperTime	proper time
G4double theDynamicalCharge	dynamical electric charge (i.e. total electric charge as a
	ion/atom )
G4ElectronOccupancy*	electron orbits for ions
theElectronOccupancy	

Table 5.12: Methods to set/get values.

Here, the dynamical mass is defined as the mass for the dynamic particle. For most cases, it is same as the mass defined in G4ParticleDefinition class (i.e. mass value given by GetPDGMass() method). However, there are two exceptions.

- · resonance particle
- ions

Resonance particles have large mass width and the total energy of decay products at the center of mass system can be different event by event.

As for ions, G4ParticleDefintion defines a nucleus and G4DynamicParticle defines an atom. G4ElectronOccupancy describes state of orbital electrons. So, the dynamic mass can be different from the PDG mass by the mass of electrons (and their binding energy). In addition, the dynamical charge, spin and magnetic moment are those of the atom/ion (i.e. including nucleus and orbit electrons).

Decay products of heavy flavor particles are given in many event generators. In such cases, G4VPrimaryGenerator sets this information in \*thePreAssignedDecayProducts. In addition, decay time of the particle can be set arbitrarily time by using PreAssignedDecayProperTime.

# **5.4 Production Threshold versus Tracking Cut**

### 5.4.1 General considerations

We have to fulfill two contradictory requirements. It is the responsibility of each individual **process** to produce secondary particles according to its own capabilities. On the other hand, it is only the GEANT4 kernel (i.e., tracking) which can ensure an overall coherence of the simulation.

The general principles in GEANT4 are the following:

- 1. Each **process** has its intrinsic limit(s) to produce secondary particles.
- 2. All particles produced (and accepted) will be tracked up to **zero range**.
- 3. Each **particle** has a suggested cut in range (which is converted to energy for all materials), and defined via a SetCut() method (see *Range Cuts*).

Points 1 and 2 imply that the cut associated with the **particle** is a (recommended) **production** threshold of secondary particles.

### 5.4.2 Set production threshold (SetCut methods)

As already mentioned, each kind of particle has a suggested production threshold. Some of the processes will not use this threshold (e.g., decay), while other processes will use it as a default value for their intrinsic limits (e.g., ionisation and bremsstrahlung).

See *Range Cuts* to see how to set the production threshold.

## 5.4.3 Apply cut

The DoIt methods of each process can produce secondary particles. Two cases can happen:

- a process sets its intrinsic limit greater than or equal to the recommended production threshold. OK. Nothing has to be done (nothing can be done!).
- a process sets its intrinsic limit smaller than the production threshold (for instance 0).

The list of secondaries is sent to the SteppingManager via a ParticleChange object.

*Before* being recopied to the temporary stack for later tracking, the particles below the production threshold will be kept or deleted according to the safe mechanism explained hereafter.

- The ParticleDefinition (or ParticleWithCuts) has a Boolean data member: ApplyCut.
- ApplyCut is OFF: do nothing. All the secondaries are stacked (and then tracked later on), regardless of their initial energy. The GEANT4 kernel respects the best that the physics can do, but neglects the overall coherence and the efficiency. Energy conservation is respected as far as the processes know how to handle correctly the particles they produced! This is the main used during GEANT4 tracking.
- ApplyCut in ON: this feature is not normally used but is potentially available; the *TrackingManager* checks the range of each secondary against the production threshold and against the safety. The particle is stacked if range > min(cut, safety).
  - If not, check if the process has nevertheless set the flag "good for tracking" and then stack it (see Why produce secondaries below threshold in some processes? below for the explanation of the GoodForTracking flag).
  - If not, recuperate its kinetic energy in the localEnergyDeposit, and set tkin=0.
  - Then check in the *ProcessManager* if the vector of *ProcessAtRest* is not empty. If yes, stack the particle for performing the "Action At Rest" later. If not, and only in this case, abandon this secondary.

With this sophisticated mechanism we have the global cut that we wanted, but with energy conservation, and we respect boundary constraint (safety) and the wishes of the processes (via "good for tracking"). Note, that for electromagnetic processes for gamma incident a specific ApplyCut option is used which guarantees energy balance and is more efficient because secondary tracks are not produced at all.

### 5.4.4 Why produce secondaries below threshold in some processes?

A process may have good reasons to produce particles below the recommended threshold:

- checking the range of the secondary versus geometrical quantities like safety may allow one to realize the possibility that the produced particle, even below threshold, will reach a sensitive part of the detector;
- another example is the gamma conversion: the positron is always produced, even at zero energy, for further annihilation;
- if a process is rare there is not practical reason make it complicate checking cut value.

These secondary particles are sent to the "Stepping Manager" with a flag GoodForTracking to pass the filter explained in the previous section (even when ApplyCut is ON).

### 5.4.5 Cuts in stopping range or in energy?

The cuts in stopping range allow one to say that the energy has been released at the correct space position, limiting the approximation within a given distance. On the contrary, cuts in energy imply accuracies of the energy depositions which depend on the material.

### 5.4.6 Summary

In summary, we do not have tracking cuts; we only have production thresholds in range. All particles produced and accepted are tracked up to zero range.

It must be clear that the overall coherency that we provide cannot go beyond the capability of processes to produce particles down to the recommended threshold.

In other words a process can produce the secondaries down to the recommended threshold, and by interrogating the geometry, or by realizing when mass-to-energy conversion can occur, recognize when particles below the threshold have to be produced.

### 5.4.7 Special tracking cuts

One may need to cut given particle types in given volumes for optimisation reasons. This decision is under user control, and can happen for particles during tracking as well.

The user must be able to apply these special cuts only for the desired particles and in the desired volumes, without introducing an overhead for all the rest.

The approach is as follows:

• special user cuts are registered in the *UserLimits* class (or its descendant), which is associated with the logical volume class.

The current default list is:

- max allowed step size
- max total track length
- max total time of flight
- min kinetic energy
- min remaining range

The user can instantiate a *UserLimits* object only for the desired logical volumes and do the association.

The first item (max step size) is automatically taken into account by the G4 kernel while the others items must be managed by the user, as explained below.

**Example**(see basic/B2/B2a or B2b): in the Tracker region, in order to force the step size not to exceed one half of the Tracker chamber thickness (chamberWidth), it is enough to put the following code in B2a::DetectorConstruction::DefineVolumes():

```
G4double maxStep = 0.5*chamberWidth;
fStepLimit = new G4UserLimits(maxStep);
trackerLV->SetUserLimits(fStepLimit);
```

and in PhysicsList, the process G4StepLimiter needs to be attached to each particle's process manager where step limitation in the Tracker region is required:

```
// Step limitation seen as a process
G4StepLimiter* stepLimiter = new G4StepLimiter();
pmanager->AddDiscreteProcess(StepLimiter);
```

If a provided GEANT4 physics list is used, as FTFP\_BERT in B2 example, then the G4StepLimiterPhysics, which will take care of attaching the G4StepLimiter process to all particles, can be added to the physics list in the main() function:

```
G4VModularPhysicsList* physicsList = new FTFP_BERT;
physicsList->RegisterPhysics(new G4StepLimiterPhysics());
runManager->SetUserInitialization(physicsList);
```

The G4UserLimits class is in source/global/management.

• Concerning the others cuts, the user must define dedicated process(es). He registers this process (or its descendant) only for the desired particles in their process manager. He can apply his cuts in the DoIt of this process, since, via G4Track, he can access the logical volume and *UserLimits*.

An example of such process (called *UserSpecialCuts*) is provided in the repository, but not inserted in any process manager of any particle.

**Example: neutrons.** One may need to abandon the tracking of neutrons after a given time of flight (or a charged particle in a magnetic field after a given total track length ... etc ...).

Example(see basic/B2/B2a or B2b): in the Tracker region, in order to force the total time of flight of the neutrons not to exceed 10 milliseconds, put the following code in B2a::DetectorConstruction::DefineVolumes():

```
G4double maxTime = 10*ms;
fStepLimit = new G4UserLimits(DBL_MAX,DBL_MAX,maxTime);
trackerLV->SetUserLimits(fStepLimit);
```

and put the following code in a physics list:

```
G4ProcessManager* pmanager = G4Neutron::Neutron->GetProcessManager();
pmanager->AddProcess(new G4UserSpecialCuts(),-1,-1,1);
```

If a provided GEANT4 physics list is used, then a SpecialCutsBuilder class can be defined in a similar way as G4StepLimiterPhysics and added to the physics list in the main() function:

```
G4VModularPhysicsList* physicsList = new FTFP_BERT;
physicsList->RegisterPhysics(new SpecialCutsBuilder());
runManager->SetUserInitialization(physicsList);
```

(The default G4UserSpecialCuts class is in source/processes/transportation.)

## 5.5 Cuts per Region

### 5.5.1 General Concepts

Beginning with GEANT4 version 5.1, the concept of a region has been defined for use in geometrical descriptions. Details about regions and how to use them are available in *Sub-detector Regions*. As an example, suppose a user defines three regions, corresponding to the tracking volume, the calorimeter and the bulk structure of a detector. For performance reasons, the user may not be interested in the detailed development of electromagnetic showers in the insensitive bulk structure, but wishes to maintain the best possible accuracy in the tracking region. In such a use case, GEANT4 allows the user to set different production thresholds ("cuts") for each geometrical region. This ability, referred to as "cuts per region", is also a new feature provided by the GEANT4 5.1 release. The general concepts of production thresholds were presented in the *Production Threshold versus Tracking Cut*.

Please note that this new feature is intended only for users who

- 1. are simulating the most complex geometries, such as an LHC detector, and
- 2. are experienced in simulating electromagnetic showers in matter.

We strongly recommend that results generated with this new feature be compared with results using the same geometry and uniform production thresholds. Setting completely different cut values for individual regions may break the coherent and comprehensive accuracy of the simulation. Therefore cut values should be carefully optimized, based on a comparison with results obtained using uniform cuts.

### 5.5.2 Default Region

The world volume is treated as a region by default. A G4Region object is automatically assigned to the world volume and is referred to as the "default region". The production cuts for this region are the defaults which are defined in the *UserPhysicsList*. Unless the user defines different cut values for other regions, the cuts in the default region will be used for the entire geometry.

Please note that the default region and its default production cuts are created and set automatically by G4RunManager. The user is **not** allowed to set a region to the world volume, **nor** to assign other production cuts to the default region.

### 5.5.3 Assigning Production Cuts to a Region

In the SetCuts() method of the user's physics list, the user must first define the default cuts. Then a G4ProductionCuts object must be created and initialized with the cut value desired for a given region. This object must in turn be assigned to the region object, which can be accessed by name from the G4RegionStore. An example SetCuts() code follows.

Listing 5.12: Setting production cuts to a region

```
void MyPhysicsList::SetCuts()
  // default production thresholds for the world volume
 SetCutsWithDefault();
  // Production thresholds for detector regions
 G4Region* region;
 G4String regName;
 G4ProductionCuts* cuts;
  regName = "tracker";
 region = G4RegionStore::GetInstance()->GetRegion(regName);
 cuts = new G4ProductionCuts;
 cuts->SetProductionCut(0.01*mm); // same cuts for gamma, proton, e- and e+
  region->SetProductionCuts(cuts);
 regName = "calorimeter";
  region = G4RegionStore::GetInstance()->GetRegion(regName);
 cuts = new G4ProductionCuts;
 cuts->SetProductionCut(0.01*mm,G4ProductionCuts::GetIndex("gamma"));
 cuts->SetProductionCut(0.1*mm, G4ProductionCuts::GetIndex("e-"));
 cuts->SetProductionCut(0.1*mm, G4ProductionCuts::GetIndex("e+"));
 cuts->SetProductionCut(0.1*mm, G4ProductionCuts::GetIndex("proton"));
  region->SetProductionCuts(cuts);
```

## 5.6 Physics Table

### 5.6.1 General Concepts

In GEANT4, physics processes use many tables of cross sections, energy losses and other physics values. Before the execution of an event loop, PreparePhysicsTable() and BuildPhysicsTable() methods of G4VProcess are invoked for all processes and as a part of initialisation procedure cross section tables are prepared. Energy loss processes calculate cross section and/or energy loss values for each pair of material and production cut value used in geometry for a give run. A change in production cut values therefore require these cross sections to be re-calculated. Cross sections for hadronic processes and gamma processes do not depend on the production cut but sampling of final state may depend on cuts, so full re-initialisation is performed.

The G4PhysicsTable class is used to handle cross section tables. G4PhysicsTable is a collection of instances of G4PhysicsVector (and derived classes), each of which has cross section values for a particle within a given energy range traveling in a material. By default the linear interpolation is used, alternatively spline may be used if the flag of spline is activated by *SetSpline* method of the G4PhysicsVector

# 5.6.2 Material-Cuts Couple

Users can assign different production cuts to different regions (see *Cuts per Region*). This means that if the same material is used in regions with different cut values, the processes need to prepare several different cross sections for that material.

The G4ProductionCutsTable has G4MaterialCutsCouple objects, each of which consists of a material paired with a cut value. These G4MaterialCutsCouples are numbered with an index which is the same as the index of a G4PhysicsVector for the corresponding G4MaterialCutsCouple in the G4PhysicsTable. The list of *MaterialCutsCouples* used in the current geometry setup is updated before starting the event loop in each run.

## 5.6.3 File I/O for the Physics Table

Calculated physics tables for electromagnetic processes can be stored in files. The user may thus eliminate the time required for the calculation of physics tables by retrieving them from the files.

Using the built-in user command "storePhysicsTable" (see *Built-in Commands*), stores physics tables in files. Information on materials and cuts defined in the current geometry setup are stored together with physics tables because calculated values in the physics tables depend on *MaterialCutsCouple*. Note that physics tables are calculated before the event loop, not in the initialization phase. So, at least one event must be executed before using the "storePhysicsTable" command.

Calculated physics tables can be retrieved from files by using the "retrievePhysicsTable" command. Materials and cuts from files are compared with those defined in the current geometry setup, and only physics vectors corresponding to the *MaterialCutsCouples* used in the current setup are restored. Note that nothing happens just after the "retrievePhysicsTable" command is issued. Restoration of physics tables will be executed in parallel with the calculation of physics tables.

## 5.6.4 Building the Physics Table

In the G4RunManagerKernel::RunInitialization() method, after the list of *MaterialCutsCouples* is updated, the G4VUserPhysicsList::BuildPhysicsTable() method is invoked to build physics tables for all processes.

Initially, the G4VProcess::PreparePhysicsTable() method is invoked. Each process creates G4PhysicsTable objects as necessary. It then checks whether the *MaterialCutsCouples* have been modified after a run to determine if the corresponding physics vectors can be used in the next run or need to be re-calculated.

Next, the G4VProcess::RetrievePhysicsTable() method is invoked if the G4VUserPhysicsList::fRetrievePhysicsTable flag is asserted. After checking materials and cuts in files, physics vectors corresponding to the *MaterialCutsCouples* used in the current setup are restored.

Finally, the G4VProcess::BuildPhysicsTable() method is invoked and only physics vectors which need to be re-calculated are built.

At the end of program G4PhysicsTable should be deleted. Before deletion of a table it should be cleaned up using the method G4PhysicsTable::clearAndDestroy(). This method should be called in a middle of the run if an old table is removed and a new one is created.

5.6. Physics Table 279

# 5.7 User Limits

## 5.7.1 General Concepts

The user can define artificial limits affecting to the GEANT4 tracking.

```
G4UserLimits(G4double uStepMax = DBL_MAX,
G4double uTrakMax = DBL_MAX,
G4double uTimeMax = DBL_MAX,
G4double uEkinMin = 0.,
G4double uRangMin = 0.);
```

where:

uStepMax	Maximum step length
uTrakMax	Maximum total track length
uTimeMax	Maximum global time for a track
uEkinMin	Minimum remaining kinetic energy for a track
uRangMin	Minimum remaining range for a track

Note that uStepMax is affecting to each step, while all other limits are affecting to a track.

The user can assign G4UserLimits to logical volume and/or to a region. User limits assigned to logical volume do not propagate to daughter volumes, while User limits assigned to region propagate to daughter volumes unless daughters belong to another region. If both logical volume and associated region have user limits, those of logical volume win.

A G4UserLimits object must be instantiated for the duration of whatever logical volume or region to which it is assigned. It is the responsibility of the user's code to delete the object *after* the assigned volume(s)/region(s) have been deleted.

# 5.7.2 Processes co-working with G4UserLimits

In addition to instantiating G4UserLimits and setting it to logical volume or region, the user has to assign the following process(es) to particle types he/she wants to affect. If none of these processes is assigned, that kind of particle is not affected by G4UserLimits.

**Limitation to step (uStepMax)** G4StepLimiter process must be defined to affected particle types. This process limits a step, but it does not kill a track.

Limitations to track (uTrakMax, uTimeMax, uEkinMin, uRangMin) G4UserSpecialCuts process must be defined to affected particle types. This process limits a step and kills the track when the track comes to one of these limits. Step limitation occurs only for the final step.

Example of G4UserLimits can be found in examples/basic/B2: see B2a::DetectorConstruction (or B2b::DetectorConstruction). The G4StepLimiter process is added in the GEANT4 physics list via the G4StepLimiterPhysics class in the main () function in exampleB4a.cc (or exampleB4b.cc).

# 5.8 Track Error Propagation

The error propagation package serves to propagate one particle together with its error from a given trajectory state until a user-defined target is reached (a surface, a volume, a given track length,...).

## 5.8.1 Physics

The error propagator package computes the average trajectory that a particle would follow. This means that the physics list must have the following characteristics:

- · No multiple scattering
- No random fluctuations for energy loss
- · No creation of secondary tracks
- No hadronic processes

It has also to be taken into account that when the propagation is done backwards (in the direction opposed to the one the original track traveled) the energy loss has to be changed into an energy gain.

All this is done in the G4ErrorPhysicsList class, that is automatically set by G4ErrorPropagatorManager as the GEANT4 physics list. It sets G4ErrorEnergyLoss as unique electromagnetic process. This process uses the GEANT4 class G4EnergyLossForExtrapolator to compute the average energy loss for forwards or backwards propagation. To avoid getting too different energy loss calculation when the propagation is done forwards (when the energy at the beginning of the step is used) or backwards (when the energy at the end of the step is used, always smaller than at the beginning) G4ErrorEnergyLoss computes once the energy loss and then replaces the original energy loss by subtracting/adding half of this value (what is approximately the same as computing the energy loss with the energy at the middle of the step). In this way, a better calculation of the energy loss is obtained with a minimal impact on the total CPU time.

The user may use his/her own physics list instead of G4ErrorPhysicsList. As it is not needed to define a physics list when running this package, the user may have not realized that somewhere else in his/her application it has been defined; therefore a warning will be sent to advert the user that he is using a physics list different to G4ErrorPhysicsList. If a new physics list is used, it should also initialize the G4ErrorMessenger with the classes that serve to limit the step:

```
G4ErrorEnergyLoss* eLossProcess = new G4ErrorEnergyLoss;
G4ErrorStepLengthLimitProcess* stepLengthLimitProcess = new G4ErrorStepLengthLimitProcess;
G4ErrorMagFieldLimitProcess* magFieldLimitProcess = new G4ErrorMagFieldLimitProcess;
new G4ErrorMessenger( stepLengthLimitProcess, magFieldLimitProcess, eLossProcess);
```

To ease the use of this package in the reconstruction code, the physics list, whether G4ErrorPhysicsList or the user's one, will be automatically initialized before starting the track propagation if it has not been done by the user.

## 5.8.2 Trajectory state

The user has to provide the particle trajectory state at the initial point. To do this it has to create an object of one of the children classes of G4ErrorTrajState, providing:

- Particle type
- Position
- Momentum
- · Trajectory error matrix

A particle trajectory is characterized by five independent variables as a function of one parameter (e.g. the path length). Among the five variables, one is related to the curvature (to the absolute value of the momentum), two are related to the direction of the particle and the other two are related to the spatial location.

There are two possible representations of these five parameters in the error propagator package: as a free trajectory state, class G4ErrorTrajStateFree, or as a trajectory state on a surface, class G4ErrorTrajStateonSurface.

### Free trajectory state

In the free trajectory state representation the five trajectory parameters are

- · G4double fInvP
- · G4double fLambda
- · G4double fPhi
- · G4double fYPerp
- G4double fZPerp

where fInvP is the inverse of the momentum. fLambda and fPhi are the dip and azimuthal angles related to the momentum components in the following way:

```
p\x = p \cos(lambda) \cos(phi) p\y = p \cos(lambda) \sin(phi) p\y = p \sin(lambda), that is, lambda = 90 - theta, where theta is the usual angle with respect to the Z axis.
```

fyperp and fzperp are the coordinates of the trajectory in a local orthonormal reference frame with the X axis along the particle direction, the Y axis being parallel to the X-Y plane (obtained by the vectorial product of the global Z axis and the momentum).

#### Trajectory state on a surface

In the trajectory state on a surface representation the five trajectory parameters are

- · G4double fInvP
- G4double fPV
- · G4double fPW
- · G4double fV
- · G4double fW

where fInvP is the inverse of the momentum; fPV and fPW are the momentum components in an orthonormal coordinate system with axis U, V and W; fV and fW are the position components on this coordinate system.

For this representation the user has to provide the plane where the parameters are calculated. This can be done by providing two vectors, V and W, contained in the plane:

#### or by providing a plane

In this second case the vector V is calculated as the vector in the plane perpendicular to the global vector X (if the plane normal is equal to X, Z is used instead) and W is calculated as the vector in the plane perpendicular to V.

## 5.8.3 Trajectory state error

The 5X5 error matrix should also be provided at the creation of the trajectory state as a G4ErrorTrajErr object. If it is not provided a default object will be created filled with null values.

Currently the G4ErrorTrajErr is a G4ErrorSymMatrix, a simplified version of CLHEP HepSymMatrix.

The error matrix is given in units of GeV and cm. Therefore you should do the conversion if your code is using other units.

## 5.8.4 Targets

The user has to define up to where the propagation must be done: the target. The target can be a surface G4ErrorSurfaceTarget, which is not part of the GEANT4 geometry. It can also be the surface of a GEANT4 volume G4ErrorGeomVolumeTarget, so that the particle will be stopped when it enters this volume. Or it can be that the particle is stopped when a certain track length is reached, by implementing a G4ErrorTrackLengthTarget.

#### Surface target

When the user chooses a G4ErrorSurfaceTarget as target, the track is propagated until the surface is reached. This surface is not part of GEANT4 geometry, but usually traverses many GEANT4 volumes. The class G4ErrorNavigator takes care of the double navigation: for each step the step length is calculated as the minimum of the step length in the full geometry (up to a GEANT4 volume surface) and the distance to the user-defined surface. To do it, G4ErrorNavigator inherits from G4Navigator and overwrites the methods ComputeStep() and ComputeSafety(). Two types of surface are currently supported (more types could be easily implemented at user request): plane and cylindrical.

## Plane surface target

G4ErrorPlaneSurfaceTarget implements an infinite plane surface. The surface can be given as the four coefficients of the plane equation ax+by+cz+d = 0:

```
G4ErrorPlaneSurfaceTarget(G4double a=0,
G4double b=0,
G4double c=0,
G4double d=0);
```

or as the normal to the plane and a point contained in it:

```
G4ErrorPlaneSurfaceTarget(const G4Normal3D &n, const G4Point3D &p);
```

or as three points contained in it:

```
G4ErrorPlaneSurfaceTarget(const G4Point3D &p1,
const G4Point3D &p2,
const G4Point3D &p3);
```

### Cylindrical surface target

G4ErrorCylSurfaceTarget implements an infinite-length cylindrical surface (a cylinder without end-caps). The surface can be given as the radius, the translation and the rotation

or as the radius and the affine transformation

```
G4ErrorCylSurfaceTarget( const G4double& radius, const G4AffineTransform& trans);
```

## Geometry volume target

When the user chooses a G4ErrorGeomVolumeTarget as target, the track is propagated until the surface of a GEANT4 volume is reached. User can choose if the track will be stopped only when the track enters the volume, only when the track exits the volume or in both cases.

The object has to be instantiated giving the name of a logical volume existing in the geometry:

```
G4ErrorGeomVolumeTarget( const G4String& name );
```

### **Track Length target**

When the user chooses a G4ErrorTrackLengthTarget as target, the track is propagated until the given track length is reached.

The object has to be instantiated giving the value of the track length:

```
G4ErrorTrackLengthTarget(const G4double maxTrkLength);
```

It is implemented as a G4VDiscreteProcess and it limits the step in PostStepGetPhysicalInteractionLength. To ease its use, the process is registered to all particles in the constructor.

## 5.8.5 Managing the track propagation

The user needs to propagate just one track, so there is no need of run and events. neither of G4VPrimaryGeneratorAction. G4ErrorPropagator creates a track from the information given in the G4ErrorTrajState and manages the step propagation. The propagation is done by the standard GEANT4 methods, invoking G4SteppingManager::Stepping() to propagate each step.

After one step is propagated, G4ErrorPropagator takes cares of propagating the track errors for this step, what is done by G4ErrorTrajStateFree::PropagateError(). The equations of error propagation are only implemented in the representation of G4ErrorTrajStateFree. Therefore if the user has provided instead a G4ErrorTrajStateOnSurface object, it will be transformed into a G4ErrorTrajStateFree at the beginning of tracking, and at the end it is converted back into G4ErrorTrajStateOnSurface on the target surface (on the normal plane to the surface at the final point).

The user G4VUserTrackingAction::PreUserTrackingAction(const G4Track\*) and G4VUserTrackingAction::PreUserTrackingAction(const G4Track\*) are also invoked at the beginning and at the end of the track propagation.

G4ErrorPropagator stops the tracking when one of the three conditions is true:

- · Energy is exhausted
- · World boundary is reached
- · User-defined target is reached

In case the defined target is not reached, G4ErrorPropagator::Propagate() returns a negative value.

The propagation of a trajectory state until a user defined target can be done by invoking the method of G4ErrorPropagatorManager

```
G4int Propagate( G4ErrorTrajState* currentTS, const G4ErrorTarget* target, G4ErrorMode mode = G4ErrorMode_PropForwards );
```

You can get the pointer to the only instance of G4ErrorPropagatorManager with

```
G4ErrorPropagatorManager* g4emgr = G4ErrorPropagatorManager::GetErrorPropagatorManager();
```

Another possibility is to invoke the propagation step by step, returning control to the user after each step. This can be done with the method

```
G4int PropagateOneStep( G4ErrorTrajState* currentTS, G4ErrorMode mode = G4ErrorMode_PropForwards);
```

In this case you should register the target first with the command

```
G4ErrorPropagatorData::GetG4ErrorPropagatorData()->SetTarget( theG4eTarget );
```

#### **Error propagation**

As in the GEANT3-based GEANE package, the error propagation is based on the equations of the European Muon Collaboration, that take into account:

- · Error from curved trajectory in magnetic field
- Error from multiple scattering
- · Error from ionization

The formulas assume propagation along an helix. This means that it is necessary to make steps small enough to assure magnetic field constantness and not too big energy loss.

## 5.8.6 Limiting the step

There are three ways to limit the step. The first one is by using a fixed length value. This can be set by invoking the user command:

```
G4UImanager::GetUIpointer()->ApplyCommand("/geant4e/limits/stepLength MY_VALUE MY_UNIT");
```

The second one is by setting the maximum percentage of energy loss in the step (or energy gain is propagation is backwards). This can be set by invoking the user command:

```
G4UImanager::GetUIpointer()->ApplyCommand("/geant4e/limits/energyLoss MY_VALUE");
```

The last one is by setting the maximum difference between the value of the magnetic field at the beginning and at the end of the step. Indeed what is limited is the curvature, or exactly the value of the magnetic field divided by the value of the momentum transverse to the field. This can be set by invoking the user command:

G4UImanager::GetUIpointer()->ApplyCommand("/geant4e/limits/magField MY\_VALUE");

The classes that limit the step are implemented as GEANT4 processes. Therefore, the invocation of the above-mentioned commands should only be done after the initialization (for example after G4ErrorPropagatorManager::InitGeant4e().

# 5.9 Exotic Physics

The GEANT4 toolkit has recently been extended to include "exotic physics". This covers the area of phonon propagation and crystal channelling. These two domains are applicable for Dark Matter experiments (phonon excitation) and beam extraction and collimation (crystal channelling). The framework within GEANT4 is similar in that a macroscopic periodic crystal lattice is required for both and wave functions are propagated within the medium (rather than discrete particles as in the case of conventional GEANT4). Contained here is a brief description of how to modify a GEANT4 application to include the crystal as both a material and a geometry (plane orientations).

## 5.9.1 Physics

For a more complete description and understanding the user is referred to the extended examples category "exotic-physics" and the references therein.

#### 5.9.2 Material

The implementation of solid-state processes in GEANT4 requires the addition of two important features, the crystal unit cell with all its parameters and the support for other data required by the processes. The extended data for a material is stored in a class derived from the virtual class G4VMaterialExtension. The G4ExtenededMaterial class collects the pointers to concrete instances of G4VMaterialExtension. The G4CrystalExtension class is a derived class of G4VMaterialExtension and collects information on the physics properties of a perfect crystal. In particular, the class contains a pointer to a G4CrystalUnitCell object, the elasticity tensor, a map of G4CrystalAtomBase objects associated with a G4Element and a vector of G4AtomicBond. The G4CrystalUnitCell class collects information on the mathematical description of the crystal unit cell, i.e. the sizes and the angles of the unit cell, the space group, the Bravais lattice and the lattice system, and methods for the calculation of the volume in the direct and reciprocal space, the spacing between two planes, the angle between two planes, and for the filling of the reduced elasticity tensor. The G4CrystalExtension constructor takes as argument a pointer to a G4Material object and has to be registered to the G4ExtendedMaterial to which it is attached. The G4CrystalAtomBase class stores the position of atoms in the crystal unit cell. Since the G4CrystalAtomBase class is mapped to a G4Element in the G4CrystalMaterial, each G4Element should have an associated G4CrystalAtomBase. The G4AtomicBond class contains information on the atomic bond in the crystal. For each instance of the class two G4Elements have to be specified as well as the atom number in the G4CrystalAtomBase associated to the G4Element.

# 5.9.3 Geometry

The G4LogicalCrystalVolume accepts only a pointer to a G4CrystalExtension in its constructor and stores the definition of the orientation of the crystalline structure with respect to the solid to which it is attached. By convention, the crystal < 100 > direction is by default set parallel to the {[1,0,0]} direction in the GEANT4 reference system, and the < 010 > axis lays on the plane which contains the [1,0,0] and [0,1,0] directions in the GEANT4 reference system.

5.9. Exotic Physics 287

**CHAPTER** 

SIX

## **USER ACTIONS**

## 6.1 User Actions

GEANT4 has two user initialization classes and one user action class whose methods the user must override in order to implement a simulation. They require the user to define the detector, specify the physics to be used, and define how initial particles are to be generated. These classes are described in *Mandatory User Actions and Initializations*.

Additionally, users may define any of several optional user actions, to collect data during event generation from steps, tracks, or whole events, to accumulate data during runs, or to modify the state of new tracks as they are created. These user actions are described in *Optional User Actions*.

To support the accumulation of data in the actions mentioned above, users may define subclasses for some of the container objects used during event generation and tracking. These are described in *User Information Classes*.

# 6.2 Mandatory User Actions and Initializations

Three user initialization class objects are registered with the run manager (*Manage the run procedures*) in the user's main() program, which takes ownership. The user must not delete these objects directly, and they must be created using 'new'. Within the G4UserActionInitialization class (*User Action Initialization*), the user must instantiate and register a concrete G4VUserPrimaryGeneratorAction subclass, which generates the primary particles for each event.

## 6.2.1 G4VUserDetectorConstruction

Listing 6.1: G4VUserDetectorConstruction

```
class G4VUserDetectorConstruction
{
  public:
    G4VUserDetectorConstruction();
    virtual ~G4VUserDetectorConstruction();

public:
    virtual G4VPhysicalVolume* Construct() = 0;
    virtual void ConstructSDandField() = 0;
};
```

In the Construct () method, material and geometry has to be described. Detailed discussions on material and geometry are given in *How to Specify Materials in the Detector* and *How to Define a Detector Geometry*. Detector sensitivity and electromagnetic field should be defined in ConstructSDandField(), as objects defined in this method are thread-local if they are used in multi-threaded mode. Detailed discussions on Detector sensitivity and electromagnetic field are given in *Hits* and *Electromagnetic Field*.

## 6.2.2 Physics Lists

The concept of a physics list arises from the fact that GEANT4 can not offer a single modeling algorithm to cover the entire energy domain from zero to the TeV scale, for all known processes and particles. Instead, a combination of ideas and approaches is typically used to perform a simulation task.

A schematic view of the GEANT4 modeling of the processes of particle passage through matter may be presented as follows:

- Physics Model = final state generator
- Physics Process = cross section + model
- Physics List = list of processes for each particle

The "patchwork" concept is especially true in the GEANT4 hadronic physics domain: models are valid only over finite energy ranges, and there maybe competing models in the same range or one model maybe working better than the other for a specific group of particles, while its competitor may be better for other species. For this reason models have to be combined to cover the large energy range; every two adjacent models may have an overlap in their validity range.

#### G4VUserPhysicsList

This is an abstract class for constructing particles and processes. An introduction into the concept of the GEANT4 Physics List and the GEANT4 Physics Processes is also given in *How to Specify Physics Processes* and further in *Physics Processes*.

While the fabrication of a physics list is, in principle, a choice of a user, the toolkit is distributed with a number of pre-fabricated physics lists for the convenience of many user applications. These physics lists are supported by the GEANT4 development team and can be recommended for specific physics tasks. However, based on the interests and needs of a specific project, a user may want to implement her or his own custom physics list.

The following sections offer several examples that show how to instantiate or select one or another pre-fabricated Physics List from the GEANT4 standard collection, as well as guidance composing a custom Physics List from pre-fabricated components or even entirely from scratch.

To view the contents of a Physics List, there are two useful methods: DumpList() and DumpCutValueTable(G4int flag).

#### **Reference Physics Lists**

Number of ready to use Physics Lists are available with GEANT4 kernel. Below an example of instantiation of FTFP BERT Physics List class is shown. The full set of reference Physics Lists is described in GEANT4 web.

#### Listing 6.2: Creating FTFP\_BERT Physics List.

```
G4int verbose = 1;
FTFP_BERT* physlist = new FTFP_BERT(verbose);
runManager->SetUserInitialization(physlist);
```

#### **Building Physics List Using Factory**

GEANT4 provides a class G4PhysListFactory allowing to defined Physics List by its name. The last for characters in the name defines an electromagnetic (EM) physics options. By default standard EM physics is used, "\_EMV" corresponding to standard option1, "\_EMX" - to standard option2, "\_LIV" to EM Livermore physics, "\_PEN" - to EM Penelope physics.

Listing 6.3: Creating Physics List by name.

```
G4int verbose = 1;
G4PhysListFactory factory;
G4VModularPhysicsList* physlist = factory.GetReferencePhysList("FTFP_BERT_EMV");
physlist.SetVerboseLevel(verbose);
runManager->SetUserInitialization(physlist);
```

The class G4PhysListFactory provides also another interface allowing to defined Physics List by the environment variable *PHYSLIST*.

Listing 6.4: Creating Physics List by name.

```
G4int verbose = 1;
G4PhysListFactory factory;
G4VModularPhysicsList* physlist = factory.ReferencePhysList();
physlist.SetVerboseLevel(verbose);
runManager->SetUserInitialization(physlist);
```

## **Building Physics List from Physics Builders**

Technically speaking, one can implement physics list in a "flat-out" manner, i.e. specify all necessary particles and associated processes in a single piece of code, as it will be shown later in this document. However, for practical purposes it is often more convenient to group together certain categories and make implementation more modular.

One very useful concept is a Modular Physics List, G4VModularPhysicsList, that is a sub-class of G4VUserPhysicsLists and allows a user to organize physics processes into "building blocks", or "modules", then compose a physics list of such modules. The concept allows to group together, at a relatively high level, desired combinations of selected particles and related processes. One of the advantages of such approach is that it allows to combine pre-fabricated physics modules that are centrally provided by GEANT4 kernel with user's applications.

G4ModularPhysicsList has all the functionalities as G4VUserPhysicsList class, plus several additional functionalities. One of the important methods is RegisterPhysics (G4VPhysicsConstructor\*) for "registering" the above mentioned pre-fabricated physics modules. There also methods for removing or replacing physics modules.

Example below shows how G4VModularPhysList can be implemented.

Listing 6.5: Creating Physics List by name.

```
MyPhysicsList::MyPhysicsList():G4VModularPhysicsList()
{
   G4DataQuestionaire it(photon, neutron, no, no, neutronxs);
```

```
G4cout << "<< Geant4 Physics List: MyPhysicsList " << G4endl;
G4cout <<G4endl:
defaultCutValue = 0.7*mm;
G4int ver = 1;
SetVerboseLevel(ver);
// EM Physics
RegisterPhysics( new G4EmStandardPhysics(ver) );
// Synchroton Radiation & GN Physics
RegisterPhysics( new G4EmExtraPhysics(ver) );
RegisterPhysics ( new G4DecayPhysics (ver) );
// Hadron physics
RegisterPhysics( new G4HadronElasticPhysicsXS(ver) );
RegisterPhysics( new G4QStoppingPhysics(ver) );
RegisterPhysics ( new G4IonBinaryCascadePhysics (ver) );
RegisterPhysics( new G4HadronInelasticQBBC(ver));
RegisterPhysics( new G4NeutronTrackingCut(ver) );
```

Note that each module to be registered with a Modular Physics List is a G4VPhysicsConstructor (or a derived object), i.e. a "sublist" that holds groups of particles and accompanying physics processes. A user can find these and other similar modules in the source/physics\_lists/list area of GEANT4 core code, and can combine selected ones with custom modules, if desired.

In order to compose a custom physics module, two mandatory methods of a G4VPhysicsConstructor must be implemented: ConstructParticle() and ConstructProcess(); beyond that the implementation can be structured according to the developer's taste.

Another useful concept in the modular approach to composing a Physics List is the concept of so called "builders". This concept allows to encapsulate certain implementation details into smaller-scale software components, and offers the flexibility of re-using those component in different modules. At the general level, the scheme is this:

- Particles (hadrons) are created, and physics models to be used to simulate applicable processes are specified, usually in a particular range of validity.
- Physics processes for each particle type in the builder are created, and each process is outfitted with one or more hadronic physics models, as specified.
- If necessary, a cross section data set for a given particle type is added.

This concept is widely used through the GEANT4 hadronic domain, but the idea would be equally applicable in the electromagnetic area.

All builders can be found in the source/physics\_lists/builders directory. There are basically two types of builders:

- · Particle Builders
- · Particle-Model Builders

A particle builder is somewhat "superior" here, as it specifies a particle or a group of particles, what category of processes are applicable, how to outfit a process with specified model(s), and how processes are to be registered with the G4ProcessManager. A particle-model builder instantiates a given model and implements details of associating it with one or more processes applicable to a given particle type. Some models can not be instantiated through a single interface class, but instead they need, in turn, to be composed from several components (examples are QGS and FTF).

Useful example builders to review and to consider as inspirations can be the following:

- G4PiKBuilder (.hh and .cc) groups pions and kaons, together with a list of associated hadronic processes.
- G4BertiniPiKBuilder (.hh and .cc) instantiates Bertini cascade model and implements how to outfit pion and kaon physics processes with this model. It also sets default validity range for the model.

• G4FTFPPiKBuilder (.hh and .cc) - composes a high energy FTF-based model and implements how to outfit hadronic processes for pions and kaons with the model. This example illustrates that a hadronic model does not always have a single interface class, but it needs to be created from several components. In particular, in this builder a "high energy generator" object (G4TheoFSGenerator) is created and is outfitted with G4FTFModel string model (which also gives this builder its name), we well as string fragmentation algorithm and intra-nuclear transport model. Please note that the quasi-elastic scattering is not set as FTF model has its own mechanism for it. A cross-section data set is specified for pions. A default validity range is also specified.

One detail to remember is that, in principle, the validity range for a given model can be setup for each particle type individually. But in these referenced applications the validity range is setup to be the same for a group of particles (i.e. for a number of corresponding inelastic hadronic processes). Once a builder is instantiated, one can override the default validity range (via SetMinEnergy or SetMaxEnergy methods), but the new value will be, again, given to a group of particles/processes. Also note that the validity range can be overridden only before calling the Build() method of a builder. Again, the approach is just a specifics of this particular implementation. Obviously, if a limited validity range is selected for a specific particle/model/process, one has to supplement another model or several models, to cover the entire range.

One more useful class is the `` G4PhysicsListHelper`` which is a service class that wraps around the technicalities of the physics process registering in GEANT4 and allows a user to easily associate a process with a particles, without knowing many details about various types of processes (discrete, continuous, etc.) and their internal ordering with G4ProcessManager. Curious users may eventually want to go deeper into details of G4ProcessManager class and, in particular, its group of AddProcess(...) methods, as it is the basis of G4PhysicsListHelper implementation. But for practical purposes, the use of G4PhysicsListHelper is likely to be sufficient in most cases.

Other useful details, including several elements of the software design philosophy and class diagrams, are given in *How to Specify Physics Processes*.

#### **Building Physics List from Scratch**

The user must derive a concrete class from G4VUserPhysicsList and implement three virtual methods:

- ConstructParticle() to instantiate each requested particle type;
- ConstructPhysics () to instantiate the desired physics processes and register each of them;
- SetCuts (G4double aValue) to set a cut value in range for all particles in the particle table, which invokes the rebuilding of the physics table.

At early stage of the initialisation of GEANT4 the method ConstructParticle() of G4VUserPhysicsList is invoked. The ConstructProcess() method must always invoke the AddTransportation() method in order to insure particle transportation. AddTransportation() must never be overridden. This is done automatically if G4VUserPhysicsList inherits of G4VModularPhysicsList. It is recommended for users as the most robust interface to Physics List. GEANT4 examples demonstrate different methods how to create user Physics List.

## 6.2.3 User Action Initialization

All user action classes must be defined through the protected method <code>SetUserAction()</code>. <code>Build()</code> methods should be used for defining user action classes for worker threads as well as for the sequential mode. <code>BuildForMaster()</code> should be used only for defining <code>UserRunAction</code> for the master thread. <code>BuildForMaster()</code> is not invoked in the sequential mode. In case the user uses his/her own <code>SteppingVerbose</code> class, it must be instantiated in the method <code>InitializeSteppingVerbose()</code> and returned.

#### G4VUserActionInitialization

Listing 6.6: G4VUserActionInitialization

```
class G4VUserActionInitialization
{
  public:
    G4VUserActionInitialization();
    virtual ~G4VUserActionInitialization();

public:
    virtual void Build() const = 0;
    virtual void BuildForMaster() const;
    virtual G4VSteppingVerbose* InitializeSteppingVerbose() const;

protected:
    void SetUserAction(G4VUserPrimaryGeneratorAction*) const;
    void SetUserAction(G4UserRunAction*) const;
    void SetUserAction(G4UserEventAction*) const;
    void SetUserAction(G4UserSteckingAction*) const;
    void SetUserAction(G4UserTrackingAction*) const;
    void SetUserAction(G4UserSteppingAction*) const;
    void SetUserAction(G4UserSteppingAction*) const;
    void SetUserAction(G4UserSteppingAction*) const;
};
```

#### G4VUserPrimaryGeneratorAction

Listing 6.7: G4VUserPrimaryGeneratorAction

```
class G4VUserPrimaryGeneratorAction
{
  public:
     G4VUserPrimaryGeneratorAction();
     virtual ~G4VUserPrimaryGeneratorAction();

  public:
     virtual void GeneratePrimaries(G4Event* anEvent) = 0;
};
```

# 6.3 Optional User Actions

There are five virtual classes whose methods the user may override in order to gain control of the simulation at various stages. Each method of each action class has an empty default implementation, allowing the user to inherit and implement desired classes and methods.

Objects of user action classes must be registered with G4RunManager (*Manage the run procedures*), which takes ownership of them. The user must not delete these objects directly, and they must be created using 'new'.

## 6.3.1 Usage of User Actions

#### G4UserRunAction

This class has three virtual methods which are invoked by G4RunManager for each run:

- GenerateRun () This method is invoked at the beginning of BeamOn. Because the user can inherit the class G4Run and create his/her own concrete class to store some information about the run, the GenerateRun () method is the place to instantiate such an object. It is also the ideal place to set variables which affect the physics table (such as production thresholds) for a particular run, because GenerateRun () is invoked before the calculation of the physics table.
- BeginOfRunAction () This method is invoked before entering the event loop. A typical use of this method would be to initialize and/or book histograms for a particular run. This method is invoked after the calculation of the physics tables.
- EndOfRunAction () This method is invoked at the very end of the run processing. It is typically used for a simple analysis of the processed run.

Listing 6.8: G4UserRunAction

```
class G4UserRunAction
{
  public:
    G4UserRunAction();
    virtual ~G4UserRunAction();

public:
    virtual G4Run* GenerateRun();
    virtual void BeginOfRunAction(const G4Run*);
    virtual void EndOfRunAction(const G4Run*);
};
```

#### G4UserEventAction

This class has two virtual methods which are invoked by G4EventManager for each event:

- beginOfEventAction() This method is invoked before converting the primary particles to G4Track objects. A typical use of this method would be to initialize and/or book histograms for a particular event.
- endOfEventAction () This method is invoked at the very end of event processing. It is typically used for a simple analysis of the processed event. If the user wants to keep the currently processing event until the end of the current run, the user can invoke fpEventManager->KeepTheCurrentEvent(); so that it is kept in G4Run object. This should be quite useful if you simulate quite many events and want to visualize only the most interest ones after the long execution. Given the memory size of an event and its contents may be large, it is the user's responsibility not to keep unnecessary events.

Listing 6.9: G4UserEventAction

```
class G4UserEventAction
{
  public:
     G4UserEventAction() {;}
     virtual ~G4UserEventAction() {;}
     virtual void BeginOfEventAction(const G4Event*);
     virtual void EndOfEventAction(const G4Event*);
  protected:
     G4EventManager* fpEventManager;
};
```

#### G4UserStackingAction

This class has three virtual methods, ClassifyNewTrack, NewStage and PrepareNewEvent which the user may override in order to control the various track stacking mechanisms. ExampleN04 could be a good example to understand the usage of this class.

ClassifyNewTrack() is invoked by G4StackManager whenever a new G4Track object is "pushed" onto a stack by G4EventManager. ClassifyNewTrack() returns an enumerator, G4ClassificationOfNewTrack, whose value indicates to which stack, if any, the track will be sent. This value should be determined by the user. G4ClassificationOfNewTrack has four possible values:

- furgent track is placed in the urgent stack
- fWaiting track is placed in the waiting stack, and will not be simulated until the urgent stack is empty
- fPostpone track is postponed to the next event
- fKill the track is deleted immediately and not stored in any stack.

These assignments may be made based on the origin of the track which is obtained as follows:

```
G4int parent_ID = aTrack->get_parentID();
```

#### where

- parent\_ID = 0 indicates a primary particle
- parent\_ID > 0 indicates a secondary particle
- parent\_ID < 0 indicates postponed particle from previous event.

NewStage() is invoked when the *urgent* stack is empty and the *waiting* stack contains at least one G4Track object. Here the user may kill or re-assign to different stacks all the tracks in the *waiting* stack by calling the stackManager->ReClassify() method which, in turn, calls the ClassifyNewTrack() method. If no user action is taken, all tracks in the *waiting* stack are transferred to the *urgent* stack. The user may also decide to abort the current event even though some tracks may remain in the *waiting* stack by calling stackManager->clear(). This method is valid and safe only if it is called from the G4UserStackingAction class. A global method of event abortion is

```
G4UImanager * UImanager = G4UImanager::GetUIpointer();
UImanager->ApplyCommand("/event/abort");
```

PrepareNewEvent () is invoked at the beginning of each event. At this point no primary particles have been converted to tracks, so the *urgent* and *waiting* stacks are empty. However, there may be tracks in the *postponed-to-next-event* stack; for each of these the ClassifyNewTrack() method is called and the track is assigned to the appropriate stack.

Listing 6.10: G4UserStackingAction

```
virtual void NewStage();
virtual void PrepareNewEvent();
};
```

### G4UserTrackingAction

Listing 6.11: G4UserTrackingAction

### G4UserSteppingAction

Listing 6.12: G4UserSteppingAction

};

## 6.3.2 Killing Tracks in User Actions and Energy Conservation

In either of user action classes described in the previous section, the user can implement an unnatural/unphysical action. A typical example is to kill a track, which is under the simulation, in the user stepping action. In this case the user have to be cautious of the total energy conservation. The user stepping action itself does not take care the energy or any physics quantity associated with the killed track. Therefore if the user want to keep the total energy of an event in this case, the lost track energy need to be recorded by the user.

The same is true for user stacking or tracking actions. If the user has killed a track in these actions the all physics information associated with it would be lost and, for example, the total energy conservation be broken.

If the user wants the GEANT4 kernel to take care the total energy conservation automatically when he/she has killed artificially a track, the user has to use a killer process. For example if the user uses G4UserLimits and G4UserSpecialCuts process, energy of the killed track is added to the total energy deposit.

# 6.4 User Information Classes

Additional user information can be associated with various GEANT4 classes. There are basically two ways for the user to do this:

- derive concrete classes from base classes used in GEANT4. These are classes for run, hit, digit, trajectory and trajectory point, which are discussed in *Optional User Actions* for G4Run, *Hits* for G4VHit, *Digitization* for G4VDigit, and *Tracking* for G4VTrajectory and G4VTrajectoryPoint
- create concrete classes from provided abstract base classes and associate them with classes used in GEANT4. GEANT4 classes which can accommodate user information classes are G4Event, G4Track, G4PrimaryVertex, G4PrimaryParticle and G4Region. These classes are discussed here.

### 6.4.1 G4VUserEventInformation

G4VUserEventInformation is an abstract class from which the user can derive his/her own concrete class for storing user information associated with a G4Event class object. It is the user's responsibility to construct a concrete class object and set the pointer to a proper G4Event object.

Within a concrete implementation of G4UserEventAction, the SetUserEventInformation() method of G4EventManager may be used to set a pointer of a concrete class object to G4Event, given that the G4Event object is available only by "pointer to const". Alternatively, the user may modify the GenerateEvent() method of his/her own RunManager to instantiate a G4VUserEventInformation object and set it to G4Event.

The concrete class object is deleted by the GEANT4 kernel when the associated G4Event object is deleted.

## 6.4.2 G4VUserTrackInformation

This is an abstract class from which the user can derive his/her own concrete class for storing user information associated with a G4Track class object. It is the user's responsibility to construct a concrete class object and set the pointer to the proper G4Track object.

Within a concrete implementation of G4UserTrackingAction, the SetUserTrackInformation() method of G4TrackingManager may be used to set a pointer of a concrete class object to G4Track, given that the G4Track object is available only by "pointer to const".

The ideal place to copy a G4VUserTrackInformation object from a mother track to its daughter tracks is G4UserTrackingAction::PostUserTrackingAction().

Listing 6.13: Copying G4VUserTrackInformation from mother to daughter tracks

```
void RE01TrackingAction::PostUserTrackingAction(const G4Track* aTrack)
{
   G4TrackVector* secondaries = fpTrackingManager->GimmeSecondaries();
   if(secondaries)
{
      RE01TrackInformation* info = (RE01TrackInformation*)(aTrack->GetUserInformation());
      size_t nSeco = secondaries->size();
   if(nSeco>0)
   {
      for(size_t i=0; i < nSeco; i++)
      {
            RE01TrackInformation* infoNew = new RE01TrackInformation(info);
            (*secondaries)[i]->SetUserInformation(infoNew);
      }
    }
   }
}
```

The concrete class object is deleted by the GEANT4 kernel when the associated G4Track object is deleted. In case the user wants to keep the information, it should be copied to a trajectory corresponding to the track.

# 6.4.3 G4VUserPrimaryVertexInformation and G4VUserPrimaryTrackInformation

These abstract classes allow the user to attach information regarding the generated primary vertex and primary particle. Concrete class objects derived from these classes should be attached to G4PrimaryVertex and G4PrimaryParticle class objects, respectively.

The concrete class objects are deleted by the GEANT4 kernel when the associated G4PrimaryVertex or G4PrimaryParticle class objects are deleted along with the deletion of G4Event.

# 6.4.4 G4VUserRegionInformation

This abstract base class allows the user to attach information associated with a region. For example, it would be quite beneficial to add some methods returning a Boolean flag to indicate the characteristics of the region (e.g. tracker, calorimeter, etc.). With this example, the user can easily and quickly identify the detector component.

Listing 6.14: A sample region information class

```
class RE01RegionInformation : public G4VUserRegionInformation
{
  public:
    RE01RegionInformation();
    (continues on next page)
```

```
~RE01RegionInformation();
void Print() const;

private:
    G4bool isWorld;
    G4bool isTracker;
    G4bool isCalorimeter;

public:
    inline void SetWorld(G4bool v=true) {isWorld = v;}
    inline void SetTracker(G4bool v=true) {isTracker = v;}
    inline void SetCalorimeter(G4bool v=true) {isCalorimeter = v;}
    inline G4bool IsWorld() const {return isWorld;}
    inline G4bool IsTracker() const {return isTracker;}
    inline G4bool IsCalorimeter() const {return isCalorimeter;}
};
```

The following code is an example of a stepping action. Here, a track is suspended when it enters the "calorimeter region" from the "tracker region".

Listing 6.15: Sample use of a region information class

```
void RE01SteppingAction::UserSteppingAction(const G4Step * theStep)
  // Suspend a track if it is entering into the calorimeter
  // check if it is alive
 G4Track * theTrack = theStep->GetTrack();
 if (theTrack->GetTrackStatus()!=fAlive) { return; }
 G4StepPoint * thePrePoint = theStep->GetPreStepPoint();
 G4LogicalVolume * thePreLV = thePrePoint->GetPhysicalVolume()->GetLogicalVolume();
  RE01RegionInformation* thePreRInfo
  = (RE01RegionInformation*)(thePreLV->GetRegion()->GetUserInformation());
 G4StepPoint * thePostPoint = theStep->GetPostStepPoint();
  G4LogicalVolume * thePostLV = thePostPoint->GetPhysicalVolume()->GetLogicalVolume();
  RE01RegionInformation* thePostRInfo
   = (RE01RegionInformation*)(thePostLV->GetRegion()->GetUserInformation());
  // check if it is entering to the calorimeter volume
   \textbf{if} (! (the PreRInfo-> IsCalorimeter()) \ \&\& \ (the PostRInfo-> IsCalorimeter())) \\
  { theTrack->SetTrackStatus(fSuspend); }
```

# 6.5 Multiple User Actions

Starting from GEANT4 Version 10.3 it is possible to attach multiple instances of the same type of user action to a single run manager. This is achieved via the use of a special proxy classes to which multiple child user actions are attached. This is allowed for run-, event-, tracking- and stepping-type user actions (G4UserRunAction, G4UserEventAction, G4UserTrackingAction, G4UserSteppingAction).

The kernel still sees a single user action of each type, the proxy will forward the calls from kernel to all the attached child user actions.

Listing 6.16: An example of the use of the use of multiple user-actions.

```
#include "G4MultiRunAction.hh"
#include "G4MultiEventAction.hh"

(continues on next page)
```

```
#include "G4MultiTrackingAction.hh"
#include "G4MultiSteppingAction.hh"
//...

void MyUserActionInitialization::Build()
{
    //...
    // Example with multiple-event action, similarly
    // for the other cases
    // multi- user actions extend std::vector
    auto multiAction = new G4MultiEventAction { new MyEventAction1, new MyEventAction2 };
    //...
    multiAction->push_back( new MyEventAction3 );
    SetUserAction( multiAction );
    //...
}
```

## 6.5.1 Exceptions

This functionality is not implemented for the stacking user action and primary generation action. There is no multiple G4UserStackingAction equivalent since this would require a complex handling of the case in which conflicting classifications are issued. For the case of G4VUserPrimaryGeneratorAction the use case of the multiple user actions is already addressed by the design of the class itself. User can implement one or more generators in the actions.

For the case of G4MultiRunAction only one of the child user actions can implement the G4UserRunAction::GenerateRun() method returning a non null, user derived G4Run object, otherwise an exception is thrown.

**CHAPTER** 

SEVEN

## CONTROL

## 7.1 Built-in Commands

GEANT4 has various built-in user interface commands, each of which corresponds roughly to a GEANT4 category. These commands can be used

- interactively via a (Graphical) User Interface (G)UI,
- in a macro file via /control/execute <command>,
- within C++ code with the ApplyCommand method of G4UImanager.

**Note:** The availability of individual commands, the ranges of parameters, the available candidates on individual command parameters vary according to the implementation of your application and may even vary dynamically during the execution of your job.

The following is a short summary of available commands. You can also see the all available commands by executing 'help' in your UI session.

• List of built-in commands

# 7.2 User Interface - Defining New Commands

# 7.2.1 G4Ulmessenger

G4UImessenger is a base class which represents a messenger that delivers command(s) to the destination class object. Concrete messengers are instantiated by, and owned by, the functional classes for which they provide a user interface; messengers should be deleted by those classes in their own destructors.

Your concrete messenger should have the following functionalities.

- Construct your command(s) in the constructor of your messenger.
- Destruct your command(s) in the destructor of your messenger.

These requirements mean that your messenger should keep all pointers to your command objects as its data members.

You can use G4UIcommand derived classes for the most frequent types of command. These derived classes have their own conversion methods according to their types, and they make implementation of the SetNewValue() and GetCurrentValue() methods of your messenger much easier and simpler.

G4UI command objects are owned by the messenger. If instantiated via *new*, they should be deleted in the messenger destructor.

For complicated commands which take various parameters, you can use the G4UIcommand base class, and construct G4UIparameter objects by yourself. You don't need to delete G4UIparameter object(s).

In the SetNewValue() and GetCurrentValue() methods of your messenger, you can compare the G4UIcommand pointer given in the argument of these methods with the pointer of your command, because your messenger keeps the pointers to the commands. Thus, you don't need to compare by command name. Please remember, in the cases where you use G4UIcommand derived classes, you should store the pointers with the types of these derived classes so that you can use methods defined in the derived classes according to their types without casting.

G4UImanager/G4UIcommand/G4UIparameter have very powerful type and range checking routines. You are strongly recommended to set the range of your parameters. For the case of a numerical value (int or double), the range can be given by a G4String using C++ notation, e.g., "X > 0 & X < 10". For the case of a string type parameter, you can set a candidate list. Please refer to the detailed descriptions below.

GetCurrentValue() will be invoked after the user's application of the corresponding command, and before the SetNewValue() invocation. This GetCurrentValue() method will be invoked only if

- at least one parameter of the command has a range
- at least one parameter of the command has a candidate list
- at least the value of one parameter is omitted and this parameter is defined as omittable and currentValueAsDefault

For the first two cases, you can re-set the range or the candidate list if you need to do so, but these "re-set" parameters are needed only for the case where the range or the candidate list varies dynamically.

A command can be "state sensitive", i.e., the command can be accepted only for a certain G4ApplicationState(s). For example, the /run/beamOn command should not be accepted when GEANT4 is processing another event ("G4State\_EventProc" state). You can set the states available for the command with the AvailableForStates() method.

#### 7.2.2 G4Ulcommand and its derived classes

#### Methods available for all derived classes

These are methods defined in the G4UIcommand base class which should be used from the derived classes.

- void SetGuidance(char\*)
  - Define a guidance line. You can invoke this method as many times as you need to give enough amount of guidance. Please note that the first line will be used as a title head of the command guidance.
- void availableForStates(G4ApplicationState s1,...)
  - If your command is valid only for certain states of the GEANT4 kernel, specify these states by this method. Currently available states are G4State\_PreInit, G4State\_Init, G4State\_Idle, G4State\_GeomClosed, and G4State\_EventProc. Refer to the as a state machine for meaning of each state. Please note that the Pause state had been removed from G4ApplicationState.
- void SetRange(char\* range)
  - Define a range of the parameter(s). Use C++ notation, e.g., "x > 0 && x < 10", with variable name(s) defined by the SetParameterName() method. For the case of a G4ThreeVector, you can set the relation between parameters, e.g., "x > y".

304 Chapter 7. Control

### **G4Uldirectory**

This is a G4UIcommand derived class for defining a directory containing commands. It is owned by, and should be deleted in the destructor of, the associated G4UImessenger class, after all of its contained commands have been deleted.

G4UIdirectory (char\* directoryPath)
 Constructor. Argument is the (full-path) directory, which must begin and terminate with "/:.

#### **G4UIcmdWithoutParameter**

This is a G4UI command derived class for a command which takes no parameter.

• G4UIcmdWithoutParameter(char\* commandPath, G4UImessenger\* theMessenger) Constructor. Arguments are the (full-path) command name and the pointer to your messenger.

#### **G4UIcmdWithABool**

This is a G4UI command derived class which takes one Boolean type parameter.

- G4UIcmdWithABool (char\* commandpath, G4UImanager\* theMessenger)
  Constructor. Arguments are the (full-path) command name and the pointer to your messenger.
- void SetParameterName(char\* paramName, G4bool omittable)

  Define the name of the Boolean parameter and set the omittable flag. If omittable is true, you should define the default value using the next method.
- void SetDefaultValue(G4bool defVal)
  - Define the default value of the Boolean parameter.
- G4bool GetNewBoolValue(G4String paramString)

  Convert G4String parameter value given by the SetNewValue() method of your messenger into Boolean.
- G4String convertToString(G4bool currVal)

  Convert the current Boolean value to G4String which should be returned by the GetCurrentValue() method of your messenger.

#### **G4UlcmdWithAnInteger**

This is a G4UI command derived class which takes one integer type parameter.

- G4UIcmdWithAnInteger(char\* commandpath, G4UImanager\* theMessenger) Constructor. Arguments are the (full-path) command name and the pointer to your messenger.
- void SetParameterName(char\* paramName, G4bool omittable)

  Define the name of the integer parameter and set the omittable flag. If omittable is true, you should define the default value using the next method.
- void SetDefaultValue(G4int defVal) Define the default value of the integer parameter.
- G4int GetNewIntValue (G4String paramString)
  - Convert G4String parameter value given by the SetNewValue () method of your messenger into integer.
- G4String convertToString(G4int currVal)

  Convert the current integer value to G4String, which should be returned by the GetCurrentValue() method of your messenger.

#### **G4UIcmdWithADouble**

This is a G4UI command derived class which takes one double type parameter.

- G4UIcmdWithADouble(char\* commandpath, G4UImanager\* theMessenger) Constructor. Arguments are the (full-path) command name and the pointer to your messenger.
- void SetParameterName(char\* paramName, G4bool omittable)

  Define the name of the double parameter and set the omittable flag. If omittable is true, you should define the default value using the next method.
- void SetDefaultValue(G4double defVal)
  - Define the default value of the double parameter.
- G4double GetNewDoubleValue(G4String paramString)

  Convert G4String parameter value given by the SetNewValue() method of your messenger into double.
- G4String convertToString(G4double currVal)

  Convert the current double value to G4String which should be returned by the GetCurrentValue() method of your messenger.

## **G4UlcmdWithAString**

This is a G4UI command derived class which takes one string type parameter.

- G4UIcmdWithAString(char\* commandpath, G4UImanager\* theMessenger) Constructor. Arguments are the (full-path) command name and the pointer to your messenger.
- void SetParameterName (char\* paramName, G4bool omittable)

  Define the name of the string parameter and set the omittable flag. If omittable is true, you should define the default value using the next method.
- void SetDefaultValue(char\* defVal)
  - Define the default value of the string parameter.
- void SetCandidates(char\* candidateList)

Define a candidate list which can be taken by the parameter. Each candidate listed in this list should be separated by a single space. If this candidate list is given, a string given by the user but which is not listed in this list will be rejected.

#### G4UlcmdWith3Vector

This is a G4UI command derived class which takes one three vector parameter.

- G4UIcmdWith3Vector(char\* commandpath, G4UImanager\* theMessenger) Constructor. Arguments are the (full-path) command name and the pointer to your messenger.
- void SetParameterName(char\* paramNamX, char\* paramNamY, char\* paramNamZ, G4bool omittable)
  - Define the names of each component of the three vector and set the omittable flag. If omittable is true, you should define the default value using the next method.
- void SetDefaultValue(G4ThreeVector defVal)
  - Define the default value of the three vector.
- G4ThreeVector GetNew3VectorValue(G4String paramString)

  Convert the G4String parameter value given by the SetNewValue() method of your messenger into a G4ThreeVector.
- G4String convertToString(G4ThreeVector currVal)

  Convert the current three vector to G4String, which should be returned by the GetCurrentValue() method of your messenger.

306 Chapter 7. Control

#### G4UlcmdWithADoubleAndUnit

This is a G4UI command derived class which takes one double type parameter and its unit.

- G4UIcmdWithADoubleAndUnit(char\* commandpath, G4UImanager\* theMessenger) Constructor. Arguments are the (full-path) command name and the pointer to your messenger.
- void SetParameterName(char\* paramName, G4bool omittable)

  Define the name of the double parameter and set the omittable flag. If omittable is true, you should define the default value using the next method.
- void SetDefaultValue(G4double defVal)
  - Define the default value of the double parameter.
- void SetUnitCategory(char\* unitCategory)
  - Define acceptable unit category.
- void SetDefaultUnit(char\* defUnit)
  - Define the default unit. Please use this method and the SetUnitCategory () method alternatively.
- G4double GetNewDoubleValue(G4String paramString)
- Convert G4String parameter value given by the SetNewValue() method of your messenger into double. Please note that the return value has already been multiplied by the value of the given unit.
- G4double GetNewDoubleRawValue(G4String paramString)
  - Convert G4String parameter value given by the SetNewValue() method of your messenger into double but without multiplying the value of the given unit.
- G4double GetNewUnitValue(G4String paramString)
  - Convert G4String unit value given by the SetNewValue() method of your messenger into double.
- G4String convertToString(G4bool currVal, char\* unitName)
  Convert the current double value to a G4String, which should be returned by the GetCurrentValue() method of your messenger. The double value will be divided by the value of the given unit and converted to a string. Given unit will be added to the string.

#### G4UlcmdWith3VectorAndUnit

This is a G4UI command derived class which takes one three vector parameter and its unit.

- G4UIcmdWith3VectorAndUnit(char\* commandpath, G4UImanager\* theMessenger)
  Constructor. Arguments are the (full-path) command name and the pointer to your messenger.
- void SetParameterName(char\* paramNamX, char\* paramNamY, char\* paramNamZ, G4bool omittable)
  - Define the names of each component of the three vector and set the omittable flag. If omittable is true, you should define the default value using the next method.
- void SetDefaultValue(G4ThreeVector defVal)
  - Define the default value of the three vector.
- void SetUnitCategory(char\* unitCategory)
  - Define acceptable unit category.
- void SetDefaultUnit(char\* defUnit)
  - Define the default unit. Please use this method and the SetUnitCategory () method alternatively.
- G4ThreeVector GetNew3VectorValue(G4String paramString)
  - Convert a G4String parameter value given by the SetNewValue() method of your messenger into a G4ThreeVector. Please note that the return value has already been multiplied by the value of the given unit.
- G4ThreeVector GetNew3VectorRawValue(G4String paramString)

  Convert a G4String parameter value given by the SetNewValue() method of your messenger into three vector, but without multiplying the value of the given unit.
- G4double GetNewUnitValue(G4String paramString)
  - Convert a G4String unit value given by the SetNewValue() method of your messenger into a double.
- G4String convertToString(G4ThreeVector currVal, char\* unitName)

Convert the current three vector to a G4String which should be returned by the GetCurrentValue() method of your messenger. The three vector value will be divided by the value of the given unit and converted to a string. Given unit will be added to the string.

#### Additional comments on the SetParameterName() method

You can add one additional argument of G4bool type for every SetParameterName () method mentioned above. This additional argument is named currentAsDefaultFlag and the default value of this argument is false. If you assign this extra argument as true, the default value of the parameter will be overridden by the current value of the target class.

## 7.2.3 An example messenger

This example is of G4ParticleGunMessenger, which is made by inheriting G4UIcommand.

Listing 7.1: An example of G4ParticleGunMessenger.hh.

```
#ifndef G4ParticleGunMessenger h
#define G4ParticleGunMessenger_h 1
class G4ParticleGun;
class G4ParticleTable;
class G4UIcommand;
class G4UIdirectory;
class G4UIcmdWithoutParameter;
class G4UIcmdWithAString;
class G4UIcmdWithADoubleAndUnit;
class G4UIcmdWith3Vector;
class G4UIcmdWith3VectorAndUnit;
#include "G4UImessenger.hh"
#include "globals.hh"
class G4ParticleGunMessenger: public G4UImessenger
    G4ParticleGunMessenger(G4ParticleGun * fPtclGun);
    ~G4ParticleGunMessenger();
  public:
    void SetNewValue(G4UIcommand * command, G4String newValues);
    G4String GetCurrentValue (G4UIcommand * command);
  private:
    G4ParticleGun * fParticleGun;
    G4ParticleTable * particleTable;
  private: //commands
    G4UIdirectory * gunDirectory;
G4UIcmdWithoutParameter * listCmd;
    G4UIcmdWithAString * particleCmd;
G4UIcmdWith3Vector * directionCmd
                                 directionCmd:
    G4UIcmdWithADoubleAndUnit * energyCmd;
    G4UIcmdWith3VectorAndUnit * positionCmd;
    G4UIcmdWithADoubleAndUnit * timeCmd;
};
#endif
```

308 Chapter 7. Control

Listing 7.2: An example of G4ParticleGunMessenger.cc.

```
#include "G4ParticleGunMessenger.hh"
#include "G4ParticleGun.hh"
#include "G4Geantino.hh"
#include "G4ThreeVector.hh"
#include "G4ParticleTable.hh"
#include "G4UIdirectory.hh"
#include "G4UIcmdWithoutParameter.hh"
#include "G4UIcmdWithAString.hh"
#include "G4UIcmdWithADoubleAndUnit.hh"
#include "G4UIcmdWith3Vector.hh"
#include "G4UIcmdWith3VectorAndUnit.hh"
#include <iostream.h>
G4ParticleGunMessenger::G4ParticleGunMessenger(G4ParticleGun * fPtclGun)
:fParticleGun(fPtclGun)
 particleTable = G4ParticleTable::GetParticleTable();
  gunDirectory = new G4UIdirectory("/gun/");
  gunDirectory->SetGuidance("Particle Gun control commands.");
  listCmd = new G4UIcmdWithoutParameter("/gun/list",this);
  listCmd->SetGuidance("List available particles.");
  listCmd->SetGuidance(" Invoke G4ParticleTable.");
 particleCmd = new G4UIcmdWithAString("/gun/particle",this);
 particleCmd->SetGuidance("Set particle to be generated.");
  particleCmd->SetGuidance(" (geantino is default)");
  particleCmd->SetParameterName("particleName", true);
  particleCmd->SetDefaultValue("geantino");
 G4String candidateList;
  G4int nPtcl = particleTable->entries();
  for (G4int i=0;i<nPtcl;i++)</pre>
    candidateList += particleTable->GetParticleName(i);
    candidateList += " ";
  particleCmd->SetCandidates (candidateList);
 directionCmd = new G4UIcmdWith3Vector("/gun/direction", this);
 directionCmd->SetGuidance("Set momentum direction.");
  directionCmd->SetGuidance("Direction needs not to be a unit vector.");
  directionCmd->SetParameterName("Px", "Py", "Pz", true, true);
  directionCmd->SetRange("Px != 0 || Py != 0 || Pz != 0");
 energyCmd = new G4UIcmdWithADoubleAndUnit("/gun/energy",this);
  energyCmd->SetGuidance("Set kinetic energy.");
  energyCmd->SetParameterName("Energy", true, true);
  energyCmd->SetDefaultUnit("GeV");
  energyCmd->SetUnitCandidates("eV keV MeV GeV TeV");
 positionCmd = new G4UIcmdWith3VectorAndUnit("/gun/position",this);
  positionCmd->SetGuidance("Set starting position of the particle.");
  positionCmd->SetParameterName("X", "Y", "Z", true, true);
 positionCmd->SetDefaultUnit("cm");
 positionCmd->SetUnitCandidates("micron mm cm m km");
  timeCmd = new G4UIcmdWithADoubleAndUnit("/gun/time",this);
  timeCmd->SetGuidance("Set initial time of the particle.");
  timeCmd->SetParameterName("t0", true, true);
  timeCmd->SetDefaultUnit("ns");
  timeCmd->SetUnitCandidates("ns ms s");
  // Set initial value to G4ParticleGun
```

```
fParticleGun->SetParticleDefinition( G4Geantino::Geantino() );
fParticleGun->SetParticleMomentumDirection( G4ThreeVector(1.0,0.0,0.0) );
fParticleGun->SetParticleEnergy( 1.0*GeV );
fParticleGun->SetParticlePosition(G4ThreeVector(0.0*cm, 0.0*cm, 0.0*cm));
fParticleGun->SetParticleTime( 0.0*ns );
}
```

```
G4ParticleGunMessenger::~G4ParticleGunMessenger()
  delete listCmd;
  delete particleCmd;
  delete directionCmd;
  delete energyCmd;
  delete positionCmd;
  delete timeCmd;
  delete gunDirectory;
void G4ParticleGunMessenger::SetNewValue(
  G4UIcommand * command, G4String newValues)
  if( command==listCmd )
  { particleTable->dumpTable(); }
  else if( command==particleCmd )
    G4ParticleDefinition* pd = particleTable->findParticle(newValues);
    if(pd != NULL)
    { fParticleGun->SetParticleDefinition( pd ); }
  else if( command==directionCmd )
  { fParticleGun->SetParticleMomentumDirection(directionCmd->
    GetNew3VectorValue(newValues)); }
  else if( command==energyCmd )
  { fParticleGun->SetParticleEnergy(energyCmd->
     GetNewDoubleValue(newValues)); }
  else if( command==positionCmd )
  { fParticleGun->SetParticlePosition(
     directionCmd->GetNew3VectorValue(newValues)); }
  else if( command==timeCmd )
  { fParticleGun->SetParticleTime(timeCmd->
     GetNewDoubleValue(newValues)); }
\texttt{G4String} \ \ \texttt{G4ParticleGunMessenger::GetCurrentValue} \ (\texttt{G4UIcommand} \ \star \ \texttt{command})
  G4String cv;
  if( command==directionCmd )
  { cv = directionCmd->ConvertToString(
     fParticleGun->GetParticleMomentumDirection()); }
  else if( command==energyCmd )
  { cv = energyCmd->ConvertToString(
     fParticleGun->GetParticleEnergy(), "GeV"); }
  else if( command==positionCmd )
  { cv = positionCmd->ConvertToString(
     fParticleGun->GetParticlePosition(), "cm"); }
  else if( command==timeCmd )
  { cv = timeCmd->ConvertToString(
     fParticleGun->GetParticleTime(), "ns"); }
  else if( command==particleCmd )
  { // update candidate list
    G4String candidateList;
    G4int nPtcl = particleTable->entries();
    for (G4int i=0;i<nPtcl;i++)</pre>
```

```
candidateList += particleTable->GetParticleName(i);
  candidateList += " ";
}
particleCmd->SetCandidates(candidateList);
}
return cv;
}
```

## 7.2.4 How to control the output of G4cout/G4cerr

Instead of *std::cout* and *std::cerr*, GEANT4 uses G4cout and G4cerr. Output streams from G4cout/G4cerr are handled by G4UImanager which allows the application programmer to control the flow of the stream. Output strings may therefore be displayed on another window or stored in a file. This is accomplished as follows:

1. Derive a class from G4UIsession and implement the two methods:

```
G4int ReceiveG4cout(const G4String& coutString);
G4int ReceiveG4cerr(const G4String& cerrString);
```

These methods receive the string stream of G4cout and G4cerr, respectively. The string can be handled to meet specific requirements. The following sample code shows how to make a log file of the output stream:

```
ostream logFile;
logFile.open("MyLogFile");
G4int MySession::ReceiveG4cout(const G4String& coutString)
{
  logFile << coutString << flush;
  return 0;
}
```

2. Set the destination of G4cout/G4cerr using G4UImanager::SetCoutDestination(session). Typically this method is invoked from the constructor of G4UIsession and its derived classes, such as G4UIGAG/G4UIteminal. This method sets the destination of G4cout/G4cerr to the session. For example, when the following code appears in the constructor of G4UIterminal, the method SetCoutDestination(this) tells UImanager that this instance of G4UIterminal receives the stream generated by G4cout.

```
G4UIterminal::G4UIterminal()
{
  UI = G4UImanager::GetUIpointer();
  UI->SetCoutDestination(this);
  // ...
}
```

Similarly, UI->SetCoutDestination (NULL) must be added to the destructor of the class.

3. Write or modify the main program. To modify exampleB1 to produce a log file, derive a class as described in step 1 above, and add the following lines to the main program:

```
#include "MySession.hh"
main()
{
    // get the pointer to the User Interface manager
    G4UImanager* UI = G4UImanager::GetUIpointer();
    // construct a session which receives G4cout/G4cerr
    MySession * LoggedSession = new MySession;
    UI->SetCoutDestination(LoggedSession);
    // session->SessionStart(); // not required in this case
    // ... do simulation here ...
    delete LoggedSession;
```

```
return 0;
}
```

**Note:** G4cout/G4cerr should not be used in the constructor of a class if the instance of the class is intended to be used as static. This restriction comes from the language specification of C++. See the documents below for details:

- M.A.Ellis, B.Stroustrup, "Annotated C++ Reference Manual", Section 3.4 [Ellis1990]
- P.J.Plauger, "The Draft Standard C++ Library" [Plauger1995]

312 Chapter 7. Control

## **EIGHT**

## VISUALIZATION

## 8.1 Introduction to Visualization

The GEANT4 visualization system was developed in response to a diverse set of requirements:

- 1. Quick response to study geometries, trajectories and hits
- 2. High-quality output for publications
- 3. Flexible camera control to debug complex geometries
- 4. Tools to show volume overlap errors in detector geometries
- 5. Interactive picking to get more information on visualized objects

No one graphics system is ideal for all of these requirements, and many of the large software frameworks into which GEANT4 has been incorporated already have their own visualization systems, so GEANT4 visualization was designed around an abstract interface that supports a diverse family of graphics systems. Some of these graphics systems use a graphics library compiled with GEANT4, such as OpenGL, Qt, while others involve a separate application, such as HepRApp or DAWN.

Most examples include a vis.mac to perform typical visualization for that example. The macro includes optional code which you can uncomment to activate additional visualization features.

#### 8.1.1 What Can be Visualized

Simulation data can be visualized:

- Detector components
  - A hierarchical structure of physical volumes
  - A piece of physical volume, logical volume, and solid
- Particle trajectories and tracking steps
- Hits of particles in detector components
- · Scoring data
- Plots

Other user defined objects can be visualized:

- Polylines, such as coordinate axes
- 3D Markers, such as eye guides
- Text, descriptive character strings, comments or titles
- Scales
- Logos

### 8.1.2 You have a Choice of Visualization Drivers

The many graphics systems that GEANT4 supports are complementary to each other.

- OpenGL
  - View directly from GEANT4
  - Requires addition of GL libraries that are freely available for all operating systems (and pre-installed on many)
  - Rendered, photorealistic image with some interactive features
  - zoom, rotate, translate
  - Fast response (can usually exploit full potential of graphics hardware)
  - Print to EPS (vector and pixel graphics)

#### • Ot

- View directly from GEANT4
- Requires addition of Qt and GL libraries that are freely available on most operating systems
- Rendered, photorealistic image
- Many interactive features
- zoom, rotate, translate
- Fast response (can usually exploit full potential of graphics hardware)
- Expanded printing ability (vector and pixel graphics)
- Easy interface to make movies

### · Open Inventor

- View directly from GEANT4
- Requires addition of Coin3d libraries (freely available for most Linux systems).
- Rendered, photorealistic image
- Many interactive features
- zoom, rotate, translate
- click to "see inside" opaque volumes
- Fast response (can usually exploit full potential of graphics hardware)
- Expanded printing ability: vector graphics (with transparency in PDF) and pixel graphics

## • Qt3D

- View directly from GEANT4
- Requires addition of Qt libraries that are freely available on most operating systems
- Rendered, photorealistic image
- Many interactive features
- zoom, rotate, translate
- Fast response (can usually exploit full potential of graphics hardware)

#### • TSG

- View directly from GEANT4
- Based on the ToolsSG library distributed with Geant4.
- Rendered, photorealistic image
- Many interactive features
- zoom, rotate, translate
- Fast response (can usually exploit full potential of graphics hardware)
- Can also view plots of histograms, etc., accumulated in your application

## • Vtk

- View directly from GEANT4
- Requires installation of Vtk (vtk.org)
- Rendered, photorealistic image
- Many interactive features
- zoom, rotate, translate
- Fast response (can usually exploit full potential of graphics hardware)

### • HepRepFile

Create a file to view in a HepRep browser such as HepRApp or FRED

- Requires a HepRep browser (above options work on any operating system)
- Wireframe or simple area fills (not photorealistic)
- Many interactive features
- zoom, rotate, translate
- click to show attributes (momentum, etc.)
- special projections (FishEye, etc.)
- control visibility from hierarchical (tree) view of data
- Hierarchical view of the geometry
- Export to many vector graphic formats (PostScript, PDF, etc.)

#### • DAWN

- Create a file to view in the DAWN Renderer
- Requires DAWN, available for all Linux and Windows systems
- Rendered, photorealistic image
- No interactive features
- Highest quality technical rendering output to vector PostScript

#### • VRML

- Create a file with VRML2FILE to view in any VRML browser (many different choices for different browsers and operating systems).
- Rendered, photorealistic image with some interactive features
- zoom, rotate, translate
- Limited printing ability (pixel graphics, not vector graphics)

#### RayTracer

- Create a jpeg file
- Forms image by using GEANT4's own tracking to follow photons through the detector
- Can show geometry but not trajectories
- Can render any geometry that GEANT4 can handle (such as Boolean solids)
- Supports shadows, transparency and mirrored surfaces

## • gMocren

- Create a gMocren file suitable for viewing in the gMocren volume data visualization application
- Represents three dimensional volume data such as radiation therapy dose
- Can also include geometry and trajectory information

#### ASCIITree

- Text dump of the geometry hierarchy
- Not graphical
- Control over level of detail to be dumped
- Can calculate mass and volume of any hierarchy of volumes

## 8.1.3 Choose the Driver that Meets Your Needs

- If you want very responsive photorealistic graphics (and have the OpenGL libraries installed)
  - OpenGL is a good solution (if you have the Motif extensions, this also gives GUI control)
- · If you want to have the User Interface and all Visualization windows in the same window
  - Only Qt can do that
- If you want very responsive photorealistic graphics plus more interactivity (and have the OpenInventor or Qt libraries installed)
  - OpenInventor with or without Qt are good solutions
  - Qt3D, TSG and Vtk are also candidates
- If you want GUI control, very responsive photorealistic graphics plus more interactivity (and have the Qt libraries installed).
  - Qt is a good solution
- If you want GUI control, want to be able to pick on items to inquire about them (identity, momentum, etc.), perhaps want to render to vector formats, and a wireframe look will do
  - HepRepFile will meet your needs

- If you want to render highest quality photorealistic images for use in a poster or a technical design report, and you can live without quick rotate and zoom
  - DAWN is the way to go
- If you want to render to a 3D format that others can view in a variety of commodity browsers (including some web browser plug-ins)
  - VRML is the way to go
- If you want to visualize a geometry that the other visualization drivers can't handle, or you need transparency or mirrors, and you don't need to visualize trajectories
  - RayTracer will do it
- If you want to visualization volume data, such as radiation therapy dose distributions
  - gMocren will meet your needs
- If you just want to quickly check the geometry hierarchy, or if you want to calculate the volume or mass of any geometry hierarchy
  - ASCIITree will meet your needs
- You can also add your own visualization driver.
  - GEANT4's visualization system is modular. By creating just three new classes, you can direct GEANT4 information to your own visualization system.

## 8.1.4 Controlling Visualization

Your GEANT4 code stays basically the same no matter which driver you use.

Visualization is performed either with commands or from C++ code.

- Some visualization drivers work directly from GEANT4
  - OpenGL
  - Ot
  - Qt3D
  - Vtk
  - TSG
  - OpenInventor
  - RayTracer
  - ASCIITree
- For other visualization drivers, you first have GEANT4 produce a file, and then you have that file rendered by another application (which may have GUI control)
  - HepRepFile
  - DAWN
  - VRML2FILE
  - gMocren

## 8.1.5 Visualization Details

The following sections of this guide cover the details of GEANT4 visualization:

- Adding Visualization to Your Executable
- The Visualization Drivers
- Controlling Visualization from Commands
- Controlling Visualization from Compiled Code
- Visualization Attributes
- · Enhanced Trajectory Drawing
- · Polylines, Markers and Text
- · Making a Movie

Other useful references for GEANT4 visualization outside of this user guide:

• Macro files vis.mac distributed in GEANT4 source in basic examples.

# 8.2 Adding Visualization to Your Executable

This section explains how to incorporate your selected visualization drivers into the main () function and create an executable for it. In order to perform visualization with your GEANT4 executable, you must compile it with support for the required visualization driver(s). You may be dazzled by the number of choices of visualization driver, but you need not use all of them at one time.

## 8.2.1 Installing Visualization Drivers

Depending on what has been installed on your system and how the Geant4 install you are using was configured, several kinds of visualization driver are available. One or many drivers may be chosen for realization in compilation, depending on your visualization requirements. Features and notes on each driver are briefly described in *The Visualization Drivers*, along with links to detailed web pages for the various drivers.

Note that not all drivers can be installed on all systems; Table 8.1 in *The Visualization Drivers* lists all the available drivers and the platforms on which they can be installed. For any of the visualization drivers to work, the corresponding graphics system must be installed beforehand.

Visualization drivers that do not depend on external libraries are by default incorporated into GEANT4 libraries during their installation. Here "installation of GEANT4 libraries" means the generation of GEANT4 libraries by compilation. The automatically incorporated visualization drivers are: DAWNFILE, HepRepFile, HepRepXML, RayTracer, VRML2FILE and ATree and GAGTree.

The OpenGL, Qt, OpenInventor, Qt3D, TSG, Vtk and RayTracerX drivers are not incorporated by default. These drivers must be selected when you build the GEANT4 Toolkit itself. This procedure is described in detail in the Installation Guide, to which you should refer.

## 8.2.2 How to Realize Visualization Drivers in an Executable

You can realize and use any of the visualization driver(s) you want in your GEANT4 executable, provided they are among the set installed beforehand into the GEANT4 libraries. A warning will appear if this is not the case.

In order to realize visualization drivers, you must instantiate and initialize a subclass of G4VisManager that implements the pure virtual function RegisterGraphicsSystems(). This subclass must be compiled in the user's domain to force the loading of appropriate libraries in the right order. The easiest way to do this is to use G4VisExecutive.

## 8.2.3 If you do wish to write your own subclass...

...you may do so. You will see how to do this by looking at G4VisExecutive.icc. A typical extract is:

```
RegisterGraphicsSystem (new G4DAWNFILE);
...
#ifdef G4VIS_USE_OPENGLX
RegisterGraphicsSystem (new G4OpenGLImmediateX);
RegisterGraphicsSystem (new G4OpenGLStoredX);
#endif
...
```

If you wish to use G4VisExecutive but register an additional graphics system, XXX say, you may do so either before or after initializing:

```
visManager->RegisterGraphicsSystem(new XXX);
visManager->Initialize();
```

and add the library name to your CMakeLists.txt file:

```
target_link_libraries(exampleB1 G4visXXX ${Geant4_LIBRARIES})
```

## 8.2.4 By default...

... you get the DAWNFILE, HepRepFile, RayTracer, VRML2FILE and ATree drivers.

## 8.2.5 Optionally...

... you may install the OpenGL-Xlib, OpenGL-Motif, Qt, OpenInventor, Qt3D, TSG, Vtk and RayTracerX drivers, each of which can be enabled when configuring your application through CMake options - see Installation Guide.

For more details, see *The Visualization Drivers* and pages linked from there.

## 8.2.6 Visualization Manager

Visualization procedures are controlled by the "Visualization Manager", a class which must inherit from G4VisManager defined in the visualization category. Most users will find that they can just use the default visualization manager, G4VisExecutive. The Visualization Manager accepts users' requests for visualization, processes them, and passes the processed requirements to the abstract interface, i.e., to the currently selected visualization driver.

## 8.2.7 How to Write the main () Function

In order for your GEANT4 executable to perform visualization, you must instantiate and initialize "your" Visualization Manager in the main() function. The core of the Visualization Manager is the class G4VisManager, defined in the visualization category. This class requires that one pure virtual function be implemented, namely, void RegisterGraphicsSystems(). The easiest way to do this is to use G4VisExecutive, as described in Listing 8.1.

Listing 8.1: The form of the main () function.

```
//---- C++ source codes: Instantiation and initialization of G4VisManager
....
// Your Visualization Manager
#include "G4VisExecutive.hh"
....
// Instantiation and initialization of the Visualization Manager
G4VisManager* visManager = new G4VisExecutive;
// G4VisExecutive can take a verbosity argument - see /vis/verbose guidance.
// G4VisManager* visManager = new G4VisExecutive("Quiet");
visManager->Initialize();
....
delete visManager;
//---- end of C++
```

Do not forget to delete the instantiated Visualization Manager.

Listing 8.2 shows a complete main () function (but see the examples distributed with GEANT4 for more ideas).

Listing 8.2: A main () function with interaction and visualization.

```
#include "G4VisExecutive.hh"
#include "G4UIExecutive.hh"
.....
int main(int argc, char** argv)
{
   auto ui = new G4UIExecutive(argc, argv);

   auto* runManager = G4RunManagerFactory::CreateRunManager();

   runManager->SetUserInitialization(new DetectorConstruction);
   auto physicsList = new QBBC;
   runManager->SetUserInitialization(physicsList);
   runManager->SetUserInitialization(new ActionInitialization);

auto visManager = new G4VisExecutive;
   visManager->Initialize();

   ui->SessionStart();

   delete visManager;
   delete runManager;
   delete ui;
}
```

The visualization manager prints useful information depending on the verbosity level:

For example, in your main () function, write:

```
G4VisManager* visManager = new G4VisExecutive("Quiet");
```

or change with the /vis/verbose command.

## 8.3 The Visualization Drivers

As explained in the Introduction to Visualization, GEANT4 provides many different choices of visualization systems. Features and notes on each driver are briefly described here along with links to detailed web pages for the various drivers.

Details are given below for:

- OpenGL
- Ot
- Open Inventor
- Open Inventor Extended Viewer
- Open Inventor Qt Viewer
- Qt3D
- ToolsSG
- Vtk

- HepRepFile
- DAWN
- VRML
- RayTracer
- gMocren
- ASCIITree

## 8.3.1 Availability of drivers on the supported systems

Table 8.1 lists required graphics systems and supported platforms for the various visualization drivers. Please refer to the Installation Guide for details of how to build Geant4 with support for these drivers, and *Use of Geant4Config.cmake with find\_package in CMake* for details on how to configure applications to use them.

Table 8.1: Required graphics systems and supported platforms for the various visualization drivers.

Driver	Required Graphics System	Platform
OpenGL-Xlib	OpenGL	Linux, UNIX, Mac with Xlib
OpenGL-Motif	OpenGL	Linux, UNIX, Mac with Motif
OpenGL-Win32	OpenGL	Windows
Qt	Qt, OpenGL	Linux, UNIX, Mac, Windows
OpenInventor-Qt	Open Inventor (Coin3D), Qt, OpenGL	Linux, UNIX, Mac
OpenInventor-X	Open Inventor (Coin3D), OpenGL	Linux, UNIX, Mac with Xlib and Motif
OpenInventor-X-Extended	Open Inventor (Coin3D), OpenGL	Linux, UNIX, Mac with Xlib and Motif
OpenInventor-Win32	Open Inventor, OpenGL	Windows
Qt3D	Qt	Linux, UNIX, Mac, Windows
ToolsSG	Native, OpenGl-ES or Qt	Linux, UNIX, Mac, Windows
Vtk	Vtk (vtk.org)	Linux, UNIX, Mac
VRML2FILE	Most internet browsers	Linux, UNIX, Mac, Windows
HepRepFile	HepRApp or FRED	Linux, UNIX, Mac, Windows
DAWNFILE	Fukui Renderer DAWN	Linux, UNIX, Mac, Windows
VRML2FILE	any VRML viewer	Linux, UNIX, Mac, Windows
RayTracer	any JPEG viewer	Linux, UNIX, Mac, Windows
RayTracerX	X11 (also produces a jpeg file)	Linux, UNIX, Mac.
ASCIITree	None	Linux, UNIX, Mac, Windows

## 8.3.2 OpenGL

These drivers have been developed by John Allison and Andrew Walkden (University of Manchester). It is an interface to the de facto standard 3D graphics library, OpenGL. It is well suited for real-time fast visualization and demonstration. Fast visualization is realized with hardware acceleration, reuse of shapes stored in a display list, etc. NURBS visualization is also supported.

Several versions of the OpenGL drivers are prepared. Versions for Xlib, Motif, Qt and Win32 platforms are available by default. For each version, there are two modes: immediate mode and stored mode. The former has no limitation on data size, and the latter is fast for visualizing large data repetitively, and so is suitable for animation.

Images can be exported using /vis/ogl/export.

More information can be found here: How to save a view to an image file

If you want to open a OGL viewer, the generic way is:

```
/vis/open OGL
```

According to your G4VIS\_USE... variables it will open the correct viewer. By default, it will be open in stored mode. You can specify to open an "OGLS" or "OGLI" viewer, or even "OGLSXm","OGLIXm",... If you don't have Motif or Qt, all control is done from GEANT4 commands:

```
/vis/open OGLIX
/vis/viewer/set/viewpointThetaPhi 70 20
/vis/viewer/zoom 2
etc.
```

But if you have Motif libraries or Qt install, you can control GEANT4 from Motif widgets or mouse with Qt:

```
/vis/open OGLSQt
```

The OpenGL driver added Smooth shading and Transparency since GEANT4 release 8.0.

## Further information (OpenGL and Mesa):

- https://www.opengl.org/
- https://www.mesa3d.org

## 8.3.3 Qt

This driver has been developed by Laurent Garnier (IN2P3, LAL Orsay). It is an interface to the powerful application framework, Qt, now free on most platforms. This driver also requires the OpenGL library.

The Qt driver is well suited for real-time fast visualization and demonstration. Fast visualization is realized with hardware acceleration, reuse of shapes stored in a display list, etc. NURBS visualization is also supported. All OpenGL features are implemented in the Qt driver, but one also gets mouse control of rotation/translation/zoom, the ability to save your scene in many formats (both vector and pixel graphics) and an easy interface for making movies.

Two display modes are available: Immediate mode and Stored mode. The former has no limitation on data size, and the latter is fast for visualizing large data repetitively, and so is suitable for animation.

This driver has the feature to open a vis window into the UI window as a new tab. You can have as many tabs you want and mix them from Stored or Immediate mode. To see the visualization window in the UI:

```
/vis/open OGL (Generic way. For Stored mode if you have define your G4VIS_USE_QT variable)
or
/vis/open OGLI (for Immediate mode)
or
/vis/open OGLS (for Stored mode)
or
/vis/open OGLIQt (for Immediate mode)
or
/vis/open OGLIQt (for Stored mode)
```

#### **Further information (Qt):**

- Qt
- |Geant4| Visualization Tutorial using the Qt Driver

## 8.3.4 Open Inventor

The original drivers were developed by Jeff Kallenbach (FNAL) and Guy Barrand (IN2P3) based on the Hepvis class library originated by Joe Boudreau (Pittsburgh University). The Open Inventor drivers and the Hepvis class library are based on the well-established Open Inventor technology for scientific visualization. They have high extendibility. They support high interactivity, e.g., attribute editing of picked objects. Some Open Inventor viewers support "stereoscopic" effects.

It is also possible to save a visualized 3D scene as an OpenInventor-formatted file, and re-visualize the scene afterwards.

Because it is connected directly to the GEANT4 kernel, using same language as that kernel (C++), OpenInventor systems can have direct access to GEANT4 data (geometry, trajectories, etc.).

Because Open Inventor uses OpenGL for rendering, it supports lighting and transparency.

Open Inventor provides thumbwheel control to rotate and zoom.

Open Inventor supports picking to ask about data. [Control Clicking] on a volume turns on rendering of that volume's daughters. [Shift Clicking] a daughter turns that rendering off: If modeling opaque solid, effect is like opening a box to look inside.

## Further information (HEPVis and OpenScientist):

- GEANT4 Inventor Visualization with OpenScientist
- Overall OpenScientist Home

## **Further information (OpenInventor):**

- Josie Wernecke, "The Inventor Mentor", Addison Wesley (ISBN 0-201-62495-8)
- Josie Wernecke, "The Inventor Toolmaker", Addison Wesley (ISBN 0-201-62493-1)
- "The Open Inventor C++ Reference Manual", Addison Wesley (ISBN 0-201-62491-5)

## 8.3.5 Open Inventor Extended Viewer

This driver was developed by Rastislav Ondrasek, Pierre-Luc Gagnon and Frederick Jones (TRIUMF). It extends the functionality of the OpenInventor driver, described in the previous section, by adding a number of new features to the viewer.

Although this viewer is still available it has been superseded by the Open Inventor Qt Viewer (see below).

## 8.3.6 Open Inventor Qt Viewer

This driver was developed by Frederick Jones (TRIUMF) and is based in part on the Extended Viewer driver. It is supported on Linux/Unix/MacOS platforms and requires Qt5 and Coin3D libraries (Coin and SoQt) to be installed. When resources become available a Windows version of the driver will be pursued.

This is the preferred Open Inventor viewer and will potentially replace the older viewers described above. It incorporates all of their capabilities together with many added functions implemented via menu bar items, viewer buttons, a navigation panel, and keyboard and mouse inputs.

## Reference path navigation

Most of the added features are concerned with navigation along a "reference path" which is a piecewise linear path through the geometry. The reference path can be any particle trajectory, which may be chosen at run time by selecting a trajectory with the mouse. Via Load and Save menu items in the File menu, a reference path can also be read from a file and the current reference path can be written to a file.

Once a reference path is established, the bottom part of the navigation panel is populated with a list of all elements in the geometry, ordered by their "distance" along the reference path (based on the perpendicular from the element center to the path).

## **Navigation controls**

[L,R,U,D refer to the arrow keys on the keyboard]

- Select an element from the list: navigate along the path to the element's "location" (distance along the reference path).
- Shift-L and Shift-R: navigate to the previous or next element on the path (with wraparound).
- L and R: rotate 90 degrees around the perpendicular to the reference path
- U and D: rotate 90 degrees around the reference path
- Ctrl-L and Ctrl-R: rotate 90 degrees around the horizontal axis

All these keys have a "repeat" function for continuous motion.

The rotation keys put the camera in a definite orientation, whereas The Shift-L and Shift-R keys can be used to "fly" along the path in whatever camera orientation is in effect. NOTE: if this appears to be "stuck", try switching from orthonormal camera to perspective camera ("cube" viewer button).

#### Menu Items:

- Tools / Go to start of reference path: useful if you get lost
- Tools / Invert reference path: flips the direction of travel and the distance readout

#### Reference path animation

This is a special mode which flies the camera steadily along the path, without wraparound. The controls are:

- Tools Menu Fly along Ref Path: start animation mode
- Page-Up: increase speed
- Page-Down: decrease speed
- U (arrow key): raise camera
- D (arrow key): lower camera
- ESC: exit animation mode

For suitable geometries the U and D keys can be used to get "Star Wars" style fly-over and fly-under effects.

#### **Bookmarks**

At any time, the viewpoint and other camera parameters can be saved in a file as a labelled "bookmark". The view can then be restored later in the current run or in another run. Bookmarks are displayed in a list in the top part of the navigation panel.

The default name for the bookmark file is "bookmarkFile". The first time a viewpoint is saved, this file will be created if it does not already exist. When the viewer is first opened, it will automatically read this file if present and load the viewpoints into the left-hand panel of the viewer's auxiliary window.

#### Controls:

- · Select bookmark from list: restore this view
- Right-arrow VIEWER button: go to next bookmark
- Left-arrow VIEWER button: go to next bookmark
- "Floppy Disk" button: bookmark the current view. The user can type in a label for the bookmark, or use the default label provided.
- File Menu Open Bookmark File: loads an existing bookmark file
- File Menu New Bookmark File: creates a new bookmark file for saving subsequent views

## Special picking modes

#### Controls:

- "Arrow +" VIEWER button: enable brief trajectory picking and mouse-over element readout For trajectories, the list of all trajectory points is replaced by the first and last point only, allowing easier identification of the particle without scrolling back. Passing the mouse over an element will give a readout of the volume name, material, and position on the reference path.
- "Crosshair" VIEWER button: select new reference path The cursor will change to a small cross (+) after which a trajectory can be selected to become the new reference path.

#### Convenience feature

When using the Open Inventor viewer with a terminal-based UI (e.g. tcsh) it is now possible to escape from the viewer without using the mouse.

In addition to the File - Escape menu item, pressing the "e" key on the keyboard will exit from the viewer's secondary event loop. The viewer will become inactive and control will return to the GEANT4 UI prompt.

## 8.3.7 Qt3D

As of writing for Release 11.0, Qt3D is an "experimental" driver exploiting a recently announced feature of Qt. Qt3D looks like Qt's attempt to get into visualisation as well as user interface. All the same, Qt programming is tough, so please bear with us. Please try it and give us feedback.

It has been developed so far by John Allison. The advantage, as we see it, is that it programs directly over Qt, which is then free to exploit the local system to its advantage. For example, on MacOS, it will in future (they say) build directly on Metal, making us independent of OpenGL (which Apple are deprecating). It is a way of future-proofing Geant4.

If you build with Qt, this driver will be instantiated automatically.

## 8.3.8 ToolsSG

Developed by Guy Barrand, this driver is based on his ToolsSG package distributed with Geant4 (which also supports the Geant4 analysis system). It offers the same features as the OpenGL drivers and comes with options over X11, Windows or Qt (depending on your CMake selections during Geant4 build - see Installation Guide). It has the ability to exploit local graphics systems so that, like Qt3D, it offers future-proofing for Geant4 visualisation.

It also supports plotting. If you have registered histograms with the Geant4 analysis manager, they will be available for plotting at end of run. Example B5 illustrates how to do this.

These drivers use the scene graph logic found in the classes under:

source/externals/g4tools/include/tools/sg

(sg being for "scene graph").

These classes are themselves a subpart of the softinex/inlib and exlib thesaurus of code accumulated for long at Orsay (at LAL before 2020 and now at the IJCLab) to help doing visualization and data analysis for various projects. (The namespaces inlib and exlib had been changed to "tools" when importing classes within Geant4 to avoid clashes with apps using both Geant4 and straight softinex). This scene graph way of doing visualization is borrowed from the great OpenInventor developed by Silicon Graphics Incs in the 1980's. The idea is that a data representation is done by creating a scene graph which is a tree of "nodes". For example a tree has in general a first tools::sg::ortho (or sg::perspective) camera node specifying a camera projection (position, orientation and depth of view), some sg::matrix node permitting to position an object in a 3D space and then some shape nodes as sg::cube, sg::cylinder or sg::vertices (a node handling a set of points, lines, segments or triangles) used to represent a piece of detector or tracks.

Whence having built a scene graph, the rendering is done, typically after having received some expose event in a drawing area window, by applying a "render\_action" that traverses the scene graph and asks to the nodes the actions that will be passed to a specific graphics engine. For example a shape node (cube, sphere, polyhedron), when traversed, will give to the render\_action the graphics primitives (points, lines, segments, triangles) representing that shape. A

camera node will give a projection matrix, a matrix node will give a model matrix. A common graphics engine being GL-ES, we have the tools::sg::GL\_action class that does that for GL-ES on macOS, Linux and Windows. We have also various render\_action to do offscreen rendering (gl2ps\_action using gl2ps and zb\_action to render in an in memory z-buffer). In softinex we have also a exlib::wasm::render to render in WebAssembly using WebGL and a exlib::metal::render to render within macOS/Cocoa/Metal, but these are not yet used in Geant4/vis.

In Geant4/vis, the ToolsSG directory contains code to create a viewer within various windowing systems, codes which are declared as "drivers" in the vis system. Today there are the TOOLSSG\_QT\_GLES and TOOLSSG\_XT\_GLES to create a viewing area ready for GL-ES rendering if using the GUI toolkits Qt or Xt/Motif (activated through the G4UIQt, G4UIXt classes), and TOOLSSG\_X11\_GLES, TOOLSSG\_WINDOWS\_GLES to create a GL-ES viewing area straight on X11 or Windows windowing systems.

From a user point of view, typical commands to create a ToolsSG viewer are:

```
/vis/sceneHandler/create TSG scene-handler-tsg
/vis/viewer/create scene-handler-tsg viewer-tsg 600x600-0+0
```

or with the compound command:

```
/vis/viewer/open TSG 600x600-0+0
```

Someone can specify straight a TOOLSSG\_[QT,XT,X11,WINDOWS]\_GLES name driver, but if specifying "TSG", the G4/vis system will pick the "right one", according to the kind of GUI or windowing context which is choosen (in general Qt for now).

Obviously, these drivers must have been built when building/installing Geant4. With the G4 cmake system, this is done by specifying the cmake flag:

```
-DGEANT4_USE_TOOLSSG=XX
```

where XX is one of: OFF, X11, XT, QT or WIN32.

When a ToolsSG viewer is created, vis commands triggering the representation of a piece of detector or a track are the same as for other drivers. For example, as can be found in the examples/basic/B1/vis.mac:

```
# Draw geometry:
/vis/drawVolume
...
# Draw smooth trajectories at end of event:
/vis/scene/add/trajectories smooth
...
```

On a technical point of view, the G4ToolsSceneHandler class is the place where tools::sg nodes are created according each Geant4/vis primitive type (G4Polyhedron, G4Polyline, G4Text, etc...).

#### ToolsSG /vis/tsg specific commands:

The:

```
/vis/tsg/export
```

permits to write the content of the current ToolsSG viewer in a file at various formats. Default file is out.eps and default format is gl2ps\_eps. Today, available formats are:

```
gl2ps_eps: gl2ps producing eps
gl2ps_ps: gl2ps producing ps
gl2ps_pdf: gl2ps producing pdf
gl2ps_svg: gl2ps producing svg
gl2ps_tex: gl2ps producing tex
gl2ps_pgf: gl2ps producing pgf
zb_ps: tools::sg offscreen zbuffer put in a PostScript file.
```

## **Book For Application Developers, Release 11.0**

An example of usage is:

/vis/tsg/export gl2ps\_pdf out.pdf

Another command is:

/vis/tsg/plotter/printParameters

It permits to print the available keys used to customize a ToolsSG plotter. This command is more documented in the ToolsSG plotting section.

## 8.3.9 Vtk

Developed by Stewart Boogert and Laurie Nevay of Royal Holloway, University of London, this driver exploits the Visualisation Toolkit (Vtk) (vtk.org). Its focus is high performance. Like Qt3D and ToolsSG, it offers future-proofing for Geant4 visualisation.

You need to install the Vtk libraries - see Installation Guide. There is a "native" driver, but also one which melds with Qt if you also have Qt installed.

## 8.3.10 HepRepFile

The HepRepFile driver creates a HepRep XML file in the HepRep1 format suitable for viewing with the HepRepPep HepRep Browser.

The HepRep graphics format is further described at http://www.slac.stanford.edu/~perl/heprep.

To write just the detector geometry to this file, use the command:

/vis/viewer/flush

Or, to also include trajectories and hits (after the appropriate /vis/viewer/add/trajectories or /vis/viewer/add/hits commands), just issue:

/run/beamOn 1

HepRepFile will write a file called G4Data0.heprep to the current directory. Each subsequent file will have a file name like G4Data1.heprep, G4Data2.heprep, etc.

View the file using the HepRApp HepRep Browser, available from:

http://www.slac.stanford.edu/~perl/HepRApp/.

HepRApp allows you to pick on volumes, trajectories and hits to find out their associated HepRep Attributes, such as volume name, particle ID, momentum, etc. These same attributes can be displayed as labels on the relevant objects, and you can make visibility cuts based on these attributes ("show me only the photons", or "omit any volumes made of iron").

HepRApp can read heprep files in zipped format as well as unzipped, so you can save space by applying gzip to the heprep file. This will reduce the file to about five percent of its original size.

Several commands are available to override some of HepRepFile's defaults

• You can specify a different directory for the heprep output files by using the setFileDir command, as in:

/vis/heprep/setFileDir <someOtherDir/someOtherSubDir>

• You can specify a different file name (the part before the number) by using the setFileName command, as in:

/vis/heprep/setFileName <my\_file\_name>

which will produce files named <my\_file\_name>0.heprep, <my\_file\_name>1.heprep, etc.

 You can specify that each file should overwrite the previous file (always rewriting to the same file name) by using the setOverwrite command, as in:

/vis/heprep/setOverwrite true

This may be useful in some automated applications where you always want to see the latest output file in the same location.

• GEANT4 visualization supports a concept called "culling", by which certain parts of the detector can be made invisible. Since you may want to control visibility from the HepRep browser, turning on visibility of detector parts that had defaulted to be invisible, the HepRepFile driver does not omit these invisible detector parts from the HepRep file. But for very large files, if you know that you will never want to make these parts visible, you can choose to have them left entirely out of the file. Use the /vis/heprep/setCullInvisibles command, as in:

/vis/heprep/setCullInvisibles true

#### **Further information:**

- HepRApp Users Home Page: http://www.slac.stanford.edu/~perl/HepRApp/
- HepRep graphics format: http://www.slac.stanford.edu/~perl/heprep

## 8.3.11 DAWN

The DAWN drivers are interfaces to Fukui Renderer DAWN, which has been developed by Satoshi Tanaka, Minato Kawaguti et al (Fukui University). It is a vectorized 3D PostScript processor, and so well suited to prepare technical high quality outputs for presentation and/or documentation. It is also useful for precise debugging of detector geometry. Remote visualization, off-line re-visualization, cut view, and many other useful functions of detector simulation are supported. A DAWN process is automatically invoked as a co-process of GEANT4 when visualization is performed, and 3D data are passed with inter-process communication, via a file.

When GEANT4 Visualization is performed with the DAWN driver, the visualized view is automatically saved to a file named q4.eps in the current directory, which describes a vectorized (Encapsulated) PostScript data of the view.

There are two kinds of DAWN drivers, the DAWNFILE driver and the DAWN-Network driver. The DAWNFILE driver is usually recommended, since it is faster and safer in the sense that it is not affected by network conditions.

The DAWNFILE driver sends 3D data to DAWN via an intermediate file, named g4.prim in the current directory. The file g4.prim can be re-visualized later without the help of GEANT4. This is done by invoking DAWN by hand:

% dawn g4.prim

DAWN files can also serve as input to two additional programs:

- A standalone program, DAWNCUT, can perform a planar cut on a DAWN image. DAWNCUT takes as input a
  .prim file and some cut parameters. Its output is a new .prim file to which the cut has been applied.
- Another standalone program, DAVID, can show you any volume overlap errors in your geometry. DAVID takes
  as input a .prim file and outputs a new .prim file in which overlapping volumes have been highlighted. The use
  of DAVID is described in section *Detecting Overlapping Volumes* of this manual.

## 8.3.12 VRML

These drivers were developed by Satoshi Tanaka and Yasuhide Sawada (Fukui University). They generate VRML files, which describe 3D scenes to be visualized with a proper VRML viewer, at either a local or a remote host. It realizes virtual-reality visualization with your WWW browser. There are many excellent VRML viewers, which enable one to perform interactive spinning of detectors, walking and/or flying inside detectors or particle showers, interactive investigation of detailed detector geometry etc.

The VRML2FILE driver sends 3D data to your VRML viewer, which is running on the same host machine as GEANT4, via an intermediate file named g4.wrl created in the current directory. This file can be re-visualization afterwards. In visualization, the name of the VRML viewer should be specified by setting the environment variable G4VRML\_VIEWER beforehand. For example,

```
% setenv G4VRML_VIEWER "netscape"
```

Its default value is NONE, which means that no viewer is invoked and only the file 94. wrl is generated.

## 8.3.13 RayTracer

This driver was developed by Makoto Asai and Minamimoto (Hirosihma Instutute of Technology). It performs ray-tracing visualization using the tracking routines of GEANT4. It is, therefore, available for every kinds of shapes/solids which GEANT4 can handle. It is also utilized for debugging the user's geometry for the tracking routines of GEANT4. It is well suited for photo-realistic high quality output for presentation, and for intuitive debugging of detector geometry. It produces a JPEG file. This driver is by default listed in the available visualization drivers of user's application.

Some pieces of geometries may fail to show up in other visualization drivers (due to algorithms those drivers use to compute visualizable shapes and polygons), but RayTracer can handle any geometry that the GEANT4 navigator can handle.

Because RayTracer in essence takes over GEANT4's tracking routines for its own use, RayTracer cannot be used to visualize Trajectories or hits.

An X-Window version, called RayTracerX, can be selected by setting GEANT4\_USE\_RAYTRACER\_X11 (for CMake) at GEANT4 library build time and application (user code) build time (assuming you use the standard visualization manager, G4VisExecutive, or an equally smart vis manager). RayTracerX builds the same jpeg file as RayTracer, but simultaneously renders to screen so you can watch as rendering grows progressively smoother.

RayTracer has its own built-in commands - /vis/rayTracer/.... Alternatively, you can treat it as a normal vis system and use /vis/viewer/... commands, e.g:

```
/vis/open RayTracerX
/vis/drawVolume
/vis/viewer/set/viewpointThetaPhi 30 30
/vis/viewer/refresh
```

The view parameters are translated into the necessary RayTracer parameters.

RayTracer is compute intensive. If you are unsure of a good viewing angle or zoom factor, you might be advised to choose them with a faster renderer, such as OpenGL, and transfer the view parameters with /vis/viewer/copyViewFrom:

```
/vis/open OGL
/vis/drawVolume
/vis/viewer/zoom # plus any /vis/viewer/commands that get you the view you want.
/vis/open RayTracerX
/vis/viewer/copyViewFrom viewer-0
/vis/viewer/refresh
```

## 8.3.14 gMocren

The gMocrenFile driver creates a gdd file suitable for viewing with the gMocren volume visualizer. gMocren, a sophisticated tool for rendering volume data, can show volume data such as GEANT4 dose distributions overlaid with scoring grids, trajectories and detector geometry. gMocren provides additional advanced functionality such as transfer functions, colormap editing, image rotation, image scaling, and image clipping.

gMocren is further described at http://geant4.kek.jp/gMocren/. At this link you will find the gMocren download, the user manual, a tutorial and some example gdd data files.

Please note that the gMocren file driver is currently considered a Beta release. Users are encouraged to try this driver, and feedback is welcome, but users should be aware that features of this driver may change in upcoming releases.

To send volume data from GEANT4 scoring to a gMocren file, the user needs to tell the gMocren driver the name of the specific scoring volume that is to be displayed. For scoring done in C++, this is the name of the sensitive volume. For command-based scoring, this is the name of the scoring mesh.

```
/vis/gMocren/setVolumeName <volume_name>
```

The following is an example of the minimum command sequence to send command-based scoring data to the a gMocren file:

```
# an example of a command-based scoring definition
/score/create/boxMesh scoringMesh  # name of the scoring mesh
/score/mesh/boxSize 10. 10. 10. cm  # dimension of the scoring mesh
/score/mesh/nBin 10 10 10  # number of divisions of the scoring mesh
/score/quantity/energyDeposit eDep  # quantity to be scored
/score/close
# configuration of the gMocren-file driver
/vis/scene/create
/vis/open gMocrenFile
/vis/gMocren/setVolumeName scoringMesh
```

To add detector geometry to this file:

```
/vis/viewer/flush
```

To add trajectories and primitive scorer hits to this file:

```
/vis/scene/add/trajectories
/vis/scene/add/pshits
/run/beamOn 1
```

gMocrenFile will write a file named G4\_00.gd to the current directory. Subsequent draws will create files named g4\_01.gdd, g4\_02.gdd, etc. An alternate output directory can be specified with an environment variable:

```
export G4GMocrenFile_DEST_DIR=<someOtherDir/someOtherSubDir/>
```

View the resulting gMocren files with the gMocren viewer, available from: http://geant4.kek.jp/gMocren/.

## 8.3.15 Visualization of detector geometry tree

ASCIITREE is a visualization driver that is not actually graphical but that dumps the volume hierarchy as a simple text tree using /vis/drawTree.

ASCIITree has command to control its verbosity, /vis/ASCIITree/verbose. The verbosity value controls the amount of information available, e.g., physical volume name alone, or also logical volume and solid names. If the volume is "sensitive" and/or has a "readout geometry", this may also be indicated. Also, the mass of the physical volume tree(s) can be printed (but beware - higher verbosity levels can be computationally intensive).

At verbosity level 4, ASCIITree calculates the mass of the complete geometry tree taking into account daughters up to the depth specified for each physical volume. The calculation involves subtracting the mass of that part of the mother that is occupied by each daughter and then adding the mass of the daughter, and so on down the hierarchy.

Some more examples of ASCIITree in action:

```
Idle> /vis/ASCIITree/verbose 1
Idle> /vis/drawTree
# Set verbosity with "/vis/ASCIITree/verbose "
    < 10: - does not print daughters of repeated placements, does not repeat replicas.
       10: prints all physical volumes.
  The level of detail is given by verbosity %10:
  for each volume:
    >= 0: physical volume name.
    >= 1: logical volume name (and names of sensitive detector and readout geometry, if any). >= 2: solid name and type.
    >= 3: volume and density.
    >= 5: daughter-subtracted volume and mass.
  and in the summary at the end of printing:
#
     >= 4: daughter-included mass of top physical volume(s) in scene to depth specified.
"Calorimeter", copy no. 0, belongs to logical volume "Calorimeter"
  "Layer", copy no. -1, belongs to logical volume "Layer" (10 replicas)
    "Absorber", copy no. 0, belongs to logical volume "Absorber"
      "Gap", copy no. 0, belongs to logical volume "Gap"
Idle> /vis/ASCIITree/verbose 15
Idle> /vis/drawTree
"tube_phys":0 / "tube_L" / "tube" (G4Tubs), 395841 cm3, 1.782 mg/cm3,
                           9.6539e-08 mm3, 1.72032e-10 mg
   "divided_tube_phys":0 / "divided_tube_L" / "divided_tube" (G4Tubs), 65973.4 cm3,
                           1.782 mg/cm3, 7587.54 cm3, 13.521 g
     "divided_tube_inset_phys":0 / "divided_tube_inset_L" / "divided_tube_inset" (G4Tubs),
                                   58385.9 cm3, 1.782 mg/cm3, 6.03369e-09 mm3, 1.0752e-11 mg
       "sub_divided_tube_phys": 0 / "sub_divided_tube_L" / "sub_divided_tube" (G4Tubs),
                                   14596.5 cm3, 1.782 mg/cm3, 12196.5 cm3, 21.7341 g
```

(continues on next page)

(continued from previous page)

```
Calculating mass(es)...

Overall volume of "expHall_P":0, is 8000 m3 and the daughter-included mass to unlimited depth is 78414 kg
.....
```

For the complete list of commands and options, see the Control... UICommands section of this user guide.

## 8.4 Controlling Visualization from Commands

This section describes just a few of the more commonly used visualization commands. For the complete list of commands and options, see the Control... UICommands section of this user guide.

These commands can by typed on the session command line when in Idle state:

```
Idle> /vis/drawVolume
```

or specified in a macro file that is executed from the command line:

```
Idle> /control/execute vis.mac
```

or from your application, e.g.:

```
UImanager->ApplyCommand("/control/execute vis.mac");
```

Most examples have a vis.mac file, where you may look for inspiration.

For simplicity, this section assumes that the GEANT4 executable was compiled incorporating the DAWNFILE and the OpenGL-Xlib drivers. For details on creating an executable for visualization see *Adding Visualization to Your Executable*.

**Warning:** This section is not a complete description of all visualisation commands; they are too numerous and continually evolving. Please refer to the command guidance, Control... UICommands or simply type "ls vis" or "help". Some viewers, notably Qt, offer interactivie guidance under the "Help" menu.

## 8.4.1 Scene, scene handler, and viewer

In using the visualization commands, it is useful to know the concept of "scene", "scene handler", and "viewer". A "scene" is a set of visualizable raw 3D data. A "scene handler" is a graphics-data modeler, which processes raw data in a scene for later visualization. And a "viewer" generates images based on data processed by a scene handler. Roughly speaking, a set of a scene handler and a viewer corresponds to a visualization driver.

The steps of performing GEANT4 visualization are explained below, though some of these steps may be done for you so that in practice you may use as few as just two commands (such as /vis/open OGLIX plus /vis/drawVolume). The seven steps of visualization are:

Table 8.2: Seven steps of visualization.

Step		Command	Alternative com-
			mand
1	Create a scene handler and a viewer	/vis/sceneHandler/create	/vis/open
		/vis/viewer/create	
2	Create an empty scene	/vis/scene/create	/vis/drawVolume
3	Add raw 3D data to the created scene	/vis/scene/add/volume	
4	Attach the current scene to the current scene han-	/vis/sceneHandler/attach	
	dler		
5	Set camera parameters, drawing style (wire-	E.g., /vis/viewer/set/viewpoint	
	frame/surface), etc		
6	Make the viewer execute visualization	/vis/viewer/refresh	
7	Declare the end of visualization for flushing	/vis/viewer/flush	

For details about the commands, see below.

These seven steps can be controlled explicitly to create multiple scenes and multiple viewers, each with its own set of parameters, with easy switching from one scene to another. But for the most common case of just having one scene and one viewer, many steps are handled implicitly for you.

## 8.4.2 Create a scene handler and a viewer: /vis/open command

Command "/vis/open" creates a scene handler and a viewer, which corresponds to Step 1.

Command: /vis/open <driver\_tag\_name>

Argument

A name of (a mode of) an available visualization driver.

Action

Create a visualization driver, i.e. a set of a scene handler and a viewer.

• Example: Create an OpenGL driver (it chooses the best available for a given type of session):

/vis/open OGL

To see a list of driver\_tag\_names:

/vis/list

(produces a lot of information) or:

/vis/open xx

## which produces:

```
parameter value (xx) is not listed in the candidate List.

Candidates are: ATree DAWNFILE HepRepFile HepRepXML OGL OGLI OGLIQt OGLS OGLSQt RayTracer

→VRML1FILE VRML2FILE gMocrenFile
```

For additional options, see the Control... UICommands section of this user guide.

## 8.4.3 Create an empty scene: /vis/scene/create command

Command "/vis/scene/create" creates an empty scene, which corresponds to Step 2.

Command: /vis/scene/create [scene\_name]

## • Argument

A name for this scene. Created for you if you don't specify one.

## 8.4.4 Visualization of a physical volume: /vis/drawVolume command

/vis/drawVolume is a "compound" command that creates a new scene (/vis/scene/create), adds a volume (/vis/scene/add/volume) and attaches it (/vis/sceneHandler/attach) to the current viewer (/control/verbose 2 to see all the invoked commands). It takes care of steps 2, 3, 4 and 6. Command /vis/viewer/flush may be required in order to do the final Step 7.

#### **Commands:**

/vis/drawVolume [physical-volume-name]

#### Argument

If physical-volume-name is "world" (the default), the top of the main geometry tree (material world) is added. If "worlds", the tops of all worlds - material world and parallel worlds, if any - are added. Otherwise a search of all worlds is made.

In the last case the names of all volumes in all worlds are matched against physical-volume-name. If this is of the form "/regexp/", where regexp is a regular expression (see C++ regex), the match uses the usual rules of regular expression matching. Otherwise an exact match is required.

For example, "/Shap/" matches "Shape1" and "Shape2".

## Action

Creates a scene consisting of the given physical volume(s) and asks the current viewer to draw it. The scene becomes current. Command "/vis/viewer/flush" should follow this command in order to declare end of visualization.

• Example: Visualization of the whole world with coordinate axes

```
/vis/drawVolume
/vis/scene/add/axes 0 0 0 500 mm
/vis/viewer/flush
```

## 8.4.5 Visualization of a logical volume: /vis/drawLogicalVolume command

/vis/drawLogicalVolume is a "compound" command that creates a new scene (/vis/scene/create), adds a logical volume (/vis/scene/add/logicalVolume) and attaches it (/vis/sceneHandler/attach) to the current viewer (/control/verbose 2 to see all the invoked commands). It shows all that can be visualised about a logical volume—Booleans, voxels, readout geometries and overlaps—and adds axes in the local coordinate system. All options are on by default.

This command is synonymous with /vis/specify.

```
Command: vis/drawLogicalVolume <logical-volume-name> [<depth-of-descent>]
[<booleans-flag>] [<voxels-flag>] [<readout-flag>] [<axes-flag>]
[<check-overlap-flag>]
```

#### Argument

A logical-volume name.

#### Action

Creates a scene consisting of the given logical volume and asks the current viewer to draw it. The scene becomes current.

• Example (visualization of a selected logical volume with coordinate axes)

```
/vis/drawLogicalVolume Absorber
/vis/scene/add/text 0 0 0 mm 40 -100 -200 LogVol:Absorber
/vis/viewer/flush
```

For more information, use the help facility or refer to Control... UICommands.

## 8.4.6 Visualization of trajectories: /vis/scene/add/trajectories command

Command "/vis/scene/add/trajectories [smooth] [rich]" adds trajectories to the current scene. The optional parameters "smooth" and/or "rich" (you may specify either, neither or both) invoke, if "smooth" is specified, the storing and displaying of extra points on curved trajectories and, if "rich" is specified, the storing, for possible subsequent selection and display, of additional information, such as volume names, creator process, energy deposited, global time. Be aware, of course, that this imposes computational and memory overheads. Note that this automatically issues the appropriate "/tracking/storeTrajectory" command so that trajectories are stored (by default they are not). The visualization is performed with the command "/run/beamOn" unless you have non-default values for /vis/scene/endOfEventAction or /vis/scene/endOfRunAction (described below).

Command: /vis/scene/add/trajectories [smooth] [rich]

#### Action

The command adds trajectories to the current scene. Trajectories are drawn at end of event when the scene in which they are added is current.

• Example: Visualization of trajectories

```
/vis/scene/add/trajectories
/run/beamOn 10
```

#### · Additional note 1

See the section *Controlling from Commands* for details on how trajectories are color-coded.

#### Additional note 2

Events may be kept and reviewed at end of run with:

```
/vis/reviewKeptEvents
```

Keep all events with:

```
/vis/scene/endOfEventAction accumulate [maxNumber]
```

(see End of Event Action and End of Run Action: /vis/scene/endOfEventAction and /vis/scene/endOfRunAction commands)

or keep some chosen subset by some selection in your user code, for example your user event action:

```
if ( some criterion ) {
   G4EventManager::GetEventManager() ->KeepTheCurrentEvent();
}
```

or:

```
if ( some criterion ) {
   UImanager->ApplyCommand("/event/keepCurrentEvent");
}
```

as described in Listing 6.8.

To draw only those events kept as above:

/vis/drawOnlyToBeKeptEvents

To suppress drawing during a run:

```
/vis/disable
/run/beamOn 10000
```

then at end of run:

```
/vis/enable
/vis/reviewKeptEvents
```

#### Additional note 3

Visualising events as they are being generated inevitably slows the simulation. Visualisation can be suspended with /vis/disable as suggested above. You may also switch off trajectory production with /tracking/storeTrajectory 0. When using OpenGL, the following can help:

```
/vis/ogl/flushAt
<[endOfEvent|endOfRun|eachPrimitive|NthPrimitive|NthEvent|never]> <N>
```

By default, this value is set to /vis/ogl/flushAt NthEvent 100

For more options, see the Control... UICommands section of this user guide.

## 8.4.7 Visualization of hits: /vis/scene/add/hits command

Command "/vis/scene/add/hits" adds hits to the current scene, assuming that you have a hit class and that the hits have visualization information. The visualization is performed with the command "/run/beamon" unless you have non-default values for /vis/scene/endOfEventAction or /vis/scene/endOfRunAction (described above).

## 8.4.8 Visualization of fields: /vis/scene/add/magneticField command

/vis/scene/add/magneticField and /vis/scene/add/electricField will draw any fields defined in the scene as an array of arrows whose direction, length and colour are related to the field strength and direction.

Sometimes this can result in a overwhelming number of arrows. To limit the extent of the arrows preface one or more of the above commands with:

```
/vis/set/extentForField
```

or:

```
/vis/set/volumeForField
```

or equivalent commands in /vis/touchable/.

This can be repeated to get the desired effect, e.g.:

```
/vis/set/extentForField -20 20 -55 0 0 50 cm

/vis/scene/add/magneticField

/vis/set/volumeForField detector1

/vis/scene/add/magneticField

/vis/set/volumeForField detector2 5

/vis/scene/add/electricField
```

To remove fields from the scene:

```
/vis/scene/activateModel Field false
```

Consult the guidance for the /vis/scene/add/...Field commands for further hints and suggestions.

## 8.4.9 Visualization of Scored Data

Scored data can be visualized using the commands "/score/drawProjection" and "/score/drawColumn". For details, see examples/extended/runAndEvent/RE03.

## 8.4.10 Additional attributes for Hits

The HepRep file formats, HepRepFile and HepRepXML, understand various additional attributes such that you can view these attributes, label trajectories by these attributes or make visibility cuts based on these attributes. Examples of adding HepRep attributes to hit classes can be found in examples /extended/analysis/A01 and /extended/runAndEvent/RE01.

For example, in example RE01's class RE01CalorimeterHit.cc, available attributes will be:

- Hit Type
- · Track ID
- Z Cell ID
- Phi Cell ID
- · Energy Deposited
- Energy Deposited by Track
- Position
- · Logical Volume

You can add additional attributes of your choosing by modifying the relevant part of the hit class (look for the methods GetAttDefs and CreateAttValues).

## 8.4.11 Visualization of histograms (plotting)

The G4/vis system is equipped to be able to do plotting, then to have a representation (a plot) of 1D or 2D histograms within a G4/vis viewer. The G4 vis primitive G4Plotter has been introduced to capture which histograms to plot, specify a grid of plots (2x2, 2x3, etc...), along some style options to customize the representations (for example to change bins color, title or axis label fonts, etc...). Specifying a grid of plots (or "regions") is a common practice in plotting and is a similar concept as the "zones" found in the good old CERN/PAW.

The known histograms are the ones managed in G4/analysis and are known in G4Plotter by using their integer id.

This said, each specific vis driver is charged with implementing the representation of a G4Plotter. Today only the ToolsSG drivers come with such representation, but we hope that more vis drivers will come with an implementation in the future.

From the user point of view, commands has been introduced to be able to specify a plot from pure .mac scripting. To start with, the best is to jump in examples/basic/B5 that comes with a commented plotter.mac example. In it you will see how to activate the vis driver (create a "scene handler"), create a viewer, create a scene containing a plotter model object (then a G4Plotter), create a grid of plotting "regions" (here 2x2 regions) and attach the histograms to each region. When done, each "run beamOn" should display at end the content of the histograms.

The skeleton of a plotting script then looks like:

```
# viewer:
/vis/sceneHandler/create TSG scene-handler-plotter
/vis/viewer/create scene-handler-plotter viewer-plotter 600x600-0+0
/vis/viewer/set/background 1 1 1
/vis/viewer/zoomTo 1
/vis/viewer/set/viewpointVector 0 0 1
# scene:
/vis/plotter/create plotter-0
/vis/scene/create scene-plotter
```

(continues on next page)

(continued from previous page)

```
/vis/scene/add/plotter plotter-0
/vis/sceneHandler/attach scene-plotter
# create a 2x2 plotter regions:
/vis/plotter/setLayout plotter-0 2 2
# attach histograms to regions (examples/basic/B5 specific):
/vis/plotter/add/h1 0 plotter-0 0
/vis/plotter/add/h1 1 plotter-0 1
/vis/plotter/add/h2 0 plotter-0 2
/vis/plotter/add/h2 1 plotter-0 3
# let's go:
/run/beamOn 100
# the upper will update the plotters at end of run.
```

## **Plotting style:**

Being able to customize the representations is an important part of plotting. The concept of named style had been introduced in G4/vis to handle this. A named style is nothing more than a named list of pairs (key,value) which is managed in the G4/vis system.

You can create a named style and set it as "current style" with:

```
/vis/plotting/style/select <name>
```

You can deposit pairs of key/value in the current style with:

```
/vis/plotter/style/add <key> <value>
/vis/plotter/style/add <key> <value>
...
```

A named style can be used on a specific region with:

```
/vis/plotter/addRegionStyle <plotter> <region> <style>
```

For example, in B5/plotter.mac:

```
/vis/plotter/addRegionStyle plotter-0 0 style-0
```

or on a whole grid of plots with:

```
/vis/plotter/addStyle <plotter> <style>
```

Note that someone can add multiple named styles on a plotter or on a region. If so the styles are applied in order with global ones first and then per region ones after.

IMPORTANT: the key/value pairs are specific of a G4Plotter representation implementation. If using the ToolsSG plotting you may have:

```
/vis/plotter/style/add bins_style.0.color blue
/vis/plotter/style/add bins_style.0.line_width 3
/vis/plotter/style/add infos_width 0.2
/vis/plotter/style/add infos_style.visible true
/vis/plotter/style/add infos_style.font roboto_bold.ttf
/vis/plotter/style/add infos_style.front_face cw
```

but, a priori, the upper key/value pairs are not expected to be known by another plotter implementation. (But it would be great to be so!).

Other usefull style commands are:

```
# to list known named styles.
/vis/plotter/style/list
# to print the list of key/value pairs of a named style:
/vis/plotter/style/print <style>
# to remove a name style from G4/vis:
/vis/plotter/style/remove <style>
```

Note that without passing by a style, a plotting region can be customised directly by using the command:

```
/vis/plotter/addRegionParameter <plotter> <region> <key> <value>
```

for example with ToolsSG plotting in B5/plotter.mac:

```
/vis/plotter/addRegionParameter plotter-0 0 bins_style.0.color blue /vis/plotter/addRegionParameter plotter-0 0 bins_style.0.line_width 3
```

As for styles, the key/value pairs are specific of a vis driver plotting implementation. Note that the pairs given with the addRegionParameter on a region are applied after all styles on this region.

## **ToolsSG plotting:**

The ToolsSG/G4Plotter representation is done by using the high level tools::sg::plots and tools::sg::plotter nodes (found in externals/g4tools/include/tools/sg). The tools::sg::plotter node uses a lot of nodes as tools::sg::axis, tools::sg::vertices, etc.. to build representations. (tools::sg::plots permits to implement a grid of plots). A tools::sg::node manages "smart fields", for example the tools::sg::sf<float> (simple float smart field) "width" in tools::sg::plotter. (Smart field is a similar concept as the SoField in OpenInventor). It is these fields that are customizable as key/value pairs from styles or region parameters. (A smart field is smart in the sense that if "touched", for example by setting a new value, it may induce an automatic update of the node at next rendering traversal of a scene graph).

The list of what is customizable on a tools::sg::plotter, is given with the ToolsSG specific command:

```
/vis/tsg/plotter/printParameters
```

For styles, specific to ToolsSG plotting, are the named styles "default", "ROOT\_default", "hippodraw" that are "embedded" styles (defined as C++ functions in: tools/sg/plotter\_some\_styles). (These styles are the same than in G4/analysis for batch plotting). In particular the ROOT\_default styles permits to mimic the default style plotting found in CERN/ROOT. Then someone can do:

```
/vis/plotter/addStyle <plotter> ROOT_default
```

to have the ROOT style for all regions. (Note that ROOT\_default needs freetype).

In the second part of B5 plotter.mac, is shown various ways to customize the regions, for example changing the bins color, the axis labels fonts, etc... This could be done by using default embedded styles, defining styles with commands, or setting up directly parameters of the various parts of a plot by using the dedicated addRegionParameter command.

For texts (title, tick labels, etc...), the fonts used by default are the Hershey vectorial ones (the ones of the good old CERN/PAW) that do not need an extra package, but you can use some freetype fonts if building with the cmake flag -DGEANT4\_USE\_FREETYPE=ON. For example the ROOT\_default embedded style uses freetype fonts. Two embedded ttf fonts come with the ToolsSG plotting: roboto\_bold (some open source kind of the Microsoft arialbd) and lato\_regular (close to an helvetica). You can use also your own .ttf files by using the TOOLS\_FONT\_PATH environment variable to specify the directory where they could be found.

## **ToolsSG plotting keys:**

A style or parameter key has the form:

```
<direct field> of sg::plotter, as width, height, left_margin, right_margin, etc...
```

or is a field of a sub node representing a component of the scene of the plot, such as [x,y,z] axis, infos box, title box, grid, bins, errors, etc... The key may refer a direct field of the component such as x\_axis.title, or the style of a component handled by a tools::sg::style or sg::text\_style node. A component key may contain two or three words separated by a dot.

Two words keys are for:

```
[x_axis,y_axis,z_axis].<field>
```

## For example:

```
x_axis.modeling (string field with value hplot, hippodraw).  
x_axis.divisions (in case of hplot modeling, an int specifiying primary/secondary ticks encoded_ \hookrightarrow as in hplot (for exa 510)).
```

or for the style components:

```
background_style, title_style, infos_style, title_box_style,
inner_frame_style, grid_style, wall_style
```

#### For example:

```
infos_style.visible
infos_style.font
infos_style.front_face
```

Three words keys are also for the style of the components of the tools::sg::axis as:

```
line_style, ticks_style, labels_style, mag_style, title_style
```

for example:

```
x_axis.labels_style.color
```

Three words keys are used also to specified style fields of the bins, errors, function, points, legend data representations components. For example, in one sg::plotter, you can specify to plot multiple histograms, ie multiple "bins". In this case, you can customize the style of the i-th "bins" (i-th histogram) with a key of the form:

```
bins_style.<i-th>.<field>
```

for example to change color of the "front" histogram:

```
bins_style.0.color
```

For the moment, the G4/vis plotting knows only histograms, but the tools::sg::plotter can handle cloud of points, errors, functions, legends, and in some future, a G4 user may have to use the errors\_style, func\_style, points\_style, legend\_style in the same way to customize a "i-th" cloud of points, a i-th function, a i-th legend, etc...

We do not give here the full list of available parameters since it may evolve in time. The best is to use the command:

```
/vis/tsg/plotter/printParameters
```

that dumps, by querying directly the nodes, the available styles and smart fields for the sg::plotter itself or for one of its component. Moreover it dumps also the type of a field (float, integer, boolean, string, etc...).

Put all together, the combinatory of available keys is rather rich and permits a strong customization of good parts of a sg::plotter.

## 8.4.12 Basic camera workings: /vis/viewer/ commands

Commands in the command directory "/vis/viewer/" set camera parameters and drawing style of the current viewer, which corresponds to Step 5. Note that the camera parameters and the drawing style should be set separately for each viewer. They can be initialized to the default values with command "/vis/viewer/reset". Some visualization systems, such as the VRML and HepRep browsers also allow camera control from the standalone graphics application.

Just a few of the camera commands are described here. For more commands, see the Control... UICommands section of this user guide.

The view is defined by a target point (initially at the centre of the extent of all objects in the scene), an up-vector and a viewpoint direction - see Fig. 8.1. By default, the up-Vector is parallel to the y-axis and the viewpoint direction is parallel to the z-axis, so the view shows the x-axis to the right and the y-axis upwards - a projection on to the canonical x-y plane - see Fig. 8.2 figure.

The target point can be changed with a /vis/viewer/set command or with the /vis/viewer/pan commands. The up-vector and the viewpoint direction can also be changed with /vis/viewer/set commands. Care must be taken to avoid having the two vectors parallel, for in that case the view is undefined.

The commands:

```
/vis/viewer/centreOn <volume-name> [<copy-number>]
/vis/viewer/centreAndZoomInOn <volume-name> [<copy-number>]
```

also change the target point.




Fig. 8.1: Up-vector and viewpoint direction

Command: /vis/viewer/set/viewpointThetaPhi [theta] [phi] [deg|rad]

#### Arguments

Arguments "theta" and "phi" are polar and azimuthal camera angles, respectively. The default unit is "degree".

#### Action

Set a view point in direction of (theta, phi).

• Example: Set the viewpoint in direction of (70 deg, 20 deg) /

/vis/viewer/set/viewpointThetaPhi 70 20

#### · Additional notes

Camera parameters should be set for each viewer. They are initialized with command "/vis/viewer/reset". Alternatively, they can be copied from another viewer with the command "/vis/viewer/copyViewFrom viewer-0", for example.




Fig. 8.2: The default view

Command: /vis/viewer/zoom [scale\_factor]

#### Argument

The scale factor. The command multiplies magnification of the view by this factor.

#### • Action

Zoom up/down of view.

• Example: Zoom up by factor 1.5

/vis/viewer/zoom 1.5

#### · Additional notes

A similar pair of commands, scale and scaleTo allow non-uniform scaling (i.e., zoom differently along different axes). For details of this and lots of other commands, see the Control... UICommands section of this user guide. Some viewers have limits to how large the zoom factor can be. This problem can be circumnavigated to some degree by using zoom and scale together. If

/vis/viewer/zoomTo 1e10

does not work, please try

```
/vis/viewer/scaleTo 1e5 1e5 1e5 /vis/viewer/zoomTo 1e5
```

Of course, with such high zoom factors, you might want to know whither you are zooming. Use /vis/viewer/set/targetPoint or /vis/viewer/centreOn or /vis/viewer/centreAndZoomInOn.

Camera parameters should be set for each viewer. They are initialized with command "/vis/viewer/reset". Alternatively, they can be copied from another viewer with the command "/vis/viewer/copyViewFrom viewer-0", for example.

Command: /vis/viewer/set/style [style\_name]

#### Arguments

Candidate values of the argument are "wireframe" and "surface". ("w" and "s" also work.)

#### Action

Set a drawing style to wireframe or surface.

• Example: Set the drawing style to "surface"

/vis/viewer/set/style surface

#### · Additional notes

The style of some geometry components may have been forced one way or the other through calls in compiled code. The set/style command will NOT override such force styles.

Drawing style should be set for each viewer. The drawing style is initialized with command "/vis/viewer/reset". Alternatively, it can be copied from another viewer with the command "/vis/viewer/set/all viewer-0", for example.

# 8.4.13 Declare the end of visualization for flushing: /vis/viewer/flush command

Command: /vis/viewer/flush

#### • Action

Declare the end of visualization for flushing.

#### · Additional notes

Command "/vis/viewer/flush" should follow "/vis/drawVolume", "/vis/specify", etc in order to complete visualization. It corresponds to Step 7.

The flush is done automatically after every /run/beamOn command unless you have non-default values for /vis/scene/endOfEventAction or /vis/scene/endOfRunAction (described above).

# 8.4.14 End of Event Action and End of Run Action: /vis/scene/endOfEventAction and /vis/scene/endOfRunAction commands

By default, a separate picture is created for each event. You can change this behaviour to accumulate multiple events, or even multiple runs, in a single picture.

Command: /vis/scene/endOfEventAction [refresh|accumulate]

#### Action

Control how often the picture should be cleared. refresh means each event will be written to a new picture. accumulate means events will be accumulated into a single picture. Picture will be flushed at end of run, unless you have also set /vis/scene/endOfRunAction accumulate

## · Additional note

You may instead choose to use update commands from your BeginOfRunAction or EndOfEventAction, as in early examples, but now the vis manager is able to do most of what most users require through the above commands.

Command: /vis/scene/endOfRunAction [refresh|accumulate]

#### Action

Control how often the picture should be cleared. refresh means each run will be written to a new picture. accumulate means runs will be accumulated into a single picture. To start a new picture, you must explicitly issue /vis/viewer/refresh, /vis/viewer/update or /vis/viewer/flush

## 8.4.15 HepRep Attributes for Trajectories

The HepRep file formats, HepRepFile and HepRepXML, attach various attributes to trajectories such that you can view these attributes, label trajectories by these attributes or make visibility cuts based on these attributes. If you use the default GEANT4 trajectory class from /tracking/src/G4Trajectory.cc (this is what you get with the plain /vis/scene/add/trajectories command), available attributes will be:

- · Track ID
- · Parent ID
- · Particle Name
- Charge
- PDG Encoding
- Momentum 3-Vector
- Momentum magnitude
- · Number of points

Using /vis/scene/add/trajectories rich will get you additional attributes. You may also add additional attributes of your choosing by modifying the relevant part of G4Trajectory (look for the methods GetAttDefs and CreateAttValues). If you are using your own trajectory class, you may want to consider copying these methods from G4Trajectory.

## 8.4.16 How to save a view.

/vis/viewer/save

This will save to a file that can be read in again with

/control/execute

If you save several views you may "fly through" them with

/vis/viewer/interpolate

See Making a Movie.

(Use the GEANT4 "help" command to see details.)

## 8.4.17 How to save a view to an image file

Most of the visualization drivers offer ways to save visualized views to PostScript (PS) or Encapsulated PostScript (EPS). Some, in addition, offer Portable Document Format (PDF). OpenGL offers a big range of formats - see below.

#### DAWNFILE

The DAWNFILE driver, which co-works with Fukui Renderer DAWN, generates "vectorized" PostScript data with "analytical hidden-line/surface removal", and so it is well suited for technical high-quality outputs for presentation, documentation, and debugging geometry. In the default setting of the DAWNFILE drivers, EPS files named "g4\_00.eps, g4\_01.eps, g4\_02.eps,..." are automatically generated in the current directory each time when visualization is performed, and then a PostScript viewer "gv" is automatically invoked to visualize the generated EPS files.

For large data sets, it may take time to generate the vectorized PostScript data. In such a case, visualize the 3D scene with a faster visualization driver beforehand for previewing, and then use the DAWNFILE drivers. For example, the following visualizes the whole detector with the OpenGL-Xlib driver (immediate mode) first, and then with the DAWNFILE driver to generate an EPS file g4\_XX.eps to save the visualized view:

```
# Invoke the OpenGL visualization driver in its immediate mode
/vis/open OGLIX

# Camera setting
/vis/viewer/set/viewpointThetaPhi 20 20

# Camera setting
/vis/drawVolume
/vis/viewer/flush

# Invoke the DAWNFILE visualization driver
/vis/open DAWNFILE

# Camera setting
/vis/viewer/set/viewpointThetaPhi 20 20

# Camera setting
/vis/drawVolume
/vis/viewer/flush
```

This is a good example to show that the visualization drivers are complementary to each other.

## OpenInventor

In the OpenInventor drivers, you can simply click the "Print" button on their GUI to generate a PostScript file as a hard copy of a visualized view.

## OpenGL

The OpenGL drivers can also generate image files, either from a pull-down menu (Motif and Qt drivers) or with /vis/ogl/export. Available formats are: eps ps pdf svg bmp cur dds icns ico jp2 jpeg jpg pbm pgm png ppm tif tiff wbmp webp xbm xpm. The default is pdf. It can generate either vector or bitmap PostScript data with /vis/ogl/set/printMode ("vectored" or "pixmap"). You can change the filename by /vis/ogl/set/printFilename And the print size by /vis/ogl/set/printSize In generating vectorized PostScript data, hidden-surface removal is performed based on the painter's algorithm after dividing facets of shapes into small sub-triangles.

The /vis/ogl/set/printSize command can be used to print EPS files even larger than the current screen resolution. This can allow creation of very large images, suitable for creation of posters, etc. The only size limitation is the graphics card's viewport dimension: GL\_MAX\_VIEWPORT\_DIMS

```
# Invoke the OpenGL visualization driver in its stored mode
/vis/open OGLSX

# Camera setting
/vis/viewer/set/viewpointThetaPhi 20 20

# Camera setting
/vis/drawVolume
/vis/viewer/flush

# set print mode to vectored
#/vis/ogl/set/printMode vectored

# set print size larger than screen
/vis/ogl/set/printSize 2000 2000

# print
/vis/ogl/export
```

## HepRep

The HepRApp HepRep Browser such as FRED can generate a wide variety of bitmap and vector output formats including PostScript and PDF.

## 8.4.18 **Culling**

"Culling" means to skip visualizing parts of a 3D scene. Culling is useful for avoiding complexity of visualized views, keeping transparent features of the 3D scene, and for quick visualization.

GEANT4 Visualization supports the following 3 kinds of culling:

- Culling of invisible physical volumes
- Culling of low density physical volumes.
- Culling of covered physical volumes by others

In order that one or all types of the above culling are on, i.e., activated, the global culling flag should also be on.

Table 8.3 summarizes the default culling policies.

Table 8.3: The default culling policies.

Culling Type	Default Value
global	ON
invisible	ON
low density	OFF
covered daughter	OFF

The default threshold density of the low-density culling is 0.01 g/cm<sup>3</sup>.

The default culling policies can be modified with the following visualization commands. (Below the argument flag takes a value of true or false.)

```
# global
/vis/viewer/set/culling global flag

# invisible
/vis/viewer/set/culling invisible flag

# low density
# "value" is a proper value of a threshold density
# "unit" is either g/cm3, mg/cm3 or kg/m3
/vis/viewer/set/culling density flag value unit

# covered daughter
/vis/viewer/set/culling coveredDaughters flag density
```

The HepRepFile graphic system will, by default, include culled objects in the file so that they can still be made visible later from controls in the HepRep browser. If this behavior would cause files to be too large, you can instead choose to have culled objects be omitted from the HepRep file. See details in the HepRepFile Driver section of this user guide.

## 8.4.19 Cut view

#### Sectioning

"Sectioning" means to make a thin slice of a 3D scene around a given plane. At present, this function is supported by the OpenGL drivers. The sectioning is realized by setting a sectioning plane before performing visualization. The sectioning plane can be set by the command,

```
/vis/viewer/set/sectionPlane on x y z units nx ny nz
```

where the vector (x,y,z) defines a point on the sectioning plane, and the vector (nx,ny,nz) defines the normal vector of the sectioning plane. For example, the following sets a sectioning plane to a yz plane at x = 2 cm:

```
/vis/viewer/set/sectionPlane on 2.0 0.0 0.0 cm 1.0 0.0 0.0
```

#### **Cutting away**

"Cutting away" means to remove a half space, defined with a plane, from a 3D scene.

- Cutting away is supported by the DAWNFILE driver "off-line". Do the following:
  - Perform visualization with the DAWNFILE driver to generate a file g4.prim, describing the whole 3D scene.
  - Make the application "DAWNCUT" read the generated file to make a view of cutting away.
- Alternatively, add up to three cutaway planes:

```
/vis/viewer/addCutawayPlane 0 0 0 m 1 0 0 /vis/viewer/addCutawayPlane 0 0 0 m 0 1 0 ...
```

and, for more that one plane, you can change the mode to

- "add" or, equivalently, "union" (default) or
- "multiply" or, equivalently, "intersection":

```
/vis/viewer/set/cutawayMode multiply
```

To de-activate:

```
/vis/viewer/clearCutawayPlanes
```

OpenGL supports this feature.

## 8.4.20 Multithreading commands

Visualising events inevitably slows things down. With multithreading this effect is all the greater. See *Visualization* of trajectories: /vis/scene/add/trajectories command, Additional Note 3, for some advice. If you wish to continue visualising, multithreading mode offers the following fine tuning.

Since GEANT4 version 10.2, in multithreading mode, events generated by worker threads are put in a queue and extracted by a special visualisation thread. If the queue gets full, workers are suspended until the visualisation thread catches up. To mitigate or avoid this try using

```
/vis/multithreading/maxEventQueueSize <N>
/vis/multithreading/actionOnEventQueueFull <wait|discard>
```

(See command guidance for details.)

## 8.5 Controlling Visualization from Compiled Code

While a GEANT4 simulation is running, visualization can be performed without user intervention. This is accomplished by calling methods of the Visualization Manager from methods of the user action classes (G4UserRunAction and G4UserEventAction, for example). In this section methods of the class G4VVisManager, which is part of the graphics\_reps category, are described and examples of their use are given.

## 8.5.1 G4VVisManager

The Visualization Manager is implemented by classes G4VisManager and G4VisExecutive. See Adding Visualization to Your Executable. In order that your GEANT4 be compilable either with or without the visualization category, you should not use these classes directly in your C++ source code, other than in the main() function. Instead, you should use their abstract base class G4VVisManager, defined in the intercoms category.

The pointer to the concrete instance of the real Visualization Manager can be obtained as follows:

```
//---- Getting a pointer to the concrete Visualization Manager instance
G4VVisManager* pVVisManager = G4VVisManager::GetConcreteInstance();
```

The method G4VVisManager::GetConcreteInstance() returns NULL if GEANT4 is not ready for visualization. Thus your C++ source code should be protected as follows:

```
//---- How to protect your C++ source codes in visualization
if (pVVisManager) {
    ...
    pVVisManager ->Draw (...);
    ....
}
```

Note: It pays to encapsulate your Draw messages in *Visualization User Actions*. The vis manager then has control over the drawing and may call your action as required, for example, to refresh the screen or write to file.

## 8.5.2 Visualization of detector components

If you have already constructed detector components with logical volumes to which visualization attributes are properly assigned, you are almost ready for visualizing detector components. Normally you would do this through UI commands - see *Controlling Visualization from Commands*.

However, if you really wish to program visualisation we recommend you invoke vis commands using the ApplyCommand() method.

For example, the following is sample C++ source codes to visualize the detector components:

```
//---- C++ source code: How to visualize detector components (2)
// ... using visualization commands in source codes

G4VVisManager* pVVisManager = G4VVisManager::GetConcreteInstance();

if(pVVisManager)
{
    ... (camera setting etc) ...
    G4UImanager::GetUIpointer()->ApplyCommand("/vis/drawVolume");
    G4UImanager::GetUIpointer()->ApplyCommand("/vis/viewer/flush");
}

//---- end of C++ source code
```

In the above, you should also describe /vis/open command somewhere in your C++ codes or execute the command from (G)UI at the executing stage.

## 8.5.3 Visualization of trajectories

In order to visualize trajectories, you can use the method void G4Trajectory::DrawTrajectory() defined in the tracking category. In the implementation of this method, the following drawing method of G4VVisManager is used:

```
//---- A drawing method of G4Polyline virtual void G4VVisManager::Draw (const G4Polyline&, ...);
```

The real implementation of this method is described in the class G4VisManager.

At the end of one event, a set of trajectories can be stored as a list of G4Trajectory objects. Therefore you can visualize trajectories, for example, at the end of each event, by implementing the method MyEventAction::EndOfEventAction() as follows:

## 8.5.4 Enhanced trajectory drawing

It is possible to use the enhanced trajectory drawing functionality in compiled code as well as from commands. Multiple trajectory models can be instantiated, configured and registered with G4VisManager. For details, see the section on *Controlling from Compiled Code*.

## 8.5.5 HepRep Attributes for Trajectories

The HepRep file formats, HepRepFile and HepRepXML, attach various attributes to trajectories such that you can view these attributes, label trajectories by these attributes or make visibility cuts based on these attributes. If you use the default GEANT4 trajectory class, from /tracking/src/G4Trajectory.cc, available attributes will be:

- Track ID
- Parent ID
- Particle Name
- Charge
- PDG Encoding
- Momentum 3-Vector
- · Momentum magnitude
- · Number of points

You can add additional attributes of your choosing by modifying the relevant part of G4Trajectory (look for the methods GetAttDefs and CreateAttValues). If you are using your own trajectory class, you may want to consider copying these methods from G4Trajectory.

## 8.5.6 Visualization of hits

Hits are visualized with classes G4Square or G4Circle, or other user-defined classes inheriting the abstract base class G4VMarker (*Polylines, Markers and Text*). Drawing methods for hits are not supported by default. Instead, ways of their implementation are guided by virtual methods, G4VHit::Draw() and G4VHitsCollection::DrawAllHits(), of the abstract base classes G4VHit and G4VHitsCollection. These methods are defined as empty functions in the digits+hits category. You can overload these methods, using the following drawing methods of class G4VVisManager, in order to visualize hits:

```
//---- Drawing methods of G4Square and G4Circle
virtual void G4VVisManager::Draw (const G4Circle%, ...);
virtual void G4VVisManager::Draw (const G4Square%, ...);
```

The real implementations of these Draw() methods are described in class G4VisManager.

The overloaded implementation of G4VHits::Draw() will be held by, for example, class *MyTrackerHits* inheriting G4VHit as follows:

```
//---- An example of giving concrete implementation of
        G4VHit::Draw(), using class MyTrackerHit: public G4VHit {...}
void MyTrackerHit::Draw()
   G4VVisManager* pVVisManager = G4VVisManager::GetConcreteInstance();
  if (pVVisManager)
     // define a circle in a 3D space
    G4Circle circle(pos);
    circle.SetScreenSize(0.3);
    circle.SetFillStyle(G4Circle::filled);
     // make the circle red
    G4Colour colour (1., 0., 0.);
    G4VisAttributes attribs(colour);
    circle.SetVisAttributes(attribs);
     // make a 3D data for visualization
    pVVisManager->Draw(circle);
 }
```

The overloaded implementation of G4VHitsCollection::DrawAllHits() will be held by, for example, class *MyTrackerHitsCollection* inheriting class G4VHitsCollection as follows:

```
//---- An example of giving concrete implementation of

// G4VHitsCollection::Draw(),

// using class MyTrackerHit : public G4VHitsCollection{...}

//

void MyTrackerHitsCollection::DrawAllHits()
{
   G4int n_hit = theCollection.entries();
   for(G4int i=0;i < n_hit;i++)
   {
      theCollection[i].Draw();
   }
}</pre>
```

Thus, you can visualize hits as well as trajectories, for example, at the end of each event by implementing the method MyEventAction::EndOfEventAction() as follows:

```
void MyEventAction::EndOfEventAction()
 const G4Event* evt = fpEventManager->GetConstCurrentEvent();
 G4SDManager * SDman = G4SDManager::GetSDMpointer();
 G4String colNam;
 G4int trackerCollID = SDman->GetCollectionID(colNam="TrackerCollection");
 G4int calorimeterCollID = SDman->GetCollectionID(colNam="CalCollection");
 G4TrajectoryContainer * trajectoryContainer = evt->GetTrajectoryContainer();
 G4int n_trajectories = 0;
 if(trajectoryContainer)
  { n_trajectories = trajectoryContainer->entries(); }
 G4HCofThisEvent * HCE = evt->GetHCofThisEvent();
 G4int n_hitCollection = 0;
 if (HCE)
  { n_hitCollection = HCE->GetCapacity(); }
 G4VVisManager* pVVisManager = G4VVisManager::GetConcreteInstance();
 if(pVVisManager) {
    // Declare begining of visualization
   G4UImanager::GetUIpointer()->ApplyCommand("/vis/scene/notifyHandlers");
    // Draw trajectories
   for(G4int i=0; i < n_trajectories; i++) {</pre>
        (*(evt->GetTrajectoryContainer()))[i]->DrawTrajectory();
   // Construct 3D data for hits
   MyTrackerHitsCollection* THC
      (MyTrackerHitsCollection*)(HCE->GetHC(trackerCollID));
    if(THC) THC->DrawAllHits();
   MyCalorimeterHitsCollection* CHC
      (MyCalorimeterHitsCollection*) (HCE->GetHC(calorimeterCollID));
   if(CHC) CHC->DrawAllHits();
    // Declare end of visualization
   G4UImanager::GetUIpointer()->ApplyCommand("/vis/viewer/update");
```

You can re-visualize a physical volume, where a hit is detected, with a highlight color, in addition to the whole set of detector components. It is done by calling a drawing method of a physical volume directly. The method is:

```
//---- Drawing methods of a physical volume
virtual void Draw (const G4VPhysicalVolume&, ...);
```

This method is, for example, called in a method MyXXXHit::Draw(), describing the visualization of hits with markers. The following is an example for this:

```
//---- An example of visualizing hits with
void MyCalorimeterHit::Draw()
{
   G4VVisManager* pVVisManager = G4VVisManager::GetConcreteInstance();
   if(pVVisManager)
   {
    G4Transform3D trans(rot,pos);
    G4VisAttributes attribs;
   G4LogicalVolume* logVol = pPhys->GetLogicalVolume();
```

(continues on next page)

(continued from previous page)

```
const G4VisAttributes* pVA = logVol->GetVisAttributes();
if(pVA) attribs = *pVA;
G4Colour colour(1.,0.,0.);
attribs.SetColour(colour);
attribs.SetForceSolid(true);

//---- Re-visualization of a selected physical volume with red color
pVVisManager->Draw(*pPhys,attribs,trans);
}
```

## 8.5.7 HepRep Attributes for Hits

The HepRep file formats, HepRepFile and HepRepXML, attach various attributes to hits such that you can view these attributes, label trajectories by these attributes or make visibility cuts based on these attributes. Examples of adding HepRep attributes to hit classes can be found in examples /extended/analysis/A01 and /extended/runAndEvent/RE01.

For example, in example RE01's class RE01CalorimeterHit.cc, available attributes will be:

- Hit Type
- Track ID
- Z Cell ID
- Phi Cell ID
- · Energy Deposited
- Energy Deposited by Track
- Position
- · Logical Volume

You can add additional attributes of your choosing by modifying the relevant part of the hit class (look for the methods GetAttDefs and CreateAttValues).

#### 8.5.8 Visualization of text

In GEANT4 Visualization, a text, i.e., a character string, is described by class G4Text inheriting G4VMarker as well as G4Square and G4Circle. Therefore, the way to visualize text is the same as for hits. The corresponding drawing method of G4VVisManager is:

```
//---- Drawing methods of G4Text virtual void G4VVisManager::Draw (const G4Text&, ...);
```

The real implementation of this method is described in class G4VisManager.

## 8.5.9 Visualization of polylines and tracking steps

Polylines, i.e., sets of successive line segments, are described by class G4Polyline. For G4Polyline, the following drawing method of class G4VVisManager is prepared:

```
//---- A drawing method of G4Polyline
virtual void G4VVisManager::Draw (const G4Polyline&, ...);
```

The real implementation of this method is described in class G4VisManager.

Using this method, C++ source codes to visualize G4Polyline are described as follows:

```
//---- How to visualize a polyline
G4VVisManager* pVVisManager = G4VVisManager::GetConcreteInstance();

if (pVVisManager) {
    G4Polyline polyline;
    ..... (C++ source codes to set vertex positions, color, etc)

    pVVisManager -> Draw(polyline);
}
```

Tracking steps are able to be visualized based on the above visualization of G4Polyline. You can visualize tracking steps at each step automatically by writing a proper implementation of class *MySteppingAction* inheriting G4UserSteppingAction, and also with the help of the Run Manager.

First, you must implement a method, MySteppingAction::UserSteppingAction(). A typical implementation of this method is as follows:

```
//---- An example of visualizing tracking steps
void MySteppingAction::UserSteppingAction()
   G4VVisManager* pVVisManager = G4VVisManager::GetConcreteInstance();
   if (pVVisManager) {
     //---- Get the Stepping Manager
     const G4SteppingManager* pSM = GetSteppingManager();
      //---- Define a line segment
     G4Polyline polyline;
     G4double charge = pSM->GetTrack()->GetDefinition()->GetPDGCharge();
     G4Colour colour;
           (charge < 0.) colour = G4Colour(1., 0., 0.);
     else if (charge < 0.) colour = G4Colour(0., 0., 1.);</pre>
                           colour = G4Colour(0., 1., 0.);
     else
     G4VisAttributes attribs(colour);
     polyline.SetVisAttributes(attribs);
     polyline.push_back(pSM->GetStep()->GetPreStepPoint()->GetPosition());
     polyline.push_back(pSM->GetStep()->GetPostStepPoint()->GetPosition());
           -- Call a drawing method for G4Polyline
     pVVisManager -> Draw(polyline);
```

Next, in order that the above C++ source code works, you have to pass the information of the *MySteppingAction* to the Run Manager in the main () function:

```
//---- Passing what to do at each step to the Run Manager
int main()
{
    ...
    // Run Manager
    G4RunManager * runManager = new G4RunManager;

    // User initialization classes
    ...
    runManager->SetUserAction(new MySteppingAction);
    ...
}
```

Thus you can visualize tracking steps with various visualization attributes, e.g., color, at each step, automatically.

As well as tracking steps, you can visualize any kind 3D object made of line segments, using class G4Polyline and its drawing method, defined in class G4VVisManager. See, for example, the implementation of the /vis/scene/

add/axes command.

#### 8.5.10 Visualization User Actions

You can implement the Draw method of G4VUserVisAction, e.g., the class definition could be:

```
class MyVisAction: public G4VUserVisAction {
  void Draw();
};
```

and the implementation:

If efficiency is an issue, create the objects in the constructor, delete them in the destructor and draw them in your Draw method.

Anyway, an instance of your class needs to be registered with the vis manager, e.g.:

```
G4VisManager* visManager = new G4VisExecutive;
visManager->RegisterRunDurationUserVisAction
("My drawings",
    new MyVisAction,
    G4VisExtent(-10*m,10*m,-10*m,10*m,10*m,10*m)); // This 3rd argument is optional.
visManager->Initialize ();
...
```

Any number of actions may be registered either as "run duration" (i.e., permanent, or at least as permanent as detector geometry) or "end of event" or "end of run" through the methods RegisterRunDurationUserVisAction, RegisterEndOfEventUserVisAction or RegisterEndOfRunUserVisAction. The vis manager will invoke your Draw method as appropriate to give your drawing a sort of permanence, for example, that can be drawn from several different angles.

Vis action drawing must be activated by adding to a scene, e.g.

```
/control/verbose 2
/vis/verbose parameters
/vis/open OGL
/vis/scene/create
/vis/scene/add/userAction
/vis/scene/add/axes
/vis/scene/add/scale
/vis/sceneHandler/attach
/vis/viewer/flush
```

The "extent" can be added on registration or on the command line or neither (if the extent of the scene is set by other components). Your Draw method will be called whenever needed to refresh the screen or rebuild a graphics database, for any chosen viewer. The scene can be attached to any scene handler and your drawing will be shown.

### 8.5.11 Standalone Visualization

The above raises the possibility of using GEANT4 as a "standalone" graphics package without invoking the run manager. The following main program (from examples/extended/visualization/standalone), together with a user vis action and a macro file—see above—will allow you to view your drawing interactively on any of the supported graphics systems:

```
#include "globals.hh"
#include "G4VisExecutive.hh"
#include "G4VisExtent.hh"
#include "G4UImanager.hh"
#include "G4UIExecutive.hh"
#include "G4SystemOfUnits.hh"
#include "StandaloneVisAction.hh"
int main(int argc, char** argv) {
  G4UIExecutive* ui = new G4UIExecutive(argc, argv);
  G4VisManager* visManager = new G4VisExecutive;
  \verb|visManager->| Register RunDuration User Vis Action|
    ("A standalone example - 3 boxes, 2 with boolean subtracted cutout",
    new StandaloneVisAction,
    G4VisExtent (-10 * m, 10 * m, -10 * m, 10 * m, -10 * m, 10 * m));
  visManager->Initialize ();
  G4UImanager::GetUIpointer()->ApplyCommand ("/control/execute standalone.mac");
  ui->SessionStart();
  delete ui;
  delete visManager;
```

# 8.5.12 Drawing a solid as a cloud of points

SolidCloudVisAction.hh:

```
#ifndef SOLIDCLOUDVISACTION_HH
#define SOLIDCLOUDVISACTION_HH
#include "G4VUserVisAction.hh"
#include "G4Polymarker.hh"
class G4VSolid;
class SolidCloudVisAction: public G4VUserVisAction {
public:
    SolidCloudVisAction(G4VSolid*, G4int nPoints);
    virtual void Draw();
private:
    G4Polymarker fPolymarker;
};
#endif
```

#### SolidCloudVisAction.cc:

```
#include "SolidCloudVisAction.hh"
#include "G4VVisManager.hh"
#include "G4VSolid.hh"
SolidCloudVisAction::SolidCloudVisAction(G4VSolid* solid, G4int nPoints).
{
    fPolymarker.SetMarkerType(G4Polymarker::dots);
    fPolymarker.SetSize(G4VMarker::screen,1.);
    for (G4int i = 0; i < nPoints; ++i) {</pre>
```

(continues on next page)

(continued from previous page)

```
G4ThreeVector p = solid->GetPointOnSurface();
G4cout << solid->GetName() << " " << p << G4endl;
fPolymarker.push_back(p);
}

void SolidCloudVisAction::Draw() {
G4VVisManager* pVisManager = G4VVisManager::GetConcreteInstance();
if (pVisManager) pVisManager->Draw(fPolymarker);
}
```

Then just after you instantiate the vis manager:

```
G4VSolid* torus = new G4Torus("Torus",2.*cm,5.*cm,6.*cm,0.,CLHEP::twopi);
visManager->RegisterRunDurationUserVisAction
("Torus",
    new SolidCloudVisAction(torus,100000),
    torus->GetExtent());
```

Then on the command line:

```
/vis/scene/create
/vis/scene/add/userAction Torus
/vis/sceneHandler/attach
```




Fig. 8.3: A torus represented by a cloud of points on its surface.

# 8.6 Visualization Attributes

Visualization attributes are extra pieces of information associated with the visualizable objects. This information is necessary only for visualization, and is not included in geometrical information such as shapes, position, and orientation. Typical examples of visualization attributes are Color, Visible/Invisible, Wireframe/Solid. For example, in visualizing a box, the Visualization Manager must know its colour. If an object to be visualized has not been assigned a set of visualization attributes, then an appropriate default set is used automatically.

A set of visualization attributes is held by an instance of class G4VisAttributes defined in the graphics\_reps category. In the following, we explain the main fields of the G4VisAttributes one by one.

# 8.6.1 Visibility

Visibility is a Boolean flag to control the visibility of objects that are passed to the Visualization Manager for visualization. Visibility is set with the following access function:

```
void G4VisAttributes::SetVisibility (G4bool visibility);
```

If you give false to the argument, and if culling is activated (see below), visualization is skipped for objects for which this set of visualization attributes is assigned. The default value of visibility is true.

Note that whether an object is visible or not is also affected by the current culling policy, which can be tuned with visualization commands.

By default the following public static function is defined:

```
static const G4VisAttributes& GetInvisible();
```

which returns a reference to a const object in which visibility is set to false. It can be used as follows:

```
experimentalHall_logical -> SetVisAttributes (G4VisAttributes::GetInvisible());
```

Direct access to the public static const data member G4VisAttributes::Invisible is also possible but deprecated on account of initialisation issues with dynamic libraries.

#### 8.6.2 Colour

#### Construction

Class G4Colour (an equivalent class name, G4Color, is also available) has 4 fields, which represent the RGBA (red, green, blue, and alpha) components of colour. Each component takes a value between 0 and 1. If an irrelevant value, i.e., a value less than 0 or greater than 1, is given as an argument of the constructor, such a value is automatically clipped to 0 or 1. Alpha is opacity. Its default value 1 means "opaque".

A G4Colour object is instantiated by giving red, green, and blue components to its constructor, i.e.,

The default value of each component is 1.0. That is to say, the default colour is "white" (opaque).

For example, colours which are often used can be instantiated as follows:

```
G4Colour white
                   (1.0, 1.0, 1.0); // white
G4Colour white
G4Colour gray
                   (0.5, 0.5, 0.5); // gray
                   (0.0, 0.0, 0.0);
G4Colour black
G4Colour red
                   (1.0, 0.0, 0.0);
G4Colour green
                   (0.0, 1.0, 0.0);
                                      // green
                   (0.0, 0.0, 1.0);
G4Colour blue
                                      // blue
G4Colour cyan (0.0, 1.0, 1.0);
G4Colour magenta (1.0, 0.0, 1.0);
                   (0.0, 1.0, 1.0);
                                      // cyan
G4Colour yellow (1.0, 1.0, 0.0);
                                      // yellow
```

It is also possible to instantiate common colours through static public data member functions:

```
static const G4Colour& White
static const G4Colour& Gray
                               ();
static const G4Colour& Grey
                               ();
static const G4Colour& Black
                              ();
static const G4Colour& Red
                               ();
static const G4Colour& Green
                               ();
static const G4Colour& Blue
                               ():
static const G4Colour& Cyan
                              ();
static const G4Colour& Magenta ();
static const G4Colour& Yellow
```

For example, a local G4Colour could be constructed as:

```
G4Colour myRed(G4Colour::Red());
```

After instantiation of a G4Colour object, you can access to its components with the following access functions:

```
G4double G4Colour::GetRed () const; // Get the red component.
G4double G4Colour::GetGreen () const; // Get the green component.
G4double G4Colour::GetBlue () const; // Get the blue component.
```

#### **Colour Map**

G4Colour also provides a static colour map, giving access to predefined G4Colour's through a G4String key. The default mapping is:

```
G4String
                 G4Colour
                 G4Colour::White
white
gray
                 G4Colour::Gray
                                  ()
                G4Colour::Grey
grey
                                  ()
black
               G4Colour::Black
                                 ()
red
                G4Colour::Red
                G4Colour::Green ()
green
                 G4Colour::Blue
                                 ()
                 G4Colour::Cyan
cyan
                                  ()
magenta
                G4Colour::Magenta ()
yellow
             G4Colour::Yellow ()
```

Colours can be retrieved through the GetColour method:

```
bool G4Colour::GetColour(const G4String& key, G4Colour& result)
```

For example:

```
G4Colour myColour(G4Colour::Black());
if (G4Colour::GetColour("red", myColour)) {
    // Successfully retrieved colour "red". myColour is now red
}
else {
    // Colour did not exist in map. myColour is still black
}
```

To see a list of available named colours, /vis/list. These names may also be used to specify colours in many /vis commands.

If the key is not registered in the colour map, a warning message is printed and the input colour is not changed. The colour map is case insensitive.

It is also possible to load user defined G4Colour's into the map through the public AddToMap method. For example:

```
G4Colour myColour(0.2, 0.2, 0.2, 1);
G4Colour::AddToMap("custom", myColour);
```

This loads a user defined G4Colour with key "custom" into the colour map.

It is also possible to use the colours in g4tools:

```
#include "tools/colors"
...
G4Colour niceColour = tools::get_color_aquamarine<G4Colour>();
```

#### Colour and G4VisAttributes

Class G4VisAttributes holds its colour entry as an object of class G4Colour. A G4Colour object is passed to a G4VisAttributes object with the following access functions:

```
//---- Set functions of G4VisAttributes.
void G4VisAttributes::SetColour (const G4Colour& colour);
void G4VisAttributes::SetColor (const G4Color& color);
```

We can also set RGBA components directly:

The following constructor with G4Colour as its argument is also supported:

```
//---- Constructor of G4VisAttributes
G4VisAttributes::G4VisAttributes (const G4Colour& colour);
```

Note that colour assigned to a G4VisAttributes object is not always the colour that ultimately appears in the visualization. The ultimate appearance may be affected by shading and lighting models applied in the selected visualization driver or stand-alone graphics system.

### 8.6.3 Forcing attributes

As you will see later, you can select a "drawing style" from various options. For example, you can select your detector components to be visualized in "wireframe" or with "surfaces". In the former, only the edges of your detector are drawn and so the detector looks transparent. In the latter, your detector looks opaque with shading effects.

The forced wireframe and forced solid styles make it possible to mix the wireframe and surface visualization (if your selected graphics system supports such visualization). For example, you can make only the outer wall of your detector "wired" (transparent) and can see inside in detail.

Forced wireframe style is set with the following access function:

```
void G4VisAttributes::SetForceWireframe (G4bool force);
```

If you give true as the argument, objects for which this set of visualization attributes is assigned are always visualized in wireframe even if in general, the surface drawing style has been requested. The default value of the forced wireframe style is false.

Similarly, forced solid style, i.e., to force that objects are always visualized with surfaces, is set with:

```
void G4VisAttributes::SetForceSolid (G4bool force);
```

The default value of the forced solid style is false, too.

You can also force auxiliary edges to be visible. Normally they are not visible unless you set the appropriate view parameter. Forcing the auxiliary edges to be visible means that auxiliary edges will be seen whatever the view parameters.

Auxiliary edges are not genuine edges of the volume. They may be in a curved surface made out of polygons, for example, or in plane surface of complicated shape that has to be broken down into simpler polygons. HepPolyhedron breaks all surfaces into triangles or quadrilaterals. There will be auxiliary edges for any volumes with a curved surface, such as a tube or a sphere, or a volume resulting from a Boolean operation. Normally, they are not shown, but sometimes it is useful to see them. In particular, a sphere, because it has no edges, will not be seen in wireframe mode in some graphics systems unless requested by the view parameters or forced, as described here.

To force auxiliary edges to be visible, use:

```
void G4VisAttributes::SetForceAuxEdgeVisible (G4bool force);
```

The default value of the force auxiliary edges visible flag is false.

For volumes with edges that are parts of a circle, such as a tube (G4Tubs), etc., it is possible to force the precision of polyhedral representation for visualisation. This is recommended for volumes containing only a small angle of circle, for example, a thin tube segment.

For visualisation, a circle is represented by an N-sided polygon. The default is 24 sides or segments. The user may change this for all volumes in a particular viewer at run time with /vis/viewer/set/lineSegmentsPerCircle; alternatively it can be forced for a particular volume with:

```
void G4VisAttributes::SetForceLineSegmentsPerCircle (G4int nSegments);
```

#### 8.6.4 Other attributes

Here is a list of Set methods for class G4VisAttributes:

```
void SetVisibility
                          (G4bool);
void SetDaughtersInvisible (G4bool);
void SetColour (const G4Colour&);
void SetColor
                           (const G4Color&);
void SetColour
                           (G4double red, G4double green, G4double blue,
                           G4double alpha = 1.);
void SetColor
                          (G4double red, G4double green, G4double blue,
                           G4double alpha = 1.);
void SetLineWidth
                           (LineStyle);
                           (G4double):
void SetForceWireframe
                          (G4bool);
void SetForceSolid
                           (G4bool);
void SetForceAuxEdgeVisible (G4bool);
void SetForceLineSegmentsPerCircle (G4int nSegments);
// Allows choice of circle approximation. A circle of 360 degrees
// will be composed of nSegments line segments. If your solid has
// curves of D degrees that you need to divide into N segments,
// specify nSegments = N * 360 / D.
void SetStartTime
                           (G4double);
```

(continues on next page)

(continued from previous page)

### 8.6.5 Constructors of G4VisAttributes

The following constructors are supported for class G4VisAttributes:

```
//---- Constructors of class G4VisAttributes

G4VisAttributes (void);

G4VisAttributes (G4bool visibility);

G4VisAttributes (const G4Colour& colour);

G4VisAttributes (G4bool visibility, const G4Colour& colour);
```

# 8.6.6 How to assign G4VisAttributes to a logical volume

In constructing your detector components, you may assign a set of visualization attributes to each "logical volume" in order to visualize them later (if you do not do this, the graphics system will use a default set). You cannot make a solid such as G4Box hold a set of visualization attributes; this is because a solid should hold only geometrical information. At present, you cannot make a physical volume hold one, but there are plans to design a memory-efficient way to do it; however, you can visualize a transient piece of solid or physical volume with a temporary assigned set of visualization attributes.

Class G4LogicalVolume holds a pointer of G4VisAttributes. This field is set and referenced with the following access functions:

```
//---- Set functions of G4VisAttributes

void G4VisAttributes::SetVisAttributes (const G4VisAttributes* pVA);

void G4VisAttributes::SetVisAttributes (const G4VisAttributes& VA);

//---- Get functions of G4VisAttributes

const G4VisAttributes* G4VisAttributes::GetVisAttributes () const;
```

The following is sample C++ source codes for assigning a set of visualization attributes with cyan colour and forced wireframe style to a logical volume:

```
//---- C++ source codes: Assigning G4VisAttributes to a logical volume
...
    // Instantiation of a logical volume
myTargetLog = new G4LogicalVolume( myTargetTube, BGO, "TLog", 0, 0, 0);
...
    // Instantiation of a set of visualization attributes with cyan colour
G4VisAttributes * calTubeVisAtt = new G4VisAttributes(G4Colour(0.,1.,1.));
    // Set the forced wireframe style
calTubeVisAtt->SetForceWireframe(true);
    // Assignment of the visualization attributes to the logical volume
myTargetLog->SetVisAttributes(calTubeVisAtt);
```

Note that the life of the visualization attributes must be at least as long as the objects to which they are assigned; it is the users' responsibility to ensure this, and to delete the visualization attributes when they are no longer needed (or just leave them to die at the end of the job).

#### 8.6.7 Additional User-Defined Attributes

GEANT4 Trajectories and Hits can be assigned additional arbitrary attributes:

- they can be displayed when you click on the relevant object in the FRED or HepRApp browsers. For example, HepRApp then lets you pick objects and see their attributes or select visibility based on these attributes.
- they can be used for filtering of trajectories, hits and digis (see *Trajectory Filtering*).

Define the attributes with lines such as:

Then fill the attributes with lines such as:

```
std::vector<G4AttValue>* values = new std::vector<G4AttValue>;
values->push_back(G4AttValue("PN",ParticleName,""));
s.seekp(std::ios::beg);
s << G4BestUnit(initialMomentum,"Energy") << std::ends;
values->push_back(G4AttValue("IMom",c,""));
```

See geant4/source/tracking/src/G4Trajectory.cc for a good example.

G4AttValue objects are light, containing just the value; for the long description and other sharable information the G4AttValue object refers to a G4AttDef object. They are based on the HepRep standard described at http://www.slac.stanford.edu/~perl/heprep/. GEANT4 also provides a way of checking the results; at the point where all the data members have been set (perhaps in your sensitive detector), for example for hit:

```
G4cout << G4AttCheck(hit->CreateAttValues(),hit->GetAttDefs()) << G4endl;
```

GEANT4 provides some default examples of the use of this facility in the trajectory classes in /source/tracking such as G4Trajectory, G4SmoothTrajectory. G4Trajectory::CreateAttValues shows how G4AttValue objects can be made and G4Trajectory::GetAttDefs shows how to make the corresponding G4AttDef objects and use the G4AttDefStore. Note that the "user" of CreateAttValues guarantees to destroy them; this is a way of allowing creation on demand and leaving the G4Trajectory object, for example, free of such objects in memory. The comments in G4VTrajectory.hh explain further and additional insights might be obtained by looking at two methods which use them, namely G4VTrajectory::DrawTrajectory and G4VTrajectory::ShowTrajectory.

Hits classes in examples /extended/analysis/A01 and /extended/runAndEvent/RE01 show how to do the same for your hits. The base class no-action methods CreateAttValues and GetAttDefs should be overridden in your concrete class. The comments in G4VHit.hh explain further.

In addition, the user is free to add a G4std::vector<G4AttValue>\* and a G4std::vector<G4AttDef>\* to a G4VisAttributes object as could, for example, be used by a G4LogicalVolume object.

At the time of writing, only the HepRep graphics systems are capable of displaying the G4AttValue information, but this information will become useful for all GEANT4 visualization systems through improvements in release 8.1 or later.

# 8.7 Enhanced Trajectory Drawing

# 8.7.1 Default Configuration

Trajectory drawing styles are specified through trajectory drawing models. Each drawing model has a default configuration provided through a G4VisTrajContext object. The default context settings are shown below.

•	
Property	Default Setting
Line colour	grey
Line visibility	true
Draw line	true
Draw auxiliary points	false
Auxiliary point type	squares
Auxiliary point size	2 pixels or mm*
Auxiliary point size type	screen
Auxiliary point fill style	filled
Auxiliary point colour	magenta
Auxiliary point visibility	true
Draw step point	false
Step point type	circles
Step point size	2 pixels or mm*
Step point size type	screen
Step point fill style	filled
Step point colour	yellow
Step point visibility	true
Time slice interval	0

Table 8.4: Default context settings for trajectory drawing models.

**Note:** Different visualisation drivers handle trajectory configuration in different ways, so trajectories may not necessarily get displayed as you have configured them.

# 8.7.2 Trajectory Drawing Models

A trajectory drawing model can override the default context according to the properties of a given trajectory. The following models are supplied with the GEANT4 distribution:

- G4TrajectoryGenericDrawer (generic)
- G4TrajectoryDrawByCharge (drawByCharge)
- G4TrajectoryDrawByParticleID (drawByParticleID)
- G4TrajectoryDrawByOriginVolume (drawByOriginVolume)
- G4TrajectoryDrawByTouchedVolume (drawByTouchedVolume)
- G4TrajectoryDrawByAttribute (drawByAttribute)

Both the context and model properties can be configured by the user. The models are described briefly below, followed by some example configuration commands.

<sup>\*</sup> Depending on size type. If size type == screen, pixels are assumed and no unit need be supplied. If size type == world, a unit must be supplied, e.g., 10 cm.

#### **G4TrajectoryGenericDrawer**

This model simply draws all trajectories in the same style, with the properties provided by the context.

### **G4TrajectoryDrawByCharge**

This is the default model - if no model is specified by the user, this model will be constructed automatically. The trajectory lines are coloured according to charge, with all other configuration parameters provided by the default context. The default colouring scheme is shown below.

Charge	Colour
1	blue
-1	red
0	green

### G4TrajectoryDrawByParticleID

This model colours trajectory lines according to particle type. All other configuration parameters are provided by the default context. Chosen particle types can be highlighted with specified colours. By default, trajectories are coloured according to the scheme below and any other particle in the default colour (grey). (All may be overridden by the set command.)

Particle	Colour
gamma	green
e-	red
e+	blue
pi+	magenta
pi-	magenta
proton	cyan
neutron	yellow

#### G4TrajectoryDrawByOriginVolume

This model colours trajectory lines according to the trajectory's originating volume name. The volume can be either a logical or physical volume. Physical volume takes precedence over logical volume. All trajectories are coloured grey by default.

### G4TrajectoryDrawByTouchedVolume

This model colours trajectory lines if it touches one or more volumes according to the physical volume name(s). It requires rich trajectories, G4RichTrajectory (/vis/scene/add/trajectories rich). All trajectories are coloured grey by default.

#### **G4TrajectoryDrawByAttribute**

This model draws trajectories based on the HepRep style attributes associated with trajectories. Each attribute drawer can be configured with interval and/or single value data. A new context object is created for each interval/single value. This makes it possible to have different step point markers etc, as well as line colour for trajectory attributes falling into different intervals, or matching single values. The single value data should override the interval data, allowing specific values to be highlighted. Units should be specified on the command line if the attribute unit is specified either as a G4BestUnit or if the unit is part of the value string.

# 8.7.3 Controlling from Commands

Multiple trajectory models can be created and configured using commands in the "/vis/modeling/trajectories/" directory. It is then possible to list available models and select one to be current.

Model configuration commands are generated dynamically when a model is instantiated. These commands apply directly to that instance. This makes it possible to have multiple instances of the drawByCharge model for example, each independently configurable through it's own set of commands.

See the interactive help for more information on the available commands.

#### **Example commands**

• Create a generic model named generic-0 by default

```
/vis/modeling/trajectories/create/generic
```

Configure context to colour all trajectories red

```
/vis/modeling/trajectories/generic-0/default/setLineColour red
```

• Create a drawByCharge model named drawCharge-0 by default (Subsequent models will be named drawByCharge-1, drawByCharge-2, etc.)

```
/vis/modeling/trajectories/create/drawByCharge
```

• Create a drawByCharge model named testChargeModel

```
/vis/modeling/trajectories/create/drawByCharge testChargeModel
```

· Configure drawByCharge-0 model

```
/vis/modeling/trajectories/drawByCharge-0/set 1 red
/vis/modeling/trajectories/drawByCharge-0/set -1 red
/vis/modeling/trajectories/drawByCharge-0/set 0 white
```

• Configure testCharge model through G4Colour components

```
/vis/modeling/trajectories/testChargeModel/setRGBA 1 0 1 1 1 1 vis/modeling/trajectories/testChargeModel/setRGBA -1 0.5 0.5 0.5 1 vis/modeling/trajectories/testChargeModel/setRGBA 0 1 1 0 1
```

Create a drawByParticleID model named drawByParticleID-0

```
/vis/modeling/trajectories/create/drawByParticleID
```

· Configure drawByParticleID-0 model

```
/vis/modeling/trajectories/drawByParticleID-0/set gamma red
/vis/modeling/trajectories/drawByParticleID-0/setRGBA e+ 1 0 1 1
```

· List available models

/vis/modeling/trajectories/list

• select drawByParticleID-0 to be current

 $/{\tt vis/modeling/trajectories/select\ drawByParticleID-0}$ 

• Create a drawByAttribute model named drawByAttribute-0

/vis/modeling/trajectories/create/drawByAttribute

• Configure drawByAttribute-0 model

/vis/modeling/trajectories/drawByAttribute-0/verbose true

Select attribute "CPN"

/vis/modeling/trajectories/drawByAttribute-0/setAttribute CPN

• Configure single value data

```
/vis/modeling/trajectories/drawByAttribute-0/addValue brem_key eBrem
/vis/modeling/trajectories/drawByAttribute-0/addValue annihil_key annihil
/vis/modeling/trajectories/drawByAttribute-0/addValue decay_key Decay
/vis/modeling/trajectories/drawByAttribute-0/addValue muIon_key muIoni
/vis/modeling/trajectories/drawByAttribute-0/addValue eIon_key eIoni

/vis/modeling/trajectories/drawByAttribute-0/brem_key/setLineColour red
/vis/modeling/trajectories/drawByAttribute-0/annihil_key/setLineColour green
/vis/modeling/trajectories/drawByAttribute-0/decay_key/setLineColour cyan
/vis/modeling/trajectories/drawByAttribute-0/eIon_key/setLineColour yellow
/vis/modeling/trajectories/drawByAttribute-0/muIon_key/setLineColour magenta
```

• Create a drawByAttribute model named drawByAttribute-1

/vis/modeling/trajectories/create/drawByAttribute

• Select "IMag" attribute

/vis/modeling/trajectories/drawByAttribute-1/setAttribute IMag

· Configure interval data

```
/vis/modeling/trajectories/drawByAttribute-1/addInterval interval1 0.0 keV 2.5MeV /vis/modeling/trajectories/drawByAttribute-1/addInterval interval2 2.5 MeV 5 MeV /vis/modeling/trajectories/drawByAttribute-1/addInterval interval3 5 MeV 7.5 MeV /vis/modeling/trajectories/drawByAttribute-1/addInterval interval4 7.5 MeV 10 MeV /vis/modeling/trajectories/drawByAttribute-1/addInterval interval5 10 MeV 12.5 MeV /vis/modeling/trajectories/drawByAttribute-1/addInterval interval6 12.5 MeV 10000 MeV /vis/modeling/trajectories/drawByAttribute-1/interval1/setLineColourRGBA 0.8 0 0.8 1 /vis/modeling/trajectories/drawByAttribute-1/interval2/setLineColourRGBA 0.23 0.41 1 1 /vis/modeling/trajectories/drawByAttribute-1/interval3/setLineColourRGBA 0 1 0 1 /vis/modeling/trajectories/drawByAttribute-1/interval4/setLineColourRGBA 1 0 1 /vis/modeling/trajectories/drawByAttribute-1/interval5/setLineColourRGBA 1 0.3 0 1 /vis/modeling/trajectories/drawByAttribute-1/interval6/setLineColourRGBA 1 0 0 1
```

Create a drawByEncounteredVolume model named drawByEncounteredVolume-0

/vis/modeling/trajectories/create/drawByEncounteredVolume

• Change the color for a specific encountered shape

```
/vis/modeling/trajectories/drawByEncounteredVolume-0/set Shape1 cyan
```

# 8.7.4 Controlling from Compiled Code

It is possible to use the enhanced trajectory drawing functionality in compiled code as well as from commands. Multiple trajectory models can be instantiated, configured and registered with G4VisManager. Once registered, the models are owned by G4VisManager, and must not be deleted by the user.

Only one model may be current. For example:

```
G4VisManager* visManager = new G4VisExecutive;
visManager->Initialize();

G4TrajectoryDrawByParticleID* model = new G4TrajectoryDrawByParticleID;
G4TrajectoryDrawByParticleID* model2 = new G4TrajectoryDrawByParticleID("test");

model->SetDefault("cyan");
model->Set("gamma", "green");
model->Set("e+", "magenta");
model->Set("e-", G4Colour(0.3, 0.3, 0.3));

visManager->RegisterModel(model);
visManager->RegisterModel(model2);

visManager->SelectTrajectoryModel(model->Name());
```

## 8.7.5 Drawing by time

To draw by time, you need to use G4RichTrajectory, for example:

```
/vis/scene/add/trajectories rich
```

or

```
/vis/scene/add/trajectories rich smooth
```

When you run, you need to create a trajectory model and set the time slice interval (remembering that particles are often relativistic and travel 30 cm/ns):

```
/vis/modeling/trajectories/create/drawByCharge
/vis/modeling/trajectories/drawByCharge-0/default/setDrawStepPts true
/vis/modeling/trajectories/drawByCharge-0/default/setStepPtsSize 5
/vis/modeling/trajectories/drawByCharge-0/default/setDrawAuxPts true
/vis/modeling/trajectories/drawByCharge-0/default/setAuxPtsSize 5
/vis/modeling/trajectories/drawByCharge-0/default/setTimeSliceInterval 0.1 ns
/vis/modeling/trajectories/list
```

and use a graphics driver that can display by time:

```
/vis/open OGL
/vis/drawVolume
/vis/scene/add/trajectories rich
/vis/viewer/set/timeWindow/startTime 0.5 ns
/vis/viewer/set/timeWindow/endTime 0.8 ns
/run/beamOn
/vis/viewer/refresh
```

For tips on how to see particles "moving through time" see Making a Movie.

# 8.8 Trajectory Filtering

Trajectory filtering allows you to visualise a subset of available trajectories. This can be useful if you only want to view interesting trajectories and discard uninteresting ones. Trajectory filtering can be run in two modes:

- **Soft filtering**: In this mode, uninteresting trajectories are marked invisible. Hence, they are still written, but (depending on the driver) will not be displayed. Some drivers, for example the HepRepFile driver, which writes an XML file for the HepRApp browser, will allow you to selectively view these soft filtered trajectories.
- Hard filtering (default): In this mode, uninteresting trajectories are not drawn at all. This mode is especially useful if the job produces huge graphics files, dominated by data from uninteresting trajectories. It is essential to use this mode for most drivers, including those using OpenGL, because they are not adapted for soft filtering.

Change mode with /vis/filtering/trajectories/mode.

Trajectory filter models are used to apply filtering according to specific criteria. The following models are currently supplied with the GEANT4 distribution:

- G4TrajectoryChargeFilter (chargeFilter)
- G4TrajectoryParticleFilter (particleFilter)
- G4TrajectoryOriginVolumeFilter (originVolumeFilter)
- G4TrajectoryTouchedVolumeFilter (touchedVolumeFilter)
- G4TrajectoryAttributeFilter (attributeFilter)

Multiple filters are automatically chained together, and can configured either interactively or in commands or in compiled code. The filters can be inverted, set to be inactive or set in a verbose mode. The above models are described briefly below, followed by some example configuration commands.

#### **G4TrajectoryChargeFilter**

This model filters trajectories according to charge. In standard running mode, only trajectories with charges matching those registered with the model will pass the filter.

### **G4TrajectoryParticleFilter**

This model filters trajectories according to particle type. In standard running mode, only trajectories with particle types matching those registered with the model will pass the filter.

#### G4TrajectoryOriginVolumeFilter

This model filters trajectories according to originating volume name. In standard running mode, only trajectories with originating volumes matching those registered with the model will pass the filter.

#### **G4TrajectoryTouchedVolumeFilter**

This model filters trajectories that touch one or more volumes according to the physical volume name(s). It requires rich trajectories, G4RichTrajectory (/vis/scene/add/trajectories rich). In standard running mode, only trajectories that touch volumes matching those registered with the model will pass the filter.

# G4T rajectory Attribute Filter

This model filters trajectories based on the HepRep style attributes (see *Additional User-Defined Attributes*) associated with trajectories. Each attribute drawer can be configured with interval and/or single value data. Single value data should override the interval data. Units should be specified on the command line if the attribute unit is specified either as a G4BestUnit or if the unit is part of the value string. Available attributes can be shown with /vis/list.

# 8.8.1 Controlling from Commands

Multiple trajectory filter models can be created and configured using commands in the "/vis/filtering/trajectories/" directory. All generated filter models are chained together automatically.

Model configuration commands are generated dynamically when a filter model is instantiated. These commands apply directly to that instance.

See the interactive help for more information on the available commands.

# 8.8.2 Example commands

```
# Create a particle filter. Configure to pass only gammas. Then
# invert to pass anything other than gammas. Set verbose printout,
# and then deactivate filter

/vis/filtering/trajectories/create/particleFilter
/vis/filtering/trajectories/particleFilter-0/add gamma
/vis/filtering/trajectories/particleFilter-0/invert true
/vis/filtering/trajectories/particleFilter-0/verbose true
/vis/filtering/trajectories/particleFilter-0/active false
```

```
# Create a charge filter. Configure to pass only neutral trajectories.
# Set verbose printout. Reset filter and reconfigure to pass only
# negatively charged trajectories.

/vis/filtering/trajectories/create/chargeFilter
/vis/filtering/trajectories/chargeFilter-0/add 0
/vis/filtering/trajectories/chargeFilter-0/verbose true
/vis/filtering/trajectories/chargeFilter-0/reset true
/vis/filtering/trajectories/chargeFilter-0/add -1
```

```
# Create an attribute filter named attributeFilter-0
/vis/filtering/trajectories/create/attributeFilter

# Select attribute "IMag"
/vis/filtering/trajectories/attributeFilter-0/setAttribute IMag

# Select trajectories with 2.5 MeV <= IMag< 1000 MeV
/vis/filtering/trajectories/attributeFilter-0/addInterval 2.5 MeV 1000 MeV</pre>
```

```
# List available attributes
/vis/list

# List filters
/vis/filtering/trajectories/list
```

Note that although particleFilter-0 and chargeFilter-0 are automatically chained, particleFilter-0 will not have any effect since it is has been deactivated.

# 8.8.3 Hit and Digi Filtering

The attribute based filtering can be used on hits and digitisations as well as trajectories. To active the interactive attribute based hit filtering, a filter call should be added to the "Draw" method of the hit (or digi) class:

```
void MyHit::Draw()
{
    ...
    if (! pVVisManager->FilterHit(*this)) return;
    ...
}
```

Interactive filtering can then be done through the commands in /vis/filtering/hits or digi.

# 8.9 Polylines, Markers and Text

Polylines, markers and text are defined in the graphics\_reps category, and are used only for visualization (*Controlling Visualization from Compiled Code*). Users may create any of these objects with local scope; once drawn, they may safely be deleted or allowed to go out of scope.

# 8.9.1 Polylines

A polyline is a set of successive line segments. It is defined with a class G4Polyline defined in the graphics\_reps category. A polyline is used to visualize tracking steps, particle trajectories, coordinate axes, and any other user-defined objects made of line segments.

G4Polyline is defined as a list of G4Point3D objects, i.e., vertex positions. The vertex positions are set to a G4Polyline object with the push\_back() method.

For example, an x-axis with length 5 cm and with red color is defined in shown in the Listing 8.3.

Listing 8.3: Defining an x-axis with length 5 cm and with colour red.

```
//---- An example of defining a line segment
// Instantiate an empty polyline object
G4Polyline x_axis;

// Set red line colour
G4Colour red(1.0, 0.0, 0.0);
G4VisAttributes att(red);
x_axis.SetVisAttributes(&att);

// Set vertex positions
x_axis.push_back( G4Point3D(0., 0., 0.) );
x_axis.push_back( G4Point3D(5.*cm, 0., 0.) );
```

#### 8.9.2 Markers

Here we explain how to use 3D markers in GEANT4 Visualization.

#### What are Markers?

Markers set marks at arbitrary positions in the 3D space. They are often used to visualize hits of particles at detector components. A marker is a 2-dimensional primitive with shape (square, circle, etc), color, and special properties (a) of always facing the camera and (b) of having the possibility of a size defined in screen units (pixels). Here "size" means "overall size", e.g., diameter of circle and side of square (but diameter and radius access functions are defined to avoid ambiguity).

So the user who constructs a marker should decide whether or not it should be visualized to a given size in world coordinates by setting the world size. Alternatively, the user can set the screen size and the marker is visualized to its screen size. Finally, the user may decide not to set any size; in that case, it is drawn according to the sizes specified in the default marker specified in the class G4ViewParameters.

By default, "square" and "circle" are supported in GEANT4 Visualization. The former is described with class G4Square, and the latter with class G4Circle:

Marker Type	Class Name
circle	G4Circle
right square	G4Square

These classes are inherited from class G4VMarker. They have constructors as follows:

```
//---- Constructors of G4Circle and G4Square
G4Circle::G4Circle (const G4Point3D& pos );
G4Square::G4Square (const G4Point3D& pos);
```

Access functions of class G4VMarker are summarized below.

#### Access functions of markers

Listing 8.4 shows the access functions inherited from the base class G4VMarker.

Listing 8.4: The access functions inherited from the base class G4VMarker.

```
//---- Set functions of G4VMarker
void G4VMarker::SetPosition( const G4Point3D& );
void G4VMarker::SetWorldSize( G4double );
void G4VMarker::SetWorldDiameter( G4double );
```

(continues on next page)

(continued from previous page)

```
void G4VMarker::SetScreenSize( G4double );
void G4VMarker::SetScreenDiameter( G4double );
void G4VMarker::SetScreenRadius( G4double );
void G4VMarker::SetFillStyle( FillStyle );
// Note: enum G4VMarker::FillStyle (noFill, hashed, filled);

//---- Get functions of G4VMarker
G4Point3D G4VMarker::GetPosition () const;
G4double G4VMarker::GetWorldSize () const;
G4double G4VMarker::GetWorldDiameter () const;
G4double G4VMarker::GetWorldRadius () const;
G4double G4VMarker::GetScreenSize () const;
G4double G4VMarker::GetScreenDiameter () const;
G4double G4VMarker::GetScreenRadius () const;
FillStyle G4VMarker::GetFillStyle () const;
// Note: enum G4VMarker::FillStyle (noFill, hashed, filled);
```

Listing 8.5 shows sample C++ source code to define a very small red circle, i.e., a dot with diameter 1.0 pixel. Such a dot is often used to visualize a hit.

Listing 8.5: Sample C++ source code to define a very small red circle.

#### 8.9.3 Text

Text, i.e., a character string, is used to visualize various kinds of description, particle name, energy, coordinate names etc. Text is described by the class G4Text. The following constructors are supported:

```
//---- Constructors of G4Text

G4Text (const G4String& text);

G4Text (const G4String& text, const G4Point3D& pos);
```

where the argument text is the text (string) to be visualized, and pos is the 3D position at which the text is visualized.

Text is currently drawn only by the OpenGL drivers, such as OGLIX, OGLIXm and OpenInventor. It is not yet supported on other drivers, including the Windows OpenGL drivers, HepRep, etc.

Note that class G4Text also inherits G4VMarker. Size of text is recognized as "font size", i.e., height of the text. All the access functions defined for class G4VMarker mentioned above are available. In addition, the following access functions are available, too:

```
//---- Set functions of G4Text
void G4Text::SetText ( const G4String& text ) ;
void G4Text::SetOffset ( double dx, double dy ) ;

//---- Get functions of G4Text
G4String G4Text::GetText () const;
G4double G4Text::GetXOffset () const;
G4double G4Text::GetYOffset () const;
```

Method SetText() defines text to be visualized, and GetText() returns the defined text. Method SetOffset() defines x (horizontal) and y (vertical) offsets in the screen coordinates. By default, both offsets are zero, and the text starts from the 3D position given to the constructor or to the method G4VMarker: SetPosition(). Offsets should be given with the same units as the one adopted for the size, i.e., world-size or screen-size units.

Listing 8.6 shows sample C++ source code to define text with the following properties:

Text: "Welcome to Geant4 Visualization"
Position: (0.,0.,0.) in the world coordinates

Horizontal offset: 10 pixels
Vertical offset: -20 pixels
Colour: blue (default)

Listing 8.6: An example of defining text.

```
//---- An example of defining a visualizable text
G4Text text ;
text.SetText ( "Welcome to Geant 4 Visualization");
text.SetPosition ( G4Point3D(0.,0.,0.) );
// These three lines are equivalent to:
   G4Text text ( "Welcome to Geant4 Visualization",
                  G4Point3D(0.,0.,0.));
//---- Size (font size in units of pixels)
G4double fontsize = 24.; // Should be 24. * pixels - to be implemented.
text.SetScreenSize ( fontsize );
G4double x_offset = 10.; // Should be 10. * pixels - to be implemented.
G4double y_offset = -20.; // Should be -20. * pixels - to be implemented.
text.SetOffset( x_offset, y_offset );
//---- Color (Blue is the default setting, and so the codes below are omittable)
G4Colour blue( 0., 0., 1. );
G4VisAttributes att (blue);
text.SetVisAttributes ( att );
```

# 8.10 Making a Movie

These ideas are illustrated in examples/extended/visualization/movies.

These instructions are suggestive only. The following procedures have not been tested on all platforms. There are clearly some instructions that apply only to Unix-like systems with an X-Windows based windowing system. However, it should not be difficult to take the ideas presented here and extend them to other platforms and systems.

The procedures described here need graphics drivers that can produce picture files that can be converted to a form suitable for an MPEG encoder. There may be other ways of capturing the screen images and we would be happy to hear about them. Graphics drivers currently capable of producing picture files are:

Driver	File type
DAWNFILE	prim then eps using dawn
HepRepFile	HepRep1
OGLX	jpeg, eps, pdf, ppm,
Qt	jpeg, eps, pdf, ppm,
RayTracer	jpeg
VRML2FILE	vrml

So far, only DAWNFILE, OGLX, OGLQt and RayTracer have been "road tested".

Once you have a set of files in a standard format, such as pdf or eps, they can be made into a movie.

- iMovie (Apple Mac only):
- Import the created files (PDF recommended).
- Reduce the cliplength to 0.1 s (that seems to be the minimum).
- Export to file.
- Play at x2.
- Convert the files to ppm with **convert** from ImageMagick, then use **ppmtompeg** from SourceForge.
- Use mpeg2encode see *Processing picture files with mpeg2encode*.

## 8.10.1 Using /vis/viewer/interpolate

- Save a sequence of views with /vis/viewer/save (see *How to save a view*.).
- "Fly through" them with /vis/viewer/interpolate (OpenGL and Qt only).
- When you are happy, add the export parameter /vis/viewer/interpolate !!! export.

The procedure is: choose a view, save, choose another view, save, and so on until you have, say, 10 saved views. Then /vis/viewer/interpolate!!! export will produce hundreds of picture files.

From GEANT4 10.5, you can interpolate time windows, and make particles appear to move:

```
# See guidance on /vis/viewer/set/timeWindow/ commands.
/vis/scene/add/trajectories rich
/vis/modeling/trajectories/drawByCharge-0/default/setTimeSliceInterval 0.01 ns
/run/beamOn # or several until you get a good event or events
# Then typically
/vis/viewer/set/timeWindow/displayLightFront true 0 0 -50 cm -0.5 ns
/vis/viewer/set/timeWindow/displayHeadTime true
/vis/viewer/set/timeWindow/fadeFactor 1
/vis/viewer/set/timeWindow/startTime 0 ns 1 ns
/vis/viewer/save
/vis/viewer/set/timeWindow/startTime 1 ns 1 ns
# Then zoom, pan etc to a view of interest and
/vis/viewer/save
# Then repeat with next start time, another view and a save, then try
/vis/viewer/interpolate
# Finally
/vis/viewer/interpolate ! ! ! export
```

See examples/extended/visualization/movies.

# 8.10.2 With a macro loop

Make a macro movie.mac with something like this:

```
/control/verbose 2
#/run/initialize
/vis/open OGL 600x600-0+0
/vis/drawVolume
/vis/viewer/set/style surface
/vis/viewer/set/projection perspective 50 deg
/control/alias phi 30
/control/loop movie.loop theta 0 360 1
```

which invokes movie.loop, which is something like:

```
/vis/viewer/set/viewpointThetaPhi {theta} {phi}
/vis/ogl/export
```

Then on the command line:

```
/control/execute movie.mac
```

It may work better in "batch mode". Assuming your main program is similar to that in example B1, from your terminal:

```
./your-app-name movie.mac
```

# 8.10.3 Processing picture files with mpeg2encode

Say you have produced lots of eps files. Then...

```
make_mpeg2encode_parfile.sh G4OpenGL_*eps
```

Then edit mpeg2encode.par to specify file type and size, etc.:

Then convert to ppm:

```
for i in G4OpenGL*eps;
  do j=`basename $i .eps`; command="convert $i $j.ppm"; echo $command; $command; done
```

Then

```
mpeg2encode mpeg2encode.par G4OpenGL.mpg
```

Then, on Mac, for example:

```
open G4OpenGL.mpg
```

opens a movie player.

### 8.10.4 Qt

The Qt driver provides one of the easiest ways to make a movie. Of course, you first need to add the Qt libraries and link with Qt, but once you have that, Qt provides a ready-made function to store all updates of the OpenGL frame into the movie format. You then use loops (as defined in OGLX section above) or even move/rotate/zoom you scene by mouse actions to form your movie.

The Qt driver automatically handles all of the movie-making steps described in the OGLX section of this document - storing the files, converting them and assembling the finished movie. You just have to take care of installing an mpeg\_encoder.

To make a movie:

- Right click to display a context menu, "Action"-<"Movie parameters".
- Select MPEG encoder path if it was not found.
- Select the name of the output movie.
- Let go! Hit SPACE to Start/Pause recording, RETURN to STOP

Then, open your movie (on Mac, for example):

```
open G4OpenGL.mpg
```

opens a QuickTime player.

### 8.10.5 DAWNFILE

You need to invoke dawn in "direct" mode, which picks up parameters from .DAWN\_1.history, and suppress the GUI:

```
alias dawn='dawn -d'
export DAWN_BATCH=1
```

Change OGL to DAWNFILE in the above set of GEANT4 commands and run. Then convert to ppm files as above:

```
for i in g4_*.eps;
  do j=`basename $i .eps`; command="convert $i $j.ppm"; echo $command; $command; done
```

Then make a .par file:

```
make_mpeg2encode_parfile.sh g4_*ppm
```

and edit mpeg2encode.par:

```
$ diff mpeg2encode.par~ mpeg2encode.par
7c7
< 1
            /* input picture file format: 0=*.Y,*.U,*.V, 1=*.yuv, 2=*.ppm */
> 2
            /* input picture file format: 0=*.Y,*.U,*.V, 1=*.yuv, 2=*.ppm */
909
            /* number of first frame */
< 1
> 0
            /* number of first frame */
15,16c15,16
    /* horizontal size */
   /* vertical_size */
> 482 /* horizontal_size */
> 730 /* vertical_size */
```

Then encode and play:

```
mpeg2encode mpeg2encode.par DAWN.mpg
open DAWN.mpg
```

# 8.10.6 RayTracerX

```
/control/verbose 2
/vis/open RayTracerX 600x600-0+0
# (Raytracer doesn't need a scene; smoother not to /vis/drawVolume.)
/vis/viewer/reset
/vis/viewer/set/style surface
/vis/viewer/set/projection perspective 50 deg
/control/alias phi 30
/control/loop movie.loop theta 0 360 1
```

where movie.loop is as above. This produces lots of jpeg files (but takes 3 days!!!). Then...

```
make_mpeg2encode_parfile.sh g4RayTracer*jpeg
```

Then edit mpeg2encode.par to specify file type and size, etc.:

Then convert to ppm, encode and play:

```
for i in g4*jpeg;
  do j=`basename $i .jpeg`; command="convert $i $j.ppm"; echo $command; $command; done
mpeg2encode mpeg2encode.par g4RayTracer.mpg
open g4RayTracer.mpg
```

# 8.11 Debugging geometry with vis

One command in particular - /vis/drawLogicalVolume (see below) - is designed to highlight geometry overlaps. But you can explore and check your geometry with simple vis commands. Most examples have a vis.mac file that contains these and several other useful commands — examples/basic/Bl/vis.mac is a good place to look.

```
/vis/drawVolume
```

will draw the whole detector and your can rotate and zoom. If you want to see just part of the detector:

```
/vis/drawVolume <sub-detector-physical-volume-name> [<copy-number>]
```

draws all volumes with matching name. You may use a regular expression of the form /regexp/, e.g.:

```
/vis/drawVolume /Shape/
```

draws Shape1 and Shape2 (in example B1).

You can accumulate volumes:

```
/vis/drawVolume <physical-volume-name1>
/vis/scene/add/volume <physical-volume-name2>
```

You can also limit the depth of descent of the geometry hierarchy:

```
/vis/drawVolume ! ! 2
```

draws the world to depth 2.

```
/vis/scene/list # to see what's in the scene.
```

If you are using Qt, what you might find helpful is a little pick icon, 5th from the left on the top menu bar of the Qt GUI. It opens a little window and if you click on a shape its properties are displayed in the window.

With a plain OpenGL window, try /vis/viewer/set/picking.

If you know the place of the volume in the geometry hierarchy (we call it a "touchable"), you can /vis/set/touchable and /vis/touchable/dump. Look at the guidance to see how to use the commands. You might find /vis/drawTree useful.

All vis commands have extensive guidance. Use help or ls on the command line or the Help tab in Qt, or see "Built-in Commands" in the Application Developers Guide.

## 8.11.1 Using advanced vis tools

/vis/drawLogicalVolume can highlight overlaps. But first you may need to identify the offending volumes. *Detecting Overlapping Volumes* describes how to do this.

```
/geometry/test/run
```

gives output such as:

Pick the offending volume name from the error message above:

```
/vis/touchable/findPath Shape1
```

This gives something like the following output:

```
World 0 Envelope 0 Shape1 0 (mother logical volume: Envelope)
Use this to set a particular touchable with "/vis/set/touchable <path>"
or to see overlaps: "/vis/drawLogicalVolume <mother-logical-volume-name>"
```

Then take the mother logical volume name from the above message:




Fig. 8.4: Example B1 with overlapping volumes. (To generate the above one placement in B1::DetectorConstruction::Construct() was moved in order to make an overlap.)

/vis/drawLogicalVolume Envelope /vis/viewer/set/style wireframe

Now we see the offending volumes highlighted in pink, and the sampling points in pale blue.

It may help to see all the points with:

/vis/viewer/set/hiddenMarker false

If by chance the offending volumes are "invisible", make them visible with:

/vis/viewer/set/culling **global** false /vis/viewer/rebuild




Fig. 8.5: Overlaps highlighted.

**CHAPTER** 

NINE

# **ANALYSIS**

# 9.1 Introduction

The analysis category based on g4tools was added in the GEANT4 9.5 release with the aim to provide the users a "light" analysis tool available directly with GEANT4 installation without a need to link their GEANT4 application with an external analysis package. It consists of the analysis manager classes and it includes also the g4tools package.

g4tools provides code to write and read histograms and ntuples in several formats: ROOT, XML AIDA format and CSV (comma-separated values format). It is a part of inlib and exlib libraries, that include also other facilities like fitting and plotting.

Since GEANT4 10.4, the output in HDF5 format is also supported, but requires the HDF5 libraries installation as well as GEANT4 libraries built with the -DGEANT4\_USE\_HDF5=ON CMake option.

The analysis classes provide a uniform, user-friendly interface to g4tools and hide the differences according to a selected output technology from the user. They take care of a higher-level management of the g4tools objects (files, histograms and ntuples), handle allocation and removal of the objects in memory and provide the access methods to them via indexes. They are fully integrated in the GEANT4 framework: they follow GEANT4 coding style and also implement the built-in GEANT4 user interface commands that can be used by users to define or configure their analysis objects.

An example of use of analysis manager classes is provided in basic examples B4 and B5, in their RunAction and EventAction classes.

# 9.2 Analysis Manager Classes

The analysis manager classes provide uniform interfaces to the g4tools package and hide the differences between use of g4tools classes for the supported output formats (ROOT, HDF5, AIDA XML and CSV).

An analysis manager class is available for each supported output format:

- G4CsvAnalysisManager
- G4Hdf5AnalysisManager
- G4RootAnalysisManager
- G4XmlAnalysisManager

Since Geant4 10.7, there is also a new analysis manager class capable to mix output file formats:

• G4GenericAnalysisManager

Mixing of different output types is supported for histogram and profiles objects, only one output type is supported for ntuples.

For a simplicity of use, each analysis manager provides the complete access to all interfaced functions though it is implemented via a more complex design. This design allows the user to use all output technologies in an identical way via a generic G4AnalysisManager type defined as:

```
• using G4AnalysisManager = G4XyzAnalysisManager; where Xyz = Generic, Csv, Hdf5, Root, Xml
```

The managers are implemented as Geant4 singletons. User code will access a pointer to a single instance of the desired manager. The manager is created with the first call to the Instance() function and it is deleted by Geant4 kernel at the end of a user application. All objects created via analysis manager are deleted automatically with the manager. In addition to the G4AnalysisManager functions, a set of GEANT4 UI commands for creating histograms and setting their properties is implemented in associated messenger classes.

## 9.2.1 Analysis Manager

To use GEANT4 analysis, an instance of the analysis manager must be created. The analysis manager object is created with the first call to G4AnalysisManager::Instance(), the next calls to this function will just provide the pointer to this analysis manager object.

The example of the code for creating the analysis manager extracted from the basic B4 example is given below:

```
#include "G4AnalysisManager.hh"

namespace B4
{

RunAction::RunAction()
{
    // Create analysis manager
    auto analysisManager = G4AnalysisManager::Instance();
    analysisManager->SetVerboseLevel(1);
}
```

It is recommended, but not necessary, to create the analysis manager in the user run action constructor. This guarantees correct behavior in multi-threading mode.

The G4AnalysisManager.hh header (new since Geant4 11) defines the G4GenericAnalysisManager as G4AnalysisManager type:

```
#ifndef G4AnalysisManager_h
#define G4AnalysisManager_h
#include "G4GenericAnalysisManager.hh"

using G4AnalysisManager = G4GenericAnalysisManager;
#endif
```

The level of informative printings can be set by SetVerboseLevel (G4int). Currently the levels from 0 (default) up to 4 are supported.

The verbose level can be also set via the UI command:

```
/analysis/verbose level
```

Since Gean4 version 11 the analysis manager is defined as a Geant4 thread-local singleton and users need not and should not delete its instance. Public functions Clear() and Reset() are provided to allow resetting and deleting all allocated analysis objects and clearing their collections:

```
G4bool Reset();
void Clear();
```

The Clear () function can be used as a replacement for deleting the analysis manager in the applications that allocate the analysis data in the begin of run and deleted the analysis manager in the end of run.

## 9.2.2 Files handling

Below we give an example of opening and closing a file extracted from the basic example B4:

```
#include "G4AnalysisManager.hh"

void RunAction::BeginOfRunAction(const G4Run* run)
{
    // Get analysis manager
    auto analysisManager = G4AnalysisManager::Instance();

    // Open an output file
    G4String fileName = "B4.root";
    analysisManager->OpenFile(fileName);
}

void RunAction::EndOfRunAction(const G4Run* aRun)
{
    // Save histograms
    auto analysisManager = G4AnalysisManager::Instance();
    analysisManager->Write();
    analysisManager->CloseFile();
}
```

The following G4AnalysisManager functions are defined for handling files:

```
G4bool OpenFile(const G4String& fileName = "");
G4bool Write();
G4bool CloseFile(G4bool reset = true);
```

The file name can be defined either directly with OpenFile(const G4String&) call or separately via SetFileName(const G4String&) function before calling OpenFile(). It is not possible to change the file name when a file is open and not yet closed. Since Geant4 version 11 multiple files can be hadled at a time, the functions remain valid and define the name of the default file.

The call to Write() triggers writing remaining data to all open files and the call to CloseFile() closing all files and automatic resetting histograms and ntuples data. Since Geant4 10.5, it is possible to close a file without resetting the histogram data. This feature is newly used in example B5 to keep the histograms available for visualization plotting (resetting of histograms is then performed by a call to Reset() in the begin of the next run). Another use case is in MPI extended examples to write the histograms collected on the master rank before they are merged and written in another file.

As G4GenericAnalysisManager can handle all supported file formats, the file names should be provided with an extension (.csv, .hdf5, .root or .xml). To continue using file names without extensions, users can set the default file type using the G4AnalysisManager function (new in Geant4 version 11):

```
void SetDefaultFileType(const G4String& value);
```

#### Multiple files handling

Users can choose to write selected objects in a different file than the default one using the G4AnalysisManager functions

The setting can be also performed with UI commands:

```
/analysis/h1/setFileName id name
/analysis/h1/setFileNameToAll name
... etc. for h2, h3, p1, p2
/analysis/ntuple/setFileName id fileName
/analysis/ntuple/setFileNameToAll fileName
```

While it is possible to mix output types for histogram and profiles objects, only one output type is supported for ntuples. Saving of histograms and ntuple in two output files in a Root file format is demonstrated in the basic B5 example.

The output specific analysis managers (the analysis manager defined via the G4XxxAnalysisManager.hh, Xxx = Csv, Hdf5, Root, Xml include) can also handle multiple files, but all files must be of the same (manager specific) output type.

Depending on the selected output format more files can be generated even when only one file name is set. This is the case of XML, which does not allow writing more than one ntuple in a file, and CSV, which is writing each object (histograms, profile or ntuple) in a separate file. The ntuple (or histogram) file name is then generated automatically from the base file name and the ntuple (or histogram) name.

#### **File Directories**

The file can be optionally structured in sub-directories. Currently only one directory for histograms and/or one directory for ntuples are supported. The directories are created automatically if their names are set to non-empty string values via G4AnalysisManager functions:

```
SetHistoDirectoryName(const G4String&)
SetNtupleDirectoryName(const G4String&)
```

The following commands for handling files and directories are available

```
/analysis/setFileName name  # Set name for the output file
/analysis/setHistoDirName name  # Set name for the histograms directory
/analysis/setNtupleDirName name  # Set name for the histograms directory
```

Since Geant4 version 11, in case of the Csv output type, which does not support a directory structure within a file, directories are interpreted as file system directories. The histogram and ntuple files are saved in directories, if their names are set and if the directories exist in the file system. If a directory does not exists (the existence is checked at SetHisto/NtupleDirectoryName() call), the histograms/ntuples are written in the current directory and a warning is issued.

# 9.2.3 Histograms

The code for handling histograms given in the following example is extracted the B4 example classes. In this example, the histograms are created in the run action constructor and they are filled in the end of event.

```
#include "G4AnalysisManager.hh"

RunAction::RunAction()
{
    // Create analysis manager
    // ...

    // Creating histograms
    analysisManager->CreateH1("Eabs", "Edep in absorber", 100, 0., 800*MeV);
    analysisManager->CreateH1("Egap", "Edep in gap", 100, 0., 100*MeV);
}

void EventAction::EndOfEventAction(const G4Run* aRun)
{
    // Fill histograms
    auto analysisManager = G4AnalysisManager::Instance();
    analysisManager->FillH1(0, fEnergyAbs);
    analysisManager->FillH1(1, fEnergyGap);
}
```

### **Creating Histograms**

A one-dimensional (1D) histogram can be created with one of these two G4AnalysisManager functions:

where name and title parameters are self-descriptive. The histogram edges can be defined either via the nbins, xmin and xmax parameters (first function) representing the number of bins, the minimum and maximum histogram values, or via the const std::vector<G4double>& edges parameter (second function) representing the edges defined explicitly. The other parameters in both functions are optional and their meaning is explained in  $Histograms\ Properties$ .

Two-dimensional (2D) and three-dimensional (3D) histograms can be created with one of these two functions analogous to those for 1D histograms:

(continues on next page)

(continued from previous page)

```
const G4String& xunitName = "none",
const G4String& yunitName = "none",
const G4String& xfcnName = "none",
const G4String& yfcnName = "none");

G4int CreateH3 (const G4String& name, const G4String& title,
G4int nxbins, G4double xmin, G4double xmax,
G4int nybins, G4double ymin, G4double ymax,
G4int nzbins, G4double zmin, G4double zmax,
const G4String& xunitName = "none",
const G4String& yunitName = "none",
const G4String& xfcnName = "none",
const G4String& xfcnName = "none",
const G4String& yfcnName = "none",
const G4String& yfcnName = "none",
const G4String& zfcnName = "none",
```

The meaning of parameters is the same as in the functions for 1D histograms, they are just applied in x, y and z dimensions.

The histograms created with G4AnalysisManager get automatically attributed an integer identifier which value is returned from the "Create" function. The default start value is 0 and it is incremented by 1 for each next created histogram. The numbering of 2D and 3D histograms is independent from 1D histograms and so the first created 2D (or 3D) histogram identifier is equal to the start value even when several 1D histograms have been already created.

The start histogram identifier value can be changed either with the SetFirstHistoId(G4int) method, which applies the new value to all histogram types, or with the SetFirstHNId(G4int), where N=1, 2, 3 methods, which apply the new value only to the relevant histogram type.

All histograms created by G4AnalysisManager are automatically deleted with deleting the G4AnalysisManager object in the end of the application or by the call to G4AnalysisManager::Clear().

Histograms can be also created via UI commands. The commands to create 1D histogram:

const G4String& xbinSchemeName = "linear",
const G4String& ybinSchemeName = "linear",
const G4String& zbinSchemeName = "linear");

```
/analysis/h1/create  # Create 1D histogram
name title [nbin min max] [unit] [fcn] [binScheme]
```

The commands to create 2D histogram:

The commands to create 3D histogram:

```
/analysis/h3/create # Create 3D histogram
name title [nxbin xmin xmax xunit xfcn xbinScheme nybin ymin ymax
yunit yfcn yBinScheme nzbin zmin zmax zunit zfcn zBinScheme]
```

### **Configuring Histograms**

The properties of already created histograms can be changed with use of one of these two functions sets. For 1D histograms:

```
G4bool SetH1 (G4int id,

G4int nbins, G4double xmin, G4double xmax,

const G4String& unitName = "none",

const G4String& fcnName = "none",

const G4String& binSchemeName = "linear");

G4bool SetH1 (G4int id,

const std::vector<G4double>& edges,

const G4String& unitName = "none",

const G4String& fcnName = "none");
```

#### for 2D histograms:

```
G4bool SetH2(G4int id,
            G4int nxbins, G4double xmin, G4double xmax,
             G4int nybins, G4double ymin, G4double ymax,
             const G4String& xunitName = "none",
             const G4String& yunitName = "none",
             const G4String& xfcnName = "none",
            const G4String& yfcnName = "none",
             const G4String& xbinSchemeName = "linear",
             const G4String& ybinSchemeName = "linear");
G4bool SetH2 (G4int id,
            const std::vector<G4double>& xedges,
            const std::vector<G4double>& yedges,
            const G4String& xunitName = "none",
             const G4String& yunitName = "none",
             const G4String& xfcnName = "none"
             const G4String& yfcnName = "none");
```

### and for 3D histograms:

```
G4bool SetH3(G4int id,
             G4int nxbins, G4double xmin, G4double xmax,
             G4int nzbins, G4double zmin, G4double zmax,
             G4int nybins, G4double ymin, G4double ymax,
             const G4String& xunitName = "none",
             const G4String& yunitName = "none",
            const G4String& zunitName = "none",
             const G4String& xfcnName = "none",
             const G4String& yfcnName = "none",
             const G4String& zfcnName = "none",
             const G4String& xbinSchemeName = "linear",
             const G4String& ybinSchemeName = "linear",
             const G4String& zbinSchemeName = "linear");
G4bool SetH3 (G4int id,
            const std::vector<G4double>& xedges,
            const std::vector<G4double>& yedges,
            const std::vector<G4double>& zedges,
             const G4String& xunitName = "none",
             const G4String& yunitName = "none",
             const G4String& zunitName = "none",
             const G4String& xfcnName = "none",
             const G4String& yfcnName = "none",
             const G4String& zfcnName = "none");
```

The histogram is accessed via its integer identifier. The meaning of the other parameters is the same as in "Create" functions.

Histogram properties can be also defined via UI commands. The commands to define 1D histogram

```
/analysis/h1/set id nbin min max [unit] [fcn] [binScheme] # Set parameters
```

The commands to define 2D histogram:

```
# Set parameters for the 2D histogram of #id
/analysis/h2/set
  id nxbin xmin xmax xunit xfcn xbinScheme nybin ymin ymax yunit yfcn yBinScheme
# Set parameters per dimension
/analysis/h2/setX id nbin min max [unit] [fcn] [binScheme] # Set x-parameters
/analysis/h2/setY id nbin min max [unit] [fcn] [binScheme] # Set y-parameters
```

The commands to define 3D histogram:

A limited set of parameters for histograms plotting, the histogram and the histogram axis titles, can be also defined via functions

```
G4bool SetH1Title (G4int id, const G4String& title);
G4bool SetH1XAxisTitle (G4int id, const G4String& title);
G4bool SetH1YAxisTitle (G4int id, const G4String& title);

G4bool SetH2Title (G4int id, const G4String& title);
G4bool SetH2XAxisTitle (G4int id, const G4String& title);
G4bool SetH2YAxisTitle (G4int id, const G4String& title);
G4bool SetH2ZAxisTitle (G4int id, const G4String& title);

G4bool SetH3Title (G4int id, const G4String& title);
G4bool SetH3XAxisTitle (G4int id, const G4String& title);
G4bool SetH3YAxisTitle (G4int id, const G4String& title);
G4bool SetH3ZAxisTitle (G4int id, const G4String& title);
G4bool SetH3ZAxisTitle (G4int id, const G4String& title);
```

The corresponding UI commands

```
/analysis/h1/setTitle id title  # Set title for the 1D histogram of #id
/analysis/h1/setXaxis id title  # Set x-axis title for the 1D histogram
/analysis/h1/setYaxis id title  # Set y-axis title for the 1D histogram
```

The same set of commands is available for the other histogram types and profiles, under the appropriate directory.

#### Filling Histograms

The histogram values can be filled using the functions:

where the weight can be given optionally.

The histograms can be also scaled with a given factor using the functions:

```
G4bool ScaleH1(G4int id, G4double factor);
G4bool ScaleH2(G4int id, G4double factor);
G4bool ScaleH3(G4int id, G4double factor);
```

### **Accessing Histograms**

Besides the fast access to histograms via their integer identifiers, the histograms can be also accessed by their names using the G4AnalysisManager function providing the conversion from a name in a histogram identifier:

```
G4int GetH1Id(const G4String& name, G4bool warn = true) const;
G4int GetH2Id(const G4String& name, G4bool warn = true) const;
G4int GetH3Id(const G4String& name, G4bool warn = true) const;
```

If a histogram with a given name is not found, a warning is issued unless it is explicitly disabled by the user. This way is however less efficient and it is not recommended for frequently called functions as e.g. Fill().

The analysis manager provides also the direct access to the g4tools histogram objects. The concrete histogram type is hidden behind a selected namespace. In example B4, the g4tools histogram functions mean () and rms () are called:

#### **Activation of Histograms**

The activation option allows the user to activate only selected histograms. When this option is activated, only the histograms marked as activated are returned, filled or saved in a file. This feature is intensively used in extended/electromagnetic examples where all histograms are first created inactivated:

```
auto analysisManager = G4AnalysisManager::Instance();
analysisManager->SetActivation(true);
// define histogram parameters name, title, nbins, vmin, vmax
G4int id = analysisManager->CreateH1(name, title, nbins, vmin, vmax);
analysisManager->SetH1Activation(id, false);
```

and then selected histograms are activated in macros, using the analysis "set" command

```
/analysis/h1/set 1 100 0 50 cm #track length of primary /analysis/h1/set 2 100 0 300 none #nb steps of primary
```

The activation option is not switched on by default. It has to be activated either via analysisManager SetActivation(true) call as above or via the UI command:

```
/analysis/setActivation true|false  # Set activation option
```

When no parameters need to be changed a histogram can be activated using "setActivation" command:

### **Histograms Properties**

The following properties, additional to those defined in g4tools, can be added to histograms via G4AnalysisManager:

- *Unit*: if a histogram is defined with a unit, all filled values are automatically converted to this defined unit and the unit is added to the histogram axis title.
- Function: if a histogram is defined with a function, the function is automatically executed on the filled values and its name is added to the histogram axis title. When a histogram is defined with both unit and function the unit is applied first. The available functions: log, log10, exp.
- *Binning scheme*: user can select logarithmic binning scheme besides the linear one (default). The available binning schemes: linear, log.
- Activation: see previous section.
- ASCII option: if activated the histogram is also printed in an ASCII file when Write() function is called.
- *Plotting option*: if activated the histogram is plotted in a file of Postscript format when Write() function is called. See more details in *Plotting*.
- *File name*: if defined, the histogram is written in a new file with the histogram file name which is open at the Write() call and then closed with all files open at CloseFile() call.

#### 9.2.4 Profiles

Profile histograms (profiles) are used to display the mean value of Y and its error for each bin in X. The displayed error is by default the standard error on the mean (i.e. the standard deviation divided by the sqrt(n).) An example of use of 1D profiles can be found in extended/electromagnetic/TestEm2. Though the functions for creating and manipulating profiles are very similar to those for histograms, they are described in this section.

#### **Creating Profiles**

A one-dimensional (1D) profile can be created with one of these two G4AnalysisManager functions

where name and title parameters are self-descriptive. The profile edges can be defined either via the nbins, xmin and xmax parameters (first function) representing the number of bins, the minimum and maximum profile values, or via the const std::vector<G4double>& edges parameter (second function) representing the edges defined explicitly. If ymin and ymax parameters are provides, only values between these limits will be considered at filling time. The other parameters in both functions are optional and their meaning is explained in *Profiles Properties*.

A two-dimensional (2D) profile can be created with one of these two functions analogous to those for 1D profiles:

```
G4int CreateP2(const G4String& name, const G4String& title,
              G4int nxbins, G4double xmin, G4double xmax,
               G4int nybins, G4double ymin, G4double ymax,
               G4double zmin = 0, G4double zmax = 0,
               const G4String& xunitName = "none",
               const G4String& yunitName = "none",
               const G4String& zunitName = "none",
               const G4String& xfcnName = "none",
               const G4String& yfcnName = "none",
               const G4String& zfcnName = "none",
               const G4String& xbinSchemeName = "linear",
               const G4String& ybinSchemeName = "linear");
G4int CreateP2(const G4String& name, const G4String& title,
               const std::vector<G4double>& xedges,
               const std::vector<G4double>& yedges,
               G4double zmin = 0, G4double zmax = 0,
               const G4String& xunitName = "none",
               const G4String& vunitName = "none",
               const G4String& zunitName = "none",
               const G4String& xfcnName = "none",
               const G4String& yfcnName = "none",
               const G4String& zfcnName = "none");
```

The meaning of parameters is the same as in the functions for 1D profiles, they are just applied in x, y and z dimensions.

The profiles created with G4AnalysisManager get automatically attributed an integer identifier which value is returned from the "Create" function. The default start value is 0 and it is incremented by 1 for each next created profile. The numbering of 2D profiles is independent from 1D profiles and so the first created 2D profile identifier is equal to the start value even when several 1D profiles have been already created.

The start profile identifier value can be changed either with the SetFirstProfileId(G4int) method, which applies the new value to both 1D and 2D profile types, or with the SetFirstPNId(G4int), where N = 1, 2 methods, which apply the new value only to the relevant profile type.

All profiles created by G4AnalysisManager are automatically deleted with deleting the G4AnalysisManager object in the end of the application or by the call to G4AnalysisManager::Clear().

Profiles can be also created via UI commands. The commands to create 1D profile

```
/analysis/p1/create  # Create 1D profile
name title [nxbin xmin xmax xunit xfcn xbinScheme ymin ymax yunit yfcn]
```

The commands to create 2D profile:

#### **Configuring Profiles**

The properties of already created profiles can be changed with use of one of these two functions sets. For 1D profiles

```
G4bool SetP1(G4int id,

G4int nbins, G4double xmin, G4double xmax,
G4double ymin = 0, G4double ymax = 0,

const G4String& xunitName = "none",
const G4String& yunitName = "none",
const G4String& xfcnName = "none",
const G4String& yfcnName = "none",
const G4String& xbinSchemeName = "linear");

(continues on next page)
```

(continued from previous page)

```
G4bool SetP1(G4int id,

const std::vector<G4double>& edges,
G4double ymin = 0, G4double ymax = 0,

const G4String& xunitName = "none",

const G4String& yunitName = "none",

const G4String& xfcnName = "none",

const G4String& yfcnName = "none");
```

### and for 2D profiles:

```
G4bool SetP2(G4int id,
             G4int nxbins, G4double xmin, G4double xmax,
             G4int nybins, G4double ymin, G4double ymax,
             G4double zmin = 0, G4double zmax = 0,
             const G4String& xunitName = "none",
             const G4String& yunitName = "none",
             const G4String& zunitName = "none",
             const G4String& xfcnName = "none",
             const G4String& yfcnName = "none",
             const G4String& zfcnName = "none",
             const G4String& xbinSchemeName = "linear",
             const G4String& ybinSchemeName = "linear");
G4bool SetP2 (G4int id,
            const std::vector<G4double>& xedges,
             const std::vector<G4double>& yedges,
             G4double zmin = 0, G4double zmax = 0,
             const G4String& xunitName = "none",
             const G4String& yunitName = "none",
             const G4String& zunitName = "none",
             const G4String& xfcnName = "none",
             const G4String& yfcnName = "none",
             const G4String& zfcnName = "none");
```

The profile is accessed via its integer identifier. The meaning of the other parameters is the same as in "Create" functions.

Profiles properties can be also defined via UI commands. The commands to define 1D profile

```
/analysis/p1/set  # Set parameters for the 1D histogram of #id id nxbin xmin xmax xunit xfcn xbinScheme ymin ymax yunit yfcn
```

The commands to create or define 2D profile:

```
/analysis/p2/set  # Set parameters for the 2D profile of #id id nxbin xmin xmax xunit xfcn xbinScheme nybin ymin ymax yunit yfcn yBinScheme zmin zmax zunit → zfcn
```

A limited set of parameters for profiles plotting, the profile and the profile axis titles, can be also defined via functions

```
G4bool SetP1Title (G4int id, const G4String& title);
G4bool SetP1XAxisTitle (G4int id, const G4String& title);
G4bool SetP1YAxisTitle (G4int id, const G4String& title);
//
G4bool SetP2Title (G4int id, const G4String& title);
G4bool SetP2XAxisTitle (G4int id, const G4String& title);
G4bool SetP2YAxisTitle (G4int id, const G4String& title);
G4bool SetP2YAxisTitle (G4int id, const G4String& title);
G4bool SetP2ZAxisTitle (G4int id, const G4String& title);
```

The parameters can be also set via the same set of UI commands as the histogram parameters available under the appropriate directory.

### **Filling Profiles**

The profile values can be filled using the functions:

```
G4bool FillP1(G4int id,
G4double xvalue, G4double yvalue,
G4double weight = 1.0);
G4bool FillP2(G4int id,
G4double xvalue, G4double yvalue, G4double zvalue,
G4double weight = 1.0);
```

where the weight can be given optionally.

The profiles can be also scaled with a given factor using the functions:

```
G4bool ScaleP1(G4int id, G4double factor);
G4bool ScaleP2(G4int id, G4double factor);
```

### **Profiles Properties**

All histogram features described in sections "Accessing Histograms", "Activation of Histograms" and "Histograms Properties" (Accessing Histograms, Activation of Histograms and Histograms Properties) are also available for profiles.

# 9.2.5 Plotting

Since GEANT4 10.2 version it is possible to produce a graphics output file in the Postscript format containing selected histograms and profiles. Histograms and profiles plotting can be activated using G4AnalysisManager functions:

```
auto analysisManager = G4AnalysisManager::Instance();
analysisManager->SetH1Plotting(id, true);
// etc for H2, H3, P1, P2
```

or using the UI commands

```
/analysis/h1/setPlotting id true|false  # (In)Activate plotting for 1D histogram #id
/analysis/h1/setPlottingToAll true|false  # (In)Activate plotting for all 1D histograms.
# etc. for h2, h3, p1, p2
```

If GEANT4 libraries are built with support for Freetype font rendering, user can choose from three plotting styles:

- ROOT\_default: ROOT style with high resolution fonts (default)
- hippodraw: hippodraw style with high resolution fonts
- inlib\_default: PAW style with low resolution fonts")

otherwise only the inlib\_default style with low resolution fonts is available.

The page size of the graphics output is fixed to A4 format. Users can choose the page layout which is defined by the number columns and the number of rows in a page. Depending on the selected plotting style, the maximum number of plots is limited to 3 columns x 5 rows for the styles with high resolution fonts and to 2 columns x 3 rows for the inlib default style.

Finally, users can also customize the plot dimensions, which represent the plotter window size (width and height) in pixels.

The customization of the plotting can be done via the UI commands in /analysis/plot directory:

```
/analysis/plot/setStyle styleName
/analysis/plot/setLayout columns rows
/analysis/plot/setDimensions width height
```

Opening more configuration parameters for users customisation can be considered in future according to the users feedback.

## 9.2.6 Ntuples

In the following example the code for handling ntuples extracted from basic example B4, from the B4::RunAction and B4a::EventAction classes, is presented.

```
#include "G4AnalysisManager.hh"

RunAction::RunAction()
: G4UserRunAction()
{
    // Create analysis manager
    // ...

    // Create ntuple
    man->CreateNtuple("B4", "Edep and TrackL");
    man->CreateNtupleDColumn("Eabs");
    man->FinishNtuple();
}

void EventAction::EndOfEventAction(const G4Run* aRun)
{
    G4AnalysisManager* man = G4AnalysisManager::Instance();
    man->FillNtupleDColumn(0, fEnergyAbs);
    man->FillNtupleDColumn(1, fEnergyGap);
    man->AddNtupleRow();
}
```

Since 10.0 release, there is no limitation for the number of ntuples that can be handled by G4AnalysisManager. Handling of two ntuples is demonstrated in extended analysis/AnaEx01 example.

### **Creating Ntuples**

An ntuple can be created using the following set of functions:

```
G4int CreateNtuple(const G4String& name, const G4String& title);

// Create columns in the last created ntuple
G4int CreateNtupleXColumn(const G4String& name);

void FinishNtuple();

// Create columns in the ntuple with given id
G4int CreateNtupleXColumn(G4int ntupleId, const G4String& name);

void FinishNtuple(G4int ntupleId);
```

The first set is demonstrated in the example. The columns can take the values of G4int, G4float, G4double or G4String type which is also reflected in the CreateNtupleXColumn() function names. where X can be I, F, D or S.

It is also possible to define ntuple columns of std::vector of G4int, G4float or G4double values using the functions:

where [X, Xtype] can be [I, G4int], [F, G4float] or [D, G4double].

When all ntuple columns are created, the ntuple has to be closed using FinishNtuple() function.

The ntuples created with G4AnalysisManager get automatically attributed an integer identifier which value is returned from the "Create" function. The default start value is 0 and it is incremented by 1 for each next created ntuple. The start ntuple identifier value can be changed with the SetFirstNtupleId (G4int) function.

The integer identifiers are also attributed to the ntuple columns. The numbering of ntuple columns is independent for each ntuple, the identifier default start value is 0 and it is incremented by 1 for each next created column regardless its type (I, F, D or S). (If the third ntuple column of a different type than double (int or float) is created in the demonstrated example, its identifier will have the value equal 2.) The start ntuple column identifier value can be changed with the SetFirstNtupleColumnId (G4int) function.

When calls to CreateNtuple-Column () and FinishNtuple() succeed the call to CreateNtuple(), the ntupleId argument need not to be specified even when creating several ntuples. However this order is not enforced and the second set of functions with ntupleId argument is provided to allow the user to create the ntuples and their columns in whatever order.

All ntuples and ntuple columns created by G4AnalysisManager are automatically deleted with deleting the G4AnalysisManager object in the end of the application or by the call to G4AnalysisManager::Clear().

#### **Filling Ntuples**

The ntuple values of fundamental and string types can be filled using the functions:

```
// Methods for ntuple with id = FirstNtupleId
G4bool FillNtupleFColumn(G4int id, G4int value);
G4bool FillNtuplePColumn(G4int id, G4float value);
G4bool FillNtupleDColumn(G4int id, G4double value);
G4bool FillNtupleSColumn(G4int id, const G4String& value);

// Methods for ntuple with id > FirstNtupleId (when more ntuples exist)
G4bool FillNtupleIColumn(G4int ntupleId, G4int columnId, G4int value);
G4bool FillNtupleFColumn(G4int ntupleId, G4int columnId, G4float value);
G4bool FillNtupleDColumn(G4int ntupleId, G4int columnId, G4double value);
G4bool FillNtupleSColumn(G4int ntupleId, G4int id, const G4String& value);
```

If only one ntuple is defined in the user application, the ntuple identifier, ntupleId, need not to be specified and the first set can be used. The second set of functions has to be used otherwise.

The FillNtupleXColumn () functions should not be called for the columns of vector type, as these are directly associated with the vector reference and so don't need to be filled.

When all ntuple columns are filled, the ntuple fill has to be closed by calling AddNtupleRow():

```
// Methods for ntuple with id = FirstNtupleId
G4bool AddNtupleRow();

// Methods for ntuple with id > FirstNtupleId (when more ntuples exist)
G4bool AddNtupleRow(G4int ntupleId);
```

### **Accessing Ntuples**

The ntuples g4tools objects can be accessed by their identifier. The concrete ntuple type is hidden behind a selected namespace:

```
auto analysisManager = G4AnalysisManager::Instance();
// If only one ntuple is defined
G4Ntuple* ntuple = analysisManager->GetNtuple();
// If more ntuples
G4int ntuple id = ...;
G4Ntuple* ntuple = analysisManager->GetNtuple(ntupleId);
```

### **Activation of Ntuples**

Similarly as for histograms, the activation option can be also applied to ntuples either using the G4AnalysisManager functions

```
void SetNtupleActivation(G4bool activation);
void SetNtupleActivation(G4int id, G4bool activation);
```

or the UI commands

# 9.2.7 Parallel Processing

As well as all other GEANT4 categories, the analysis code has been adapted for multi-threading. In multi-threading mode, the analysis manager instances are internally created on the master and thread workers and data accounting is processed in parallel on workers threads.

Histograms produced on thread workers are automatically merged on Write() call and the result is written in a master file. Merging is protected by a mutex locking, using G4AutoLock utility.

Ntuples produced on thread workers are, by default, written on separate files, which names are generated automatically from a base file name, a thread identifier and eventually also an ntuple name. Since GEANT4 version 10.3 it is possible to activate merging of ntuples with the ROOT output type:

```
auto analysisManager = G4AnalysisManager::Instance();
analysisManager->SetNtupleMerging(true);
```

The ntuples produced on workers will be then progressively being merged to the main ntuples on the master.

By default, the nuples are written at the same file as the final histograms. Users can also select merging in a given number of files via the optional parameter of the SetNtupleMerging() function:

```
void SetNtupleMerging(G4bool mergeNtuples, G4int nofReducedNtupleFiles = 0);
```

No merging of ntuples is provided with HDF5, CSV and AIDA XML formats.

Users can override the defaults and change the ntuple merging mode with a new function (since 10.5, with the added second argument in 10.6):

```
void SetNtupleRowWise(G4bool rowWise, G4bool rowMode = true);
```

The available merging modes:

- *column-wise not preserving rows* (rowWise = false, rowMode=false)

  The fastest option, but without preserving the ntuple rows after merging.
- row-wise (rowWise = true, rowMode value is not used)
  In order to preserve an "event point of view" (the ntuple rows) after merging, a row-wise merging mode was introduced in 10.4 and became a default in 10.5. In this mode, columns are defined as leaves of a single TBranch attached to each ntuple per worker.

This approach has an inconvenience that as column-wise is used in sequential mode and row-wise is used in parallel, the user will have different data schema (different organizations of TBranches and TLeaves) in files, which may complicate his life when reading back his data. While this does not affect a simple analysis using TTree::Draw("branchName"), different methods need to be used to access the data per branch. The example macros with a simple analysis are provided in basic examples (for example B4/macros/plotNtuple.C) and a complete access to data is demonstrated in several extended examples (for example medical/dna/dnaphysics/plot.C).

column-wise with preserving rows (rowWise = false, rowMode=true)
 The column-wise mode enhanced with preserving the ntuple rows, it became a default in 10.6. It requires larger memory size than the other two modes depending on the users applications.

Users can also change the default values of basket size (32000) and basket entries (4000) using new functions (since 10.6).

```
void SetBasketSize(unsigned int basketSize);
void SetBasketEntries(unsigned int basketEntries);
```

In previous Geant4 versions the basket size could be set as an optional argument of the SetNtupleMerging function.

To simplify the scaling of a GEANT4 application across nodes on a cluster GEANT4 provides the support of MPI. In particular it is possible to run a hybrid MPI/MT application that uses MPI to scale across nodes and MT to scale across cores. This is demonstrated in the extended example parallel/MPI/exMPI03 which includes usage of GEANT4 analysis for histograms.

A new example parallel/MPI/exMPI04, the same as exMPI03 with added ntuple, shows how to merge, using g4tools, ntuples via MPI in sequential mode, so that the entire statistics is accumulated in a single output file. If MT is enabled, the ntuples are merged from threads to files per ranks. Combined MT + MPI merging is not yet supported.

# 9.2.8 Coexistence of Several Managers

The specific manager classes are singletons and so it is not possible to create more than one instance of an analysis manager of one type, e.g. G4RootAnalysisManager. However two analysis manager objects of different types can coexist. Then instead of the generic G4AnalysisManager typedef the concrete type of each manager has to be given explicitly.

```
#include "G4CsvAnalysisManager.hh"
#include "G4XmlAnalysisManager.hh"

auto csvManager = G4CsvAnalysisManager::Instance();
auto xmlManager = G4XmlAnalysisManager::Instance();
```

# 9.2.9 Supported Features and Limitations

The analysis category based on g4tools is provided with certain limitations that can be reduced according to the feedback from GEANT4 users and developers.

Below is a summary of currently supported features in Root, Hdf5, Csv and Xml manager classes:

- Histogram types: 1D, 2D, 3D of double
- Profile types: 1D, 2D of double
- Ntuple column types: int, float, double, G4String, std::vector<int>, std::vector<float>, std::vector<std::string>
- Optional directory structure limited to one directory for histograms and/or one for ntuples

# 9.3 Analysis Reader Classes

The analysis reader classes allow to read in g4analysis objects from the files generated by the analysis manager(s) during processing GEANT4 application.

An analysis reader class is available for each supported output format:

- G4CsvAnalysisReader
- G4Hdf5AnalysisReader
- G4RootAnalysisReader
- G4XmlAnalysisReader

For a simplicity of use, each analysis reader provides the complete access to all interfaced functions though it is implemented via a more complex design. This design allows the user to use all output technologies in an identical way via a generic G4AnalysisReder type defined as:

```
• using G4AnalysisReder = G4XyzAnalysisReader; where Xyz = Csv, Hdf5, Root, Xml
```

The readers are implemented as Geant4 singletons. User code will access a pointer to a single instance of the desired reader object. The reader is created with the first call to the Instance() function and it is deleted by Geant4 kernel at the end of a user application. All objects created via analysis reader are deleted automatically with the manager.

While the histograms and profiles objects handled by the analysis reader are of the same type as those handled by the analysis manager, the reader's ntuple type is different.

All objects read with G4AnalysisReader (histograms, profiles and ntuples) get automatically attributed an integer identifier which value is returned from the "Read" or "GetNtuple" function. The default start value is 0 and it is incremented by 1 for each next created object. The numbering each object type is independent from other objects types and also from the numbering of the same object type in analysis manager. The start identifier value can be changed in the same way as with the analysis manager (see *Creating Histograms*).

The read objects can be accessed in the analysis reader via their integer identifiers or by their names in the same way as in the analysis manager (see *Accessing Histograms*). Note that the type of read ntuple is different from the ntuple type in the analysis manager.

The specific manager classes are singletons and so it is not possible to create more than one instance of an analysis reader of one type, e.g. G4RootAnalysisReader. However two analysis reader objects of different types can coexist (see also *Coexistence of Several Managers*).

As well as all other GEANT4 categories, the analysis code has been adapted for multi-threading. In multi-threading mode, the analysis reader instances are internally created on the master or thread workers, depending on the client code call, and data reading can be processed in parallel on workers threads.

# 9.3.1 Analysis Reader

For reading in the output files created with G4AnalysisManager, an instance of the analysis reader must be created. The analysis reader object is created with the first call to G4AnalysisReader::Instance() the next calls to this function will just provide the pointer to this analysis manager object.

The example of the code for creating the analysis reader for the Root output type is given below:

```
#include "G4RootAnalysisReader.hh"

using G4AnalysisReader = G4RootAnalysisReader;

// Create (or get) analysis reader
auto analysisReader = G4AnalysisReader::Instance();
analysisReader->SetVerboseLevel(1);
```

The using declaration defines the G4RootAnalysisReader as G4AnalysisReader type.

The level of informative printings can be set by SetVerboseLevel (G4int). Currently the levels from 0 (default) up to 4 are supported.

# 9.3.2 File handling

The name of file to be read can be specified either via G4AnalysisReader::SetFileName() function, or directly when reading an object. It is possible to change the base file name at any time. The analysis reader can handle more than one file at same time.

```
auto analysisReader = G4AnalysisReader::Instance();
// Define a base file name
analysisReader->SetFileName("MyFileName");
```

The following functions are defined for handling files:

```
void SetFileName(const G4String& fileName);
G4String GetFileName() const;
```

A file is open only when any "Read" function is called. When more objects are read from the same file (Xml, Root), the file is open only once. When reading an object without specifying the file name explicitly in "Read" call, the object is searched in all open files in the order of their creation time.

# 9.3.3 Histograms and Profiles

In the following example the code for reading an histogram is presented.

The histograms and profiles can be read with these G4AnalysisReader functions:

```
G4int ReadH1 (const G4String& h1Name, const G4String& fileName = "");
G4int ReadH2 (const G4String& h2Name, const G4String& fileName = "");
G4int ReadH3 (const G4String& h3Name, const G4String& fileName = "");
G4int ReadP1 (const G4String& h1Name, const G4String& fileName = "");
G4int ReadP2 (const G4String& h2Name, const G4String& fileName = "");
```

where hNname is the name of the object to be read from a file. The file name can be defined explicitly for each reading object.

All histograms and profiles created by G4AnalysisReader are automatically deleted with deleting the G4AnalysisReader object in the end of the application.

# 9.3.4 Ntuples

In the following example the code for reading ntuples is presented.

When the ntuple columns are associated with the variables of the appropriate type, the ntuple they can be read in a loop with GetNtupleRow() function. The function returns true until all data are read in.

An overview of all available functions for ntuple reading is given below:

where [X, Xtype] in SetNtupleXColumn() can be [I, G4int], [F, G4float], [D, G4double] or [S, G4String].

All ntuples and ntuple columns created by G4AnalysisReader are automatically deleted with deleting the G4AnalysisReader object in the end of the application.

# 9.4 Accumulables

The classes for users accumulables management were added in 10.2 release for the purpose of simplification of users application code. The accumulables objects are named variables registered to the accumulable manager, which provides the access to them by name and performs their merging in multi-threading mode according to their defined merge mode. Their usage is demonstrated in the basic examples B1 and B3a.

To better reflect the meaning of these objects, the classes base name "Parameter" used in 10.2 was changed in "Accumulable" in 10.3. Further integration in the GEANT4 framework is foreseen in the next GEANT4 versions.

### 9.4.1 G4Accumulable<T>

G4Accumulable<T> templated class can be used instead of built-in types in order to facilitate merging of the values accumulated on workers to the master thread. The G4Accumulable<T> object has, besides its value of the templated type T, also a name, the initial value, which the value is set to in Reset () function and a merge mode, specifying the operation which is performed in Merge () function.

accumulable object be and can either instantiated using its constructor registered in G4AccumulablesManager explicitly, or it can be created using G4AccumulablesManager::CreateAccumulable() function, their registering is then automatic. The first way is used in the basic examples B1 and B3a:

```
// B1/include/RunAction.hh
class RunAction : public G4UserRunAction
{
    // ...
    private:
        G4Accumulable<G4double> fEdep = 0.;
        G4Accumulable<G4double> fEdep2 = 0.;
};

// B1/src/RunAction.cc
RunAction::RunAction()
{
    // ..
    // Register accumulable to the accumulable manager
    G4AccumulableManager* accumulableManager = G4AccumulableManager::Instance();
    accumulableManager->RegisterAccumulable(fEdep);
    accumulableManager->RegisterAccumulable(fEdep2);
}
```

An alternative way of creating an accumulable using G4AccumulablesManager is demonstrated below:

```
// B1/src/RunAction.cc
RunAction::RunAction()
{
    // ..
    // Accumulables can be also created via accumulable manager
    G4AccumulableManager* accumulableManager = G4AccumulableManager::Instance();
    accumulableManager->CreateAccumulable<G4double>("EdepBis", 0.);
    accumulableManager->CreateAccumulable<G4double>("Edep2Bis", 0.);
}
```

The G4AccumulablesManager takes ownership of the accumulables created by its CreateAccumulable() function the accumulables allocated in the user code has to be deleted in the user code.

Since GEANT4 10.3, the name of the accumulable can be omitted. A generic name "accumulable\_N", where N is the current number of registered objects, will be then attributed.

In multi-threading mode all accumulables registered to G4AccumulablesManager accumulated on workers can

9.4. Accumulables 401

be merged to the master thread by calling G4AccumulablesManager::Merge() function. This step may be not necessary in future after a planned closer integration of G4Accumulable classes in the GEANT4 kernel.

```
// B1/src/RunAction.cc
void RunAction::EndOfRunAction(const G4Run* run)
{
    // ...
    // Merge accumulables
    G4AccumulableManager* accumulableManager = G4AccumulableManager::Instance();
    accumulableManager->Merge();
}
```

The merging mode can be specified using the third (or the second one, if the name is omitted) G4Accumulable<T> constructor argument. The merge modes are defined in G4MergeMode class enumeration:

The default accumulable merge operation is addition.

The registered accumulables can be accessed via G4AccumulablesManager by name or by the id, attributed in the order of registering:

```
// ...
G4AccumulableManager* accumulableManager = G4AccumulableManager::Instance();
// Access accumulables by name
G4double edepBis = accumulableManager->GetAccumulable<G4double>("EdepBis")->GetValue();
G4double edep2Bis = accumulableManager->GetAccumulable<G4double>("Edep2Bis")->GetValue();
// Access accumulables by id
G4VAccumulable* accumulable = accumulableManager->GetAccumulable(id);
```

### 9.4.2 User defined accumulables

Users can define their own accumulable class derived from G4VAccumulable abstract base class. An example of a ProcessCounterAccumulable class, implementing an accumulable holding a map of the processes occurrences by the processes names, is given below. Such processes occurrences map is used in several electromagnetic extended examples, e.g. TestEm1.

ProcCounterAccumulable.hh:

(continues on next page)

(continued from previous page)

```
std::map<G4String,G4int> fProcCounter;
};
```

ProcCounterAccumulable.cc:

The implementation of the CountProcesses () function is identical as in Run::CountProcesses () function in TestEm1.

# 9.5 g4tools

g4tools is a "namespace protected" part of inlib and exlib which is of some interest for GEANT4, mainly the histograms, the ntuples and the code to write them at the ROOT, HDF5, AIDA XML and CSV file formats. The idea of g4tools is to cover, with a very light and easy to install package, what is needed to do analysis in a "GEANT4 batch program".

As <code>g4tools</code> is distributed through GEANT4 and in order to avoid potential namespace clashes with other codes that use the <code>inlib/exlib</code> to do GEANT4 visualization (as for the <code>g4view</code> application or some of the exlib examples), the <code>inlib</code> and <code>exlib</code> namespaces had been automatically changed to <code>tools</code> in the <code>g4tools</code> distribution. Since in principle GEANT4 users will not have to deal directly with the <code>g4tools</code> classes, but will manipulate histograms and ntuples through the <code>G4AnalysisManager</code>, we are not going to extensively document the <code>g4tools</code> classes here. Interested people are encouraged to go at the <code>inlib/exlib</code> web pages for that (see <code>inlib/exlib</code> site).

9.5. q4tools 403

# 9.5.1 g4tools package

## g4tools code is pure header

As explained in inlib/exlib, the code found in g4tools is "pure header". This comes from the need to have an easy way to build applications, as the ioda one, from smartphone, passing by tablets and up to various desktops (UNIX and Windows). For example, if building an application targeted to the Apple AppStore and GooglePlay, the simplest way is to pass through Xcode and the Android make system (or Eclipse), and having not to build libraries simplifies a lot the handling of all these IDEs for the same application. A fallback of that is that the installation of g4tools (if not using the one coming with GEANT4) is straightforward, you simply unzip the file containing the source code! To build an application using g4tools, as for inlib/exlib, you simply have to declare to your build system the "-I" toward the unfolded directory and do "Build and Run".

### g4tools test

g4tools comes with test programs of its own that may be useful in case of problems (for example porting on a not yet covered platform). You can build and run them with:

```
UNIX> <get g4tools.zip>
UNIX> <unzip g4tools.zip>
UNIX> cd g4tools/test/cpp
UNIX> ./build
UNIX> ./tools_test_histo
UNIX> ./tools_test_wroot
UNIX> etc...
```

#### and on Windows:

```
DOS> <setup VisualC++ so that CL.exe is in your PATH>
DOS> <get g4tools.zip>
DOS> <unzip g4tools.zip> (you can use the unzip.exe of CYGWIN)
DOS> cd g4tools\test\cpp
DOS> .\build.bat
DOS> .\tools_test_histo.exe
DOS> .\tools_test_wroot.exe
DOS> etc...
```

#### g4tools in GEANT4

The <code>g4tools</code> header files are distributed in the <code>GEANT4</code> source in the <code>source/analysis/include/tools</code> directory and in the <code>GEANT4</code> installation, they are installed in <code>include/tools</code> directory. The <code>g4tools</code> test programs, included only in <code>GEANT4</code> development versions, can be downloaded with the <code>g4tools-[version]</code>. <code>zip</code> file from the <code>inexlib</code> development site).

While the GEANT4 analysis manager provides the methods for booking and filling the g4tools objects, it does not interface all public functions. Users can access the g4tools objects (see *Accessing Histograms*) and use the g4tools API described in the next section to get the needed informations.

### 9.5.2 User API

We describe here some of the public methods potentially seen by a user doing analysis.

### **Booking and filling**

```
hld(const std::string& title, unsigned int Xnumber, double Xmin, double Xmax);
hld(const std::string& title, const std::vector<double>& edges);
bool fill(double X, double Weight = 1);
```

#### example

```
#include <tools/histo/h1d>
#include <tools/randd>
...
tools::histo::h1d h("Gauss",100,-5,5);
tools::rgaussd rg(1,2);
for(unsigned int count=0;count<entries;count++) h.fill(rg.shoot(),1.4);</pre>
```

#### Mean and rms

```
tools::histo::hld h("Gauss",100,-5,5);
...
std::cout << " mean " << h.mean() << ", rms " << h.rms() << std::endl;</pre>
```

#### Bin infos

When doing a:

```
bool fill(double X, double Weight = 1);
```

the histogram class maintains, for each bin, the number of entries, the sum of weights that we can note "Sw", the sum of W by W "Sw2", the sum of X by Weight "Sxw", the sum of X by X by W "Sx2w". Then bin method names reflect these notations, for example to get the 50 bin sum of X\*X\*W:

```
double Sx2w = h.bin_Sx2w(50);
```

and the same for the other sums:

```
double Sw = h.bin_Sw(50);
double Sw2 = h.bin_Sw2(50);
double Sxw = h.bin_Sxw(50);
unsigned int n = h.bin_entries(50);
```

You can have also all infos on all bins with:

```
tools::histo::hld h(...);
...
const std::vector<unsigned int>& _entries = h.bins_entries();
const std::vector<double>& _bins_sum_w = h.bins_sum_w();
const std::vector<double>& _bins_sum_w2 = h.bins_sum_w2();
const std::vector< std::vector<double>>& _bins_sum_xw = h.bins_sum_xw();
const std::vector< std::vector<double>>& _bins_sum_xw = h.bins_sum_xw();
const std::vector< std::vector<double>>& _bins_sum_x2w = h.bins_sum_x2w();
```

for example to dump bin 50 of an histo booked with 100 bins:

9.5. g4tools 405

(Take care that the [0] entries in the upper vectors are for the "underflow bin" and the last one is for the "overflow bin").

#### All data

You can get all internal data of an histo through the histo\_data class:

```
const tools::histo::hld::hd_t& hdata = h.dac(); //dac=data access.
```

and then, for example, find back the bins infos with:

```
const std::vector<unsigned int>& _entries = hdata.m_bin_entries;
const std::vector<double>& _bins_sum_w = hdata.m_bin_Sw;
const std::vector<double>& _bins_sum_w2 = hdata.m_bin_Sw2;
const std::vector< std::vector<double> >& _bins_sum_xw = hdata.m_bin_Sxw;
const std::vector< std::vector<double> >& _bins_sum_xw = hdata.m_bin_Sxw;
const std::vector< std::vector<double> >& _bins_sum_x2w = hdata.m_bin_Sx2w;
// dump bin 50:
std::cout << "entries[50] = " << _entries[50] << std::endl;
std::cout << "sum_w[50] = " << _bins_sum_w[50] << std::endl;
std::cout << "sum_w2[50] = " << _bins_sum_w2[50] << std::endl;
std::cout << "sum_xw[50] = " << _bins_sum_xw[50][0] << std::endl; //0 = xaxis
std::cout << "sum_x2w[50] = " << _bins_sum_x2w[50][0] << std::endl; //0 = xaxis</pre>
```

See the tools/histo/histo\_data class for all internal fields.

### **Projections**

From a 2D histo, you can get the x projection with:

```
tools::histo::h1d* projection = tools::histo::projection_x(h2d, "ProjX");
...
delete projection;
```

See test/cpp/histo.cpp for example code. Other slicing and projection methods are:

```
// h2d -> h1d. (User gets ownership of the returned object).
h1d* slice_x(const h2d&, int y_beq_ibin, int y_end_ibin, const std::string& title);
hld* projection_x(const h2d&,const std::string& title);
hld* slice_y(const h2d&,int x_beg_ibin,int x_end_ibin,const std::string& title);
h1d* projection_y (const h2d&, const std::string& title);
// h2d -> p1d. (User gets ownership of the returned object).
pld* profile_x(const h2d&,int y_beg_ibin,int y_end_ibin,const std::string& title);
pld* profile_x(const h2d&,const std::string&);
pld* profile_y(const h2d&,int x_beg_ibin,int x_end_ibin,const std::string& title);
pld* profile_y(const h2d&,const std::string& title);
// h3d -> h2d. (User gets ownership of the returned object).
h2d* slice_xy(const h3d&,int z_beg_ibin,int z_end_ibin,const std::string& title);
h2d* projection_xy(const h3d&,const std::string& title);
h2d* slice_yz(const h3d&,int x_beg_ibin,int x_end_ibin,const std::string& title);
h2d* projection_yz(const h3d&,const std::string& title);
h2d* slice_xz(const h3d&,int y_beg_ibin,int y_end_ibin,const std::string& title);
h2d* projection_xz(const h3d&,const std::string& title);
```

**CHAPTER** 

**TEN** 

# **EXAMPLES**

# 10.1 Introduction

The GEANT4 toolkit includes several fully coded examples that demonstrate the implementation of the user classes required to build a customized simulation.

The new "basic" examples cover the most typical use-cases of a GEANT4 application while keeping simplicity and ease of use. They are provided as a starting point for new GEANT4 application developers.

A set of "extended" examples range from the simulation of a non-interacting particle and a trivial detector to the simulation of electromagnetic and hadronic physics processes in a complex detector. Some of these examples require some libraries in addition to those of GEANT4.

The "advanced" examples cover the use-cases typical of a "toolkit"-oriented kind of development, where real complete applications for different simulation studies are provided.

All examples can be compiled and run without modification. Most of them can be run both in interactive and batch mode using the input macro files (\*.in) and reference output files (\*.out) provided. Most examples are run routinely as part of the validation, or testing, of official releases of the GEANT4 toolkit.

The previous set of examples oriented to novice users, "novice", has been refactored in "basic" and "extended" examples sets in GEANT4 10.0. The information about the original set of these examples can be found at the last section of this chapter.

# 10.2 Basic Examples

# 10.2.1 Basic Examples Summary

Descriptions of the 5 basic examples are provided here along with links to source code documentation automatically generated with Doxygen.

Example B1 (see also Doxygen page)

- Simple geometry with a few solids
- Geometry with simple placements (G4PVPlacement)
- Scoring total dose in a selected volume in user action classes
- Using G4Accumulable for automatic merging of scored values inmulti-threading mode
- GEANT4 physics list (QBBC)

#### Example B2 (see also Doxygen page)

- Simplified tracker geometry with uniform magnetic field
- Geometry with simple placements (G4PVPlacement) and parameterisation (G4PVParameterisation)
- Scoring within tracker via G4 sensitive detector and hits

- GEANT4 physics list (FTFP\_BERT) with step limiter
- Started from novice N02 example

### Example B3 (see also Doxygen page)

- Schematic Positron Emission Tomography system
- Geometry with simple placements with rotation (G4PVPlacement)
- · Radioactive source
- Scoring within Crystals via G4 scorers plus via user actions (a), via user own Run object (b)
- Using G4Accumulable for automatic merging of scored values in multi-threading mode (a) and G4StatAnalysis for accumulating statistics (b)
- Modular physics list built via builders provided in GEANT4

## Example B4 (see also Doxygen page)

- Simplified calorimeter with layers of two materials
- Geometry with replica (G4PVReplica)
- Scoring within layers in four ways: via user actions (a), via user own Run object (b), via G4 sensitive detector and hits (c) and via scorers (d)
- GEANT4 physics list (FTFP\_BERT)
- Saving histograms and ntuple in a file using GEANT4 analysis tools
- UI commands defined using G4GenericMessenger
- Started from novice/N03 example

## Example B5 (see also Doxygen page)

- A double-arm spectrometer with wire chambers, hodoscopes and calorimeters with a local constant magnetic field
- Geometry with placements with rotation, replicas and parameterisation
- Scoring within wire chambers, hodoscopes and calorimeters via G4 sensitive detector and hits
- GEANT4 physics list (FTFP\_BERT) with step limiter
- UI commands defined using G4GenericMessenger
- Saving histograms and ntuple in two files using GEANT4 analysis tools
- · Plotting of histograms with visualization drivers
- Started from extended/analysis/A01

The next three tables display the "item charts" for the examples currently prepared in the basic level. (Table 10.1, Table 10.2, and Table 10.3.)

Table 10.1: The "item chart" for basic level examples *B1* and *B2*.

	Example B1	Example B2
Description	Simple application for accounting	Fixed target tracker geometry
	dose in a selected volume	
Geometry	<ul> <li>solids: box, cons, trd</li> <li>simple placements with translation</li> </ul>	<ul> <li>solids: box, tubs</li> <li>simple placements with translation (a)</li> <li>parameterised volume (b)</li> <li>uniform magnetic field</li> </ul>
Physics	GEANT4 physics list: QBBC	GEANT4 physics list: FTFP_BERT
Primary generator	Particle gun	Particle gun
Scoring	User action classes	Sensitive detector & hits
Vis/GUI	Detector & trajectory drawing	Detector, trajectory & hits drawing     GUI
Stacking		
Analysis		

Table 10.2: The "item chart" for basic level examples *B3* and *B4*.

	Example B3	Example B4
Description	Schematic Positron Emitted Tomography system	Simplified calorimeter with layers of two materials
Geometry	<ul><li> solids: box, tubs</li><li> simple placements with rotation</li></ul>	<ul> <li>solids: box</li> <li>simple placements with translation</li> <li>replica</li> <li>uniform magnetic field</li> </ul>
Physics	Modular physics list with GEANT4 builders	GEANT4 physics list: FTFP_BERT
Primary generator	Radioactive source (particle gun with Fluor ions)	Particle gun
Scoring	Multi functional (sensitive) detector & scorers and  • User action classes  • User own run object	<ul> <li>User action classes</li> <li>User own object (runData)</li> <li>Sensitive detector &amp; hits</li> <li>Multi functional (sensitive) detector &amp; scorers</li> </ul>
Vis/GUI	Detector, trajectory & hits drawing	Detector, trajectory & hits drawing     GUI
Stacking	Killing all neutrina	
Analysis		Histograms 1D, ntuple

Example B5 Description Double-arm spectrometer with several detectors and a local constant magnetic field Geometry • solids: box, tubs • simple placements with rotation • replica • parameterised volume · local constant magnetic field • modifying geometry between runs GEANT4 physics list: FTFP\_BERT **Physics** Primary generator Particle gun Scoring Sensitive detectors & hits Vis/GUI • Detector, trajectory & hits drawing • User defined visualization attributes • Plotting of histograms Stacking Analysis • Histograms 1D, ntuple · Saving two files per run

Table 10.3: The "item chart" for basic level example B5.

# 10.2.2 Basic Examples Macros

All basic examples can be run either interactively or in a batch mode (see section *How to Define the main() Program* and *How to Execute a Program*) and they are provided with the following set of macros:

- init\_vis.mac
- vis.mac
- [qui.mac]
- [plotter.mac]
- run1.mac, run2.mac
- exampleBN.in

The selection is done automatically according to the application build configuration.

The init\_vis.mac macro is always executed just after the GEANT4 kernel and user application classes instantiation. It sets first some defaults, then performs GEANT4 kernel initialization and finally calls the vis.mac macro with visualization setting.

The vis.mac macros in each of the examples all have the same structure - except for example B1, see below. There are only a few lines in each example with a setting different from the other examples and so they can be easily spotted when looking in the macro. Various commands are proposed in commented blocks of lines with explanations so that a user can just uncomment lines and observe the effect. Additionally, in example B4, there are some visualization tutorial macros in macros/visTutor/. See more on visualization in section *How to Visualize the Detector and Events* and chapter *Visualization*.

From Release 9.6 the vis.mac macro in example B1 has additional commands that demonstrate additional functionality of the vis system, such as displaying text, axes, scales, date, logo and shows how to change viewpoint and style. Consider copying these to your favourite example or application. To see even more commands use help or ls or browse the available UI commands in section *Built-in Commands*.

The gui.mac macros are provided in examples B2, B4 and B5. This macro is automatically executed if GEANT4 is built with any GUI session. See more on graphical user interfaces in section *How to Set Up an Interactive Session*.

When running interactively, the example program stops after processing the init\_vis.mac macro and the GEANT4 kernel initialization, invoked from the macro, with the prompt Idle>. At this stage users can type in the commands from run1.mac line by line (recommended when running the example for the first time) or execute all commands at once using the "/control/execute run1.mac" command.

The run2.mac macros define conditions for execution a run with a larger number of events and so they are recommended to be executed in a batch. The exampleBN.in macros are also supposed to be run in a batch mode and their outputs from the GEANT4 system testing are available in the files exampleBN.out.

The plotter.mac macro is provided in example B5. This macro shows how to use the plotting coming with some of the visualization drivers (for example the ToolsSG ones) to see histograms. This macro can be run interactively, after example start at the prompt Idle>, using the "/control/execute plotter.mac" command, the content of the histograms is then displayed at the end of each run.

# 10.2.3 Multi-threading

### Multi-threading mode

All basic examples have been migrated to multi-threading (MT). No special steps are needed to build the examples in multi-threading mode. They will automatically run in MT when they are built against the GEANT4 libraries built with MT mode activated, otherwise they will run in sequential mode.

The choice of multi-threading mode is handled automatically by the use of G4RunManagerFactory in the example main():

```
#include "G4RunManagerFactory.hh"

// ...
auto* runManager = G4RunManagerFactory::Create();
```

The concrete type of runManager will be G4MTRunManager when the Geant4 install used supports multithreading, or *G4RunManager* 'otherwise.

### Action Initialization class [B1, B2, B3, B4, B5]

```
See B1, B2, B3, B4, B5
```

A newly introduced Bn::ActionInitialization class derived from G4VUserActionInitialization, present in all basic examples, instantiates and registers all user action classes with the GEANT4 kernel.

While in sequential mode the action classes are instantiated just once, via invocation of the method BnActionInitialization::Build(). In multi-threading mode the same method is invoked for each worker thread, so all user action classes are defined thread-locally.

A run action class is instantiated both thread-locally and globally; that is why its instance is created also in the method Bn::ActionInitialization::BuildForMaster(), which is invoked only in multi-threading mode.

# 10.2.4 Example B1

See also Doxygen page

#### **Basic concept:**

This example demonstrates a simple (medical) application within which users will familiarize themselves with simple placement, use the NIST material database, and can utilize electromagnetic and/or hadronic physics processes. Two items of information are collected in this example: the energy deposited and the total dose for a selected volume.

This example uses the GEANT4 physics list QBBC, which is instantiated in the main() function. It requires data files for electromagnetic and hadronic processes. See more on installation of the datasets in Geant4 Installation Guide - Geant4 Build Options. The following datasets: G4LEDATA, G4LEVELGAMMADATA, G4NEUTRONXSDATA, G4SAIDXSDATA and G4ENSDFSTATEDATA are mandatory for this example.

#### Namespace:

Since Geant4 version 11 all example classes are defined in namespace B1.

#### Classes:

- B1::DetectorConstruction The geometry is constructed in the B1::DetectorConstruction class. The setup consists of a box shaped envelope containing two volumes: a circular cone and a trapezoid. Some common materials from medical applications are used. The envelope is made of water and the two inner volumes are made from tissue and bone materials. These materials are created using the G4NistManager class, which allows one to build a material from the NIST database using their names. Available materials and their compositions can be found in the Appendix *Material Database*.

  The physical volumes are made from Constructive Solid Geometry (CSG) solids and placed without rotation
  - The physical volumes are made from Constructive Solid Geometry (CSG) solids and placed without rotation using the G4PVPlacement class.
- **B1::PrimaryGeneratorAction** The default kinematics is a 6 MeV gamma, randomly distributed in front of the envelope across 80% of the transverse (X,Y) plane. This default setting can be changed via the commands of the G4ParticleGun class.
- **B1::SteppingAction** It is in the UserSteppingAction() function that the energy deposition is collected for a selected volume.
- **B1::EventAction** The statistical event by event accumulation of energy deposition. At the end of event, the accumulated values are passed in B1::RunAction and summed over the whole run.
- **B1::RunAction** Sums the event energy depositions. In multi-threading mode the energy deposition accumulated in G4Accumulable objects per worker is merged to the master. Information about the primary particle is printed in this class along with the computation of the dose. An example of creating and computing new units (e.g., dose) is also shown in the class constructor.
  - G4Accumulable<G4double> type instead of G4double is used for the B1::RunAction data members in order to facilitate merging of the values accumulated on workers to the master. At present the accumulables have to be registered to G4AccumulablesManager and G4ParametersManager::Merge() has to be called from the users code. This is planned to be further simplified with a closer integration of G4Accumulable classes in the GEANT4 kernel next year.

# **10.2.5 Example B2**

### See also Doxygen page

This example simulates a simplified fixed target experiment. To demonstrate alternative ways of constructing the geometry two variants are provided: B2a (explicit construction) and B2b (parametrized volumes).

The set of available particles and their physics processes are defined in the FTFP\_BERT physics list. This GEANT4 physics list is instantiated in the main() function. It requires data files for electromagnetic and hadronic processes. See more on installation of the datasets in |Geant4| Installation Guide. The following datasets: G4LEDATA, G4LEVELGAMMADATA, G4NEUTRONXSDATA, G4SAIDXSDATA and G4ENSDFSTATEDATA are mandatory for this example.

This example also illustrates how to introduce tracking constraints like maximum step length via G4StepLimiter, and minimum kinetic energy, etc., via the G4UserSpecialCuts processes. This is accomplished by adding G4StepLimiterPhysics to the physics list.

#### Namespaces:

Since Geant4 version 11 the example classes are defined in namespaces B2, B2a and B2b

#### Classes:

B2[a, b]::DetectorConstruction The setup consists of a target followed by six chambers of increasing transverse size at defined distances from the target. These chambers are located in a region called the Tracker region. Their shape are cylinders constructed as simple cylinders (in B2a::DetectorConstruction) and as parametrised volumes (in B2b::DetectorConstruction) - see also B2b::ChamberParameterisation class.

In addition, a global uniform transverse magnetic field can be applied using G4GlobalMagFieldMessenger, instantiated in ConstructSDandField() with a non zero field value, or via an interactive command. An instance of the B2::TrackerSD class is created and associated with each logical chamber volume (in B2a) and with the one G4LogicalVolume associated with G4PVParameterised (in B2b).

One can change the materials of the target and the chambers interactively via the commands defined in B2a::DetectorMessenger(or B2b::DetectorMessenger).

This example also illustrates how to introduce tracking constraints like maximum step length, minimum kinetic energy etc. via the G4UserLimits class and associated G4StepLimiter and G4UserSpecialCuts processes. The maximum step limit in the tracker region can be set by the interactive command defined in B2a::DetectorMessenger (or B2b::DetectorMessenger).

- **B2::PrimaryGeneratorAction** The primary generator action class employs the G4ParticleGun. The primary kinematics consists of a single particle which hits the target perpendicular to the entrance face. The type of the particle and its energy can be changed via the G4 built-in commands of the G4ParticleGun class.
- B2::EventAction The event number is written to the log file every requested number of events in BeginOfEventAction() and EndOfEventAction(). Moreover, for the first 100 events and every 100 events thereafter information about the number of stored trajectories in the event is printed as well as the number of hits stored in the G4VHitsCollection.
- **B2::RunAction** The run number is printed at BeginOfRunAction(), where the G4RunManager is also informed how to SetRandomNumberStore for storing initial random number seeds per run or per event.
- **B2::TrackerHit** The tracker hit class is derived from G4VHit. In this example, a tracker hit is a step by step record of the track identifier, the chamber number, the total energy deposit in this step, and the position of the energy deposit.
- B2::TrackerSD The tracker sensitive detector class is derived from G4VSensitiveDetector. In ProcessHits() called from the GEANT4 kernel at each step it creates one hit in the selected volume so long as energy is deposited in the medium during that step. This hit is inserted in a HitsCollection. The HitsCollection is printed at the end of each event (via the method B2::TrackerSD::EndOfEvent()), under the control of the "/hits/verbose 2" command.

# **10.2.6 Example B3**

See also Doxygen page

This example simulates a Schematic Positron Emission Tomography system. To demonstrate alternative ways of accumulation event statistics in a run two variants are provided: B3a (using new G4Accumulable class) and B3b (using G4Run class).

## Namespaces:

Since Geant4 version 11 the example classes are defined in namespaces B3, B3a and B3b

#### Classes:

- **B3::DetectorConstruction** Crystals are circularly arranged to form a ring. A number rings make up the full detector (gamma camera). This is done by positioning Crystals in Ring with an appropriate rotation matrix. Several copies of Ring are then placed in the full detector.
  - The Crystal material, Lu2SiO5, is not included in the G4Nist database. Therefore, it is explicitly built in DefineMaterials().
  - Crystals are defined as scorers in DetectorConstruction::CreateScorers(). There are two G4MultiFunctionalDetector objects: one for the Crystal (EnergyDeposit), and one for the Patient (DoseDeposit).
- **B3::PhysicsList** The physics list contains standard electromagnetic processes and the radioactiveDecay module for GenericIon. It is defined in the B3::PhysicsList class as a GEANT4 modular physics list with registered GEANT4 physics builders:
  - G4DecayPhysics
  - G4RadioactiveDecayPhysics
  - G4EmStandardPhysics
- **B3::PrimaryGeneratorAction** The default particle beam is an ion (F18), at rest, randomly distributed within a zone inside a patient and is defined in GeneratePrimaries ().
- B3a::EventAction, B3a::RunAction Energy deposited in crystals is summed by G4Scorer.

The scorers hits are saved in form of ntuples in a Root file using Geant4 analysis tools. This feature is activated in the main () function with instantiating G4TScoreNtupleWriter.

At the end of event, the values accumulated in B3aEventAction are passed in B3a::RunAction and summed over the whole run. In multi-threading mode the data accumulated in G4Accumulable objects per workers is merged to the master in B3a::RunAction::EndOfRunAction() and the final result is printed on the screen.

G4Accumulable<> type instead of G4double and G4int types is used for the B3a::RunAction data members in order to facilitate merging of the values accumulated on workers to the master. At present the accumulables have to be registered to G4AccumulablesManager and G4AccumulablesManager::Merge() has to be called from the users code. This is planned to be further simplified with a closer integration of G4Accumulable classes in the GEANT4 kernel next year.

- B3b::Run, B3b::RunAction Energy deposited in crystals is summed by G4Scorer. B3b::Run::RecordEvent() collects information event by event from the hits collections, and accumulates statistics for B3b::RunAction::EndOfRunAction(). In multi-threading mode the statistics accumulated per worker is merged to the master in Run::Merge().
  - In addition, results for dose are accumulated in a standard floating-point summation and using a new lightweight statistical class called G4StatAnalysis. The G4StatAnalysis class records four values: (1) the sum, (2) sum^2, (3) number of entries, and (4) the number of entries less than mean \* machine-epsilon (the machine epsilon is the difference between 1.0 and the next value representable by the floating-point type). From these 4 values, G4StatAnalysis provides the mean, FOM, relative error, standard deviation, variance, coefficient of variation, efficiency, r2int, and r2eff.
- **B3::StackingAction** Beta decay of Fluorine generates a neutrino. One wishes not to track this neutrino; therefore one kills it immediately, before created particles are put in a stack.

# 10.2.7 Example B4

See also Doxygen page

This example simulates a simple Sampling Calorimeter setup. To demonstrate several possible ways of data scoring, the example is provided in four variants: B4a, B4b, B4c, B4d. (See also examples/extended/electromagnetic/TestEm3).

The set of available particles and their physics processes are defined in the FTFP\_BERT physics list. This GEANT4 physics list is instantiated in the main() function. It requires data files for electromagnetic and hadronic processes. See more on installation of the datasets in |Geant4| Installation Guide. The following datasets: G4LEDATA, G4LEVELGAMMADATA, G4NEUTRONXSDATA, G4SAIDXSDATA and G4ENSDFSTATEDATA are mandatory for this example.

#### Namespaces:

Since Geant4 version 11 the example classes are defined in namespaces B4, B4a, B4b, B4c and B4d

#### Classes:

- **B4[c, d]::DetectorConstruction** The calorimeter is a box made of a given number of layers. A layer consists of an absorber plate and of a detection gap. The layer is replicated. In addition a transverse uniform magnetic field can be applied using G4GlobalMagFieldMessenger, instantiated in ConstructSDandField() with a non zero field value, or via interactive commands.
- **B4::PrimaryGeneratorAction** The primary generator action class uses G4ParticleGun. It defines a single particle which hits the calorimeter perpendicular to the input face. The type of the particle can be changed via the G4 built-in commands of the G4ParticleGun class.
- B4::RunAction It accumulates statistics and computes dispersion of the energy deposit and track lengths of charged particles with the aid of analysis tools. H1D histograms are created in BeginOfRunAction() for the energy deposit and track length in both Absorber and Gap volumes. The same values are also saved in an ntuple. The histograms and ntuple are saved in the output file in a format according to a selected file extension. In EndOfRunAction(), the accumulated statistics and computed dispersion are printed. When running in multi-threading mode, the histograms accumulated on threads are automatically merged in a single output file, while the ntuple is written in files per thread.

### Classes in B4a (scoring via user actions):

- **B4a::SteppingAction** In UserSteppingAction() the energy deposit and track lengths of charged particles in each step in the Absorber and Gap layers are collected and subsequently recorded in B4a::EventAction.
- **B4a::EventAction** It defines data members to hold the energy deposit and track lengths of charged particles in the Absorber and Gap layers. In EndOfEventAction(), these quantities are printed and filled in H1D histograms and ntuple to accumulate statistic and compute dispersion.

### Classes in B4b (via user own object):

- B4b::RunData A data class, derived from G4Run, which defines data members to hold the energy deposit and track lengths of charged particles in the Absorber and Gap layers. It is instantiated in B4b::RunAction::GenerateRun. The data are collected step by step in B4b::SteppingAction, and the accumulated values are entered in histograms and an ntuple event by event in B4b::EventAction.
- **B4b::SteppingAction** In UserSteppingAction() the energy deposit and track lengths of charged particles in Absorber and Gap layers are collected and subsequently recorded in B4b::RunData.
- **B4b::EventAction** In EndOfEventAction(), the accumulated quantities of the energy deposit and track lengths of charged particles in Absorber and Gap layers are printed and then stored in B4b::RunData.

#### Classes in B4c (via |Geant4| sensitive detector and hits):

- **B4c::DetectorConstruction** In addition to materials, volumes and uniform magnetic field definitions as in B4DetectorConstruction, in ConstructSDandField() two instances of the B4c::CalorimeterSD class are created and associated with Absorber and Gap volumes.
- **B4c::CalorHit** The calorimeter hit class is derived from G4VHit. It defines data members to store the energy deposit and track lengths of charged particles in a selected volume.
- B4c::CalorimeterSD The calorimeter sensitive detector class is derived from G4VSensitiveDetector. Two instances of this class are created in B4c::DetectorConstruction and associated with Absorber and Gap volumes. In Initialize(), it creates one hit for each calorimeter layer and one more hit for accounting the total quantities in all layers. The values are accounted in hits in the ProcessHits() function, which is called by the GEANT4 kernel at each step.
- **B4c::EventAction** In EndOfEventAction(), the accumulated quantities of the energy deposit and track lengths of charged particles in Absorber and Gap layers are printed and then stored in the hits collections.

#### Classes in B4d (via |Geant4| scorers):

**B4d::DetectorConstruction** In addition to materials, volumes and uniform magnetic field definitions as in B4DetectorConstruction, in ConstructSDandField() sensitive detectors of G4MultiFunctionalDetector type with primitive scorers are created and associated with Absorber and Gap volumes.

**B4d::EventAction** Energy deposited in crystals is summed by G4Scorer.

The scorers hits are saved in form of ntuples in a Root file using Geant4 analysis tools. This feature is activated in the main () function with instantiating G4TScoreNtupleWriter.

In <code>EndOfEventAction()</code>, the accumulated quantities of the energy deposit and track lengths of charged particles in Absorber and Gap layers are printed and then stored in the hits collections.

# **10.2.8 Example B5**

See also Doxygen page

This example simulates a double-arm spectrometer with wire chambers, hodoscopes and calorimeters with a uniform local magnetic field.

The set of available particles and their physics processes are defined in the FTFP\_BERT physics list. This GEANT4 physics list is instantiated in the main() function. It requires data files for electromagnetic and hadronic processes. See more on installation of the datasets in |Geant4| Installation Guide. The following datasets: G4LEDATA, G4LEVELGAMMADATA, G4NEUTRONXSDATA, G4SAIDXSDATA and G4ENSDFSTATEDATA are mandatory for this example.

This example also illustrates how to introduce tracking constraints like maximum step length via G4StepLimiter, and minimum kinetic energy, etc., via the G4UserSpecialCuts processes. This is accomplished by adding G4StepLimiterPhysics to the physics list.

#### Namespace:

Since Geant4 version 11 all example classes are defined in namespace B5.

#### Classes:

**B5::DetectorConstruction** The spectrometer consists of two detector arms. One arm provides position and timing information of the incident particle while the other collects position, timing and energy information of the particle after it has been deflected by a magnetic field centered at the spectrometer pivot point.

First arm: box filled with air, also containing:

- 1 hodoscope (15 vertical strips of plastic scintillator)
- 1 drift chamber (horizontal argon gas layers with a "virtual wire" at the center of each layer)

Second arm: box filled with air, also containing:

- 1 hodoscope (25 vertical strips of plastic scintillator)
- 1 drift chamber (5 horizontal argon gas layers with a "virtual wire" at the center of each layer)
- 1 electromagnetic calorimeter: a box sub-divided along x,y and z axes into cells of CsI (see also B5::CellParameterisation class)
- 1 hadronic calorimeter: a box sub-divided along x,y, and z axes into cells of lead, with a layer of plastic scintillator placed at the center of each cell

The magnetic field region is represented by an air-filled cylinder which contains the field (see B5::MagneticField.). The maximum step limit in the magnetic field region is also set via the G4UserLimits class in a similar way as in Example B2.

The rotation angle of the second arm and the magnetic field value can be set via the interactive command defined using the G4GenericMessenger class.

**B5::PrimaryGeneratorAction** The primary generator action class employs the G4ParticleGun. The primary kinematics consists of a single particle which is is sent in the direction of the first spectrometer arm.

The type of the particle and its several properties can be changed via the GEANT4 built-in commands of the G4ParticleGun class or this example command defined using the G4GenericMessenger class.

**B5::EventAction** An event consists of the generation of a single particle which is transported through the first spectrometer arm. Here, a scintillator hodoscope records the reference time of the particle before it passes

through a drift chamber where the particle position is measured. Momentum analysis is performed as the particle passes through a magnetic field at the spectrometer pivot and then into the second spectrometer arm. In the second arm, the particle passes through another hodoscope and drift chamber before interacting in the electromagnetic calorimeter. Here it is likely that particles will induce electromagnetic showers. The shower energy is recorded in a three-dimensional array of CsI crystals. Secondary particles from the shower, as well as primary particles which do not interact in the CsI crystals, pass into the hadronic calorimeter. Here, the remaining energy is collected in a three-dimensional array of scintillator-lead sandwiches.

In first execution of <code>BeginOfEventAction()</code> the hits collections identifiers are saved in data members of the class and then used in <code>EndOfEventAction()</code> for accessing the hists collections and filling the accounted information in defined histograms and ntuples and printing its summary in a log file. The frequency of printing can be tuned with the built-in command <code>"/run/printProgress frequency"</code>.

**B5::RunAction** The run action class handles the histograms and ntuples with the aid of GEANT4 analysis tools in a similar way as in Example B4. From Release 10.2 the vectors of energy deposits in Electromagnetic and Hadronic calorimeter cells are also stored in the ntuple. In difference from example B4, G4GenericAnalysisManager is used to demonstrate saving histograms and ntuple in two separate files.

**Hit and Sensitive Detector Classes** All the information required to simulate and analyze an event is recorded in hits. This information is recorded in the following sensitive detectors:

- Hodoscope (B5::HodoscopeSD, B5::HodoscopeHit)
  - particle time
  - strip ID, position and rotation
- Drift chamber: (B5::DriftChamberSD, B5::DriftChamberHit)
  - particle time
  - particle position
  - laver ID
- Electromagnetic calorimeter: (B5::EmCalorimeterSD, B5::EmCalorimeterHit)
  - energy deposited in cell
  - cell ID, position and rotation
- Hadronic calorimeter: (B5::HadCalorimeterSD, B5::HadCalorimeterHit)
  - energy deposited in cell
  - cell column ID and row ID, position and rotation

The hit classes include methods <code>GetAttDefs</code> and <code>CreateAttValues</code> to define and then fill extra "HepRepstyle" Attributes that the visualization system can use to present extra information about the hits. For example, if you pick a <code>B5::HadCalorimeterHit</code> in OpenGL or a HepRep viewer, you will be shown the hit's "Hit Type", "Column ID", "Row ID", "Energy Deposited" and "Position".

These attributes are essentially arbitrary extra pieces of information (integers, doubles or strings) that are carried through the visualization. Each attribute is defined once in G4AttDef object and then is filled for each hit in a G4AttValue object. These attributes can also be used by commands to filter which hits are drawn: "/vis/filtering/hits/drawByAttribute".

Detector Geometry and trajectories also carry HepRep-style attributes, but these are filled automatically in the base classes. HepRep is further described at: http://www.slac.stanford.edu/~perl/heprep/

# 10.3 Extended Examples

GEANT4 extended examples serve three purposes:

- testing and validation of processes and tracking,
- demonstration of GEANT4 tools, and
- extending the functionality of GEANT4.

The code for these examples is maintained as part of the categories to which they belong. Links to descriptions of the examples are listed below.

# 10.3.1 Analysis

- AnaEx01 histogram and tuple manipulations using GEANT4 internal g4tools system
- AnaEx02 histogram and tuple manipulations using ROOT
- B1Con modified basic example B1 showing how to use a Convergence Tester
- [A01] this examples has been refactored in Example B5 in the basic set.

# 10.3.2 Biasing

- Variance Reduction examples (B01, B02 and B03) on variance reduction techniques and scoring and application
  of Reverse Monte Carlo in GEANT4 ReverseMC
- Generic biasing examples illustrate the usage of a biasing scheme implemented since version GEANT4 10.0.
  - GB01 This example illustrates how to bias process cross-sections in this scheme.
  - GB02 Illustrates a force collision scheme similar to the MCNP one.
  - GB03 Illustrates geometry based biasing.
  - GB04 Illustrates a bremsstrahlung splitting.
  - GB05 Illustrates a "splitting by cross-section" technique: a splitting-based technique using absorption cross-section to control the neutron population.
  - GB06 Illustrates the usage of parallel geometries with generic biasing.
  - GB07 Illustrates how to use the leading particle biasing option.

### 10.3.3 Common

• ReadMe - a set of common classes which can be reused in other examples demonstrating just a particular feature.

# 10.3.4 Electromagnetic

- TestEm0 how to print cross-sections and stopping power used in input by the standard EM package
- TestEm1 how to count processes, activate/inactivate them and survey the range of charged particles. How to define a maximum step size
- TestEm2 shower development in an homogeneous material: longitudinal and lateral profiles
- TestEm3 shower development in a sampling calorimeter : collect energy deposited, survey energy flow and print stopping power
- TestEm4 9 MeV point like photon source: plot spectrum of energy deposited in a single media
- TestEm5 how to study transmission, absorption and reflection of particles through a single, thin or thick, layer.
- TestEm6 physics list for rare, high energy, electromagnetic processes: gamma conversion and e+ annihilation into pair of muons
- TestEm7 how to produce a Bragg curve in water phantom. How to compute dose in tallies
- TestEm8 test of photo-absorption-ionisation model in thin absorbers, and transition radiation
- TestEm9 shower development in a crystal calorimeter; cut-per-region
- TestEm10 XTR transition radiation model, investigation of ionisation in thin absorbers
- TestEm11 how to plot a depth dose profile in a rectangular box
- TestEm12 how to plot a depth dose profile in spherical geometry: point like source
- TestEm13 how to compute cross sections of EM processes from rate of transmission coefficient
- TestEm14 how to compute cross sections of EM processes from direct evaluation of the mean-free path. How
  to plot final state
- TestEm15 compute and plot final state of Multiple Scattering as an isolated process
- TestEm16 simulation of synchrotron radiation
- TestEm17 check the cross sections of high energy muon processes
- TestEm18 energy lost by a charged particle in a single layer, due to ionization and bremsstrahlung

Table 10.4: TestEm by theme

Check basic quantities			
Total cross sections, mean free paths	Em0, Em13, Em14		
Stopping power, particle range	Em0, Em1, Em5, Em11, Em12		
Final state : energy spectra, angular distributions	Em14		
Energy loss fluctuations	Em18		
Multiple Coulomb scattering			
as an isolated mechanism	Em15		
as a result of particle transport	Em5		
More global verifications			
Single layer: transmission, absorption, reflection	Em5		
Bragg curve, tallies	Em7		
Depth dose distribution	Em11, Em12		
Shower shapes, Moliere radius	Em2		
Sampling calorimeters, energy flow	Em3		
Crystal calorimeters	Em9		
Other specialized programs			
High energy muon physics	Em17		
Other rare, high energy processes	Em6		
Synchrotron radiation	Em16		
Transition radiation	Em8		
Photo-absorption-ionization model	Em10		

# 10.3.5 Error Propagation

• ReadMe - error propagation utility

#### 10.3.6 Event Generator

- exgps illustrating the usage of the G4GeneralParticleSource utility
- particleGun demonstrating three different ways of usage of G4ParticleGun, shooting primary particles in different cases
- userPrimaryGenerator demonstrating how to create a primary event including several vertices and several primary particles per vertex
- HepMCEx01 simplified collider detector using HepMC interface and stacking
- HepMCEx02 connecting primary particles in GEANT4 with various event generators using the HepMC interface
- MCTruth demonstrating a mechanism for Monte Carlo truth handling using HepMC as the event record
- pythia illustrating the usage of Pythia as Monte Carlo event generator, interfaced with GEANT4, and showing how to implement an external decayer. Examples decayer6 and py8decayer

# 10.3.7 Exotic Physics

- Channeling simulates channeling of 400 GeV/c protons in a bent crystal.
- Dmparticle a very preliminary and simplified GEANT4 example for light dark matter (LDM) particles.
- Monopole illustrating how to measure energy deposition in classical magnetic monopole.
- Phonon demonstrates simulation of phonon propagation in cryogenic crystals.
- Saxs implements the typical setup of a Small Angle X-ray Scattering (SAXS) experiment. It is meant to illustrate the usage of molecular interference (MI) of Rayleigh (coherent) scattering of photons inside the matter.
- UCN simulates the passage of ultra-cold neutrons (UCN) in a hollow pipe.

### 10.3.8 Fields

- BlineTracer tracing and visualizing magnetic field lines
- field01 tracking using magnetic field and field-dependent processes
- field02 tracking using electric field and field-dependent processes
- field03 tracking in a magnetic field where field associated with selected logical volumes varies
- field04 definition of overlapping fields either magnetic, electric or both
- field05 demonstration of "spin-frozen" condition, how to cancel the muon g-2 precession by applying an electric field
- field06 exercising the capability of tracking massive particles in a gravity field

### 10.3.9 Geant3 to Geant4

General ReadMe - converting simple geometries in Geant3.21 to their GEANT4 equivalents (example clGeometry)

## **10.3.10 Geometry**

- General ReadMe
- transforms demonstrating various ways of definition of 3D transformations for placing volumes
- vecGeomNavigation demonstrating integration of the navigation elements of VecGeom

#### 10.3.11 Hadronic

- Hadr00 example demonstrating the usage of G4PhysListFactory to build physics lists and usage of G4HadronicProcessStore to access the cross sections
- Hadr01 example based on the application IION developed for simulation of proton or ion beam interaction with a water target. Different aspects of beam target interaction are included
- Hadr02 example application providing simulation of ion beam interaction with different targets. Hadronic
  aspects of beam target interaction are demonstrated including longitudinal profile of energy deposition, spectra
  of secondary particles, isotope production spectra.
- Hadr03 example demonstrating how to compute total cross section from the direct evaluation of the mean free path, how to identify nuclear reactions and how to plot energy spectrum of secondary particles
- Hadr04 example focused on neutronHP physics, especially neutron transport, including thermal scattering
- Hadr05 examples of hadronic calorimeters
- Hadr06 demonstrates survey of energy deposition and particle's flux from a hadronic cascade
- Hadr07 demonstrates survey of energy deposition and particle's flux from a hadronic cascade. Show how to plot a depth dose profile in a rectangular box.
- Hadr08 demonstrates how to use "generic biasing" to get the following functionality which is currently not available directly in the Geant4 hadronic framework. We want to use the physics list FTFP\_BERT everywhere in

- our detector, except that in one (or more) logical volume(s) we want to use a different combination of hadronic models, e.g. FTFP + INCLXX (instead of the default FTFP + BERT), for the final-state generation.
- Hadr09 demonstrates how to use Geant4 as a generator for simulating inelastic hadron-nuclear interactions.
   Notice that the Geant4 run-manager is not used. See the README file (provided with the example) for more information.
- Hadr10 aims to test the treatment of decays in Geant4. In particular, we want to test the decays of the tau lepton, charmed and bottom hadrons, and the use of pre-assigned decays.
- FissionFragment This example demonstrates the Fission Fragment model as used within the neutron\_hp model. It will demonstrate the capability for fission product containment by the cladding in a water moderated subcritical assembly. It could also be further extended to calculate the effective multiplication factor of the subcritical assembly for various loading schemes.
- NeutronSource NeutronSource is an example of neutrons production. It illustrates the cooperative work of nuclear reactions and radioactive decay processes. It surveys energy deposition and particle's flux. It uses PhysicsConstructor objects.

# 10.3.12 Medical Applications

- DICOM geometry set-up using the GEANT4 interface to the DICOM image format
- DICOM2 inheritance from the DICOM example, method for memory savings, scoring into a sequential container instead of an associative container, accumulating the scoring with a statistics class instead of a simple floating point, and generic iteration over the variety of scoring container storage variants
- electronScattering benchmark on electron scattering
- electronScattering2 benchmark on electron scattering (second way to implement the same benchmark as the above)
- fanoCavity dose deposition in an ionization chamber by a monoenergetic photon beam
- fanoCavity2 dose deposition in an ionization chamber by an extended one-dimensional monoenergetic electron source
- GammaTherapy gamma radiation field formation in water phantom by electron beam hitting different targets
- dna Set of examples using the GEANT4-DNA physics processes and models.
  - AuNP Simulation of the track structure of electrons in a microscopic gold volume.
  - chem1 Simple activation of the chemistry module.
  - chem2 Usage of TimeStepAction in the chemistry module.
  - chem3 Activate the full interactivity with the chemistry module.
  - chem4 Simulation of G radiochemical yields with the chemistry module.
  - chem5 A variation of the chem4 example, using preliminary G4EmDNAPhysics\_option8 and G4EmDNAChemistry option1 constructors.
  - chem6 Scoring of the radiochemical yield G as a function of time and LET.
  - clustering Clustering application for direct damage extraction.
  - dnadamage1 Simulation of damage on a chromatin fiber.
  - dnaphysics Simulation of track structures in liquid water using the GEANT4-DNA physics processes and models.
  - icsd Use of cross section models for DNA materials.
  - mfp Simulation of mean free path in liquid water.
  - microdosimetry Simulation of the track of a 5 MeV proton in liquid water. GEANT4 standard EM models
    are used in the World volume while GEANT4-DNA models are used in a Target volume, declared as a
    Region.
  - microprox Computation of proximity functions in liquid water.
  - microyz Simulation of microdosimetry spectra.
  - neuron Irradiation of a realistic neuron cell.
  - pdb4dna Usage of the Protein Data Bank (PDB) file format to build geometries.
  - range Simulation of ranges.
  - slowing Simulation of slowing down spectra.
  - scavenger Simulation of the scavenging process in chemistry using the deterministic treatment of the IRT

model.

- splitting Acceleration of Geant4-DNA physics simulations by particle splitting.
- spower Simulation of stopping power.
- svalue Simulation of S-values in spheres of liquid water using the GEANT4-DNA physics processes and models.
- wholeNuclearDNA Description of the full nucleus of a biological cell.
- wvalue Simulation of W-values in liquid water using the GEANT4-DNA physics processes and models.

# 10.3.13 Optical Photons

- · General ReadMe
- OpNovice simulation of optical photons generation and transport. (It was moved in extended examples from novice/N06 with removal of novice examples.)
- OpNovice2 investigate optical properties and parameters; details of optical photon boundary interactions on a surface, optical photon generation and transport
- LXe optical photons in a liquid xenon scintillator
- WLS application simulating the propagation of photons inside a Wave Length Shifting (WLS) fiber

# 10.3.14 Parallel Computing

- · General ReadMe
- MPI interface and examples of applications (*exMPI01*, *exMPI02*, exMPI03\* and *exMPI04*) parallelized with different MPI compliant libraries, such as LAM/MPI, MPICH2, OpenMPI, etc.
- TBB demonstrate how to interface a simple application with the Intel Threading Building Blocks library (TBB), and organise MT event-level parallelism as TBB tasks
- ThreadsafeScorers demonstrates a very simple application where an energy deposit and # of steps is accounted in thread-local (i.e. one instance per thread) hits maps with underlying types of plain-old data (POD) and global (i.e. one instance) hits maps with underlying types of atomics.
- TopC set of examples (*ParN02* and *ParN04*) derived from novice using parallelism at event level with the TopC application

# 10.3.15 Parameterisations

- Par01 Demonstrates the use of parameterisation facilities. (It was moved in extended examples from novice/N05 with removal of novice examples.)
- Par02 Shows how to do "track and energy smearing" in GEANT4, in order to have a very fast simulation based on assumed detector resolutions.
- Par03 Demonstrates how to create multiple energy deposits using helper class G4FastSimHitMaker.
   Thanks to storing hits in the same hit collection (using one sensitive detector class) whether they originated in the full or fast simulation, this example allows to perform the same analysis on both outputs and compare the results.
- *Par04* (doxygen) Demonstrates how to use machine learning techniques for the fast simulation of calorimeters, and how to incorporate inference libraries into C++ framework.
- Gflash Examples set (*gflash1*, 2, 3, *gflasha*) demonstrating the use of the GFLASH parameterisation library. It uses the GFLASH equations (hep-ex/0001020, Grindhammer & Peters) to parametrise electromagnetic showers in matter.

#### Par04

Par04 example focuses on application of Machine Learning (ML) techniques to fast simulation of calorimeters. Its main goal is to demonstrate how to do ML inference using Geant4.

In order to show how to perform ML inference, Par04 contains an ML model. It was trained externally (with Python) on dataset from standard (full) simulation done with this example. It is not optimized as its accuracy is not the concern of this example.

#### Installation

Par04 example depends on external libraries used for the ML inference. Currently, following libraries can be used:

- · ONNX Runtime,
- LWTNN.

If those libraries are not available, Par04 example can still be built to run standard (full) simulation. Such application can be used for instance to simulate the dataset used for ML training. The search for external libraries is by default switched on, but it can be switched off by setting the CMake variable INFERENCE\_LIB to OFF.

To build the application you need to:

```
$ cmake <Par04_SOURCE>
$ make
```

Replace <Par04\_SOURCE> with the path to Par04 example source directory. CMake will look for inference libraries unless you use -DINFERENCE\_LIB=OFF. You can point manually to them using CMAKE\_PREFIX\_PATH variable.

For instance, to run the example on lxplus8 you could use:

```
$ source /cvmfs/sft.cern.ch/lcg/contrib/gcc/11.1.0/x86_64-centos8-gcc11-opt/setup.sh
$ cmake <Par04_SOURCE> -DCMAKE_PREFIX_PATH="/cvmfs/sft.cern.ch/lcg/releases/onnxruntime/1.8.0-
$\to 47224/x86_64-centos8-gcc11-opt;/cvmfs/sft.cern.ch/lcg/releases/lwtnn/2.11.1-72aca/x86_64-
$\to centos8-gcc11-opt/"
```

#### How to run

Example can be run in batch mode, as well as in the interactive mode with the hit visualization.

To run the example in the batch mode you need to specify the macro (options) passing it with -m:

```
$ ./examplePar04 -m <MACRO_FILE>
```

To run the example in the interactive mode:

```
$ ./examplePar04
```

Example contains following macro files:

- examplePar04.in runs full simulation.
- examplePar04\_onnx.in runs inference with ONNX Runtime. It is installed in the build directory only if ONNX Runtime is found by CMake.
- examplePar04\_lwtnn.in runs inference with LWTNN. It is installed in the build directory only if LWTNN is found by CMake.
- vis.mac this macro is used in the interactive mode.

#### ML fast calorimeter simulation

#### Calorimeter

Calorimeter used in this example is a simple setup of concentric cylinders of active and passive material. It can be configured from the macro using the UI commands.

Energy deposits are scored in the detector using the cylindrical readout structure, centered around the particle momentum, as shown in Fig. 10.1. Dimensions of the readout structure (number and size of cells) can be also configured using the UI commands.




Fig. 10.1: Energy deposits are scored in cylindrical readout around particle momentum.

This example uses silicon as an active material, and tungsten as the passive absorber. 90 layers of both materials are placed, with 1.4 mm of tungsten and 0.3 mm of silicon. Size of the cylindrical readout has been optimized to contain (on average) 95 % of energy of 1 TeV electrons. The size of single cell has been chosen to correspond to (approximately) 0.25 Moliere radius and 0.5 radiation length.

Detector and readout (mesh) used in the example macros are configured with following commands:

```
# Detector Construction
/Par04/detector/setDetectorInnerRadius 80 cm
/Par04/detector/setDetectorLength 2 m
/Par04/detector/setNbOfLayers 90
/Par04/detector/setAbsorber 0 G4_W 1.4 mm false
/Par04/detector/setAbsorber 1 G4_Si 0.3 mm true
## 2.325 mm of tungsten =~ 0.25 * 9.327 mm = 0.25 * R_Moliere
/Par04/mesh/setSizeOfRhoCells 2.325 mm
## 2 * 1.4 mm of tungsten =~ 0.65 X_0
/Par04/mesh/setSizeOfZCells 3.4 mm
/Par04/mesh/setNbOfRhoCells 18
/Par04/mesh/setNbOfPhiCells 50
/Par04/mesh/setNbOfPhiCells 45
```

Particle momentum that is used to define the orientation and the placement of the cylindrical readout (which will differ from particle to particle) is measured at the entrance to the calorimeter. This measurement can be done in several different ways, and this example is using a fast simulation model (Par04DefineMeshModel) that is triggered at the entrance to the calorimeter and that sets up particle entrance position and momentum in the event information Par04EventInformation (since single particle events are used). For simplicity of the example Par04DefineMeshModel is attached to the same region as Par04InferenceModel. It has two direct consequences:

- In fast simulation order of activation of those model must be respected (first the model which sets up the readout properties, and then the model which kills a particle and creates deposits).
- Full simulation is slowed down by the large region of calorimeter and presence of fast simulation model that is called (to check if particle enters the calorimeter) for every electron or photon. For realistic use case this model should be attached to very thin cylindrical region located just *before* the entrance to the calorimeter.

#### **Output data**

Cylindrical readout is used in the sensitive detector Par04SensitiveDetector which accumulates energy from the event in the collection of hits, ignoring the deposits outside of the cylindrical mesh. At the end of each event, hit collection is saved to ntuple and stored in ROOT files. Additionally, simple analysis of the shower shape is performed and histograms are saved alongside the ntuple (technically, if G4 is run in sequential mode, otherwise multiple ROOT files are produced because histograms are merged while ntuples are not).

Structure of the output file(s) is the following:



#### Where:

- (D) is a double value.
- (VD) is a vector of double values,
- (VI) is a vector of integers,
- (H) is a histogram.

Ntuple events contains information on energy of primary particle (in units of MeV), and vector of energy deposits: cylindrical coordinates and energy in default GEANT4 units (rad for phi, mm for rho and z, MeV for energy). Only deposits above hard-coded threshold (E>0.5 keV) are stored in the file. Histograms are created in a simple post-event analysis. Please note that for readability, energy of primary particle and total deposited energy are plotted in units of GeV. Moreover, all hits with non-zero energy are taken into account (there is no minimal energy threshold). Hit type can be used to distinguish between full and fast simulation. Hit with ID=0 is used for full simulation, and ID=1 for fast simulation.

#### ML model

The model used in this example was trained externally (in Python) on data from this examples' full simulation. It is a Variational Autoencoder (VAE): a deep learning generative model. The VAE is composed of two stacked deep neural networks acting as encoder and decoder. The encoder learns a mapping from the input space to an unobserved or latent space in which a lower dimensional representation of the full simulation is learned. The decoder learns the inverse mapping, thus reconstructing the original input from this latent representation. The encoded distributions are constrained to be Gaussian distributions and the encoder is tasked to return the mean and the covariance matrix that describe these distributions.

The loss function that is optimized during the training of the VAE is composed of a regularisation loss to minimize Kulback-Leibler divergence between encoded distributions and prior Gaussian distributions, a reconstruction loss to minimize the error by computing the binary cross-entropy between the input and its reconstruction version using the latent representation.

The VAE architecture used in this example comprises 4 hidden layers with width of 100,50,20,14 and 14,20,50,100 for the encoder and decoder respectively as shown in the figure below.




Fig. 10.2: VAE model architecture.

The full simulation samples for the two detector geometries (Si/W as used in the example, and additionally 1.2 mm Scintillator/4.4 mm Pb) are showers of electron particles generated with an energy range from 1 GeV to 1 TeV (in powers of 2) and angles from 50 to 90 degrees (in a step of 10 degrees). 90 degrees means perpendicular to the z-axis. The VAE is conditioned on the three parameters.

The three figures below show the validation plots comparing the full simulation to the (ML) fast simulation after using the inference with ONNX. The plots show the longitudinal (Fig. 10.3), transverse profiles (Fig. 10.4) and simulation time (Fig. 10.5) for 64 GeV particles with an angle of 90 degrees.




Fig. 10.3: Longitudinal profile for 64 GeV electrons.




Fig. 10.4: Transvers profile for 64 GeV electrons.




Fig. 10.5: Simulation time for 64 GeV electrons.

#### Inference

In this example, the input inference vector is constructed by sampling from a 10D Gaussian distribution. The condition vector comprises condition values of energy and angle of a particle and two values encoding the calorimeter geometry. The condition value of the energy of the particle is normalized to the maximum energy point in the range of training. For the angle, the value in degrees is also normalized to the maximum angle point in the range of training. The model was trained on two detector geometries and the conditioning of the geometry used is a one hot encoding vector with [0,1] for SiW geometry and [1,0] for SciPb geometry. After running the inference, the values are rescaled back by the energy of the particle.

#### How to run inference of user models

This example was designed to facilitate integration of user model in Geant4 toolkit. Figure Fig. 10.6 shows how fast simulation components were implemented. Fast simulation model Par04InferenceModel is responsible for taking the particle out of full simulation, and creation of energy deposits with energy and position returned by Par04InferenceSetup. This is the model(user) specific class that should configure the ML model, run the inference using one of the inference libraries (configured in the example with UI commands thanks to Par04InferenceSetupMessenger), do the energy postprocessing, and finally be aware where to place energy inside of the detector. Interface to inference libraries (Par04InferenceInterface) is designed in a model-agnostic way. The inference works for any trained model by sampling N points from a predefined distribution where N represents the size of the input inference vector.

For a specific application, the user should therefore only change Par04InferenceSetup class, where all inference parameters are defined. These parameters include the name of the inference library, the path and name of the inference model, the size of the input inference vector (latent vector size and condition vector size). In this class the user can define the input inference vector including the vector of conditions, run the inference and also apply a post processing step to retrieve the original energy range if the model was trained on any specific preprocessed values. The important part is also assignment of positions to the energy deposits. Fast simulation model Par04InferenceModel will use those positions to place the deposits, therefore it needs to be a position of the sensitive detector. For this reason,




Fig. 10.6: Diagram of the classes used for fast simulation with ML inference.

in Par04 example, where simple center of cell positions are used, both materials (active and passive) is considered as sensitive for the fast simulation runs.

#### Inference with LWTNN

Lightweight Trained Neural Network (LWTNN) supports scikit-learn and Keras models where this model is saved as two separate files of the architecture (in JSON) and the weights (in HDF5). The trained model can be saved into these two separate files with:

```
# save the architecture in a JSON file
with open('architecture.json', 'w') as arch_file:
    arch_file.write(model.to_json())
# save the weights as an HDF5 file
model.save_weights('weights.h5')
```

After building the LWTNN code available at this link, run the kerasfunc2json python script (available in lwtnn/converters/) to generate a template file of your functional model input variables by calling:

```
$ kerasfunc2json.py architecture.json weights.h5 > inputs.json
```

And run again kerasfunc2 json script to get your output file that would be used for the inference in C++:

```
$ kerasfunc2json.py architecture.json weights.h5 inputs.json > Generator.json
```

Par04LwtnnInference is the class called if the user chooses the LWTNN library. The object that will do the computation in this class is a LightweightGraph, initialized from Generator.json file. The inference is based on evaluating the graph using the input inference vector constructed in Par04InferenceSetup.

#### Inference with ONNX runtime

Open Neural Network Exchange (ONNX) runtime supports models from Tensorflow/Keras, PyTorch, TFLite, scikit-learn and other frameworks. For a Keras model for example, to save it into an ONNX, you can first save it as HDF5 file with:

```
model.save("model.h5")
```

This model is then converted into an ONNX format using keras2onnx with:

```
# Create the Keras model
kerasModel = tensorflow.keras.models.load_model("model.h5")
# Convert Keras model into an ONNX model
onnxModel = keras2onnx.convert_keras( kerasModel , 'name')
# Save the ONNX model
keras2onnx.save_model(onnxModel, 'Generator.onnx')
```

Par040nnxInference is the class that is called if the user chooses ONNX. It creates an environment which manages an internal thread pool and creates as well the inference session for the model. This session runs the inference using the input vector constructed in Par04InferenceSetup.

### 10.3.16 Persistency

- · General ReadMe
- GDML examples set (G01, G02, G03 and G04) illustrating import and export of a detector geometry with GDML, and how to extend the GDML schema or use the auxiliary information field for defining additional persistent properties
- P01 storing calorimeter hits using reflection mechanism with Root
- P02 storing detector description using reflection mechanism with Root
- · P03 illustrating import and export of a detector geometry using ASCII text description and syntax

### 10.3.17 Physics lists

- General ReadMe
- factory demonstrates the usage of G4PhysListFactory to build the concrete physics list.
- extensibleFactory demonstrates the usage of extensible g4alt::G4PhysListFactory to build a concrete physics list. It also demonstrates the setting of an alternative "default" physics list; extending existing lists by adding/replacing physics constructors; and extending the factory with user supplied physics lists.
- genericPL demonstrates the usage of G4GenericPhysicsList to build the concrete physics list at the run time.

#### 10.3.18 Polarisation

• Pol01 - interaction of polarized beam (e.g. circularly polarized photons) with polarized target

## 10.3.19 Radioactive Decay

- rdecay01 demonstrating basic functionality of the G4RadioactiveDecay process
- rdecay02 (Exrdm) decays of radioactive isotopes as well as induced radioactivity resulted from nuclear interactions
- Activation compute and plot time evolution of each nuclide in an hadronic cascade. Compute and plot activity
  of emerging particles.

#### 10.3.20 Run & Event

- RE01 information between primary particles and hits and usage of user-information classes
- RE02 simplified fixed target application for demonstration of primitive scorers
- RE03 use of UI-command based scoring; showing how to create parallel world(s) for defining scoring mesh(es)
- RE04 demonstrating how to define a layered mass geometry in parallel world
- RE05 demonstrating interfacing to the PYTHIA primary generator, definition of a 'readout' geometry, event
  filtering using the stacking mechanism. (It was moved in extended examples from novice/N04 with removal of
  novice examples.)
- RE06 demonstrating how to modify part of the geometry setup at run-time, detector description parameterisation by materials, sharing of a sensitive detector definition for different sub-detectors, different geometrical regions definition with different production thresholds, customization of the G4Run (It was moved in extended examples from novice/N07 with removal of novice examples.)
- RE07 based on extended/electromagnetic/TestEm3, this example demonstrates how to register specialized tracking managers for a particle or a set of particles.

#### 10.3.21 Visualization

- General ReadMe examples (perspective, standalone and userVisAction) of customisation for visualization
- movies illustrating how to create a movie

# 10.4 Advanced Examples

GEANT4 advanced examples illustrate realistic applications of GEANT4 in typical experimental environments. Most of them also show the usage of analysis tools (such as histograms, ntuples and plotting), various visualization features and advanced user interface facilities, together with the simulation core.

**Note:** Maintenance and updates of the code is under the responsibility of the authors. These applications are therefore not subject to regular system testing and no guarantee can be provided.

#### The advanced examples include:

- air\_shower, Simulation of a Fresnel lens focusing direct or reflected UV light onto a photomultiplier. Object parameterisation and replication capabilities of GEANT4 are used to describe the lens geometry. The example is inspired in the configuration of the ULTRA experiment (NIM A 570 (2007) 22).
- amsEcal, illustrating simulation in the AMS electro-magnetic calorimeter.
- brachytherapy, calculating the dose of different brachytherapy sources in a homogeneous phantom.
- CaTS, it demonstrates the G4Opticks hybrid workflow calling Opticks from within Geant4 for the creation and propagation of optical photons on GPU's.
- ChargeExchangeMC, simulating real experiments in Petersburg Nuclear Physics Institute (PNPI, Russia).
- composite calorimeter, test-beam simulation of the CMS Hadron calorimeter at LHC.
- doiPET, modelling a positron emission tomography (PET) scanner with depth-of-interaction detectors.

- eRosita, simplified version of the simulation of the shielding of the eROSITA X-ray mission; it demonstrates the simulation of PIXE (Particle Induced X-ray Emission) as described in M.G. Pia et al., PIXE simulation with GEANT4, IEEE Trans. Nucl. Sci., vol. 56, no. 6, pp. 3614-3649, 2009.
- fastAerosol, demonstrating an efficient solution for accurately and efficiently simulating aerosols.
- gammaknife, reproducing in detail a gammaknife device for stereotactic radiosurgery. In particular, the gammaknife model C is simulated, which is characterized by a symmetrical displacement of the Co60 sources. Dose distributions are acquired in a water spherical phantom using voxelized geometries. The possibility to change the source pattern in order to simulate different gammaknife models is in development and new versions with these additional features will be released.
- gammaray\_telescope, illustrating an application to typical gamma ray telescopes with a flexible configuration.
- gorad, (Geant4 Open-source Radiation Analysis and Design) is developed as a turn-key application for radiation analysis and spacecraft design built on top of Geant4. Simulation geometry should be provided in the form of GDML. Gorad is controlled by UI commands, and it works both in interactive mode with a Qt window and in batch mode with an input macro file. The current Gorad requires Geant4 version 10.7. It does not work with earlier versions of Geant4. Geant4 has to be installed with the GDML interface enabled. Qt is also recommended for the use of Gorad in interactive mode. The Geant4 GDML interface requires Xerces-C++ version 3 or higher. Xerces-C++ has to be compiled with the same compiler version that is used for the Geant4 compilation.
- hadrontherapy, is an example for people interested in Monte Carlo studies related to proton/ion therapy. Hadron-therapy permits the simulation of a typical hadron therapy beam line (with all its elements) and the calculation of fundamentals quantities of interest: 3D dose distributions, fluences, and average LET for both primary and secondary particles, etc.. A typical beamline for laser-driven ion beams is also included.
- HGCal\_testbeam, is an example demonstrating a High Energy Physics test beam setup. It is based on the High Granularity Calorimeter for the CMS experiment and used for Geant4 validation.
- human\_phantom, implementing an Anthropomorphic Phantom body built importing the description from a GDML representation.
- ICRP110\_HumanPhantoms, modelling the ICRP 110 reference computational human phantoms (HG Menzel, C Clement, and P DeLuca. ICRP publication 110. "Realistic reference phantoms: an icrp/icru joint effort: A report of adult reference computational phantoms", Annals of the ICRP, 39(2):1, 2009). The example calculates the dose in individual voxels and in entire organs.
- iort\_therapy, specifically developed to address typical needs related to the IntraOperative Radio-Therapy (IORT) technique. This technique delivers a single dose of radiation directly to the tumor bed, or to the exposed tumor, during surgery. The idea of iort\_therapy is to provide a useful tool for Users interested to radiation dosimetry, dose planning and radio-protection studies in IORT. In fact, the application allows to reconstruct dose distribution curves in water or other materials, to plan dose distribution in the tumor treatment region with different clinical set-up, and to optimize radio-protection of normal patient tissues simulating a composite metallic shielding disc. iort\_therapy simulates the collimator beam line system of a typical medical mobile linac, the phantom, the detector and the composite metallic shielding disc. Via external macro commands it is possible to change the physic models, the collimator beam line, the phantom, the detector and shielding disc geometries, the visualization, the beam particle characteristics, and to activate the Graphical Users Interface (QT libraries are requested)
- lAr calorimeter, simulating the Forward Liquid Argon Calorimeter (FCAL) of the ATLAS Detector at LHC.
- medical\_linac, illustrating a typical medical physics application simulating energy deposit in a phantom filled with water for a typical linac used for intensity modulated radiation therapy. The experimental set-up is very similar to one used in clinical practice.
- microbeam, simulates the cellular irradiation beam line installed on the AIFIRA electrostatic accelerator facility located at CENBG, Bordeaux-Gradignan, France.
- microelectronics, simulates the track of a 5 MeV proton in silicon using very low energy electromagnetic GEANT4 MicroElec processes. It illustrates how to combine these discrete processes with usual GEANT4 condensed history ones, using different processes for different regions of the geometry and different energy ranges.
- nanobeam, simulates the beam optics of the "nanobeam line" installed on the AIFIRA electrostatic accelerator facility located at CENBG, Bordeaux-Gradignan, France.
- purging\_magnet, illustrating an application that simulates electrons traveling through a 3D magnetic field; used in a medical environment for simulating a strong purging magnet in a treatment head.
- radioprotection, illustrating the response characterization of novel solid state detectors for radiation protection

in human space missions and aviation. This example shows how to perform simulations for experimental microdosimetry.

- STCyclotron, simulating the solid target of the South Australian Health and Medical Research Institute (SAHMRI), Adelaide, South Australia. The simulation aims at modelling the production of radio-isotopes and undesired by-products.
- underground\_physics, illustrating an underground detector for dark matter searches.
- xray fluorescence, illustrating the emission of X-ray fluorescence and PIXE.
- xray\_telescope, illustrating an application for the study of the radiation background in a typical X-ray telescope.

## 10.5 Novice Examples

The old "novice" set of examples is now replaced with a new "basic" set, covering the most typical use-cases of a GEANT4 application with keeping simplicity and ease of use.

The source code of the last version of the novice examples set (in 9.6.p02 release) can be viewed in the GEANT4 LXR code browser.

The new location of each example in 10.0 release:

- N01 removed
- N02 basic/B2
- N03 basic/B4
- N04 extended/runAndEvent/RE05
- N05 extended/parameterisations/Par01
- N06 extended/optical/OpNovice
- N07 extended/runAndEvent/RE06

**CHAPTER** 

### **ELEVEN**

### **APPENDIX**

# 11.1 Python Interface

Python is a popular scripting language with an interactive interpreter. Geant4Py, a GEANT4-Python bridge, provides a bridge for GEANT4 classes. This enables to directly access GEANT4 classes from Python scripting. User applications can be easily configured with many Python third-party modules, such as PyROOT, on the Python software bus.

Geant4Py is supplied in the directory environments/g4py/ of the GEANT4 source package and can be built/installed together with the core C++ libraries.

Note that Geant4Py only supports Python 3 and newer.

## 11.1.1 Using Geant4Py

The Geant4 python package is installed by default under <Geant4InstallPrefix>/lib{64}/python3. <PYMINOR>/site-packages, where <*Geant4InstallPrefix*> is the path under which you installed Geant4, and <*PYMINOR*> is the minor version of Python the bindings were built against. If the path to the Geant4 package is not known to Python, it should be appended to the PYTHONPATH environment variable.

Before running Python and importing Geant4, you should also ensure that the environment variables for the Geant4 data libraries are set otherwise you will see errors on import Geant 4.

#### **Import GEANT4**

To use Geant4Py, you start with importing the module called "Geant4".

```
# python
...
>>> from Geant4 import *
```

#### **Access to GEANT4 Globals**

When importing the GEANT4 module, the G4RunManager object will be automatically instantiated. GEANT4 singleton objects are also automatically instantiated. These singleton objects can be accessed by "gXXXX" variables, like "gRunManager".

```
gLossTableManager gTerminate
gApplyUICommand gMaterialTable gTrackingManager
gControlExecute gNistManager gTransportationManager
gElementTable gParticleIterator gUImanager
gEmCalculator gParticleTable gVisManager
```

gEventManager gProcessTable
gExceptionHandler gProductionCutsTable
gG4Date gRunManager
gG4VERSION\_NUMBER gRunManagerKernel
gG4Version gStackManager
gGeometryManager gStartUISession
gGetCurrentValues gStateManager

#### **Call GEANT4 Methods**

Once a Python object of a GEANT4 class instantiated, GEANT4 methods can be directly called the same way as in C++.

```
>>> from Geant4 import *
>>> print gRunManager.GetVersionString()
```

## 11.1.2 Developing Geant4Py

A new set of examples and further documentation are under preparation for Geant4Py at this time. We welcome questions, comments, suggestions for improvement, and example use cases on our Discourse Forum.

## 11.2 GEANT4 Material Database

## 11.2.1 Simple Materials (Elements)

Z	Name	density(g/cm^3)	I(eV)
1	G4_H	8.3748e-05	19.2
2	G4_He	0.000166322	41.8
3	G4_Li	0.534	40
4	G4_Be	1.848	63.7
5	G4_B	2.37	76
6	G4_C	2	81
7	G4_N	0.0011652	82
8	G4_O	0.00133151	95
9	G4_F	0.00158029	115
10	G4_Ne	0.000838505	137
11	G4_Na	0.971	149
12	G4_Mg	1.74	156
13	G4_A1	2.699	166
14	G4_Si	2.33	173
15	G4_P	2.2	173
16	G4_S	2	180
17	G4_Cl	0.00299473	174
18	G4_Ar	0.00166201	188
19	G4_K	0.862	190
20	G4_Ca	1.55	191
21	G4_Sc	2.989	216
22	G4_Ti	4.54	233

Table 11.1 – continued from previous page

Z	Name	density(g/cm^3)	I(eV)
23	G4 V	6.11	245
24	G4 Cr	7.18	257
25	G4 Mn	7.44	272
26	G4_Win	7.874	286
27	G4_1c	8.9	297
28	G4_C0	8.902	311
29	G4_Cu	8.96	322
30	G4_Cu G4 Zn	7.133	330
31	G4_Zii	5.904	334
32	G4_Ga G4 Ge	5.323	350
33	G4_Ge	5.73	347
34	G4_As G4 Se	4.5	348
35	G4_Se G4 Br	0.0070721	343
	G4_Br G4 Kr	0.0070721	352
36	G4_Rb	1.532	
	G4_Rb G4 Sr		363
38		2.54	366
39	G4_Y	4.469	379
40	G4_Zr	6.506	393
41	G4_Nb	8.57	417
42	G4_Mo	10.22	424
43	G4_Tc	11.5	428
44	G4_Ru	12.41	441
45	G4_Rh	12.41	449
46	G4_Pd	12.02	470
47	G4_Ag	10.5	470
48	G4_Cd	8.65	469
49	G4_In	7.31	488
50	G4_Sn	7.31	488
51	G4_Sb	6.691	487
52	G4_Te	6.24	485
53	G4_I	4.93	491
54	G4_Xe	0.00548536	482
55	G4_Cs	1.873	488
56	G4_Ba	3.5	491
57	G4_La	6.154	501
58	G4_Ce	6.657	523
59	G4_Pr	6.71	535
60	G4_Nd	6.9	546
61	G4_Pm	7.22	560
62	G4_Sm	7.46	574
63	G4_Eu	5.243	580
64	G4_Gd	7.9004	591
65	G4_Tb	8.229	614
66	G4_Dy	8.55	628
67	G4_Ho	8.795	650
68	G4_Er	9.066	658
69	G4_Tm	9.321	674
70	G4_Yb	6.73	684
71	G4_Lu	9.84	694
		continues on nex	t nago

Table 11.1 – continued from previous page

Z	Name	density(g/cm^3)	I(eV)
72	G4_Hf	13.31	705
73	G4_Ta	16.654	718
74	G4_W	19.3	727
75	G4_Re	21.02	736
76	G4_Os	22.57	746
77	G4_Ir	22.42	757
78	G4_Pt	21.45	790
79	G4_Au	19.32	790
80	G4_Hg	13.546	800
81	G4_T1	11.72	810
82	G4_Pb	11.35	823
83	G4_Bi	9.747	823
84	G4_Po	9.32	830
85	G4_At	9.32	825
86	G4_Rn	0.00900662	794
87	G4_Fr	1	827
88	G4_Ra	5	826
89	G4_Ac	10.07	841
90	G4_Th	11.72	847
91	G4_Pa	15.37	878
92	G4_U	18.95	890
93	G4_Np	20.25	902
94	G4_Pu	19.84	921
95	G4_Am	13.67	934
96	G4_Cm	13.51	939
97	G4_Bk	14	952
98	G4_Cf	10	966

## 11.2.2 NIST Compounds

G4_A-150_TISSUE 1.127 65.1  1 0.101327 6 0.7755 7 0.035057 8 0.0523159 9 0.017422 20 0.018378 3 G4_ACETONE 0.7899 64.2 6 3 1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4 6 5 1 5	Ncomp		Name d	lensity(g/cm^3)	I(eV) ChFormula
6 0.7755 7 0.035057 8 0.0523159 9 0.017422 20 0.018378 3 G4_ACETONE 0.7899 64.2 6 3 1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4	6	=====	G4_A-150_TISSUE	1.127	
7 0.035057 8 0.0523159 9 0.017422 20 0.018378 3 G4_ACETONE 0.7899 64.2 6 3 1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4		1	0.101327		
8 0.0523159 9 0.017422 20 0.018378 3 G4_ACETONE 0.7899 64.2 6 3 1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4		6	0.7755		
9 0.017422 20 0.018378 3 G4_ACETONE 0.7899 64.2 6 3 1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4		7	0.035057		
20 0.018378 3 G4_ACETONE 0.7899 64.2 6 3 1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4		8	0.0523159		
3		9	0.017422		
6 3 1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4		20	0.018378		
1 6 8 1 2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4	3		G4_ACETONE	0.7899	64.2
2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4		6	3		
2 G4_ACETYLENE 0.0010967 58.2 6 2 1 2 3 G4_ADENINE 1.6 71.4		1	6		
6 2 1 2 3 <b>G4_ADENINE</b> 1.6 71.4		8	1		
2 3 <b>G4_ADENINE</b> 1.6 71.4	2		G4_ACETYLENE	0.0010967	58.2
		6	2		
		1	2		
6 5 1 5	3		G4_ADENINE	1.6	71.4
1 5		6	5		
		1	5		
7 5		7	5		

					(continued from previous page)
7	G4_	ADIPOSE_TISSUE_ICRP	0.95	63.2	
	1				
	6				
	7				
	8				
	11				
	16				
	17				
4			0.00120479	85.7	
	6				
	7				
	8				
	18				
4		G4_ALANINE	1.42	71.9	
	6				
	1	7			
	7	1			
	8	2			
2		G4_ALUMINUM_OXIDE	3.97	145.2	Al_20_3
	13				
	8				
3		G4_AMBER	1.1	63.2	
	1				
	6	0.788974			
	8	0.105096			
2		G4_AMMONIA	0.000826019	53.7	
	7				
	1	3			
3		G4_ANILINE	1.0235	66.2	
	6	_ 6			
	1	7			
	7	1			
2		G4_ANTHRACENE	1.283	69.5	
	6	14			
	1	10			
6		G4_B-100_BONE	1.45	85.9	
	1	0.0654709			
	6	0.536944			
	7	0.0215			
	8	0.032085			
	9	0.167411			
	20	0.176589			
3		G4_BAKELITE	1.25	72.4	
	1				
	6	0.774591			
	8				
2		G4_BARIUM_FLUORIDE	4.89	375.9	
	56				
	9				
3		G4_BARIUM_SULFATE	4.5	285.7	
	56				
	16				
	8				
2		G4_BENZENE	0.87865	63.4	
	6				
	1				
2		G4_BERYLLIUM_OXIDE	3.01	93.2	
	4				
	8				
3			7.13	534.1	
	83				
	32				
	8				
10		G4_BLOOD_ICRP	1.06	75.2	
	1				
	6	0.11			
					(continues on next page)

				(continued from previous page)
	7 0.033			
	8 0.745			
	11 0.001			
	15 0.001			
	16 0.002			
	17 0.003			
	19 0.002			
	26 0.001			
8	G4_BONE_COMPACT_ICRU	1.85	91.9	
	1 0.064			
	6 0.278			
	7 0.027			
	8 0.41			
	12 0.002			
	15 0.07			
	16 0.002			
	20 0.147			
9	G4_BONE_CORTICAL_ICRP	1.92	110	
	1 0.034	1.02		
	6 0.155			
	7 0.042			
	8 0.435			
	11 0.001			
	12 0.002			
	15 0.103			
	16 0.003			
	20 0.225			
2	G4_BORON_CARBIDE	2.52	84.7	
_	5 4	2.02	01.7	
	6 1			
2	G4_BORON_OXIDE	1.812	99.6	
_	5 2	1.012	JJ. 0	
	8 3			
9	G4_BRAIN_ICRP	1.04	73.3	
	1 0.107	1.01	, 3 • 3	
	6 0.145			
	7 0.022			
	8 0.712			
	11 0.002			
	15 0.004			
	16 0.002			
	17 0.003			
	19 0.003			
2	G4_BUTANE	0 00249343	48.3	
	6 4	0.00219313	10.5	
	1 10			
3	G4_N-BUTYL_ALCOHOL	0.8098	59.9	
3	6 4	0.0000	33.3	
	1 10			
	8 1			
5		1.76	26.2	
3	1 0.02468	1.70	00.0	
	6 0.501611			
	8 0.004527			
	9 0.465209			
	14 0.003973			
2		6.2	530 3	
2	G4_CADMIUM_TELLURIDE	6.2	539.3	
	48 1			
3	52 1	7 0	460	
3	G4_CADMIUM_TUNGSTATE	7.9	468.3	
	48 1			
	74 1			
	8 4		100	
3	G4_CALCIUM_CARBONATE	2.8	136.4	
	20 1			
	6 1			(continues on next page)
				(continues on next nage)

					(continued from previous page)
	8				
2		4_CALCIUM_FLUORIDE	3.18	166	
	20				
0	9	2	2.2	176.1	
2	20	G4_CALCIUM_OXIDE	3.3	176.1	
	8	1			
3		G4_CALCIUM_SULFATE	2.96	152.3	
	20	1	2.30	102.0	
	16	1			
	8	4			
3		_CALCIUM_TUNGSTATE	6.062	395	
	20	1			
	74 8	1 4			
2	0	G4_CARBON_DIOXIDE	0 00184212	85	CO_2
_	6	1	0.00101212	00	00_2
	8	2			
2	G4_CA	RBON_TETRACHLORIDE	1.594	166.3	
	6	1			
	17	4			
3	G4_CE 6	LLULOSE_CELLOPHANE	1.42	77.6	
	1	10			
	8	5			
3		CELLULOSE_BUTYRATE	1.2	74.6	
	1	0.067125			
	6	0.545403			
	8	0.387472			
4		_CELLULOSE_NITRATE	1.49	87	
	6	0.029216 0.271296			
	7	0.121276			
	8	0.578212			
5		G4_CERIC_SULFATE	1.03	76.7	
	1	0.107596			
	7	0.0008			
	8	0.874976			
	16	0.014627 0.002001			
2		G4_CESIUM_FLUORIDE	<i>A</i> 115	440 7	
2	55	1	4.113	440.7	
	9	1			
2		G4_CESIUM_IODIDE	4.51	553.1	
	55	1			
	53	1			
3	_	G4_CHLOROBENZENE	1.1058	89.1	
	6 1	6 5			
	17	1			
3		G4_CHLOROFORM	1.4832	156	
	6	1			
	1	1			
	17	3		105	
10	1	G4_CONCRETE	2.3	135.2	
	1 6	0.01			
	8	0.529107			
	11	0.016			
	12	0.002			
	13	0.033872			
	14	0.337021			
	19	0.013			
	20 26	0.044			
2	26	G4_CYCLOHEXANE	0.779	56.4	
		G1_C1CHOHEARNE	0.119	50.4	(continues on next page)

				(continued from previous page)
	6 6			
	1 12	1 2212	106	
3	G4_1,2-DICHLOROBENZENE	1.3048	106.5	
	1 4			
	17 2			
4	G4_DICHLORODIETHYL_ETHER	1.2199	103.3	
	6 4 1 8			
	8 1			
	17 2			
3	G4_1,2-DICHLOROETHANE	1.2351	111.9	
	6 2 1 4			
	17 2			
3	G4_DIETHYL_ETHER	0.71378	60	
	6 4 1 10			
	8 1			
4	G4_N,N-DIMETHYL_FORMAMIDE	0.9487	66.6	
	6 3			
	1 7 7 1			
	8 1			
4	G4_DIMETHYL_SULFOXIDE	1.1014	98.6	
	6 2			
	1 6 8 1			
	16 1			
2		0.00125324	45.4	
	6 2 1 6			
3	G4_ETHYL_ALCOHOL	0.7893	62.9	
	6 2			
	1 6			
3	8 1 G4_ETHYL_CELLULOSE	1 13	69 3	
	1 0.090027	1.10	03.0	
	6 0.585182			
2	8 0.324791 G4_ETHYLENE	0 00117407	50 7	
2	6 2	0.0011/45/	30.7	
	1 4			
8	G4_EYE_LENS_ICRP	1.07	73.3	
	1 0.096 6 0.195			
	7 0.057			
	8 0.646			
	11 0.001 15 0.001			
	16 0.003			
	17 0.001			
2	G4_FERRIC_OXIDE	5.2	227.3	
	26 2 8 3			
2	G4_FERROBORIDE	7.15	261	
	26 1			
2	5 1 G4 FERROUS OXIDE	E 7	210 6	
2	G4_FERROUS_OXIDE	5.7	248.6	
	8 1			
7	G4_FERROUS_SULFATE	1.024	76.4	
	1 0.108259 7 2.7e-05			
	8 0.878636			
	11 2.2e-05			
				(continues on next page)

(continues on next page)

442

					(continued from previous page)
	16	0.012968			
	17	3.4e-05			
	26	5.4e-05			
3		G4_FREON-12	1.12	143	
	6	0.099335			
	9	0.314247			
3	17	0.586418	1 0	2010	
3	6	G4_FREON-12B2 0.057245	1.8	284.9	
	9	0.181096			
	35	0.761659			
3		G4_FREON-13	0.95	126.6	
	6	0.114983			
	9	0.545621			
	17	0.339396			
3	_	G4_FREON-13B1	1.5	210.5	
	6 9	1 3			
	35	1			
3		G4_FREON-13I1	1.8	293.5	
	6	0.061309			
	9	0.290924			
	53	0.647767			
3	_	LINIUM_OXYSULFIDE	7.44	493.3	
	64	2			
	8 16	2 1			
2		_GALLIUM_ARSENIDE	5.31	384.9	
	31	1			
	33	1			
5			1.2914	74.8	
	1	0.08118			
	6 7	0.41606			
	8	0.11124 0.38064			
	16	0.01088			
6		G4_Pyrex_Glass	2.23	134	
	5	0.0400639			
	8	0.539561			
	11	0.0281909			
	13	0.011644			
	14 19	0.377219 0.00332099			
5	1.0	G4_GLASS_LEAD	6.22	526.4	
	8	0.156453			
	14	0.080866			
	22	0.008092			
	33	0.002651			
4	82	0.751938	0.4	1 4 5 4	
4	8	G4_GLASS_PLATE 0.4598	2.4	145.4	
	11	0.0964411			
	14	0.336553			
	20	0.107205			
4		G4_GLUTAMINE	1.46	73.3	
	6	5			
	1	10			
	7 8	2 3			
3	δ	G4_GLYCEROL	1.2613	72.6	
	6	3	1.2010		
	1	8			
	8	3			
4		G4_GUANINE	2.2	75	
	6 1	5 5			
	1	7			(continues on next page)

				(continued from previous page)
	7 5			
	8 1			
4		2.32	129.7	
	20 1 16 1			
	8 6			
	1 4			
2	G4_N-HEPTANE	0.68376	54.4	
	6 7			
2	1 16 G4_N-HEXANE	0 6603	54	
2	6 6	0.0003	54	
	1 14			
4		1.42	79.6	
	6 22 1 10			
	1 10 7 2			
	8 5			
3	G4_LANTHANUM_OXYBROMIDE	6.28	439.7	
	57 1			
	35 1 8 1			
3	G4_LANTHANUM_OXYSULFIDE	5.86	421.2	
3	57 2	3.00	121.2	
	8 2			
	16 1			
2	<b>G4_LEAD_OXIDE</b> 8 0.071682	9.53	766.7	
	82 0.928318			
3		1.178	55.5	
	3 1			
	7 1			
3	1 2 G4_LITHIUM_CARBONATE	2 11	07.0	
3	3 2	2.11	87.9	
	6 1			
	8 3			
2		2.635	94	
	3 1 9 1			
2	G4_LITHIUM_HYDRIDE	0.82	36.5	
	3 1			
	1 1			
2		3.494	485.1	
	3 1 53 1			
2	G4_LITHIUM_OXIDE	2.013	73.6	
	3 2			
	8 1			
3	G4_LITHIUM_TETRABORATE	2.44	94.6	
	3 2 5 4			
	8 7			
9	G4_LUNG_ICRP	1.04	75.3	
	1 0.105			
	6 0.083			
	7 0.023 8 0.779			
	11 0.002			
	15 0.001			
	16 0.002			
	17 0.003			
5	19 0.002	1.05	67.9	
3	G4_M3_WAX 1 0.114318	1.05	07.9	
	6 0.655824			
				(continues on next page)

				(continued from previous page)
	8 0.0921831			
	12 0.134792			
	20 0.002883			
3	G4_MAGNESIUM_CARBONATE	2.958	118	
	12 1	2.,,00	110	
	6 1			
	8 3			
2	G4_MAGNESIUM_FLUORIDE	3	134.3	
	12 1	9	134.3	
	9 2			
2		3.58	143.8	
_	12 1	0.00	110.0	
	8 1			
3	G4_MAGNESIUM_TETRABORATE	2.53	108.3	
	12 1	2.00	100.0	
	5 4			
	8 7			
2		6.36	684.5	
_	80 1	0.00	001.0	
	53 2			
2		0.000667151	41.7	
_	6 1			
	1 4			
3		0.7914	67.6	
	6 1		J. •	
	1 4			
	8 1			
5		0.99	60.9	
	1 0.13404	0.33	00.5	
	6 0.77796			
	8 0.03502			
	12 0.038594			
	22 0.014386			
6	G4_MS20_TISSUE	1	75 1	
O	1 0.081192	_	73.1	
	6 0.583442			
	7 0.017798			
	8 0.186381			
	12 0.130287			
	17 0.0009			
9	G4_MUSCLE_SKELETAL_ICRP	1 05	75.3	
9	1 0.102	1.00	75.5	
	6 0.143			
	7 0.034			
	11 0.001			
	15 0.002			
	16 0.003			
	17 0.001			
0	19 0.004	1 0 1	74.7	
8	G4_MUSCLE_STRIATED_ICRU	1.04	74.7	
	1 0.102102			
	6 0.123123			
	7 0.035035			
	8 0.72973			
	11 0.001001			
	15 0.002002			
	16 0.004004			
	19 0.003003			
4	G4_MUSCLE_WITH_SUCROSE	1.11	74.3	
	1 0.0982341			
	6 0.156214			
	7 0.035451			
	8 0.710101			
4		1.07	74.2	
	1 0.101969			
				(continues on next page)

					(continued from previous page)
	6	0.120058			
	7	0.035451			
	8	0.742522			
2		G4_NAPHTHALENE	1.145	68.4	
	6	10			
	1	8			
4		G4_NITROBENZENE	1.19867	75.8	
	6	6 5			
	1 7	1			
	8	2			
2	0	G4_NITROUS_OXIDE	0 00183094	84 9	
2	7	2	0.00103031	01.9	
	8	1			
4		G4_NYLON-8062	1.08	64.3	
	1	0.103509			
	6	0.648416			
	7	0.0995361			
	8	0.148539			
4	_	G4_NYLON-6-6	1.14	63.9	
	6 1	6 11			
	7	1			
	8	1			
4	O O	G4_NYLON-6-10	1.14	63.2	
	1	0.107062			
	6	0.680449			
	7	0.099189			
	8	0.1133			
4		G4_NYLON-11_RILSAN	1.425	61.6	
	1				
	6	0.720818			
	7	0.0764169			
2	8	0.0872889 G4_OCTANE	0.7026	54.7	
2	6	G4_OCIANE 8	0.7026	54.7	
	1	18			
2	-	G4_PARAFFIN	0.93	55.9	
	6	<b>–</b> 25			
	1	52			
2		G4_N-PENTANE	0.6262	53.6	
	6	5			
	1	12	0.045	0.04	
8	-	G4_PHOTO_EMULSION	3.815	331	
	1	0.0141 0.072261			
	7	0.072261			
	8	0.066101			
	16	0.00189			
	35	0.349103			
	47	0.474105			
	53	0.00312			
2 0	G4_PLAST	TIC_SC_VINYLTOLUENE	1.032	64.7	
	6				
	1				
2		1_PLUTONIUM_DIOXIDE	11.46	746.5	
	94	1			
2	8		1 19	60 6	
3	6	1_POLYACRYLONITRILE	1.17	69.6	
	1				
	7	1			
3	,	G4_POLYCARBONATE	1.2	73.1	
	6	16		,,,,	
	1				
	8	3			
					(continues on next page)

				(continued from previous page)
3	G4_POLYCHLOROSTYRENE	1.3	81.7	
	6 8			
	1 7 17 1			
2	G4_POLYETHYLENE	0.94	57.4	(C_2H_4)_N-Polyethylene
	6 1			
3	1 2 G4_MYLAR	1.4	78.7	
3	6 10	1.4	10.1	
	1 8			
2	8 4	1 10	7.4	
3	G4_PLEXIGLASS 6 5	1.19	74	
	1 8			
	8 2			
3	G4_POLYOXYMETHYLENE 6 1	1.425	77.4	
	1 2			
	8 1			
2	G4_POLYPROPYLENE	0.9	56.5	(C_2H_4)_N-Polypropylene
	6 2 1 4			
2	G4_POLYSTYRENE	1.06	68.7	
	6 8			
2	1 8 G4_TEFLON	2.2	99.1	
	6 2	2 • 2	JJ.1	
	9 4			
3 (	G4_POLYTRIFLUOROCHLOROETHYLENE 6 2	2	.1 120	.7
	9 3			
	17 1			
3	G4_POLYVINYL_ACETATE 6 4	1.19	73.7	
	1 6			
	8 2			
3	G4_POLYVINYL_ALCOHOL 6 2	1.3	69.7	
	1 4			
	8 1			
3		1.12	67.2	
	6 8 1 14			
	8 2			
3	G4_POLYVINYL_CHLORIDE	1.3	108.2	
	6 2 1 3			
	17 1			
3 (	G4_POLYVINYLIDENE_CHLORIDE	1.7	134.3	
	6 2 1 2			
	17 2			
3 (	G4_POLYVINYLIDENE_FLUORIDE	1.76	88.8	
	6 2 1 2			
	9 2			
4	G4_POLYVINYL_PYRROLIDONE	1.25	67.7	
	6 6 1 9			
	7 1			
	8 1			
2	G4_POTASSIUM_IODIDE 19 1	3.13	431.9	
	53 1			
2	G4_POTASSIUM_OXIDE	2.32	189.9	
	19 2			(continues on payt page)

					(continued from previous page	e)
	8 1					
2		0.00187939	47.1			
	6 3					
2	1 8	0.42	FO			
2	G4_1PROPANE 6 3	0.43	52			
	1 8					
3	G4_N-PROPYL_ALCOHOL	0.8035	61.1			
	6 3					
	1 8					
	8 1					
3	G4_PYRIDINE	0.9819	66.2			
	6 5 1 5					
	1 5 7 1					
2	G4_RUBBER_BUTYL	0.92	56.5			
-	1 0.143711	0.52	30.3			
	6 0.856289					
2	G4_RUBBER_NATURAL	0.92	59.8			
	1 0.118371					
	6 0.881629					
3	G4_RUBBER_NEOPRENE	1.23	93			
	1 0.05692 6 0.542646					
	6 0.542646 17 0.400434					
2	G4_SILICON_DIOXIDE	2 32	139 2	SiO 2		
	14 1	2.52	137.2	510_2		
	8 2					
2	G4_SILVER_BROMIDE	6.473	486.6			
	47 1					
	35 1					
2	G4_SILVER_CHLORIDE	5.56	398.4			
	47 1 17 1					
3	G4_SILVER_HALIDES	6 17	487.1			
3	35 0.422895	0.47	407.1			
	47 0.573748					
	53 0.003357					
2	G4_SILVER_IODIDE	6.01	543.5			
	47 1					
	53 1	4 00				
9	G4_SKIN_ICRP 1 0.1	1.09	72.7			
	6 0.204					
	7 0.042					
	8 0.645					
	11 0.002					
	15 0.001					
	16 0.002					
	17 0.003					
3	19 0.001 G4_SODIUM_CARBONATE	2 522	125			
5	G4_SODIOM_CARBONATE	2.332	123			
	6 1					
	8 3					
2	G4_SODIUM_IODIDE	3.667	452			
	11 1					
	53 1					
2	G4_SODIUM_MONOXIDE	2.27	148.8			
	11 2 8 1					
3	G4_SODIUM_NITRATE	2 261	114.6			
	11 1 1	2.201	114.0			
	7 1					
	8 3					
2	G4_STILBENE	0.9707	67.7			
					(continues on next no	-~ \

				(continued from previous page)
	6 14			
	1 12			
3	G4_SUCROSE	1.5805	77.5	
	6 12			
	1 22			
	8 11			
2	G4_TERPHENYL	1.24	71.7	
	6 18			
9	1 14	1.04	75	
9	G4_TESTIS_ICRP 1 0.106	1.04	75	
	6 0.099			
	7 0.02			
	8 0.766			
	11 0.002			
	15 0.001			
	16 0.002			
	17 0.002			
	19 0.002			
2	G4_TETRACHLOROETHYLENE	1.625	159.2	
	6 2 17 4			
2	17 4 G4_THALLIUM_CHLORIDE	7.004	690.3	
2	81 1	7.004	0,00.5	
	17 1			
9	G4_TISSUE_SOFT_ICRP	1.03	72.3	
	1 0.105			
	6 0.256			
	7 0.027			
	8 0.602			
	11 0.001			
	15 0.002			
	16 0.003 17 0.002			
	19 0.002			
4	G4_TISSUE_SOFT_ICRU-4	1	74.9	
	1 0.101			
	6 0.111			
	7 0.026			
	8 0.762			
4	G4_TISSUE-METHANE	0.00106409	61.2	
	1 0.101869			
	6 0.456179			
	7 0.035172 8 0.40678			
4	G4_TISSUE-PROPANE	0 00182628	59.5	
-4	1 0.102672	0.00102020	39.3	
	6 0.56894			
	7 0.035022			
	8 0.293366			
2	G4_TITANIUM_DIOXIDE	4.26	179.5	
	22 1			
	8 2			
2	G4_TOLUENE	0.8669	62.5	
	6 7 1 8			
3	G4_TRICHLOROETHYLENE	1 46	148 1	
5	6 2	1.10	140.1	
	1 1			
	17 3			
4	G4_TRIETHYL_PHOSPHATE	1.07	81.2	
	6 6			
	1 15			
	8 4			
0	15 1	0.1	254.4	
2	G4_TUNGSTEN_HEXAFLUORIDE	2.4	354.4	(continues on payt page)

						(continued from previous page)
	74	1				
	9	6				
2	G4_1	URANIUM_DICARBIDE	11.28	752		
	92	1				
	6	2				
2	G4_UR	ANIUM_MONOCARBIDE	13.63	862		
	92	1				
	6	1				
2		G4_URANIUM_OXIDE	10.96	720.6		
	92	1				
	8	2				
4		G4_UREA	1.323	72.8		
	6	1				
	1	4				
	7	2				
	8	1				
4		G4_VALINE	1.23	67.7		
	6	5				
	1	11				
	7	1				
	8	2				
3	-	G4_VITON	1.8	98.6		
	1	0.009417				
	6	0.280555				
2	9	0.710028	1	78		
2	1	G4_WATER 2	1	78	H_20	
	8	1				
2	O	G4_WATER_VAPOR	0 000756102	71 6	H_20-Gas	
	1	2	0.000730102	71.0	n_20-Gas	
	8	1				
2		G4_XYLENE	0.87	61.8		
	6	8	0.07	01.0		
	1	10				
1	_	G4_GRAPHITE	2.21	78	Graphite	
_		00				

## 11.2.3 HEP and Nuclear Materials

Ncomp	====	 Name	density(g/cm^3)	I (eV)	 ChFormula
1	=====	G4_1H2	 2 0.0708	21.8	
1		G4_1N2	0.807	82	
1		G4_102	1.141	95	
1		G4_lAı	1.396	188	
1		G4_lBr	3.1028	343	
1		G4_lKı	2.418	352	
1		G4_1X6	2.953	482	
3		G4_PbWO4	8.28	0	
	8	4			
	82	1			
	74	1			
1		G4_Galactic	1e-25	21.8	
1	(	G4_GRAPHITE_POROUS	1.7	78	Graphite
3		G4_LUCITE	1.19	74	
	1	0.080538			
	6	0.599848			
	8	0.319614			
3		G4_BRASS	8.52	0	
	29	62			
	30	35			
	82	3			
3		G4_BRONZE	8.82	0	

	29	89					
	30	9					
	82	2					
3	G4_	_STAINLESS-STEEL	8	0			
	26	74					
	24	18					
	28	8					
3		G4_CR39	1.32	0			
	1	18					
	6	12					
	8	7					
3		G4_OCTADECANOL	0.812	0			
	1	38					
	6	18					
	8	1					

## 11.2.4 Space (ISS) Materials

Ncomp	 >	Name d		I(eV) ChFormula
4		_	1.44	0
	6 1	14		
	8	2		
	7	2		
3	6	G4_DACRON	1.4	0
	1	8		
	8	4		
3	6	G4_NEOPRENE	1.23	0
	1	5		
	17	1		

## 11.2.5 Bio-Chemical Materials

Ncomp		 Name	density(g/cm^3)	I (eV)	ChFormula
4		G4_CYTOSINE	1.55	72	
	1	5			
	6	4			
	7	3			
	8	1			
4		G4_THYMINE	1.23	72	
	1	6			
	6	5			
	7	2			
	8	2			
4		G4_URACII	1.32	72	
	1	4			
	6	4			
	7	2			
	8	2			
3		G4_DNA_ADENINE	1	72	
	1	4			
	6	5			
	7	5			
4		G4_DNA_GUANINE	1	72	

				(continued from previous page)
	1 4			
	6 5			
	7 5			
	8 1			
4		1	72	
	1 4			
	6 4			
	7 3			
	8 1	4	70	
4		1	12	
	1 5 6 5			
	7 2			
	8 2			
4	G4_DNA_URACIL	1	72	
	1 3			
	6 4			
	7 2			
	8 2			
4		1	72	
	1 10			
	6 10			
	7 5			
4	8 4 G4_DNA_GUANOSINE	1	70	
4	G4_DNA_GUANOSINE 1 10	1	72	
	6 10			
	7 5			
	8 5			
4	G4 DNA CYTIDINE	1	72	
	1 10			
	6 9			
	7 3			
	8 5			
4	G4_DNA_URIDINE	1	72	
	1 9			
	6 9			
	7 2			
1	8 6 G4_DNA_METHYLURIDINE	1	72	
4	G4_DNA_METHILORIDINE 1 11	1	12	
	6 10			
	7 2			
	8 6			
2		1	72	
	15 1			
	8 3			
5	G4_DNA_A	1	72	
	1 10			
	6 10			
	7 5			
	8 7			
_	15 1			
5	G4_DNA_G	1	72	
	1 10 6 10			
	7 5			
	8 8			
	15 1			
5	G4_DNA_C	1	72	
	1 10			
	6 9			
	7 3			
	8 8			
	15 1			
5	G4_DNA_U	1	72	
				(continues on next page)



# 11.3 Transportation in Magnetic Field - Further Details

## 11.3.1 The challenge of integrating all tracks

#### What leads us to discard tracks looping in a magnetic field

The integration of charged particle tracks in magnetic field is an important part of the computational cost (CPU time). Part of this cost is due to integration of low-energy particles in a volume with low density and strong magnetic field.

In HEP applications the most important type of tracks causing such problems are electrons in the vacuum of beam pipes. Charged particles in volumes near decay volumes and muons in large volumes of air are other examples.

To limit this CPU cost, an effective tracking cut was implemented since Geant4 release 7.0 in G4Transportation and G4CoupledTransportation. Tracks which require more than a threshold number of integration steps (currently 1,000) during a physics/tracking step are marked as 'looping' and are considered candidates for being killed i.e. they can potentially be abandoned after the current step, and have their energy deposited locally.

Recent enhancements (in 10.5-beta) have provided more comprehensive information about the tracks killed, in the form of G4Exceptions warning messages.

This section describes this policy, the parameters which the user is able to set to tune it, and recent refinements implemented in Geant4 10.5.

#### **Cost of integration**

Occasionally tracks 'looping' in a strong magnetic field, making little progress even over thousands of integration steps. This is due to a combination of a strong magnetic field and a thin material (gas or vacuum) in which the size of a physics step is substantially larger than the radius of curvature of the track.

The preferred integration method for tracks in an EM field is the Runge-Kutta method. This and other similar methods are well suited to variations in magnetic fields and step sizes up to a few times the radius of curvature of the charged tracks.

However when the step sizes are hundreds or thousands of times larger than the curvature of the track, these methods are expensive as they do not progress the integration of a track adequately.

The amount of CPU time which can be consumed by one or few such tracks can very large, sometimes contributing per cent increases to the simulation of some primary particles. Some tracks with a very small drift velocity (projection of the velocity along the vector of the magnetic field) can stop the progress of a simulation if they are not limited or integrated using alternative means.

So it is important to limit the number of integration steps spent on these tracks. The module for propagation in field in Geant4 flags tracks which take more than a certain number (default 1,000) integration steps without reaching the requested end of the step size, which was determined by the physics and geometry.

#### Parameters for eliminating or controling which particles are killed

The Geant4 G4Transportation and G4CoupledTransportation processes are tasked to select which of the tracks flagged as looping are killed and which survive. To balance the potential significant cost of integrating looping particles, three thresholds exist: - the 'Warning' Energy: a track with energy below this value that is found to loop is killed silently (no warning.) Above the 'Warning Energy', if a track is selected for killing then a warning is generated. - the 'Important' Energy: the threshold energy above which a track will survive for multiple steps if found looping. - the number of extra 'tracking' steps for important particles. These tracks will be only be killed only if they still loop more than this number of trial steps. (So in effect the number of integration steps will be this number times the maximum number of steps allowed in G4PropagatorInField.

In versions of Geant4 from 7.0 up to release 10.4, Transportation did not examine the types of a charged particle - all types of particles were killed if they fulfilled the same criteria. A short message was written in the G4cout output that gave the energy and location of the killed track. This printout was under the G4VERBOSE flag, so it was suppressed if the G4 NO VERBOSE configuration option was chosen at installation.

#### In Geant4 10.5 several changes have been implemented:

- only stable particles are killed. ( Re-enabling the killing of unstable particles as an option is envisioned. )
- each particle with energy above the warning energy which is killed generates a detailed warning (using G4Exception) with the full information about the particle location, the current volume and its material, and the particle momentum and energy.
- for the first 5 tracks killed a detailed description is printed that describes the criteria and parameters which are used to decide what tracks are killed, and provides a first guidance regarding how to 'save' tracks by chaning the values of thresholds or by adopting different integration methods.

Below we discuss the different way in which a user can change the thresholds for killing 'looping' tracks, which criteria can be used to ensure that a track continues to propagate and for how many steps an 'important' track that is 'looping' can survive.

Two techniques are demonstrated below. An example of using them is available in the extended example field01, in the directory examples/extended/field01.

## 11.3.2 Using preset thresholds for killing loopers

This method is new in Geant4 release 10.5, and uses the G4PhysicsListHelper which has methods to choose a preselected set of parameter values. The choices are between a set each of low and high thresholds. Either one can be enabled by calling correspondingly method.

It is possible to select a set of pre-selected values of the parameters for looping particles using

New functionality in G4PhysicsListHelper, introduced in Geant4 release 10.5, enables the Transportation process chosen to be provided with this set of parameters. This reuses the AddTransportation method, which is called in each thread.

To configure with low values of the thresholds, appropriate for typical applications using low-energy physics, choose

```
#include "G4PhysicsListHelper.hh"

int main( int, char**)
{
    auto plHelper = G4PhysicsListHelper::GetPhysicsListHelper();

    plHelper->UseLowLooperThresholds();
    //
    // Use low values for the thresholds
    // Warning 1 keV, Important 1 MeV, trials 10

    auto physList = new FTFP_BERT();
    // ...
}
```

The original high values of the parameters can be selected with a similar call

```
plHelper->UseHighLooperThresholds();
//
// Configures with the original (high) values of parameters. Currently:
// Warning 100 MeV, Important 250 MeV, trials 10
```

and are chosen as starting points for energy-frontier HEP experiments.

The above sequence is demonstrated in the main() of field01.cc, part of the extended field examples (examples/extended/field01.)

This configuration method works only if modular physics lists are used, or if the AddTransportation() method is used to construct the transportation in a user physics list.

These calls must be done *before* a physics list is instantiated, in particular before G4PhysicsListHelper::AddTransportation() is called during the construction of a physics list. Else the configuration of the parameters does not occur.

These methods must be called before the physics is constructed - i.e. typically before G4RunManager 's Initialise method is called.

In order for this method to work the physics list must be constructed in one of two ways:

- a preconstructed physics lists, from the list of recommended physics lists, or
- the list must be constructed using the G4ModularPhysicsList and its AddTransportation method.

Note that in each thread the AddTransportation instantiates a single common transportation process which is then used by all particles types.

Users who build a physics list without making use of G4ModularPhysicsList and its AddTransportation method, are responsible to register a Transportation process to each particle type, and to set its parameters appropriately. This would allow the most finer grained control, and would also allow different thresholds to be chosen for different particle types.

## 11.3.3 Fine grained control of the parameters for killing looping particles

Fine grained control is also possible. The user can choose arbitrary values for the different parametes related to killing loopers and also refine the integration of charged particle propagation in particular volumes in order to eliminate or reduce the incidence of looping tracks.

This method will work in all Geant4 versions since 7.0.

To obtain reliable configuration of the G4Transportation (or G4CoupledTransportation) process in a potentially multi-threaded application, we configure it using a G4VUserRunAction. In particular such configuration can be undertaken in the BeginOfRunAction methods.

For example, to ensure that only looping particles with energy 10 keV are killed silently we change the value of the 'Warning' Energy

```
transport->SetThresholdWarningEnergy( 1.0 * CLHEP::keV );
```

As a result the killing of any (stable) looping track with energy over 10 keV will generate a warning.

The second configurable energy threshold is labelled the 'important' energy and it enables tracks above its value to survive a chosen number of 'tracking' steps. They will be only be killed only if they are still looping after the given number of tracking steps.

These are demonstrated also in the F01RunAction's ChangeLooperParameters method, which is called by the BeginOfRunAction.

To obtain the appropriate Transportation object for a particular particle type G4ParticleDefinition \particleDef; we can use a helper method F01RunAction::FindTransportation, or else manually obtain it:: G4VProcess\* partclTransport = particleDef->GetProcessManager()->GetProcess("Transportation");

auto transport= dynamic\_cast<G4Transportation\*>(partclTransport);

In case a different Transportation type is used, e.g. G4CoupledTransportation or G4ITTransportation, similar code is currently required for each class. (This is also backward compatible with previous G4 versions.)

Once a pointer is obtained to the transportation process, it is a simple matter to change the values of the relevant parameters, e.g.

```
transport->SetThresholdWarningEnergy( 1.0 * CLHEP::keV );
transport->SetThresholdImportantEnergy( 1.0 * CLHEP::MeV );
transport->SetNumberOfTrials( 20 );
```

Such an example on how to overwrite the thresholds in the G4Transportation class can be found in F01RunAction 's .. comment ChangeLooperParameters (const G4ParticleDefinition\* particleDef) ChangeLooperParameters method

```
if( transport != nullptr )
{
    // Change the values of the looping particle parameters of Transportation
    transport->SetThresholdWarningEnergy( theWarningEnergy);
    transport->SetThresholdImportantEnergy( theImportantEnergy);
    transport->SetThresholdTrials( theNumberOfTrials);
}
else if( coupledTransport != nullptr )
{
    // Change the values for Coupled Transport
    coupledTransport->SetThresholdWarningEnergy( theWarningEnergy);
    coupledTransport->SetThresholdImportantEnergy( theImportantEnergy);
    coupledTransport->SetThresholdTrials( theNumberOfTrials );
}
.. SetTransportationParams2::
```

Note that for all pre-configured and modular physics lists share a single Transportation process for all types of particles. So the parameters for killing loopers will be shared by all particle types in this case.

F01RunAction plays the role of a helper object, which holds the proposed (new) values of parameters, and which can allow them to be set, e.g., in the main () function

```
runAction->SetWarningEnergy( 10.0 * CLHEP::keV );
```

F01RunAction then forwards them to the Transportation object of each thread at the start of each run.

#### Using a helper object to forward parameter changes

Since the type of the transportation it can be useful to use a helper object to hold the desired values for the parameters (thresholds, number of iterations), and to forward them to the Transportation class.

This is demonstrated in the class F01RunAction and its ChangeLooperParameters method of the field01 extended example.

It copes with either transportation class, G4Transportation or a G4CoupledTransportation, and passes new values of parameters as needed.

In field01 the methods of F01RunAction

```
runAction->SetImportantEnergy( 0.1 * CLHEP::MeV );
runAction->SetNumberOfTrials( 30 );
```

which the run action passes to the G4Transportation or G4CoupledTransportation object registered for the electron in F01RunAction 's method ChangeLooperParameters.

#### Avoiding loopers or reducing the incidence of looping particles

There are different ways to reduce the occurrence of looping particles. This section will provide an overview, and refer the user to the detailed information on particle propagation in a magnetic field for details.

Volumes which have a strong field and contain vacuum, large air cavities or large volumes of gases are prime candidates for causing integration difficulties for low energy charged particles, which result in looping particles.

- A very simple way to reduce the incidence of looping particles is to reduce the maximum step size which particles that interact very infrequently can travel. Geant4 attempts to estimate an effective maximum using the diameter of the world volume, and frequently the maximum step size is large if the experimental hall is used as the world volume and has large dimentions. A smaller value can be impose by using the method. G4PropagatorInField::SetMaximumStepSize()
- Another ways is to change the maximum number of integration substeps. The default value is 1000, but it can be obtained from G4PropagatorInField:

It can be also be changed simply by calling the corresponding set method, e.g.:

```
propFld->SetMaxLoopCount(2500);
```

- Assign a separate G4FieldManager class to each such volume. It can use adapted methods for the integration
  of the ODEs of motion.
- One solution is to use a helical stepper, such as G4HelixImplicitEuler or G4HelixHeum which are inherently for steps over multiple 'turns' of a helix-like track. Their reason d' etre is the ability to use the helix solution as baseline 'first-order' like solution and treat deviations from this as something like pertubations.
- A new integration driver G4BFieldIntegrationDriver, introduced in Geant4 10.6 samples the value of the magnetic field at the start of each step and using the estimated track curvature determines whether the current step will traverse an angler smaller or larger than 2 \* π. For larger steps the hybrid-helical stepper G4HelixHeum is used, and for smaller steps the G4DormandPrince745 stepper is used. This driver is the default driver in Geant4 10.6, created by G4ChordFinder for magnetic fields, and when G4FieldManager 's CreateChordFinder method is called. Note that it is applicable only for charged particles in pure magnetic field.
- An older approach, usable before Geant4 10.6, is to use the G4HelixMixedStepper. This also combines a helix stepper for large steps with a Runge-Kutta stepper for small and intermediate step sizes. It does this by checking the value of the field at the start of every integration. As a result it is less efficient than the new method G4BFieldIntegrationDriver.

#### **Ensuring progress for particles**

To allow better progress for looping particles, the default behaviour was changed in Geant4 10.6, so that a track's parameters are changed within a Geant4 step after it has undertaken 100 integration substeps.

For the remainder of the current step the track 'tightness' parameter *delta chord* is relaxed, first by a factor of 2 at the hundredth step, and again by another factor of 2 after every 100 subsequent steps. The original value of *delta chord* is restored at the end of the current Geant4 step.

This will allow tracks which are in a tight spiral with a radius of curvature less than the user-defined *delta chord* to make substantial progress.

Note that this applies only to particles below the 'Important' energy threshold, which would be killed if their integration is not completed within a single Geant4 step.

#### **Status of this Document**

Guide for Application Developers using the GEANT4 toolkit.

- Rev 1.0: First Sphinx version implemented for GEANT4 Release 10.4, 8th Dec 2017
- Rev 2.0: Updates and fixes in documentatio for GEANT4 Release 10.4, 15th May 2018
- Rev 3.0: GEANT4 Release 10.5, 11th December 2018
- Rev 3.1: GEANT4 Updates and fixes especially to search functionality, 5th March 2019
- Rev 4.0: GEANT4 Release 10.6, 6th December 2019
- Rev 5.0: Geant4 Release 10.7, 4th December 2020
- Rev 6.0: GEANT4 Release 11.0, 10th December 2021

### **BIBLIOGRAPHY**

- [Booch1994] Grady Booch *Object-Oriented Analysis and Design with Applications*. The Benjamin/Cummings Publishing Co. Inc 1994 ISBN: 0-8053-5340-2
- [Ellis1990] Margaret Ellis and Bjarne Stroustrup *Annotated C++ Reference Manual (ARM)*. Addison-Wesley Publishing Co. 1990
- [Hecht1974] E. Hecht and A. Zajac Optics. Addison-Wesley Publishing Co. 1974 pp. 71-80 and pp. 244-246
- [Janecek2010] M. Janecek, W. W. Moses, IEEE Trans. Nucl. Sci. 57 (3) (2010) 964-970 http://ieeexplore.ieee.org/document/5485130/
- [Knoll1988] G.F. Knoll, T.F. Knoll and T.M. Henderson, Light Collection Scintillation Detector Composites for Neutron Detection, IEEE Trans. Nucl. Sci., 35 (1988) 872.
- [Levin1996] A. Levin and C. Moisan, A More Physical Approach to Model the Surface Treatment of Scintillation Counters and its Implementation into DETECT, TRIUMF Preprint TRI-PP-96-64, Oct. 1996 https://inis.iaea.org/collection/NCLCollectionStore/\_Public/29/030/29030591.pdf; https://doi.org/10.1109/NSSMIC.1996.591410
- [Plauger1995] P.J. Plauger The Draft Standard C++ Library. Prentice Hall, Englewood Cliffs 1995
- [RoncaliCherry2013] Roncali E & Cherry S 2013 Simulation of light transport in scintillators based on 3D characterization of crystal surfaces. (https://www.ncbi.nlm.nih.gov/pubmed/23475145) Phys. Med. Biol., Volume 58(7), p. 2185–2198.
- [Roncali2017] Roncali et al. 2017 *An integrated model of scintillator-reflector properties for advanced simulations of optical transport.* (https://www.ncbi.nlm.nih.gov/pubmed/28398905) Phys. Med. Biol., Volume 62(12), p. 4811-4830.
- [Stockhoff2017] Stockhoff et al. 2017 Advanced optical simulation of scintillation detectors in GATE V8.0: first implementation of a reflectance model based on measured data. (https://www.ncbi.nlm.nih.gov/pubmed/28452339) Phys. Med. Biol., Volume 62(12), L1-L8.