# **GalSim Quick Reference**

# **Contents**

1	Ove	rview	3	
2	GSObjects			
	2.1	GSObject classes and when to use them	4	
	2.2	Units	6	
	2.3	Important GSObject methods	6	
3	Chr	omaticity	9	
	3.1	Bandpasses	10	
	3.2	SEDs	11	
	3.3	ChromaticObjects	12	
4	Ran	dom deviates	13	
	4.1	Random deviate classes and when to use them	13	
	4.2	Important random deviate methods	14	
	4.3	Noise models	15	
5	Images			
	5.1	Image classes and when to use them	15	
	5.2	Important Image methods and operations	16	

6	Miso	cellaneous classes and functions	17
	6.1	Angles	18
	6.2	Bounds and Positions	18
	6.3	Shear and Ellipse transformations	18
	6.4	Lensing shear fields	19
	6.5	Additional FITS input/output tools	20

#### 1. Overview

The GalSim package provides a number of Python classes and methods for simulating astronomical images. We assume GalSim is installed; see the *GalSim Wiki* or the file INSTALL.md in the base directory /your/path/to/GalSim/ for instructions. The package is imported into Python with

```
>>> import galsim
```

and the typical work flow, as demonstrated in the example scripts in the examples/ directory (all paths given relative to /your/path/to/GalSim/ from now on), will normally be something like the following:

- Construct a representation of your desired astronomical object as an instance of either the GSObject or ChromaticObject class, which represent (possibly wavelength-dependent) surface brightness profiles (of galaxies or PSFs). Multiple components can be combined using the special Add and Convolve functions see Section 2.
- Chromatic objects will generally also require the construction of spectral energy distribution SED class instances and Bandpass class instances.
- Apply transformations such as shears, shifts or magnification using the methods of the GSObject or ChromaticObject see Sections 2.3 & 3.
- Draw the object into a GalSim Image, representing a postage stamp image of your astronomical object. This can be done using the obj.draw(...) or obj.drawShoot(...) methods carried by all GSObjects or the obj.draw method carried by ChromaticObjects for rendering images see Sections 2.3 & 5.
- Add noise to the Image using one of the GalSim random deviate classes see Section 4.
- Add the postage stamp Image to a subsection of a larger Image instance see Section 5.2 or to a Python list containing multiple Image instances.
- Save the Image(s) to file in FITS (Flexible Image Transport System) format see Sections 5.2 & 6.5.

There are many examples of this workflow in the directory examples/, showing most of the GalSim library in action, in the scripts named demol.py-demol2.py. This document provides a brief, reference description of the GalSim classes and methods which can be used in these workflows.

Where possible in the following Sections this document has been hyperlinked to the online GalSim documentation generated by *doxygen*, where a more detailed description can be found. We also suggest accessing the full docstrings for *all* the classes and functions described below in Python itself, e.g. by typing

```
>>> help(galsim.<ObjectName>)
```

within the Python interpreter. If using the *ipython* package, which is recommended, instead simply type

```
In [1]: galsim.<ObjectName>?
```

and be sure to use the excellent tab-completion feature to explore the many methods and attributes of the GalSim classes.

## 2. GSObjects

## 2.1. GSObject classes and when to use them

There are currently 13 types of GSObjects that represent various types of surface brightness profiles. The first 11 listed are 'simple' GSObjects that can be initialized by providing values for their required and optional parameters. The last two are 'compound' classes used to represent combinations of GSObjects.

They are summarized in the following hyperlinked list, in which we also give the required parameters for initializing each class in parentheses after the class name. For more information and initialization details for each GSObject, the Python docstring for each class is available within the Python interpreter, for example for Sersic the documentation would be accessed using

```
>>> help(galsim.Sersic)
```

Alternatively follow the hyperlinks on the class names listed below to view the documentation based on the Python docstrings.

We now list the GSObjects. Where multiple options for specifying the object <code>size</code> exist we list these in the object description. We also show some of the non-optional parameters available for use (e.g. total flux) along with default values:

- o galsim.Gaussian(size, flux=1.)
  - a 2D Gaussian light profile. Requires one of the following size parameters to be set as a keyword argument: sigma; fwhm; half\_light\_radius.
- o galsim.Moffat(beta, size, flux=1.)
  - a Moffat profile with slope parameter beta, used to approximate ground-based telescope PSFs. Requires one of the following <code>size</code> parameters to be set as a keyword argument: <code>scale\_radius</code>; fwhm; half\_light\_radius. For information about other optional parameters, see the documentation for this object.
- galsim.AtmosphericPSF (size, flux=1.)
   currently simply an image-based implementation of a Kolmogorov PSF (see below), and therefore deprecated, but expected to evolve to store a stochastically modeled atmospheric PSF in the near

future. Requires one of the following size parameters to be set as a keyword argument: fwhm; lam\_over\_r0. For information about other optional parameters, see the documentation for this object.

- o galsim.Airy(lam\_over\_diam, obscuration=0., flux=1.) an Airy PSF for ideal diffraction through a circular aperture, parametrized by the wavelength-aperture diameter ratio lam\_over\_diam, with optional obscuration.
- o galsim.Kolmogorov(size, flux=1.) the Kolmogorov PSF for long-exposure images through a turbulent atmosphere. Requires one of the following size parameters to be set as a keyword argument: lam\_over\_r0; fwhm; half\_light\_radius.
- o galsim.OpticalPSF (lam\_over\_diam, flux=1.)
  a simple model for non-ideal (aberrated) propagation through circular/square apertures, parametrized
  by the wavelength-aperture dimension ratio lam\_over\_diam, with optional obscuration. For
  information about other optional parameters, see the documentation for this object.
- galsim.InterpolatedImage(image, ...)
   a class representing in principle arbitrary surface brightness profiles for which we have an Image representation. For information about other optional parameters, see the documentation for this object.
- galsim.Pixel(scale, flux=1.)
   used for integrating light onto square pixels.
- galsim.Box(width, height, flux=1.)
   an arbitrary rectangular box profile.
- o galsim.Sersic(n, half\_light\_radius, flux=1.)
  the Sérsic family of galaxy light profiles, parametrized by an index n and half\_light\_radius.
- o galsim.Exponential(size, flux=1.) the Exponential galaxy disc profile, a Sérsic with index n=1. Requires one of the following size parameters to be set as a keyword argument: scale\_radius; half\_light\_radius.
- o galsim.DeVaucouleurs (half\_light\_radius, flux=1.) the De Vaucouleurs galaxy bulge profile, a Sérsic with index n=4 and input half\_light\_radius.
- o galsim.RealGalaxy(real\_galaxy\_catalog, ...) models galaxies using real data, including a correction for the original PSF. Requires the download of external data, stored and input as the real\_galaxy\_catalog parameter (an instance of the RealGalaxyCatalog class), for full functionality.

An example catalog of 100 real galaxies is in the repository itself; a set of  $\sim$ 26 000 real galaxy images, with original PSFs, can be downloaded from the *RealGalaxy Data Download Page* on the

#### GalSim Wiki:

https://github.com/GalSim-developers/GalSim/wiki/RealGalaxy%20Data%20Download%20Page. For information about other optional parameters, see the documentation for this object.

```
    galsim.Sum([list of objects])
    a compound object representing the sum of multiple GSObjects.
```

```
o galsim.Convolution([list of objects]) a compound object representing the convolution of multiple GSObjects.
```

Note that the last two objects, Sum and Convolution, are usually created by invoking the galsim. Add and galsim. Convolve functions. These functions will automatically create ChromaticSum and ChromaticConvolution objects instead if any of their arguments are ChromaticObjects instead of GSObects (see Section 3).

Also note that all of the GSObjects except for RealGalaxy, Add, and Convolve require the specification of one radius size parameter.

#### **2.2.** Units

The choice of units for the size parameters is up to the user, but it must be kept consistent between all GSObjects. These units must also adopted when specifying the Image pixel scale, whether this is set via the GSObject instance methods obj.draw(...) and obj.drawShoot(...) (see Section 2.3), or when setting the scale of an Image using image.scale = scale (see Section 5).

As an example, consider the lam\_over\_diam parameter, which provides an angular scale for the Airy via the ratio  $\lambda/D$  for light at wavelength  $\lambda$  passing through a telescope of diameter D. Putting both  $\lambda$  and D in metres and taking the ratio gives lam\_over\_diam in radians, but this is not a commonly used angular scale when describing astronomical objects such as galaxies and stellar PSFs, nor is it often used for image pixel scales. If wishing to use arcsec, which is more common in both cases, the user should multiply the result in radians by the conversion factor  $648000/\pi$ . In principle, however, any consistent system of units could be used.

#### 2.3. Important GSObject methods

A number of methods are shared by all the GSObjects of Section 2, and are also to be found in galsim/base.py within the definition of the GSObject base class. In what follows, we assume that a GSObject labelled obj has been instantiated using one of the calls described in the documentation linked above. For example,

```
>>> obj = galsim.Sersic(n=3.5, half_light_radius=1.743).
```

One important fact about GSObjects is that all of the methods which change the properties of the astronomical object represented by the instance (e.g., setFlux(), applyShear() etc.) also make fundamental changes to the instance itself. In most cases this will mean that special methods available to individual classes described in Section 2.1, such as getFWHM() for the Moffat, will be unavailable.

Once again, for more information regarding each galsim. GSObject method, the Python docstring is available

```
>>> help(obj.<methodName>)
```

zero):

within the Python interpreter. Alternatively follow the hyperlinks on the class names above to view the documentation based on the Python docstrings.

Some of the most important and commonly-used methods for such an instance are:

```
o obj.copy()
 return a copy of the GSObject.
o obj.centroid()
  return the (x, y) centroid of the GSObject as a PositionD (see Section 6.2).
o obj.qetFlux()
  get the flux of the GSObject.
o obj.scaleFlux(flux_ratio)
  multiply the flux of the GSObject by flux_ratio.
o obj.setFlux(flux)
  set the flux of the GSObject to flux.
o obj.applyTransformation(ellipse)
  apply an Ellipse transformation represented by ellipse to the GSObject (see Ellipse; Sec-
  tion 6.3).
o obj.applyDilation(scale)
  change of the linear size of the GSObject by a factor scale, conserving flux.
o obj.applyMagnification(scale)
  dilate linear size by scale and multiply total flux by scale2, conserving surface brightness.
o obj.applyShear(...)
  apply a shear to the GSObject, handling a number of different input conventions (see also Shear;
  Section 6.3). Commonly-used input conventions (supplied as keyword arguments, default values
```

- obj.applyShear (g1=g1, g2=g2) apply the first (g1) and second (g2) component of a shear defined so that |g| = (a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.
- obj.applyShear (e1=e1, e2=e2) apply the first (e1) and second (e2) component of a shear defined so that  $|e|=(a^2-b^2)/(a^2+b^2)$  where a and b are the semi-major and semi-minor axes of an ellipse.
- obj.applyShear (g=g, beta=beta) apply magnitude (g) and polar angle (beta) of a shear defined using the |g| definition above.
- obj.applyShear (e=e, beta=beta) apply magnitude (e) and polar angle (beta) of a shear defined using the |e| definition above.
- o obj.applyRotation(theta) apply a rotation of theta (positive direction anti-clockwise) to the GSObject, where theta is an Angle instance (see Section 6.1).
- o obj.applyShift (dx, dy) apply a (dx, dy) position shift to the GSObject centroid.

draw and return an Image (see Section 5) of the GSObject using Discrete Fourier Transforms and interpolation to perform the image rendering. Note that if a profile is not convolved with a pixel response before drawing, then draw samples the surface brightness distribution without integrating within pixels, so the sum of pixel values might not equal the GSObject flux. Some information about important optional parameters (see the linked / Python docstrings for more detail), along with default values:

- image (default = None)
   if supplied, the drawing will be done into a user-supplied Image instance image. If not supplied (i.e. image = None), an automatically-sized Image instance will be returned.
- scale (default = None) the optional image pixel scale, which if provided should use the same units as used for the GSObject size parameters.
- wcs (default = None)
  the wcs may optionally be provided in lieu of a simple pixel scale, in which case this would specify the conversion between image coordinates and world (aka sky) coordinates. The GSObject is taken to be defined in world coordinates and this function tells GalSim how to convert to image coordinates when it draws the profile. If neither scale nor wcs are provided here, then GalSim will use the wcs attribute of the image if available. Otherwise, it will use the Nyquist scale given the maximum modeled frequency in the GSObject.

add\_to\_image (default = False)
 Whether to add flux to a (must be supplied) image rather than clear out anything in the image before drawing.

The draw method has a number of additional optional parameters. Please see the linked / Python docstrings for more details.

draw and return an Image (see Section 5) of the GSObject by shooting a finite number of photons. The resulting rendering therefore contains stochastic noise, but uses few approximations. Note however, that you cannot drawShoot with a RealGalaxy instance. drawShoot shares all the parameters listed for draw, above, but the drawShoot method also has a number of additional optional parameters. Important examples worthy of mention are:

- n\_photons (default = 0)
   If provided, the number of photons to use. If not provided, use as many photons as necessary to end up with an image with the correct poisson shot noise for the object's flux.
- max\_extra\_noise (default = 0.)
  If provided, the allowed extra noise in each pixel. This is only relevant if n\_photons = 0, so the number of photons is being automatically calculated. In that case, if the image noise is dominated by the sky background, you can get away with using fewer shot photons than the full n\_photons = flux. Essentially each shot photon can have a flux > 1, which increases the noise in each pixel. The max\_extra\_noise parameter specifies how much extra noise per pixel is allowed because of this approximation.
- poisson\_flux (default = True)
   Whether to allow total object flux scaling to vary according to Poisson statistics for n\_photons samples.

As before, you are strongly encouraged to see the linked / Python docstrings for more details.

Finally, you may see by exploring the docstrings that many of the GSObject instances also have their own specialized methods, often for retrieving parameter values. Examples are obj.getSigma() for the Gaussian, or obj.getHalfLightRadius() for many of the GSObjects.

#### 3. Chromaticity

Wavelength-dependent surface brightness profiles are represented as galsim.ChromaticObject instances in GalSim. These objects generally require an galsim.SED to be created, and always require a galsim.Bandpass object in order to draw. Thus we will go over SEDs and Bandpasses first.

## 3.1. Bandpasses

The galsim.Bandpass class represents a spectral throughput function, which could be an entire imaging system throughput response function (reflection off of mirrors, transmission through filters, lenses and the atmosphere, quantum efficiency of detectors), or individual pieces thereof. Bandpasses, together with spectral energy distributions (SEDs; below) are necessary to compute the relative contribution of each wavelength of a ChromaticObject to a drawn image.

Bandpass instances may be initialized in several ways:

- galsim.Bandpass (filename)
   where filename points to a text file with two columns, the first for wavelength and the second for dimensionless throughput.
- o galsim.Bandpass (function, red\_limit=red\_limit, blue\_limit=blue\_limit) where function is a python function that accepts wavelength and returns dimensionless throughput. The keywords red\_limit and blue\_limit are required in this case to specify the integration limits of the bandpass.

By default, the units for wavelength in the above functions/file are assumed to be nanometers. If the keyword argument wave\_type = 'Ang' is supplied, then the wavelengths will instead be interpretted as Angstroms.

For Bandpass instances initialized from a file, the following two methods can be used to reduce the number of samples used for integrations (and hence reduce the time it takes to draw a ChromaticObject).

- bandpass.truncate(blue\_limit=blue\_limit, red\_limit=red\_limit, relative\_throughput=relative\_throughput)

  Clip the wavelength range to be between blue\_limit and red\_limit. Additionally clip any leading or trailing wavelengths for which the throughput is less than the fraction relative\_throughput of the peak throughput.
- bandpass.thin(rel\_err)

  Remove samples defining the bandpass while retaining the accuracy of the integral over the bandpass to the stated relative error rel\_err.

Finally, note that Bandpass instances may be multiplied together and are callable, returning dimensionless throughput as a function of wavelength in nanometers.

## **3.2. SEDs**

Spectral energy distributions may be constructed in several ways, similarly to bandpasses:

- galsim.SED (filename)
   where filename points to a text file with two columns, the first for wavelength in nanometers and the second for flux density.
- galsim.SED (function)
   where function is a python function that accepts wavelength in nanometers and returns flux density.
- o galsim.SED(expression)
  where expression is a string that can be evaluated into a python function via
  eval('lambda wave : '+expression),
  e.g. expression = '0.8 + 0.2 \* (wave-800)'.

The units for wavelength in the above constructions can be set to Angstroms by supplying the keyword argument wave\_type = 'Ang'. The units for flux density in the above are assumed to be proportional to ergs/nm, but can be overridden to be proportional to ergs/Hz by setting flux\_type = 'fnu', or overridden to be proportional to photons/nm by setting flux\_type = 'fphotons'.

Important methods for SED objects include:

- SED.withFluxDensity(target\_flux\_density, base\_wavelength)
  Return a new SED with flux density (in units proportional to ergs/nm) at the reference wavelength base\_wavelength set to target\_flux\_density. Note that SED objects are immutable, so the original SED is unchanged.
- calculateFlux (bandpass)

  Calculate and return the flux transmitted through a bandpass in photons.
- withFlux(target\_flux, bandpass)

  Return a new SED for which the flux transmitted through the input bandpass is target\_flux.
- atRedshift (z)
   Return a new SED instance with wavelength shifted be at redshift z. Note that SED instances remember their redshifts (except when created as sums and differences of other SEDs), so applying this method a second twice with the same argument z is equivalent to applying it just once.

Finally, note that SED instances can be added together, multiplied by scalars or functions (of wavelength in nanometers), and are callable, returning flux density in photons/nm.

# 3.3. ChromaticObjects

Chromatic surface brightness profiles are generally constructed by modifying an existing GSObject. The simplest possible ChromaticObject can be formed by passing a GSObject to the ChromaticObject constructor:

```
>>> obj = galsim.Gaussian(fwhm=1.0)
>>> chromatic_obj = galsim.ChromaticObject(obj)
```

At this stage, chromatic\_obj essentially represents the same profile as obj, but now has access to ChromaticObject methods.

The simplest way to construct a non-trivial chromatic object is to multiply a GSObject by an SED. This creates a separable wavelength-dependent surface brightness profile:

ChromaticObject
$$(x, y, \lambda) = \text{GSObject}(x, y)\text{SED}(\lambda)$$
 (1)

```
>>> gal = galsim.Sersic(n=2.5, half_light_radius=1.1)
>>> SED = galsim.SED('wave**1.1') # Power-law spectrum.
>>> chromatic_gal = gal*SED
```

ChromaticObjects may be combined and transformed similarly to GSObjects, using the functions, methods and compound classes Add, Convolve, scaleFlux, applyExpansion, applyDilation, applyMagnification, applyShear, applyLensing, applyRotation, applyShift, and all the create\* methods as well.

The applyDilation, applyExpansion, and applyShift methods of ChromaticObjects can also accept as an argument a function of wavelength (in nanometers) that returns a wavelength-dependent dilation, expansion, or shift. These can be used to implement chromatic PSFs. For example, a diffraction limited PSF might look like:

```
>>> psf500 = galsim.Airy(lam_over_diam=2.0)
>>> chromatic_psf = ChromaticObject(psf500)
>>> chromatic_psf.applyDilation(lambda w:(w/500.0)**(1.0))
```

The draw method of a ChromaticObject is similar to the draw method of a GSObject, except that it requires a Bandpass object as its first argument.

```
>>> gband = galsim.Bandpass(lambda w:1.0, blue_limit=410, red_limit=550)
>>> pix = galsim.Pixel(0.2)
>>> final = galsim.Convolve(chromatic_gal, chromatic_psf, pix)
>>> image = final.draw(gband)
```

GalSim also comes with built-in support for ground-based PSFs affected by differential chromatic refraction and Kolmogorov chromatic seeing (FWHM  $\propto \lambda^{-0.2}$ ) through the following function:

```
o ChromaticAtmosphere (base_obj, base_wavelength, zenith_angle, position_angle=position_angle) where base_obj is the fiducial PSF at wavelength base_wavelength. Differential chromatic refraction is calculated for a telescope pointed at zenith_angle, where the zenith lies in the direction position_angle measured from "up" through "right".
```

## For example:

#### 4. Random deviates

#### 4.1. Random deviate classes and when to use them

Random deviates can be used to add a stochastic component to the modeling of astronomical images, such as drawing object parameters according to a given distribution or generating random numbers to be added to image pixel values to model noise.

We now give a short summary of the 9 random deviates currently implemented in GalSim. The optional parameter <code>seed</code> listed below is used to seed the pseudo-random number generator: it can either be omitted (the random deviate seed will be set using the current time), set to an integer seed, or used to pass another random deviate (the new instance will then use and update the same underlying generator as the input deviate). The deviates, with a description of their distributions, parametrization and default parameter values, are as follows:

```
    galsim.UniformDeviate(seed)
        uniform distribution in the interval [0,1).
    galsim.GaussianDeviate(seed, mean=0., sigma=1.)
        Gaussian distribution with mean and standard deviation sigma.
    galsim.BinomialDeviate(seed, N=1, p=0.5)
        Binomial distribution for N trials each of probability p.
```

```
o galsim.PoissonDeviate (seed, mean=1.)
Poisson distribution with a single mean rate.
o galsim.WeibullDeviate (seed, a=1., b=1.)
Weibull distribution family (includes Rayleigh and Exponential) with shape parameters a and b.
o galsim.GammaDeviate (seed, alpha=1., beta=1.)
Gamma distribution with parameters alpha and beta.
o galsim.Chi2Deviate (seed, n=1.)
χ² distribution with degrees-of-freedom parameter n.
o galsim.DistDeviate (seed, function, x.min, x.max)
Use an arbitrary function for P(x) from x.min.x.max.
```

It is possible to specify the random seed so as to get fully deterministic behavior of the noise when running a particular script. Unfortunately the random deviate classes are not yet fully integrated within the documentation, due to their being C++ with compiled Python wrappers. This means that the class names above and methods below are not yet hyperlinked. For more information, please refer to the full docstrings in galsim/random.py, or type

```
>>> help(galsim.<RandomDeviateName>)
```

within the Python interpreter.

## 4.2. Important random deviate methods

We now illustrate the most commonly-used methods of the random deviates, assuming that some random deviate instance dev has been instantiated, for example by

```
>>> dev = galsim.GaussianDeviate(sigma=3.9, mean=50.).
```

The most important and commonly-used method for such instances is:

```
o dev()
```

calling the deviate directly simply returns a single new random number drawn from the distribution represented by dev. As an example:

```
>>> dev = galsim.UniformDeviate(12345)
>>> dev()
0.9296160866506398
>>> dev()
0.8901547130662948
```

#### 4.3. Noise models

One common way to use the random deviates is as part of a noise model for adding noise to an image. These have their own separate hierarchy of classes

- galsim.GaussianNoise (dev, sigma=1.)
   Every pixel gets Gaussian noise with rms sigma, using the same random number generator as the supplied Deviate instance dev.
- galsim.PoissonNoise (dev, sky\_level=0.)
   Every pixel gets Poisson noise according to the flux in the image plus an option sky level, sky\_level, using the same random number generator as the supplied Deviate instance dev.
- galsim.DeviateNoise(dev)
   The noise value for every pixel is drawn from the given Deviate instance dev.
- o galsim.CCDNoise(dev, sky\_level=0., gain=1., read\_noise=0.)
  A combination of Poisson noise (with a gain value in electrons/ADU) and Gaussian read noise, using the same random number generator as the supplied Deviate instance dev.

To apply noise to an Image using these noise models, the command is simply:

 image.addNoise(noise)
 this adds stochastic noise, according to the noise model noise, to each element of the data array in the Image instance image.

#### 5. Images

## 5.1. Image classes and when to use them

The GalSim Image classes store array data, along with the bounds of the array, and a function that converts between image coordinates and world coordinates (also known as sky coordinates). The most common World Coordinate System (WCS) function that you will encounter is a simple scaling of the units from pixels to arcsec. This WCS can be specified simply by im.scale, as we have seen already. More complicated WCS functions would need to referenced via im.wcs. See the docstring for BaseWCS for more details.

Image instances can be operated upon to add stochastic noise simulating real astronomical images (see Section 4), and have methods for writing to FITS format output.

The most common way to initialize an image is with two integer parameters nx and ny, giving the image extent in the x and y dimensions, respectively. Example initialization is therefore:

```
o galsim. Image(nx, ny)
```

This would create an image with single precision (32 bit) floats for the data elements, which is usually the most appropriate type for astronomical images. However, you can specify other types for the data using a suffix letter after Image:

```
galsim.ImageS (nx, ny) for 16 bit integers.
galsim.ImageI (nx, ny) for 32 bit integers.
galsim.ImageF (nx, ny) for single precision (32 bit) floats.
galsim.ImageD (nx, ny) for double precision (64 bit) floats.
```

Other ways to construct an Image can be found in the docstrings.

To access the data as a NumPy array, simply use the image array attribute, where image is an instance of one of these Image classes. However, note that the individual elements in the array attribute are accessed as image array [y, x], matching the standard NumPy convention, while the Image class's own accessors are all (x, y) in ordering.

Unfortunately the Image classes are not yet fully integrated within the online documentation, due to their being in C++ with compiled Python wrappers. This means that the class names above and methods below are not hyperlinked. However, the full docstrings are available in galsim/image.py, so please refer there for more information, or type

```
>>> help(galsim.<ImageName>)
```

within the Python interpreter.

## 5.2. Important Image methods and operations

We now illustrate the most commonly-used methods of Image class instances. We will assume that some Image instance image has been instantiated, for example by

```
>>> image = galsim.ImageD(100, 100).
```

This Image instance is then ready to pass to a GSObject for drawing. The most important and commonly-used methods for such an instance are:

```
• image.bounds
get the bounding box of the data.
```

- image.wcs
   get the WCS function to convert between image coordinates and world coordinates.
- image.scale
   get or set the pixel scale scale for this image. The getter only works if the WCS is really just a pixel scale. The setter will make it a pixel scale.
- o image.addNoise(dev) this adds stochastic noise, distributed as represented by the random deviate instance dev, to each element of the data array in image. This is the method previously referenced in Section 4.
- o image.write(fits, ...) write the imageView to a FITS file or object as determined by the fits input parameter (see galsim/fits.py). In Section 6.5 we discuss how to write to multi-extension FITS files.

Image instances are also returned when accessing a sub-section of an existing Image. For example

```
>>> imsub = image.subImage(bounds)
```

where bounds is a Bounds I instance (see Section 6.2) assigns imsub as an view into the sub-region of image lying in the area represented by bounds. Equivalent syntax is also

```
>>> imsub = image[bounds]
```

It is also possible to change the values of a sub-region of an image this way, for example

```
>>> image[imsub.bounds] += imsub
```

if wishing to add the contents of imsub to the area lying within its bounds in image. Note that here we have made use of the image. bounds attribute carried by all of the Image classes.

#### 6. Miscellaneous classes and functions

A summary of miscellaneous GalSim library objects, subcategorized into broad themes. As ever, docstrings for *all* the classes and functions below can be accessed via

```
>>> help(galsim.<Name>)
```

within the Python interpreter.

# 6.1. Angles

- o galsim. Angle (value, angle\_unit) class to represent angles (with multiple unit types), which can be initialized by multiplying a numerical value and an AngleUnit instance angle\_unit (see below, and galsim/angle.py).
- o galsim.AngleUnit

There are five built-in AngleUnits which are always available for use:

- galsim.radians
- galsim.degrees
- galsim.hours
- galsim.arcmin
- galsim.arcsec

Please see the Python docstrings for information about defining your own AngleUnits.

#### **6.2.** Bounds and Positions

```
o galsim.BoundsI(...)
galsim.BoundsD(...)
```

classes to represent image boundaries as the vertices of a rectangle (see galsim/bounds.py).

```
o galsim.PositionI(x, y)
galsim.PositionD(x, y)
```

classes to represent 2D positions on the x-y plane (see galsim/position.py), e.g., for describing object centroid positions.

For both bounds and positions, the I and D refer to integer and double-precision floating point representations.

# 6.3. Shear and Ellipse transformations

o galsim.Shear(...)

class to represent shears in a variety of ways. This class can be initialized using a variety of different parameter conventions (see galsim/shear.py). Commonly-used examples (supplied as keyword arguments, default values zero):

- galsim. Shear (g1=g1, g2=g2) set via the first (g1) and second (g2) component of a shear defined so that |g| = (a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.

- galsim. Shear (e1=e1, e2=e2) set via the first (e1) and second (e2) component of a shear defined so that  $|e|=(a^2-b^2)/(a^2+b^2)$  where a and b are the semi-major and semi-minor axes of an ellipse.
- galsim. Shear (g=g, beta=beta) set via magnitude (g) and polar angle (beta) of a shear defined according to the |g| definition above.
- galsim. Shear (e=e, beta=beta) set via magnitude (e) and polar angle (beta) of a shear defined according to the |e| definition above.
- o galsim.Ellipse(...)
  class to represent ellipses and thus ellipse-type transformations, specifically shears, shifts, and dilations. The class can be initialized using a variety of different parameter conventions (see, e.g., galsim/ellipse.py), including being initialized with a Shear instance.

## 6.4. Lensing shear fields

GalSim has functionality to simulate scientifically-motivated lensing shear fields. The code and documentation for the "lensing engine" is in galsim/lensing.py. The two relevant classes for users are:

- o galsim.PowerSpectrum(...) represents a flat-sky shear power spectrum P(k), where the E and B-mode power spectra can be separately specified as E\_power\_function and B\_power\_function. The getShear(...) method is used to generate a random realization of a shear field from a given PowerSpectrum object, and there are methods to get convergence or magnification as well.
- o galsim.NFWHalo(...)
  represents a matter density profile corresponding to a projected, circularly-symmetric NFW profile such as might be used to simulate lensing by a galaxy cluster. This class has two methods of interest for users, getShear() and getConvergence(), which can be used to get the shears and convergences at any (non-gridded) image-plane position.

These classes have additional requirements on the units used to specify positions; see the documentation for these classes for more details.

The GalSim repository also contains a module with a PowerSpectrumEstimator class that can be used to estimate shear power spectra from gridded shear values even if GalSim is not installed: galsim/pse.py (see documentation in that file for more information).

# 6.5. Additional FITS input/output tools

- o image = galsim.fits.read(fits)
  returns an Image instance image from a FITS representation fits. If fits is a string it is interpreted as a filename, otherwise it is interpreted as a PyFITS representation of HDU data (see galsim/fits.py). If the FITS file has a WCS defined in the header, then GalSim will attempt to read that WCS and store it as image.wcs.
- o image\_list = galsim.fits.readMulti(fits)
  returns a Python list of Image instances (image\_list) from a Multi-Extension FITS file or
  PyFITS HDU object, specified by the fits input parameter (see galsim/fits.py).
- galsim.fits.writeMulti(image\_list, fits, ...)
   write multiple Image instances stored in a Python list (image\_list) to a Multi-Extension FITS file or PyFITS HDU object, specified by the fits input parameter (see galsim/fits.py).
- galsim.fits.writeCube(image\_list, fits, ...)
   write multiple Image instances stored in a Python list (image\_list) to a three-dimensional FITS datacube or PyFITS HDU object, specified by the fits input parameter (see galsim/fits.py).

The routines for reading and writing FITS images are able to handle compressed inputs / outputs via keywords.