GalSim Quick Reference

Contents

1	Ove	rview	2
2	GSObjects		3
	2.1	GSObject classes and when to use them	3
	2.2	Units	4
	2.3	Important GSObject methods	5
3	Random deviates		7
	3.1	Random deviate classes and when to use them	7
	3.2	Important random deviate methods	8
4	Images		
	4.1	Image classes and when to use them	8
	4.2	Important Image methods and operations	9
5	Miscellaneous classes and functions		10
	5.1	Angles	11
	5.2	Bounds and Positions	11
	5.3	Shear and Ellipse transformations	11
	5.4	Multiple image FITS output tools	12

1. Overview

The GalSim package provides a number of Python classes and methods for simulating astronomical images. We assuming GalSim is installed; see the *GalSim Wiki* or the file INSTALL.md in the base directory /your/path/to/GalSim/ for instructions. The package is imported into Python with

```
>>> import galsim
```

and the typical work flow, as demonstrated in the example scripts in the examples/ directory (all paths given relative to /your/path/to/GalSim/ from now on), will normally be something like the following:

- Construct a representation of your desired astronomical object as an instance of the GSObject class, which represent surface brightness profiles (of galaxies or PSFs). Multiple components can be combined using the special Add and Convolve classes see Section 2.
- Apply transformations such as shears, shifts or magnification using the methods of the GSObject
 — see Section 2.3.
- Draw the object into a GalSim Image, representing a postage stamp image of your astronomical object. This can be done using the obj.draw(...) or obj.drawShoot(...) methods carried by all GSObjects for rendering images see Sections 2.3 & 4.
- Add noise to the Image using one of the GalSim random deviate classes see Section 3.
- Add the postage stamp Image to a subsection of a larger Image instance see Section 4.2 or to a Python list containing multiple Image instances.
- Save the Image(s) to file in FITS (Flexible Image Transport System) format see Sections 4.2 & 5.4.

There are many examples of this workflow in the directory examples/, showing most of the GalSim library in action, in the scripts named demol.py-demo8.py. This document provides a brief, reference description of the GalSim classes and methods which can be used in these workflows.

Where possible in the following Sections this document has been hyperlinked to the online GalSim documentation generated by *doxygen* where a more detailed description can be found. We also suggest accessing the full docstrings for the *all* the classes and functions described below in Python itself, e.g. by typing

```
>>> help(galsim.<ObjectName>)
```

within the Python interpreter. If using the ipython package, which is recommended, instead simply type

```
In [1]: galsim.<ObjectName>?
```

and be sure to use the excellent tab-completion feature to explore the many methods and attributes of the GalSim classes.

2. GSObjects

2.1. GSObject classes and when to use them

There are currently 13 types of GSObjects that represent various types of surface brightness profiles. The first 11 listed are 'simple' GSObjects that can be initialized by providing values for their required and optional parameters. The last two are 'compound' classes used to represent combinations of GSObjects.

They are summarized in the following hyperlinked list, in which we also give the required parameters for initializing each class in parentheses after the class name. For more information and initialization details for each GSObject, the Python docstring for each class is available within the python interpreter, for example for Sersic the documentation would be accessed using

```
>>> help(galsim.Sersic)
```

Alternatively follow the hyperlinks on the class names listed below to view the documentation based on the Python docstrings.

In the order in which the classes appear in galsim/base.py, with all non-optional parameters listed:

- o galsim.Gaussian(...)

 a 2D Gaussian light profile. Requires one of the following size parameters to be set: sigma; FWHM;

 half_light_radius.
- o galsim. Moffat (beta, ...)

 a Moffat profile with slope parameter beta, used to approximate ground-based telescope PSFs. Requires one of the following size parameters to be set: scale_radius; FWHM; half_light_radius.
- o galsim. Atmospheric PSF (...) currently simply an image-based implementation of a Kolmogorov PSF (see below), and therefore deprecated, but expected to evolve to store a stochastically modelled atmospheric PSF in the near future. Requires one of the following size parameters to be set: FWHM; lam_over_r0.
- o galsim.Airy (lam_over_diam, ...)

 an Airy PSF for ideal diffraction through a circular aperture, parametrized by the wavelength-aperture diameter ratio lam_over_diam, with optional obscuration.
- o galsim.Kolmogorov (...) the Kolmogorov PSF for long-exposure images through a turbulent atmosphere.
- o galsim.OpticalPSF (lam_over_diam, ...)
 a simple model for non-ideal (aberrated) propagation through circular or square apertures, parametrized
 by the wavelength-aperture dimension ratio lam_over_diam, with optional obscuration.

- \circ galsim.Pixel(xw, ...) used for integrating light onto square or rectangular pixels, requires at least one side dimension xw.
- o galsim.Sersic(n, half_light_radius, ...)

 the Sérsic family of galaxy light profiles, parametrized by an index n and size half_light_radius.
- o galsim. Exponential (...) the Exponential galaxy disc profile, a Sérsic with index n=1. Requires one of the following size parameters to be set: scale_radius; half_light_radius.
- o galsim.DeVaucouleurs (half_light_radius, flux=1.) the De Vaucouleurs galaxy bulge profile, a Sérsic with index n=4. Requires the size parameter half_light_radius to be set.
- o galsim.RealGalaxy (real_galaxy_catalog, ...)
 models galaxies using real data, including a correction for the original PSF. Requires the download of
 external data, stored and input in real_galaxy_catalog(an instance of the RealGalaxyCatalog
 class), for full functionality. A set of ~26 000 real galaxy images, with original PSFs, can be downloaded from the following Public Dropbox folder:

https://www.dropbox.com/sh/ns2yh4q00trqs5r/JypUX8qwLw.

- galsim.Add(...)

 a compound object representing the sum of multiple GSObjects.
- galsim.Convolve(...)
 a compound object representing the convolution of multiple GSObjects.

Note that all of the GSObjects except for RealGalaxy, Add, and Convolve *require* the specification of some radius parameter, where the choice of possible radii to specify (e.g., half-light radius, FWHM, etc.) is given in the documentation for the class.

2.2. Units

The choice of units for the size parameters is up to the user, but it must be kept consistent between all GSObjects. These units must also adopted when specifying the Image sample rate dx, whether this is set via the GSObject instance methods obj.draw(...) and obj.drawShoot(...) (see Section 2.3), or when setting the scale of an Image with a given dx using the image.setScale(dx) method (see Section 4).

As an example, consider the lam_over_diam parameter which provides an angular scale for the Airy via the ratio λ/D for light at wavelength λ passing through a telescope of diameter D. Putting both λ and D in metres and taking the ratio gives lam_over_diam in radians, but this is not a commonly used angular

scale when describing astronomical objects such as galaxies and stellar PSFs, nor is it often used for image pixel scales. If wishing to use arcsec, which is more common in both cases, the user should multiply the result in radians by the conversion factor $648000/\pi$. In principle, however, any consistent system of units could be used.

2.3. Important GSObject methods

A number of methods are shared by all the GSObjects of Section 2, and are also to be found in galsim/base.py within the definition of the GSObject base class. In what follows, we assume that a GSObject labelled obj has been instantiated using one of the calls described in the documentation linked above. For example,

```
>>> obj = galsim.Sersic(n=3.5, half_light_radius=1.743).
```

One important fact about GSObjects is that all of the methods which change the properties of the astronomical object represented by the instance (e.g., setFlux(), applyShear() etc.) also make fundamental changes to the instance itself. In most cases this will mean that special methods available to individual classes described in Section 2.1, such as getFWHM() for the Moffat, will be unavailable.

Some of the most important and commonly-used methods for such an instance are:

```
obj.copy()
return a copy of the GSObject.
obj.centroid()
return the (x,y) centroid of the GSObject as a PositionD(see Section 5.2).
obj.getFlux()
get the flux of the GSObject.
obj.scaleFlux(flux_ratio)
multiply the flux of the GSObject by flux_ratio.
obj.setFlux(flux)
set the flux of the GSObject to flux.
obj.applyTransformation(ellipse)
apply an Ellipse transformation represented by ellipse to the GSObject (see Ellipse;
Section 5.3).
obj.applyDilation(scale)
change of the linear size of the GSObject by a factor scale, conserving flux.
```

- o obj.applyMagnification(scale) dilate linear size by scale and multiply total flux by scale², conserving surface brightness.
- o obj.applyShear(...)

 apply a shear to the GSObject, handling a number of different input conventions (see also Shear;

 Section 5.3). Commonly-used input conventions:
 - obj.applyShear (g1=g1, g2=g2) apply the first (g1) and second (g2) component of a shear defined so that |g| = (a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.
 - obj.applyShear (e1=e1, e2=e2) apply the first (e1) and second (e2) component of a shear defined so that $|e| = (a^2 b^2)/(a^2 + b^2)$ where a and b are the semi-major and semi-minor axes of an ellipse.
 - obj.applyShear(g=g, beta=beta) apply magnitude (g) and polar angle (beta) of a shear defined so that |g|=(a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.
 - obj.applyShear (e=e, beta=beta) apply magnitude (e) and polar angle (beta) of a shear defined so that $|e|=(a^2-b^2)/(a^2+b^2)$ where a and b are the semi-major and semi-minor axes of an ellipse.
- o obj.applyRotation (theta) apply a rotation of theta (positive direction anti-clockwise) to the GSObject, where theta is an Angle instance (see Section 5.1).
- o obj.applyShift(dx, dy) apply a(dx, dy) position shift to the GSObject centroid.
- o obj.draw(..., dx=1) draw an image of the GSObject using Discrete Fourier Transforms and interpolation to perform the image rendering. The optional image sample scale dx (default dx = 1) should use the same units as used for the GSObject size parameters.
- o obj.drawShoot (image, ..., dx=1)

 draw an image of the GSObject by shooting a finite number of photons into a user-supplied Image instance, image, which unlike for draw() is a required input. The resulting rendering therefore contains stochastic noise, but uses few approximations. The optional image sample scale dx (default dx = 1) should use the same units as used for the GSObject size parameters.

Once again, for more information regarding each galsim. GSObject method, the Python docstring is available

```
>>> help(obj.<methodName>)
```

within the Python interpreter. Alternatively follow the hyperlinks on the class names above to view the documentation based on the Python docstrings. You will see that many of the GSObject instances also have their own specialized methods, often for retrieving parameter values. Examples are obj.getSigma() for the Gaussian, or obj.getHalfLightRadius() for many of the GSObjects.

3. Random deviates

3.1. Random deviate classes and when to use them

Random deviates will be used when wishing to add a stochastic component to the modelling of astronomical images, such as drawing object parameters according to a given distribution or generating random numbers to be added to image pixel values to model noise.

A short summary of the 8 random deviates currently implemented in GalSim, with a short description of their distributions, parametrization and default parameter values:

```
o galsim.UniformDeviate(...)
  uniform distribution in the interval [0, 1).
o galsim.GaussianDeviate(..., mean=0., sigma=1.)
  Gaussian distribution with mean and standard deviation sigma.
o galsim.BinomialDeviate(..., N=1, p=0.5)
  Binomial distribution for N trials each of probability p.
o galsim.PoissonDeviate(..., mean=1.)
  Poisson distribution with a single mean rate.
o galsim.CCDNoise(..., gain=1., read_noise=0.)
  a basic detector noise model, parametrized by gain and read_noise.
o galsim.WeibullDeviate(..., a=1., b=1.)
  Weibull distribution family (includes Rayleigh and Exponential) with shape parameters a and b.
o galsim.GammaDeviate(..., alpha=1., beta=1.)
  Gamma distribution with parameters alpha and beta.
o galsim.Chi2Deviate(..., n=1.)
  \chi^2 distribution with degrees-of-freedom parameter n.
```

It is possible to specify the random seed so as to get fully deterministic behavior of the noise when running a particular script. Unfortunately the random deviate classes are not yet fully integrated within the documentation, due to their being C++ with compiled Python wrappers. This means that the class names above and

methods below are not yet hyperlinked. However, the full docstrings are available in galsim/random.py, so please refer there for more information, or type

```
>>> help(galsim.<RandomDeviateName>)
```

within the Python interpreter.

3.2. Important random deviate methods

We now illustrate the most commonly-used methods of the random deviates, assuming that some random deviate instance dev has been instantiated, for example by

```
>>> dev = galsim.GaussianDeviate(sigma=3.9, mean=50.).
```

The two most important and commonly-used methods for such an instance are:

- dev.applyTo(image)
 adds a random number, distributed according to the distribution represented by dev, to each element in a supplied Image instance image (see Section 4).
- dev()
 calling the deviate directly simply returns a single new random number drawn from the distribution represented by dev. As an example:

```
>>> dev = galsim.UniformDeviate()
>>> dev()
0.35068059829063714
>>> dev()
0.56841182382777333
```

4. Images

4.1. Image classes and when to use them

The GalSim Image classes store array data, along with a figure for the pixel separation in physical units and image bounds information (origin, extent). The ImageView provides a mutable view into Image instance data (although not all Image methods are available), and ConstImageView an immutable view into Image instance data.

If creating these objects directly you will mostly only need to use Image instances. The ImageView classes are most commonly encountered as the output of the GSObject instance methods obj.draw(...)

and obj.drawShoot (...). Both Image and ImageView instances can be operated on to add stochastic noise simulating real astronomical images (see Section 3), and have methods for writing to FITS format output.

There are several types of GalSim Image, one for each of four supported array data types:

```
o galsim.ImageS(...); galsim.ImageViewS(...); galsim.ConstImageViewS(...) for short integers (typically 16 bit).
```

```
    galsim.ImageI(...);galsim.ImageViewI(...);galsim.ConstImageViewI(...)
    for integers (typically 32 bit).
```

```
o galsim.ImageF(...); galsim.ImageViewF(...); galsim.ConstImageViewF(...) for single precision (typically 32 bit) floats.
```

```
o galsim.ImageD(...);galsim.ImageViewD(...);galsim.ConstImageViewD(...) for double precision (typically 64 bit) floats.
```

To access the data as a NumPy array, simply use the img.array attribute, where img is an instance of one of these Image classes. However, note that the individual elements in the array attribute are accessed as img.array[y,x], matching the standard NumPy convention, while the Image class's own accessors are all (x,y) in ordering.

Unfortunately the Image classes are not yet fully integrated within the online documentation, due to their being in C++ with compiled Python wrappers. This means that the class names above and methods below are not hyperlinked. However, the full docstrings are available in galsim/image.py, so please refer there for more information, or type

```
>>> help(galsim.<ImageName>)
```

within the Python interpreter.

4.2. Important Image methods and operations

We now illustrate the most commonly-used methods of Image class instances. We will assume that some Image instance img has been instantiated, for example by

```
img = galsim.ImageD(100, 100).
```

This Image instance is then ready to pass to a GSObject for drawing. The most important and commonly-used methods for such an instance are:

- o img.getScale()
 get the sample scale dx for this image.
- img.setScale(dx)
 set the sample scale for this image to dx note that this scale should use the same units adopted for the GSObject sizes.
- o img.addNoise(dev) this adds stochastic noise, distributed as represented by the random deviate instance dev, to each element of the data array in img. This therefore has the same effect as dev.applyTo(img) (see Section 3; also galsim/noise.py).
- o img.write(fits, ...) write the imageView to a FITS file or object as determined by the fits input parameter (see galsim/fits.py). In Section 5.4 we discuss how to write to multi-extension FITS files.

The ImageView classes are also returned when accessing a sub-section of an existing Image. For example

```
>>> imv = img.subImage(bounds)
```

where bounds is a Bounds I instance (see Section 5.2) assigns imv as an ImageView into the sub-region of img lying in the area represented by bounds. Equivalent syntax is also

```
>>> imv = img[bounds].
```

It is also possible to change the values of a sub-region of an image this way, for example

```
>>> img[imv.bounds] += imv
```

if wishing to add the contents of imv to the area lying within its bounds in img. Note that here we have made use of the .bounds attribute carried by all of the Image classes.

5. Miscellaneous classes and functions

A summary of miscellaneous GalSim library objects, subcategorized into broad themes. As ever, docstrings for the *all* the classes and functions below can be accessed via

```
>>> help(galsim.<Name>)
```

within the Python interpreter.

5.1. Angles

- o galsim. Angle (value, angle_unit) class to represent angles and handle multiple unit types, which can be initialized very simply by multiplying a numerical value and an AngleUnit instance angle_unit (see below, and galsim/angle.py).
- o galsim. AngleUnit (radians) class for holding angular unit definitions, specified on initialization in radians. There are five built-in AngleUnits which are always available for use:

```
- galsim.radians # = galsim.AngleUnit(1.)
- galsim.degrees # = galsim.AngleUnit(pi / 180.)
- galsim.hours # = galsim.AngleUnit(pi / 12.)
- galsim.arcmin # = galsim.AngleUnit(pi / 180. / 60.)
```

- galsim.arcsec # = galsim.AngleUnit(pi / 180. / 3600.)

5.2. Bounds and Positions

- o galsim.BoundsI(...) & galsim.BoundsD(...) classes to represent image bounds in the x-y plane as the vertices of a rectangle (see galsim/bounds.py).
- o galsim.PositionI(x, y) & galsim.PositionD(x, y)
 classes to represent 2D positions on the x-y plane (see galsim/position.py), e.g., for describing object centroid positions.

5.3. Shear and Ellipse transformations

- o galsim.Ellipse(...)

 class to represent ellipses and thus ellipse-type transformations. The class can be initialized using a

 variety of different parameter conventions (see galsim/ellipse.py), including being initialized

 with a Shear instance (see below).
- o galsim. Shear (...)

 class to represent shears in a variety of ways. Like the galsim. Ellipse, this class can be initialized using a variety of different parameter conventions (see galsim/shear.py). Commonly-used examples:
 - galsim. Shear (g1, g2) set via the first (g1) and second (g2) component of a shear defined so that |g| = (a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.

- galsim. Shear (e1, e2) set via the first (e1) and second (e2) component of a shear defined so that $|e| = (a^2 b^2)/(a^2 + b^2)$ where a and b are the semi-major and semi-minor axes of an ellipse.
- galsim. Shear (g), beta) set via magnitude (g) and polar angle (beta) of a shear defined so that |g| = (a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.
- galsim. Shear (e, beta) set via magnitude (e) and polar angle (beta) of a shear defined so that $|e|=(a^2-b^2)/(a^2+b^2)$ where a and b are the semi-major and semi-minor axes of an ellipse.

5.4. Multiple image FITS output tools

- o galsim.fits.writeMulti(image_list, fits, ...)
 write multiple Image instances stored in a Python list object image_list to a Multi-Extension
 FITS file or object as determined by the fits input parameter (see galsim/fits.py).
- o galsim.fits.writeCube(image_list, fits, ...)
 write multiple Image instances stored in a Python list object image_list to a three-dimensional
 FITS datacube object as determined by the fits input parameter (see galsim/fits.py).