GalSim Quick Reference

Contents

1	Ove	rview	2
2	GSC	Objects	3
	2.1	GSObject classes and when to use them	3
	2.2	Units	5
	2.3	Important GSObject methods	5
3	Random deviates		8
	3.1	Random deviate classes and when to use them	8
	3.2	Important random deviate methods	9
	3.3	Noise models	9
4	Images		10
	4.1	Image classes and when to use them	10
	4.2	Important Image methods and operations	11
5	Miscellaneous classes and functions		12
	5.1	Angles	12
	5.2	Bounds and Positions	13
	5.3	Shear and Ellipse transformations	13
	5.4	Lensing shear fields	14
	5.5	Additional FITS input/output tools	14

1. Overview

The GalSim package provides a number of Python classes and methods for simulating astronomical images. We assume GalSim is installed; see the *GalSim Wiki* or the file INSTALL.md in the base directory /your/path/to/GalSim/ for instructions. The package is imported into Python with

```
>>> import galsim
```

and the typical work flow, as demonstrated in the example scripts in the examples/ directory (all paths given relative to /your/path/to/GalSim/ from now on), will normally be something like the following:

- Construct a representation of your desired astronomical object as an instance of the GSObject class, which represent surface brightness profiles (of galaxies or PSFs). Multiple components can be combined using the special Add and Convolve classes see Section 2.
- Apply transformations such as shears, shifts or magnification using the methods of the GSObject
 — see Section 2.3.
- Draw the object into a GalSim Image, representing a postage stamp image of your astronomical object. This can be done using the obj.draw(...) or obj.drawShoot(...) methods carried by all GSObjects for rendering images see Sections 2.3 & 4.
- Add noise to the Image using one of the GalSim random deviate classes see Section 3.
- Add the postage stamp Image to a subsection of a larger Image instance see Section 4.2 or to a Python list containing multiple Image instances.
- Save the Image(s) to file in FITS (Flexible Image Transport System) format see Sections 4.2 & 5.5.

There are many examples of this workflow in the directory examples/, showing most of the GalSim library in action, in the scripts named demol.py-demo8.py. This document provides a brief, reference description of the GalSim classes and methods which can be used in these workflows.

Where possible in the following Sections this document has been hyperlinked to the online GalSim documentation generated by *doxygen*, where a more detailed description can be found. We also suggest accessing the full docstrings for *all* the classes and functions described below in Python itself, e.g. by typing

```
>>> help(galsim.<ObjectName>)
```

within the Python interpreter. If using the ipython package, which is recommended, instead simply type

```
In [1]: galsim.<ObjectName>?
```

and be sure to use the excellent tab-completion feature to explore the many methods and attributes of the GalSim classes.

2. GSObjects

2.1. GSObject classes and when to use them

There are currently 13 types of GSObjects that represent various types of surface brightness profiles. The first 11 listed are 'simple' GSObjects that can be initialized by providing values for their required and optional parameters. The last two are 'compound' classes used to represent combinations of GSObjects.

They are summarized in the following hyperlinked list, in which we also give the required parameters for initializing each class in parentheses after the class name. For more information and initialization details for each GSObject, the Python docstring for each class is available within the Python interpreter, for example for Sersic the documentation would be accessed using

```
>>> help(galsim.Sersic)
```

Alternatively follow the hyperlinks on the class names listed below to view the documentation based on the Python docstrings.

We now list, in the order in which the classes appear in galsim/base.py, the GSObjects. Where multiple options for specifying the object size exist we list these in the object description. We also show some of the non-optional parameters available for use (e.g. total flux) along with default values:

- galsim.Gaussian(size, flux=1.)
 a 2D Gaussian light profile. Requires one of the following size parameters to be set as a keyword argument: sigma; fwhm; half_light_radius.
- o galsim.Moffat(beta, size, flux=1.) a Moffat profile with slope parameter beta, used to approximate ground-based telescope PSFs. Requires one of the following size parameters to be set as a keyword argument: scale_radius; fwhm; half_light_radius. For information about other optional parameters, see the documentation for this object.
- o galsim.AtmosphericPSF(size, flux=1.) currently simply an image-based implementation of a Kolmogorov PSF (see below), and therefore deprecated, but expected to evolve to store a stochastically modelled atmospheric PSF in the near future. Requires one of the following size parameters to be set as a keyword argument: fwhm; lam_over_r0. For information about other optional parameters, see the documentation for this object.
- o galsim.Airy(lam_over_diam, obscuration=0., flux=1.) an Airy PSF for ideal diffraction through a circular aperture, parametrized by the wavelength-aperture diameter ratio lam_over_diam, with optional obscuration.

- o galsim.Kolmogorov(size, flux=1.)
 - the Kolmogorov PSF for long-exposure images through a turbulent atmosphere. Requires one of the following <code>size</code> parameters to be set as a keyword argument: <code>lam_over_r0</code>; fwhm; half_light_radius.
- o galsim.OpticalPSF(lam_over_diam, flux=1.)
 a simple model for non-ideal (aberrated) propagation through circular/square apertures, parametrized by the wavelength-aperture dimension ratio lam_over_diam, with optional obscuration. For information about other optional parameters, see the documentation for this object.
- galsim.InterpolatedImage(image, ...)
 a base class representing in principle arbitrary surface brightness profiles for which we have an Image representation. For information about other optional parameters, see the documentation for this object.
- o galsim.Pixel(xw, yw = None, flux=1.) used for integrating light onto square or rectangular pixels, requires at least one side dimension xw. If no width yw for the y dimension of the Pixel is given, the assumed shape is square.
- galsim.Sersic(n, half_light_radius, flux=1.)
 the Sérsic family of galaxy light profiles, parametrized by an index n and half_light_radius.
- o galsim.Exponential(size, flux=1.) the Exponential galaxy disc profile, a Sérsic with index n=1. Requires one of the following size parameters to be set as a keyword argument: scale_radius; half_light_radius.
- galsim.DeVaucouleurs(half_light_radius, flux=1.)
 the De Vaucouleurs galaxy bulge profile, a Sérsic with index n=4 and input half_light_radius.
- o galsim.RealGalaxy(real_galaxy_catalog, ...)
 models galaxies using real data, including a correction for the original PSF. Requires the download
 of external data, stored and input as the real_galaxy_catalog parameter (an instance of the
 RealGalaxyCatalog class), for full functionality.

An example catalog of 100 real galaxies is in the repository itself; a set of \sim 26 000 real galaxy images, with original PSFs, can be downloaded from the *RealGalaxy Data Download Page* on the *GalSim Wiki*:

https://github.com/GalSim-developers/GalSim/wiki/RealGalaxy%20Data%20Download%20Page. For information about other optional parameters, see the documentation for this object.

- galsim.Add([list of objects])a compound object representing the sum of multiple GSObjects.
- galsim.Convolve([list of objects])
 a compound object representing the convolution of multiple GSObjects.

Note that all of the GSObjects except for RealGalaxy, Add, and Convolve *require* the specification of one radius size parameter.

2.2. Units

The choice of units for the size parameters is up to the user, but it must be kept consistent between all GSObjects. These units must also adopted when specifying the Image pixel scale dx, whether this is set via the GSObject instance methods obj.draw(...) and obj.drawShoot(...) (see Section 2.3), or when setting the scale of an Image with a given dx using the image.setScale(dx) method (see Section 4).

As an example, consider the lam_over_diam parameter, which provides an angular scale for the Airy via the ratio λ/D for light at wavelength λ passing through a telescope of diameter D. Putting both λ and D in metres and taking the ratio gives lam_over_diam in radians, but this is not a commonly used angular scale when describing astronomical objects such as galaxies and stellar PSFs, nor is it often used for image pixel scales. If wishing to use arcsec, which is more common in both cases, the user should multiply the result in radians by the conversion factor $648000/\pi$. In principle, however, any consistent system of units could be used.

2.3. Important GSObject methods

A number of methods are shared by all the GSObjects of Section 2, and are also to be found in galsim/base.py within the definition of the GSObject base class. In what follows, we assume that a GSObject labelled obj has been instantiated using one of the calls described in the documentation linked above. For example,

```
>>> obj = galsim.Sersic(n=3.5, half_light_radius=1.743).
```

One important fact about GSObjects is that all of the methods which change the properties of the astronomical object represented by the instance (e.g., setFlux(), applyShear() etc.) also make fundamental changes to the instance itself. In most cases this will mean that special methods available to individual classes described in Section 2.1, such as getFWHM() for the Moffat, will be unavailable.

Once again, for more information regarding each galsim. GSObject method, the Python docstring is available

```
>>> help(obj.<methodName>)
```

within the Python interpreter. Alternatively follow the hyperlinks on the class names above to view the documentation based on the Python docstrings.

Some of the most important and commonly-used methods for such an instance are:

```
o obj.copy()
 return a copy of the GSObject.
o obj.centroid()
  return the (x, y) centroid of the GSObject as a PositionD (see Section 5.2).
o obj.getFlux()
  get the flux of the GSObject.
o obj.scaleFlux(flux_ratio)
  multiply the flux of the GSObject by flux_ratio.
o obj.setFlux(flux)
  set the flux of the GSObject to flux.
o obj.applyTransformation(ellipse)
  apply an Ellipse transformation represented by ellipse to the GSObject (see Ellipse; Sec-
  tion 5.3).
o obj.applyDilation(scale)
  change of the linear size of the GSObject by a factor scale, conserving flux.
o obj.applyMagnification(scale)
  dilate linear size by scale and multiply total flux by scale<sup>2</sup>, conserving surface brightness.
o obj.applyShear(...)
  apply a shear to the GSObject, handling a number of different input conventions (see also Shear;
  Section 5.3). Commonly-used input conventions (supplied as keyword arguments, default values
 zero):
    - obj.applyShear(g1=g1, g2=g2)
```

- obj.applyShear (g1=g1, g2=g2) apply the first (g1) and second (g2) component of a shear defined so that |g| = (a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.
- obj.applyShear (e1=e1, e2=e2) apply the first (e1) and second (e2) component of a shear defined so that $|e|=(a^2-b^2)/(a^2+b^2)$ where a and b are the semi-major and semi-minor axes of an ellipse.
- obj.applyShear (g=g, beta=beta) apply magnitude (g) and polar angle (beta) of a shear defined using the |g| definition above.
- obj.applyShear (e=e, beta=beta) apply magnitude (e) and polar angle (beta) of a shear defined using the |e| definition above.
- o obj.applyRotation(theta) apply a rotation of theta (positive direction anti-clockwise) to the GSObject, where theta is an Angle instance (see Section 5.1).

- o obj.applyShift(dx, dy) apply a (dx,dy) position shift to the GSObject centroid.
- o image = obj.draw(image=None, dx=None, add_to_image=False, ...) draw and return an Image (see Section 4) of the GSObject using Discrete Fourier Transforms and interpolation to perform the image rendering. Note that if a profile is not convolved with a pixel response before drawing, then draw samples the surface brightness distribution without integrating within pixels, so the sum of pixel values might not equal the GSObject flux. Some information about important optional parameters (see the linked / Python docstrings for more detail), along with default values:
 - image (default = None)
 if supplied, the drawing will be done into a user-supplied Image instance image. If not supplied (i.e. image = None), an automatically-sized Image instance will be returned.
 - dx (default = None)
 the optional image pixel scale dx, which if provided should use the same units as used for the GSObject size parameters. If not provided, will take either the scale from a supplied image, else use the Nyquist scale given the maximum modelled frequency in the GSObject.
 - add_to_image (default = False)
 Whether to add flux to a (must be supplied) image rather than clear out anything in the image before drawing.

The draw method has a number of additional optional parameters. Please see the linked / Python docstrings for more details.

```
o image = obj.drawShoot(image=None, dx=None,
  add_to_image=False, ...)
```

draw and return an Image (see Section 4) of the GSObject by shooting a finite number of photons. The resulting rendering therefore contains stochastic noise, but uses few approximations. Note however, that you cannot drawShoot with a RealGalaxy instance. drawShoot shares all the parameters listed for draw, above, but the drawShoot method also has a number of additional optional parameters. Important examples worthy of mention are:

- n_photons (default = 0)
 If provided, the number of photons to use. If not provided, use as many photons as necessary to end up with an image with the correct poisson shot noise for the object's flux.
- max_extra_noise (default = 0.)
 If provided, the allowed extra noise in each pixel. This is only relevant if n_photons = 0, so the number of photons is being automatically calculated. In that case, if the image noise is dominated by the sky background, you can get away with using fewer shot photons than the full n_photons = flux. Essentially each shot photon can have a flux > 1, which increases

the noise in each pixel. The max_extra_noise parameter specifies how much extra noise per pixel is allowed because of this approximation.

poisson_flux (default = True)
 Whether to allow total object flux scaling to vary according to Poisson statistics for n_photons samples.

As before, you are strongly encouraged to see the linked / Python docstrings for more details.

Finally, you may see by exploring the docstrings that many of the GSObject instances also have their own specialized methods, often for retrieving parameter values. Examples are obj.getSigma() for the Gaussian, or obj.getHalfLightRadius() for many of the GSObjects.

3. Random deviates

3.1. Random deviate classes and when to use them

Random deviates can be used to add a stochastic component to the modelling of astronomical images, such as drawing object parameters according to a given distribution or generating random numbers to be added to image pixel values to model noise.

We now give a short summary of the 9 random deviates currently implemented in GalSim. The optional parameter <code>seed</code> listed below is used to seed the pseudo-random number generator: it can either be omitted (the random deviate seed will be set using the current time), set to an integer seed, or used to pass another random deviate (the new instance will then use and update the same underlying generator as the input deviate). The deviates, with a description of their distributions, parametrization and default parameter values, are as follows:

```
galsim.UniformDeviate(seed)
uniform distribution in the interval [0,1).
galsim.GaussianDeviate(seed, mean=0., sigma=1.)
Gaussian distribution with mean and standard deviation sigma.
galsim.BinomialDeviate(seed, N=1, p=0.5)
Binomial distribution for N trials each of probability p.
galsim.PoissonDeviate(seed, mean=1.)
Poisson distribution with a single mean rate.
galsim.WeibullDeviate(seed, a=1., b=1.)
Weibull distribution family (includes Rayleigh and Exponential) with shape parameters a and b.
```

- o galsim.GammaDeviate(seed, alpha=1., beta=1.)
 Gamma distribution with parameters alpha and beta.
- o galsim.Chi2Deviate(seed, n=1.) χ^2 distribution with degrees-of-freedom parameter n.
- \circ galsim.DistDeviate(seed, function, x_min, x_max) Use an arbitrary function for P(x) from x_min.x_max.

It is possible to specify the random seed so as to get fully deterministic behavior of the noise when running a particular script. Unfortunately the random deviate classes are not yet fully integrated within the documentation, due to their being C++ with compiled Python wrappers. This means that the class names above and methods below are not yet hyperlinked. For more information, please refer to the full docstrings in galsim/random.py, or type

```
>>> help(galsim.<RandomDeviateName>)
```

within the Python interpreter.

3.2. Important random deviate methods

We now illustrate the most commonly-used methods of the random deviates, assuming that some random deviate instance dev has been instantiated, for example by

```
>>> dev = galsim.GaussianDeviate(sigma=3.9, mean=50.).
```

The most important and commonly-used method for such instances is:

o dev()

calling the deviate directly simply returns a single new random number drawn from the distribution represented by dev. As an example:

```
>>> dev = galsim.UniformDeviate(12345)
>>> dev()
0.9296160866506398
>>> dev()
0.8901547130662948
```

3.3. Noise models

One common way to use the random deviates is as part of a noise model for adding noise to an image. These have their own separate hierarchy of classes

- galsim.GaussianNoise(rng, sigma=1.)
 Every pixel gets Gaussian noise with rms sigma.
- o galsim.PoissonNoise(rng, sky_level=0.)

 Every pixel gets Poisson noise according to the flux in the image plus an option sky level, sky_level.
- galsim.DeviateNoise(dev)
 The noise value for every pixel is drawn from the given Deviate instance.
- o galsim.CCDNoise(rng, sky_level=0., gain=1., read_noise=0.)
 A combination of Poisson noise (with a gain value in electrons/ADU) and Gaussian read noise.

These noise models are used with a method of Image objects (see Section 4, below). This takes the following form:

 image.addNoise(noise)
 this adds stochastic noise, according to the noise model noise, to each element of the data array in the Image instance image.

4. Images

4.1. Image classes and when to use them

The GalSim Image classes store array data, along with a figure for the pixel separation in physical units and image bounds information (origin, extent). Image instances can be operated upon to add stochastic noise simulating real astronomical images (see Section 3), and have methods for writing to FITS format output.

There are four types of GalSim Image, one for each of four supported array data types. The most common way to initialize an image is with two integer parameters nx and ny, giving the image extent in the x and y dimensions, respectively. Example initialization calls for the four types of Image are therefore:

- o galsim. ImageS (nx, ny) for short integers (typically 16 bit).
- o galsim.ImageI(nx, ny) for integers (typically 32 bit).
- o galsim. ImageF (nx, ny) for single precision (typically 32 bit) floats.

¹ There are additional flavours of Image that you might also encounter: ImageView provides a mutable view into Image instance data, and ConstImageView an immutable view into Image instance data. These may be the type of images returned from various GalSim functions, but as they work the same way as Image, you shouldn't notice the difference. See their docstrings for more information.

o galsim.ImageD (nx, ny) for double precision (typically 64 bit) floats.

Other ways to construct an Image can be found in the docstrings.

To access the data as a NumPy array, simply use the image.array attribute, where image is an instance of one of these Image classes. However, note that the individual elements in the array attribute are accessed as image.array [y, x], matching the standard NumPy convention, while the Image class's own accessors are all (x, y) in ordering.

Unfortunately the Image classes are not yet fully integrated within the online documentation, due to their being in C++ with compiled Python wrappers. This means that the class names above and methods below are not hyperlinked. However, the full docstrings are available in galsim/image.py, so please refer there for more information, or type

```
>>> help(galsim.<ImageName>)
```

within the Python interpreter.

4.2. Important Image methods and operations

We now illustrate the most commonly-used methods of Image class instances. We will assume that some Image instance image has been instantiated, for example by

```
>>> image = galsim.ImageD(100, 100).
```

This Image instance is then ready to pass to a GSObject for drawing. The most important and commonly-used methods for such an instance are:

- image.getScale()get the pixel scale dx for this image.
- \circ image.setScale(dx) set the pixel scale for this image to dx note that this scale should use the same units adopted for the GSObject sizes.
- image.addNoise(dev)
 this adds stochastic noise, distributed as represented by the random deviate instance dev, to each element of the data array in image. This is the method previously referenced in Section 3.
- image.write(fits, ...)
 write the imageView to a FITS file or object as determined by the fits input parameter (see galsim/fits.py). In Section 5.5 we discuss how to write to multi-extension FITS files.

Image² instances are also returned when accessing a sub-section of an existing Image. For example

```
>>> imsub = image.subImage(bounds)
```

where bounds is a Bounds I instance (see Section 5.2) assigns imsub as an view into the sub-region of image lying in the area represented by bounds. Equivalent syntax is also

```
>>> imsub = image[bounds]
```

It is also possible to change the values of a sub-region of an image this way, for example

```
>>> image[imsub.bounds] += imsub
```

if wishing to add the contents of imsub to the area lying within its bounds in image. Note that here we have made use of the image. bounds attribute carried by all of the Image classes.

5. Miscellaneous classes and functions

A summary of miscellaneous GalSim library objects, subcategorized into broad themes. As ever, docstrings for *all* the classes and functions below can be accessed via

```
>>> help(galsim.<Name>)
```

within the Python interpreter.

5.1. Angles

- o galsim.Angle(value, angle_unit) class to represent angles (with multiple unit types), which can be initialized by multiplying a numerical value and an AngleUnit instance angle_unit (see below, and galsim/angle.py).
- o galsim.AngleUnit

There are five built-in AngleUnits which are always available for use:

- galsim.radians
- galsim.degrees
- galsim.hours
- galsim.arcmin
- galsim.arcsec

Please see the Python docstrings for information about defining your own AngleUnits.

²Actually, the functionally almost-equivalent ImageView, see the footnote in Section 4.1.

5.2. Bounds and Positions

```
    galsim.BoundsI(...)
    galsim.BoundsD(...)
    classes to represent image boundaries as the vertices of a rectangle (see galsim/bounds.py).
```

```
o galsim.PositionI(x, y)
galsim.PositionD(x, y)
```

classes to represent 2D positions on the x-y plane (see galsim/position.py), e.g., for describing object centroid positions.

For both bounds and positions, the I and D refer to integer and double-precision floating point representations.

5.3. Shear and Ellipse transformations

o galsim.Shear(...)

class to represent shears in a variety of ways. This class can be initialized using a variety of different parameter conventions (see galsim/shear.py). Commonly-used examples (supplied as keyword arguments, default values zero):

- galsim. Shear (g1=g1, g2=g2) set via the first (g1) and second (g2) component of a shear defined so that |g| = (a-b)/(a+b) where a and b are the semi-major and semi-minor axes of an ellipse.
- galsim. Shear (e1=e1, e2=e2) set via the first (e1) and second (e2) component of a shear defined so that $|e|=(a^2-b^2)/(a^2+b^2)$ where a and b are the semi-major and semi-minor axes of an ellipse.
- galsim. Shear (g=g, beta=beta) set via magnitude (g) and polar angle (beta) of a shear defined according to the |g| definition above.
- galsim. Shear (e=e, beta=beta) set via magnitude (e) and polar angle (beta) of a shear defined according to the |e| definition above.

```
o galsim.Ellipse(...)
```

class to represent ellipses and thus ellipse-type transformations, specifically shears, shifts, and dilations. The class can be initialized using a variety of different parameter conventions (see, e.g., galsim/ellipse.py), including being initialized with a Shear instance.

5.4. Lensing shear fields

GalSim has functionality to simulate scientifically-motivated lensing shear fields. The code and documentation for the "lensing engine" is in galsim/lensing.py. The two relevant classes for users are:

- o galsim.PowerSpectrum(...) represents a flat-sky shear power spectrum P(k), where the E and B-mode power spectra can be separately specified as E_power_function and B_power_function. The getShear(...) method is used to generate a random realization of a shear field from a given PowerSpectrum object, and there are methods to get convergence or magnification as well.
- o galsim.NFWHalo(...)
 represents a matter density profile corresponding to a projected, circularly-symmetric NFW profile such as might be used to simulate lensing by a galaxy cluster. This class has two methods of interest for users, getShear() and getConvergence(), which can be used to get the shears and convergences at any (non-gridded) image-plane position.

These classes have additional requirements on the units used to specify positions; see the documentation for these classes for more details.

The GalSim repository also contains an example script that can be used to estimate shear power spectra from gridded shear values even if GalSim is not installed: examples/PowerSpectrumEstimator.py (see documentation in that file for more information).

5.5. Additional FITS input/output tools

- o image = galsim.fits.read(fits)
 returns an Image instance image from a FITS representation fits. If fits is a string it is interpreted as a filename, otherwise it is interpreted as a PyFITS representation of HDU data (see
 galsim/fits.py).
- image_list = galsim.fits.readMulti(fits)
 returns a Python list of Image instances (image_list) from a Multi-Extension FITS file or PyFITS HDU object, specified by the fits input parameter (see galsim/fits.py).
- galsim.fits.writeMulti(image_list, fits, ...)
 write multiple Image instances stored in a Python list (image_list) to a Multi-Extension FITS
 file or PyFITS HDU object, specified by the fits input parameter (see galsim/fits.py).
- galsim.fits.writeCube (image_list, fits, ...)
 write multiple Image instances stored in a Python list (image_list) to a three-dimensional FITS datacube or PyFITS HDU object, specified by the fits input parameter (see galsim/fits.py).

The routines for reading and writing FITS images are able to handle compressed inputs / outputs via keywords.