
Lecture 8: Address Translation


Yinqian @ 2021, Spring copyright@Bo Tang

Want Processes to Co-exist



- Consider multiprogramming on physical memory
 - What happens when pintos needs to expand?
 - If emacs needs more memory than is on the machine?
 - If pintos has an error and writes to address 0x7100?
 - When does gcc have to know it will run at 0x4000?
 - What if emacs is not using its memory?

Virtualizing Resources



- Physical Reality: different processes/threads share the same hardware
 - Need to multiplex CPU (done)
 - Need to multiplex use of Memory (today)
 - Need to multiplex disk and devices (later in term)
- Why worry about memory sharing?
 - The complete working state of a process is defined by its data in memory (and registers)
 - Consequently, two different processes cannot use the same memory
 - Two different data cannot occupy same locations in memory
 - May not want different threads to have access to each other's memory

Next Objective

 Dive deeper into the concepts and mechanisms of memory sharing and address translation

Enabler of many key aspects of operating systems

stributed supplies (8) supplies (8)

Protection

Multi-programming

Isolation
 ■

Memory resource management

I/O efficiency


Sharing

Inter-process communication

Demand paging

Today: Linking, Segmentation

Processes



- Threads encapsulate concurrency
 - "Active" component of a process
- Address spaces encapsulate protection
 - Keeps buggy program from trashing the system
 - "Passive" component of a process

Important Aspects of Memory Multiplexing


- Protection: prevent access to private memory of other processes
 - Kernel data protected from User programs
 - Programs protected from themselves
 - May want to give special behavior to different memory regions (Read Only, Invisible to user programs, etc)
- Controlled overlap: sometimes we want to share memory across processes.
 - E.g., communication across processes, share code
 - Need to control such overlap

Important Aspects of Memory Multiplexing


Translation:

- Ability to translate accesses from one address space (virtual) to a different one (physical)
- When translation exists, processor uses virtual addresses, physical memory uses physical addresses
- Side effects:
 - Can be used to give uniform view of memory to programs
 - Can be used to provide protection (e.g., avoid overlap)
 - Can be used to control overlap

Recall: OS Bottom Line: Run Programs




Recall: Address Space



https://gabrieletolomei.wordpress.com/miscellanea/operating-systems/in-memory-layout/ (text → code segment, read only / execute), BSS: block started by symbol, "static int i" (data segment: read-write)

Recall: Context Switch




One address maps to one byte.

On a 32-bit system,


- The maximum amount of memory in a process is 2³² bytes = **4GB**.

Then, how about a 64-bit system? = **16EB**

Binding of Instructions and Data to Memory




2nd copy of program from previous example



Need address translation!


2nd copy of program from previous example



Compile time, Link/Load time, or Execution time?

Multi-step Processing of a Program for Execution

- Preparation of a program for execution involves components at:
 - (1) Compile time (i.e., "gcc")
 - (2) Link time (UNIX "ld" does link)
 - (3) Load time
 - (4) Execution time (e.g., dynamic libs)
- Addresses can be bound to final values anywhere in this path
 - Depends on hardware support
 - Also depends on operating system
- Dynamic Libraries
 - Linking postponed until execution
 - Small piece of code, *stub*, used to locate appropriate memory-resident library routine
 - Stub replaces itself with the address of the routine, and executes routine



Multiplexing Memory Approaches

- Uniprogramming
- Multiprogramming
 - Without protection
 - With protection (base+bound)
- Virtual memory
 - Base & Bound
 - Segmentation
 - **Paging**
 - Paging + Segmentation

Uniprogramming

- Uniprogramming (no Translation or Protection)
 - Application always runs at same place in physical memory since only one application at a time
 - Application can access any physical address

Operating System

Application

OXFFFFFFF

Valid 32-bit Addresses



0x00000000

Application given illusion of dedicated machine by giving it reality of a dedicated machine

Multiprogramming (primitive stage)

- Multiprogramming without Translation or Protection
 - Must somehow prevent address overlap between threads

Operating System


Application2

Application1

OXFFFFFFF

0x00020000


0x000000000



- Use Loader/Linker: Adjust addresses while program loaded into memory (loads, stores, jumps)
 - Everything adjusted to memory location of program
 - Translation done by a linker-loader (relocation)
 - Common in early days (... till Windows 3.x, 95?)
- With this solution, no protection: bugs in any program can cause other programs to crash or even the OS

Multiprogramming (Version with Protection)


Can we protect programs from each other without translation?




- Yes: use two special registers *BaseAddr* and *LimitAddr* to prevent user from straying outside designated area
 - If user tries to access an illegal address, cause an error
- During switch, kernel loads new base/limit from PCB (Process Control Block)
 - User not allowed to change base/limit registers

Virtual memory support in modern CPUs


- ♦ The MMU memory management unit
 - Usually on-chip (but some architecture may off-chip or no hardware MMU)




- Step 1. When CPU wants to fetch an instruction
 - the virtual address is sent to MMU and
 - is translated into a **physical address**.




Step 2. The memory returns the instruction




- Step 3. The CPU decodes the instruction.
 - **■** An instruction **uses virtual addresses**
 - but not physical addresses.



Step 4. With the help of the MMU, the target memory is retrieved.




General Address translation




- * Recall: Address Space.te
 - All the addresses and state a process can touch
 - Each process has different address space
- Consequently, two views of memory:
 - View from the CPU (what program sees, virtual memory)
 - View from memory (physical memory)
 - Translation box (MMU) converts between the two views
- Translation makes it much easier to implement protection
 - If task A cannot even gain access to task B's data, no way for A to adversely affect B
- With translation, every program can be linked/loaded into same region of user address space

Simple Example: Base and Bounds




- Could use base/bounds for dynamic address translation translation happens at execution:
 - Alter address of every load/store by adding "base"
 - Generate error if address bigger than limit
- This gives program the illusion that it is running on its own dedicated machine, with memory starting at 0
 - Program gets continuous region of memory
 - Addresses within program do not have to be relocated when program placed in different region of DRAM


Issues with Simple B&B Method



- Fragmentation problem over time
 - Not every process is same size memory becomes fragmented
- Missing support for sparse address space
 - Would like to have multiple chunks/program (Code, Data, Stack)
- Hard to do inter-process sharing
 - Want to share code segments when possible
 - Want to share memory between processes
 - Helped by providing multiple segments per process


More Flexible Segmentation





- Logical View: multiple separate segments
 - Typical: Code, Data, Stack
 - Others: memory sharing, etc
- Each segment is given region of contiguous memory
 - Has a base and limit
 - Can reside anywhere in physical memory


Implementation of Multi-Segment Model



As many chunks of physical memory as entries

Error check catches offset out of range


- Segment addressed by portion of virtual address
- However, could be included in instruction instead:
 - * x86 Example: mov [es:bx],ax.
- ♦ What is "V/N" (valid / not valid)?
 - Can mark segments as invalid; requires check as well





Space

ciito (1 1			addi C
Seg ID	Seg ID #		2	Limit
O (code	2)	0x40 0	0	0x080 0
1 (data	१)	0x48 0	0	0x140 0
2 (shared	2)	OXFO	<u>о</u> 	0x100 0
3 (stac	k)	0x00 0	0	0x300 0

Physical Address Space







Virtual Address Space

Physical Address Space

0x240	main:	la \$	a0, varx	
0x244		jal strlen		
•••				
0x360	strlen:	li	\$v0, 0 ;count	
0x364	loop:	1b	\$t0, (\$a0)	
0x368		beq	\$r0,\$t0, done	
		•••		
0x4050	varx	dw	0x314159	

Seg ID #	Base	Limit
O (code)	0x40 00	0x08 00
1 (data)	0x48 00	0x14 00
2 (shared)	OxFOO O	0x10 00
3 (stack)	0x00 00	0x30 00

Let us simulate a bit of this code to see v

1. Fetch 0x240. Virtual segment #? 0; Offset? 0x

Physical address? Base=0x4000, so physical addr=0x4240

Fetch instruction at 0x4240. Get "la \$a0, varx"

Move $0x4050 \rightarrow $a0$, Move PC+4 \rightarrow PC

0x240	main:	la \$	a0, varx
0x244		jal strlen	
0x360	strlen:	li	\$v0, 0 ;count
0x364	loop:	1b	\$t0, (\$a0)
0x368		beq	\$r0,\$t0, done
•••			
0x4050	varx	dw	0x314159

Seg ID #	Base	Limit
O (code)	0x40 00	0x08 00
1 (data)	0x48 00	0x14 00
2 (shared)	OxFOO O	0x10 00
3 (stack)	0x00 00	0x30 00

Let us simulate a bit of this code to see v

1. Fetch 0x240. Virtual segment #? 0; Offset? 0x Physical address? Base=0x4000, so physical addr=0x4240 Fetch instruction at 0x4240. Get "la \$a0, varx"

Move $0x4050 \rightarrow $a0$, Move PC+4 \rightarrow PC

2. Fetch 0x244. Translated to Physical=0x4244. Get "jal strlen" Move $0x0248 \rightarrow ra (return address!), Move $0x0360 \rightarrow PC$

0x240 0x244 	main:	la \$a0, varx jal strlen 	
0x360	strlen:	li	\$v0, 0 ;count
0x364	loop:	1b	\$t0, (\$a0)
0x368		beq	\$r0,\$t0, done
•••			
0x4050	varx	dw	0x314159

Seg ID #	Base	Limit
O (code)	0x40 00	0x08 00
1 (data)	0x48 00	0x14 00
2 (shared)	OxFOO O	0x10 00
3 (stack)	0x00 00	0x30 00

Let us simulate a bit of this code to see w

- 1. Fetch 0x240. Virtual segment #? 0; Offset? 0xPhysical address? Base=0x4000, so physical addr=0x4240Fetch instruction at 0x4240. Get "la \$a0, varx"
 Move $0x4050 \rightarrow $a0$, Move $PC+4 \rightarrow PC$
- 2. Fetch 0x244. Translated to Physical=0x4244. Get "jal strlen" Move $0x0248 \rightarrow ra (return address!), Move $0x0360 \rightarrow PC$
- 3. Fetch 0x360. Translated to Physical=0x4360. Get "li \$v0, 0" Move $0x0000 \rightarrow $v0$, Move PC+4 \rightarrow PC

0x240	main:	la \$a0, varx	
0x244		jal strlen	
0x360	strlen:	li	<pre>\$v0, 0 ;count</pre>
0x364	loop:	lb	\$t0, (\$a0)
0x368		beq	\$r0,\$t0, done
•••			
0x4050	varx	dw	0x314159

Seg ID #	Base	Limit
O (code)	0x40 00	0x08 00
1 (data)	0x48 00	0x14 00
2 (shared)	0xF00 0	0x10 00
3 (stack)	0x00 00	0x30 00

Let us simulate a bit of this code to see w

- 1. Fetch 0x240. Virtual segment #? 0; Offset? 0x Physical address? Base=0x4000, so physical address? Fetch instruction at 0x4240. Get "la \$a0, varx" Move $0x4050 \rightarrow $a0$, Move $PC+4 \rightarrow PC$
- 2. Fetch 0x244. Translated to Physical=0x4244. Get "jal strlen" Move $0x0248 \rightarrow ra (return address!), Move $0x0360 \rightarrow PC$
- 3. Fetch 0x360. Translated to Physical=0x4360. Get "li \$v0, 0" Move $0x0000 \rightarrow $v0$, Move PC+4 \rightarrow PC
- 4. Fetch 0x0364. Translated to Physical=0x4364. Get "lb \$t0, (\$a0)" Since \$a0 is 0x4050, try to load byte from 0x4050, Translate 0x4050 ($0100\ 0000\ 0101\ 000$). Virtual segment #? 1; Offset? 0x50 Physical address? Base=0x4800, Physical address = 0x4850, Load Byte from $0x4850 \rightarrow $t0$, Move PC+ $4 \rightarrow$ PC


Observations about Segmentation

- Virtual address space has holes
 - Segmentation efficient for sparse address spaces
 - A correct program should never address gaps
 - If it does, trap to kernel and dump core
- When is it OK to address outside valid range?
 - This is how the stack and heap are allowed to grow
 - For instance, stack takes fault, system automatically increases size of stack
- Need protection mode in segment table
 - For example, code segment would be read-only
 - Data and stack would be read-write (stores allowed)
 - Shared segment could be read-only or read-write
- What must be saved/restored on context switch?
 - Segment table stored in CPU, not in memory (small)
 - Might store all of processes memory onto disk when switched (called "swapping")

Problems with Segmentation

- Must fit variable-sized chunks into physical memory
- May move processes multiple times to fit everything
- Fragmentation: wasted space
 - External: free gaps between allocated chunks
 - Internal: do not need all memory within allocated chunks

General Address Translation




Physical Address Space

Paging: Physical Memory in Fixed Size Chunks

- Solution to fragmentation from segments?
 - Allocate physical memory in fixed size chunks ("pages")
 - Every chunk of physical memory is equivalent
 - Can use simple vector of bits to handle allocation:
 00110001110001101 ... 110010
 - Each bit represents page of physical memory $1 \Rightarrow$ allocated, $0 \Rightarrow$ free

- Should pages be as big as our previous segments?
 - No: Can lead to lots of internal fragmentation
 - Typically have small pages (1K-16K)
 - Consequently: need multiple pages per segment


How to Implement Paging?




- Resides in physical memory
- Contains physical page and permission for each virtual page
 - Permissions include: Valid bits, Read, Write, etc
- Virtual address mapping
 - Offset from Virtual address copied to Physical Address
 - * Example: 10 bit offset \Rightarrow 1024-byte pages
 - Virtual page # is all remaining bits
 - * Example for 32-bits: 32-10 = 22 bits, i.e. 4 million entries
 - Physical page # copied from table into physical address
 - Check Page Table bounds and permissions

Simple Page Table Example


Example (4 byte pages)




What about Sharing?




Summary: Paging



Summary: Paging



Summary: Paging




Page Table Discussion


- What needs to be switched on a context switch?
 - Page table pointer and limit
- Analysis
 - □ Pros
 - Simple memory allocation
 - Easy to share
 - ☐ Con: What if address space is sparse?
 - E.g., on UNIX, code starts at 0, stack starts at (2³¹-1)
 - With 1K pages, need 2 million page table entries!
 - ☐ Con: What if table really big?
 - Not all pages used all the time ⇒ would be nice to have working set of page table in memory
- How about multi-level paging or combining paging and segmentation?

Fix for sparse address space: The two-level page table 20 bits 12 bits Physical Page # 10 bits 10 bits 12 bits Offset Address: P1 index P2 index Offset Virtual Address: 4KB PageTablePtr → 4 bytes Tree of Page Tables Tables fixed size (1024 entries) On context-switch: save single PageTablePtr register Valid bits on Page Table Entries Don't need every 2nd-level table Even when exist, 2nd-level tables can 4 bytes reside on disk if not in use

Summary: Two-Level Paging




Summary: Two-Level Paging



Pages

- What about a tree of tables?
 - Lowest level page table ⇒ memory still allocated with bitmap
 - Higher levels often segmented
- Could have any number of levels. Example (top segment):



- What must be saved/restored on context switch?
 - Contents of top-level segment registers (for this example)
 - Pointer to top-level table (page table)

what about Sharing (Complete Seament)? Process Seg # Virtuai Page # Offset page #0 V,R page #1 V,R page #2 $V_{i}R_{i}V_{i}$ Baseo Limito V page #3 $V_{i}R_{i}V_{i}$ Lim.ic1 Base1 page #4 Basez Limit2 page #5 V,R,W Base3 Limit3 N Base4 Limit4 Shared Segment Limits Base5 Base Limita Limite N Base6 Limit1 Base Limit7 Base 7 Limit2 Base 2 _imit3 N Base3 Base4 _imit4 _imits Base5 Limite N Base6 Base 7 Limit

Offset

Process B Seg #

Virtual

Page #

Thank You!