# Lecture 9: Caching & Demand page

Yinqian Zhang @ 2021, Spring

Copyright@Bo Tang

# Caching


# Caching Concept



- Cache: a repository for copies that can be accessed more quickly than the original
  - Make frequent case fast and infrequent case less dominant
- Caching underlies many techniques used today to make computers fast
  - Cache may include: memory locations, address translations, pages, file blocks, file names, network routes, etc...
- Only good if:
  - Frequent case: frequent enough
  - Infrequent case: not too expensive
- Important measure: Average Access time = (Hit Rate x Hit Time) + (Miss Rate x Miss Time)

# Recall: CPU Cache and Memory

Caching is key to memory system performance



Average Access time=(Hit Rate x HitTime) + (Miss Rate x MissTime)


HitRate + MissRate = 1

HitRate = 90% => Avg. Access Time= $(0.9 \times 10) + (0.1 \times 100) = 19$ ns

HitRate = 99% => Avg. Access Time= $(0.99 \times 10) + (0.01 \times 100) = 10.9$  ns


# Review: Direct Mapped Cache

- Direct Mapped 2<sup>N</sup> byte cache:
  - The uppermost (32 N) bits are always the Cache Tag
  - ⋄ The lowest M bits are the Byte Select (Block Size =  $2^{M}$ )
- Example: 1 KB Direct Mapped Cache with 32 B Blocks
  - Index chooses potential block
  - Tag checked to verify block
  - Byte select chooses byte within block




### Review: Set Associative Cache

- N-way set associative: N entries per Cache Index
  - N direct mapped caches operates in parallel
- Example: Two-way set associative cache
  - Cache Index selects a "set" from the cache
  - Two tags in the set are compared to input in parallel




# Review: Fully Associative Cache

- Fully Associative: Every block can hold any line
  - Address does not include a cache index
  - Compare Cache Tags of all Cache Entries in Parallel
- Example: Block Size=32B blocks
  - We need N 27-bit comparators
  - Still have byte select to choose from within block



#### Where does a Block Get Placed in a Cache?

Example: Block 12 placed in 8 block cache 32-Block Address Space:



Block

111111111122222222233 01234567890123456789012345678901 no.

#### **Direct mapped:**


block 12 can go only into block 4 (12 mod 8)

Block 01234567 no.

#### Set associative:

block 12 can go anywhere in set 0 (12 mod 4)

01234567 **Block** no.



#### **Fully associative:**

block 12 can go anywhere

01234567 **Block** no.


# Review: Which block should be replaced on a miss?

- Easy for Direct Mapped: Only one possibility
- Set Associative or Fully Associative:
  - Random
  - LRU (Least Recently Used)


Miss rates for a workload:

	2-	way	4-1	way	8-way			
<u>Size</u>	LRU	Randor	n LRU	Randor	n LRU	<u>Random</u>		
16 KB	5.2%	5.7%	4.7%	5.3%	4.4%	5.0%		
64 KB	1.9%	2.0%	1.5%	1.7%	1.4%	1.5%		
256 KI	31.159	%1.17%	6 1.13	% 1.13	%1.12°	%1.12%		


# Why Does Caching Help? Locality!



- Temporal Locality (Locality in Time):
  - Keep recently accessed data items closer to processor
- Spatial Locality (Locality in Space):
  - Move contiguous blocks to the upper levels




### How is the Translation Accomplished?




- What, exactly happens inside MMU?
- One possibility: Hardware MMU
  - For each virtual address traverse the page table using hardware
  - Generates a "Page Fault" if it encounters invalid PTE
    - Fault handler will decide what to do
  - Pros: Relatively fast (but still many memory accesses!)
  - Cons: Inflexible, Complex hardware
- Another possibility: Software MMU
  - Each traversal done in software
  - Pros: Very flexible
  - Cons: Every translation must invoke Fault!
- In fact, need way to cache translations for either case!

# Another Major Reason to Deal with Caching




- Cannot afford to translate on every access
  - At least three DRAM accesses per actual DRAM access
  - Or: perhaps I/O if page table partially on disk!
- Solution? Cache translations!
  - Translation Cache: TLB ("Translation Lookaside Buffer")

Caching Applied to Address Translation




- Page locality: does it exist?
  - Instruction accesses spend a lot of time on the same page (since accesses sequential)
  - Stack accesses have definite locality of reference
  - Data accesses have less page locality, but still some...
- Can we have a TLB hierarchy?
  - Sure: multiple levels at different sizes/speeds

# Putting All Together: Address Translation



# Putting Everything Together: TLB




### Where are all places that caching arises in OSes?

- Direct use of caching techniques
  - TLB (cache of PTEs)
  - Paged virtual memory (memory as cache for disk)
  - DNS (cache hostname => IP address translations)
  - CDN (cache recently accessed pages)


# Demand Paging

# Demand Paging

- Modern programs require a lot of physical memory
  - Memory per system growing faster than 25%-30%/year
- But they do not use all their memory all of the time
  - 90-10 rule: programs spend 90% of their time in 10% of their code
  - Wasteful to require all of user's code to be in memory
- Solution: use main memory as cache for disk




# Illusion of Infinite Memory (1/2)



- $\bullet$  Disk is larger than physical memory  $\Rightarrow$ 
  - In-use virtual memory can be bigger than physical memory
  - Combined memory of running processes much larger than physical memory
    - More programs fit into memory, allowing more concurrency

# Illusion of Infinite Memory (2/2)



- Principle: Transparent Level of Indirection (page table)
  - Supports flexible placement of physical data
    - Data could be on disk or somewhere across network
  - Variable location of data transparent to user program
    - Performance issue, not correctness issue

# Since Demand Paging is Caching, Must Ask...

- What is block size?
  - 1 page
- What is organization of this cache (i.e. direct-mapped, set-associative, fully-associative)?
  - $\bullet$  Fully associative: arbitrary virtual  $\rightarrow$  physical mapping
- How do we find a page in the cache when look for it?
  - First check TLB, then page-table traversal
- What is page replacement policy? (i.e. LRU, Random...)
  - This requires more explanation
- What happens on a miss?
  - Go to lower level to fill miss (i.e. disk)
- What happens on a write? (write-through, write back)
  - Definitely write-back need dirty bit!

# Demand Paging Mechanisms

- PTE helps us implement demand paging
  - ♦ Valid ⇒ Page in memory, PTE points at physical page
  - Not Valid ⇒ Page not in memory; use info in PTE to find it on disk when necessary
- Suppose user references page with invalid PTE?
  - Memory Management Unit (MMU) traps to OS
    - Resulting trap is a "Page Fault"
  - What does OS do on a Page Fault?:
    - Choose an old page to replace
    - If old page modified ("D=1"), write contents back to disk
    - Change its PTE and any cached TLB to be invalid
    - Load new page into memory from disk
    - Update page table entry, invalidate TLB for new entry
    - Continue thread from original faulting location
  - TLB for new page will be loaded when thread continued!
  - While pulling pages off disk for one process, OS runs another process from ready queue
    - Suspended process sits on wait queue



# Recall: Some follow-up questions

- During a page fault, where does the OS get a free frame?
  - Keeps a free list
  - Unix runs a "reaper" if memory gets too full
    - Schedule dirty pages to be written back on disk
    - Zero (clean) pages which have not been accessed in a while
  - As a last resort, evict a dirty page first
- How can we organize these mechanisms?
  - Work on the replacement policy
- How many page frames per process?
  - Like thread scheduling, need to "schedule" memory resources:
    - Utilization? fairness? priority?
  - Allocation of disk paging bandwidth

# Demand Paging Cost Model

- Since Demand Paging like caching, can compute average access time! ("Effective Access Time")
  - EAT = Hit Rate x Hit Time + Miss Rate x Miss Penalty
- Example:
  - Memory access time = 200 nanoseconds
  - Average page-fault service time = 8 milliseconds
  - Suppose p = Probability of miss, 1-p = Probably of hit
  - Then, we can compute EAT as follows:

```
EAT = (1-p) \times 200 \text{ns} + p \times 8 \text{ ms}
= (1-p) \times 200 \text{ns} + p \times 8,000,000 \text{ns}
```

- $_{\odot}$  If one access out of 1,000 causes a page fault, then EAT is about 8.2  $\mu s$ :
  - This is a slowdown by a factor of 40!
- What if we want slowdown by less than 10%?
  - ◆ 200ns x 1.1 < EAT  $\Rightarrow$  p < 2.5 x 10<sup>-6</sup>
  - This is about 1 page fault in 400,000!

#### What Factors Lead to Misses?

#### Compulsory Misses:

- Pages that have never been paged into memory before
- Now might we remove these misses?
  - Prefetching: loading them into memory before needed
  - Need to predict future somehow! More later

#### Capacity Misses:

- Not enough memory. Must somehow increase available memory size.
- Can we do this?
  - One option: Increase amount of DRAM (not quick fix!)
  - Another option: If multiple processes in memory: adjust percentage of memory allocated to each one!

#### Conflict Misses:

Technically, conflict misses don't exist in virtual memory, since it is a "fully-associative" cache

#### Policy Misses:

- Caused when pages were in memory, but kicked out prematurely because of the replacement policy
- How to fix? Better replacement policy

# Page Replacement Policies

- Why do we care about Replacement Policy?
  - Replacement is an issue with any cache
  - Particularly important with pages
    - The cost of being wrong is high: must go to disk
    - Must keep important pages in memory, not toss them out

#### FIFO (First In, First Out)

- Throw out oldest page. Be fair let every page live in memory for same amount of time.
- Bad throws out heavily used pages instead of infrequently used

#### MIN (Minimum):


- Replace page that will not be used for the longest time
- Great, but cannot really know future...

#### RANDOM:

- Pick random page for every replacement
- Typical solution for TLB's. Simple hardware
- Pretty unpredictable makes it hard to make real-time guarantees

# Replacement Policies (Con't)

- LRU (Least Recently Used):
  - Replace page that has not been used for the longest time
  - Programs have locality, so if something not used for a while, unlikely to be used in the near future.
  - Seems like LRU should be a good approximation to MIN.
- How to implement LRU? Use a list!



- On each use, remove page from list and place at head
- LRU page is at tail
- Problems with this scheme for paging?
  - Need to know immediately when each page used so that can change position in list...
  - Many instructions for each hardware access
- In practice, people approximate LRU (more later)

### Example: FIFO

- Suppose we have 3 page frames, 4 virtual pages, and following reference stream:
  - ⋄ ABCABDADBCB
- Consider FIFO Page replacement:

Ref:	Α	В	С	Α	В	D	Α	D	В	С	В
Page:											
1	Α					D				С	
2		В					Α				
3			С						В		

- FIFO: 7 faults
- When referencing D, replacing A is bad choice, since need A again right away

# Example: MIN

- Suppose we have the same reference stream:
  - A B C A B D A D B C B
- Consider MIN Page replacement:

Ref: Page:	Α	В	С	А	В	D	А	D	В	С	В
Page:											
1	Α									С	
2		В									
3			С			D					

- MIN: 5 faults
  - Where will D be brought in? Look for page not referenced farthest in future
- What will LRU do?
  - Same decisions as MIN here, but will not always be true!

# When will LRU perform badly?

- Consider the following: A B C D A B C D A B C D
- LRU Performs as follows (same as FIFO here):

Ref:	Α	В	С	D	Α	В	С	D	Α	В	С	D
Page:												
1	Α			D			С			В		
2		В			А			D			С	
3			С			В			Α			D

Every reference is a page fault!

# When will LRU perform badly?


- Consider the following: A B C D A B C D A B C D
- LRU Performs as follows (same as FIFO here):

Ref:	Α	В	С	D	Α	В	С	D	Α	В	С	D
Page:												
1	Α			D			С			В		
2		В			Α			D			С	
3			С			В			Α			D

- Every reference is a page fault!
- MIN Does much better:

Ref:	Α	В	С	D	Α	В	С	D	Α	В	С	D
Page:												
1	Α									В		
2		В					С					
3			С	D								

### Graph of Page Faults Versus The Number of Frames



- One desirable property: When you add memory the miss rate drops
  - Does this always happen?
  - Seems like it should, right?
- No: Bélády's anomaly
  - Certain replacement algorithms (FIFO) don't have this obvious property!

### Adding Memory Doesn't Always Help Fault Rate

- Does adding memory reduce number of page faults?
  - Yes for LRŬ and MIN
  - Not necessarily for FIFO! (Called Bélády's anomaly)

Ref: Page:	Α	В	С	D	Α	В	E	Α	В	С	D	E
1	Α			D			Е					
2		В			Α					С		
3			С			В					D	
Ref: Page:	Α	В	С	D	Α	В	Е	Α	В	С	D	Е
1	Α						Е				D	
2		В						Α				Е
3			С						В			
4				D						С		

- After adding memory:
  - With FIFO, contents can be completely different
  - In contrast, with LRU or MIN, contents of memory with X pages are a subset of contents with X+1 Page

# Implementing LRU

- Perfect:
  - Timestamp page on each reference
  - Keep list of pages ordered by time of reference
  - Too expensive to implement in reality for many reasons
- Clock Algorithm: Arrange physical pages in circle with single clock hand
  - Approximate LRU (approximation to approximation to MIN)
  - Replace an old page, not the oldest page
- Details:
  - Wardware "use" bit per physical page:
    - Hardware sets use bit on each reference
    - If use bit is not set, means not referenced in a long time
  - On page fault:
    - Advance clock hand (not real time)
    - Check use bit:  $1 \rightarrow$  used recently; clear and leave alone  $0 \rightarrow$  selected candidate for replacement
  - Will always find a page or loop forever?
    - Even if all use bits set, will eventually loop around ⇒ FIFO

# Clock Algorithm: Not Recently Used



#### Single Clock Hand:

Advances only on page fault!
Check for pages not used recently
Mark pages as not used recently



- What if hand moving slowly?
  - Good sign or bad sign?
    - Not many page faults and/or find page quickly
- What if hand is moving quickly?
  - Lots of page faults and/or lots of reference bits set
- One way to view clock algorithm:
  - © Crude partitioning of pages into two groups: young and old
  - Why not partition into more than 2 groups?

# Nth Chance version of Clock Algorithm

- Nth chance algorithm: Give page N chances
  - OS keeps counter per page: # sweeps
  - On page fault, OS checks use bit:
    - 1  $\rightarrow$  clear use and also clear counter (used in last sweep)
    - $0 \rightarrow$  increment counter; if count=N, replace page
  - Means that clock hand has to sweep by N times without page being used before page is replaced
- How do we pick N?
  - Why pick large N? Better approximation to LRU
    - If N ~ 1K, really good approximation
  - Why pick small N? More efficient
    - Otherwise might have to look a long way to find free page
- What about dirty pages?
  - Takes extra overhead to replace a dirty page, so give dirty pages an extra chance before replacing?
  - Common approach:
    - Clean pages, use N=1
    - Dirty pages, use N=2 (and write back to disk when N=1)

# Demand Paging (more details)

- Does software-loaded TLB need use bit? Two Options:
  - Nardware sets use bit in TLB; when TLB entry is replaced, software copies use bit back to page table
  - Software manages TLB entries as FIFO list; everything not in TLB is Second-Chance list, managed as strict LRU

#### Core Map

- $\diamond$  Page tables map virtual page  $\rightarrow$  physical page
- Do we need a reverse mapping (i.e. physical page → virtual page)?
  - Yes. Clock algorithm runs through page frames. If sharing, then multiple virtual-pages per physical page
  - Can't push page out to disk without invalidating all PTEs

# Allocation of Page Frames (Memory Pages)

- How do we allocate memory among different processes?
  - Does every process get the same fraction of memory? Different fractions?
  - Should we completely swap some processes out of memory?
- Each process needs minimum number of pages
  - Want to make sure that all processes that are loaded into memory can make forward progress
- Possible Replacement Scopes:
  - Global replacement process selects replacement frame from set of all frames; one process can take a frame from another
  - Local replacement each process selects from only its own set of allocated frames

# Fixed/Priority Allocation

- Equal allocation (Fixed Scheme):
  - Every process gets same amount of memory
  - $\bullet$  Example: 100 frames, 5 processes  $\rightarrow$  process gets 20 frames
- Proportional allocation (Fixed Scheme)
  - Allocate according to the size of process
  - Computation proceeds as follows:

$$s_i$$
 = size of process  $p_i$  and  $S = \sum s_i$   
 $m$  = total number of frames

$$a_i$$
 = allocation for  $p_i = \frac{S_i}{S} \times m$ 

- Priority Allocation:
  - Proportional scheme using priorities rather than size
    - Same type of computation as previous scheme
  - ightharpoonup Possible behavior: If process  $p_i$  generates a page fault, select for replacement a frame from a process with lower priority number
- Perhaps we should use an adaptive scheme instead???
  - What if some application just needs more memory?

### Summary

- Replacement policies
  - FIFO: Place pages on queue, replace page at end
  - MIN: Replace page that will be used farthest in future
  - LRU: Replace page used farthest in past
- Clock Algorithm: Approximation to LRU
  - Arrange all pages in circular list
  - Sweep through them, marking as not "in use"
  - If page not "in use" for one pass, then can replace
- Nth-chance clock algorithm: Another approximate LRU
  - Give pages multiple passes of clock hand before replacing

# Thank You!