# Wizard Pseudo Machine Volume One, Programmer's Guide, revision 0.0.10

Tuomo Petteri Venäläinen

April 30, 2013

# Contents

Ι	$\mathbf{Pr}$	eface			5			
1	Notes 7							
2	Cha	nges			9			
П	P	seudo	o Machine		11			
3	Arc	hitectı	ure		13			
	3.1	Memo	ory Map		14			
4	Inst	ructio	n Set		15			
	4.1	Instru	ction Reference		15			
		4.1.1	Instructions and Flags		15			
			4.1.1.1 Instruction Table		17			
		4.1.2	Hooks		18			
			4.1.2.1 Hook Interface		18			
		4.1.3	I/O		18			
	4.2	Machi	ne Operations		19			
	4.3		ence		20			
		4.3.1	Opcode Format		20			
		4.3.2	Instruction Set		21			
			4.3.2.1 Cheat Sheet		23			
5	Ass	embly			<b>25</b>			
	5.1	•	x		25			
	5.2		abler Directives		26			
		5.2.1	Input Directives		26			
			5.2.1.1 include		26			
			5.2.1.2 .import		27			
		5.2.2	Link Directives		27			
			5.2.2.1 .org		27			
			5.2.2.2 .space		27			
			5.2.2.3 .align		27			
		<b>500</b>	5.2.2.4 .globl		27			
		5.2.3	Data Directives		27			
			5.2.3.1 .long		27			

4 CONTENTS

		5.2.3.3 .short	8
		5.2.3.4 .asciz	8
	5.2.4	Preprocessor Directives	8
		5.2.4.1 .define	8
5.3	Input a	and Output	9
	5.3.1	Simple Program	9
5.4	Thread	$\operatorname{ds}$	9
	5.4.1	Example Program	0
5.5	Hooks		0
	5.5.1	Pre-Defined Hooks	0
	5.5.2	Hook Interface	0
	5.5.3	Example Program	0
5.6	Interru	$_{ m ipts}$	1
	5.6.1	Break Points	1
	5.6.2	Interrupt Interface	2
	5.6.3	Keyboard Input	2
		5.6.3.1 Keyboard Interrupt Handler	2
		5.6.3.2 Keyboard Support Code	2

Part I

Preface

# Notes

#### Brief

Wizard Pseudo Machine, WPM, is a software-based virtual machine. It can be programmed in its own instruction set / assembly dialect, using AT&T syntax assembly. The incorporated assembler (**zas**) does not yet support loading pretranslated objects, but translates assembly code into bytecode before execution. This bytecode is then handled to the pseudo machine (**wpm**) to be executed.

The pseudo machine instruction set is designed to be a close match to basic operations of the C programming language, with some other typical machine operations.

#### Background and Future

Wizard Pseudo Machine project started as an attempt to create a tool for educational purposes. The machine is a virtual processor with custom instruction set that is close to existing ones; goals include making this instruction set simple, relatively complete, and useful for C language operations in case we decide to create a C compiler or code generator for an existing one.

At the time of this writing, the virtual assembler is in good shape. The assembler provides not only .include to place other files into the stream verbatim, but also .import to 'link' with other assembly files with access to their global symbols.

The project is by no means complete yet. I wish for useful libraries for audio and graphics, a useful stock 'standard' library, and lots of other things to happen in the near future. :)

# Changes

#### 0.0.10

- added section **Instruction Reference** along with CPU-flag management by some instructions
- added PDF-index and hyperlink-TOC

#### 0.0.9

• grammatical and layout corrections

# 0.0.8

- added .asciz
- added new instruction **hook** to invoke high level services; this lets us run them with native code in the virtual machine

#### 0.0.7

- adding more content
- cleaning up

#### 0.0.6

- still fixing typoes
- added a new **Architecture** Chapter

#### 0.0.5

• Added text on threading as well as a couple of assembly examples

# 0.0.4

• changed the title, made a couple of mistakes there; the book is now correctly called **Wizard Pseudo Machine** 

#### 0.0.3

• added new subsection Opcode Format

# 0.0.2

- $\bullet$  reorganised some assembly sections; added .space, .long, .short, and .byte  $\bf 0.0.1$ 
  - changed the assembler to use . include and .import instead of  $\# \mathrm{include}$  and  $\# \mathrm{import}$
  - changed the term 'argument' to 'operand' in many places in this booklet

# Part II Pseudo Machine

# Architecture

Wizard Pseudo Machine is an architecture with 32-bit machine words; however, room has been left in the implementation for 64-bit support.

The pseudo machine supports flat 4-gigabyte address space, of which some is mapped for interrupt vector, interrupt handlers, thread and interrupt stacks, graphics, and other purposes.

Native word size is **32-bit**. Words are little endian, i.e. lowest byte first.

There exists an instruction, **thr**, to start executing new threads from desired code locations in memory.

We follow the **von Neumann architecture**, so we basically have 3 abstractions; **CPU**, **memory**, and **input/output**.

The machine is a purposefully **RISC**-like **load-store** approach, meaning there is only a single load-store instruction (**mov**) that deals with memory-addressed operands.

# 3.1 Memory Map

# Notes

Address	Purpose	Brief
0	interrupt vector	interrupt handler descriptors
4096	keyboard buffer	keyboard input queue
8192	text segment	application program code (read-execute)
8192 + TEXTSIZE	data segment	program data (read-write)
DATA + DATASIZE	BSS segment	uninitialised data (runtime-allocated and zeroed)
MEMSIZE - 3.5 G	dynamic segment	free space for slab allocator
3.5 gigabytes	graphics	32-bit ARGB-format draw buffer

- $\bullet\,$  the VM's memory size is currently specified as  $\mathbf{MEMSIZE}$
- $\bullet$  thread stacks live at MEMSIZE thrid \* THRSTKSIZE, i.e. at top of 'physical' address space

# Instruction Set

The WPM instruction set was designed to resemble the C language closely, as well as support a RISC-oriented set of typical machine operations.

# 4.1 Instruction Reference

# 4.1.1 Instructions and Flags

# Operands

- $\bullet$  i stands for immediate operand
- $\bullet$  **r** stands for register operand
- ullet m stands for memory operand

# Flags

Certain instructions set bits in the machine status word (MSW). This is documented here on per-instruction basis.

- z stands for zero flag (ZF)
- c stands for carry flag (CF)
- o stands for overflow flag (OF)
- s stands for sign flag (SF)

**TODO**: stack/call conventions for certain instructions

# 4.1.1.1 Instruction Table

not and or	Operand #1 r r, i	Operand $\#2$ N/A	op1 = op1;	Flags
and or	r i	ı / ·	opt  -  opt,	Z
	1, 1	r	op2 = op2 & op1;	z
yor	r, i	r	$op2 = op2 \mid op1;$	N/A
AUI	r, i	r	$op2 = op2 \hat{o}p1;$	z
_	r, i	r	op2 = op2 * op1; (zero-fill)	z
shra	r, i	r	op2 = op2 * op1; (sign-fill)	z
shl	r, i	r	op2 = op2   op1; (ordinary) $op2 = op2   op1;$	o, c
	r, i	r	op2 = op2  ROR op1; $op2 = op2  ROR op1;$	c c
	r, i	r	op2 = op2 ROL op1; $op2 = op2 ROL op1;$	c
	r, i	N/A	op2 = op2 from op1, op1++;	0
dec		N/A N/A	op1++; op1-;	
add	r, i			0, Z
	r, i	r	op2 = op2 + op1;	0, Z
	r, i	r	op2 = op2 - op1;	s, z
cmp	r, i	r	compare two values and set flags	s, z
mul	r, i	r	op2 = op2 * op1;	0, s, z
div	r, i	r	op2 = op2 / op1;	s, z
mod	r, i	r	op2 = op2 % op1;	N/A
	r, i	N/A	branch to op1 if (CF == 0)	N/A
bnz	r, i	N/A	branch to op1 if (CF!= 0)	N/A
	r, i	N/A	branch to op1 if (SF != 0)	N/A
ble	r, i	N/A	branch to op1 if (SF $!= 0$ )    (ZF $== 0$ )	N/A
$\mathbf{bgt}$	r, i	N/A	branch to op1 if (SF != 0) && (ZF != 0)	N/A
bge	r, i	N/A	branch to op1 if (SF $!= 0$ )    (ZF $== 0$ )	N/A
bo	r, i	N/A	branch to op1 if (OF!= 0)	N/A
bno	r, i	N/A	branch to op1 if $(OF == 0)$	N/A
bc	r, i	N/A	branch to op1 if (CF!= 0)	N/A
bnc	r, i	N/A	branch to op1 if (CF == 0)	N/A
pop	N/A	N/A	pop top of stack	N/A
push	r, i	N/A	push value on stack	N/A
mov	r, i, m	r, i, m	load or store 32-bit longword	N/A
movb	r, i, m	r, i, m	load or store 8-bit byte	N/A
movw	r, i, m	r, i, m	load or store 16-bit word	N/A
	r, i	N/A	call subroutine; construct stack frame	N/A
enter	N/A	N/A	enter subroutine	N/A
leave	N/A	N/A	leave subroutine	N/A
ret	N/A	N/A	return from subroutine	N/A
lmsw	/	N/A	load machine status word	N/A
	r, i	N/A N/A	load machine status word	N/A
reset	m	N/A N/A	reset machine	N/A N/A
	m	/		/
hlt	m NT / A	N/A	halt machine	N/A
nop	N/A	N/A	no/dummy operation	N/A
brk	N/A	N/A	breakpoint	N/A
trap	N/A	N/A	software interrupt	N/A
cli	N/A	N/A	disable interrupts	N/A
sti	N/A	N/A	enable interrupts	N/A
iret	N/A	N/A	return from interrupt handler	N/A
thr	m	N/A	start new thread at address	N/A
cmpswap	m	r, i	atomic compare and swap	N/A
inb	r, i	N/A	read 8-bit byte from input port	N/A
outb	r, i	N/A	write 8-bit byte to input port	N/A
inw	r, i	N/A	read 16-bit word from input port	N/A
outw	r, i	N/A	write 16-bit word to input port	N/A
inl	r, i	N/A	read 32-bit longword from input port	N/A
outl	r, i	N/A	write 32-bit longword to input port	N/A
hook	r, i	N/A	invoke system service	N/A

#### 4.1.2 Hooks

Hooks are a simple way to request system services such as dynamic memory. At the time of writing this, the following hooks are defined.

#### **Hook List**

The **hook** instruction takes an immediate argument of the hook number; symbolic constants are listed below.

```
.define BZERO 0
.define PZERO 1
.define PALLOC 2
.define PFREE 3
.define FOPEN 4
.define FCLOSE 5
.define FREAD 6
.define FWRITE 7
.define FSEEK 8
```

#### 4.1.2.1 Hook Interface

The table below lists hooks that have been implemented and their argument registers.

Hook	r0	r1	Brief
BZERO	adr	size	set size bytes at adr to zero
PZERO	adr	size	set size bytes' worth of pages to zero at adr
PALLOC	size	N/A	allocate size bytes of dynamic memory, return address in r0
PFREE	adr	N/A	free dynamic memory at adr

# 4.1.3 I/O

#### Standard Descriptors

WPM uses standard descriptors for keyboard input as well as terminal and error output. The numerical values of these standard descriptors are declared in **<stdio.def>** as follows.

```
.define STDIN 0 // keyboard input
.define STDOUT 1 // terminal output
.define STDERR 2 // error output
```

Standard I/O is done as byte streams; for example, you can **write a character** on the user's terminal with

# 4.2 Machine Operations

The following is a C-code snippet listing machine instructions and their IDs in opcodes.

```
/* instruction set */
/* ALU instructions */
#define OPNOT
                   0x01 // 2's complement, args
#define OPAND
                   0x02 // logical AND
                   0x03 // logical OR
#define OPOR
                   0x04 // logical exclusive OR
#define OPXOR
#define OPSHR
                   0x05 // logical shift right (fill with zero)
#define OPSHRA
                   0x06 // arithmetic shift right (fill with sign)
#define OPSHL
                   0x07 // shift left (fill with zero)
#define OPROR
                   0x08 // rotate right
                   0x09 // rotate left
#define OPROL
#define OPINC
                   0x0a // increment by one
#define OPDEC
                   0x0b // decrement by one
#define OPADD
                 0x0c // addition
#define OPSUB
                 0x0d // subtraction
#define OPCMP
                   0x0e // compare
#define OPMUL
                 0x0f // multiplication
#define OPDIV
                 0x10 // division
#define OPMOD
                 0x11 // modulus
#define OPBZ
                0x12 // branch if zero
#define OPBNZ
                 0x13 // branch if not zero
#define OPBLT
                 0x14 // branch if less than
#define OPBLE
                 0x15 // branch if less than or equal to
#define OPBGT
                 0x16 // branch if greater than
#define OPBGE
                 0x17 // branch if greater than or equal to
#define OPBO
                0x18 // branch if overflow
#define OPBNO
                 0x19 // branch if no overflow
#define OPBC
                0x1a // branch if carry
#define OPBNC
                 0x1b // branch if no carry
#define OPPOP
                 0x1c // pop from stack
#define OPPUSH
                  0x1d // push to stack
#define OPMOV
                 0x1e // load/store 32-bit longword
#define OPMOVB
                   0x1f // load/store 8-bit byte
#define OPMOVW
                   0x20 // load/store 16-bit word
#define OPJMP
                   0x21 // jump to given address
                   0x22 // call subroutine
#define OPCALL
#define OPENTER
                   0x23 // subroutine prologue
#define OPLEAVE
                   0x24 // subroutine epilogue
#define OPRET
                 0x25 // return from subroutine
#define OPLMSW
                   0x26 // load machine status word
#define OPSMSW
                  0x27 // store machine status word
#define OPRESET
                   0x28 // reset into well-known state
#define OPNOP
                   0x29 // dummy operation
                   0x2a // halt execution
#define OPHLT
```

```
#define OPBRK
                  0x2b // breakpoint
#define OPTRAP
                  0x2c // trigger a trap (software interrupt)
#define OPCLI
                  0x2d // disable interrupts
#define OPSTI
                  0x2e // enable interrupts
#define OPIRET
                  0x2f // return from interrupt handler
#define OPTHR
                  0x30 // start new thread at given address
#define OPCMPSWAP 0x31 // atomic compare and swap
#define OPINB
                  0x32 // read 8-bit byte from port
#define OPOUTB
                  0x33 // write 8-bit byte to port
#define OPINW
                  0x34 // read 16-bit word
#define OPOUTW
                  0x35 // write 16-bit word
                  0x36 // read 32-bit long
#define OPINL
#define OPOUTL
                  0x37 // write 32-bit long
                  0x38 // system services
#define OPHOOK
```

# 4.3 Reference

# 4.3.1 Opcode Format

The following C structure is what the stock assembler uses for opcode output.

#### Opcode Structure

#### Notes

- inst is the instruction ID; 0 is invalid
- unit is a future unit ID; ALU, FPU, VPU (SIMD), GPU?
- reg1 and reg2 are source and destination register IDs
- $\bullet$  operation size can be calculated as op->size  $\ll 2$
- res-bits are reserved for future extensions
- args contains 0, 1, or 2 32-byte addresses or values

4.3. REFERENCE 21

# 4.3.2 Instruction Set

# **Operand Types**

- r stands for register operand
- $\bullet$  i stands for immediate operand value
- a stands for immediate direct address operand
- p stands for indirect address operand
- $\bullet$  n stands for indexed address operand
- $\bullet$  m stands for all of a, i, and n

#### Notes

- C language doesn't specify whether right shifts are arithmetic or logical
- Arithmetic right shift fills leftmost 'new' bits with the sign bit, logical shift fills with zero; left shifts are always fill rightmost bits with zero

#### Instructions

Below, I will list machine instructions and illustrate their relation to C.

# Notes

- the inb() and other functions dealing with I/O are usually declared through  $<\!sys/io.h>$ 

23

# 4.3.2.1 Cheat Sheet

C Operation	Instruction	Operands	Brief
	not	r dest	reverse all bits
&	and	r/i src, r dest	logical AND
	or	r/i src, r dest	logical OR
^	xor	r/i src, r dest	logical exclusive OR
«	shl	r/i cnt, r dest	shift left by count
<b>»</b>	shr	r/i cnt, r dest	arithmetic shift right
	shrl	r/i cnt, r dest	logical shift right
N/A	ror	r/i cnt, r dest	rotate right by count
N/A	rol	r/i cnt, r dest	rotate left by count
++	inc	r dest	increment by one
_	dec	r dest	decrement by one
+	add	r/i cnt, r dest	addition
-	sub	r/i cnt, r dest	subtraction
==, $!=$ etc.	cmp	r/i src, r dest	comparison; sets MSW-flags
*	mul	r/i src, r dest	multiplication
/	div	r/i src, r dest	division
%	mod	r/i src, r dest	modulus
==,!	bz	none	branch if zero
!=, (val)	bnz	none	branch if not zero
<	blt	none	branch if less than
<=	ble	none	branch if less than or equal
>	bgt	none	branch if greater than
>=	bge	none	branch if greater than or equal
N/A	bo	none	branch if overflow
N/A	bno	none	branch if no overflow
N/A	bc	none	branch if carry
N/A	bnc	none	branch if no carry
dest = *sp++	pop	r dest	pop from stack
$-\mathrm{sp}=\mathrm{src}$	push	r src	push onto stack
$\mathrm{dest} = \mathrm{src}$	mov	r/i/m src, $r/m$ dest	load/store longword (32-bit)
$\mathrm{dest} = \mathrm{src}$	movb	r/i/m src, $r/m$ dest	load/store byte (8-bit)
dest = src	movw	r/i/m src, $r/m$ dest	load/store word (16-bit)
N/A	jmp	r/m dest	continue execution at dest
N/A	call	a/p dest	call subroutine
N/A	enter	none	subroutine prologue
N/A	leave	none	subroutine epilogue
N/A	ret	none	return from subroutine
N/A	lmsw	r/i dest	load machine status word
N/A	smsw	m r/i~src	store machine status word
N/A	reset	none	reset machine
N/A	nop	none	no operation
N/A	hlt	none	halt machine
N/A	brk	none	breakpoint
N/A	trap	m r/i~src	trigger software interrupt
N/A	cli	none	disable interrupts
N/A	sti	none	enable interrupts
N/A	iret	none	return from interrupt handler
N/A	thr	r/i dest	start thread at dest
N/A	cmpswap	r/i src, m dest	atomic compare and swap
inb()	inb	r/i src	read byte (8-bit)
outb()	outb	r/i src, r/i dest	write byte (8-bit)
inw()	inw	r/i src	read word (16-bit)
outw()	outw	r/i src, r/i dest	write word (16-bit)
$\operatorname{inl}()$	inl	r/i src	read longword (32-bit)
outl()	outl	r/i src, r/i dest	write longword (32-bit)
hook()	hook	r1 cmd, r2 arg	system service

# Assembly

# 5.1 Syntax

#### AT&T Syntax

We use so-called AT&T-syntax assembly. Perhaps the most notorious difference from Intel-syntax is the operand order; AT&T lists the source operand first, destination second, whereas Intel syntax does it vice versa.

#### Symbol Names

Label names must start with an underscore or a letter; after that, the name may contain underscores, letters, and digits. Label names end with a ':', so like

```
value: .long 0xb4b5b6b7
```

would declare a longword value at the address of value.

#### Instructions

The instruction operand order is source first, then destination. For example,

```
mov 8(%r0), val
```

would store the value from address  ${\bf r0}$  +  ${\bf 8}$  to the address of the label  ${\bf val}$ .

#### **Operands**

Register operand names are prefixed with a '%. Immediate constants and direct addresses are prefixed with a textbf\$'. Label addresses are referred to as their names without prefixes.

The assembler supports simple preprocessing (of constant-value expressions), so it is possible to do things such as

```
.define FLAG1 0x01
.define FLAG2 0x02
mov $(FLAG1 | FLAG2), %r1
```

#### Registers

Register names are prefixed with '%'; there are 16 registers r0..r15. For example,

add %r0, %r1

would add the longword in r0 to r1.

#### Direct Addressing

Direct addressing takes the syntax

mov val, %r0

which moves the longword at address val into r0.

# **Indexed Addressing**

Indexed addressing takes the syntax

mov 4(%r0), %r1

where 4 is an integral constant offset and r0 is a register name. In short, this would store the value at the address  $\mathbf{r0} + \mathbf{4}$  into r1.

#### **Indirect Addressing**

Indirect addresses are indicated with a '\*', so

mov \*%r0, %r1

would store the value from the address in the register r0 into register r1, whereas

mov \*val, %r0

would move the value **pointed to by val** into r0.

Note that the first example above was functionally equivalent with

mov (%r0), %r1

#### Immediate Addressing

Immediate addressing takes the syntax

mov \$str, %r0

which would store the address of str into r0.

# 5.2 Assembler Directives

# 5.2.1 Input Directives

#### **5.2.1.1** .include

The .include directive takes the syntax

.include <file.asm>

to insert file.asm into the translation stream verbatim.

#### 5.2.1.2 .import

The .import directive takes the syntax

```
.import <file.asm>
```

or

```
.import <file.obj>
```

to import foreign assembly or object files into the stream. **Note** that only symbols declared with **.globl** will be made globally visible to avoid namespace pollution.

#### 5.2.2 Link Directives

#### 5.2.2.1 .org

The .org directive takes a single argument and sets the linker location address to the given value.

#### 5.2.2.2 .space

The .space directive takes a single argument and advances the link location address by the given value.

# 5.2.2.3 .align

The .align directive takes a single argument and aligns the next label, data, or instruction to a boundary of the given size.

# 5.2.2.4 .globl

The .globl directive takes one or several symbol names arguments and declares the symbols to have global visibility (linkage).

#### 5.2.3 Data Directives

#### 5.2.3.1 .long

.long takes any number of arguments and declares in-memory 32-bit entities.

### 5.2.3.2 .byte

.byte takes any number of arguments and declares in-memory 8-bit entities.

#### 5.2.3.3 .short

.short takes any number of arguments and declares in-memory 16-bit entities.

#### 5.2.3.4 .asciz

.asciz takes a C-style string argument of characters enclosed within double quotes ('"'). Escape sequences '\n' (newline), '\t' (tabulator), and '\r' (carriage return) are supported.

# 5.2.4 Preprocessor Directives

#### **5.2.4.1** .define

.define lets one declare symbolic names for constant (numeric) values. For example, if you have

#### <hook.def>

```
.define PZERO 0
.define PALLOC 1
.define PFREE 2
```

you can then use the symbolic names like

```
.include <hook.def>
.import <bzero.asm>
```

#### memalloc:

```
mov $16384, %r0 hook $PALLOC mov %r0, ptr ret
```

#### memzero:

mov ptr, %r0 mov \$4096, %r1 hook \$PZER0 ret

#### memfree:

mov ptr, %r0 hook \$PFREE

ret

#### \_start:

call memalloc
call memzero
call memfree
hlt

ptr: .long 0x00000000

# 5.3 Input and Output

The pseudo machine uses some predefined ports for keyboard and console  ${\rm I/O}.$  The currently predefined ports are

Port	Use	Notes
0x00	keyboard input	interrupt-driven
0x01	console output	byte stream
0x02	error output	directed to console by default

# 5.3.1 Simple Program

The following code snippet prints the string  $\ddot{h}$ ello $\ddot{+}$  a newline to the console. Note that the string is saved using the standard C convention of NUL-character termination.

msg:	.asciz	z "hello\n"
.align	4	
_start:		
	mov	\$msg, %r0
	movb	*%r0, %r1
	mov	\$0x01, %r2
	cmp	\$0x00, %r1
	bz	done
loop:		
	inc	%r0
	outb	%r1, %r2
	movb	*%r0, %r1
	cmp	\$0x00, %r1
	bnz	loop
done:		
	h1t	

# 5.4 Threads

Wizard Pseudo Machine supports hardware threads with the **thr** instruction. It takes a single argument, which specifies the new execution start address; function arguments should be passed in registers.

# 5.4.1 Example Program

The following piece of code shows simple utilisation of threads.

# 5.5 Hooks

Hooks exist to provide system services. Hooks invoke native code in the virtual machine to do things such as manage memory and I/O.

# 5.5.1 Pre-Defined Hooks

Number	Name	Purpose
0x00	PZERO	zero given number of pages at given address
0x01	PALLOC	allocate given number of bytes from dynamic segment
0x01	PFREE	free region at given address

#### 5.5.2 Hook Interface

Hook **parameters** are passed **in registers**. Hook **return value** is stored **in r0**. Here is the current interface definition.

- PZERO takes two arguments; destination address in r0, and region size (in bytes) in r1. PZERO returns nothing.
- PALLOC takes one argument; allocation size in r0. PALLOC returns allocated address or zero on failure.
- PFREE takes one argument; allocation address in r0. PFREE returns nothing.

#### 5.5.3 Example Program

The following programs uses hooks to accomplish 3 tasks: allocate 16384 bytes of memory, zero it, and finally free it. In reality this alone is useless, but it serves as an example.

```
.import <bzero.asm>
alloc:
         $16384, %r0
{\tt mov}
hook
         %r0, ptr
mov
ret
zero:
         ptr, %r0
mov
         $16384, %r1
{\tt mov}
hook
ret
free:
mov ptr, %r0
hook $2
ret
_start:
call
         alloc
call
         zero
call
         free
hlt
ptr:
         .long
                   0x00000000
                   4096, 0xff
_foo:
         .space
```

# 5.6 Interrupts

Software- and CPU-generated interrupts are often refered to as **traps**. I call those and hardware-generated **interrupt requests** interrupts, collectively.

# 5.6.1 Break Points

The **brk** instruction triggers a breakpoint interrupt. The default action is to print a stack trace and continue execution.

The **use** of brk is simple; just use the zero-operand instruction in your assembly file:

brk ; trigger breakpoint

# 5.6.2 Interrupt Interface

The lowest page (4096 bytes) in virtual machine address space contains the **interrupt vector**, i.e. a table of interrupt handler addresses to trigger them.

Interrupt handler invokations only push the **program counter** and **old frame pointer**, so you need to reserve the registers you use manually. This is so interrupts could be as little overhead as possible to handle.

# 5.6.3 Keyboard Input

In order to read keyboard input without polling, we need to hook the **interrupt 0**. This is done in two code modules; an interrup handler as well as other support code.

I will illustrate the interrupt handler first.

#### 5.6.3.1 Keyboard Interrupt Handler

TODO: example interrupt handler

#### 5.6.3.2 Keyboard Support Code

TODO: queue keypresses in 16-bit values; 32-bit if full Unicode requested.