Wizard Pseudo Machine Volume One, Programmer's Guide, revision 0.0.8

Tuomo Petteri Venäläinen

July 15, 2012

Contents

4 CONTENTS

Part I

Preface

Background and Future

Wizard Pseudo Machine project started as an attempt to create a tool for educational purposes. The machine is a virtual processor with custom instruction set that is close to existing ones; goals include making this instruction set simple, relatively complete, and be useful for C language operations in case someone wants to create a C compiler or code generator for an existing one.

At the time of this writing, the virtual assembler is in good shape. The assembler provides not only .include to place other files into the stream verbatim, but also .import to 'link' with other assembly files with access to their global symbols.

The project is by no means complete yet. I wish for useful libraries for audio and graphics, a useful stock 'standard' library, and lots of other things to happen in the near future. :)

Changes

0.0.8

- \bullet added .asciz
- added new instruction **hook** to invoke high level services; this lets us run them with native code in the virtual machine

0.0.7

- adding more content
- cleaning up

0.0.6

- still fixing typoes
- added a new Architecture Chapter

0.0.5

• Added text on threading as well as a couple of assembly examples

0.0.4

• changed the title, made a couple of mistakes there; the book is now correctly called **Wizard Pseudo Machine**

0.0.3

• added new subsection Opcode Format

0.0.2

 \bullet reorganised some assembly sections; added .space, .long, .short, and .byte

0.0.1

- changed the assembler to use . include and .import instead of $\# \mathrm{include}$ and $\# \mathrm{import}$
- changed the term 'argument' to 'operand' in many places in this booklet

Part II Pseudo Machine

Architecture

The pseudo machine supports flat 4-gigabyte address space, of which some is mapped for interrupt vector, interrupt handlers, thread and interrupt stacks, graphics, and other purposes.

Native word size is 32-bit. Words are little endian, i.e. lowest byte first.

There exists an instruction, **thr**, to start executing new threads at the desired locations in memory.

We follow the **von Neumann architecture**, so we basically have 3 abstraction; CPU, memory, and input/output.

The machine is a purposefully **RISC**-like load-store approach, meaning there is only a single load-store instruction (**mov**) that deals with memory addressed operands.

3.1 Memory Map

Notes

- \bullet the VM's memory size is currently specified as $\mathbf{MEMSIZE}$
- ullet thread stacks live at MEMSIZE thrid * THRSTKSIZE

Address	Purpose	Brief
0	interrupt vector	interrupt handler function pointers
4096	keyboard buffer	keyboard input queue
8192	text segment	application program code (read-execute)
8192 + TEXTSIZE	data segment	program data (read-write)
DATA + DATASIZE	BSS segment	uninitialised data (runtime-allocated and zeroed)
MEMSIZE - 3.5 G	dynamic segment	free space for slab allocator
3.5 gigabytes	graphics	32-bit ARGB-format draw buffer

Instruction Set

4.1 Machine Operations

The following is a C-code snippet listing machine instructions and their IDs in opcodes.

```
#define OPNOT
                  0x01 // 2's complement
#define OPAND
                  0x02 // logical AND
#define OPOR
                  0x03 // logical OR
#define OPXOR
                  0x04 // logical exclusive OR
#define OPSHL
                  0x05 // shift left (fill with zero)
#define OPSHR
                  0x06 // arithmetic shift right (fill with sign)
#define OPSHRL
                  0x07 // logical shift right (fill with zero)
#define OPROR
                  0x08 // rotate right
#define OPROL
                  0x09 // rotate left
#define OPINC
                  0x0a // increment by one
#define OPDEC
                  0x0b // decrement by one
                  0x0c // addition
#define OPADD
                  0x0d // subtraction
#define OPSUB
#define OPCMP
                  0x0e // compare
#define OPMUL
                  0x0f // multiplication
#define OPDIV
                  0x10 // division
#define OPMOD
                  0x11 // modulus
#define OPBZ
                  0x12 // branch if zero
                  0x13 // branch if not zero
#define OPBNZ
#define OPBLT
                  0x14 // branch if less than
#define OPBLE
                  0x15 // branch if less than or equal to
#define OPBGT
                  0x16 // branch if greater than
#define OPBGE
                  0x17 // branch if greater than or equal to
#define OPBO
                  0x18 // branch if overflow
#define OPBNO
                  0x19 // branch if no overflow
#define OPBC
                  0x1a // branch if carry
#define OPBNC
                  0x1b // branch if no carry
#define OPPOP
                  0x1c // pop from stack
```

```
#define OPPUSH
                      0x1d // push to stack
                      0x1e // load/store 32-bit longword
#define OPMOV
#define OPMOVB
                      0x1f // load/store 8-bit byte
                      0x20 // load/store 16-bit word
#define OPMOVW
#define OPJMP
                      0x21 // jump to given address
#define OPCALL
                      0x22 // call subroutine
                      0x23 // subroutine prologue
#define OPENTER
                      0x24 // subroutine epilogue
#define OPLEAVE
#define OPRET
                      0x25 // return from subroutine
#define OPLMSW
                      0x26 // load machine status word
                      0x27 // store machine status word
#define OPSMSW
#define OPRESET
                      0x28 // reset into well-known state
#define OPNOP
                      0x29 // dummy operation
#define OPHLT
#define OPBRK
#define OPTRAP
#define OPHLT
                      0x2a // halt execution
                      0x2b // breakpoint
                     0x2c // trigger a trap (software interrupt)
#define OPIRET
#define OPTHR
                      0x2d // return from interrupt handler
#define OPTHR
                     0x2e // start new thread at given address
#define OPCMPSWAP 0x2f // atomic compare and swap
#define OPINB
                     0x30 // read 8-bit byte from port
#define OPOUTB Ox31 // write 8-bit byte 1
#define OPINW Ox32 // read 16-bit word
#define OPOUTW Ox33 // write 16-bit word
#define OPINL Ox34 // read 32-bit long
#define OPOUTL Ox35 // write 32-bit long
                      0x31 // write 8-bit byte to port
```

4.2 Reference

4.2.1 Opcode Format

The following C structure is what the stock assembler uses for opcode output.

Opcode Structure

```
struct wpmopcode {
                  : 8; // instruction ID
   unsigned inst
   unsigned unit
                  : 2; // unit ID
   unsigned arg1t
                  : 3; // argument #1 type
   unsigned arg2t : 3;
                          // argument #2 type
   unsigned reg2
                  : 6; // register #2 ID + addressing flags
   unsigned size
                  : 2;
                         // 1...3, shift count
   unsigned res
                  : 2;
                          // reserved
   int32_t args[2];
} __attribute__ ((__packed__));
```

Notes

• inst is the instruction ID; 0 is invalid

4.2. REFERENCE 17

- unit is a future unit ID; ALU, FPU, VPU (SIMD), GPU?
- reg1 and reg2 are source and destination register IDs
- ullet operation size can be calculated as op->size $\ll 2$
- res-bits are reserved for future extensions
- args contains 0, 1, or 2 32-byte addresses or values

4.2.2 Instruction Set

Operand Types

- r stands for register operand
- i stands for immediate operand value
- a stands for immediate direct address operand
- p stands for indirect address operand
- n stands for indexed address operand
- m stands for all of a, i, and n

Notes

- C language doesn't specify whether right shifts are arithmetic or logical
- Arithmetic right shift fills leftmost 'new' bits with the sign bit, logical shift fills with zero; left shifts are always fill rightmost bits with zero

Instructions

Below, I will list machine instructions and illustrate their relation to C.

Notes

 the inb() and other functions dealing with I/O are usually declared through <sys/io.h>

C Operation	Instruction	Operands	Brief
	not	r dest	reverse all bits
&	and	r/i src, r dest	logical AND
	or	r/i src, r dest	logical OR
^	xor	r/i src, r dest	logical exclusive OR
«	shl	r/i cnt, r dest	shift left by count
»	shr	r/i cnt, r dest	arithmetic shift right
	shrl	r/i cnt, r dest	logical shift right
N/A	ror	r/i cnt, r dest	rotate right by count
N/A	rol	r/i cnt, r dest	rotate left by count
++	inc	r dest	increment by one
	dec	r dest	decrement by one
+	add	r/i cnt, r dest	addition
_	sub	1 '	subtraction
- 1 ata		r/i cnt, r dest	
==, != etc.	cmp	r/i src, r dest	comparison; sets MSW-flags
	mul	r/i src, r dest	multiplication
/	div	r/i src, r dest	division
%	mod	r/i src, r dest	modulus
==,!	bz	none	branch if zero
:=, (val)	bnz	none	branch if not zero
<	blt	none	branch if less than
<=	ble	none	branch if less than or equal
>	bgt	none	branch if greater than
>=	bge	none	branch if greater than or equal
N/A	bo	none	branch if overflow
N/A	bno	none	branch if no overflow
N/A	bc	none	branch if carry
N/A	bnc	none	branch if no carry
$\det = *sp++$	pop	r dest	pop from stack
$-\mathrm{sp} = \mathrm{src}$	push	r src	push onto stack
dest = src	mov	r/i/m src, r/m dest	load/store longword (32-bit)
dest = src	movb	r/i/m src, r/m dest	load/store byte (8-bit)
dest = src	movw	r/i/m src, r/m dest	load/store word (16-bit)
N/A	jmp	r/m dest	continue execution at dest
N/A	call	a/p dest	call subroutine
1 '			subroutine prologue
N/A	enter	none	
N/A	leave	none	subroutine epilogue
N/A	ret	none	return from subroutine
N/A	lmsw	r/i dest	load machine status word
N/A	smsw	r/i src	store machine status word
N/A	reset	none	reset machine
N/A	nop	none	no operation
N/A	hlt	none	halt machine
N/A	brk	none	breakpoint
N/A	trap	r/i src	trigger software interrupt
N/A	cli	none	disable interrupts
N/A	sti	none	enable interrupts
N/A	iret	none	return from interrupt handler
N/A	thr	r/i dest	start thread at dest
N/A	cmpswap	r/i src, m dest	atomic compare and swap
inb()	inb	r/i src	read byte (8-bit)
outb()	outb	r/i dest	write byte (8-bit)
inw()	inw	r/i src	read word (16-bit)
outw()	outw	r/i dest	write word (16-bit)
inl()	inl	r/i src	read longword (32-bit)
outl()	outl	r/i dest	write longword (32-bit)
Juin()	Juu	1/1 (105)	wine longword (32-bit)

Assembly

5.1 Syntax

AT&T

We use so-called AT&T-syntax assembly. Perhaps the most notorious difference from Intel-syntax is the operand order; AT&T lists the source operand first, destination second, whereas Intel syntax does it vice versa.

Symbol Names

Label names must start with an underscore or a letter; after that, the name may contain underscores, letters, and digits. Label names end with a ':', so like

value: .long 0xb4b5b6b7

would declare a longword value at the address of value.

Instructions

The instruction operand order is source first, then destination. For example,

mov 8(%r0), val

would store the value from address r0 + 8 to the address of the label val.

Operands

Register operand names are prefixed with a '%. Immediate constants and direct addresses are prefixed with a textbf\$'. Label addresses are refered to as their names without prefixes.

Registers

Register names are prefixed with '%'; there are 16 registers r0..r15. For example,

add %r0, %r1

would add the longword in r0 to r1.

Direct Addressing

Direct addressing takes the syntax

```
mov val, %r0
```

which moves the longword at address val into r0.

Indexed Addressing

Indexed addressing takes the syntax

```
mov 4(%r0), %r1
```

where 4 is an integral constant offset and r0 is a register name. In short, this would store the value at the address $\mathbf{r0} + \mathbf{4}$ into r1.

Indirect Addressing

Indirect addresses are indicated with a '*', so

```
mov *%r0, %r1
```

would store the value from the address in the register r0 into register r1, whereas

```
mov *val, %r0
```

would move the value **pointed to by val** into r0.

Note that the first example above was functionally equivalent with

```
mov (%r0), %r1
```

Immediate Addressing

Immediate addressing takes the syntax

```
mov $str, %r0
```

which would store the address of str into r0.

5.2 Assembler Directives

5.2.1 Input Directives

5.2.1.1 .include

The .include directive takes the syntax

```
.include <file.asm>
```

to insert file.asm into the translation stream verbatim.

5.2.1.2 .import

The .import directive takes the syntax

```
.import <file.asm>
```

or

.import <file.obj>

to import foreign assembly or object files into the stream. **Note** that only symbols declared with **.globl** will be made globally visible to avoid namespace pollution.

5.2.2 Link Directives

5.2.2.1 .org

The .org directive takes a single argument and sets the linker location address to the given value.

5.2.2.2 .space

The .space directive takes a single argument and advances the link location address by the given value.

5.2.2.3 .align

The **.align** directive takes a single argument and aligns the next label, data, or instruction to a boundary of the given size.

5.2.2.4 .globl

The .globl directive takes one or several symbol names arguments and declares the symbols to have global visibility (linkage).

5.2.3 Data Directives

5.2.3.1 .long

.long takes any number of arguments and declares in-memory 32-bit entities.

5.2.3.2 .byte

.byte takes any number of arguments and declares in-memory 8-bit entities.

5.2.3.3 .short

.short takes any number of arguments and declares in-memory 16-bit entities.

5.2.3.4 .asciz

.asciz takes a C-style string argument of characters enclosed within double quotes ('"'). Escape sequences '\n' (newline), '\t' (tabulator), and '\r' (carriage return) are supported.

5.2.4 Preprocessor Directives

5.2.4.1 .define

.define lets one declare symbolic names for constant (numeric) values. For example, if you have

<hook.def>

```
.define PZERO 0
.define PALLOC 1
.define PFREE 2
```

you can then use the symbolic names like

```
.include <hook.def>
.import <bzero.asm>
```

memalloc:

mov \$16384, %r0 hook \$PALLOC mov %r0, ptr ret

memzero:

mov ptr, %r0 mov \$4096, %r1 hook \$PZER0

memfree:

mov ptr, %r0 hook \$PFREE

ret

ret

_start:

call memalloc
call memzero
call memfree
hlt

ptr: .long 0x00000000

5.3 Input and Output

The pseudo machine uses some predefined ports for keyboard and console ${\rm I/O}.$ The currently predefined ports are

Port	Use	Notes
0x00	keyboard input	interrupt-driven
0x01	console output	byte stream
0x02	error output	directed to console by default

5.3.1 Simple Program

The following code snippet prints the string \ddot{h} ello $\ddot{+}$ a newline to the console. Note that the string is saved using the standard C convention of NUL-character termination.

```
msg:
             .asciz "hello\n"
.align
_start:
                    $msg, %r0
        mov
                    *%r0, %r1
        movb
                    $0x01, %r2
        mov
                    $0x00, %r1
        cmp
        bz
                    done
loop:
                    %r0
        inc
                    %r1, %r2
        outb
        movb
                    *%r0, %r1
                    $0x00, %r1
        cmp
        bnz
                    loop
done:
        hlt
```

5.4 Threads

Wizard Pseudo Machine supports hardware threads with the **thr** instruction. It takes a single argument, which specifies the new execution start address; function arguments should be passed in registers.

5.4.1 Example Program

The following piece of code shows simple utilisation of threads.

```
.import <bzero.asm>
```

5.5 Hooks

Hooks exist to provide system services. Hooks invoke native code in the virtual machine to do things such as manage memory and I/O.

5.5.1 Pre-Defined Hooks

Number	Name	Purpose
0x00	PZERO	zero given number of pages at given address
0x01	PALLOC	allocate given number of bytes from dynamic segment
0x01	PFREE	free region at given address

5.5.2 Hook Interface

Hook **parameters** are passed **in registers**. Hook **return value** is stored **in r0**. Here is the current interface definition.

- PZERO takes two arguments; destination address in r0, and region size (in bytes) in r1. PZERO returns nothing.
- PALLOC takes one argument; allocation size in r0. PALLOC returns allocated address or zero on failure.
- PFREE takes one argument; allocation address in r0. PFREE returns nothing.

5.5.3 Example Program

The following programs uses hooks to accomplish 3 tasks: allocate 16384 bytes of memory, zero it, and finally free it. In reality this alone is useless, but it serves as an example.

```
.import <bzero.asm>
alloc:
mov $16384, %r0
hook $1
mov %r0, ptr
```

```
ret
zero:
mov
        ptr, %r0
mov
        $16384, %r1
hook
ret
free:
mov ptr, %r0
hook $2
ret
_start:
call
        alloc
call
        zero
call
        free
hlt
                  0x0000000
ptr:
        .long
                  4096, 0xff
_foo:
        .space
```

5.6 Interrupts

Software- and CPU-generated interrupts are often referred to as **traps**. I call those and hardware-generated **interrupt requests** interrupts, collectively.

5.6.1 Break Points

The \mathbf{brk} instruction triggers a breakpoint interrupt. The default action is to print a stack trace and continue execution.

The **use** of brk is simple; just use the zero-operand instruction in your assembly file:

brk; trigger breakpoint

5.6.2 Interrupt Interface

The lowest page (4096 bytes) in virtual machine address space contains the **interrupt vector**, i.e. a table of interrupt handler addresses to trigger them.

Interrupt handler invokations only push the **program counter** and **old frame pointer**, so you need to reserve the registers you use manually. This is so interrupts could be as little overhead as possible to handle.

5.6.3 Keyboard Input

In order to read keyboard input without polling, we need to hook the **interrupt 0**. This is done in two code modules; an interrup handler as well as other support code.

I will illustrate the interrupt handler first.

5.6.3.1 Keyboard Interrupt Handler

TODO: example interrupt handler

5.6.3.2 Keyboard Support Code

TODO: queue keypresses in 16-bit values; 32-bit if full Unicode requested.