
# **Chapter 8: Main Memory**





## **Chapter 8: Memory Management**

- Background
- Swapping
- Contiguous Memory Allocation
- Segmentation
- Paging
- Structure of the Page Table
- Example: The Intel 32 and 64-bit Architectures
- Example: ARM Architecture





## **Objectives**

- To provide a detailed description of various ways of organizing memory hardware
- To discuss various memory-management techniques, including paging and segmentation
- To provide a detailed description of the Intel Pentium, which supports both pure segmentation and segmentation with paging







#### **Background**

- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are the only storage CPU can access directly
- Memory unit only sees a stream of addresses + read requests, or address + data and write requests
- Register access in one CPU clock (or less)
- Main memory can take many cycles, causing CPU stall
- Cache sits between main memory and CPU registers
- Protection of memory required to ensure correct operation
  - correct operation to protect the operating system from access by user processes
  - protect user processes from one another









The **base register** holds the smallest legal physical memory address; the **limit register** specifies the size of the range.

Any attempt by a program executing in user mode to access operatingsystem memory or other users' memory results in a trap to the Figure 8.1 A base and a limit register define a logical address space operating system, which treats the attempt as a fatal error






#### **Multistep Processing of a User Program**



#### **Source and Object Code**








#### **Address Binding**

- Programs on disk, ready to be brought into memory to execute form an input queue.
- Although the address space of computer starts at 00000, first address of user process need not be 00000.
  - Source code addresses usually symbolic addresses
  - Compiled code will bind symbolic addresses to relocatable addresses
    - i.e. "14 bytes from beginning of this module"
  - Linker or loader will bind relocatable addresses to absolute addresses
    - i.e. 74014
- address generated by the CPU is commonly referred to as a logical address.
- address seen by memory is commonly referred to as a physical address.



#### **Binding of Instructions and Data to Memory**

- Address binding of instructions and data to memory addresses can happen at three different stages
  - Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes
  - Load time: If memory location is not known a priori, compiler generates relocatable code. In this case final binding is delayed until load time.
  - **Execution time**: Binding delayed until run time.
  - In contrast to absolute code, which contains fixed memory addresses for the program's instructions and data, relocatable code uses relative memory addressing or symbolic references to access memory locations. This allows the code to be loaded into any memory location without requiring any modification to the code itself.




## Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
  - Logical address generated by the CPU; also referred to as virtual address
  - Physical address address seen by the memory unit
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program





#### **Hardware Support for Relocation and Limit Registers**



This protection must be provided by the hardware because the operating system doesn't usually intervene between the CPU and its memory accesses (because of the resulting performance penalty).






## **Memory-Management Unit (MMU)**

- Hardware that at run time maps virtual to physical address
- Many methods possible
- To start, consider simple scheme where the value in the relocation register is added to every address generated by a user process at the time it is sent to memory
  - Base register now called relocation register
  - 8086 used 4 relocation registers
- The user program deals with logical addresses; it never sees the real physical addresses
- mapping from virtual to physical addresses is done by a hardware called the MMU





#### **Hardware Support for Relocation and Limit Registers**








#### Dynamic relocation using a relocation register

#### A simple MMU mapping scheme







## **Dynamic Loading**

- Entire program and all data need not be in memory for execution
- For better memory utilization; use dynamic loading
- With dynamic loading, a routine is not loaded until it is called.
- The main program is loaded into memory and is executed.
- When a routine needs to call another routine, the calling routine first checks to see whether the other routine has been loaded. If it has not, the relocatable linking-loader is called to load the desired routine into memory.
- The advantage of dynamic loading is that an unused routine is never loaded.
  - Relocatable linking- loader: is a type of loader that combines the functions of both linking and loading

The relocatable linking-loader adjusts the memory addresses in the program so that it can be correctly executed from whatevers memory location it is loaded into Operating System Concepts – 9th Edition 8.14



#### **Dynamic Linking**

- Static linking system libraries and program code combined by the loader into the binary program image
- Dynamic linking —linking postponed until execution time
- Small piece of code, stub, used to locate the appropriate memoryresident library routine
- Stub replaces itself with the address of the library routine, and executes the routine
- Operating system checks if routine is in processes' memory address
  - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries

```
gcc -o my_program my_program.c -static
gcc -o my_program my_program.c -lm (link dynamically the math library)
```




## **Swapping**

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution
  - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped





### **Schematic View of Swapping**



main memory





#### **Context Switch Time including Swapping**

- If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process
- Context switch time can then be very high
- 100MB process swapping to hard disk with transfer rate of 50MB/sec
  - Swap out time of 2seconds
  - Plus swap in of same sized process
  - Total context switch swapping component time of 4000ms (4 seconds)
- Can reduce if reduce size of memory swapped by knowing how much memory really being used
  - System calls to inform OS of memory use via request\_memory()—requests additional memory and release\_memory()—releases the memory that is no longer needed.





#### Contiguous Allocation

- •Main memory must support both OS and user processes
- •Limited resource, must allocate efficiently
- Contiguous allocation is one early method
- •Main memory usually into two partitions:
  - Resident operating system, usually held in low memory with interrupt vector
  - User processes then held in high memory
  - Each process contained in single contiguous section of memory






#### **Multiple-partition allocation**

- Multiple-partition allocation
  - Fixed-partition Degree of multiprogramming limited by number of partitions
  - Variable-partition sizes for efficiency (sized to a given process' needs)
  - Hole block of available memory; holes of various size are scattered throughout memory
  - When a process arrives, it is allocated memory from a hole large enough to accommodate it
  - Process exiting frees its partition, adjacent free partitions combined
  - Operating system maintains information about:
     a) allocated partitions
     b) free partitions (hole)





## **Dynamic Storage-Allocation Problem**

How to satisfy a request of size *n* from a list of free holes?

- First-fit: Allocate the *first* hole that is big enough
- Best-fit: Allocate the smallest hole that is big enough; must search entire list, unless ordered by size
  - Produces the smallest leftover hole
- Worst-fit: Allocate the *largest* hole; must also search entire list
  - Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization






#### **Fragmentation**

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous(Variable sized memory)
- Internal Fragmentation available memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used(Fixed size memory)
- Reduce external fragmentation by compaction
  - Shuffle memory contents to place all free memory together in one large block





## **Segmentation**

- Memory-management scheme that supports user view of memory
- A program is a collection of segments
  - A segment is a logical unit such as:

```
main program
```

procedure

function

method

object

local variables, global variables

common block

stack


symbol table

arrays






## User's View of a Program








## **Logical View of Segmentation**




4 2 3

physical memory space





# Example of segmentation








#### **Segmentation Architecture**

- Logical address consists of a two tuple:
  - <segment-number, offset>,
- Segment table maps two-dimensional physical addresses; each table entry has:
  - base contains the starting physical address where the segments reside in memory
  - limit specifies the length of the segment
- The segment table is thus essentially an array of base-limit register pairs.
- Segment-table base register (STBR)
- Segment-table length register (STLR)





#### **Segmentation Hardware**





8.31



## **Paging**

- Divide physical memory into fixed-sized blocks called frames
- Divide logical memory into blocks of same size called pages
- Page size=frame size
- Keep track of all free frames
- To run a program of size N pages, need to find N free frames and load program
- Set up a page table to translate logical to physical addresses





#### Paging Model of Logical and Physical Memory

frame

page 0

page 1

page 2


page 3

logical memory






# **Paging Hardware**







#### **Address Translation Scheme**


- Address generated by CPU is divided into:
  - Page number (p) used as an index into a page table which contains base address of each page in physical memory
  - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit

page number	page offset
р	d
m -n	n

For given logical address space 2<sup>m</sup> and page size 2<sup>n</sup>

8 -bits 4-bits


Logical memory





## **Paging Example**

n=2 and m=4 32-byte main memory and 4-byte pages



Page no| Frame no


page table

Logical address space 2<sup>m</sup>=16 bytes Page size=2<sup>n</sup>=4 bytes Page number is represented with m-n bits=4-2=2bits Offset is represented with n bits=2 bits

4	i j k
8	m n o p
12	
16	
20	a b c d
24	e f g h
28	



#### **Free Frames**



Before allocation

After allocation





## Paging (Cont.)

- Calculating internal fragmentation
  - Page size = 2,048 bytes
  - Process size = 72,766 bytes
  - 35 pages + 1,086 bytes (35x2048=71680)+1086
  - Internal fragmentation of 2,048 1,086 = 962 bytes
  - Worst case fragmentation = 1 frame 1 byte






#### Implementation of Page Table

- Page table is kept in main memory
- Page-table base register (PTBR) points to the page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
  - One for the page table and one for the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)





#### **Associative Memory**

- On a TLB miss, value is loaded into the TLB for faster access next time
- Associative memory parallel search


Page #	Frame #

- Address translation (p, d)
  - If p is in associative register, get frame # out
  - Otherwise get frame # from page table in memory





#### **Paging Hardware With TLB**







#### **Effective Access Time**

- Hit ratio percentage of times that a page number is found in the associative registers
- TLB hit 80%, 20ns for TLB search, 100ns for memory access, then a mapped-memory access takes 120 nanoseconds when the page number is in the TLB.
- If we fail to find the page number in the TLB (20 nanoseconds), then we must first access memory for the page table and frame number (100 nanoseconds) and then access the desired byte in memory (100 nanoseconds), for a total of 220 nanoseconds
- Effective Access Time (EAT)

$$EAT = 0.80 \times 120 + 0.20 \times 220 = 140 \text{ns}$$

For 98% hit ratio

$$EAT = 0.98 \times 120 + 0.02 \times 220 = 122 \text{ns}$$






#### **Memory Protection**


- Memory protection implemented by associating protection bit.
- Valid-invalid bit attached to each entry in the page table:
  - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
  - "invalid" indicates that the page is not in the process' logical address space
  - Or use page-table length register (PTLR)
- Any violations result in a trap to the kernel






#### Valid (v) or Invalid (i) Bit In A Page Table

valid-invalid bit









#### **Shared Pages**

#### Shared code

- Reentrant code is non-self-modifying code: it never changes during execution. Thus, two or more processes can execute the same code at the same time.
  - One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers etc)
  - Similar to multiple threads sharing the same process space

#### Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space






- If the text editor consists of 150 KB of code and 50 KB of data space, we need 8,000 KB(150\*40+50\*40) to support the 40 users.
- To support 40 users, we need only one copy of the editor (150 KB), plus 40 copies of the 50 KB of data space per user.
- The total space required is now 2150 KB(150+50\*40) instead of 8,000 KB
- Organizing memory according to pages provides numerous benefits in addition to allowing several processes to share the same physical pages





#### **Shared Pages Example**





# **End of Chapter 8**

