### Operating System Concepts

Lecture 24: Segmentation and Paging

Omid Ardakanian oardakan@ualberta.ca
University of Alberta

MWF 12:00-12:50 VVC 2 215

#### Today's class


- Memory-management strategies
  - contiguous memory allocation
  - segmentation
  - paging
- Hardware support
  - mapping tables in addition to registers

#### Segmentation

- process generates contiguous virtual addresses from 0 to MAX<sub>proc</sub>
- OS lays the process down on arbitrary size segments and hardware translates virtual addresses to physical addresses in memory
  - using a segment table that keeps track of the segment locations in memory


#### Segmentation

- process generates contiguous virtual addresses from 0 to MAX<sub>proc</sub>
- OS lays the process down on arbitrary size segments and hardware translates virtual addresses to physical addresses in memory
  - using a segment table that keeps track of the segment locations in memory
- the virtual address is identified by a pair (s, d)
  - s is the segment number
  - d is the offset within the segment



### Segmentation

- process generates contiguous virtual addresses from 0 to MAX<sub>proc</sub>
- OS lays the process down on arbitrary size segments and hardware translates virtual addresses to physical addresses in memory
  - using a segment table that keeps track of the segment locations in memory
- the virtual address is identified by a pair (s, d)
  - s is the segment number
  - d is the offset within the segment




enable sharing code and data between processes (for example when linking libraries)

# How to find addresses when segments are not allocated contiguously in memory?


add a segment table containing base & limit register values

# How to find addresses when segments are not allocated contiguously in memory?




add a segment table containing base & limit register values

## How to find addresses when segments are not allocated contiguously in memory?



add a segment table containing base & limit register values

#### Hardware support for segmentation



#### Is segmentation enough?

- segmentation leads to poor memory utilization
  - we might not use much of a large segment, but we must keep the whole thing in memory
  - suffers from external fragmentation
  - allocation/deallocation of arbitrary size segments is complex
- how can we improve memory management? using fixed-size allocation units

#### • 90/10 rule

- processes spend 90% of their time accessing 10% of their space in memory
- so keep only those parts in memory that are being used

- 90/10 rule
  - processes spend 90% of their time accessing 10% of their space in memory
  - so keep only those parts in memory that are being used
- logical memory of a process is contiguous, but pages need not be allocated contiguously in memory


#### 90/10 rule

- processes spend 90% of their time accessing 10% of their space in memory
- so keep only those parts in memory that are being used
- logical memory of a process is contiguous, but pages need not be allocated contiguously in memory
- paging eliminates external fragmentation by dividing memory into fixed-size pages
  - the getpagesize() system call returns the page size (e.g., 4096 bytes)
  - this command in linux returns the page size as well: getconf PAGESIZE

- 90/10 rule
  - processes spend 90% of their time accessing 10% of their space in memory
  - so keep only those parts in memory that are being used
- logical memory of a process is contiguous, but pages need not be allocated contiguously in memory
- paging eliminates external fragmentation by dividing memory into fixed-size pages
  - the getpagesize() system call returns the page size (e.g., 4096 bytes)
  - this command in linux returns the page size as well: getconf PAGESIZE
- paging causes internal fragmentation though
  - on average half a page is lost per process


# How to find addresses when pages are not allocated contiguously in memory?

- OS divides processes into fixed sized pages
- selectively allocates pages to page frames in memory
  - the virtual address contains the page number (p) and the page offset (d)
  - p is used as an index into the page table, allowing to extract the frame number (f)
  - the page table keeps track of the page frame in memory in which the page is located
- keeps track of free frames in a frame table which has an entry for each physical page frame




# How to find addresses when pages are not allocated contiguously in memory?

- OS divides processes into fixed sized pages
- selectively allocates pages to page frames in memory
  - the virtual address contains the page number (p) and the page offset (d)
  - p is used as an index into the page table, allowing to extract the frame number (f)
  - the page table keeps track of the page frame in memory in which the page is located
- keeps track of free frames in a frame table which has an entry for each physical page frame



#### Paging details

- page sizes (and frame sizes) are typically a power of 2 between 512 bytes and 8192 bytes per page
  - makes the translation of virtual addresses into physical addresses easier
- for example, given a memory of size 2<sup>m</sup> bytes and a page of size 2<sup>n</sup> then
  - the high order m-n bits of a virtual address select the page
  - the low order *n* bits select the offset in the page



#### Example

page 0

page 1

page 2


page 3

logical memory

a process is comprised of fixed size pages mem. size:  $65,536 = 2^{16}$  page size:  $8,196 = 2^{13}$ 

page table (page #, frame #)

page table is like a set of relocation registers, one for each frame



#### Example

page 0

page 1

page 2

page 3

logical memory

a process is comprised of fixed size pages mem. size:  $65,536 = 2^{16}$  page size:  $8,196 = 2^{13}$ 

page table (page #, frame #)

page table is like a set of relocation registers, one for each frame

> physical memory

How many bits for an address (assuming we can address 1 byte increments)?16 in this example

#### Example of address translation

- how many frames do we have? 8 frames
- what is the page size? 2<sup>13</sup> bytes
- assuming we can address 1 byte increments, how many bits for an address?
   16bits (3 bits for page table, 13 bits for offset)
- assuming we can address 1 word (4 bytes) increments, how many bits for an address?
   14bits (3 bits for page table, 11 bits for offset)

#### Calculating internal fragmentation

- recall that
  - worst-case internal fragmentation: 1 frame 1 byte
  - average-case internal fragmentation: 1/2 frame size
- let the page size be 2,048 bytes and the process size be 72,766 bytes (i.e., 35 pages + 1,086 bytes)
  - internal fragmentation of 2,048 1,086 = 962 bytes

#### Calculating internal fragmentation

- recall that
  - worst-case internal fragmentation: 1 frame 1 byte
  - average-case internal fragmentation: 1/2 frame size
- let the page size be 2,048 bytes and the process size be 72,766 bytes (i.e., 35 pages + 1,086 bytes)
  - internal fragmentation of 2,048 1,086 = 962 bytes
- can we say small frame sizes are desirable?
  - No, each page table entry takes memory to track


#### Where to store the page table?

- put it in memory?
  - page-table base register (PTBR) points to the page table
  - page-table length register (PTLR) indicates size of the page table
  - every data/instruction access requires two memory accesses: one for the page table and one for the data/instruction
- translation look-aside buffer (TLB) is a fast-lookup hardware cache in MMU (fully associative memory) that stores page numbers (key) and the frame (value) in which they are stored
  - if memory accesses have locality, address translation has locality too
  - typical TLB sizes range from 64 to 1,024 entries (TLB is small)
  - TLB is typically on chip, access time of a few nanoseconds instead of several hundred of nanoseconds for main memory

#### Paging with TLB

on a TLB miss, value is loaded into the TLB for faster access next time

- replacement policies must be considered




#### Valid/invalid bit in TLB

#### v: valid/invalid bit used for protection

 "valid" indicates that the associated page is in the process logical address space, and is thus a legal page

 "invalid" indicates that the page is not in the process logical address space



0

page 0

page 1

page 2

page 3

page 4

page 5

page n

#### Effective memory access cost with TLB

- the effective access time (EAT) if the page table is in memory? EAT =  $2 \times C_{ma}$
- the effective access time with a TLB?

$$EAT = \rho_{hit}(C_{ma} + C_{TLB}) + (1 - \rho_{hit})(2 \times C_{ma} + C_{TLB})$$

- where  $\rho_{hit}$  is the hit ratio (i.e., percentage of times that a page number is found in the TLB)
- a large TLB improves hit ratio, decreases average memory cost
- example: let  $C_{ma} = 10 \text{ns}$ ,  $C_{TLB} = 0 \text{ns}$ 
  - if  $\rho_{hit}$ =80% then EAT=12ns (20% slowdown in access time)
  - if  $\rho_{hit}$ =99% then EAT=10.1ns (1% slowdown in access time)


#### How to allocate memory when starting a process?

suppose the process needs *k* pages

- if k page frames are free, then allocate these frames to pages; otherwise, free frames that
  are no longer needed and allocate them to the process
- the OS puts each page in a frame and then puts the frame number in the corresponding entry in the page table
- OS marks all TLB entries as invalid (flushes the TLB) and starts the process

as process executes, OS loads TLB entries as each page is accessed, replacing an existing

entry if the TLB is full



after allocation

before allocation

13 page 1

14 page 0

18 page 2

20 page 3

15

16

17

19


#### What happens on a context switch?

- OS saves the PTBR value to the PCB
- OS saves the process's page table in its PCB (i.e., copying the TLB to the PCB)
- OS marks all TLB entries as invalid (i.e., flushes the TLB)
- OS restores the PTBR value of the new process
- OS restores the TLB if it was saved

### Sharing

- increases the level of multiprogramming by sharing code and data between different processes
  - shared code must be reentrant, that means the processes that are using it cannot change it
  - OS keeps track of available reentrant code in memory and reuses them if a new process requests the same program
- allows running many processes given a limited amount of memory
- sharable units: segments or pages
- paging allows sharing of memory across processes, since memory used by a process no longer needs to be contiguous

#### How to implement sharing?



### Segmentation versus paging

- paging is a big improvement over segmentation
  - eliminates the problem of external fragmentation and therefore the need for compaction
  - enables processes to run when they are only partially loaded in main memory

### Segmentation versus paging

- paging is a big improvement over segmentation
  - eliminates the problem of external fragmentation and therefore the need for compaction
  - enables processes to run when they are only partially loaded in main memory
- however, paging has its cost:
  - causes internal fragmentation
  - translating from a virtual address to a physical address is more time-consuming
    - segment table tends to be much smaller than page table
  - paging requires hardware support in the form of a TLB to be efficient enough
  - paging requires more complex OS to maintain the page table