Operating System Concepts

Lecture 19: Synchronization Primitives — Part 2

Omid Ardakanian oardakan@ualberta.ca
University of Alberta

MWF 12:00-12:50 VVC 2 215

Today's class

- Synchronization primitives
 - Semaphore
 - Monitor

Why should we really care?

```
class Account {
public:
    void deposit(int amount) {
        balance += amount;
    }
    void withdraw(int amount) {
        balance -= amount;
    }
private:
    int balance;
}
```

Why should we really care?

```
class Account {
public:
  void deposit(int amount) {
    balance += amount;
  void withdraw(int amount) {
    balance -= amount;
private:
  int balance;
```







news

Top Stories

Local

The National

Opinion

World

Canada

Politics

Indigenous

British Columbia

'You're at their mercy': customer says RBC charged him twice for Visa cheque transactions

Semaphores

- semaphores are generalized locks invented by Dijkstra in 1965
 - they are a (non-negative) integer variable that supports two **atomic** operations: wait and signal (or down and up)

Semaphores

- semaphores are generalized locks invented by Dijkstra in 1965
 - they are a (non-negative) integer variable that supports two **atomic** operations: wait and signal (or down and up)
- binary semaphore: used for mutual exclusion (just like mutex locks)
 - guarantees mutually exclusive access to a resource (i.e., only one thread/process in the critical section at a time)
 - can vary from 0 to 1; it is initialized to free (value = 1)

Semaphores

- semaphores are generalized locks invented by Dijkstra in 1965
 - they are a (non-negative) integer variable that supports two **atomic** operations: wait and signal (or down and up)
- binary semaphore: used for mutual exclusion (just like mutex locks)
 - guarantees mutually exclusive access to a resource (i.e., only one thread/process in the critical section at a time)
 - can vary from 0 to 1; it is initialized to free (value = 1)
- counting semaphore: used for conditional synchronization
 - useful when multiple units or instances of a specific resource are available
 - the semaphore is usually initialized to the number of resources
 - a process can acquire access so long as at least one unit of the resource is available

Atomic operations with semaphores

- each semaphore supports a queue of processes that are waiting to access the critical section (e.g., to check and buy milk)
- if a thread executes Wait() and the semaphore is free (non-zero), it continues executing after decrementing the semaphore's variable. But if it is not free, the OS puts the thread on the wait queue for that semaphore
- Signal() unblocks one thread on the semaphore's wait queue

Using semaphores to implement mutual exclusion

```
Semaphore milksemaphore; // suppose value is set to 1

milksemaphore.Wait()

<critical section>
milksemaphore.Signal()

accessing shared data
released after
accessing shared data
```

Implementing signal and wait by disabling interrupts

```
class Semaphore {
public:
  void Wait(Thread T);
  void Signal();
private:
  int value;
  Queue Q;
Semaphore::Semaphore(int val) {
  value = val; // initialized to the number of available resources
Semaphore::Wait(Thread T) {
  intr disable();
  value = value - 1;
  if(value < 0) { // |value| is the number of waiting threads
    queue add(Q, T);
    thread block(T);
  intr enable();
Semaphore::Signal() {
  intr disable();
  value = value + 1;
  if(value <= 0) // if there is a waiting thread
    thread unblock(queue_remove(Q));
  intr enable();
```

Implementing signal and wait by disabling interrupts

```
class Semaphore {
public:
  void Wait(Thread T);
  void Signal();
private:
  int value;
  Queue Q;
Semaphore::Semaphore(int val) {
  value = val; // initialized to the number of available resources
Semaphore::Wait(Thread T) {
  intr disable();
  value = value - 1;
  if(value < 0) { // |value| is the number of waiting threads
    queue add(Q, T);
    thread block(T);
  intr enable();
                                            can you implement these atomic
                                            operations using test_and_set?
Semaphore::Signal() {
  intr disable();
  value = value + 1;
  if(value <= 0) // if there is a waiting thread
    thread unblock(queue_remove(Q));
  intr enable();
```

			Semaphore value	Semaphore queue	Thread 1's state	Thread 2's state
			2	empty		
Thread	1:	SM.wait()	1	empty		
Thread	2:	SM.wait()	0	empty		
Thread	1:	SM.wait()	0	T1	waiting	
Thread	2:	<pre>SM.signal()</pre>	0	empty		
Thread	1:	<pre>SM.signal()</pre>	1	empty		
Thread	1:	<pre>SM.signal()</pre>	2	empty		

Suppose each thread needs two units of the available resource

			Semaphore value	Semaphore queue	Thread 1's state	Thread 2's state
			value queue		State	State
			2	empty		
Thread	1:	SM.wait()	1	empty		
Thread	2:	SM.wait()	0	empty		
Thread	1:	SM.wait()	0	T1	waiting	
Thread	2:	SM.wait()	0	T1, T2	waiting	waiting

Suppose each thread needs two units of the available resource

			Semaphore	emaphore Semaphore		Thread 2's
			value	queue	state	state
			2	empty		
Thread	1:	SM.wait()	1	empty		
Thread	2:	SM.wait()	0	empty		
Thread	1:	SM.wait()	0	T1	waiting	
Thread	2:	SM.wait()	0	T1, T2	waiting	waiting

Deadlock

			Semaphore value	Semaphore queue	Thread 1's state	Thread 2's state	Thread 3's state
			2	empty			
Thread	1:	SM.wait()	1	empty			
		SM.wait()	0	empty			
		SM.wait()	0	T2		waiting	
Thread	3:	SM.wait()	0	T2, T3		waiting	waiting
Thread	1:	SM.signal()	0	T3			waiting
Thread	1:	SM.signal()	0	empty			
Thread	3:	SM.signal()	1	empty			
Thread	2:	SM.signal()	2	empty			

 semaphore can be implemented using a count variable, a condition variable, and a mutex lock

- semaphore can be implemented using a count variable, a condition variable, and a mutex lock
- condition variables do not have any history, but semaphores do
 - on a condition variable signal if no one is waiting, the signal is a no operation
 - if a thread then does a condition. Wait, it waits
 - on a semaphore. Signal if no one is waiting, the value of the semaphore is incremented
 - if a thread then does a semaphore. Wait, then value is decremented and the thread continues

- semaphore can be implemented using a count variable, a condition variable, and a mutex lock
- condition variables do not have any history, but semaphores do
 - on a condition variable signal if no one is waiting, the signal is a no operation
 - if a thread then does a condition. Wait, it waits
 - on a semaphore. Signal if no one is waiting, the value of the semaphore is incremented
 - if a thread then does a semaphore. Wait, then value is decremented and the thread continues
- semaphore Wait and Signal are commutative, i.e., the result is the same regardless of the order of execution

- semaphore can be implemented using a count variable, a condition variable, and a mutex lock
- condition variables do not have any history, but semaphores do
 - on a condition variable signal if no one is waiting, the signal is a no operation
 - if a thread then does a condition. Wait, it waits
 - on a semaphore. Signal if no one is waiting, the value of the semaphore is incremented
 - if a thread then does a semaphore. Wait, then value is decremented and the thread continues
- semaphore Wait and Signal are commutative, i.e., the result is the same regardless of the order of execution
- condition variables are not, and as a result they must be in a critical section to access state variables and do their job

What's wrong with semaphores?

- semaphore operations can be used incorrectly by programmers
 - → two processes/threads may be in their critical sections simultaneously or may permanently block!

```
- signal(mutex) ... wait(mutex)
```

- wait(mutex) ... wait(mutex)
- omitting wait(mutex) and/or signal(mutex)

What's wrong with semaphores?

- semaphore operations can be used incorrectly by programmers
 - → two processes/threads may be in their critical sections simultaneously or may permanently block!

```
- signal(mutex) ... wait(mutex)
```

- wait(mutex) ... wait(mutex)

- omitting wait(mutex) and/or signal(mutex)

shared data

operations

initialization
code

solution? a higher-level synchronization construct

Monitors

- <u>Definition</u>: a thread-safe class that ties (private) data and methods (including the synchronization operations) together, introduced by Per Brinch Hansen in 1970s
 - guarantees mutual exclusion, i.e., only one thread may execute a given monitor method at a time
 - provides a mechanism for threads to temporarily give up exclusive access to wait for a certain condition

Monitors

- <u>Definition</u>: a thread-safe class that ties (private) data and methods (including the synchronization operations) together, introduced by Per Brinch Hansen in 1970s
 - guarantees mutual exclusion, i.e., only one thread may execute a given monitor method at a time
 - provides a mechanism for threads to temporarily give up exclusive access to wait for a certain condition
- it defines a lock and zero, one, or more condition variables for managing concurrent access to shared data
 - the lock provides mutual exclusion for shared data
 - used to ensure that only a single thread is active in the monitor at a time
 - condition variables enable threads to go to sleep inside critical sections, by releasing their lock at the same time they are put to sleep
 - used when an operation cannot complete (because the condition is not true)

Monitors


- <u>Definition</u>: a thread-safe class that ties (private) data and methods (including the synchronization operations) together, introduced by Per Brinch Hansen in 1970s
 - guarantees mutual exclusion, i.e., only one thread may execute a given monitor method at a time
 - provides a mechanism for threads to temporarily give up exclusive access to wait for a certain condition
- it defines a lock and zero, one, or more condition variables for managing concurrent access to shared data
 - the lock provides mutual exclusion for shared data
 - used to ensure that only a single thread is active in the monitor at a time
 - condition variables enable threads to go to sleep inside critical sections, by releasing their lock at the same time they are put to sleep
 - used when an operation cannot complete (because the condition is not true)
- many programming languages, such as C# and Java, incorporated the idea of Monitor

Recall the CokeMachine class

```
Class CokeMachine{
    storage for cokes (buffer)
    Lock lock;
                                   // a shared lock
    int count = 0;
    Condition notFull, notEmpty;
CokeMachine::Deposit(){
    lock->acquire( );
    while(count == n)
      notFull.wait(&lock);
    add coke to the machine;
    count++;
    notEmpty.notify();
    lock->release();
CokeMachine::Remove(){
    lock->acquire();
    while(count == 0)
      notEmpty.wait(&lock);
    remove coke from the machine;
    count--;
    notFull.notify();
    lock->release();
```

- there is an entry queue (binary semaphore) for the entire class
- there is a wait queue for every counting semaphore defined inside the class

Mesa-style monitor



What if a thread frees a resource needed by a waiting thread?

- should the waiting thread be immediately awakened or should the signalling thread finish first?
 - this gives rises to different versions of monitor semantics

```
CokeMachine::Deposit(){
    lock->acquire( );
   while(count == n)
                                         thread A is put to sleep
      notFull.wait(&lock);
                                         after releasing the lock
    add coke to the machine;
    count++;
   notEmpty.notify();
    lock->release();
CokeMachine::Remove(){
    lock->acquire();
   while(count == 0)
      notEmpty.wait(&lock);
   remove coke from the machine;
    count--;
    notFull.notify();
    lock->release();
}
```

What if a thread frees a resource needed by a waiting thread?

- should the waiting thread be immediately awakened or should the signalling thread finish first?
 - this gives rises to different versions of monitor semantics


```
CokeMachine::Deposit(){
   lock->acquire( );
   while(count == n)
                                        thread A is put to sleep
      notFull.wait(&lock);
                                        after releasing the lock
   add coke to the machine;
   count++;
   notEmpty.notify();
   lock->release();
CokeMachine::Remove(){
    lock->acquire();
   while(count == 0)
      notEmpty.wait(&lock);
   remove coke from the machine;
   count--;
                                   thread B removes a coke so
   notFull.notify(); 
                                   thread A can resume execution now
    lock->release();
}
```

Two types of monitors

- Mesa-style monitors (used in most real operating systems)
 - signal puts a waiting thread on ready queue (with no special priority)
 but the signalling thread keeps the lock and thus the processor
 - some other thread could grab the lock before the waiting thread gets to run
 - hence, the waiting thread may have to wait again after it is woken up (the condition may not be met at that time)!
- Hoare-style monitors (not commonly used but presented in textbooks)
 - signalling thread gives the processor and the lock to the waiting thread which should immediately execute
 - when the waiting finishes or waits again, processor and lock are given back to the signalling thread
 - so the signalling thread should be kept in another queue known as the signal queue

- there is an lock queue (binary semaphore) for the entire class
- there is a wait queue for every counting semaphore defined inside the class
- there is a next queue for every counting semaphore defined inside the class

Hoare-style monitor



Implications

- with Mesa semantics, you always have to check the condition after waking up (done in a while loop)
 - efficient implementation but can lead to concurrency bugs if the condition is not checked again

Implications

- with Mesa semantics, you always have to check the condition after waking up (done in a while loop)
 - efficient implementation but can lead to concurrency bugs if the condition is not checked again

```
CokeMachine::Deposit(){
   lock->acquire();
   while(count == n)
        notFull.wait(&lock);
   add coke to the machine;
   count++;
   notEmpty.notify();
   lock->release();
}
```

Implications

- with Mesa semantics, you always have to check the condition after waking up (done in a while loop)
 - efficient implementation but can lead to concurrency bugs if the condition is not checked again
- with Hoare semantics, you can assume that the condition holds after wait ('while' can be replaced with 'if')
 - inefficient and much more complicated, but leads to a nicer proof of correctness

```
CokeMachine::Deposit(){
                                     CokeMachine::Deposit(){
    lock->acquire( );
                                          lock->acquire( );
    while(count == n)
                                          if(count == n)
                                            notFull.wait(&lock);
      notFull.wait(&lock);
    add coke to the machine;
                                          add coke to the machine;
                                          count++;
    count++;
    notEmpty.notify();
                                          notEmpty.notify();
    lock->release();
                                          lock->release();
```

EXAMPLES OF MESA-STYLE MONITOR

Monitor in the Producer-Consumer problem

- use a binary semaphore for mutual exclusion
- use counting semaphores for each constraint
- putting them together:
 Semaphore mutex;
 Semaphore full_buffer;
 Semaphore empty buffer;

```
class BoundedBuffer {
  public:
   void Producer();
   void Consumer();
  private:
    /* shared data */
    Items buffer;
    int last, count;
    /* shared data */
    Semaphore mutex; // control access to buffers
    Semaphore empty; // number of free slots
    Semaphore full; // number of used slots
BoundedBuffer::BoundedBuffer(int N){
  mutex.value = 1; // initially free
  empty.value = N;  // initially all slots are empty
  full.value = 0; // initially all slots are empty
  buffer = new Items[N];
  last = 0;
  count = 0;
```

```
BoundedBuffer::Producer(){
  coduce item>
  empty.Wait(); // one fewer full slot, or wait
 mutex.Wait(); // entering critical section to access buffer
  <add item to buffer>
 mutex.Signal(); // leaving critical section
  full.Signal(); // one more used slot
BoundedBuffer::Consumer(){
  full.Wait(); // one fewer full slot, or wait
 mutex.Wait(); // entering critical section to access buffer
  <remove item from buffer>
 mutex.Signal(); // leaving critical section
 empty.Signal(); // one more free slot
```

```
BoundedBuffer::Producer(){
  coduce item>
  empty.Wait(); // one fewer full slot, or wait
 mutex.Wait(); // entering critical section to access buffer
  <add item to buffer>
 mutex.Signal(); // leaving critical section
  full.Signal(); // one more used slot
BoundedBuffer::Consumer(){
  full.Wait(); // one fewer full slot, or wait
 mutex.Wait(); // entering critical section to access buffer
  <remove item from buffer>
 mutex.Signal(); // leaving critical section
  empty.Signal(); // one more free slot
```


what if there are multiple producers and/or consumers?

```
BoundedBuffer::Producer(){
  coduce item>
  empty.Wait(); // one fewer full slot, or wait
 mutex.Wait(); // entering critical section to access buffer
  <add item to buffer>
 mutex.Signal(); // leaving critical section
  full.Signal(); // one more used slot
BoundedBuffer::Consumer(){
  full.Wait(); // one fewer full slot, or wait
 mutex.Wait(); // entering critical section to access buffer
  <remove item from buffer>
 mutex.Signal(); // leaving critical section
  empty.Signal(); // one more free slot
```

what if there are multiple producers and/or consumers? it still works!

EXAMPLES OF HOARE-STYLE MONITOR

How does it work?



```
class Monitor {
 public:
   void ConditionWait(); // calls cvar.wait() and implements Hoare semantics
   void ConditionSignal(); // calls cvar.singal() and implements Hoare semantics
   private:
   <shared data>;  // data being protected by monitor
   semaphore lock; // controls entry to monitor
   semaphore cvar; // suspends a thread on a wait
   int waiters cvar; // number of threads waiting on a cvar
   semaphore next; // suspends this thread when signalling another
   int waiters next; // number of threads suspended on next
}
Monitor::Monitor(int N) {
 cvar = N; // initialized to N
 lock = 1; // initialized to 1 as nobody is in the monitor
 next = 0; // initialized to 0 as nobody is suspended because of signalling
 waiters next = 0;
 waiters cvar = 0;
}
```

```
void Monitor::ConditionWait() {
 waiters cvar += 1;// increment the number of waiters
  if(waiters next > 0)
   next.Signal(); // resume a suspended thread
  else
    lock.Signal(); // allow a new thread in the monitor
 cvar.wait(); // wait on the condition
 waiters cvar -= 1;// on waking up decrement the number of waiters
void Monitor::ConditionSignal() {
  if (waiters_cvar > 0) { // don't signal cvar if nobody is waiting
   waiters next += 1; // increment the number of suspended threads
   cvar.Signal();  // awaken a waiting thread
   next.Wait(); // wait for it to finish or wait again
   waiters next -= 1; // decrement the number of suspended threads
```

Using the monitor class