# **EMEP/MSC-W Model Unofficial User's Guide**

Release rv4\_10

emep.mscw@met.no

# **CONTENTS:**

1	Welc	ome to EMEP	1
	1.1	Licenses and Caveats	1
	1.2	Computer Information	2
	1.3	Getting Started	2
	1.4	Model code	3
	1.5	Model grid	3
2	Inpu	t files	
	2.1	NetCDF files	(
	2.2	ASCII files	
3	Outp	out files	15
3	Outp 3.1	Out files Output parameters NetCDF files	15 16
3	_	Output parameters NetCDF files	16
3	3.1	Output parameters NetCDF files	16
	3.1 3.2	Output parameters NetCDF files	16
	3.1 3.2	Output parameters NetCDF files	16 17 19
	3.1 3.2 <b>Subr</b>	Output parameters NetCDF files	10 10 19
	3.1 3.2 <b>Subr</b> 4.1	Output parameters NetCDF files	16 17 19 19 21

**CHAPTER** 

ONE

## WELCOME TO EMEP

This guide gives a brief documentation of the EMEP/MSC-W model version rv4.10. It is intended primarily as a guide on how to run the model, and to help users wishing to understand or change the model in terms of domains, outputs, chemistry, etc.

The main documentation for the EMEP/MSC-W model is an article published in Atmospheric Chemistry and Physics in 2012. This article will be referred to as Simpson et al. (2012) in this manual.

Simpson, D., Benedictow, A., Berge, H., Bergström, R., Emberson, L.D., Fagerli, H., Flechard, C.R., Hayman, G.D., Gauss, M., Jonson, J.E., Jenkin, M.W., Nyíri, Á, Richter, C., Semeena, V.S, Tsyro, S., Tuovinen, J.-P., Valdebenito, Á., and Wind, P.: The EMEP MSC-W chemical transport model – technical description. Atmospheric Chemistry and Physics, 12, 7825-7865, 2012.

http://www.atmos-chem-phys.net/12/7825/2012/acp-12-7825-2012.html

The model source code is available from the Open Source EMEP/MSC-W model github page:

https://github.com/metno/emep-ctm

## 1.1 Licenses and Caveats

The EMEP code is provided under the GNU General Public License version 3 (http://fsf.org and/or http://www.gnu.org/copyleft/gpl.html).

Each code module is prefaced with something like:

```
! <EXAMPLE_CODE.f90 - A component of the EMEP MSC-W Eulerian
1
         Chemical transport Model>
! *
  Copyright (C) 2007-2016 met.no
!* Contact information:
!* Norwegian Meteorological Institute
!* Box 43 Blindern
!* 0313 OSLO
! * NORWAY
! *
   email: emep.mscw@met.no
! *
! *
     This program is free software: you can redistribute it and/or modify
     it under the terms of the GNU General Public License as published by
1 *
     the Free Software Foundation, either version 3 of the License, or
! *
     (at your option) any later version.
! *
! *
     This program is distributed in the hope that it will be useful,
```

And a copy of the license file, **gpl.txt**, is provided with the model code source files.

It is important to note that the code is provided "as it is", and EMEP/MSC-W has very limited resources with which to support usage of the code.

# 1.2 Computer Information

To compile the EMEP/MSC-W model you need:

- Fortran 95 compiler
- NetCDF Library (> 4.1.3)
- MPI Library (> 1.0)

It is necessary to compile with double precision real (8 bytes real). The program has been used on computers ranging from a Linux laptop to supercomputers (Itanium2 cluster, Intel Xeon cluster, Cray XT4, IBM power5+). It is compatible with all compilers tested so far: Intel, PGI, gfortran, XL Fortran. A Makefile is included, the path to NetCDF (INCL and LLIB) have to be adapted to your machine, and the Fortran compiler (F90) and flags (F90FLAGS) to the compiler you are using.

The code has been tested with 1 to 1024 CPUs, and scales well (for large grids). If only one CPU is used 1-2 GB memory is required. If more than one, for example 64 CPUs are used, 200 MB of memory per CPU is enough (in the case of a 132 X 159 grid size). For runs on more than 32 CPUs, a fast interconnect is recommended (infiniband for example), for smaller runs, gigabit Ethernet is sufficient. It takes ~5 hours on 64\*Xeon X5355 (2.66GHz) for 1 year simulation.

When downloading input data in order to do a "base run" please make sure that there are 35 Gb disc space available, especially due to large meteorology input files. The model can be run for shorter periods, users can download meteorology for only the period they are interested in, plus one day.

# 1.3 Getting Started

It is recommended to read all the chapters of this EMEP/MSC-W model User Guide before you start downloading anything from the EMEP/MSC-W Open Source website.

This is what you need to do before you can do a "base run" with the EMEP/MSC-W model:

- Read the EMEP/MSC-W model User Guide
- Download input data, description and downloading instructions in ch-inputfiles.
- Download the EMEP/MSC-W model source code, description and downloading instructions Section 1.4.
- Follow the instructions for "Submitting a Run" description in Section 4.
- Download some model results for comparison, description in and downloading instructions Section 3.

# 1.4 Model code

The latest release Open Source of the EMEP/MSC-W model is version rv4\_10. This and previous releases can be found on the releases section of the EMEP/MSC-W Open Source github page.

Although the source code is available for download as a single compressed file on the release page, the preferred retrieval method is via the catalog tool as follows:

```
# download the catalog tool
wget https://raw.githubusercontent.com/metno/emep-ctm/master/tools/catalog.py

# make it executable and run it
chmod +x catalog.py

# download the source code for rv4_10 release
catalog.py -R rv4_10 --source
```

The model source code, makefiles, and a copy of the license file will be placed under the directory EMEP\_MSC-W\_model.rv4.10.OpenSource/source/. An overview of the files is given in Table 1.1.

Туре	Filename
modules files	*.f90
include files	*.inc
namelist	config_emep.nml
makefiles	Makefile and Makefile.SRCS
dependency file	dependencies
a copy of the license	gpl.txt

Table 1.1: Model source files

In addition there is a run script called modrun.sh, which will be placed in the EMEP\_MSC-W\_model.rv4.10. OpenSource directory. The run script, modrun.sh, can easily be modified to work on your computer system. This script is described in detail in Section 4.

# 1.5 Model grid

The current EMEP model version, and the provided gridded input data, have a horizontal resolution of  $50 \times 50 km^2$  (at  $60^\circ N$ ) and are defined on a polar stereographic projection with 20 sigma levels vertically. The model is very flexible with regard to the horizontal resolution, in that it readily makes use of meteorological data provided with the model. The vertical resolution is currently still restricted to the fixed 20 layer system. The physical description is given in detail in Chapter 2 of the EMEP Status Report 1/2003 Part I (Simpson *et al.*, 2003).

In 2008 the EMEP domain was extended eastwards in order to include the EECCA countries in the EMEP model grid, see Figure 1.1. To distinguish the new grid from the old EMEP grid, the new grid is called EECCA in this text and in the config\_emep.nml.

1.4. Model code 3




Figure 1.1: The extended EMEP grid covering EECCA area with  $132 \times 159$  gridpoints on  $50 \times 50 km^2$  resolution defined on a polar stereographic projection.

**CHAPTER** 

**TWO** 

## **INPUT FILES**

This chapter provides an overview on the necessary input files to run the EMEP/MSC-W model. A complete set of input files is provided in the EMEP/MSC-W Open Source web page to allow model runs for the meteorological year 2014. Table 2.1 lists the input files.

The input files can be downloaded directly from our ftp server (ftp://ftp.met.no/projects/emep/OpenSource/201609/), However, the preferred retrieval method is via the catalog tool (Section 1.4) as follows:

```
# download the meteorology
catalog.py -R rv4_10 --meteo

# download other input files
catalog.py -R rv4_10 --input
```

The meteorology files will be placed under EMEP\_MSC-W\_model.rv4.10.OpenSource/meteo2014/, and the remaining input files will be placed under EMEP\_MSC-W\_model.rv4.10.OpenSource/input/

This are all input files needed to run the EMEP/MSC-W model, except the aircraft emissions (AircraftEmis\_FL. nc), and forest fire emissions (FINN\_ForestFireEmis\_2014.nc). See sections Section 2.1.9 and Section 2.1.11 for details about these emissions data.

**IMPORTANT:** The input data available in the EMEP/MSC-W Open Source Web site should be appropriately acknowledged when used for model runs. If nothing else is specified according to references further in this chapter, please acknowledge EMEP/MSC-W in any use of these data.

Data	Name	Format
Meteorology data	met/	
Meteorology	meteoyyyyMMDD.nc(365+1 files)	netCDF1
Other Input files	input/	
Global Ozone	GLOBAL_03.nc	netCDF
New Global Ozone	Logan_P.nc	netCDF <sup>2</sup>
BVOC emissions	EMEP_EuroBVOC.nc	netCDF
Landuse	LanduseGLC.nc and Landuse_PS_5km_LC.nc	netCDF
Degree-day factor	DegreeDayFactors.nc	netCDF
N depositions	annualNdep.nc	netCDF
Road dust	RoadMap.nc and AVG_SMI_2005_2010.nc	netCDF <sup>3</sup>
Aircraft emissions	AircraftEmis_FL.nc	netCDF <sup>3</sup>
Surface Pressure	SurfacePressure.nc	netCDF <sup>3</sup>
Forest Fire	FINN_ForestFireEmis_YYYY.nc	netCDF <sup>3</sup>
Dust files	Soil_Tegen.nc	netCDF <sup>3</sup>
	SoilTypes_IFS.nc	netCDF <sup>3</sup>
	Continued on	next page

Table 2.1: List of input data files

Data	Name	Format
Emissions	emislist.POLL (7 files, EMEP 50km PS grid)	ASCII <sup>4</sup>
	Emis_TNO7.nc (regional, $0.125  imes 0.0625$ lon-lat)	netCDF <sup>3</sup>
	Emis_GLOB_05.nc (global, $0.5  imes 0.5$ lon-lat)	netCDF <sup>3</sup>
Vertical level distribution	Vertical_levels.txt	ASCII
Time factors for monthly emissions	MonthlyFac.POLL(7 files)	ASCII <sup>4</sup>
Time factors for daily emissions	DailyFac.POLL (7 files)	ASCII <sup>4</sup>
Time factors for hourly emissions	HOURLY-FACS	ASCII
Emission heights	EmisHeights.txt	ASCII
Natural SO <sub>2</sub>	natso2MM.dat(12 files)	ASCII <sup>1</sup>
Volcanoes	columnsource_emission.csv	ASCII
	columnsource_location.csv	ASCII
Lightning emissions	lightningMM.dat(12 files)	ASCII <sup>1</sup>
Emissions speciation	emissplit.defaults.POLL	ASCII <sup>4</sup>
	emissplit.specials.POLL	ASCII <sup>43</sup>
Emission factors for scenario runs	femis.dat	ASCII
Photo-dissociation rates	jclearSS.dat(4 files)	ASCII <sup>5</sup>
	jcl1kmSS.dat (4 files) and jcl1.jun	ASCII <sup>5</sup>
	jcl3kmSS.dat (4 files) and jcl3.jun	ASCII <sup>5</sup>
Landuse definitions	Inputs_LandDefs.csv	ASCII
Stomatal conductance	Inputs_DO3SE.csv	ASCII
Sites locations for surface output	sites.dat	ASCII
Sondes locations for vertical output	sondes.dat	ASCII

Table 2.1 – continued from previous page

## 2.1 NetCDF files

# 2.1.1 Meteorology

The daily meteorological input data (meteoyyyyMMDD.nc, where yyyy is year, MM is month and DD is day) used for the EMEP/MSC-W Model are based on forecast experiment runs with the Integrated Forecast System (IFS), a global operational forecasting model from the European Centre for Medium-Range Weather Forecasts (ECMWF).

The IFS forecasts has been run by MSC-W as independent experiments on the HPCs at ECMWF with special requests on some output parameters. The meteorological fields are retrieved on a  $0.1^{\circ} \times 0.1^{\circ}$  longitude latitude coordinates and interpolated to  $50 \times 50 km^2$  polar-stereographic grid projection. Vertically, the fields on 60 eta  $(\eta)$  levels from the IFS model are interpolated onto the 37 EMEP sigma  $(\sigma)$  levels. The meteorology is prepared into 37 sigma levels since the model is under test for a finer vertical resolution.

The open source code is released with 20 sigma levels and to make the model read the meteorology properly, a description of the 20 vertical sigma levels is needed. This is provided in an ASCII file called Vertical\_levels. txt together with the other input data (Table 2.1). The version of the IFS model used for preparing these fields, Cycle 38r2, is documented in http://www.ecmwf.int/research/ifsdocs/index.html. Previous years are based on Cycle 36r1 with a resolution of  $0.2^{\circ} \times 0.2^{\circ}$  on a spherical grid. Meteorological fields currently used for EMEP/MSC-W Model runs are given in Table 2.2. Some verification and description of these meteorological fields are given in Chapter 2 of the EMEP Status Report 1/2016.

<sup>&</sup>lt;sup>1</sup> YYYY: year, MM: month, DD: day.

<sup>&</sup>lt;sup>2</sup> New O<sub>3</sub> boundary condition data in 30 levels. Can be used with NewLogan=.true.in BoundaryConditions\_ml.f90.

<sup>&</sup>lt;sup>3</sup> Optional, in most cases.

<sup>&</sup>lt;sup>4</sup> POLL: pollutant type (NH<sub>3</sub>, CO, NO<sub>x</sub>, SO<sub>x</sub>, NMVOC, PM<sub>2.5</sub> and PM<sub>co</sub>).

<sup>&</sup>lt;sup>5</sup> SS: seasons.

Acknowledgement: ECMWF, met.no

Table 2.2: Input meteorological data used in the EMEP/MSC-W Model

Parameter	Unit	Description
3D fields		for 37 $\sigma$
u, v	m/s	Horizontal wind velocity components
q	kg/kg	Specific humidity
$\theta$	K	Potential temperature
CW	kg/kg	Cloud water
CL	%	3D Cloud cover
cnvuf	$kg/sm^2$	Convective updraft flux
cnvdf	$kg/sm^2$	Convective downdraft flux
PR	mm	Precipitation
2D fields		for surface
PS	hPa	Surface pressure
T2	K	Temperature at $2m$ height
Rh2	%	Relative humidity at $2m$ height
SH	$W/m^2$	Surface flux of sensible heat
LH	$W/m^2$	Surface flux of latent heat
au	$N/m^2$	Surface stress
SST	K	Sea surface temperature
SWC	$m^{3}/m^{3}$	Soil water content
lspr	m	Large scale precipitation
cpr	m	Convective precipitation
sdepth	m	Snow depth
ice	%	Fraction of ice
SMI1		Soil moisture index level 1
SMI3		Soil moisture index level 3
u10, v10	m/s	Wind at 10m height

#### 2.1.2 Gridded emissions

Since 2015 different formats of gridded emissions can be used and mixed (with some restrictions) under one common framework. The different formats that are presently supported are:

#### "Old style" ASCII emissions format: Total yearly emissions.

The gridded emission files contain 16 columns where the first column represents the country code (http://www.emep.int/grid/country\_numbers.txt), the second and the third columns are the i and j indices of the EMEP grid, the fourth and fifth columns are the total emissions from low and high sources, and the last 11 columns contain emissions from 10 anthropogenic SNAP sectors.

The advantage of the ASCII emissions format, is that they are easy to modify, and the interpretation of the numbers is straightforward. The main disadvantage of the ASCII emissions format, is that they are only valid for one specific grid projection. Visualization of these emissions, needs also some more efforts.

#### **Countrywise NetCDF emissions:** Yearly totals.

Each country and sector has its own NetCDF field.

The main advantage of NetCDF emissions is that all the information about the data (projection, units) is given in the same file. This allows the code to reproject the emissions to any grid projection on the fly. It is easy to

2.1. NetCDF files 7

visualize the emissions of one country with simple tools, like noview. The data is simple to interpret and it is possible to add new countries to an existing file (with appropriate tools).

The disadvantage of countrywise NetCDF emissions, is that there are quite a large number of fields, with most of the data being zero. NetCDF will compress the data, but it will still take some time for the model to read all the data.

#### "Fraction type" NetCDF emissions: Yearly totals.

The total emissions are stored in one gridded map, and in addition information about which country the emission belongs to.

The main advantage of "fraction type" NetCDF emissions, is that they will keep the grid flexibility, have a more compact form and be faster to read in.

The disadvantage is that the interpretation of the content of the fields is more difficult and it is hard, for instance, to add a new country to the file. Total emissions and coverage of countries can easily be visualized, but not emissions from one single country.

Description of main fields for "fraction type" NetCDF Emissions Table 2.3

Table 2.3: Description of main fields for "fraction type" NetCDF Emissions

Variable name	Description
Ncodes	Number of countries sharing the same grid cell
poll_secNN	Pollutant from each sector
Codes	Country code number
fractions_poll_secNN	Fraction of emissions to assign to one country

#### Monthly "fraction type" NetCDF emissions.

This is similar to the yearly "fraction type" NetCDF emissions, but there are 12 monthly values for each field. This format cannot be combined with other formats.

#### Using and combining gridded emissions

These gridded emission files are controlled via the <code>config\_emep.nml</code> file. Each file is assigned as one set of values for <code>emis\_inputlist</code>. Listing 2.1 line 1 includes an ASCII emission file, where the keyword <code>POLL</code> will be replaced by the model by all the emitted pollutants (according to the names defined in <code>CM\_EmisFiles.inc</code>). An additional NetCDF emission is included in line 2.

Now all emissions from both ASCII file and NetCDF file will be used. In practice some countries might be counted twice. Therefore some new data can be included in the emis\_inputlist, to specify which countries to keep or to avoid. Listing 2.1 lines 3–4 will include only 'NO', 'SE' and 'FI' from the first file (ASCII), and take all countries except 'NO', 'SE' and 'FI' from the second file (NetCDF).

Sets of countries can in principle be defined; for now only the set 'EUMACC2' is defined.

Listing 2.1: Mixed emission configuration example.

```
emis_inputlist(1)%name = '/MyPathToEmissions/emislist.POLL',
emis_inputlist(2)%name = '/MyPathToEmissions/Emis_GLOB_05.nc',
emis_inputlist(1)%incl(1:) = 'NO', 'SE', 'FI',
emis_inputlist(2)%excl(1:) = 'NO', 'SE', 'FI',
```

#### 2.1.3 Global Ozone

Initial concentration of ozone are required in order to initialize the model runs. Boundary conditions along the sides of the model domain and at the top of the domain are then required as the model is running.

The Logan\_P.nc file contains monthly averaged fields in NetCDF format. The initial and background concentrations are based on the Logan (1998) climatology. The Logan climatology is scaled on run time according to the Mace Head measurements as described in Simpson *et al.* (2003). For a number of other species, background/initial conditions are set within the model using functions based on observations (Simpson *et al.*, 2003 and Fagerli *et al.*, 2004).

## 2.1.4 BVOC emissions

Biogenic emissions of isoprene and monoterpene are calculated in the model as a function of temperature and solar radiation, using the landuse datasets. The light and temperature dependencies are similar to those used in the original open source model, see Chapter 4.2 of the EMEP Status Report 1/2003 Part I (Simpson *et al.*, 2003).

Biogenic VOC emission potentials (i.e. rates at  $30^{\circ}C$  and full sunlight) are included for four different forest types in the NetCDF file EMEP\_EuroBVOC.nc. These emission potentials have unit  $\mu g/m^2/h$ , and refer to emissions per area of the appropriate forest category. In addition, default emission potentials are given for other land-cover categories in the file Inputs\_LandDefs.csv. The underlying emission potentials, land-cover data bases, and model coding have however changed substantially since model version v.2011-06. The new approach is documented in Simpson *et al.*, 2012.

#### 2.1.5 Landuse

Landuse data are required for modelling boundary layer processes (i.e. dry deposition, turbulent diffusion). The EMEP/MSC-W model can accept landuse data from any data set covering the whole of the domain, providing reasonable resolution of the vegetation categories. Gridded data sets providing these landuse categories across the EMEP domain have been created based on the data from the Stockholm Environment Institute at York (SEI-Y) and from the Coordinating Center for Effects (CCE). 16 basic landuse classes have been identified for use in the deposition module in the model, and three additional "fake" landuse classes are used for providing results for integrated assessment modeling and effects work.

There are two NetCDF files included, one file Landuse\_PS\_5km\_LC.nc on 5 km resolution over the EMEP domain, and a global LanduseGLC.nc. The different landuse types are desribed in Simpson et al (2012).

## 2.1.6 Degree-day factor

Domestic combustion which contribute to a large part of SNAP 2, varies on the daily mean temperature. The variation is based on the heating degree-day concept. These degree days are pre-calculated for each day and stored in the file <code>DegreeDayFactors.nc</code>. See Simpson et al. (2012) section 6.1.2.

2.1. NetCDF files 9

## 2.1.7 NO<sub>x</sub> depositions

Areas with high NO deposition loads have greater soil-NO emissions. To include this in the model, a NetCDF file where pre-calculated N-depositions are included. The file made by the results from the EMEP/MSC-W model runs over a 5-year period.

#### 2.1.8 Road Dust

Road traffic produces dust. These emissions are handled in the EMEP/MSC-W model in the Emissions\_ml. f90 module. To include road dust, set USE\_ROADDUST=.true.in config\_emep.nml. There are two files included in input data, RoadMap.nc and AVG\_SMI\_2005-2010.nc. RoadMap.nc include gridded roads and PM emissions over Europe, AVG\_SMI\_2005-2010.nc are global.

#### 2.1.9 Aircraft emissions

In the EMEP/MSC-W model aircraft emissions are 'OFF' by default. They can be switched 'ON' by setting USE\_AIRCRAFT\_EMIS=.true. in config\_emep.nml and download the data from http://www.pa.op.dlr.de/quantify. The EMEP model uses data provided by the EU-Framework Programme 6 Integrated Project QUANTIFY (http://www.pa.op.dlr.de/quantify). However, before using these data a protocol has to be signed, which is why the data file can not be provided directly on the EMEP/MSC-W Open Source website. If you want to use aircraft emissions go to http://www.pa.op.dlr.de/quantify, click on 'QUANTIFY emission inventories and scenarios', and then click on 'Register'. That page will provide information about the registration process and the protocol that has to be signed. Once you are registered, click 'Login' and provide user name and password. On the new page, search for 'Emissions for EMEP', which links directly to the Readme file and the emission data file in NetCDF format. Download the emission data file and place it in the input folder.

#### 2.1.10 Surface Pressure

If USE\_AIRCRAFT\_EMIS=.true. in config\_emep.nml, then in addition to the Aircraft Emission file, there will be need for a SurfacePressure.nc file, which is already in the /input folder. The NetCDF file consists of surface pressure fields for each of the months in 2008 called surface\_pressure, and one field for the whole year called surface\_pressure\_year. All fields are given in Pa.

#### 2.1.11 Forest Fire

Since model version rv3.9 (November 2011), daily emissions from forest and vegetation fires are taken from the "Fire INventory from NCAR version 1.0" (FINNv1, Wiedinmyer et al. 2011). Data are available from 2005, with daily resolution, on a fine  $1km \times 1km$  grid. We store these data on a slightly coarser grid  $(0.2^{\circ} \times 0.2^{\circ})$  globally for access by the EMEP/MSC-W model. To include forest fire emissions set USE\_FOREST\_FIRES=.true. in config\_emep.nml and download the 2012 GEOS-chem daily data http://bai.acd.ucar.edu/Data/fire/. The data needs to be stored with units mole/day in a NetCDF file called FINN\_ForestFireEmis\_2014.nc compatible with the ForestFire\_ml.f90 module.

#### 2.1.12 Dust files

The annual ASCII data for sand and clay fractions as well as the monthly data for boundary and initial conditions for dust from Sahara are replaced with a single NetCDF file Soil\_Tegen.nc since 2013. This covers data for a global domain in  $0.5 \times 0.5$  degree resolution.

The variables 'sand' and 'clay' gives the fraction (in %) of sand an clay in the soil for each grid cell over land.

The files are used by the module <code>DustProd\_ml.f90</code>, which calculates windblown dust emissions from soil erosion. Note that the parametrization is still in the development and testing phase, and is by default 'turned off'. To include it in the model calculations, set <code>USE\_DUST=.true.in config\_emep.nml</code>. The user is recommended to read carefully documentation and comments in the module <code>DustProd\_ml.f90</code>.

There is also a possibility to include boundary and initial conditions for dust from Sahara. The input file gives monthly dust mixing ratios (MM - month, e.g. 01, 02, 03,...) for fine and coarse dust from Sahara. The files are based on calculations from a global CTM at the University of Oslo for 2000. To include Saharan dust, set USE\_SAHARA=. true. in config emep.nml.

Another source for dust is an arid surface. This is accounted for by soilmosture calculations in DustProd\_ml. f90. Together with Soil Water Index from the meteorology files and permanent wilting point (pwp) from SoilTypes\_IFS.nc. This file is global and NetCDF. See Simpson et al. (2012) section 6.10.

## 2.2 ASCII files

## 2.2.1 Natural SO<sub>2</sub>

Natural SO<sub>2</sub> emissions (dimethylsulfide (DMS) from sea) are provided as monthly gridded files. The values are given at the surface in  $\mu g/m^2$  for each grid cell in the domain.

#### 2.2.2 Volcanoes

Emissions from volcanic passive degassing of  $SO_2$  are included for the active Italian volcanoes, Etna, Vulcano and Stromboli, and based upon the officially submitted data. To consider these volcanic emissions, we need to feed the locations and heights of volcanoes into the model. The input file columnsource\_location.csv contains the geographical coordinates (latitudes and longitudes) and the heights (in meters) of the included volcanoes, while columnsource\_emission.csv contains the emission parameters.

Since 2010 the EMEP/MSC-W model has also been used to model the transport of ash and  $SO_2$  from volcanic eruptions. In addition to data for passive degassing of  $SO_2$ , the above two input files also contain locations and emission parameters for two recent eruptions of Icelandic volcanoes (Eyjafjallajökull in 2010 and Grimsvötn in 2011). In order to include emissions from these eruptions one needs to set  $USE\_ASH=.true.in config\_emep.nml$ .

#### 2.2.3 Gridded emissions

The official emission input for the EMEP/MSC-W model consists of gridded annual national emissions based on emission data reported every year to EMEP/MSC-W (until 2005) and to CEIP (from 2006) by each participating country. More details about the emission input with references can be found in Chapter 4 of the EMEP Status Report 1/2003 Part I (Simpson et al., 2003).

Since 2015 different formats of gridded emissions can be used and mixed (with some restrictions) in the EMEP model under one common framework. The new emission system is described in Section 2.1.2. Here we focus only on the "old style" ASCII emission format.

Seven gridded emission input files (emislist.poll) are available in ASCII format for the following compounds:  $CO, NH_3, NO_x, PM_{2.5}, PM_{co}, SO_x$  and VOC.

The gridded ASCII emission files contain 16 columns where the first column represents the country code (http://www.emep.int/grid/country\_numbers.txt), the second and the third columns are the i and j indices of the EMEP grid, the fourth and fifth columns are the total emissions from low and high sources, and the last 11 columns contain emissions from 10 anthropogenic SNAP sectors (http://reports.eea.eu.int/technical\_report\_2001\_3/en) and 1 source-sector called "Other sources and sinks", which include natural and biogenic emission sources. The data are given with the Mq.

2.2. ASCII files 11

**Acknowledgement:** EMEP

#### 2.2.4 Time factors for emissions

Monthly and daily time factors for emission of the 7 compounds (CO,  $NH_3$ ,  $NO_x$ ,  $PM_{2.5}$ ,  $PM_{co}$ ,  $SO_x$  and VOC). There is one file available per compound in ASCII format.

The first two columns in the files represent the country code (http://www.emep.int/grid/country\_numbers.txt), the second column represents the sector (http://webdab.emep.int/sectors.html). In the monthly files, the 12 consecutive columns represent the time factors corresponding to the months of the year. In the daily files there are 7 consecutive columns representing the time factor for each day of the week.

The file HOURLY-FACS includes factors for each of the eleven SNAP sectors for every hour (the columns) for each day of the week, see Simpson et al. (2012) section 6.1.2

# 2.2.5 Emission heights

A vertical distribution for the eleven SNAP sectors are given in the file EmisHeights.txt. The file has seven vertical levels, over the columns and the SNAP sectors given in the first row. Read more in Simpson et al. (2012) section 6.1.1.

#### 2.2.6 Emission factor for scenario runs

Scenario run in the case of the EMEP/MSC-W model means a run to test the impact of one or more pollutants from a particular country.

Emission factors are applied to specified countries and emission sectors and can be set by changing the ASCII file femis.dat. This file can be changed by the users according to their needs.

The file contains several columns (the number is flexible). The first column represents the country code (http://www.emep.int/grid/country\_numbers.txt), the second represents the sector (http://reports.eea.eu.int/technical\_report\_2001\_3/en) where '0' means all sectors, and then in the remaining columns one can specify which emissions to reduce. Here 1.0 means no reduction of the given pollutant (SO<sub>x</sub>, NO<sub>x</sub>, VOC, NH<sub>3</sub>, CO, PM<sub>2.5</sub>and PM<sub>co</sub>) from sectors of specified country. The number following the first text ("Name") in line 1 (number 5 in the downloaded file) gives the number of pollutants treated in the file.

## 2.2.7 Chemical speciation of emissions

Many of the emission files give emissions of a group of compounds, e.g.  $NO_x$  includes NO+NO2, and VOC can include many compounds. The information needed to retrieve emissions of individual compounds from these the gridded files is given in files labelled emissplit.defaults.POLL or emissplit.specials.POLL, where POLL can be  $NO_x$ , VOC, etc.

The defaults file give the emission split for each SNAP sector (one per row, with second index being the SNAP sector), which is applied to all countries by default. For VOC this split was derived from the UK inventory of Passant (2002), as part of the chemical comparison project of Hayman *et al.* (2011).

The specials files are in general optional, and can be used to specify speciation for particular countries or SNAP sectors. The 1<sup>st</sup> column specifies the country code of interest, the second the SNAP sector.

If forest fires are used, then the file emissplit.specials.voc is required (not optional), and the country-code 101 used to specify the VOC speciation of forest fires in this file.

# 2.2.8 Lightning emissions

Emissions of  $NO_x$  from lightning are included in the model as monthly averages on T21 (5.65° × 5.65°) resolution (Køhler *et al.*, 1995). The lightning emissions are defined on a  $64 \times 32$  grid with 17 vertical levels, with global coverage, and are provided as 12 ASCII files lightningMM.dat.

#### 2.2.9 Landuse definitions

For the vegetative landuse categories where stomatal modelling is undertaken, the start and end of the growing season (SGS, EGS, in days) must be specified. The calculation of SGS and EGS with respect to latitude is done in the module LandDefs\_ml.f90. The parameters needed to specify the development of the leaf area index (LAI) within the growing season are given in the ASCII file Inputs\_LandDefs.csv. For more information, see chapter 5 of the EMEP Status Report 1/2003 Part I (Simpson *et al.*, 2003).

The file, designed to be opened with excel or gnumeric, contains a header briefly explaining the contents of the 14 columns. The first three columns are representing the landuse name, code (which are consistent with those in Landuse.Input file) and type (grouping of the landuse classes). The fourth column (PFT) gives a plant-functional type code (for future use), the fifth gives the maximum height of vegetation (m), the sixth indicates albedo (%) and the seventh indicates possible source of NH<sub>x</sub> (0 off/1 on, curently not used). Columns 8 to 11 define the growing season (day number), column 12 and 13 lists the LAI minimum and maximum  $(m^2/m^2)$  and columns 14 and 15 defines the length of the LAI increase and decline periods (no. of days). Finally, the last four columns give default values of foliar biomass and biogenic VOC emission potentials. See Simpson et al., (2012) for details.

#### 2.2.10 Stomatal conductance

Parameters for the stomatal conductance model, deposition of  $O_3$  and stomatal exchange (DO3SE) must be specified. That are based upon the ideas in Emberson *et al.*, 2000, and are discussed in Simpson and Emberson, 2006 and Tuovinen et al. 2004.

The ASCII file Inputs\_DO3SE.csv provides land-phenology data of each landuse type for stomatal conductance calculations. The data are summarised in Table 5.1 in Chapter 5 of the EMEP Status Report 1/2003 Part I (Simpson *et al.*, 2003).

The file contains a **header** with the contents of the file, with different factors needed for each of the landuse classes used in the EMEP/MSC-W model. The first two columns represent the landuse code (which are consistent with those in Landuse. Input file) and name. The next 22 values are different phenology factors.

#### 2.2.11 Photo-dissociation rates

The photo-dissociation rates (J-values) are provided as lookup tables. The method is previously described in Jonson *et al.*, (2001). J-values are provided as clear sky, light cloud and dense cloud conditions, and the model interpolates between these according to cloudiness from the meteorological input data. In the lookup tables data are listed for every 10 degree latitude at an interval of 1 degree zenith angle at every model height.

For the two types of cloud conditions there are one ASCII file averaged for each season (SS); 01, 02, 03 and 04. For light cloud the four seasonal files are called jcllkmSS.dat, for dense cloud conditions the four seasonal files are called jcl3kmSS.dat, and then for clear sky four files called jclearSS.dat. In addition there are two files for June called jcl1.jun and jcl3.jun.

Each file contains 18 columns. The first column is latitude of zenith angle and then the next 17 are the values for the model levels with the 1/s. For more details about these rates, please read Chapter 7.2 of the EMEP Status Report 1/2003 Part I (Simpson *et al.*, 2003).

2.2. ASCII files 13

# 2.2.12 Site and Sonde locations for output

The model provides a possibility for extra output data of surface concentration for a set of specified measurement site locations and concentrations for the vertical column above a set of specified locations. These site and sonde locations are listed in the ASCII files sites.dat and sondes.dat files. These files can be changed by the user, this is described in Section 3.2.

**CHAPTER** 

# **THREE**

# **OUTPUT FILES**

Output files from a model run are written out in either ASCII, or (for most data outputs) in NetCDF format. The different NetCDF files are named after the runlabell parameter set in modrun. sh. The model output is written to the same directory as where the runscript where submitted, as described in Section 4.

To check your model run, already prepared model result files can be downloaded using the catalog tool (Section 1.4) as follows:

```
# download the output catalog.py -R rv4_10 --output
```

Unpacked files are placed in an output directory with model run results for a whole year, and sometimes with a smaller test run for e.g. April.

Table 3.1: List of model output f	пies
-----------------------------------	------

Output data files	Short description	Format
Base_hour.nc	Gridded hourly values of a	NetCDF
	selection of compounds	
Base_day.nc	Gridded daily values of a	NetCDF
	selection of compounds	
Base_month.nc	Gridded monthly values of a	NetCDF
	selection of compounds	
Base_fullrun.nc	Gridded yearly values of a	NetCDF
	selection of compounds	
sites_YYYY.nc	Surface daily values of a	NetCDF <sup>1</sup>
	selection of stations and compounds	
sondes_YYYY.nc	Vertical daily values of a	NetCDF <sup>1</sup>
	selection of stations and compounds	
sites_YYYY.cvs	ASCII version of sites_YYYY.nc	ASCII <sup>2</sup>
sondes_YYYY.csv	ASCII version of sondes_YYYY.nc	ASCII <sup>2</sup>
Additional files		
RunLog.out	Summary log of runs, including total emissions	ASCII
	of different air pollutants per country	
Timing.out	Timing log file	ASCII

<sup>1</sup> YYYY: year.

<sup>&</sup>lt;sup>2</sup> Deprecated output.

# 3.1 Output parameters NetCDF files

Parameters to be written out Base\_day.nc, Base\_month.nc and Base\_year.nc are defined in My\_Derived\_ml.f90 and Derived\_ml.f90. In My\_Derived\_ml.f90, the use can specify the output species (air concentrations, depositions, column values), units and temporal resolution of the outputs (daily, monthly, yearly).

The name of output parameter provides some information about data. The names start with TYPE of the parameter, namely SURF (surface air concentrations), DDEP (Dry deposition), WDEP (Wet deposition), COLUMN (Vertically integrated parameters), Area (Surface area) etc.

For surface air concentrations, the general name pattern is SURF\_UNITS\_COMPONENT. Here, UNITS can e.g. be "ug"  $(\mu g/m^3)$ , "ugS"  $(\mu g(S)/m^3)$ , "ugN"  $(\mu g(N)/m^3)$ , or "ppb". Note that the components are classified either as "SPEC" (species) or "GROUP". The content of complex GROUP components can be found in CM\_ChemGroups\_ml.f90.

For column integrated parameters, the names are  $COLUMN\_COMPONENT\_kNLAYERS$ , where NLAYERS is the number of layers from model top included in the integration. The units for column outputs are "ugm2"  $(\mu g/m^2)$ , "mcm2"  $(molec/m^2)$  or "e15mcm2"  $(10^{15}molec/m^2)$ .

For dry depositions, given per  $1m^2$  of specified landuse, the names look like DDEP\_COMPONENT\_m2LANDUSE, where LANDUSE can be either a specific landuse type or a cell average. For wet depositions, the names are WDEP\_COMPONENT. The units for dry and wet depositions are  $mg/m^2$ ,  $mg(S)/m^2$  or  $mg(N)/m^2$ .

Surface concentrations, column integrated, wet and dry deposition outputs are defined by the user in <code>config\_emep.nml</code> file. Surface concentrations and column integrated outputs are described in <code>OutputConcs\_config</code> namelist, Dry and wet deposition outputs are described in <code>OutputDep\_config</code> namelist.

VG\_COMPONENT\_LANDUSE are the dry deposition velocities on various landuse types, typically in cm/s.

Table 3.2 lists most of output parameters, providing additional explanation to the complex components. For a complete suit of currently selected output parameters, see provided output NetCDF files, or My\_Derived\_ml.f90 module.

Parameter name	Short description	Comments
<b>Surface Concentrations</b>		
SURF_ppb_03	O <sub>3</sub> [ppb]	
SURF_ugN_NO	NO $[\mu g(N)/m^3]$	Available also in ppb
SURF_ugN_NO2	$NO_2 \left[\mu g(N)/m^3\right]$	Available also in ppb
SURF_ugN_HNO3	HNO <sub>3</sub> [ $\mu g(N)/m^3$ ]	Available also in ppb
SURF_ugN_NH3	$NH_3 \left[\mu g(N)/m^3\right]$	Available also in ppb
SURF_ugS_SO2	$SO_2 \left[\mu g(S)/m^3\right]$	Available also in ppb
SURF_ug_SO4	$SO_4^{2-} [\mu g/m^3]$	
SURF_ug_NO3_F	$NO_3^-$ fine aerosol $[\mu g/m^3]$	As ammonium nitrate
SURF_ug_NO3_C	$NO_3^-$ coarse aerosol [ $\mu g/m^3$ ]	Associated with sea salt and mineral dust
SURF_ug_TNO3	$NO_3^-$ total $[\mu g/m^3]$	Sum of fine and coarse nitrate
SURF_ug_NH4_F	$NH_4^+$ fine aerosol [ $\mu g/m^3$ ]	As ammonium sulphate and ammonium nitrate
SURF_ug_SIA	SIA [ $\mu g/m^3$ ]	Secondary Inorganic Aerosol
SURF_ug_SIA	SIA $[\mu g/m^3]$	Secondary Inorganic Aerosol
SURF_ug_ECFINE	EC fine $[\mu g/m^3]$	Elemental carbon
SURF_ug_ECCOARSE	EC coarse $[\mu g/m^3]$	Elemental carbon
SURF_ug_PM_OM25	OM fine $[\mu g/m^3]$	Organic Matter fine aerosol
SURF_ug_PM_OMCOARSE	OM coarse $[\mu g/m^3]$	Organic Matter coarse aerosol
SURF_ug_SEASALT_F	Sea salt fine aerosol $[\mu g/m^3]$	

Table 3.2: List of output parameters

Continued on next page

Table 3.2 – continued from previous page

Parameter name	Short description	Comments
SURF_ug_SEASALT_C	Sea salt coarse aerosol $[\mu g/m^3]$	
SURF_ug_SEASALT	Sea salt $[\mu g/m^3]$	Sum of fine and coarse sea salt
SURF_ug_DUST_ROAD_F	Road dust fine aerosol $[\mu g/m^3]$	
SURF_ug_DUST_ROAD_C	Road dust coarse aerosol $[\mu g/m^3]$	
SURF_ug_DUST_WB_F	Windblown dust fine $[\mu g/m^3]$	
SURF_ug_DUST_WB_C	Windblown dust coarse $[\mu g/m^3]$	
SURF_ug_DUST_SAH_F	Saharan dust fine $[\mu g/m^3]$	From Boundary conditions
SURF_ug_DUST_SAH_C	Saharan dust coarse $[\mu g/m^3]$	From Boundary conditions
SURF_ug_DUST_NAT_F	Natural dust fine $[\mu g/m^3]$	Windblown and Saharan
SURF_ug_DUST_NAT_C	Natural dust coarse $[\mu g/m^3]$	Windblown and Saharan
SURF_ug_DUST	Mineral dust $[\mu g/m^3]$	From all sources
SURF_ug_PM10	$PM_{10}$ dry $[\mu g/m^3]$	
SURF_ug_PM10_rh50	$PM_{10}$ wet $[\mu g/m^3]$	PM <sub>10</sub> particle water at 50 %rh
SURF_ug_PM25	$PM_{2.5} dry [\mu g/m^3]$	Includes fine PM and 27% of coarse NO <sub>3</sub>
SURF_ug_PM25_rh50	$PM_{2.5}$ wet $[\mu g/m^3]$	PM <sub>2.5</sub> particle water at 50 %rh
SURF_ug_PM25X	$PM_{2.5}$ dry $[\mu g/m^3]$	Includes fine PM and 27% of coarse NO <sub>3</sub> , EC and OM
SURF_ug_PM25X_rh50	$PM_{2.5} [\mu g/m^3]$	As PM25X + particle water at 50 %rh
SURF_ug_PMFINE	Fine PM [ $\mu g/m^3$ ]	Sum of all fine aerosols
SURF_ug_PPM25	Primary PIPM25I [ $\mu g/m^3$ ]	Anthropogenic emissions
SURF_ug_PPM_C	Primary coarse PM [ $\mu g/m^3$ ]	Anthropogenic emissions
SURF_ug_PM25_FIRE	$PM_{2.5}$ from forest fires $[\mu g/m^3]$	Sum of BC, OC and rest PM <sub>2.5</sub>
Dry Depositions		
DDEP_SOX_m2Grid	Oxidized sulphur $[mg(S)/m^2]$	For a grid cell landuse area weighted
DDEP_SOX_m2Conif	Oxidized sulphur $[mg(S)/m^2]$	To coniferous forest
DDEP_NOX_m2Grid	Oxidized nitrogen $[mg(N)/m^2]$	For a grid cell landuse area weighted
DDEP_NOX_m2Decid	Oxidized nitrogen $[mg(N)/m^2]$	To decideous forest
DDEP_RDN_m2Grid	Reduced nitrogen $[mg(N)/m^2]$	For a grid cell landuse area weighted
DDEP_RDN_m2Seminat	Reduced nitrogen $[mg(N)/m^2]$	To semi-natural
Wet Depositions		
WDEP_PREC	Precipitation [mm]	
WDEP_SOX	Oxidized sulphur $[mg(S)/m^2]$	
WDEP_SS	Sea salt $[mg/m^2]$	
Others		
AOD	Aerosol Optical Depth at 550nm	Experimental
Area_Crops_Frac	Area fraction of crops	Available for several landuses
VG_NO3_F_Grid	Dry deposition velocity of fine NO <sub>3</sub>	Grid cell average
Meteorological parameters		
USTAR_GRID	$U^*$ grid averaged	Available for several landuses
T2m	Temperature at $2m \ [^{\circ}C]$	
rh2m	Fractional relative humidity at 2m	

# 3.2 ASCII outputs: sites and sondes

Two main options are available for the output of ASCII files for comparison with measurements or detailed model analysis. These are

sites output of surface concentrations for a set of specified measurement site locations.

sondes output of concentrations for the vertical column above a set of specified locations.

Both sites and sondes are specified and handled in similar ways, in the module Sites\_ml.f90, so we treat them both together below. Locations are specified in the input files sites.dat and sondes.dat. The files start with a description of its content followed by a list of the stations. For example, a sondes.dat input file may look like this:

Listing 3.1: Minimum modrun.sh example.

```
# "Sondes: names, locations, elevations"
# "Area: EMEP-Europe"
# "ix: x coordinate"
# "iy: y coordinate"
# "lev: vertical coordinate (20=ground)"
: Units index
: Coords LatLong
: VertCoords EMEPsigma
: DomainName NA
name lat long lev #HEADERS
   deg deg level #SKIP
#DATA:
Uccle
                 50.80
                         4.35 20 ! comment
                 60.13
                         -1.18 20 ! comment
Lerwick
                 67.39
                         26.65 20 ! comment
Sodankyla
                78.93
                         11.88 20 ! comment
Ny_Alesund
Hohenpeissenberg 47.80
                         11.02 20 ! comment
```

The first line in each file is a header with file content. Then, the contents are described in more detail. Text strings after # are just clarifying comments. 'Area', e.g., is the domain to which the stations belong, e.g. 'Northern Hemisphere'.

Text after: is read in by the model:

Units Either 'deg' (degrees) or 'index' (model grid indices).

**Coords** Either 'LatLong' (latitudes/longitudes) or 'ModelCoords' (indices of the grid box in which the station is located).

**VertCoords** Vertical coordinate system that is used in the model (usually 'EMEPsigma').

Both sites.dat and sondes.dat files are optional, but recommended. The species and meteorological data requested for site and sonde output are specified in My\_Outputs.f90 by the use of arrays. Only a few met fields are defined so far but more can be added into Sites\_ml.f90 as required.

The output files  $sites_2014.csv$  and  $sondes_2010.csv$  are comma separated files that can be read by excel. If you include the whole year, or the  $31^{st}$  December,  $sites_2015.csv$  and  $sondes_2015.csv$  are also included in the output.

**CHAPTER** 

**FOUR** 

## SUBMITTING A RUN

In this chapter we provide detailed information on how to run the regional EMEP/MSC-W model for two different types of simulations, namely:

**Base run** This is the default set up for yearly transport model calculations in  $50 \times 50 km^2$  grid.

**Scenario run** A run with reduced emissions from a particular country or several countries is called a "Scenario run". It is the basic type of run for the source-receptor calculations.

Details about the submission of these different types of runs are given below. We suggest that users test the "Base run" first, which can be done without significant changes in the code itself. One can also use the outputs of such a run in the future as a reference run for the other simulations.

# 4.1 Base run

This is an example of a minimum modrun. sh script to run the model.

Listing 4.1: Minimum modrun.sh example.

```
#!/bin/bash

# Minimalistic script for run the EMEP/MSC-W model

# Link the input data
inputdir=.
ln -s $inputdir/input/* . # Other input files

# Run the model
mpirun $inputdir/code/Unimod

# Clean the links to the input data
find . -type l -delete
```

This bash shell script is designed so that users can easily adapt it to fit their needs. It contain the minimum information required to run the EMEP/MSC-W model. The script should be self-explanatory. It assumes one directory for input data other than meteorology data. The metdata for the year, and for January  $1^{st}$  the following year (365 +1 files) is linked directly in the <code>config\_emep.nml</code> file. You need to set the right paths for the input directories. All the input files in the input directories are linked to the directory you are working from.

#### 4.1.1 config\_emep.nml

The model has a namelist system. It is possible to set different constants and flags for running the model. The constants and flags itself is defined in ModelConstants\_ml.f90, while they are set in the namelist file under

ModelConstants\_config parameter. Some of these are briefly explained in ch-inputfiles. Model gets information about running for special cases from this file. The datasets provided are for the EMEP grid EECCA.

The different parameters for the model run are set in the config\_emep.nml file. In the very beginning of this, the section INPUT\_PARA has all these variables including the link to the meteorology data. The trendyear can be set to change the boundary emissions for earlier and future years, see the modules BoundaryConditions\_ml.f90 and GlobalBCs\_ml.f90 to understand better what the trendyear setting does. The default setting is the meteorological year you are running for, in this case 2014. The runlabel1 option sets the name of the different output NetCDF files, see Section 3. The startdate and enddate parameters are set for the time period you want the model to run (YYYY,MM,DD), and you need meteorology data for the period, as shown in Listing 4.2.

Listing 4.2: Basic namelist example.

```
&INPUT_PARA
 GRID
       = 'EECCA',
 iyr\_trend = 2014,
 runlabel1 = 'Base',
 runlabel2 = 'Opensource_Setup_2016',
 startdate = 2014,01,01,000000,
 enddate = 2014,01,10,000000,
&end
&Machine_config
 DataPath(1) = '../input', ! define 'DataDir' keyword
&ModelConstants config
                       = '../meteoYYYY/meteoYYYYMMDD.nc',
 meteo
 DegreeDayFactorsFile = 'MetDir/DegreeDayFactors.nc',
          = 'DataDir/EECCA',
 EmisDir
 emis_inputlist(1)%name= 'EmisDir/gridPOLL', ! ASCII
 ! -----Sub domain x0 x1 y0 y1
 RUNDOMAIN = 36, 100, 50, 150 ! EECCA sub-domain
&end
```

In Listing 4.2, the model is run for the period 1 January to 10 January 2014 and the trend year used is 2014. Output files will be stored with the name 'Base' and the meteorological correspond to the 'EECCA' grid.

It is possible to run the model on a smaller domain than the full regional model domain, as defined by indexes x and y. For the 'EECCA' gtid  $x=1,\ldots,132; y=1,\ldots,159$ . To set a smaller domain, use RUNDOMAIN variable in the ModelConstants\_config namelist to idicate the sub-domain indexes. In Listing 4.2, RUNDOMAIN defines a subdomain with  $x=36,\ldots,100; y=50,\ldots,150$ .

To run the model, the correct path to the EMEP/MSC-W model code has to be set (mpirun path\_to\_the\_modelcode/Unimod).

It is recommended to submit the script as a batch job. Please check the submission routine on the computer system you are running on. In the newer model versions (since 4.0) the number of nodes is set automatically from what is asked for when submitting a job. The approximate time and CPU usage is described in Section 1.2.

When the job is no longer running or in the queue, it is either finished or has crashed for some reason. If the model run crashed, an error message will give information on what was missing or wrong in the routine. If the run was successful, a message

will be stated at the end of the log file, before printing the Timing.out file.

The model results will be written to this same directory. Please make sure there is enough disk place for the model results. For more information about the model result output files, see Section 3.

If for some reason the model crashed, please check both the log and the error file for any clue of the crash. After fixing the problem the job can be submitted again. If the model has crashed, then the links to the input data are not removed.

The script can also be submitted interactively, and either have the output written to the screen or to named error and output log files. The variables wanted in the output are specified in the OutputConcs\_config, OutputDep\_config and in the OutputMisc\_config parameters respectively for surface concentrations, depositions and some miscellaneous outputs.

# 4.2 Nesting

The boundary conditions needed for EMEP MSC-W model is provided with the input data. The model can read Boundary conditions data from other models as well. These data has to be in NetCDF format. The boundary conditions needed for EMEP MSC-W model is provided with the input data. The model can read Boundary conditions data from other models as well. These data has to be in NetCDF format.

Different Nesting modes are:

- read the external BC data only,
- produce EMEP BC data from the simulation,
- read the external BC data and produce EMEP BC data,
- using the default EMEP BC data from the input data directory and write out EMEP BC at the end of the simulation,
- read the external BC data only in the beginning of the simulation,
- read external BC at the beginning of the simulation and write out EMEP BC at the end of the simulation.

These options are controlled by the MODE\_READ and MODE\_SAVE variables in Nest\_config namelist, in config\_emep.nml file. The mode options are:

#### MODE READ

'NONE' do nothing (default).

'START' read at the start of run.

**'FORECAST'** read at the start of run, if the files are found.

'NHOUR' read at given NHOURREAD hourly intervals. NHOURREAD is set in Nest\_config and should be an integer fraction of 24.

#### MODE\_SAVE

'NONE' do nothing (default).

'END' write at end of run.

'FORECAST' write every OUTDATE (1:FORECAST\_NDUMP). OUTDATE and FORECAST\_NDUMP are set in Nest\_config.

**'NHOUR'** write at given *NHOURSAVE* hourly intervals. NHOURSAVE is set in Nest\_config and should be an integer fraction of 24.

4.2. Nesting 21

If BC data are read at NHOURREAD intervals from the file defined by template\_read\_BC in Nest\_config. The IC data (entire 3D domain) will be set at start of run from the file defined by template\_read\_3D in Nest\_config.

#### 4.2.1 Write BCs from EMEP MSC-W model

Listing 4.3 shows an example to write every 3 hours into daily Nest/BC files. Output file name is defined by template\_write ('BC\_YYYYMMDD.nc'), where 'YYYYMMDD' is replaced by corresponding date.

All advected model variables will be written out for the sub-domain defined by out\_DOMAIN (x = 60, ..., 107; y = 11, ..., 58). If no out\_DOMAIN is given, the model inner domain will be written out.

Listing 4.3: Write BCs configuration example.

```
&Nest_config
 MODE_READ
                = 'NONE',
                                  ! do not read external BC
               = 'NHOUR',
 MODE_SAVE
                                  ! write BCs
 NHOURSAVE = 3,
                                 ! every 3 hours
 template_write = 'BC_YYYYMMDD.nc' ! to your (daily) BC output file
                                  ! (8 records per file)
 !---- Sub domain for write modes
 out_DOMAIN
               = 60, 107, 11, 58,
                                ! istart, iend, jstart, jend
&end
```

#### 4.2.2 Read BCs from EMEP MSC-W model

Listing 4.4 shows an example to read every 3 hours from the Nest/BC files created previously by running Listing 4.3. Please note that the model sub-domain for a nested run is set by RUNDOMAIN, as shown in Listing 4.2.

Listing 4.4: Read BCs configuration example.

```
&Nest_config

MODE_READ = 'NHOUR', ! read external BC

NHOURREAD = 3, ! every 3 hours

template_read_BC = 'BC_YYYYMMDD.nc' ! your (daily) BC input file

MODE_SAVE = 'NONE', ! do not write BCs

&end
```

#### 4.2.3 Read external BCs

Reading BCs from a different model is more involved than the previous example. The vertical axis and variables in the file need to be mapped to the corresponding model variables.

Listing 4.5 shows an example to read every 3 hours from an external BC file. The model will read 3 variables from MyBC.nc:  $O_3$ , NO, and  $NO_2$ . The maping between the MyBC.nc variables and the corresponding model variables is defined in the ExternalBICs\_bc namelist.

Listing 4.5: External BCs configuration example.

```
&Nest_config

MODE_READ = 'NHOUR', ! read external BC

NHOURREAD = 3, ! every 3 hours

template_read_BC = 'MyBC.nc' ! from your BC input file

MODE_SAVE = 'NONE', ! do not write BCs
```

```
&end
&ExternalBICs_config

USE_EXTERNAL_BIC = T,

EXTERNAL_BIC_NAME= 'MyBICScenario', ! variable mapping, see ExternalBICs_bc

TOP_BC = T, ! use top BC also from your BC file
filename_eta = 'filename.zaxis',! text file containing the
! description of your BC file

&end
&ExternalBICs_bc
description='MyBICScenario','Version name',3, ! name,version,size
map_bc=! emep,external,frac,wanted,found,IXADV,
'O3','O3_VMR_inst',1.0,T,F,-1,
'NO','NO_VMR_inst',1.0,T,F,-1,
'NO2','NO2_VMR_inst',1.0,T,F,-1,
&end
```

#### Vertical coordinate

In ordet the determine the vertical levels on the external BC file ('MyBC.nc' in Listing 4.5), the following checks will take place in the following order:

- 1.  $\eta$  (eta) coordinate: If the variable hyam (hybrid a coefficient at layer midpoint) is found,  $\eta$  is calculated from hyam and hyam variables on the file.
- 2.  $\sigma$  (sigma) coordinate: If the vertical level is indexed by variable k.
- 3.  $\eta$  coordinate: If the file defined by variable filename\_eta exist ('filename.zaxis' in Listing 4.5),  $\eta$  is derived from vct and vctsize variables on the file.
- 4. **pressure coordinate:** If the vertical level is indexed by variable lev.

Independent of the coordinates of the BC file, the BC levels will be interpolated into EMEP model levels. If the BC file level structure is not recognized, and there is no filename\_eta provided, the model will write an error message and stop execution.

An example of the filename\_eta for EMEP model levels is given below. Here the vct variable describes the model level boundaries in hybrid eta coordinate:

Listing 4.6: filename eta for EMEP model levels.

```
zaxistype = hybrid
size
     : 20
         : k
name
longname : vertical sigma coordinates
         : sigma_level
units
         : 0.0200 0.0600 0.1000 0.1425 0.1950 0.2635 0.3470
levels
       0.4365 0.5215 0.5990 0.6695 0.7330 0.7895 0.8390
       0.8815 0.9170 0.9455 0.9670 0.9820 0.9940
vctsize
vct.
       10000. 09600. 09200. 08800. 08350. 07750. 06980.
       06080. 05190. 04380. 03640. 02970. 02370. 01840.
       01380. 00990. 00670. 00420. 00240. 00120. 00000.
       0.0000 0.0400 0.0800 0.1200 0.1650 0.2250 0.3020
       0.3920 0.4810 0.5620 0.6360 0.7030 0.7630 0.8160
       0.8620 0.9010 0.9330 0.9580 0.9760 0.9880 1.0000
```

4.2. Nesting 23

vct is the vertical coordinate table describing the hybrid a and b paramters at the layer interfaces in  $\eta$  coordinate system (hyai and hybi). They must respect the following constraints:

- $hyai_1 = 0$  and  $hybi_1 = 1$ ;
- $hyai_0 = P_t$  and  $hybi_0 = 0$ .
- $P_t$  is the pressure at top of the model domain.

In this file, the first 21 values in vct represent hyai and the remaining 21 represent hybi values in hPa.

#### Variable mapping

The variables to be used from the external boundary condition data are given in the ExternalBICS\_bc namelist in the config\_emep.nml file. In Listing 4.5,  $map\_bc$  maps 3 variables in the 'MyBC.nc' file to 3 model variables (O<sub>3</sub>, NO, and NO<sub>2</sub>). On each line of  $map\_bc$  contains the 6 elements:

- 1. Variable name in EMEP MSC-W model, e.g. 'O3'.
- 2. Variable name in the External BC data file, e.g. 'O3\_VMR\_inst'.
- 3. External BC component to EMEP component fraction, e.g. 1.0.
- 4. Is this component wanted or not, set to T or .true. to read the variable.
- 5. Was the BC variable found on the file, will be set by the model on run time.
- 6. Index of the advected model variable, will be set by the model on run time.

The fraction is helpful, when one has to map a variable that is explicitly not in the model but a fraction of that variable can be mapped to a matching variable in the model.

Unit conversions are delegated to the Units\_ml.f90 module. The supported units are:  $\mu g/m^3$ ,  $\mu g(S)/m^3$ ,  $\mu g(N)/m^3$ ,  $\mu g(C)/m^3$ , ppb, mixing ratio (mol/mol) and mass mixing ratio (kg/kg).

If the BC data has different units, either convert them into one of the above mentioned units in pre-processing or add the respective conversion factor in the module Units\_ml.f90.

# 4.3 Source Receptor (SR) Runs

The EMEP/MSC-W model can be used to test the impact of reduced emission of one or more pollutants from a particular country or a number of countries. Such runs are called "Scenario runs". They are the basic runs for source-receptor calculations.

Emission factors for reduced emissions of pollutants from different sectors and countries can be defined in the input file called femis.dat, which can be found in the downloaded input data directory, see section Section 2.2.6.

Listing 4.7: femis.dat for a base run.

Name	7	sox	nox	CO	VOC	nh3	pm25	pmco
27	0	1.0	1.0	1.0	1.0	1.0	1.0	1.0

This base run example means that there are (1.0), no emission reductions of  $SO_x$ ,  $NO_x$ , CO, VOC,  $NH_3$ ,  $PM_{2.5}$  and  $PM_{co}$  from all sectors in the UK.

• The first column of the second line represents the country code. (27 is the code for UK.) The codes for all countries can be found in Fortran module Country\_ml.f90. Please note that the country code must be the same as in the emission files for the given country. Some countries and areas are divided into sub-areas in the emission files. In this case, one line for each sub-area has to be included into the femis.dat file. Countries and areas where emissions are given for sub-areas include the Russian Federation, Germany and all sea areas.

- The second column of the second line represents the sector and "0" means all sectors. Here one can write the appropriate sector code if the emission is reduced only from a specific sector. The description of each sector can also be found in the Fortran module EmisDef\_ml.f90.
- The columns under the pollutant names show the emission factors for the given pollutants. For example, 0.7 would mean 70% of the original emission, thus 30% reduction.
- The number ("7") following the first text ("Name") in the first line gives the number of pollutants treated in the file

An example of femis. dat file describing 50% reduced emission of  $SO_x$  from sector 10 (the emission from agriculture) in the UK is shown in Listing 4.8.

Listing 4.8: femis.dat for 50%  $SO_x$  reduction from sector 10 over UK.

Name	7	sox	nox	СО	VOC	nh3	pm25	pmco
27	10	0.5	1.0	1.0	1.0	1.0	1.0	1.0

For a scenario run femis.dat file should be edited manually depending on the level of reduction one would like to test with any pollutant from any sector and/or any country. Several lines can be written in the file.

## REFERENCES

- **Andersson-Sköld and Simpson, 1997** Y. Andersson-Sköld and D. Simpson. Comparison of the chemical schemes of the EMEP MSC-W and the IVL photochemical trajectory models *Atmos. Environ.*, 1999, 33, 1111-1129
- **Emberson** *et al.*, **2000** L. Emberson, D. Simpson, J.-P. Tuovinen, M.R. Ashmore and H.M. Cambridge. Towards a model of ozone deposition and stomatal uptake over Europe. EMEP/MSC-W Note 6/2000.
- **Fagerli et al., 2004** H. Fagerli, D. Simpson and S. Tsyro. Unified EMEP model: Updates. In *EMEP Status Report* 1/2004, Transboundary acidification, eutrophication and ground level ozone in Europe. Status Report 1/2004, pages 11–18. The Norwegian Meteorological Institute, Oslo, Norway, 2004.
- **Gardner** *et al.*, **1997** R.M. Gardner, K. Adams, T. Cook, F. Deidewig, S. Ernedal, R. Falk, E. Fleuti, E. Herms, C.E. Johnson, M. Lecht, D.S. Lee, M. Leech, D. Lister, B. Masse, M. Metcalfe, P. Newton, A. Schmitt, C. Vandenbergh and R. Van Drimmelen. The ANCAT/EC global inventory of NO:math:\_x emissions from aircraft. *Atmos. Environ.*, 31 (12): 1751-1766, 1997.
- **Jonson** *et al.*, **2001** J.E.Jonson, J.K.Sundet and L. Tarrasón. Model calculations of present and future levels of ozone and ozone precursors with a global and a regional model. *Atmos. Environ.*, 35: 525-537, 2001.
- **Köhler** *et al.*, **1995** I. Köhler, R. Sausen and G. Klenner. NO:math:\_x production from lightning. The impact of NO:math:\_x emissions from aircraft upon the atmosphere at flight altitudes 8-15 km (AERONOX), edited by U. Schumann, final report to the Commission of the European Communities, Deutch Luft und Raumfart, Oberpfaffenhofen, Germany, 343–345, 1995.
- **Logan, 1998** J. A. Logan. An analysis of ozonesonde data for the troposhere: Recommendations for testing 3-D models and development of a gridded climatology for troposheric ozone. *J. Geophys. Res.*, 10 (D13):16, 115–116, 149, 1998.
- **Passant, 2002** Passant NR., Speciation of UK emissions of non-methane volatile organic compounds. AEA Technology Report ENV-0545, Culham, Abingdon, United Kingdom, 2002.
- Simpson et al., 2003 D. Simpson, H. Fagerli, J.E. Jonson, S. Tsyro, P. Wind and J.-P. Tuovinen. *The EMEP Unified Eulerian Model. Model Description. EMEP MSC-W Report 1/2003*. The Norwegian Meteorological Institute, Oslo, Norway, 2003.
- Simpson and Emberson, 2006 D. Simpson and L. Emberson. Ozone fluxes Updates. In *Transboundary Acidification, Eutrophication and Ground Level Ozone in Europe from 1990 to 2004 in support for the review of the Gothenburg Protocol. EMEP Status Report 1/2006*, pages 63–79. The Norwegian Meteorological Institute, Oslo, Norway, 2006.
- Simpson *et al.*, **2012** Simpson, D., Benedictow, A., Berge, H., Bergström, R., Emberson, L. D., Fagerli, H., Flechard, C. R., Hayman, G. D., Gauss, M., Jonson, J. E., Jenkin, M. E., Nyri, A., Richter, C., Semeena, V. S., Tsyro, S., Tuovinen, J.-P., Valdebenito, Á., and Wind, P. The EMEP MSC-W chemical transport model technical description *Atmos. Chem. Physics*, 2012, 12, 7825-7865
- **Tuovinen** *et al.*, **2004** Tuovinen, J.-P.; Ashmore, M.; Emberson, L. & Simpson, D. Testing and improving the EMEP ozone deposition module Atmos. Environ., 2004, 38, 2373-2385

Wiedinmyer *et al.*, **2011** Wiedinmyer, C., Akagi, S. K., Yokelson, R. J., Emmons, L. K., Al-Saadi, J. A., Orlando, J. J., and Soja, A. J.: The Fire INventory from NCAR (FINN): a high resolution global model to estimate the emissions from open burning, Geosci. Model Dev., 4, 625–641,doi:10.5194/gmd-4-625-2011, 2011

#### Todo

- Spellcheck
- Un numbered chapter Section 5:
- :numref: `does not work ch-inputfiles:
- Center in page Table 2.2, Table 2.3, Table 3.1
- Wrap long lines in Table 3.2
- · Next release
  - Section 3: sites and sondes NetCDF output
  - ch-subitarun: output namelist
  - Section 5: NatBib/BibTex references