思考题1: 阅读汇编代码kernel/arch/aarch64/boot/raspi3/init/start.S。说明ChCore是如何选定主CPU,并阻塞其他其他CPU的执行的

寄存器mpidr_el1传入寄存器x8中,mpidr_el1存放cpuid,将x8与0xFF & 操作,获取当前CPUid,如果是0号(即主CPU),则跳转至primary;

如果不是0号,则会在运行至wait_until_smp_enabled之后一直循环,实现阻塞效果,直到主CPU初始化完成,正确设置secondary_boot_flag,其它核跳出循环,执行secondary_init_c,进入初始化阶段

```
mrs x8, mpidr_el1
       and x8, x8, \#0xFF
       cbz x8, primary
wait_for_bss_clear:
   adr x0, clear_bss_flag
   ldr x1, [x0]
   cmp x1, #0
   bne wait_for_bss_clear
   /* Set cntkctl_el1 to enable cntvct_el0.
        * Enable it when you need to get current tick
         * at ELO, e.g. Running aarch64 ROS2 demos
   mov x10, 0b11
   msr cntkctl_el1, x10 */
   /* Turn to ell from other exception levels. */
   bl arm64_elx_to_el1
   /* Prepare stack pointer and jump to C. */
   mov x1, #INIT_STACK_SIZE
   mul x1, x8, x1
    adr x0, boot_cpu_stack
    add x0, x0, x1
    add x0, x0, #INIT_STACK_SIZE
    mov sp, x0
wait_until_smp_enabled:
   /* CPU ID should be stored in x8 from the first line */
   mov x1, #8
   mul x2, x8, x1
   ldr x1, =secondary_boot_flag
   add x1, x1, x2
   ldr x3, [x1]
   cbz x3, wait_until_smp_enabled
   /* Set CPU id */
   mov x0, x8
   b secondary_init_c
   /* Should never be here */
   b .
```

思考题2: 阅读汇编代码kernel/arch/aarch64/boot/raspi3/init/start.S, init_c.c以及 kernel/arch/aarch64/main.c,解释用于阻塞其他CPU核心的secondary_boot_flag是物理地址还是虚拟地址? 是如何传入函数enable_smp_cores中,又是如何赋值的(考虑虚拟地址/物理地址)?

1. 物理地址, secondary_boot_flag定义在init_c.c中,在引导时进入的是init段(低地址) / 同时观察函数: secondary_init_c 在此处其它核开启页表,在跳出阻塞之后才执行,这同样说明阻塞时其它核的页表并没有开启,因此使用的是物理地址

2.CPU0执行 main函数的参数中paddr_t boot_flag 即为smp的boot_flag地址,是物理地址,main函数调用enable_smp_cores(paddr_t boot_flag)将参数传入;如何赋值:由于CPU0启用了页表,调用phys_to_virt将boot_flag转为虚拟地址,放入对应的内存中

```
void secondary_init_c(int cpuid)
{
    el1_mmu_activate();
    secondary_cpu_boot(cpuid);
}
wait_until_smp_enabled:
   /* CPU ID should be stored in x8 from the first line */
    mov x1, #8
    mul x2, x8, x1
    ldr x1, =secondary_boot_flag
    add x1, x1, x2
    ldr x3, [x1]
   cbz x3, wait_until_smp_enabled
    /* Set CPU id */
    mov x0, x8
    b secondary_init_c
    /* Should never be here */
void main(paddr_t boot_flag, void *info)
void enable_smp_cores(paddr_t boot_flag)
    int i = 0;
   long *secondary_boot_flag;
    /* Set current cpu status */
    cpu_status[smp_get_cpu_id()] = cpu_run;
    secondary_boot_flag = (long *)phys_to_virt(boot_flag);
    for (i = 0; i < PLAT_CPU_NUM; i++) {
        secondary_boot_flag[i] = 1;
        flush_dcache_area((u64) secondary_boot_flag,
                  (u64) sizeof(u64) * PLAT_CPU_NUM);
        asm volatile ("dsb sy");
        while (cpu_status[i] == cpu_hang)
        kinfo("CPU %d is active\n", i);
    /* wait all cpu to boot */
    kinfo("All %d CPUs are active\n", PLAT_CPU_NUM);
   init_ipi_data();
}
```

练习 1:在 kernel/sched/policy_rr.c 中完善 rr_sched_init 函数,对 rr_ready_queue_meta 进行初始化。在完成填写之后,你可以看到输出"Scheduler metadata is successfully initialized!"并通过 Scheduler metadata initialization 测试点。

对每个CPU核心初始化队列和队列锁

```
int rr_sched_init(void)
{
    /* LAB 4 TODO BEGIN (exercise 1) */
    /* Initial the ready queues (rr_ready_queue_meta) for each CPU core */
    for (int i = 0; i < PLAT_CPU_NUM; ++i) {
            init_list_head(&rr_ready_queue_meta[i].queue_head);
            rr_ready_queue_meta[i].queue_len = 0;
            lock_init(&rr_ready_queue_meta[i].queue_lock);
    }
    /* LAB 4 TODO END (exercise 1) */
    test_scheduler_meta();
    return 0;
}</pre>
```

练习 2:在 kernel/sched/policy_rr.c 中完善 __rr_sched_enqueue 函数,将thread插入到cpuid对应的就绪队列中。在完成填写之后,你可以看到输出"Successfully enqueue root thread"并通过 Schedule Enqueue 测试点。

通过list_append将节点加入对应cpu队列,同时更新长度

```
int __rr_sched_enqueue(struct thread *thread, int cpuid)
        /* Already in the ready queue */
        if (thread->thread_ctx->state == TS_READY) {
                return -EINVAL;
        }
        thread->thread_ctx->cpuid = cpuid;
        thread->thread_ctx->state = TS_READY;
        obj_ref(thread);
        /* LAB 4 TODO BEGIN (exercise 2) */
        /* Insert thread into the ready queue of cpuid and update queue length */
        /* Note: you should add two lines of code. */
        list_append(&thread->ready_queue_node,
&rr_ready_queue_meta[cpuid].queue_head);
        rr_ready_queue_meta[cpuid].queue_len += 1;
        /* LAB 4 TODO END (exercise 2) */
        return 0;
}
```

练习 3:在 kernel/sched/sched.c 中完善 find_runnable_thread 函数,在就绪队列中找到第一个满足运行条件的线程并返回。在 kernel/sched/policy_rr.c 中完善 __rr_sched_dequeue 函数,将被选中的线程从就绪队列中移除。在完成填写之后,运行 ChCore 将可以成功进入用户态,你可以看到输出"Enter Procmgr Root thread (userspace)"并通过 Schedule Enqueue 测试点。

根据提示,遍历线程列表,如果线程没有被阻塞,且对应内核栈空闲或者线程为当前线程,即为选中的可以运行的线程。

在列表中删除节点, 更新队列长度。

练习 4:在kernel/sched/sched.c中完善系统调用sys_yield,使用户态程序可以主动让出CPU核心触发线程调度。此外,请在kernel/sched/policy_rr.c 中完善rr_sched函数,将当前运行的线程重新加入调度队列中。在完成填写之后,运行 ChCore 将可以成功进入用户态并创建两个线程交替执行,你可以看到输出"Cooperative Schedluing Test Done!"并通过 Cooperative Schedluing 测试点。

sys_yield中触发调度函数 rr_shed中将线程重新加入队列

```
void sys_yield(void)
{
    current_thread->thread_ctx->sc->budget = 0;
    /* LAB 4 TODO BEGIN (exercise 4) */
    /* Trigger sched */
    /* Note: you should just add a function call (one line of code) */
    sched();
    /* LAB 4 TODO END (exercise 4) */
    eret_to_thread(switch_context());
}

    /* LAB 4 TODO BEGIN (exercise 4) */
    /* Enqueue current running thread */
    /* Note: you should just add a function call (one line of code) */
    rr_sched_enqueue(old);    /* LAB 4 TODO END (exercise 4)
*/
```

练习 5:请根据代码中的注释在kernel/arch/aarch64/plat/raspi3/irq/timer.c中完善plat_timer_init函数,初始化物理时钟。需要完成的步骤有:

```
1. 读取 CNTFRQ_ELO 寄存器,为全局变量 cntp_freq 赋值。
2. 根据 TICK_MS(由ChCore决定的时钟中断的时间间隔,以ms为单位,ChCore默认每10ms触发一次时钟中断)和 cntfrq_elo (即物理时钟的频率)计算每两次时钟中断之间 system count 的增长量,将其赋值给 cntp_tval 全局变量,并将 cntp_tval 写入 CNTP_TVAL_ELO 寄存器!
3. 根据上述说明配置控制寄存器CNTP_CTL_ELO。
```

由于启用了时钟中断,但目前还没有对中断进行处理,所以会影响评分脚本的评分,你可以通过运行 ChCore观察是否有"[TEST] Physical Timer was successfully initialized!: OK"输出来判断是否正确对物理 时钟进行初始化。

说明见汉字注释

```
void plat_timer_init(void)
   u64 timer_ctl = 0;
   u32 cpuid = smp_get_cpu_id();
   /* Since QEMU only emulate the generic timer, we use the generic timer here
*/
    asm volatile ("mrs %0, cntpct_el0":"=r" (cntp_init));
    kdebug("timer init cntpct_el0 = %lu\n", cntp_init);
    /* LAB 4 TODO BEGIN (exercise 5) */
    /* Note: you should add three lines of code. */
    /* Read system register cntfrq_el0 to cntp_freq*/
    asm volatile ("mrs %0, cntfrq_el0":"=r" (cntp_freq));
    # 从cntfrq_el0读值到cntp_freq变量
    /* Calculate the cntp_tval based on TICK_MS and cntp_freq */
    cntp_tval = (cntp_freq * TICK_MS / 1000);
    # 计算两次时钟中断之间 system count 的增长量,赋值给cntp_tval
    /* Write cntp_tval to the system register cntp_tval_el0 */
    asm volatile ("msr cntp_tval_el0, %0"::"r" (cntp_tval));
    # 将cntp_tval写入cntp_tval_el0寄存器
    /* LAB 4 TODO END (exercise 5) */
    tick_per_us = cntp_freq / 1000 / 1000;
    /* Enable CNTPNSIRQ and CNTVIRQ */
    put32(core_timer_irqcntl[cpuid], INT_SRC_TIMER1 | INT_SRC_TIMER3);
    /* LAB 4 TODO BEGIN (exercise 5) */
    /* Note: you should add two lines of code. */
    /* Calculate the value of timer_ctl */
    timer_ctl = 0 << 1 | 1;
    /* write timer_ctl to the control register (cntp_ctl_el0) */
    asm volatile ("msr cntp_ctl_el0, %0"::"r" (timer_ctl));
    # 开启时钟中断 将对应的bit写入cntp_ctl_el0
    /* LAB 4 TODO END (exercise 5) */
    test_timer_init();
    return;
```

练习 6: 请在kernel/arch/aarch64/plat/raspi3/irq/irq.c中完善plat_handle_irq函数,当中断号irq为INT_SRC_TIMER1(代表中断源为物理时钟)时调用handle_timer_irq并返回。 请在kernel/irq/irq.c中完善handle_timer_irq函数,递减当前运行线程的时间片budget,并调用sched函数触发调度。 请在kernel/sched/policy_rr.c中完善rr_sched函数,在将当前运行线程重新加入就绪队列之前,恢复其调度时间片budget为DEFAULT_BUDGET。 在完成填写之后,运行 ChCore 将可以成功进入用户态并打断创建的"自旋线程"让内核和主线程可以拿回CPU核心的控制权,你可以看到输出"Hello, I am thread 3. I'm spinning."和"Thread 1 successfully regains the control!"并通过 Preemptive Scheduling 测试点。

case时钟中断,调用中断处理函数并返回 如果当前线程不为空则减少时间片,然后触发一次调度

```
/* LAB 4 TODO BEGIN (exercise 6) */
/* Call handle_timer_irq and return if irq equals INT_SRC_TIMER1 (physical timer)
*/
case INT_SRC_TIMER1:
    handle_timer_irq();
    return;
/* LAB 4 TODO END (exercise 6) */'

/* LAB 4 TODO BEGIN (exercise 6) */
/* Decrease the budget of current thread by 1 if current thread is not NULL */
    if (current_thread) {
            current_thread->thread_ctx->sc->budget -= 1;
    }
    /* Then call sched to trigger scheduling */
    sched();
/* LAB 4 TODO END (exercise 6) */
```

练习 7:在user/chcore-libc/musl-libc/src/chcore-port/ipc.c与kernel/ipc/connection.c中实现了大多数 IPC相关的代码,请根据注释补全kernel/ipc/connection.c中的代码。之后运行ChCore可以看到 "[TEST] Test IPC finished!" 输出,你可以通过 Test IPC 测试点。

1. register_server 根据注释参数ipc_routine为服务线程入口函数地址,回调线程为通过register_thread_cap获得的线程

```
@ipc_routine (the real ipc service routine entry)
/* LAB 4 TODO BEGIN (exercise 7) */
/* Complete the config structure, replace xxx with actual values */
/* Record the ipc_routine_entry */
    config->declared_ipc_routine_entry = ipc_routine;

/* Record the registration cb thread */
    config->register_cb_thread = register_cb_thread;
/* LAB 4 TODO END (exercise 7) */
```

- 2. create_connection
 - 1. 连接记录client端分配的虚拟地址
 - 2. 记录通过get_pmo_size获得到的client端分配pmo大小
 - 3. 记录client进程的capability
 - 4. 记录通过cap_copy得到的服务端对应capability

```
/* LAB 4 TODO BEGIN (exercise 7) */
/* Complete the following fields of shm, replace xxx with actual values */
    conn->shm.client_shm_uaddr = shm_addr_client;
    conn->shm.shm_size = shm_size;
    conn->shm.shm_cap_in_client = shm_cap_client;
    conn->shm.shm_cap_in_server = shm_cap_server;
/* LAB 4 TODO END (exercise 7) */
```

- 3. sys_register_client
 - 1. 在register_server中, register_cb_config设置了cb_thread的PC和SP
 - 2. 在ipc.c中,调用register_cb需要传递服务端线程入口地址
 - 3. 在sys_register_client中将其取出,设置对应属性,为跳转到该thread做准备

```
/* LAB 4 TODO BEGIN (exercise 7) */
/* Set target thread SP/IP/arg, replace xxx with actual arguments */
/* Note: see how stack address and ip are get in sys_register_server */
    arch_set_thread_stack(register_cb_thread, register_cb_config-
>register_cb_stack);
    arch_set_thread_next_ip(register_cb_thread, register_cb_config-
>register_cb_entry);
 * Note: see the parameter of register_cb function defined
 * in user/chcore-libc/musl-libc/src/chcore-port/ipc.c
    arch_set_thread_arg0(register_cb_thread, server_config-
>declared_ipc_routine_entry);
/* LAB 4 TODO END (exercise 7) */
/* Record PC as well as the thread's initial stack (SP). */
    register_cb_config->register_cb_entry =
            arch_get_thread_next_ip(register_cb_thread);
    register_cb_config->register_cb_stack =
            arch_get_thread_stack(register_cb_thread);
```

- 4. sys_ipc_regster_cb_return
 - 1. 填充server端的共享内存虚拟地址(通过参数传递)

```
/* LAB 4 TODO BEGIN (exercise 7) */
/* Complete the server_shm_uaddr field of shm, replace xxx with the actual value
*/
    conn->shm.server_shm_uaddr = server_shm_addr;
/* LAB 4 TODO END (exercise 7) */
```

- 5. ipc_thread_migrate_to_server
 - 1. IPC迁移至服务端线程运行
 - 2. 在sys_ipc_register_cb_return中 配置了handler线程的PC SP等
 - 3. 设置线程的PC和SP,通过handler_config
 - 4. 在ipc.h中 函数声明为typedef void (*server_handler)(void *shm_ptr, unsigned int max_data_len, unsigned int send_cap_num, badge_t client_badge);

5. 传递参数 共享内存地址,共享内存大小,发送capability的数量,Identification of the client(client的conn_budget)

```
/* Set the target thread SP/IP/arguments */
 /* LAB 4 TODO BEGIN (exercise 7) */
  * Complete the arguments in the following function calls,
  * replace xxx with actual arguments.
 /* Note: see how stack address and ip are get in sys_ipc_register_cb_return */
      arch_set_thread_stack(target, handler_config->ipc_routine_stack);
      arch_set_thread_next_ip(target, handler_config->ipc_routine_entry);
 /* see server_handler type in uapi/ipc.h */
      arch_set_thread_arg0(target, shm_addr);
      arch_set_thread_arg1(target, shm_size);
      arch_set_thread_arg2(target, cap_num);
      arch_set_thread_arg3(target, conn->client_badge);
 /* LAB 4 TODO END (exercise 7) */
 /*
  * Record the initial PC & SP for the handler_thread.
  * For serving each IPC, the handler_thread starts from the
   * same PC and SP.
      handler_config->ipc_routine_entry =
          arch_get_thread_next_ip(ipc_server_handler_thread);
      handler_config->ipc_routine_stack =
          arch_get_thread_stack(ipc_server_handler_thread);
      handler_config->ipc_exit_routine_entry =server_thread_exit_routine;
      handler_config->destructor = config->destructor;
Succeeded to build all targets
To use choore toolchain, please input the commnad
       export CMAKE_TOOLCHAIN_FILE=/home/voider/Desktop/OS-Course-Lab/build/toolchain.cmake
make[1]: Leaving directory '/home/voider/Desktop/OS-Course-Lab'
_____
Grading lab 4...(may take 10 seconds)
GRADE: Scheduler metadata initialization: 10
GRADE: Schedule Enqueue: 10
GRADE: Schedule Dequeue: 10
GRADE: Cooperative Schedluing: 20
GRADE: Preemptive Schedluing: 20
```

练习 8:请在树莓派3B上运行ChCore,并确保此前实现的所有功能都能正确运行。 见视频提交

练习 9:尝试优化在第三部分实现的IPC的性能,降低test_ipc_perf.bin的三个测试所消耗的cycle数根据判断,可以在调度方面优化,尝试过更改调度器代码,然而运行失败,因此通过更改参数试图产生优化效果

```
/* BUDGET represents the number of TICKs */
#define DEFAULT_BUDGET 1
/* The time interval of one tick in ms (by default, trigger one tick per 10 ms)
*/
#define TICK_MS 10

/* The config can be tuned. */
#define LOADBALANCE_THRESHOLD 5
#define MIGRATE_THRESHOLD 5
```

优化过程与效果

A	В	C	D	E	F	G	H		J	K	L	M
时钟中断间隔减小至5ms	60276534	11307016	22291042	61892004	11394804	22359962	63075853	11429178	22577308	61748130	11376999	22409437
中断减小至5ms 时间片增长至2	61859844	11025267	21819488	43549640	11385716	22411670	59127920	11373238	22323827	54845801	11261407	22184995
中断减小至5ms 为sysyield的线程增加时间片	59636235	11023645	20986321	58642356	11652013	22031566	60129356	11565235	22102365	59469316	11413631	21706751
增加时间片大小至2	60356496	10990141	21996731	60906069	11259535	22218326	62002554	11380593	22447998	61088373	11210090	22221018
CPU负载均衡的阈值长度增加至10	42325693	11267031	22308387	45239108	11245581	22307558	43824858	11362448	22549280	43796553	11291687	22388408
时钟中断时间增长至15	63653135	11087902	21852263	66223276	11279807	22180925	74788673	11365047	22455481	68221695	11244252	22162890
origin	67180094	11008400	21902427								11008400	21902427
	第一次test1	第一次test2	第一次test3	第二次test1	第二次test2	第二次test3	第三次test1	第三次test2	第三次test3	ave	ave	ave

简单分析:

- 1. 减少时钟中断:对于短任务影响不大,开销较大的任务会频繁触发中断
- 2. 减小时钟中断并增长时间片:可以及时中断阻塞的任务,且短任务退出之后会更快触发调度,但是中断次数过多也会增大开销
- 3. 修改了shed函数 对yield线程的shed单独处理,赋予两个时间片,变相提高yield线程的优先级,但是仍旧放到队尾,与1,2优化差别不大
- 4. 单纯增加时间片大小任务有多次执行机会。不会因为一次调度就放入队尾执行,能够更快将任务执 行完毕
- 5. 修改CPU负载均衡的阈值长度,防止过多线程与不同CPU绑定,从而造成CPU之间同步开销增大, 利用CPU的局部性,尽量放在一个核上完成
- 6. 增加时钟中断时间长度,虽然降低了CPU处理中断的频率,但是也会导致一些任务占用时间,因此 基本没有产生优化

总结,水平与时间有限,仅通过修改参数的方式进行优化,对于传递CAP的IPC基本上没有效果,其效果主要在第一个任务上面,其中增加核负载均衡阈值有利于减少跨核IPC通信,降低了线程切换的开销,且对于本身不传递CAP的任务来说,这种开销适当小一些会更好,因此对第一个任务产生了不错的优化效果