

Lab 04

Configure AAA Authentication on Cisco Routers

Name: Syed Asghar Abbas Zaidi Student ID: 07201

2.1 Objective

The Objectives of this lab are:

- Configure a local user account on R1 and configure authenticate on the console and vty lines using local AAA.
- Verify local AAA authentication from the R1 console and the PC-A client. Packet Tracer Configure AAA Authentication on Cisco Routers
- Configure server-based AAA authentication using TACACS+.
- Verify server-based AAA authentication from the PC-B client.
- Configure server-based AAA authentication using RADIUS.
- Verify server-based AAA authentication from the PC-C client.

2.2 Introduction

The network topology shows routers R1, R2 and R3. Currently, all administrative security is based on knowledge of the enable secret password. Your task is to configure and test local and server-based AAA solutions.

You will create a local user account and configure local AAA on router R1 to test the console and vty logins.

• User account: Admin1 and password admin1pa55

You will then configure router R2 to support server-based authentication using the TACACS+ protocol. The TACACS+ server has been pre-configured with the following:

- Client: **R2** using the keyword tacacspa55
- User account: Admin2 and password admin2pa55

Finally, you will configure router R3 to support server-based authentication using the RADIUS protocol. The RADIUS server has been pre-configured with the following:

- Client: **R3** using the keyword **radiuspa55**
- User account: Admin3 and password admin3pa55

The routers have also been pre-configured with the following:

- Enable secret password: **ciscoenpa55**
- OSPF routing protocol with MD5 authentication using password: MD5pa55



Note: The console and vty lines have not been pre-configured.

Note: IOS version 15.3 uses SCRYPT as a secure encryption hashing algorithm; however, the IOS version that is currently supported in Packet Tracer uses MD5. Always use the most secure option available on your equipment.

Topology




Figure 1: Topology

Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway	Switch Port
R1	G0/1	192.168.1.1	255.255.255.0	N/A	S1 F0/1
KI	S0/0/0 (DCE)	10.1.1.2	255.255.255.252	N/A	N/A
	G0/0	192.168.2.1	255.255.255.0	N/A	S2 F0/2
R2	S0/0/0	10.1.1.1	255.255.255.252	N/A	N/A
	S0/0/1 (DCE)	10.2.2.1	255.255.255.252	N/A	N/A
D0	G0/1	192.168.3.1	255.255.255.0	N/A	S3 F0/5
R3	S0/0/1	10.2.2.2	255.255.255.252	N/A	N/A
TACACS+ Server	NIC	192.168.2.2	255.255.255.0	192.168.2.1	S2 F0/6
RADIUS Server	NIC	192.168.3.2	255.255.255.0	192.168.3.1	S3 F0/1
PC-A	NIC	192.168.1.3	255.255.255.0	192.168.1.1	S1 F0/2
РС-В	NIC	192.168.2.3	255.255.255.0	192.168.2.1	S2 F0/1
PC-C	NIC	192.168.3.3	255.255.255.0	192.168.3.1	S3 F0/18


Table 1: Addressing Table

Task 1: Configure Local AAA Authentication for Console Access on R1


1. Test connectivity.



• Ping from PC-A to PC-B.




• Ping from PC-A to PC-C.



• Ping from PC-B to PC-C.





2. Configure a local username on R1.

Configure a username of **Admin1** with a secret password of **admin1pa55**.

Attach screenshot of commands below.

```
PC-A (192.168.1.3), PC-B (192.168.2.3), PC-C (192.168.3.3)

Rl>en
Password:
Rl#config t
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config)#
Rl(config)#username Admin privilege 15 secret adminlpa55
Rl(config)#end
Rl#
%SYS-5-CONFIG_I: Configured from console by console
write memory
Building configuration...
[OK]
```

3. Configure local AAA authentication for console access on R1.

Enable AAA on R1 and configure AAA authentication for the console login to use the local database



```
R1(config) #aaa ?
                    Accounting configurations parameters.
  accounting
  authentication Authentication configurations parameters.
  authorization Authorization configurations parameters.

new-model Enable NEW access control commands and functions. (Disables
                    OLD commands.)
R1(config) #aaa new-model
R1(config) #aaa authentication ?
  enable Set authentication lists for enable. login Set authentication lists for logins.
          Set authentication lists for ppp.
R1(config) #aaa authentication login ?
           Named authentication list.
  default The default authentication list.
R1(config) #aaa authentication login default ?
              Use enable password for authentication.
               Use Server-group.
               Use local username authentication.
  local
  local-case Use case-sensitive local username authentication.
               NO authentication.
R1(config) #aaa authentication login default local
R1(config)#
```

Note: You can enter a question mark after a command to see the available list of options for it as shown above.

Attach screenshot of commands below.

```
R1(config) #username Admin privilege 15 secret admin1pa55
R1(config)#end
%SYS-5-CONFIG I: Configured from console by console
write memory
Building configuration...
[OK]
Rl#enable
Rl#config t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config) #aaa new-model
R1(config) #aaa authentication login default local
R1(config)#line con 0
Rl(config-line)#login authentication default
Rl(config-line)#exit
R1(config) #write memory
% Invalid input detected at '^' marker.
R1(config)#exit
R1#
%SYS-5-CONFIG_I: Configured from console by console
write memory
Building configuration...
[OK]
```

4. Configure the **line console** to use the defined AAA authentication method.

Configure AAA authentication for the console login to use the default method list.



Use the **line** command on a Cisco router to enter line configuration mode, you can configure settings for specific lines, such as the console, auxiliary, or virtual terminal (VTY) lines. Here, **line console 0** will configure settings for the console line.

Attach screenshot below.

```
Rl(config) #line console 0
Rl(config-line) #login authentication default
```

5. Verify the AAA authentication method.

Verify the user EXEC login using the local database.

Attach screenshot below.

Task 2: Configure Local AAA Authentication for vty Lines on R1

Note: You have already seen how to configure some of these settings in the previous lab. You may refer to that lab for the necessary commands.

- 1. Configure domain name and crypto key for use with SSH.
 - a. Use conasecurity.com as the domain name on R1.
 - b. Create an RSA crypto key using 1024 bits.

Attach screenshot of your commands below.

```
Rl(config) #ip domain-name conasecurity.com
Rl(config) #crypto key generate rsa
The name for the keys will be: Rl.conasecurity.com
Choose the size of the key modulus in the range of 360 to 4096 for your
General Purpose Keys. Choosing a key modulus greater than 512 may take
a few minutes.

How many bits in the modulus [512]: 1024
% Generating 1024 bit RSA keys, keys will be non-exportable...[OK]
```

2. Configure a named list AAA authentication method for the **vty lines** on R1.



Configure a named list called SSH-LOGIN to authenticate logins using local AAA.

Attach screenshot of your commands below.

```
Rl(config) #aaa authentication login SSH-LOGIN local
```

3. Configure the vty lines to use the defined AAA authentication method.

Configure the vty lines to use the named AAA method and only allow **SSH** for remote access. Hint: use the **transport** command to define protocols for lines.

```
Attach screenshot of commands below.

Rl(config) #line vty 0 4
Rl(config-line) #login authentiation SSH-LOGIN


* Invalid input detected at '^' marker.

Rl(config-line) #login authentication SSH-LOGIN
Rl(config-line) #transport input ssh
Rl(config-line) #end
Rl#
```

4. Verify the AAA authentication method.

Verify the SSH configuration SSH to R1 from the command prompt of PC-A.

Attach screenshot below.






Task 3: Configure Server-Based AAA Authentication Using TACACS+ on R2

1. Configure a backup local database entry called Admin.

For backup purposes, configure a local username of **Admin2** and a secret password of **admin2pa55**.

2. Verify the TACACS+ Server configuration.

Click the TACACS+ Server. On the Services tab, click AAA. Notice that there is a Network configuration entry for R2 and a User Setup entry for Admin2.





3. Configure the TACACS+ server specifics on R2.

Configure the AAA TACACS server IP address and secret key on R2.

```
R2(config) # tacacs-server host 192.168.2.2
R2(config) # tacacs-server key tacacspa55
```

Note: The commands **tacacs-server host** and **tacacs-server key** are deprecated. Currently, Packet Tracer does not support the new command **tacacs server**.

```
R2(config) #username Admin2 secret admin2pa55
R2(config) #tacacs-server host 192.168.2.2
R2(config) #tacacs-server key tacacspa55
```

- 4. Configure AAA login authentication for console access on R2.
 - a. Enable AAA on R2
 - b. Configure all logins to authenticate using the AAA TACACS+ server. If it is not available, then use the local database.

R2(config) # aaa authentication login default group tacacs+ local

Attach screenshots of the commands below.

```
R2(config) #aaa new-model
R2(config) #aaa authentication login default group tacacs+ local
```

5. Configure the line console to use the defined AAA authentication method.

Configure AAA authentication for console login to use the default AAA authentication method.

```
Enter configuration commands, one per line. End with CNTL/Z. R2(config) #line console 0
R2(config-line) #login authentication default
```

6. Verify the AAA authentication method.

Verify the user EXEC login using the AAA TACACS+ server.

Attach screenshot below.



Task 4: Configure Server-Based AAA Authentication Using RADIUS on R3

1. Configure a backup local database entry called Admin.


For backup purposes, configure a local username of **Admin3** and a secret password of **admin3pa55**.

```
R3#config t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)# username Admin3 secret admin3pa55
```

2. Verify the RADIUS Server configuration.

Click the RADIUS Server. On the Services tab, click **AAA**. Notice that there is a Network configuration entry for **R3** and a User Setup entry for **Admin3**.





3. Configure the RADIUS server specifics on R3.

Configure the AAA RADIUS server IP address and secret key on R3.

```
R3(config) # radius-server host 192.168.3.2
R3(config) # radius-server key radiuspa55
```

Note: The commands **radius-server host** and **radius-server key** are deprecated. Currently Packet Tracer does not support the new command radius server.

```
R3(config) #radius-server host 192.168.3.2
R3(config) #radius-server key radiuspa55
```

4. Configure AAA login authentication for console access on R3.

Enable AAA on **R3** and configure all logins to authenticate using the AAA RADIUS server. If it is not available, then use the local database.

Attach screenshot of your commands below.

```
R3(config) #aaa new-model
R3(config) #aaa authentication login default group radius local
```



5. Configure the line console to use the defined AAA authentication method.

Configure AAA authentication for console log

```
R3(config)#line console 0
R3(config-line)#login authentication default
```

6. Verify the AAA authentication method.

Verify the user EXEC login using the AAA RADIUS server.

Attach screenshot below

```
R3 con0 is now available
```

Press RETURN to get started.

User Access Verification

Username: Admin3

Password: Admin

asdas exit

% Login invalid

Username: Admin3


Password:

R3>

7. Check results.



Your completion percentage should be 100%. Click Check Results to see feedback and verification of which required components have been completed.





Assessment Rubric Lab 04 Configure AAA Authentication on Cisco Routers

Name: Syed Asghar Abbas Zaidi	Student ID: 07201
-------------------------------	-------------------

Points Distribution

Task No.	LR 2 Simulation	LR9 Report
Task 1	30	
Task 2	10	
Task 3	20	
Task 4	20	
Total	/80	/10
CLO Mapped	CLO 1	CLO1

Affective Domain Rubric		Points	CLO Mapped
AR 7	Report Submission	/10	CLO 1

CLO	Total Points	Points Obtained
1	90	
1	10	
Total	100	

For description of different levels of the mapped rubrics, please refer the provided Lab Evaluation Assessment Rubrics and Affective Domain Assessment Rubrics.



Lab Evaluation Assessment Rubric

#	Assessment Elements	Level 1: Unsatisfactory Points 0-1	Level 2: Developing Points 2	Level 3:Good Points 3	Level 4:Exemplary Points 4
LR2	Program/Code / Simulation Model/ Network Model	n model/network model does not implement the required functionality and has several errors. The student is not able to utilize even the basic	n model/network model has some errors and does not produce completely accurate	correct output but not efficiently implemented or implemented by computationally complex	command on the basic tools of
LR9	Report	not included in report	included in report but are not well explained. All the necessary figures / plots are not included.	in-lab tasks is included in report. The work is supported by figures and plots with explanations. The	Detailed summary of the in-lab tasks is provided. All tasks are included and explained well. Data is presented clearly including all the necessary figures, plots and tables.