## Section 2 / Floating Point Literals

Recall that all AARCH64 instructions are 4 bytes long. Recall also that this means that there are constraints on what can be specified as a literal since the literal must be encoded into the 4 byte instruction. If the literal is too large, an assembler error will result.

Given that floating point values are always at least 4 bytes long themselves, using floating point literals is extremely constrained. For example:

```
fmov d0, 1 // 1
fmov d0, 1.1 // 2
```

Line 1 will pass muster but Line 2 will cause an error.

To load a float, you could translate the value to binary and do as the following:

```
.text
                                                                       // 2
         .global main
         .align
                                                                       // 3
                                                                       // 4
main:
        str
                     x30, [sp, -16]!
                     s0, =0x3fc00000
         ldr
        fcvt
                     d0, s0
        ldr
                     x0, =fmt
                                                                       // 8
        bl
                     printf
                                                                       // 9
                     x30, [sp], 16
                                                                       // 10
         ldr
                     w0, wzr
                                                                       // 11
        mov
                                                                       // 12
        ret
                                                                       // 13
                                                                       // 14
         .data
                                                                       // 15
fmt:
         .asciz
                    "%f\n"
```

The above code is kind of found here - the file is used for miscellaneous testing.

Line 6 puts the translated value of 1.5 into s0 (since we are thinking of the value as a float it goes in an s register). The assembler performs some magic getting a 32 bit value seemingly fit into a 32 bit instruction. See below.

Line 7 converts the single precision number into a double precision number for printing.

printf() only knows how to print double precision values. When you specify a float, it will convert it to a double before emitting it.

Translating floats and doubles by hand isn't a common practice for humans, though compilers are happy to do so.

Instead for us humans, the assembler directives .float and .double are used more frequently to specify float and double values putting them into RAM.

The following example prints an array of floats and doubles:

```
// 1
        .global main
                                                                        // 2
        .text
                                                                        // 3
        .align 2
                                                                        // 4
counter .req
                                                                        // 5
                 x20
                                                                        // 6
dptr
                 x21
        .req
                 x22
                                                                        // 7
fptr
        .req
                 max, 4
                                                                        // 8
        .equ
                                                                        // 9
main:
        stp
                 counter, x30, [sp, -16]!
                                                                        // 10
                                                                        // 11
        stp
                 dptr, fptr, [sp, -16]!
        ldr
                 dptr, =d
                                                                        // 12
        ldr
                 fptr, =f
                                                                        // 13
                                                                        // 14
                 counter, xzr
        mov
                                                                        // 15
                                                                        // 16
1:
        cmp
                 counter, max
        beq
                 2f
                                                                        // 17
                                                                        // 18
        ldr
                 d0, [dptr, counter, 1sl 3]
                                                                        // 19
        ldr
                 s1, [fptr, counter, lsl 2]
                                                                        // 20
                                                                        // 21
                 d1, s1
        fcvt
        ldr
                 x0, =fmt
                                                                        // 22
        add
                 counter, counter, 1
                                                                        // 23
                                                                        // 24
        mov
                 x1, counter
                                                                        // 25
        bl
                 printf
                                                                        // 26
                 1b
                                                                        // 27
2:
        ldp
                 dptr, fptr, [sp], 16
                                                                        // 28
                 counter, x30, [sp], 16
                                                                        // 29
        ldp
        mov
                 w0, wzr
                                                                        // 30
                                                                        // 31
        ret
                                                                        // 32
        .data
                                                                        // 33
        .asciz
                "%d %f %f\n"
                                                                        // 34
fmt:
        .double 1.111111, 2.222222, 3.333333, 4.444444
                                                                        // 35
d:
        .float 1.111111, 2.222222, 3.333333, 4.444444
                                                                        // 36
f:
                                                                        // 37
                                                                        // 38
        .end
```

The above code is found here.

A number of interesting things in this source code:

• We use .req to give symbolic names to various registers. This can help you in remembering which register is being used for what purpose.

- We use .equ to encode a small integer literal value to give it a symbolic name, eliminating the use of a "magic number."
- Lines 19 and 20 use address arithmetic to march through an array of doubles (8 bytes each) and an array of floats (4 bytes each).

Line 19 is equivalent to:

```
// ldr d0, [dptr, counter, lsl 3]
d0 = dptr[counter];
```

counter is multiplied by 8 then added to dptr.

Line 20 is equivalent to:

counter is multiplied by 4 then added to fptr.

```
// ldr s1, [fptr, counter, lsl 2]
s1 = fptr[counter];
```

Cool huh?

On Linux, just as w/x0 through w/x7 are scratch registers and used to pass parameters, s/d0 and s/d7 are as well beginning with the 0 register.

## Fitting 32 bits into a 32 bit bag

This section is currently LINUX-centric - in the future it will address both native Apple and Linux equally.\*

AARCH64 instructions are 32 bits in width. Yet, line 6 from this program reads:

```
ldr s0, =0x3fc00000 // 6
```

This appears to show a 32 bit constant being held in an instruction that itself is 32 bits wide. Well, the Assembler does some magic. Let's see what that magic is.

Build the program with the -g option to enable debugging using GDB.

```
% gcc -g t.s
```

Then launch GDB on the executable:

% gdb a.out

Set a breakpoint on line 6.

```
(gdb) b 6
Breakpoint 1 at 0x784: file t.s, line 6.
(gdb)
```

Enter a cool GDB layout (one of several cool layouts):

layout asm

You should see something like this:

```
Terminal
                                     x30, [sp, #-16]!
s0, 0x7a0 <main+32>
   0x780 <main>
                             str
   0x784 <main+4>
                             ldr
   0x788 <main+8>
                                     d0, s0
                             fcvt
   0x78c <main+12>
                             ldr
                                      x0, 0x7a8 <main+40>
   0x790 <main+16>
                             ы
                                      0x660 <printf@plt>
   0x794 <main+20>
                             ldr
                                     x30, [sp], #16
   0x798 <main+24>
                             mov
                                     w0, wzr
   0x79c <main+28>
                             ret
   0x7a0 <main+32>
                             .inst
                                      0x3fc00000 ;
                                                   undefined
   0x7a4 <main+36>
                             .inst
                                     0x00000000; undefined
   0x7a8 <main+40>
                                      0x00011010;
                                                   undefined
                             .inst
                                     0x00000000; undefined
   0x7ac <main+44>
                             .inst
   0x7b0 <__libc_csu_init> stp
                                      x29, x30, [sp, #-64]!
                                                                           PC: ??
exec No process In:
(gdb)
```

Figure 1: gdb01

We expected line 6 to read:

```
ldr s0, =0x3fc00000
```

Instead we find:

```
b+ 0x784 <main+4> ldr s0, 0x7a0 <main+32>
```

Scan downward to find 0x7a0:

```
0x7a0 < main+32 > .inst 0x3fc00000 ; undefined
```

Hey look! Here's our literal float. The .inst is an ARM specific GNU assembler directive says:  $^{-}(-)_{-}$ .

Note, the encoded "instruction" does not have to make any sense - instead the compiler has emitted a make believe instruction that happens to have the value of our literal.

What we're seeing the actual line 6 doing is reaching ahead a short distance to load the value of another location in memory where our constant is really found.

Let us take this explanation further. Notice we see:

```
0x78c <main+12> ldr x0, 0x7a8 <main+40>
```

where we expected:

ldr x0, =fmt

Scan down to 0x7a8:

0x7a8 <main+40> .inst 0x00011010; undefined

 $\mathtt{x0}$  is serving as a pointer to the format string of a call to  $\mathtt{printf}(\tt)$  . Let's follow the pointer...

(gdb) x/s 0x00011010 0x11010: "%f\n"

(gdb)

Magic.