



AuScope Discovery Portal User Guide

AuScope Discovery Portal User Guide

Contents

Table of Figures	2
Overview	3
Data Services	4
Map	5
Filter Panel	6
Wildcards	7
Download Panel	g
Selecting a bounding box to limit the download size	10
Custom layers	12
Custom URL	12
Custom File	13
Data Search	14
Map Navigation	16
Split View	17
Map Projection	18
Changing the default ESRI World Imagery base map	18
Search and Download Bar	20
Permanent Link	21
Login	22
Logout	23
Example 1: NVCL Boreholes	24
NVCL Boreholes: Steps 1,2,3 & 4	25
NVCL Boreholes: Step 5	26
NVCL Boreholes: Step 6	26
NVCL Boreholes: Step 7	27
NVCL Borehole Service View	27
NVCL Boreholes: Steps 8 & 9	29
Example 2: Download an NVCL TSG Dataset	31
Example 3: Filter By Geological Province	33
Steps 1 & 2: Filtering by name, add geological province layer	33
Step 5: Add NVCL borehole layer	35
Glossarv	36

Table of Figures

Figure 1: AuScope Portal with ESRI National Geographic base map	3
Figure 2: Map Layer controls	
Figure 3: Map of Australia with default "ESRI World Imagery" base map	5
Figure 4: Filter Panel	6
Figure 5: Info Panel	
Figure 6: Two different kinds of download Panel	9
Figure 7: Selecting a bounding box to limit the download size	10
Figure 8: Download Panel with bounding box filter	11
Figure 9: Custom layers	
Figure 10: Load a KML or KMZ file onto map	
Figure 11: Data search options	
Figure 12: Loading a layer on the map after the search	15
Figure 13: Using the magnify button to zoom to a certain area on the map (ESRI National Geographic)	
Figure 14: Comparing borehole layers using the split view and the "Left", "Right" and "Both" buttons	
Figure 15: Selecting map projection	
Figure 16: Background map selection	
Figure 17: Polygon Filter	
Figure 18: Search and Download Bar	
Figure 19: The location of the login button	
Figure 20: layers can be bookmarked	
Figure 21: Example core sample	
Figure 22: NVCL Boreholes: Steps 1,2,3 & 4	
Figure 23: NVCL Boreholes: Step 5	
Figure 24: NVCL Boreholes: Step 6	
Figure 25: NVCL Boreholes: Step 7	
Figure 26: NVCL Borehole Service View	
Figure 27: NVCL Borehole Service detailed image and spectral data plots	
Figure 28: NVCL Boreholes: Steps 8 & 9	
Figure 29: Depth and sample count at a point	
Figure 30: NVCL Boreholes: Graph of borehole minerals	30
Figure 31: NVCL Boreholes: Details of graph controls	
Figure 32: Click on "Add Layer"	
Figure 33: Click on Prepare Tsg Dataset button	
Figure 34: Step 1 & Step 2, filter by geological province	
Figure 35: Steps 3 & 4, filter by geological province	
Figure 36: Step 5, filter by geological province	35

Overview

The AuScope Discovery Portal https://portal.auscope.org.au/ displays geospatial data obtained from a number of geoscience organisations around Australia. The portal provides a way to find and download geospatial data and display it on the map. Finding the data is managed by the data services panels at the left hand side; and the new search bar at the top.

The following sections describe the portal: the first section of this document is an overview of the portal. Later sections provide details on the portal's operations. The examples section contains steps to perform common activities.




Figure 1: AuScope Portal with ESRI National Geographic base map

Data Services

The data services are a collection of web-based services from organisations around Australia that provide geospatial data, such as Geoscience Australia, CSIRO, state governments geological surveys and several Australian universities.

Various organisations provide data to the portal: it may be as simple as satellite imagery or a view into a geospatial database. The data provided by these services are drawn as *layers* overlaying the background map. Selecting the data to view is managed by the panel to the left hand side of the window.



To view a layer you have to:

- 1. Select a layer from one of the lists, by clicking on the layer category, then the layer name
- 2. Select the "Filter" panel by clicking on the its tab
- 3. Optionally filter the data (for example, a specific mineral type); and
- 4. Add the data as a map layer by clicking on Add Layer button in "Filter" panel

Note that adding a layer may not display the data immediately: the data has to be fetched from the providers and so it may take a few minutes and be displayed in batches.

Map

The map area is a standard web-based map display: showing a background map with zero or more layers overlaying the map to display selected features. You can zoom in or out by using the mouse wheel and move the map by dragging the mouse around.



Figure 3: Map of Australia with default "ESRI World Imagery" base map.

Filter Panel




Figure 4: Filter Panel

Each layer provides different ways to filter the data depending on the structure its data. The following image shows a sample of the filters from three different mining layers. Note that each filter provides fields of several types: plain text, dates and select lists.

- Plain text fields match the data exactly, but case insensitive. Some data services also support wildcards to match portions of the field.
- Date fields are in the format: yyyy-mm-dd and also provide a pop-up calendar to selected the date (invalid dates are indicated with a red border around the input text box).
- Select lists are populated from unique values from the data.

Some layers may not have any filters. Layers that supply imagery may only provide a filter to change the layer's opacity when the images are drawn on the map.

Some layer fields are numeric, for example the amount of ore processed. There are no checks to verify that you have entered a numeric value in these fields. Entering non-numeric will

result in either no data or the filter will be ignored.

Click the **Add layer to map** button to apply any filters to the data and display the results on the map. If the layer is already active it will be replaced by a layer with the new filter.



A number of data services provide data from external sources and when they are added to the map a copyright notice will be show.

Wildcards

Wildcards are special characters that allow filters to match all or part of a text field. They may also position the match at the beginning or end of the field.

A data provider may choose not to implement wildcards (for example, to reduce processing overheads) or limit their behaviour. This means a filter on a text field *may* accept any of these matching rules:

- 1. A strict match of the entire text field, usually case insensitive.
- 2. A match to any portion of the field. For example a filter of "old" will match "goldfield lease" and "the folding chair".
- 3. A "match any" beginning/end wildcard (asterisk: **). For example "sil**" will match "silver mine" and "silicon chip". Similarly "*ts" will match "hot spots" and "polar orbits"
- 4. A "single character" wildcard (Hash: #). For example "*9#" will match "bore 295" and "mine number 1294"

Info Panel

Clicking on the "info" button to open up the information panel to find more detailed information about the layer. Click on the provider name to display service details.




Figure 5: Info Panel

Download Panel




Figure 6: Two different kinds of download Panel

If you would like to perform further analysis on the data being viewed in the portal you can download the data to your workstation by selecting the **Download**Tab.

If you click on the **Download** button, you will download all the data from all providers. This request may fail if there is too much data, as the connection may time out.

It is therefore advisable to use the **Draw Bounds** or **Draw Polygon** (if available) buttons to reduce the size of the download request.

Selecting a bounding box to limit the download size




Figure 7: Selecting a bounding box to limit the download size

If you click on the **Draw Bounds** button you can create a bounding box by clicking twice in the map area, once in the top left corner and again in the bottom right corner as shown above. Some layers will provide a **Draw Polygon** button that will allow you to draw a polygon to define download bounds.



Figure 8: Download Panel with bounding box filter

Once a bounding box has been defined, the Download Panel will display its coordinates (above), and you can click on the **Download** button to get the results.

Custom layers

Custom URL




Figure 9: Custom layers

Custom Layers allow you to add layers from any mapping server in the world. You will need the link (URL) to the web service and enter it into the field in the panel:

Press **Enter** or click on the **magnifying glass** to connect to the service and the portal will query the service's capabilities. In the above figure a flood map provides precipitation and cloud maps amongst other weather data. These capabilities are treated like normal map layer and can be added to the map by clicking on the layer name and clicking the **Add layer to map** button.

Type of data	Source Type	URL	
Flood reports	WMS	https://afrip.ga.gov.au/geoserver/floods/wms	
WA bike trail	KML	https://catalogue.data.wa.gov.au/dataset/f950141e-f484-4edd-b6d3- 2ead49a4a476/resource/553e646a-0bff-406f-8c45- 85c733642f0f/download/munda_biddi_cycle_trail.kml	
Power liines	KMZ	https://d28rz98at9flks.cloudfront.net/83105/ElectricityTransmissionLines v2.kmz	

Custom File




Figure 10: Load a KML or KMZ file onto map

The user can also load a custom KML or KMZ file onto the map, by clicking on the "Load KML/KMZ" button selecting a file, then adding the layer as described in the previous section.

Data Search




Figure 11: Data search options

Data Search can be accessed under the "Custom Layers". This enables you to search catalogues for datasets to display on the portal's map.

There are many options to use in your search.

- Text search
- Spatial Bounds
- Keywords
- Publication Date Range
- Service Type
- Registry




Figure 12: Loading a layer on the map after the search

A search is commenced by clicking on

A list of layers is generated. If <u>you</u> click on the layer can be loaded on the map.

The layer can be removed via button.

Clicking on opens up an information panel with a map of the area covered by the dataset marked in blue, if it is available from the catalogue.

Map Navigation




Figure 13: Using the magnify button to zoom to a certain area on the map (ESRI National Geographic)

There are several ways to navigate around the map.

- Using the Zoom button, click the **plus +** or **minus -** signs to zoom in or out.
- Magnify button can be used to zoom to a particular area on the map:
 - 1. Click Magnify
 - 2. Click at the top left hand corner
 - 3. Click at the bottom right hand corner
- Using the mouse:
 - Move the map: hold the left-mouse button down and move the mouse.
 Zoom in and out: use the mouse's scroll wheel.

Split View




Figure 14: Comparing borehole layers using the split view and the "Left", "Right" and "Both" buttons

Once split view mode is enabled via this button , you can load two layers into the "Left", "Right" or "Both" sides of the map by toggling the buttons.

Map Projection

Using the map projection button you can select:

- 2D
- 3D
- Columbus View



Figure 15: Selecting map projection

Changing the default ESRI World Imagery base map



Figure 16: Background map selection

There are a number of base maps to choose from by clicking on the button in the far top right corner of the map.



Figure 17: Polygon Filter

The polygon filter is used as a map filter when selecting an area of the map from which to download data, for example.

Search and Download Bar

Use the search bar at the top of the page to search for specific layers.

Enter a search term in the text field provided and press the search button to conduct the search. You may also choose from one of the suggested terms as you type by clicking on it.

Press the Advanced Options button to show the Advanced Option toolbar, which allow you to further refine your search to specific record fields, OGCS services and spatial locations.

Results may automatically be hidden as you interact with the map, to reveal them again press the show/hide results button





Figure 18: Search and Download Bar

If you click on the then a "Select Layers to Download" section will open up and you can select layers' datasets for downloading . They are downloaded via the button. Multiple layers can be

downloaded using the button.

Permanent Link

The current state of the portal can be captured in the form of a unique URL. The URL can be revisited at any time by entering it into your web browser. This is very useful, for example for sharing maps with others.



To activate, you click on "Permanent Link" at the top left hand corner. The URL will be generated.

button.

To copy it to the system clipboard click on the

Login




Figure 19: The location of the login button

You can also login to the portal via AAF or Google ot github by clicking on the login button shown above.




Figure 20: layers can be bookmarked

Once logged in, layers can be bookmarked for future reference using the button. Click on the button a second time to undo the layer bookmark. The bookmarked layers are kept for you and will still be there next time you login.

Logout

Logout can be selected via the button on the top right hand corner of the page.

Example 1: NVCL Boreholes

The National Virtual Core Library (NVCL) is a geospatial database holding high resolution pictures of drill samples to help explore the mineralogy and composition of the upper 1-2 km of the Australian continent. The drill samples in the library come from a number of sources including State agencies and industry.




Figure 21: Example core sample

The following steps display the NVCL data on the portal's map and view the details for one of the core samples. Images of the each step are shown below.

- 1. Select **Boreholes** from the list.
- 2. Select the National Virtual Core Library V2.0 from the list of layers.
- 3. Click on the **Add layer** button to draw the data points on the map. You may also filter the data to a subset using the options in the filter panel (remember to select the filters *before* adding the layer to the map).
- 4. Click on a coloured marker on the map, a popup dialog box will appear.
- 5. Click on borehole id to open up details panel.
- 6. Click on **Analytic** tab.
- 7. This shows thumbnail images of the borehole cores. Next, click on **Scalar** tab.
- 8. This shows all datasets obtained from measurements of the core samples. For example infra-red spectroscopy measurements of the samples. You can click on the "Definition" link to get more information about what kind of sample was taken. The next action is to select a dataset or more by clicking in the tickboxes.
- 9. Click on graph icon to display a graph of the selected mineral measurements.

NVCL Boreholes: Steps 1,2,3 & 4




Figure 22: NVCL Boreholes: Steps 1,2,3 & 4

NVCL Boreholes: Step 5



Figure 23: NVCL Boreholes: Step 5

NVCL Boreholes: Step 6




Figure 24: NVCL Boreholes: Step 6

NVCL Boreholes: Step 7




Figure 25: NVCL Boreholes: Step 7

NVCL Borehole Service View

In Step 7 above, you can click on a thumbnail in the AuScope portal and get a high resolution image of the borehole drill samples from the relevant NVCL service website.

At the left and right hand side of the image there are arrows which can be used to view borehole images at lower and higher depths (see below).




Figure 26: NVCL Borehole Service View

If you *double click* on this picture, you can see spectral data plots taken from the samples, as depicted below.




Figure 27: NVCL Borehole Service detailed image and spectral data plots

NVCL Boreholes: Steps 8 & 9




Figure 28: NVCL Boreholes: Steps 8 & 9

A typical graph of the mineral measurements is shown below. A user can hold the mouse pointer over a point in the graph and the depth and sample count at that point will be displayed, e.g.





Figure 29: Depth and sample count at a point






Figure 30: NVCL Boreholes: Graph of borehole minerals




Figure 31: NVCL Boreholes: Details of graph controls

Example 2: Download an NVCL TSG Dataset

To download an NVCL TSG Dataset:

1. Select Boreholes from the list.

Select the National Virtual Core Library V2.0 from the list of layers.

Click the Filter tab.

Click on **Select Filter** dropdown and select **Name**.

Enter a name (e.g. Shittim).

Click Select Filter dropdown and select Provider.

Click on **Tasmania** (for example).

Click the blue **Add Layer** button to display boreholes on the map.




Figure 32: Click on "Add Layer"

2. Click a red borehole point on the map.

A popup window will open up.

Click on the grey borehole identifier.

Click the **Analytic** tab.

Click the **Download** tab.

Enter your email address.

Click on Prepare Tsg Dataset button.




Figure 33: Click on Prepare Tsg Dataset button

Example 3: Filter By Geological Province

Steps 1 & 2: Filtering by name, add geological province layer




Figure 34: Step 1 & Step 2, filter by geological province

Step 1: Filtering by name, add geological province layer

Step 2: Click on layer

Steps 3 & 4: Clicking on 'gml:ProvinceFullExtent ...' link




Figure 35: Steps 3 & 4, filter by geological province

Step 3: Click on "gml:ProvinceFullExtent ..." link to reveal details as shown above

Step 4: Click on "Add to clipboard" button, close dialog box

Step 5: Add NVCL borehole layer




Figure 36: Step 5, filter by geological province

Step 5: Add NVCL borehole layer, using the "Polygon BBox" filter, making sure "Apply clipboard BBox" checkbox is ticked.

Glossary

Term	Meaning
CSW	Catalog Service for the Web (Catalog Service – Web)
<u>GA</u>	Geoscience Australia
GML	Geography Markup Language
OGC	Open Geospatial Consortium
SRS	Spatial Reference System
WCS	Web Coverage Service
WFS	Web Feature Service
WMS	Web Mapping Service
XML	Extensible Markup Language