Contents

Basic Information

Contents	1
Recent Updates:	
Overview:	
Installation:	6
HEPMC3:	8
Input:	9
DPMJET:	16
Output	18
Class Diagram	20
File Descriptions	21

Recent Updates:

vxxx (Nov. 13, 2024) Removed warning that ω -> $\pi^+\pi^-\pi^0$ is unstable, since it seems OK.

vxxx (Nov. 10, 2023) Added Option for photoproduction of phi + direct KK, just like rho + direct pipi. This is particle type 933. The phi:direct KK ratio default is the same as for the rho + direct pipi

v328 - Implemented the HEPMC3 standard for two-photon interactions and coherent photonuclear interactions with INTERFERENCE turned off and 0n0n breakup modes. Made changes to the parameterization of the normalization constant for the default nuclear density distribution (2-parameter Fermi Model) in STARlight.

v327 - Updated CMAkeLists.tx and cmake_modules/FindDMJet.cmake with versions from Luan Arbeletche that accommodate the new version of DPMJET. Updated documentation to point to that version. n. b. There may still be a problem with running DPMJet, but this is much closer

v326 - Updated the Documentations to reflect recent changes.

v325 - Moved the repository from HEPForge to GIT. Hosted remotely on GitHub. Created a README.md and AGPL LICENSE file for the repository.

GIT

v320 - Added channel: $\varphi \rightarrow e^+e^-$. with code (333011) - Nov 9 2022

v319 - updated the nuclear model for oxygen to the three parameter Fermi Model. Updated the code for Eta cut application to work correctly in assymetric collisions. Added PT_CUT and Eta_Cut functionalities for the FOURPRONG, ZOVERZO3, F2, F2Prime,and AXION Channels. Fixed the errors and bugs in the output of ω -> $\pi^+\pi^-\pi^0$ Channel - Eta cuts are now applied only to the charged pions and not on the uncharged pion. Fixed the bug causing incomplete output EVENTS in the FOURPRONG and Omega3pion channel. Fixed other bugs and potential bugs. Created copy constructors to fix warnings on new gcc compilers.

v317 - remove register keyword from randomgenerator.cpp for compatibility with C++17

- ${
 m v316}$ -added destructors for randomnumbergenerator and paramterbase, for LHCb
- v315: added documentation for PRINTVM=2 command and a note about the last line of slight.in not working.
- v313: Found a bug in channel: ω -> $\pi^+\pi^-\pi^0$. Reconstructed ω mass is about 0.4% too high. While debugging, resolved an unrelated error. Marked ω -> $\pi^+\pi^-\pi^0$ as UNSTABLE in this document.
- v311: (UNSTABLE) Added channel: $\omega \to \pi^+\pi^-\pi^0$ with code (223211111).
- v309: Added channels: ρ^0 -> e^+e^- and ρ^0 -> $\mu^+\mu^-$ with codes(113011) and (113013) respectively.
- v308: Added an option to display a header in the output file. This header will show input parameters in a similar format to eSTARlight. Option is controlled by input parameter "OUTPUT HEADER", see below.
- v307: Fixed 4-prong mass spectrum, properly converting dsigma/ds to dsigma/dW. The net effect is to scale the mass spectrum by $1/M \{4\pi\}$, reducing the number of high-mass states.
- v306: Updated gammavm.cpp, to properly output 4 pions with net charge 0. Also changed default Wmax for 4-prong final state to be the larger of the kinematic limit or 10 GeV; previously, it was unduly large for the LHC.
- v305: Changed coefficient in calculation of pt2 in gammavm.cpp from 8 to 32. This changes the maximum p_T for vector mesons for calculations without interference from about 250 MeV/c to about 1 Gev/c. In the long run, we could rename INT_PT_MAX and make it required parameter with or without interference. This could make the running a bit more efficient.
- v304: Fixed a bug in gammaaluminosity.cpp lines 404, where photonDensity was called with its arguments reversed. This bug affected the p_T spectrum when interference is turned on.
- v299: Added hard-coded Woods-Saxon radii, thickness and density for 96 Ru and 96 Zr, for the RHIC isobar run. Data is from arXiv:1607.04697
- v297: Changed normalized for Woods-Saxon density for non-predefined (i. e. not gold, lead, xenon or copper or nuclei with Z<7) so that the density is properly normalized $\inf d^3r \ rho(r) = A$. The normalization was previously done for a hard-sphere nucleus, so this over-estimated the cross-sections by 5-10%.
- v295: Added hard-coded values for xenon-129 to match the recent LHC run. Radius=5.36 fm, density=0.18406
- v293: Introduced shared random number generator which can be externally passed by the user. All particle constants (masses,

widths, branching ratios, and spins) can now also be set by the user, but should be changed from the default values with care.

v290: Added an new BREAKUP_MODE option to generate two-photon events in peripheral collisions. BREAKUP_MODE=8 sets a fixed impact parameter range, regardless of the presence of nuclear breakup; it is intended to study two-photon production in peripheral collisions. It requires two additional otherwise optional input lines, BMIN and BMAX, to set the impact parameter range. It does not (yet?) work for photonuclear interactions.

278: Added two new optional parameters:

IMPULSE_VM Normally 0, but can be set to 1 to perform an impulse
approximation calculation (i.e. ignoring nuclear effects)

QUANTUM_GLAUBER. When set to 1, performs a quantum Glauber calculation, rather than a classical one. This leads to greatly increased rho and omega cross-sections for heavy nuclei, little effect for heavier mesons.

Also added a final state, 4432212, for J/psi -> pbar p

v276: Added two new optional parameters (BSLOPE DEFINITION and BSLOPE_VALUE) for the p_{T} spectrum ('bslope') for proton targets or incoherent production on nuclei

v275: Added $\gamma\gamma$ to axion channel as two-photon channel 88, per S. Knapen et al., arXiv:1607.07083 v273: "Baseline" version, described in arXiv:1607.03838)

Overview:

The STARlight Monte Carlo models 2-photon and photon-Pomeron interactions in ultra-peripheral heavy ion collisions. The physics approach for the photon-Pomeron interactions is described in Klein and Nystrand, Phys. Rev. C60, 014903 (1999), with the p_t spectrum (including vector meson interference) discussed in Phys. Rev. Lett. 84, 2330 (2000). The 2-photon interactions are described in Baltz, Gorbunov, Klein, Nystrand, Phys.Rev. C80 044902 (2009).

STARlight has several input files, all of which are expected to be in the same directory as the starlight code. User-specified input parameters are read from a file named "slight.in"; these parameters are described below in Input. Note that STARlight ignores the last line of slight.in, so it should be something irrelevant.

The simulated events are written to an ASCII file named "slight.out", which is described below in $\underline{\text{Output}}$.

Installation:

GitHub Based Installation:

As of present, STARlight has been moved from HEPforge to GitHub. The detailed installation instructions for the latest version on GitHub can be found in the READMe.md file via this link https://github.com/STARlightsim/STARlight/blob/main/README.md. Please note that instructions on enabling either PYTHIA or DPMJET is still the same for both HEPforge and GitHub, so consult this material for those portions of the installation instructions.

Hepforge Based Installation:

The portion below may not be relevant anymore. This is because STARlight has been moved from HEPforge to GitHub with all its history. So you can easily find any previous version you might be interested in, in the GitHub repository. The HEPforge version is no longer maintained nor updated, and though the HEPforge repository has not yet been closed, this installation process cannot be guaranteed to work properly any longer.

To install & run STARlight in a *nix based environment, follow these steps(README):

Download the starlight package from 'Downloads' on the left sidebar of the homepage. The version in the example might be outdated.

-wget 'https://starlight.hepforge.org/downloads?f=starlight r300.tar'

-mv 'downloads?f=starlight_r300.tar' starlight_r300.tar

-tar xvf starlight r300.tar

Alternatively, one may obtain the latest version via svn. HEPforge uses phabricator and no longer allows for anonymous checkouts of the repository. (Please read https://www.hepforge.org/guide.pdf .)

To obtain an account, register here: https://www.hepforge.org/register

Once you are registered, login: https://phab.hepforge.org/auth/start/?next=%2F

Set up a version control settings (VCS) password under your account's Settings->AUTHENTICATION->VCS password . The VCS password is needed to checkout the code.

(For remote users) To identify yourself, upload a SSH public key under account's Settings->AUTHENTICATION->SSH Public Keys with the button SSH Key Actions->Upload Public Key. This key will provide your identity when checking out the code as VCS. If you do not have a public ssh key to

upload, you may generate a pair on the same SSH Public Keys page with the button SSH Key Actions-> Generate Keypair.

With the private ssh key loaded on your machine (and public on their machine), use svn to checkout the trunk/:
-svn co svn+ssh://vcs@phab.hepforge.org/source/starlightsvn/trunk

Change to the installation directory of your choice
-mkdir /home/my/installation/dir
-cd /home/my/installation/dir
Setup the compilation with cmake
-cmake /path/to/trunk
Compile with (g)make
-gmake
Setup the input file, slight.in, for your simluation needs
-cp /path/to/trunk/config/slight.in .
-vim slight.in
Run

-./starlight >& output.txt&

For more information and special scenarios, such as running with PYTHIA or DPMJET, consult the README files located in trunk/

If you would like to browse the code, please visit: https://phab.hepforge.org/source/starlightsvn/

-----Before HEPForge updated their repository management system---To obtain the latest version:
-svn co http://starlight.hepforge.org/svn/trunk

Alternatively:

- -Visit https://starlight.hepforge.org/trac/browser
- -Download the trunk [click on the download symbol in the Size column]
- -Unpackage the zip file. The trunk/ represents <PathToSource>

To build Starlight:

- First create your build directory <BUILDDIR> (e.g. mkdir bin)
- \$ cd <BUILDDIR>
- \$ cmake <PathToSource>
- \$ make

This creates an executable file, starlight, in the build directory.

To clean the build:

- \$ make clean

To run starlight, a configuration file, slight.in, is needed. Examples of slight.in may be found in the config/ directory.

To run:

\$./starlight

Enabling Pythia:

To simulate the η , η' , and η_c channels, you need Pythia v8.2 or higher to handle their decays. To enable Pythia support you need to run cmake with the option -DENABLE_PYTHIA=ON and have \$PYTHIADIR pointing to the top directory of Pythia8. [Note: when building Pythia, be sure to enable shared libraries(.so). ./configure --enable-shared before compiling Pythia.]

- \$ setenv PYTHIADIR /my/local/pythia8
- \$ cmake <PathToSource> -DENABLE PYTHIA=ON

Note: v8.2+ is necessary since the Pythia directory structure changed[trunk/cmake_modules/FindPythia8.cmake depends on the structure layout], libhapdfdummy was removed, and Standalone:allowResDec was removed.

To enable DPMJET, please see the passage on DPMJET

HEPMC3:

The HEPMC3 standard is the latest standard for writing event records or output files in high energy physics event generators. STARlight has implemented this new standard by interfacing with the CERN HEPMC3 module. But it is important to note the following as there are situations where STARlight reverts to the old output standard.

The HEPMC3 standard is implemented for both two-photon and photonuclear interactions. But in photonuclear interactions, it is not implemented for incoherent interaction, neither is it implemented for coherent interactions when INTERFERENCE is turned on. So in these cases, STARlight reverts to the old output standard.

The HEPMC3 standard has only been implemented for the breakup-mode where there is no coulomb or hadronic breakup. This is BREAKUP_MODE = 4, 0n0n. In all other breakup modes, STARlight reverts to the old standard.

How to turn-on the HEPMC3 feature.

When the HEPMC3 feature is turned off (the default situation), STARlight's output follows the old standard and is written out to the slight.out file. To turn on the HEPMC3 feature, the CERN HEPMC3 module needs to be installed and linked to STARlight, when

STARlight's code is being compiled. With this successfully done, STARlight provides two outputs, the slight.hepmc file (in hepmc3 format) and the slight.out file (in the old STARlight format).

An extended version of the old STARlight output that contains the momenta and energy of the outgoing beams, as an addition to those of the outgoing final state particles, can also be accessed (with/without installing the CERN HEPMC3 module) in the slight.out file, by setting the HEPMC3_EXTENDED_OUTPUT parameter to 1 in the input slight.in file.

The instructions on how to install the CERN HEPMC3 module, link to STARlight and compile STARlight with the HEPMC3 option enabled is well described in HEPMC3 Output section of the Github README.md file at https://github.com/STARlightsim/STARlight/blob/main/README.md.

Input:

The input parameters are listed below with typical values for LHC Pb-Pb running given in parentheses. Optional parameters are denoted with \star

baseFileName	# The name of the output files. STARlight will copy the input slight.in to baseFileName.in, and produce output files baseFileName.txt and baseFileName.out. (slight)
BEAM_1_Z = 82	# Charge of beam one projectile. (82)
$BEAM_1 = 208$	# Atomic number of beam one projectile. (208)
BEAM_2_Z = 82 BEAM 2 A = 208	# Charge of beam two projectile. (82) # Atomic number of beam two projectile. (208)
	
BEAM_1_GAMMA = 1470	# Lorentz boost for beam one projectile($pz>0$). (1470)
BEAM_2_GAMMA = 1470.0	# Lorentz boost for beam two projectile($pz<0$). (1470)
W_MAX = 12.0	# Maximum value for the gamma-gamma center of mass energy, W = $4E_1E_2$, in GeV. Setting W_MAX = -1 tells STARlight to use the default value specified in inputParameters.cpp (recommended for single meson production). For single mesons, the default W_MAX is the particle mass plus five times the width. For lepton pairs, the default W_MAX is given by $2\hbar c \sqrt{\frac{\gamma_1 \gamma_2}{R_1 R_2}}$. These are defined in
W_MIN = -1	src/inputParameters.cpp (-1) #Min value of w. Minimum value for the gamma-gamma center of mass energy, W = $4E_1E_2$, in GeV. Setting W_MIN = -1 tells STARlight to use the default

W N BINS = 40

 $RAP_MAX = 8.$ RAP N BINS = 80

CUT PT* = 0

 $PT_MIN* = 1.0$

 $PT_MAX* = 3.0$

 $CUT_ETA* = 0$

ETA MIN* = -10

ETA MAX* = 10

 $PROD_MODE = 2$

value specified in inputParameters.cpp (recommended for single meson production). The default W_MIN is the larger of the kinematic limit (e.g. $2m_\pi$ for ρ decays) or the particle mass minus five times the width. (-1)

#Bins w maximum and minimum values for w (the gamma-gamma center of mass energy, w = $4E_1E_2$), and the number of w bins in the lookup tables (40)

Maximum rapidity of produced particle. (8)

Number of rapidity bins used in the cross section calculation (80)

Specifies whether the user chooses to place restrictions on the transverse momentum of the decay products. 0= no, 1= yes. (0)

If a transverse momentum cut is applied, this specifies the minimum value produced, in GeV/c. (1.0)

If a transverse momentum cut is applied, this specifies the maximum value produced, in GeV/c. (3.0)

Specifies whether the user chooses to place restrictions on the pseudorapidity of the decay products. 0= no, 1 = yes. (0). PLEASE NOTE that in the ω -> $\pi^+\pi^-\pi^0$ channel Eta cuts are not applied to the uncharged pion. It is only applied to the 2 charged pions.

If a pseudorapidity cut is applied, this
specifies the minimum value produced. (-10)
If a pseudorapidity cut is applied, this
specifies the maximum value produced. (10)

#PROD_MODE=1: Two-photon interaction.

PROD_MODE=2: Coherent photonuclear vector meson production assuming narrow resonances. This option should also be used for exclusive vector meson production in pp collision. In pA or pp collisions, this option means that the proton emits the photon and that the gamma-A interaction is coherent.

PROD_MODE=3: Coherent photonuclear vector meson
production assuming wide resonances. This option
should in be used for exclusive \$\rho^0\$
production.

PROD_MODE=4: Incoherent photonuclear vector meson production. In pA collisions, this option means that the nucleus emits the photon. Do not use for pp.

PROD_MODE=5: Photonuclear one photon exchange uses DPMJET single.

PROD_MODE=6: Photonuclear two photon exchange
(both nuclei excited) uses DPMJET double.

PROD_MODE=7: Photonuclearsinglepa uses DPMJET
Single, proton mode.

PROD_MODE=8: [not supported/verified] Photonuclear
singlepapy uses Pythia 6

#Number of events produced (1000) N EVENTS = 10PROD PID = 443013# For PROD\ MODE 1 through 4, this selects the channel to be produced, in PDG notation. Currently supported options are list below. (443013) RND SEED = 34533# Seed for random number generator. (34533) BREAKUP MODE = 5 # Specifies the way nuclear break-up is handled. This option only works for lead or gold. It has no meaning in proton-proton or proton-nucleus collisions 1 = hard sphere nuclei (no hadronic break-up if impact parameter is greater than the sum of nuclear radii, no restriction on Coulomb breakup). 2 = requires Coulomb break-up of both nuclei, with no restriction on the number of neutrons emitted by either nucleus (XnXn). 3 = requires Coulomb break-up of both nuclei, but requires that a single neutron is emitted from each nucleus (1n1n). 4 = requires Coulomb break-up of neither nucleus. (0n0n) 5 = requires that there be no hadronic break up, no restriction on Coulomb break-up (This is similar to option 1, but with the actual hadronic interaction probability). 6 = requires Coulomb break up of one or both nuclei, with no restriction on the number of neutrons emitted (XnXn + 0nXn + Xn0n). 7 = requires Coulomb break up of only one nucleus, with no restriction on the number of neutrons emitted (0nXn+ Xn0n). 8 = selectable input parameter range (i.e. for peripheral collisions, not UPCs) regardless of nuclear breakup. Fixed input range between BMAX and BMIN (set by two otherwise optional cards, below) INTERFERENCE = 0# Specifies whether interference based on the ambiguity of which nucleus emits the photon is included. The effect of this interference is only visible at very small transverse momentum. 0 = interference off, 1 = interference on. (0) # If interference is turned on, specifies the IF STRENGTH = 1. percentage of interference. The range is -1.0 -1.0.; 1 is the standard value for ion-ion collisions, while -1.0 is expected for protonantiproton collisions. (1) INT PT MAX = 0.24# Used only when the interference option above is turned on. This specifies the maximum transverse momentum considered, in GeV/c. (0.24) INT PT N BINS = 120# Used only when the interference option above is turned on. This specifies the number of bins in

transverse momentum to use. (120)

INT PT WIDTH = 0#Used only when the interference option above is turned on. This specifies the width of bins in transverse momentum to use. (0) XSEC METHOD* = 0#Determines which method is used to calculate the cross-section for $\gamma\gamma$ cross-sections. XSEC METHOD=0 is faster, but works only for symmetric collisions (i.e. with identical nuclei). XSEC METHOD=1 always works, but is slower. (0) BSLOPE DEFINITION*=0 Used for proton and nucleon (i. e. incoherent nuclear) collisions to set the t-spectrum, dN/dt=exp(-bt). When BSLOPE DEFINITION=1, then the slope is determined by BSLOPE VALUE (below). When BSLOPE DEFINITION=2, the slope is calculated as a function of γp center of mass energy per the H1 analysis, Eur. Phys. J. C46, 585 (2006): b=4.63/GeV² + 4α ln(W_{yp}/90 GeV) The default value, BSLOPE DEFINITION=0 has no effect. Note that this affects the t-slope only; it does not affect the total cross-section WHEN BSLOPE DEFINITION=1, this determines the BSLOPE VALUE* exponential slope for dN/dt=exp(-BSLOPE VALUE*t) When set =1, performs an impulse approximation SELECT IMPULSE VM calculation (this ignores most nuclear physics, including shadowing). Default=0; no change When set =1, perform a quantum Glauber QUANTUM GLAUBER calculation, rather than classical, which is the default (or when set =0) Needed for Breakup mode=8. Sets the minimum impact BMIN parameter BMAX Needed for Breakup mode=8. Sets sthe maximum impact parameter. OUTPUT HEADER Adds a header to the output file. This header will contain various input parameters. (1 for header, 0 for no header, default is no header)

The physics constants used by STARlight can be set with the following parameters:

deuteronSlopePar	<pre>deuteron slope parameter (effective temperature) [(GeV/c)^-2]</pre>
protonMass	mass of the proton [GeV/c^2]
pionChargedMass	mass of the $pi^+/-$ [GeV/c^2]
pionNeutralMass	mass of the pi^0 [GeV/c^2]
kaonChargedMass	mass of the $K^+/-$ [GeV/c^2]
mel	mass of the $e^+/-$ [GeV/c^2]
muonMass	mass of the $mu^+/-$ [GeV/c^2]
tauMass	mass of the tau $^+/-$ [GeV/c 2]
f0Mass	mass of the $f_0(980)$ [GeV/c^2]
f0Width	width of the f_0 (980) [GeV/c ²]
f0BrPiPi	branching ratio f $0(980) \rightarrow pi^+ pi^- and pi^0$
pi^0	_
etaMass	mass of the eta [GeV/c^2]

```
width of the eta [GeV/c^2]
etaWidth
etaPrimeMass
                        mass of the eta' [GeV/c^2]
                       width of the eta' [GeV/c^2]
etaPrimeWidth
etaCMass
                       mass of the eta c [GeV/c^2]
etaCWidth
                       width of the eta c [GeV/c^2]
                       mass of the f 2(1270) [GeV/c<sup>2</sup>]
f2Mass
f2Width
                       width of the f 2(1270) [GeV/c<sup>2</sup>]
f2BrPiPi
                       [GeV/c] f 2(1270) -> pi^+ pi^-
                       mass of the a 2(1320) [GeV/c<sup>2</sup>]
a2Mass
                       width of the a_2(1320) [GeV/c<sup>2</sup>]
a2Width
f2PrimeMass
                       mass of the f' 2(1525) [GeV/c<sup>2</sup>]
f2PrimeWidth
                        width of the f' 2(1525) [GeV/c<sup>2</sup>]
                        branching ratio f' 2(1525) \rightarrow K^+ K^- and K^0
f2PrimeBrKK
                        K^0bar
zoverz03Mass
                        mass of four-quark resonance (rho^0 pair
                        production) [GeV/c^2]
                       partial width f 0(980) \rightarrow g g [GeV/c^2]
f0PartialggWidth
                    partial width eta -> g g [GeV/c^2]
etaPartialggWidth
etaPrimePartialggWidth partial width eta' -> g g [GeV/c^2]
etaCPartialggWidth partial width eta c -> g g [GeV/c^2]
                        partial width f 2(1270) \rightarrow g g [GeV/c^2]
f2PartialggWidth
a2PartialggWidth
                       partial width a_2(1320) \rightarrow g g [GeV/c^2]
f2PrimePartialggWidth partial width f' 2(1525) -> g g [GeV/c^2]
zoverz03PartialggWidth partial width four-quark resonance -> g g (rho^0
                        pair production) [GeV/c^2]
                        spin of the f 0(980)
f0Spin
                        spin of the eta
etaSpin
                        spin of the eta'
etaPrimeSpin
                        spin of the eta c
etaCSpin
                        spin of the f_2(1270)
f2Spin
a2Spin
                       spin of the a 2(1320)
                       spin of the f' 2(1525)
f2PrimeSpin
                       spin of the four-quark resonance -> g g (rho^0
zoverz03Spin
                       pair production)
axionSpin
                       spin of the axion
                       mass of the rho^0 [GeV/c^2]
rho0Mass
                       width of the rho^0 [GeV/c^2]
rho0Width
                       branching ratio rho^0 -> pi^+ pi^-
rho0BrPiPi
                        mass of the rho'^0 (4 pi^+/- final state)
rho0PrimeMass
                        [GeV/c^2]
                        width of the rho'^0 (4 pi^+/- final state)
rho0PrimeWidth
                        [GeV/c^2]
rho0PrimeBrPiPi
                        branching ratio rho'^0 -> pi^+ pi^-
OmegaMass
                       mass of the omega [GeV/c^2]
OmegaWidth
                        width of the omega [GeV/c^2]
OmegaBrPiPi
                       branching ratio omega -> pi^+ pi^-
PhiMass
                       mass of the phi [GeV/c^2]
                       width of the phi [GeV/c^2]
PhiWidth
PhiBrKK
                       branching ratio phi -> K^+ K^-
JpsiMass
                      mass of the J/psi [GeV/c^2]
                     width of the J/psi [GeV/c^2] branching ratio J/psi -> e^+ e^- branching ratio J/psi -> mu^+ mu^-
JpsiWidth
JpsiBree
JpsiBrmumu
JpsiBrppbar
                       branching ratio J/psi -> p pbar
```

Psi2SMass Psi2SWidth Psi2SBree Psi2SBrmumu Upsilon1SMass Upsilon1SWidth Upsilon1SBree Upsilon1SBrmumu Upsilon2SMass Upsilon2SMass Upsilon2SBree Upsilon2SBree Upsilon3SBree Upsilon3SMass Upsilon3SMass Upsilon3SWidth	mass of the psi(2S) [GeV/c^2] width of the psi(2S) [GeV/c^2] branching ratio psi(2S) -> e^+ e^- branching ratio psi(2S) -> mu^+ mu^- mass of the Upsilon(1S) [GeV/c^2] width of the Upsilon(1S) [GeV/c^2] branching ratio Upsilon(1S) -> e^+ e^- branching ratio Upsilon(1S) -> mu^+ mu^- mass of the Upsilon(2S) [GeV/c^2] width of the Upsilon(2S) [GeV/c^2] branching ratio Upsilon(2S) -> e^+ e^- branching ratio Upsilon(2S) -> mu^+ mu^- mass of the Upsilon(3S) [GeV/c^2] width of the Upsilon(3S) [GeV/c^2] width of the Upsilon(3S) [GeV/c^2]
Upsilon3SWidth Upsilon3SBree Upsilon3SBrmumu	width of the Upsilon(3S) [GeV/c^2] branching ratio Upsilon(3S) $->$ e^+ e^- branching ratio Upsilon(3S) $->$ mu^+ mu^-

The following parameters are used only when interfacing with the PYTHIA and/or DPMJET interfaces:

MIN_GAMMA_ENERGY = 6 #Allows the user to set the minimum photon energy (in GeV) in the rest frame of the target nucleus. The default is 6.0 GeV and it should never be set below this value since DPMJET was not designed to handle low energy interactions.

MAX GAMMA ENERGY = 600000

#Allows the user to set the maximum photon energy (in GeV) in the rest frame of the target nucleus. The default is 60000.0 GeV.

PYTHIA PARAMS = ""

#Used to supply input parameters to the PYTHIA interface. This takes a string to pass on semicolon separated parameters to PYTHIA 6. eg: "mstj(1)=0;paru(13)=0.1" (the default is a blank string " ")

PYTHIA FULL EVENT RECORD = 1

#Determines whether the full event record from PYTHIA is written to slight.out. true = yes, false = no (false). The additional information added is as follows: daughter production vertex (x [mm], y [mm], z [mm], t [mm/c]), mother1, mother2, daughter1, daughter2, PYTHIA particle status code. PYTHA 8 Particle Properties page describes in more detail the properties of mother, daughter, and status code designations.

PRINT VM=2

This command will make STARlight print out a table of y and $W_{gamma-p}$, kdN_{gamma}/dk and sigma(gamma-A) for the two possible photon directions. PRINT_VM=0, the assumed default, will not produce this ouptput.

Channels of Interest:

2-Photon Channels

Currently supported 2-photon (prod. mode = 1) channel options: jetset id particle

221	eta
331	eta-prime
441	eta-c
9010221	f0(975)
225	f2(1270)
115	a2(1320)
335	f2(1525)
33	rho0 pair
11	e+/e- pair
13	mu+/mu- pair
15	tau+/tau- pair
88	axion-like particle (ALP)

Process 88 refers to the single production of a hypothetical axion-like particle (ALP), which decays to a pair of photons. The ALP mass has to be specified by the user through the parameter AXION_MASS. The narrow width approximation is assumed here, with a fixed axion decay constant of \Lambda=1 TeV. (See equation (1) of arXiv:1607.06083 for the appropriate conventions.) The cross section can be then rescaled to arbitrary \Lambda, as long as the narrow width approximation remains valid.

Pomeron-Photon Channels

Currently supported vector meson (prod. mode = 2/3/4) options: jetset id particle

```
113
          rho0
        rho0 --> e+e-
113011
113013
         rho0 --> mu+mu-
223
         omega
223211111 omega --> pi+pi-pi0
333
          phi
933
          phi _ direct KK
333011
          phi ---> e+e-
          J/psi --> e+e-
443011
443013
          J/Psi --> mu+mu-
4432212 J/psi --> proton antiproton
444011
          Psi(2S) --> e+e-
          Psi(2S) --> mu+mu-
444013
553011
          Upsilon(1S) --> e+e-
553013
          Upsilon(1S) --> mu+mu-
          Upsilon(2S) --> e+e-
554011
          Upsilon(2S) --> mu+mu-
554013
          Upsilon(3S) --> e+e-
555011
555013
          Upsilon(3S) --> mu+mu-
913
          rho0 + direct pi+pi- (with interference). The direct
           pi+pi- fraction is from the ZEUS results, EPJ C2 p247
           (1998)
999
           four-prong final states (rho'-like to pi+pi-pi+pi-)
```

DPMJET:

Simulation of photonuclear interactions with STARlight is possible through an interface with DPMJet. These interfaces can be enabled through options passed to cmake during the configuration process. [Depreciated: Using Pythia 6 as a substitute for DPMJet]

The gfortran compiler is required to use the photonuclear interfaces.

The DPMJet package can be obtained by contacting the authors as explained here: http://sroesler.web.cern.ch/sroesler/dpmjet3.html

Once you have the code proceed with these steps:

Change the line containing the OPT variable in the DPMJet Makefile:

OPT = -c -C -std=legacy -O -O3 -g -fexpensive-optimizations -funroll-loops -fno-automatic -fbounds-check -v -fPIC

----- 64-bit -----

Make sure that all -m32 options are removed from the Makefile.

Unfortunately, the DPMJet package depends on a floating point exception trap implementation, and only a 32-bit version of that is included in the package, which needs to be replaced. An example implementation can be found here:

http://www.arsc.edu/arsc/support/news/hpcnews/hpcnews376/

Under "Fortran Floating Point Traps for Linux" there is a code example. A file based on this, fpe.c, can be found in the external/ directory in STARlight. Move that to your DPMJet directory to replace the original file and run:

\$ gcc -o fpe.o fpe.c

Note: if the above command returns the following error: /usr/lib/../lib64/crt1.o: In function `_start': (.text+0x20): undefined reference to `main' /tmp/ccs2CQsd.o: In function `enable_exceptions_': fpe.c:(.text+0xe): undefined reference to `feenableexcept'

```
collect2: error: ld returned 1 exit status
     Try: qcc fpe.c -Wall -q -c
           feenableexcept is a gcc extension and gcc may need all of the
     headers present.
                 ----- End 64-bit -----
     Then in the DPMJet directory run:
           $ make
     Note: When compiling at RCAS(BNL), needed to change g77 \rightarrow
gfortran, needed to install fluka and setenv FLUPRO /path/to/fluka, and
modify phojet before compiling. The changes for phojet is at line 29875,
from:
         PRINT LO, 'PHO DIFSLP: ERROR: this option is not installed !'
     to:
        WRITE (LO, '(/1X, A, I2)')
       & 'PHO DIFSLP: ERROR: this option is not installed
        & !', ISWMDL(13)
----- 1.2. Compiling Starlight with DPMJet interface ------
           To enable the compilation of the DPMJet interface please
     follow these steps:
            CMake uses an environment variable $DPMJETDIR to locate the
            DPMJet object files, so define it.
           $ export DPMJETDIR=<path to dpmjet>
           Then create a build directory for STARlight
           $ mkdir <build-dir>
           and change into it
           $ cd <build-dir>
           Run CMake with the option to enable DPMJet
```

\$ cmake <path-to-starlight-source> -DENABLE_DPMJET=ON

Then build it

\$ make

Note: When compiling at RCAS(BNL), needed to add the gfortran library to the CMakeLists.txt and left it there.

----- 1.3. Running Starlight with DPMJet interface -----

To run Starlight with the DPMJet interface a couple of files are needed in the directory where you want to run Starlight.

The files needed are:

slight.in (Starlight config file. An example suitable for
DPMJet can be found in config/slight.in.dpmjet)
my.input (DPMJet config file. An example can be found in
config/my.input)
dpmjet.dat (Can be found in the DPMJet source directory)

In the slight.in file the relevant production modes (PROD_MODE) for DPMJET is:

5: A+A single excitation6: A+A double excitation7: p+A single excitation

In addition the minimum and maximum gamma energies must be set. These must be within the interval set in the my.input file.

To run:

\$./starlight < my.input
[DPMJET reads from direct input/interactive]</pre>

Output

STARlight outputs an ASCII file named slight.out.

If OUTPUT_HEADER = 1 (set in input file), then there will be a header at the beginning of the output file followed by a list of events. If OUTPUT_HEADER = 0, or if OUTPUT_HEADER is not set, then there will be no header in the output file and the file will start with the list of events.

If there is a header, it will be three lines, with the following format:

CONFIG_OPT: prod_mod particle_id nevents q_glauber impulse seed
where prod mod indicates if a wide or narrow resonance has been used,

particle_id specifies the vector meson species (and decay channel) being produced, nevents indicates the total number of events in the simulation, q_glauber indicates if a quantum (=1) or classical (=0) Glauber has been selected, impulse indicates if the nuclear effects are being modelled (=0) or a simple impulse approx. is employed, and

finally seed records the random number seed used when initializing the Monte Carlo. The config opt line is followed by two lines with brief descriptions of beams in the collision, with the format:

BEAM 1(2): beam1(2) Z beam1(2) A beam1(2) LorentzGamma

where beam1(2)Z is the is the charge of the particles in beam 1(2), beam1(2)A indicates the atomic number of beam 1(2) and beam1(2)LorentzGamma is the Lorentz gamma factor associated to beam 1(2)

For each event, a summary line is printed, with the format

EVENT: n ntracks nvertices,

where n is the event number (starting with 1), ntracks is the number of tracks in the event, and nvertices is the number of vertices in the event (STARlight does not currently produce events with more than one vertex).

EVENT line is followed by a description of the vertex, with the format

VERTEX: x y z t nv nproc nparent ndaughters,

where x, y, z and t are the 4-vector components of the vertex location, nv is the vertex number, nproc is a number intended to represent physical process (always set to 0), nparent is the track number of parent track (0 for primary vertex) and ndaughters is the number of daughter tracks from this vertex.

This is followed by a series of lines describing each of the daughter tracks emanating from this vertex. Each track line has the format

TRACK: GPID px py nev ntr stopv PDGPID,

where GPID is the Geant particle id code, px, py and pz are the three vector components of the track's momentum, nev is the event number, ntr is the number of this track within the vertex (starting with 0), stopv is the vertex number where track ends (0 if track does not terminate within the event), and PDGPID is the Monte Carlo particle ID code endorsed by the Particle Data Group.

Class Diagram inputParameters inputParser inputrarser + inputrarser() + ~ inputrarser() + parseFile() + parseString() + addIntParameter() + addVintParameter() + addSouParameter() + addBoolParameter() + addSoolParameter() + inputParameters() + ~ inputParameters() + init() + configureFromFile() + baseFileName() pythiaDecayer + beam1Z() + beam1A() + beam2Z() twoPhotonLuminosity photonNucleusLuminosity starlightLimits + twoPhotonLuminosity() + photonNucleusLuminosity() + pythiaDecayer() + nucleus() + nucleus() photonNucleusLuminosity() pythiaDecaver(+ ~ nucleus() + init() + Z() + A() + init() + beam2A() twoPhotonDifferentialLuminosity() photonNucleusDifferentialLuminosity() addParticle() + beamLorentzGamma() - addStringParameter() D2LDMDY() vmsigmapt() bessel + beam1LorentzGamma() + beam2LorentzGamma() + printParameterInfo() + validateParameters() D2LDMDY() nofe() execute() pythiaDecayer() operator ==() D2LDMDY Threaded() + maxW() + addParameter() + addParameter() nuclearRadius() integral() starlightParticleCodes + nuclearRadius() + formFactor() + dipoleFormFactor() + thickness() + minW() + minW() + maxRapidity() + maxRapidity() + ptCuttnabled() + ptCuttMin() + ptCuttMin() + etaCuttMin() + etaCuttMin() + etaCuttMin() + etaCuttMin() + productionMode() + mmbEvents() + productionMode() + randomSeed() + randomSeed() + beamBreakupMode() + interferenceStrepth() + minW() pythiaStarlight + jetsetToGeant() - pythiaStarlight() - init() starlightConstants getPythia() starlightStandalone + starlightStandalone() starlightStandalone() photonNucleusCrossSection incoherentPhotonNucleusLuminosity + init() + run() + baseFileName() + configFileName() + eventDataFileName() + setBaseFileName() 5' setConfigFileName() + setEventDataFileName(+ boostEvent() photonNucleusCrossSection() + incoherentPhotonNucleusLuminosity() beamBeamSystem beamBeamSystem() + beamBeamSystem() + beamBeamSystem() + beam() + beam() + beam() + beam() + broab() + broab() + cmsBoost() + init() - generateBreakupProbabilities() - probabilityOfHadronBreakup() - probabilityOfHadronBreakup() ~ photonNucleusCrossSection(+ ~ incoherentPhotonNucleusLuminosity() - incoherentPhotonNucleusDifferentialLuminosity() slopeParameter() getChannelMass() + beam() + ~ beam() + photonFlux() + rapidity() getBNORM() luminosity() wideResonanceCrossSection getbbs() + wideResonanceCrossSection() + ~ wideResonanceCrossSection() + crossSectionCalculation() + interferenceStrength() vmPhotonCoupling() + bbs setBeamLorentzGamma() + maxPtInterference() getDefaultC() + nmbPtBinsInterference() + ptBinWidthInterference() + coherentProduct maxPhotonEnergy() crossSectionCalculation() + crossSectionC + getcsgA() + photonFlux() + sigmagp() + sigma_A() + sigma_N() + breitWigner() + nepoint() incoherentVMCrossSection + incoherentFactor() + incoherentVMCrossSection() + minGammaEnergy() - maxGammaEnergy() ~ incoherentVMCrossSection() + pythiaParams() + bbs + crossSectionCalculation() + pythiaFullEventRecord() + xsecCalcMethod() + starlight + pythia-full-Ventikecord() + xsecCalc-Method() + prodParticleType() + prodParticleDecayType() + interactionType() + protonEnergy() + setBaseFileName() + setBeam1Z() + setBeam1Z() + setBeam2Z() + setBeam2A() + setBeam2A() + setBeam2A() + setBeam1LorentzGamma() + setBeam1LorentzGamma() + setBeam2LorentzGamma() + setMaxW() + setMinW() + setMinW() + setMaxRapidity() + setMaxRapidity() + setMaxRapidity() + setMaxRapidity() starlight narrowResonanceCrossSection + starlight() + narrowResonanceCrossSection() + starlight() + ~ starlight() + rotal () + produceEvent() + baseFileName() + nmbAtempts() + nmbAccepted() + setInputParameters() - luminosityTableIsValid() - createEventChannel() + ~ narrowResonanceCrossSection() + crossSectionCalculation() starlightPythia randomGenerator + starlightPythia() + starlightPythia() + ~ starlightPythia() + init() + produceEvent() + produceEvent() + produceEvent() + setSingleMode() + setDoubleMode() + setMinGammaEngray() fileWriter eventFileWriter + fileWriter() +_randy + eventFileWriter() + eventFileWriter() + writeEvent() + writeFullPythiaInfo() ~ fileWriter() eventChannel + eventChannel() readLuminosity eventChannel(nmbAttempts() setMinGammaEnergy() nmbAccepted() setMaxGammaEnergy() ~ readLuminosity() + setNmbRapidityBins() + setPtCutEnabled() 0..1 + setFullEventRecord() + read() +_inputParameter starlightPythia() + setPtCutMin() starlightPythia() spectrumProtonNucleus + setPtCutMax() + setEtaCutEnabled() + spectrumProtonNucleus() operator ==() + setEtaCutMin() getNucleonNucleonSigma() setEtaCutMax() starlightDpmJet generateBreakupProbabilities() setProductionMode() # getSigma() + setNmbEvents() + starlightDpmJet() setProdParticleId() + init() + Gammagammasingle() + Cammagammasingle() + Cammagammasingle() + singleCrossSection() + produceEvent() - prickw() - pickw() - parentMomentum() - pp1() produceEvent() + setRandomSeed() + setBamBreakupMode() + setInterferenceEnabled() + setInterferenceEnrapt() + setMaxPitnterference() + setMaxPitnterference() + setPtBinWidthInterference() + setCoherentProduction() + setMaxGammaEnergy() + setMaxGammaEnergy() + setPythiaParams() + setPythiaParams() + setPythiaPullEventRecord() + setXsecCall Method() produceSingleEvent() produceDoubleEvent() produceEvent() setSingleMode() setDoubleMode() starlightParticle lorentzVector + starlightParticle() + lorentzVector() setMinGammaEnergy() + pTgamma() setMaxGammaEnergy() + ~ lorentzVector() + lorentzVector() vmpt() + setProtonMode() - starlightDpmJet() · twoBodyDecay() · fourBodyDecay() ~ starlightParticle() pp1() picky() + setPdgCode() + getPdgCode() + SetXYZT() pp2() + SetPxPyPzE() twoBodyDecay() pp_1() getMass() + GetPx() + GetPy() setCharge() getMass() pp_2() getWidth() getCharge() setFirstParent() getWidth() twoBodyDecay() + getTheta() + GetPz() getSpin() thetalep() + getSpin() setLastParent() + GetE() + setProdParticleType() tauDecay() + getDaughterMass() getFirstParent() operator +=() + setProdParticleDecayType() + setInteractionType() + setProtonEnergy() + setParameter() getMass() + pseudoRapidity() getLastParent() setFirstDaughter() getFirstDaughter() setLastDaughter() + operator -=() + M2() getWidth() M() BoostVector() + print() + write() + setLastDaughter() + getLastDaughter() + setStatus() + getStatus() + setVertex() + getVertex() + Boostvector() + Boost() + operator <<() validate : bool + parameterValueKey() parameter nBodyPhaseSpaceGen + parameter() vector3 + vector3() + vector3() + vector3() + vector3() + cetVector() + SetVector() + SetVector() + operator =() + operator :=() parameterbase upcEvent value() + upcEvent() validationkey() toString() + upcEvent() + operator <<() ~ upcEvent() addParticle() Gammaaincoherentym Gammaar Gammaawidevm addVertex() + setRequired() + validationkey() addGamma() + Gammaaincoherentym() + Gammaanarrowym() + Gammaawidevm() + addGamma() + getParticles() + getVertices() + getGammaEne + operator =() + operator +() + boost() parameterlist + operator <<(- parameter() Gammaaincoherentvm() + operator +=(+ operator -=() + X() + Y() + Z() + Mag2() + Mag() + parameterlist() + add() + validationKey() + operator <<()

File Descriptions

Readme.pdf

[This file.] provides information on the installation, operation, and construction of STARlight.

CMakeLists.txt

controls STARlight compilation. For details, please see above in Installation. This is the default/supported compilation method.

Makefile

A sample Makefile for compilation on *nix systems. This file is not actively supported. Please use CMake.

starlightconfig.h.in

passes on some compiler settings; such as enabling the Pythia/DPMJet sections within the source code.

starlightDoxyfile.conf

Doxygen configuration file.

CMake Modules:

FindPythia8.cmake

used by CMake to find the Pythia 8 files needed to compile STARlight with Pythia 8 dependent options enabled. It searches for: Pythia.h, Index.xml, libpythia8

FindPythia6.cmake

used by CMake to find the Pythia 6 files needed to compile STARlight with Pythia 6 dependent options enabled. It searches for: libPythia6. Pythia 6 functionality has been deprecated.

FindDPMJet.cmake

used by CMake to find the DPMJET files needed to compile STARlight with DPMJET dependent options enabled. It searches for: dpmjet3.0-5.0, pythia6115dpm3v1.0, and phojet1.12-35c4.0

FindROOT.cmake

used by CMake to find the ROOT files needed to compile STARlight with ROOT dependent options enabled. It searches for: root-config. root-config is then used to set the rest of the paths/options needed to enable ROOT within STARlight.

CommonMacros.cmake

A collection of useful cmake macos.

FindLHAPDF.cmake

used by CMake to find the LHAPDF dependent options enabled. This was necessary for older versions of Pythia8, but this is no longer the case. However, this file is being kept in the

distribution for users that would like to re-enable it. It searches for: Pythia.h and liblhapdfdummy

Config files:

my.input

A sample DPMJET configuration file.

slight.in

A sample STARlight input file, to select the desired final state and associated options. The section $\underline{\text{Input}}$ has more information.

slight.in.dpmjet

A sample slight.in file to use the DPMJET options (eg: PROD MODE = 5, 6, 7, and MIN_GAMMA_ENERGY, and MAX_GAMMA_ENERGY.).

slight.in.ee_rhic

A sample slight.in file for e+e- production by Au-Au at top RHIC energies

slight.in.jpsi_lhc

A sample slight.in file for \mbox{J}/ψ production by Pb-Pb at the LHC.

slight.in.pPb_lhc

A sample slight.in file for \mbox{J}/ψ production by p-Pb at the LHC.

slight.in.rho rhic

A sample slight.in file for $\boldsymbol{\rho}$ production by Au-Au at top RHIC energies.

dpmjet:

dpmjetint.f

This is a DPMJET library, used in the CMakeLists.txt file to link when enabling DPMJET.

external:

fpe.c

corrects for the floating point trap differences between 32 and 64-bit. The $\underline{\text{DPMJET}}$ section has more information.

pythia6:

pythiainterface.h

interfaces Pythia6 with STARlight. Pythia 6 functionality has been deprecated.

utils:

Ana.C

This macro runs Analyze.cxx, which takes as input an ASCII STARlight output file, slight.out, and creates a standard set of histograms, which are stored in histograms.root

Analyze.cxx

This macro reads in a starlight output file and creates histograms of the p_T and rapidity of the daughters, as well as the p_T, rapidity and mass of the parent. It assumes there are only 2 daughter tracks that are electrons, muons, or pions. The histograms for the daughter particles are called fPt2, fPt2, fRap1, and fRap2. Parent histograms are created for each possible daughter species (e.g., parent p_T histograms are created with the names fPtE1, fPtMu, and fPtPi), but only the ones corresponding to the actual daughter particle are filled. The histograms are saved in a file called histograms.root.

To use this Analyze.cxx, modify the file Ana.C to call your input file (as downloaded, it calls slight.out) and the number of events you wish to process (as downloaded, it processes 20 events). Then open root and type ".x Ana.C".

Analyze.h

The header file for Analyze.cxx and Ana.C.

AnalyzeTree.cxx

This macro reads the starlight.root file produced by ConvertStarlightAsciiToTree.C, which contains TLorentzVectors for the parents and a TClonesArray of TLorentzVectors for the daughters. It creates histograms of the p_T and rapidity of the daughters, as well as the p_T, rapidity and mass of the parent. While the parents may have been created as the vector sum of any number of daughter particles, this macro currently produces histograms for only the first two daughter particles. The daughter histograms are called D1Pt, D2Pt, D1Rapidity, and D1Rapidity. Parent histograms are named ParentPt, ParentRapidity, and ParentMass. The histograms are stored in starlight histos.root.

To use Analyzetree.cxx, first run ConvertStarlightAsciiToTree.C to produce the starlight.root file. If needed, modify the file AnalyzeTree.h to call your input file (as downloaded, it calls starlight.root). Then open root and type .x AnaTree.C .

AnalyzeTree.h

The header file for AnalyzeTree.cxx.

AnaTree.C

compiles and runs AnalyzeTree.cxx, which takes as input the starlight.root file produced by ConvertStarlightAsciiToTree.cxx output histograms are stored in starlight histos.root

ConvertStarlightAsciiToTree.C

reads a starlight output file (default name slight.out) and creates a root file with TLorentzVectors for the parent and a TClonesArray of TLorentzVectors for the daughter particles. The output is stored in a root file (default name starlight.root) with one branch labeled "parent" and the other labeled "daughters". Any number of daughter tracks can be accommodated. Daughter species currently accommodated are: electrons, muons, charged or neutral pions, charged or neutral kaons, and protons.

To use AnaTree.C, open root and then type .x ConvertStarlightAsciiToTree.C("inputfilename", "outputfilename") The root file produced can be examined in a root TBrowser.

A macro to read this root file and make some standard plots is also provided. This macro is called AnalyzeTree.cxx; it can be compiled and run with the AnaTree.C macro by opening root and typing .x AnaTree.C()

Source Files:

beam.cpp

generates the beam class, which inherits from the nucleus class (cf. <u>nucleus.cpp</u>). The object represents an accelerated nucleus, or a beam.

Functions:

beam::beam
beam::~beam

beambeamsystem.cpp

represents the colliding system of interest.

Functions:

beamBeamSystem::beamBeamSystem
beamBeamSystem::~beamBeamSystem
beamBeamSystem::probabilityOfBreakup

beamBeamSystem::generateBreakupProbabilities
beamBeamSystem::probabilityOfHadronBreakup
beamBeamSystem::probabilityOfPhotonBreakup

bessel.cpp

calculate modified Bessel functions of the first and second $\ensuremath{\mathsf{kind.}}$

Functions:

bessel::besI0
bessel::dbesk0
bessel::dbesk1
bessel::besI1

eventchannel.cpp

inherits from readLuminosity. It is a base for class for functions to produce events that is overloaded by other classes (Gammagammaleptonpair, Gammagammasingle, Gammaavectormeson, starlightDpmJet, and starlightPythia).

Functions:

eventfilewriter.cpp

writes event information in the output file.

Functions:

eventFileWriter::eventFileWriter
eventFileWriter::~eventFileWriter
eventFileWriter::writeEvent

filewriter.cpp

The base class for eventFileWriter, which is writes event information in the output file.

Functions:

fileWriter::fileWriter()
fileWriter::~fileWriter()
fileWriter::open
fileWriter::open(filename)
fileWriter::close

gammaaluminosity.cpp

contains the photonNucleusLuminosity class, which inherits from photonNucleusCrossSection. It calculates the differential cross-section for gamma-A interactions.

Functions:

photonNucleusLuminosity::photonNucleusLuminosity
photonNucleusLuminosity::~photonNucleusLuminosity
photonNucleusLuminosity::photonNucleusDifferentialLuminosi
ty //Calculates and outputs the differential luminosity
photonNucleusLuminosity::pttablegen // Calculates the pt
spectra for VM production with interference per S. Klein
and J. Nystrand, Phys. Rev Lett. 84, 2330 (2000).
photonNucleusLuminosity::vmsigmapt //calculates the effect
of the nuclear form factor on the pt spectrum, for use in
interference calculations. It calculates the cross section
suppression SIGMAPT(PT) as a function of pt. The input pt
values come from pttable.inc
photonNucleusLuminosity::nofe //calculates the 'photon
density'd^2N gamma/db^2

gammaavm.cpp

is responsible for classes Gammaavectormeson, Gammaanarrowvm, and Gammaawidevm. Both Gammaanarrowvm and Gammaawidevm inherit from Gammaavectormeson, which inherits from eventChannel. The classes are responsible for generating and decaying the vector mesons produced by photon-nucleus interactions.

Functions:

Gammaavectormeson::Gammaavectormeson Gammaavectormeson::~Gammaavectormeson Gammaavectormeson::pickwy //responsible for selecting the events center of mass energy and rapidity Gammaavectormeson::twoBodyDecay // This routine decays a particle into two particles of mass mdec, taking spin into account Gammaavectormeson::fourBodyDecay // decays a particle into four particles with isotropic angular distribution Gammaavectormeson::getDaughterMass //returns the daughter particles mass, & the final particles id... Gammaavectormeson::getTheta //This depends on the decay angular distribution Gammaavectormeson::getWidth Gammaavectormeson::getMass Gammaavectormeson::getSpin //it's a VM, returns 1 Gammaavectormeson::momenta // calculates momentum and energy of vector meson given W and Y, without interference. Gammaavectormeson::pTgamma //finds the photon pT Gammaavectormeson::vmpt // calculates momentum and energy of a vector meson given W and Y, including interference. It gets the pt distribution from a lookup table. produceEvent pseudorapidity Gammaanarrowvm::Gammaanarrowvm Gammaanarrowvm::~Gammaanarrowvm Gammaanarrowvm::gammaaincoherentvm Gammaawidevm::Gammaawidevm Gammaawidevm::~Gammaawidevm

gammagammaleptonpair.cpp

inherits from eventChannel. It calculates the lepton pair's cross-section and generates and decayes the lepton pairs.

Functions:

Gammagammaleptonpair::Gammagammaleptonpair Gammagammaleptonpair::~Gammagammaleptonpair Gammagammaleptonpair::twoLeptonCrossSection // calculates section for 2-particle decay, per, see STAR Note 243, Eq. 9. It calculates the 2-lepton differential cross section Gammagammaleptonpair::twoMuonCrossSection // gives the two muon cross section as a function of Y&W, per G.Soff et. al Nuclear Equation of State, part B, 579 Gammagammaleptonpair::pickw // Picks a w for the 2- photon calculation. Gammagammaleptonpair::picky // Picks a y given a W Gammagammaleptonpair::pairMomentum // calculates px,py,pz,and E given w and y Gammagammaleptonpair::pp 1 // For beam 1, returns a random momentum drawn from from pp 1(E) distribution Gammagammaleptonpair::pp 2 // For beam 2, returns a random momentum drawn from from pp_2(E) distribution Gammagammaleptonpair::twoBodyDecay //decays a particle into two particles of mass mdec, taking spin into account

```
Gammagammaleptonpair::thetalep // calculates the cross-
section as a function of angle for a given W and Y, for
the production of two muons or taus, per Brodsky et al.
PRD 1971, 1532 equation 5.7
Gammagammaleptonpair::produceEvent //returns the vector
with the decay particles inside
Gammagammaleptonpair::calculateTable //calculates the
tables that are used elsewhere in the Monte Carlo the tau
decay follows V-A theory, 1 - 1/3 cos(theta) the energy of
each of the two leptons in tau decay is calculated using
formula 10.35 in "Introduction to elementary particles by
D. Griffiths," which assumes that the mass of the electron
is 0. The maximum electron energy in in such a system is
0.5 * mass of the tau
Gammagammaleptonpair::tauDecay
                               // assumes that the
tauons decay to electrons and calculates the directons of
the decays
```

Gammagammaleptonpair::getMass
Gammagammaleptonpair::getWidth
Gammagammaleptonpair::getSpin

gammagammasingle.cpp

inherits from eventChannel. It calculates the cross-section for single mesons and generates and decays the single mesons from gamma-gamma interactions. It also generates single mesons which are then decayed by Pythia 8.

Functions:

```
Gammagammasingle::Gammagammasingle
Gammagammasingle::~Gammagammasingle
Gammagammasingle::singleCrossSection // calculates the
cross-section in the narrow-width approximation, per STAR
Note 243, Eq. 8
Gammagammasingle::pickw // picks a w for the 2-photon
calculation.
Gammagammasingle::picky
Gammagammasingle::parentMomentum // calculates
px,py,pz,and E given w and y
Gammagammasingle::pp 1 // For beam 1, returns a random
momentum drawn from from pp(E) distribution
                     // For beam 2, returns a random
Gammagammasingle::pp_2
momentum drawn from from pp(E) distribution
two particles of mass mdec, taking spin into account
Gammagammasingle::produceEvent
Gammagammasingle::getMass
Gammagammasingle::getSpin
```

incoherentPhotonNucleusLuminosity.cpp

is responsible for the incoherentPhotonNucleusLuminosity class and inherits from photonNucleusCrossSection. It houses the differential luminosity calculation for incoherent gamma-A interactions.

Functions:

incoherentPhotonNucleusLuminosity::incoherentPhotonNucleus Luminosity incoherentPhotonNucleusLuminosity::~incoherentPhotonNucleu
sLuminosity

incoherentPhotonNucleusLuminosity::incoherentPhotonNucleus
DifferentialLuminosity

incoherentPhotonNucleusLuminosity::nofe //Function for the
calculation of the "photon density".

incoherentVMCrossSection.cpp

inherits from photonNucleusCrossSection. It calculates the cross-section for incoherent photon-nucleus interactions.

Functions:

incoherentVMCrossSection::incoherentVMCrossSection incoherentVMCrossSection::~incoherentVMCrossSection incoherentVMCrossSection::crossSectionCalculation // calculates the vector meson cross section assuming a narrow resonance. For reference, see STAR Note 386.

inputParameters.cpp

sets and stores STARlight's input parameters.

Functions:

inputParameters::inputParameters
inputParameters::~inputParameters

inputParameters::init

inputParameters::configureFromFile

inputParameters::print
inputParameters::write

inputParameters::parameterValueKey

inputParser.cpp

parses the input files and stores the information in the inputParameters.

Functions:

inputParser::inputParser()
inputParser::~inputParser()
inputParser::parseFile
inputParser::parseString
inputParser::addIntParameter
inputParser::addVintParameter
inputParser::addFloatParameter
inputParser::addDoubleParameter
inputParser::addBoolParameter
inputParser::addStringParameter
inputParser::printParameterInfo
inputParser::validateParameters

lorentzvector.cpp

holds Lorentz 4-vectors.

Functions:

lorentzVector::lorentzVector
lorentzVector::~lorentzVector
SetXYZT

main.cpp

the "main" file/function-where the program starts.

narrowResonanceCrossSection.cpp

inherits from photonNucleusCrossSection. It calculates the cross-section for narrow resonance vector mesons.

Functions:

narrowResonanceCrossSection::narrowResonanceCrossSection narrowResonanceCrossSection::~narrowResonanceCrossSection narrowResonanceCrossSection::crossSectionCalculation // calculates the vector meson cross section assuming a narrow resonance, per STAR Note 386.

nBodyPhaseSpaceGen.cpp

is responsible for the kinematics used in the four-prong decays.

Functions:

nBodyPhaseSpaceGen::nBodyPhaseSpaceGen nBodyPhaseSpaceGen::~nBodyPhaseSpaceGen nBodyPhaseSpaceGen::setDecay // sets decay constants and prepares internal variables nBodyPhaseSpaceGen::generateDecay// generates event with certain n-body mass and momentum and returns event weight general purpose function nBodyPhaseSpaceGen::generateDecayAccepted// generates full event with certain n-body mass and momentum only, when event is accepted (return value = true) this function is more efficient, if only weighted evens are needed nBodyPhaseSpaceGen::pickMasses// randomly choses the (n -2) effective masses of the respective (i + 1)-body systems nBodyPhaseSpaceGen::calcWeight// computes event weight (= integrand value) and breakup momenta uses vector of intermediate two-body masses prepared by pickMasses() nBodyPhaseSpaceGen::calcEventKinematics// calculates complete event from the effective masses of the (i + 1)body systems, the Lorentz vector of the decaying system, and the decay angles uses the break-up momenta calculated by calcWeight() nBodyPhaseSpaceGen::estimateMaxWeight// calculates maximum weight for given n-body mass nBodyPhaseSpaceGen::print

nucleus.cpp

defines the basis properties of a nucleus such as radius, form factor, and thickness.

Functions:

nucleus::nucleus
nucleus::~nucleus
nucleus::init
nucleus::nuclearRadius
nucleus::formFactor

nucleus::dipoleFormFactor
nucleus::thickness// calculates the nuclear thickness
function per Eq. 4 in Klein and Nystrand, PRC 60

photonNucleusCrossSection.cpp

calculates the cross-section for coherent photon-Nucleus interactions.

Functions:

photonNucleusCrossSection::photonNucleusCrossSection

```
photonNucleusCrossSection::~photonNucleusCrossSection
           photonNucleusCrossSection::getcsgA // returns the cross-
            section for photon-nucleus interaction producing vector
           mesons
           photonNucleusCrossSection::photonFlux
                                                     // gives the
           photon flux as a function of energy Egamma for arbitrary
           nuclei and gamma. The first time it is called, it
           calculates a lookup table which is used on subsequent
            calls. It returns dN gamma/dE (dimensions 1/E), not dI/dE
            energies are in GeV, in the lab frame
           photonNucleusCrossSection::nepoint// gives the spectrum of
            virtual photons, dn/dEgamma, for a point charge q=Ze
           sweeping past the origin with velocity gamma, integrated
           over impact parameter from bmin to infinity, per Eq. 15.54
           of Jacksons Classical Electrodynamics
           photonNucleusCrossSection::sigmagp// gives the gamma-
           proton --> VectorMeson cross section. Wgp is the gamma-
           proton CM energy. Unit for cross section: fm**2
           photonNucleusCrossSection::sigma A// Nuclear Cross Section
           sig N, sigma A in (fm**2)
           \verb"photonNucleusCrossSection":: \verb"sigma" N// Nucleon Cross Section" \\
            in (fm**2)
           photonNucleusCrossSection::breitWigner// uses simple
            fixed-width s-wave Breit-Wigner without coherent
           backgorund for rho' (PDG '08 eq. 38.56)
pythiadecayer.cpp
      links Pythia 8 and STARlight, and initalizes Pythia 8.
      Functions:
           pythiaDecayer::pythiaDecayer
           pythiaDecayer::~pythiaDecayer
           pythiaDecayer::init
           pythiaDecayer::addParticle
           pythiaDecayer::execute
randomgenerator.cpp
      STARlight's random number generator, using the same algorithm
      as ROOTs TRANDOM3 class. It is based on M. Matsumoto and T.
      Nishimura, Mersenne Twistor: A 623-dimensionally
      equidistributed uniform pseudorandom number generator. For
      more information see
      http://www.math.keio.ac.jp/~matumoto/emt.html
      Functions:
            randomGenerator::SetSeed
            randomGenerator::Rndom
readinluminosity.cpp
      reads in the luminosity tables from slight.txt, which is
      generated in the early stages of the program.
      Functions:
            readLuminosity::readLuminosity
            readLuminosity::~readLuminosity
            readLuminosity::read
```

spectrum.cpp

sets up functions needed to make cross-section calculations for general photonuclear interactions modeled with DPMJET.

Functions:

spectrum::spectrum
spectrum::generateKsingle
spectrum::generateKdouble
spectrum::drawKsingle
spectrum::drawKdouble

spectrum::generateBreakupProbabilities

spectrum::getFnSingle
spectrum::getFnDouble

spectrum::getTransformedNofe

sprectrumprotonnucleus.cpp

sets up functions needed to make cross-section calculations for general photonuclear interactions modeled with DPMJET.

Functions:

spectrumProtonNucleus::spectrumProtonNucleus
spectrumProtonNucleus::generateBreakupProbabilities
spectrumProtonNucleus::getSigma

starlight.cpp

initializes and then produces and decays events.

Functions:

starlight::starlight
starlight::~starlight
starlight::init

Starright::Int

starlight::produceEvent

starlight::luminosityTableIsValid
starlight::createEventChannel

starlightdpmjet.cpp

hosts the class starlightDpmJet which inherits from the eventChannel class. It includes methods to generate diffractive events with DPMJET.

Functions:

starlightDpmJet::starlightDpmJet

starlightDpmJet::init

starlightDpmJet::produceEvent

starlightDpmJet::produceSingleEvent
starlightDpmJet::produceDoubleEvent

starlightparticle.cpp

is a container to store particle information.

Functions:

starlightParticle::starlightParticle
starlightParticle::~starlightParticle

starlightparticlecodes.cpp

 ${f c}$ onverts jetset particle numbers to the corresponding GEANT code.

Functions:

starlightParticleCodes::jetsetToGeant

starlightpythia.cpp

inherits from the eventChannel class. It includes methods to calculate diffractive events with Pythia6. Pythia 6 functionality has been deprecated.

Functions:

starlightPythia::starlightPythia
starlightPythia::~starlightPythia
starlightPythia::init

starlightPythia::produceEvent

starlightStandalone.cpp

is used by Main.cpp and in turn calls methods from the starlight class.

Functions:

starlightStandalone::starlightStandalone
starlightStandalone::~starlightStandalone
starlightStandalone::init
starlightStandalone::run
starlightStandalone::boostEvent

twophotonluminosity.cpp

inherits from beamBeamSystem, and is responsible for calculating the two photon luminosity table based on ${\tt W}$ and ${\tt Y}$.

Functions:

twoPhotonLuminosity::twoPhotonLuminosity
twoPhotonLuminosity::~twoPhotonLuminosity
twoPhotonDifferentialLuminosity
twoPhotonLuminosity::D2LDMDY
twoPhotonLuminosity::D2LDMDY_Threaded
twoPhotonLuminosity::integral
twoPhotonLuminosity::radmul
twoPhotonLuminosity::integrand
twoPhotonLuminosity::Nphoton

upcevent.cpp

stores the final event information.

Functions:

upcEvent::upcEvent
upcEvent::operator=
upcEvent::operator+
upcEvent::boost

vector3.cpp

is a container for 3D-vectors.

Functions:

vector3::vector3
vector3::~vector3
vector3::SetVector

wideResonanceCrossSection.cpp

inherits from photnNucleusCrossSection. It is responsible for calculating the cross-section of vector mesons with a wide resonance (eg. Rho).

Functions:

wideResonanceCrossSection::wideResonanceCrossSection
wideResonanceCrossSection::~wideResonanceCrossSection

```
wideResonanceCrossSection::crossSectionCalculation //
calculates the cross-section assuming a wide (Breit-Wigner)
resonance.
```

Include Files:

```
beam.h //This class includes a single beam of nucleons
            Included in files
                  beambeamsystem.h
                  twophotonluminosity.h
                  beam.cpp
                  gammaaluminosity.cpp
                  incoherentPhotonNucleusLuminosity.cpp
                  spectrumprotonnucleus.cpp
                  twophotonluminosity.cpp
            Functions
                  beam
                  ~beam
                  rapidity
                  photonFlux
                  setBeamLorentzGamma
     beambeamsystem.h //This class covers a coliding beam system
            Included in files
                  eventchannel.h
                  gammaaluminosity.h
                  gammaavm.h
                  gammagammasingle.h
                  incoherentPhotonNucleusLuminosity.h
                  photonNucleusCrossSection.h
                  starlightpythia.h
                  twophotonluminosity.h
                  beambeamsystem.cpp
                  gammaaluminosity.cpp
                  incoherentPhotonNucleusLuminosity.cpp
                  spectrum.cpp
                  spectrumprotonnucleus.cpp
                  twophotonluminosity.cpp
            Functions
                  beamBeamSystem
                  ~beamBeamSystem
                  cmsBoost
                  beamLorentzGamma
                  beam1
                  beam2
                  probabilityOfBreakup
                  init
                  generateBreakupProbabilities
                  probabilityOfHadronBreakup
                  probabilityOfPhotonBreakup
      bessel.h
```

Included in files

beam.cpp beambeamsystem.cpp

```
bessel.cpp
            gammaaluminosity.cpp
            incoherentPhotonNucleusLuminosity.cpp
            photonNucleusCrossSection.cpp
            twophotonluminosity.cpp
      Functions
            besI0
            dbesk0
            dbesk1
            besI1
eventchannel.h
      Included in files
            gammaavm.h
            gammagammaleptonpair.h
            gammagammasingle.h
            starlight.h
            starlightdpmjet.h
            starlightpythia.h
            eventchannel.cpp
            starlight.cpp
     Functions
            eventChannel
            ~eventChannel
            nmbAttempts ///< returns number of attempted events
            nmbAccepted ///< returns number of accepted events</pre>
            produceEvent
            transform ///< Lorentz-transforms given 4-vector</pre>
            pseudoRapidity ///< calculates pseudorapidity for</pre>
            given 3-momentum
eventfilewriter.h
      Included in files
            eventfilewriter.cpp
            main.cpp
            starlight.cpp
            starlightStandalone.cpp
      Functions
            eventFileWriter
            writeEvent /** Write an UPC event to file */
            writeFullPythiaInfo /** Set if we want to write full
            pythia information */
filewriter.h
      Included in files
            eventfilewriter.h
            eventfilewriter.cpp
            filewriter.cpp
            main.cpp
            starlight.cpp
            starlightStandalone.cpp
      Functions
            fileWriter
            ~fileWriter
            open //opens the file
            setFileName//set the filename we're writing to
```

```
gammaaluminosity.h
```

Included in files

gammaaluminosity.cpp
starlight.cpp

Functions

photonNucleusLuminosity
 ~photonNucleusLuminosity
photonNucleusDifferentialLuminosity
vmsigmapt
nofe
pttablegen

gammaavm.h

Included in files

gammaavm.cpp
starlight.cpp

Functions

Gammaavectormeson \sim Gammaavectormeson produceEvent pickwy momenta pTgamma vmpt twoBodyDecay fourBodyDecay getMass getWidth getTheta getSpin getDaughterMass pseudoRapidity Gammaanarrowvm ~Gammaanarrowvm Gammaawidevm ~Gammaawidevm Gammaaincoherentvm ~Gammaaincoherentvm

gammagammaleptonpair.h

Included in files

gammagammaleptonpair.cpp
starlight.cpp

Functions

Gammagammaleptonpair ~Gammagammaleptonpair twoLeptonCrossSection calculateTable produceEvent twoMuonCrossSection pickw picky pairMomentum pp_1 pp_2

twoBodyDecay
thetalep
tauDecay
getMass
getWidth
getSpin

gammagammasingle.h

Included in files

gammagammasingle.cpp
starlight.cpp

Functions

Gammagammasingle
~Gammagammasingle
singleCrossSection
produceEvent
pickw
picky
parentMomentum
pp
twoBodyDecay
thephi
getMass
getWidth
getSpin

incoherentPhotonNucleusLuminosity.h

Included in files

incoherentPhotonNucleusLuminosity.cpp
starlight.cpp

Functions

incoherentPhotonNucleusLuminosity
~incoherentPhotonNucleusLuminosity
incoherentPhotonNucleusDifferentialLuminosity
nofe

incoherentVMCrossSection.h

Included in files

gammaavm.cpp

incoherentVMCrossSection.cpp

Functions

incoherentVMCrossSection
~incoherentVMCrossSection
crossSectionCalculation

inputParameters.h

Included in files

beam.h
gammaaluminosity.h
incoherentPhotonNucleusLuminosity.h
readinluminosity.h
starlightpythia.h
beam.cpp
beambeamsystem.cpp
gammaaluminosity.cpp
incoherentPhotonNucleusLuminosity.cpp

inputParameters.cpp
nucleus.cpp
readinluminosity.cpp
starlight.cpp
starlightStandalone.cpp
twophotonluminosity.cpp

Functions

parameterlist add validationKey parameterbase toString operator<< parameter operator=

ptr
value
name
required

setValue setName

setRequired
inputParameters
~inputParameters

init
configureFromFile

baseFileName

beam1Z beam1A beam2Z beam2A

beamLorentzGamma
beamlLorentzGamma
beamllorentzGamma

 ${\tt beam2LorentzGamma}$

maxW
minW
nmbWBins

maxRapidity

nmbRapidityBins

ptCutEnabled
ptCutMin

ptCutMax

etaCutEnabled

etaCutMin

etaCutMax

 ${\tt production} {\tt Mode}$

nmbEvents

prodParticleId

randomSeed

beamBreakupMode

interferenceEnabled

interferenceStrength

 ${\tt maxPtInterference}$

nmbPtBinsInterference

ptBinWidthInterference

 ${\tt coherentProduction}$

incoherentFactor

minGammaEnergy maxGammaEnergy pythiaParams pythiaFullEventRecord xsecCalcMethod prodParticleType prodParticleDecayType interactionType protonEnergy setBaseFileName setBeam1Z setBeam1A setBeam2Z setBeam2A setBeamLorentzGamma setBeam1LorentzGamma setBeam2LorentzGamma setMaxW setMinW setNmbWBins setMaxRapidity setNmbRapidityBins setPtCutEnabled setPtCutMin setPtCutMax setEtaCutEnabled setEtaCutMin setEtaCutMax setProductionMode setNmbEvents setProdParticleId setRandomSeed setBeamBreakupMode setInterferenceEnabled setInterferenceStrength setMaxPtInterference setNmbPtBinsInterference setPtBinWidthInterference setCoherentProduction setIncoherentFactor setMinGammaEnergy setMaxGammaEnergy setPythiaParams setPythiaFullEventRecord setXsecCalcMethod setProdParticleType setProdParticleDecayType setInteractionType setProtonEnergy setParameter print write parameterValueKey instance

inputParser.h

Included in files

```
inputParameters.h
            inputParameters.cpp
            inputParser.cpp
      Functions
            inputParser
            inputParser
            parseFile/** Parse a file */
            parseString
            addIntParameter
            addUintParameter
            addFloatParameter
            addDoubleParameter
            addBoolParameter
            addStringParameter
            printParameterInfo
            validateParameters
            _parameter
            operator==
            operator<
            printParameterInfo
            addParameter
lorentzvector.h
      Included in files
            nBodyPhaseSpaceGen.h
            starlightparticle.h
            lorentzvector.cpp
      Functions
            lorentzVector
            ~lorentzVector
            SetXYZT
            SetPxPyPzE
            GetPx
            GetPv
            GetPz
            GetE
            operator +=
            operator -=
            М2
            BoostVector
            Boost
            operator <<
narrowResonanceCrossSection.h
      Included in files
            narrowResonanceCrossSection.cpp
            gammaavm.cpp
      Functions
            narrowResonanceCrossSection
            ~narrowResonanceCrossSection
            crossSectionCalculation
nBodyPhaseSpaceGen.h
      Included in files
            gammaavm.h
```

nBodyPhaseSpaceGen.cpp

Functions

Factorial breakupMomentum nBodyPhaseSpaceGen ~nBodyPhaseSpaceGen setDecay random generateDecay generateDecayAccepted setMaxWeight maxWeight normalization eventWeight maxWeightObserved resetMaxWeightObserved estimateMaxWeight eventAccepted daughter daughters nmbOfDaughters daughterMass intermediateMass breakupMom cosTheta phi print operator << pickMasses calcWeight pickAngles calcEventKinematics eventAccepted

nucleus.h

Included in files

beam.h
beambeamsystem.h
twophotonluminosity.h
gammaaluminosity.h
incoherentPhotonNucleusLuminosity.cpp
nucleus.cpp
spectrumprotonnucleus.cpp
starlightdpmjet.cpp
starlightpythia.cpp
twophotonluminosity.cpp

Functions nucleus

~nucleus
init
Z
A
nuclearRadius
formFactor
dipoleFormFactor
thickness

```
00
            rho0
            woodSaxonSkinDepth
            fritiofR0
            rws
photonNucleusCrossSection.h
      Included in files
             gammaaluminosity.h
             incoherentPhotonNucleusLuminosity.h
             incoherentVMCrossSection.h
            narrowResonanceCrossSection.h
             wideResonanceCrossSection.h
            gammaavm.cpp
             photonNucleusCrossSection.cpp
      Functions
            photonNucleusCrossSection
            ~photonNucleusCrossSection
            slopeParameter///< returns slope of t-distribution</pre>
             [(GeV/c)^{-2}]
            getChannelMass ///< returns mass of the produced</pre>
            system [GeV/c^2]
            getBNORM
            luminosity//< returns luminosity [10^{26} cm^{-2}]</pre>
            sec^{-1}]
            getbbs///< returns beamBeamSystem</pre>
            vmPhotonCoupling ///< vectormeson-photon coupling</pre>
            constant f v / 4 pi (cf. Eq. 10 in KN PRC 60 (1999)
            014903)
            getDefaultC
            maxPhotonEnergy///< returns max photon energy in lab</pre>
            frame [GeV] (for vectormesons only)
            crossSectionCalculation
            aetcsaA
            photonFlux
            sigmagp
            sigma A
            sigma N
            breit\( \overline{W} \) igner
            nepoint
pythiadecayer.h
      Included in files
            gammagammasingle.h
             pythiadecayer.cpp
      Functions
            pythiaDecayer
            ~pythiaDecayer
            init// Initialize
            addParticle// Add particle to current event
            execute// Execute event and return starlight type
            event
            pythiaDecayer
            operator==
```

PythiaStarlight.h

```
Included in files
            starlight.cpp
      Functions
            pythiaStarlight
            init
            getPythia
randomgenerator.h
      Included in files
            eventchannel.h
            gammaavm.h
            gammagammasingle.h
            nBodyPhaseSpaceGen.h
            inputParameters.cpp
            randomgenerator.cpp
            spectrum.cpp
      Functions
            SetSeed
            Rndom
            randomGenerator
            instance
readinluminosity.h
      Included in files
            eventchannel.h
            gammaavm.h
            gammagammaleptonpair.h
            gammagammasingle.h
            readinluminosity.cpp
      Functions
            readLuminosity
            ~readLuminosity
            read
reportingUtils.h
      Included in files
            inputParser.h
            nBodyPhaseSpaceGen.h
            beam.cpp
            beambeamsystem.cpp
            inputParameters.cpp
            main.cpp
            nucleus.cpp
            photonNucleusCrossSection.cpp
            pythiadecayer.cpp
            starlight.cpp
            starlightStandalone.cpp
      Functions
            getClassMethod
            printErr
            printWarn
            printInfo
            svnVersion
            printSvnVersion
```

compileDir

printCompilerInfo

operator <<
progressIndicator
trueFalse
yesNo
onOff
enDisabled</pre>

spectrum.h

Included in files

spectrumprotonnucleus.h
starlightdpmjet.h
spectrum.cpp
starlightdpmjet.cpp

Functions

spectrum // Spectrum must be constructed with beambeam system, default constructor disallowed generateKsingle // Generate a table of photon energy probabilities. Use NK+1 logarithmic steps between Et min and Eg max generateKdouble // Generate a 2-D table of photon energy probabilities. Use NK+1 x NK+1 logarithmic steps between Et min and Eg max drawKsingle // Get the energy of a single gamma @return energy of the gamma drawKdouble // Get the energy of a single gamma @param egamma1 variable passed by reference to get the energy of the frst gamma @param egamma2 variable passed by reference to get the energy of the second gamma @return energy of the gamma setBeamBeamSystem // Set the beam beam system setMinGammaEnergy //Set the minimum gamma energy setMaxGammaEnergy / Set the maximum gamma energy setBmin //Set minimum impact parameter setBMax //Set maximum impact parameter generateBreakupProbabilities //Generate the hadron breakup probability table qetSigma ---1.05? getTransformedNofe getFnSingle getFnDouble

sprectrumprotonnucleus.h

Included in files

spectrumprotonnucleus.cpp
starlightdpmjet.cpp
starlightpythia.cpp

Functions

spectrumProtonNucleus
getNucleonNucleonSigma --- 7.35?
generateBreakupProbabilities
getSigma

starlight.h

Included in files

main.cpp
starlight.cpp

```
starlight
            ~starlight
            init
            produceEvent
            configFileName
            nmbAttempts
            nmbAccepted
            luminosityTableIsValid
            createEventChannel
starlightconstants.h
      Included in files
            eventchannel.h
            gammaavm.h
            gammagammasingle.h
            gammagammaleptonpair.h
            inputParameters.h
            nBodyPhaseSpaceGen.h
            photonNucleusCrossSection.h
            upcevent.h
            beam.cpp
            beambeamsystem.cpp
            gammaaluminosity.cpp
            gammagammaleptonpair.cpp
            gammagammasingle.cpp
            incoherentPhotonNucleusLuminosity.cpp
            incoherentVMCrossSection.cpp
            inputParameters.cpp
            narrowResonanceCrossSection.cpp
            nucleus.cpp
            photonNucleusCrossSection.cpp
            readinluminosity.cpp
            twophotonluminosity.cpp
            wideResonanceCrossSection.cpp
      Functions
            N/A
starlightdpmjet.h
      Included in files
            starlight.cpp
            starlightdpmjet.cpp
      Functions
            starlightDpmJet
            init.
            produceEvent
            produceSingleEvent
            produceDoubleEvent
            setSingleMode
            setDoubleMode
            setMinGammaEnergy
            setMaxGammaEnergy
            setProtonMode
starlightlimits.h
```

starlightStandalone.cpp

Functions

```
Included in files
```

gammagammaleptonpair.h
readinluminosity.h
twophotonluminosity.h

Functions

N/A

starlightparticle.h

Included in files

pyhthiadecayer.h
upcevent.h
starlightparticle.cpp

Functions

starlightParticle ~starlightParticle setPdqCode getPdgCode setCharge getCharge setFirstParent getFirstParent setLastParent getLastParent setFirstDaughter getFirstDaughter setLastDaughter getLastDaughter getStatus setStatus setVertex getVertex

starlightparticlecodes.h

Included in files

eventfilewriter.cpp
starlightparticlescodes.cpp

Functions

jetsetToGeant//Converts a jetset code into a GEANT
codes

starlightpythia.h

Included in files

starlight.cpp
starlightpythia.cpp

Functions

starlightPythia
~starlightPythia
init
produceSingleEvent
produceDoubleEvent
produceEvent
setSingleMode
setDoubleMode
setMinGammaEnergy
setMaxGammaEnergy
setFullEventRecord

```
starlightStandalone.h
      Included in files
            main.cpp
            starlightStandalone.cpp
      Functions
            starlightStandalone
            ~starlightStandalone
            init
            run
            configFileName
            eventDataFileName
            setConfigFileName
            setEventDataFileName
            boostEvent
twophotonluminosity.h
      Included in files
            starlight.cpp
            twophotonluminosity.cpp
      Functions
            twoPhotonLuminosity
            ~twoPhotonLuminosity
            twoPhotonDifferentialLuminosity
            D2LDMDY
            D2LDMDY Threaded
            integral
            radmul
            integrand
            Nphoton
upcevent.h
      Included in files
            eventchannel.h
            filewriter.h
            gammaavm.h
            pythiadecayer.h
            starlight.h
            starlightpythia.h
            starlight.cpp
            upcevent.cpp
      Functions
            upcEvent
            ~upcEvent
            addParticle
            addVertex
            addGamma
            getParticles
            getVertices
```

vector3.h

Included in files

operator=
operator+
boost

getGammaEnergies

$\frac{\texttt{lorentzvector.h}}{\texttt{vector3.cpp}}$

Functions

vector3
~vector3
GetVector
SetVector
operator +=
operator =
operator -=
X
Y
Z
Mag2
Mag
operator <<</pre>

wideResonanceCrossSection.h

Included in files

gammaavm.cpp

wideResonanceCrossSection.cpp

Functions

wideResonanceCrossSection
~wideResonanceCrossSection
crossSectionCalculation