IBM[®] Netezza[®] Analytics Release 11.x

Spatial Package Developer's Guide

Revised: Oct. 05, 2017





Note: Before using this information and the product that it supports, read the information in Notices and Trademarks on page 23.

Contents

| | Pretace | |
|---|--|----|
| | Audience for This Guide | |
| | Purpose of This Guide | |
| | Symbols and Conventions | |
| | If You Need Help | |
| | Comments on the Documentation | ٠١ |
| L | Netezza Spatial Package Overview | |
| | About the Netezza Spatial Package | |
| | Installation and Administration | |
| | Changing from nzspatial to nzspatial_esri | 8 |
| 2 | Getting Started with Geometric Analysis | |
| | Spatial Concepts | |
| | Geometry Types | 10 |
| | Geometric Properties | 11 |
| | Simple and Non-Simple Geometries | |
| | Spatial Package Geometry Types | 13 |
| | Netezza Spatial Package Functions | 15 |
| | Getting Started with Geometric Analysis | 18 |
| | About the Netezza Spatial Data Representation | 19 |
| | Understanding Geometric Data as VARCHARs | 20 |
| | Loading Geometric Data into the Netezza Database | |
| | Using Spatial in non-INZA User Databases | 21 |
| | APPENDIX A | |
| | | |
| | Notices and Trademarks | |
| | Notices | 23 |
| | Trademarks | 25 |
| | Regulatory and Compliance | 26 |

List of Tables

| Table 1: OpenGIS standard geometry type values | 13 |
|--|----|
| Table 2: Spatial functions and operation types | |
| Table 3: Spatial functions and geometry types | |
| Table 3. Spatial falletions and geometry types | / |

List of Figures

| Figure 1: Geometry types and relationships | 10 |
|--|----|
| Figure 2: Simple and Non-Simple Geometries | 11 |
| Figure 3: Sample geometry definition for a simple linestring | 12 |
| Figure 4: Sample geometry definition for a non-simple linestring | 12 |

Preface

Audience for This Guide

The IBM Netezza Spatial Package Developer's Guide is for users who wish to use the spatial features of the IBM Netezza Analytics package on their IBM Netezza systems. For best results, you should be very familiar with spatial analysis and the OpenGIS standards. You should also be familiar with the basic operation and concepts of the Netezza system.

Purpose of This Guide

The Netezza Spatial Package provides spatial analysis functions that can be used in queries that run on the Netezza appliance. This guide provides a reference to the spatial functions and the aggregate (ST_GrandMBR) included with the Netezza Spatial Package. While the guide describes the Netezza-specific aspects of the Spatial Package, it does not provide a broad general discussion of spatial or geospatial analysis and concepts.

Symbols and Conventions

Note on Terminology: The terms *User-Defined Analytic Process (UDAP)* and *Analytic Executable (AE)* are synonymous.

The following conventions apply:

- ▶ Italics for emphasis on terms and user-defined values, such as user input.
- ▶ Upper case for SQL commands, for example, INSERT or DELETE.
- ▶ Bold for command line input, for example, nzsystem stop.
- ▶ Bold to denote parameter names, argument names, or other named references.
- ► Angle brackets (< >) to indicate a placeholder (variable) that should be replaced with actual text, for example, inza-<release number>.zip.
- A single backslash ("\") at the end of a line of code to denote a line continuation. Omit the backslash when using the code at the command line, in a SQL command, or in a file.
- ▶ When referencing a sequence of menu and submenu selections, the ">" character denotes the different menu options, for example, **Menu Name > Submenu Name > Selection**.

If You Need Help

If you are having trouble using the IBM Netezza appliance, IBM Netezza Analytics or any of its components:

- **1.** Retry the action, carefully following the instructions in the documentation.
- 2. Go to the IBM Support Portal at: http://www.ibm.com/support. Log in using your IBM ID and password. You can search the Support Portal for solutions. To submit a support request, click the 'Service Requests & PMRs' tab.
- If you have an active service contract maintenance agreement with IBM, you may contact customer support teams via telephone. For individual countries, please visit the Technical Support section of the IBM Directory of worldwide contacts (http://www14.software.ibm.com/webapp/set2/sas/f/handbook/contacts.html#phone)

Comments on the Documentation

We welcome any questions, comments, or suggestions that you have for the IBM Netezza documentation. Please send us an e-mail message at netezza-doc@wwpdl.vnet.ibm.com and include the following information:

- ▶ The name and version of the manual that you are using
- Any comments that you have about the manual
- Your name, address, and phone number

We appreciate your comments.

CHAPTER 1

Netezza Spatial Package Overview

About the Netezza Spatial Package

The Netezza Spatial Package package provides a set of spatial and geospatial analytic functions for Netezza data warehouse appliances. These functions provide the ability to analyze distance, space, shape, and intersection questions for the data on the Netezza system.

The Netezza Spatial Package functions follow the Open Geospatial Consortium, Inc. (OGC) OpenGIS standards as documented in the *OpenGIS Implementation Specification for Geographic Information - Simple Feature Access - Part 1: Common Architecture 1.2.0* and the ISO19107 & ISO13249-3:2006 – SQL Multimedia and Application Packages – Part 3 – Spatial 3rd Ed.

While the OpenGIS framework is geared toward user-defined methods on custom datatypes, Netezza uses a more standard ANSI SQL function style of syntax, where user-defined functions (UDFs) are used instead with the first parameter representing the object for which the method is to be applied.

For example, to find the area of an ST_Polygon object in column A of table **counties** under OpenGIS, a SQL query such as the following may be used:

```
SELECT A.ST Area() FROM counties;
```

Using the Netezza Spatial Package, the equivalent SQL is written as:

SELECT ST Area(A) FROM counties;

Installation and Administration

For complete information on installation and administration of the Netezza Spatial Package, refer to the *IBM Netezza Analytics Administrator's Guide*.

Important: Depending on the selections that you make during the installation, several new databases are created, one of which is the INZA database. You must not use this INZA database for user data.

Changing from nzspatial to nzspatial_esri

For details on how to change your data from nzspatial- to nzspatial_esri-compatible, see the IBM Netezza Spatial ESRI Package User's Guide.

CHAPTER 2

Getting Started with Geometric Analysis

Spatial Concepts

The Netezza Spatial package contains functions and capabilities that allow you to process queries about geometric features or geographical data using the data contained ion the NPS. An example of geographical data could include such items as:

- ▶ The location of a store, restaurant, a wireless service tower, national park, or other landmark
- A plot or area of land, such as an office park, a county or precinct, or a wireless coverage zone
- A running feature such as a street, river, railway line, tunnel, or power line

The combination of spatial information with relational database information, allows powerful interpretations as well as images of the data correlations. For example:

- ▶ Identify the number of wireless calls that occur in a particular area to improve the planning process for the addition of new towers for better wireless service
- ► Map the location of stores and calculate the distance between customer addresses and the store location to plan advertising coverage
- Identify an aquifer area and plan a buffer around it to calculate the impact and cost of a fence or enclosure protecting the water zone from unauthorized access

Spatial data typically originates from three sources: it can be derived from business data, calculated using spatial functions, or imported from external sources or databases.

Geometry Types

There are two main categories of geometry types – instantiated and abstract – categorized based on whether a visual rendering can be created. Instantiated types can be rendered visually while abstract, or non-instantiated, types cannot be rendered visually. See Figure 1 for geometry type examples.




Figure 1: Geometry types and relationships

In Figure 1, the boxes that are shaded blue, specifically Geometry, Curve, Surface, MultiCurve, and MultiSurface, are non-instantiable or abstract types that cannot be rendered visually. They define a subtype or grouping of object types. As instantiable types, Point, LineString, Polygon, Geometry Collection, MultiString, MultiPolygon, and MultiPoint can be rendered visually in mapping or image applications. These geometric types are often used to represent various geographic features:

- ▶ Points can represent a specific location, such as a city, an intersection of two streets, a radio tower, or a building.
- LineStrings can represent features such as a street, trail, route, river, or power line.
- ▶ Polygons represent areas or parcels, such as a university campus, a homeowner's property, a park, a floodplain, a service coverage area, or a floor plan.

For a complete description of the geometry types, refer to the OpenGIS standard specification.

Geometric Properties

Geometric types have coordinate and dimension properties. Coordinates define location as well as shape and size, while dimension specifies whether an object has length, width, and/or height. For example, points have four possible ordinate values:

- ► X—left/right
- ► Y—up/down
- ► Z—altitude/depth
- ► M—a measure associated with the object, such as a distance along a linestring from the start point, a flow rate for a pipe, or an average speed for a particular area of roadway

There are four possible dimensions for each geometry object:

- ► -1—an empty object
- ▶ 0—a point type
- ▶ 1—a line string
- ▶ 2—a polygon that has an area larger than 0

Note: The Netezza Spatial Package supports vector objects and spatial operators, as defined in the OpenGIS standard. The package does not support 3D geocodings or raster data/functions.

Simple and Non-Simple Geometries

As defined in the OpenGIS standard, a simple geometry is one that does not have any "anomalous" geometric points, such as self intersection or self tangency. Each geometric type defines its simple and non-simple aspects. Some examples of non-simple geometries include: a polygon with vertices inside the area of the polygon itself; a linestring that intersects itself; a multipoint that has two points with equal coordinates; a polygon with an interior ring that touches the polygon's boundary. See Figure 2: Simple and Non-Simple Geometries.

Figure 2: Simple and Non-Simple Geometries




Figure 2 shows some examples of simple and non-simple geometries. The two geometries on the left are simple geometries that do not intersect within themselves. On the right side, both the linestring and the polygon have self-intersecting lines, and thus are non-simple. By default, the Netezza Spatial Package supports only simple geometries; thus, a geometric object definition that is non-simple cannot be inserted or loaded. The only exception is when a geometry is created and the "skipSimpleTest" parameter is set to true (ST_WKBToSQL()) and ST_WKTToSQL()).

Figure 3 shows a sample SQL query to add the linestring object illustrated in the Cartesian grid to a table named *geomtable*. The query successfully adds the linestring object.

Figure 3: Sample geometry definition for a simple linestring

```
CREATE TABLE geomtable(geoms ST_GEOMETRY(500));
CREATE TABLE

INSERT INTO geomtable VALUES
(inza, ST_WKTToSQL('LineString(1 1, 2 3, 3 4, 4 2, 5 3)'));
INSERT 0 1
```




Figure 4 shows a sample query that defines the non-simple linestring object illustrated in the grid.

Figure 4: Sample geometry definition for a non-simple linestring

```
INSERT INTO geomtable VALUES
(inza..ST_WKTToSQL('LineString(0 0, 2 3, 1 3,
1 1, 4 3, 2 5)', 4326));
ERROR: Geometry is not simple

INSERT INTO geomtable VALUES (inza..ST_WKTToSQL('LineString(0 0, 2 3, 1 3,1 1, 4 3, 2 5)', 4326, true));
INSERT 0 1
```

Note that the SQL query returns an error.

Other databases may allow loading of non-simple geometric data, but that can lead to unexpected, incorrect results when analyzing the non-simple geometries for values such as distance, area, contains, or intersections. To load geometric data from other sources to the Netezza database, best practices are available for dealing with potential non-simple geometries in the data. For more information, see the Loading Geometric Data into the Netezza Database section.

Spatial Package Geometry Types

In the Netezza implementation, geometry types are defined by a new fundamental type called ST_Geometry. ST_Geometry is a VARCHAR data field that represents a spatial object such as a point, linestring, or polygon.

The subtypes of ST_Geometry are as follows:

- ► ST Point
- ► ST Curve (non-instantiable)
- ST Linestring
- ► ST Surface (non-instantiable)
- ST_Polygon
- ST_MultiCurve (non-instantiable)
- ST_Multipoint
- ST_MultiLineString
- ST_MultiSurface (non-instantiable)
- ST_MultiPolygon
- ▶ ST GeomCollection

The spatial package does *not* support the following two subtypes of the OpenGIS standard:

- ST_Polyhedral
- ST_Text

In the OpenGIS standard, each geometry type has a defined integer value. Table 1 shows the integer code values and the number of coordinates for each type. These codes are used in some of the spatial functions described in the *Netezza Spatial Package Reference Guide*.

Table 1: OpenGIS standard geometry type values

| Code | Geometry Types | Coordinates |
|------|----------------|-------------|
| 0 | GEOMETRY | ХҮ |
| 1 | POINT | ХҮ |
| 2 | LINESTRING | ΧY |

| Code | Geometry Types | Coordinates |
|------|--------------------|-------------|
| 3 | POLYGON | ΧY |
| 4 | MULTIPOINT | ΧY |
| 5 | MULTILINESTRING | ΧY |
| 6 | MULTIPOLYGON | ΧY |
| 7 | GEOMCOLLECTION | ΧY |
| 13 | CURVE | ΧY |
| 14 | SURFACE | ΧY |
| 15 | POLYHEDRALSURFACE | ΧY |
| 1000 | GEOMETRYZ | XYZ |
| 1001 | POINTZ | XYZ |
| 1002 | LINESTRINGZ | XYZ |
| 1003 | POLYGONZ | XYZ |
| 1004 | MULTIPOINTZ | XYZ |
| 1005 | MULTILINESTRINGZ | XYZ |
| 1006 | MULTIPOLYGONZ | XYZ |
| 1007 | GEOMCOLLECTIONZ | XYZ |
| 1013 | CURVEZ | XYZ |
| 1014 | SURFACEZ | XYZ |
| 1015 | POLYHEDRALSURFACEZ | XYZ |
| 2000 | GEOMETRYM | XYM |
| 2001 | POINTM | XYM |
| 2002 | LINESTRINGM | XYM |
| 2003 | POLYGONM | XYM |
| 2004 | MULTIPOINTM | XYM |

| Code | Geometry Types | Coordinates |
|------|---------------------|-------------|
| 2005 | MULTILINESTRINGM | XYM |
| 2005 | MULTILINESTRINGM | XYM |
| 2006 | MULTIPOLYGONM | хүм |
| 2007 | GEOMCOLLECTIONM | хүм |
| 2013 | CURVEM | XYM |
| 2014 | SURFACEM | XYM |
| 2015 | POLYHEDRALSURFACEM | XYM |
| 3000 | GEOMETRYZM | XYZM |
| 3001 | POINTZM | XYZM |
| 3002 | LINESTRINGZM | XYZM |
| 3003 | POLYGONZM | XYZM |
| 3004 | MULTIPOINTZM | XYZM |
| 3005 | MULTILINESTRINGZM | XYZM |
| 3006 | MULTIPOLYGONZM | XYZM |
| 3007 | GEOMCOLLECTIONZM | XYZM |
| 3013 | CURVEZM | XYZM |
| 3014 | SURFACEZM | XYZM |
| 3015 | POLYHEDRALSURFACEZM | XYZM |

Netezza Spatial Package Functions

This section provides an overview of the spatial package functions. The spatial functions typically perform operations that fall into these categories:

- ▶ Geometric information functions, which return information about a geometric object
- ► Conversion (or constructor) functions, which convert an object into another representation
- Comparison functions, which evaluate whether two or more objects touch, overlap, or otherwise intersect or connect

- ► Geometric object manipulation functions, which can set coordinate values or derive new objects such as centroids, buffers, bounding regions, and so on
- ▶ Distance and area functions, which evaluate objects for measurements such as area, distance, and length

Table 2 categorizes the spatial functions by the type of operations they perform. The functions and their arguments are described in the *Netezza Spatial Package Reference Guide*.

Table 2: Spatial functions and operation types

| Operation Type | | Functions | | |
|-----------------------|-------------------|-----------------------|------------------|--------------------|
| Geometric Information | ST_CoordDim | ST_Is3D | ST_MaxX | ST_NumInteriorRing |
| | ST_Dimension | ST_IsClosed | ST_MaxY | ST_NumPoints |
| | ST_EndPoint | ST_IsEmpty | ST_MaxZ | ST_SRID |
| | ST_GeomFromText | ST_IsMeasured | ST_MinM | ST_StartPoint |
| | ST_GeomFromWKB | ST_IsRing | ST_MinX | ST_X |
| | ST_GeometryN | ST_IsSimple | ST_MinY | ST_Y |
| | ST_GeometryType | ST_M | ST_MinZ | ST_Z |
| | ST_GeometryTypeId | ST_MaxM | ST_NumGeometries | |
| Conversion | ST_AsBinary | ST_AsKML ¹ | ST_WKBToSQL | ST_WKTToSQL |
| Functions | ST_AsText | | | |
| Comparison | ST_Contains | ST_DWithin | ST_Intersects | ST_Touches |
| Functions | ST_Crosses | ST_MBRIntersects | ST_Overlaps | ST_Within |
| | ST_Disjoint | ST_Equals | ST_Relate | |
| Object Manipulation | ST_Buffer | ST_Envelope | ST_MBR | ST_X |
| Functions | ST_Boundary | ST_ExteriorRing | ST_Point | ST_Y |
| | ST_Centroid | ST_InteriorRingN | ST_PointN | ST_Z |
| | ST_ConvexHull | ST_Intersection | ST_SRID | |
| | ST_Difference | ST_M | ST_SymDifference | |

¹ For more information on the Keyhole Markup Language (KML) used in the ST_AsKML function, see http://code.google.com/apis/kml/documentation/kmlreference.html.

| Operation Type | | Functions | | | |
|------------------------------------|---------|-------------|-----------|--------------|--|
| Measurement and Distance Functions | ST_Area | ST_Distance | ST_Length | ST_Perimeter | |

Table 3 lists the functions and aggregates that can be used on each geometry type.

Restriction: nzspatial supports only the following SRIDs. Furthermore, not all nzspatial functions are supported for all of these SRIDs.

- ▶ 4326 WGS84
- ▶ 1111 Spherical
- ▶ 1234 Cartesian

Table 3: Spatial functions and geometry types

| Geometry Type | Functions and Aggregates Supported | | |
|---------------|--|--|--|
| ST_Geometry | ST_AsBinary, ST_AsText, ST_Boundary, ST_Buffer, ST_Contains, ST_ConvexHull, ST_CoordDim, ST_Crosses, ST_Difference, ST_Dimension, ST_Disjoint, ST_Distance, ST_DWithin, ST_Envelope, ST_Equals, ST_GeometryType, ST_GeometryTypeld, ST_Intersection, ST_Intersects, ST_Is3D, ST_IsEmpty, ST_IsMeasured, ST_IsSimple, ST_Length, ST_MBR, ST_MaxM, ST_MaxX, ST_MaxY, ST_MaxZ, ST_MinM, ST_MinX, ST_MinY, ST_MinZ, ST_Overlaps, ST_Perimeter, ST_Relate, ST_SRID, ST_SymDifference, ST_Touches, ST_Union, ST_Within, ST_WKBToSQL, ST_WKTToSQL | | |
| ST_Point | ST_M ST_Point ST_X ST_Y ST_Z | | |
| ST_LineString | ST_EndPoint ST_IsClosed ST_IsRing ST_NumPoints ST_PointN ST_StartPoint | | |
| ST_Surface | ST_Area ST_Centroid | | |
| ST_Polygon | ST_ExteriorRing | | |

| Geometry Type | Functions and Aggregates Supported |
|--------------------|--|
| | ST_InteriorRingN ST_NumInteriorRing |
| ST_GeomCollection | ST_GeometryN ST_NumGeometries |
| ST_MultiPoint | All the functions supported by ST_GeomCollection and ST_Geometry |
| ST_MultiLineString | ST_IsClosed ST_IsRing |
| ST_MultiPolygon | ST_Area ST_Centroid |

Getting Started with Geometric Analysis

To get started with the Netezza Spatial Package, spatial data is first loaded into a Netezza database. A table is created with a geometry column as a VARCHAR column.

```
CREATE TABLE PointData (PointID integer, the geom varchar(200));
```

This command creates a table suitable for loading point data. To insert a point to the table, commands similar to the following examples can be used:

```
INSERT INTO PointData VALUES (1, inza..ST_Point(3423, 4356));
INSERT INTO PointData VALUES (1, inza..ST_WKTToSQL('Point (3423 4356)'));
```

Note that only one of these INSERT commands is needed to insert the point into the PointData table. Executing both INSERT commands results in two points with the same PointID. The column the geom can be used anywhere that the datatype ST_Geometry (or the subclass ST_Point) is shown in the Spatial API functions, documented the *Netezza Spatial Package Reference Guide*.

As an example, the following command displays the geometry type of the data in the the_geom column:

To create a table that contains polygons, use the following command:

```
CREATE TABLE Polys (PolyID integer, the geom varchar(200));
```

To add polygons to the table, commands similar to the following can be used. These commands define the points which are the vertices of two square polygons:

```
INSERT INTO Polys VALUES (1, inza..ST_WKTToSQL('Polygon ((1000 1000, 1000 5000, 4000 5000, 4000 1000, 1000 1000))'));
INSERT INTO Polys VALUES (2, inza..ST_WKTToSQL('Polygon ((100 100, 100 500, 400 500, 400 100, 100 100))'));
```

With the polygons defined in the Polys table, basic point-in-polygon queries can be performed by joining through the ST Intersects() function, as follows:

About the Netezza Spatial Data Representation

When you create a geometric object or load existing geometry data into the Netezza, the data is saved in an internal format referred to as the Netezza Spatial Data representation. For example, the following commands create a small table named geoms and add a polygon and linestring object to the table:

```
CREATE TABLE geoms (PolyID INTEGER, the geom VARCHAR(64000));
CREATE TABLE

INSERT INTO geoms VALUES (1, inza..ST_WKTtoSQL('Polygon ((1 1, 1 4, 3.5 2.5, 6 4, 6 1, 1 1))'));
INSERT O 1

INSERT INTO geoms VALUES (2, inza..ST_WKTtoSQL('Linestring (1 1, 1 4, 6 4, 6 1)'));
INSERT O 1
```

If a standard SELECT * FROM query is used to view the spatial data, the geometric data does not appear in detail. To display the table contents in more readable form, use one of the Spatial functions such as ST_AsText() to render the spatial data in text format:

```
SELECT inza..ST_AsText(the_geom) FROM geoms;

ST_ASTEXT

POLYGON ((1 1, 1 4, 3.5 2.5, 6 4, 6 1, 1 1))

LINESTRING (1 1, 1 4, 6 4, 6 1)

(2 rows)
```

As another example, the following query outputs the spatial data in Keyhole Markup Language (KML):

```
SELECT inza..ST_AsKML(the_geom) FROM geoms;

ST_ASKML

<LineString><coordinates>1,1 1,4 6,4 6,1</coordinates></LineString>
<Polygon><outerBoundaryIs><LinearRing><coordinates>1,1 1,4 3.5,2.5 6,4 6,1 1,1</coordinates></LinearRing></outerBoundaryIs></Polygon>
(2 rows)
```

Understanding Geometric Data as VARCHARs

With the Netezza Spatial Package, geometric data is saved in a VARCHAR datatype column. In the Netezza database, a VARCHAR column has a maximum size of 64,000 bytes, and a database row has a maximum size of 65,535 bytes. While a geometry object can often be defined completely within one 64,000-byte VARCHAR field, some geometry object definitions could exceed the space available in one VARCHAR column, for example polygons with thousands or millions of vertices, or linestrings/multipoints with thousands of points.

Typically, a polygon that has a single ring—the outer ring--and uses XY ordinates for vertices can have up to 3990 vertices before reaching the VARCHAR column limit. The maximum number of vertices in one VARCHAR column decreases if a polygon has interior rings (holes) or if its vertices use XYZ, XYM, or XYZM ordinates.

For spatial objects larger than can be saved in one VARCHAR column, there are methods that can be uses to save those objects in the Netezza database, as described in the Loading Geometric Data into the Netezza Database section.

Although the spatial data is in a VARCHAR column, never attempt to manipulate the data in the VARCHAR fields using Netezza string functions or other operators other than Netezza Spatial Package functions. Since the spatial data is saved in an internal format as described in the About the Netezza Spatial Data Representation section, changes to the VARCHAR field corrupt the spatial data in the affected columns.

Loading Geometric Data into the Netezza Database

For geospatial data loaded from other databases or third-party spatial sources into the Netezza database, it is possible that the objects are too large to store in one VARCHAR column. It is also possible that the data could contain non-simple geometry types, or use characters or other values not supported by the Netezza loading processes.

As a best practice, Netezza recommends that you use the Feature Manipulation Engine (FME) Workbench application, which is a product of Safe Software Inc. The FME Workbench application helps prepare data sets and load them into the Netezza database.

NOTE: For more information about the use of the Safe Software Inc. FME Workbench product, refer to the documentation from the vendor and the online help that is available from that application.

The FME Workbench application helps ensure that the data loaded into the Netezza database is properly prepared. For example, the application can do the following:

- ▶ Detect polygons with greater than 3990 vertices and take a user-specified action such as "chop" the geometry into smaller geometries, skip/ignore the geometry, fail (or stop) the load, or generalize (or smooth) the geometry to make it small enough to fit within the VARCHAR field.
- ▶ Detect non-simple geometries, which are not supported by the Netezza Spatial package, and either filter them out or "buffer" them to transform them into simple geometries.
- ► Load binary spatial data while detecting and escaping known binary values which are not supported by the Netezza loading processes.

Using Spatial in non-INZA User Databases

When Netezza Analytics is installed, all spatial functions and stored procedures are registered in the INZA database by default. However, you can register nzspatial functions and stored procedures also into non-INZA user databases. Thus, you have multiple versions of nzspatial available in the system, for example, to test a newer version of nzspatial.

To register nzspatial functions and stored procedures into user databases, do the following steps:

 Create the new user database by entering the following command, where <newdb> is the name of the user database that you want to create, and <version number> is the number of your Netezza Analytics version.

```
% nzsql -c "create database <newdb>;"
CREATE DATABASE
```

2. Register nzspatial by entering the following command:

```
% nzcm -d <newdb> -r nzspatial
```

The following messages are displayed:

```
Registering: nzspatial Netezza Spatial was successfully registered on <newdb>. Registration of nzspatial completed on '<newdb>'. Log file: /nz/var/log/nzcm.20131126.13 50 34.3856.log
```

3. Run the create_inza_db.sh script by entering the following command:

```
% /nz/export/ae/utilities/bin/create inza db.sh <newdb>
```

The output from the create inza db.sh script is as follows:

```
CREATE GROUP
  CREATE GROUP
  CREATE GROUP
  GRANT
  GRANT
  GRANT
  GRANT
  GRANT
  GRANT
  GRANT
  GRANT
  GRANT
  REVOKE
  ALTER GROUP
  ALTER GROUP
  nzspatialregistered in <newdb>
Setting up nzspatial
```

```
Using newdb database version version number>
ST_INITIALIZE

The metadata objects are successfully initialized.
(1 row)

GRANT
GRANT
GRANT
GRANT
```

Within the user database, spatial functions and stored procedures are registered as follows:

- ▶ In the INZA schema, when the full schema support NPS feature is enabled
- ▶ In the default schema, when the full schema support NPS feature disabled

APPENDIX A

Notices and Trademarks

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 1623-14, Shimotsuruma, Yamato-shi Kanagawa 242-8502 Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR

IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact: *IBM Corporation*

26 Forest Street

Marlborough, MA 01752 U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only. This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

- © (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs.
- © Copyright IBM Corp. (enter the year or years). All rights reserved.

Trademarks

IBM, the IBM logo, ibm.com and Netezza are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both. If these and other IBM trademarked terms are marked on their first occurrence in this information with a trademark symbol (® or ™), these symbols indicate U.S. registered or common law trademarks owned by IBM at the time this information was published. Such trademarks may also be registered or common law trademarks in other countries. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at ibm.com/legal/copytrade.shtml.

The following terms are trademarks or registered trademarks of other companies:

Adobe is a registered trademark of Adobe Systems Incorporated in the United States, and/or other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

NEC is a registered trademark of NEC Corporation.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Red Hat is a trademark or registered trademark of Red Hat, Inc. in the United States and/or other countries.

D-CC, D-C++, Diab+, FastJ, pSOS+, SingleStep, Tornado, VxWorks, Wind River, and the Wind River logo are trademarks, registered trademarks, or service marks of Wind River Systems, Inc. Tornado patent pending.

APC and the APC logo are trademarks or registered trademarks of American Power Conversion

Corporation.

Other company, product or service names may be trademarks or service marks of others.

Regulatory and Compliance

Regulatory Notices

Install the NPS system in a restricted-access location. Ensure that only those trained to operate or service the equipment have physical access to it. Install each AC power outlet near the NPS rack that plugs into it, and keep it freely accessible. Provide approved circuit breakers on all power sources.

Product may be powered by redundant power sources. Disconnect ALL power sources before servicing. High leakage current. Earth connection essential before connecting supply. Courant de fuite élevé. Raccordement à la terre indispensable avant le raccordement au réseau.

Homologation Statement

This product may not be certified in your country for connection by any means whatsoever to interfaces of public telecommunications networks. Further certification may be required by law prior to making any such connection. Contact an IBM representative or reseller for any questions.

FCC - Industry Canada Statement

This equipment has been tested and found to comply with the limits for a Class A digital device, pursuant to part 15 of the FCC rules. These limits are designed to provide reasonable protection against harmful interference when the equipment is operated in a commercial environment. This equipment generates, uses, and can radiate radio-frequency energy and, if not installed and used in accordance with the instruction manual, may cause harmful interference to radio communications. Operation of this equipment in a residential area is likely to cause harmful interference, in which case users will be required to correct the interference at their own expense.

This Class A digital apparatus meets all requirements of the Canadian Interference-Causing Equipment Regulations.

Cet appareil numérique de la classe A respecte toutes les exigences du Règlement sur le matériel brouilleur du Canada.

CE Statement (Europe)

This product complies with the European Low Voltage Directive 73/23/EEC and EMC Directive 89/336/EEC as amended by European Directive 93/68/EEC.

Warning: This is a class A product. In a domestic environment this product may cause radio interference in which case the user may be required to take adequate measures.

VCCI Statement

この装置は、情報処理装置等電波障害自主規制協議会 (VCCI) の基準 に基づくクラス A 情報技術装置です。この装置を家庭環境で使用すると電波 妨害を引き起越すことがあります。この場合には使用者が適切な対策を講ず るう要求されることがあります。