

# Implementing Real-Time Analysis with Hadoop in Azure HDInsight

Lab 2 - Getting Started with Storm (C#)

## Overview

In this lab, you will provision HDInsight Storm and HBase clusters, and use Microsoft C# to create a simple Storm topology that captures a stream of data and stores the captured data in HBase. You will then create a more complex Storm topology that aggregates data as it is captured.

# What You'll Need

To complete the labs, you will need the following:

- A web browser
- A Microsoft account
- A Microsoft Azure subscription
- A Microsoft Windows computer containing:
  - Microsoft Visual Studio
  - The lab files for this course

**Note**: You can only complete this lab on a Windows client computer with Visual Studio 2015 and the latest version of the Microsoft .NET SDK for Azure installed. To set up the required environment for the lab, follow the instructions in the **Setup** document for this course, including the procedure to install Visual Studio and the .NET SDK for Azure.

# **Provisioning HDInsight Clusters**

The first task you must perform is to provision an HDInsight Storm cluster to capture and process as real-time stream of data, and an HBase cluster in which the captured data will be stored.

**Note**: The Microsoft Azure portal is continually improved in response to customer feedback. The steps in this exercise reflect the user interface of the Microsoft Azure portal at the time of writing, but may not match the latest design of the portal exactly.

#### Create a Storage Account

You will use an Azure storage account to provide the distributed file system for your HDInsight cluster.

- 1. In a web browser, navigate to <a href="http://portal.azure.com">http://portal.azure.com</a>, and if prompted, sign in using the Microsoft account that is associated with your Azure subscription.
- 2. In the Microsoft Azure portal, in the Hub Menu (on the left edge of the page), click **New**. Then in the **Storage** menu, click **Storage** account.
- 3. In the Storage account blade, select the Resource Manager deployment model, and click Create
- 4. In the **Create storage account** blade, enter the following settings, and then click **Create**:
  - **Name**: Enter a unique name for your storage account (and make a note of it!)
  - **Deployment model:** Resource manager
  - Account kind: General purpose
  - **Performance:** Standard
  - Replication: Select Locally redundant storage (LRS)
  - Storage service encryption: Disabled
  - **Subscription**: Your subscription
  - **Resource group**: Select **Create New** and enter a name for a new resource group (and make a note of it!)
  - **Location:** *Select any available region*
  - Pin to dashboard: Unselected
- 5. At the top of the page, click **Notifications** and verify that deployment has started. Wait until your storage account has been created before proceeding to the next procedure. This should take a few minutes.

# Provision an HDInsight Storm Cluster

To use Storm, you must provision an HDInsight Storm cluster.

- 1. In the Microsoft Azure portal, in the Hub Menu, click **New**. Then in the **Data + Analytics** menu, click **HDInsight**.
- 2. In the **New HDInsight Cluster** blade, enter the following settings, and then click **Create**:
  - **Cluster Name**: Enter a unique name (and make a note of it!)
  - **Subscription**: Select your Azure subscription
  - Cluster type:
    - Cluster Type: Storm
    - Cluster Operating System: Windows
    - **Version**: Choose the latest version of Storm available.
    - Cluster Tier: Standard
  - **Credentials**: Configure the following settings:
    - **Cluster Login Username**: Enter a user name of your choice (and make a note of it!)
    - Cluster Login Password: Enter and confirm a strong password (and make a note of it!)
    - **Remote Desktop Username:** Enter another user name of your choice (and make a note of it!)
    - **Remote Desktop Password:** Use the same password as the cluster login password
  - **Resource Group**: Select the resource group you created for your storage account
  - **Storage**: Select the existing storage account you created in the first procedure, and set the default container to the cluster name you specified above
  - **Applications**: None
  - **Cluster size**: Configure the following settings:
    - Number of Supervisor nodes: 1
    - Supervisor Node Size: Leave the default size selected
    - Nimbus Node Size: Leave the default size selected
    - Zookeeper Node Sizes: Leave the default size selected
  - Advanced settings: None

3. At the top of the page, click **Notifications** and verify that deployment has started. Then, while waiting for the cluster to be deployed (which can take a long time – often 30 minutes or more), move onto the next procedure

**Note:** As soon as an HDInsight cluster is running, the credit in your Azure subscription will start to be charged. Free-trial subscriptions include a limited amount of credit limit that you can spend over a period of 30 days, which should be enough to complete the labs in this course as long as clusters are deleted when not in use. If you decide not to complete this lab, follow the instructions in the Clean Up procedure at the end of the lab to delete your cluster to avoid using your Azure credit unnecessarily.

## Provision an HDInsight HBase Cluster

In addition to the Storm cluster, you will use an HBase cluster in some later exercises in this lab.

- 1. In the Microsoft Azure portal, in the Hub Menu, click **New**. Then in the **Data + Analytics** menu, click **HDInsight**.
- 2. In the **New HDInsight Cluster** blade, enter the following settings, and then click **Create**:
  - **Cluster Name**: Enter a unique name (and make a note of it!)
  - **Subscription**: Select your Azure subscription
  - Cluster type:
    - Cluster Type: HBase
    - Cluster Operating System: Linux
    - **Version**: Choose the latest version of HBase available.
    - Cluster Tier: Standard
  - **Credentials**: Configure the following settings:
    - Cluster Login Username: Enter a user name of your choice (and make a note of it!)
    - Cluster Login Password: Enter and confirm a strong password (and make a note of it!)
    - **SSH Username:** Enter another user name of your choice (and make a note of it!)
    - SSH Password: Use the same password as the cluster login password
  - **Resource Group**: The resource group you created for the storm cluster in the previous procedure
  - **Storage**: Select the existing storage account you created in the first procedure, and set the default container to the cluster name you specified above
  - Applications: None
  - **Cluster size**: Configure the following settings:
    - Number of Region nodes: 1
    - Region Node Size: Leave the default size selected
    - **Head Node Size**: Leave the default size selected
    - Zookeeper Node Sizes: Leave the default size selected
  - Advanced settings: None
- 3. At the top of the page, click **Notifications** and verify that deployment has started. Then, wait for the clusters to be deployed (as previously indicated, this can take a long time often 30 minutes or more; so take a break you've been working hard!)

**Note**: Remember - as soon as an HDInsight cluster is running, the credit in your Azure subscription will start to be charged.

# Creating a Storm Topology

In the previous exercise, you provisioned a Storm HDInsight cluster. In this exercise, you will create a simple Storm topology based on the default template provided with the Azure SDK.

#### Create a Storm Project in Visual Studio

The Azure SDK adds a number of project templates to Visual Studio, including templates for Storm topology projects. You will use one of these templates to create a simple Storm topology.

- 1. Start Visual Studio and create a new project with the following settings:
  - **Template**: In the **Azure Data Lake** category, select **Storm Application**.
  - Name: SensorStream
  - **Location**: Browse to the **Lab02** folder in the directory where you extracted the lab files.
  - Solution name: Storm Sensor Reader
- 2. When the project opens, view the Solution Explorer pane and note that the project template includes the following code files:
  - Program.cs: Contains code to initiate the topology.
  - **Spout.cs**: Contains code to implement a spout that consumes a stream from a data source and adds it to the topology.
  - **Bolt.cs**: Contains code to implement a bolt that consumes the stream from the spout and processes the event data it contains.
- 3. Open **Spout.cs** if it is not already open, and review the code it contains. Note that this code defines a class named **Spout** that includes the following methods:
  - **Spout**: This is the initializer method for the class, and defines the component schema for the event data. An output schema named **default** is declared, consisting of a list containing a single integer value. Because this class represents a spout that does not consume events from any other spouts in the topology, the input schema is null.
  - **Get**: This method returns a spout associated with the context passed to it. It is used by Storm to create instances of the spout on cluster nodes.
  - **NextTuple**: This method emits tuples containing event data to the topology, where they can be consumed by bolts. The default code in the template emits a list containing a single integer value, which is randomly generated using a C# **Random** class.
  - Ack: This method is called to acknowledge that a tuple emitted by the spout and identified by a sequence ID, has been successfully processed. The Ack method is used to implement retry logic, and is empty in the default template.
  - **Fail**: This method is called to indicate that a failure occurred when processing a tuple. The **Fail** method is used to implement retry logic, and is empty in the default template.
- 4. Open **Bolt.cs** if it is not already open, and review the code it contains. Note that this code defines a class named **Bolt** that includes the following methods:
  - Bolt: This is the initializer method for the class, and defines the component schema for
    the event data. The input schema named default is declared, consisting of a list
    containing a single integer value. Because this class represents a bolt that does not emit
    events for processing by other downstream bolts in the topology, the output schema is
    null.
  - **Get**: This method returns a bolt associated with the context passed to it. It is used by Storm to create instances of the bolt on cluster nodes.
  - Execute: This method is called each time a tuple containing event data is received from the stream, and contains code to process it. The code in the default template retrieves the first value from the tuple, which is assumed to be an integer, and adds it to a running count. The count value is then written to the log for the topology.

5. Open Program.cs if it is not already open, and review the code it contains. Note that the class includes a public GetToplogyBuilder function that is called by Storm to initiate the topology. This method creates a topology named SensorStream plus the current date and time, adds the Spout class as a spout, and adds the Bolt class as a bolt that consumes the stream from the spout using a shuffle grouping (which means that the events are spread randomly across nodes on which the bolt is running).

## Submit the Toplogy

The default code in the Storm Application template defines a valid topology that can be submitted to a Storm cluster and started. In this procedure, you will submit the topology to see it running.

- 1. On the Build menu, click Build Solution.
- 2. View the Server Explorer pane, and connect to your Azure subscription if you are not already connected. Then expand **Azure**, expand **HDInsight**, and right-click your Storm cluster (which is indicated by a **\*** icon) and click **Properties**.
- 3. In the Properties pane, verify that the **Status** of your cluster is **Running**.
- 4. In the Solution Explorer pane, right-click the **SensorStream** project and click **Submit to Storm on HDInsight**. Then, when prompted, select your Storm cluster and click **Submit**.
- 5. After the storm topology has been submitted, in the **Storm Topology** window that is automatically opened, select the **SensorStream** topology to view its status. The topology should show the **Spout** spout transferring **default** tuples to the **Bolt** bolt, where they are executed. Click the **Refresh** icon at the top of the page to see an updated indication of the uptime.
- 6. In your web browser, in the Azure portal, browse to your Storm HDInsight cluster.
- 7. At the top of the blade for your Storm cluster, click **Dashboard**, and when prompted, enter the cluster login credentials you specified for your Storm cluster.
- 8. In the Storm Dashboard, view the **Storm UI** tab, and note that the **Topology summary** list includes a topology named **SensorStream** and the current date and time. Click this topology to view its statistics.
- 9. Under **Topology actions**, click **Deactivate** to stop the topology. When prompted to confirm, click **OK**. Then close the Storm UI tab, but keep the Azure portal tab open.
- 10. Switch back to Visual Studio and refresh the Storm Topology view. Note that the topology has a status of INACTIVE.
- 11. On the toolbar in the Storm Topology page, click **Kill** to delete the topology; and when prompted to confirm, click **OK**. Then close the Storm Topology window within Visual Studio.
- 12. Keep the Visual Studio open, you will enhance the SensorStream project in the next exercise.

# Creating a Custom Storm Topology


In the previous exercise, you created and submitted a Storm topology based on the default template. While this topology ran successfully, it didn't really do anything very useful. In this exercise, you will create a more complex topology that captures simulated sensor readings and stores them in an HBase table.

#### Create an HBase Table

Before creating a Storm topology, you must create an HBase table into which the captured sensor readings will be written.

**Note**: The commands in this procedure are <u>case-sensitive</u>.

- In the Microsoft Azure portal, browse to the blade for your HDInsight cluster, click Secure Shell, and then in the Secure Shell blade, under Windows users, copy the Host name (which should be your\_cluster\_name-ssh.azurehdinsight.net) to the clipboard.
- 2. Open PuTTY, and in the **Session** page, paste the host name into the **Host Name** box. Then under **Connection type**, select **SSH** and click **Open**.



- 3. If a security warning that the host certificate cannot be verified is displayed, click **Yes** to continue.
- 4. When prompted, enter the SSH username and password you specified when provisioning the cluster (not the cluster login).
- 5. In the console window for your SSH connection, enter the following command to start the HBase shell.

hbase shell

6. Enter the following command to create a table named **Sensors** with a column family named **Reading**.

```
create 'Sensors', 'Reading'
```

7. Minimize the SSH console (you will return to the HBase shell later.)

#### Create a Sensor Simulator Class

The sensors in your topology will be simulated by a class that generates random sensor readings. Each reading will consist of the date and time the reading was taken, the name of the sensor, and the value of the reading.

1. In Visual Studio, add a new class file named Sensor.cs to the SensorStream project.

**Tip**: You can copy and paste code in the following instructions from **Sensor.txt** in the **Lab02\C#** folder.

2. In the **Sensor.cs** code file, replace the existing **using** statements with the following code:

```
using System;
using Microsoft.SCP;
```

3. Modify the **Sensor** class definition to be static, as shown here:

```
public static class Sensor
{
}
```

4. In the **Sensor** class, add the following code to define a static method named **GetSensorReading**:

This code initializes a new **Random** class, and then generates a **Values** list containing:

- The current date and time.
- A string in the format *SensorN*, where N is a random number between 0 and 9.
- A random integer value.
- 5. Save the modified **Sensor.cs** code file.

## Modify the Spout Class

Now that you have created a source for the sensor readings, you must modify the spout to consume them.

**Tip**: You can copy and paste code in the following instructions from **Spout.txt** in the **Lab02\C#** folder.

1. Open the **Spout.cs** code file, and in the **Spout** initializer method, find the following code:

```
outputSchema.Add("default", new List<Type>() { typeof(int) });
```

2. Replace this code with the following code, which defines the output schema as a list containing a date, a string, and an integer:

3. In the **NextTuple** method, find the following code:

```
ctx.Emit(new Values(r.Next()));
```

4. Replace this code with the following code, which emits a sensor reading to the default stream:

```
Values sensorReading = Sensor.GetSensorReading();
ctx.Emit(Constants.DEFAULT STREAM ID, sensorReading);
```

5. Above the **Spout** method, delete the following variable declaration, which is no longer required:

```
private Random r = new Random();
```

6. Save the modified **Spout.cs** code file.

#### Modify the Bolt Class

Now you're ready to modify the **Bolt** class that will process the sensor readings by writing them to the HBase table.

**Tip**: You can copy and paste code in the following instructions from **Bolt.txt** in the **Lab02\C#** folder.

- 1. On the **Tools** menu, point to **NuGet Package Manager**, and click **Manage NuGet Packages for Solution**.
- 2. In the NuGet Package Manager window, search nuget.org for *HBase Client*, and in the list of results, select **Microsoft.HBase.Client**.
- 3. Install the latest stable version of the HBase Client package in the **SensorStream** project. Then close the NuGet Package Manager window.
- 7. In the **Bolt.cs** code file, add the following **using** statements under the existing **using** statements:

```
using Microsoft.HBase.Client;
using org.apache.hadoop.hbase.rest.protobuf.generated;
```

8. At the beginning of the class, find the following variable declarations:

```
private int count;
private Context ctx;
```

9. Replace these declarations with the following ones, substituting the name of your HDInsight HBase cluster, your HBase cluster user name, and your HBase cluster password where indicated:

```
private Context ctx;
private DateTime readingTime;
private string sensorName;
private int sensorValue;
string clusterURL = "https://clustername.azurehdinsight.net";
string hadoopUsername = "username";
string hadoopUserPassword = "password";
```

10. In the **Bolt** initializer method, find the following code:

```
inputSchema.Add("default", new List<Type>() { typeof(int) });
```

11. Replace this code with the following code, which defines the input schema as a list containing a date, a string, and an integer:

12. In the **Execute** method, replace all of the existing code with the following code, which reads the data from the tuple received by the bolt and writes it to the HBase table using the sensor name as the row key:

```
// Get data from tuple
readingTime = (DateTime)tuple.GetValue(0);
```

```
sensorName = tuple.GetString(1);
sensorValue = tuple.GetInteger(2);
// log tuple
Context.Logger.Info("Sensor Reading", sensorName);
try
{
  // Insert live data into an HBase table.
 ClusterCredentials creds = new ClusterCredentials(
                                        new Uri(clusterURL),
                                        hadoopUsername,
                                        hadoopUserPassword);
 HBaseClient hbaseClient = new HBaseClient(creds);
 CellSet cellSet = new CellSet();
 CellSet.Row cellSetRow = new CellSet.Row
              { key = Encoding.UTF8.GetBytes(sensorName) };
 cellSet.rows.Add(cellSetRow);
 Cell valueCell = new Cell
   { column = Encoding.UTF8.GetBytes("Reading:Value"),
     data = Encoding.UTF8.GetBytes(sensorValue.ToString()) };
 cellSetRow.values.Add(valueCell);
 Cell timeCell = new Cell
   { column = Encoding.UTF8.GetBytes("Reading:LastUpdated"),
     data = Encoding.UTF8.GetBytes(readingTime.ToString()) };
  cellSetRow.values.Add(timeCell);
 hbaseClient.StoreCellsAsync("Sensors", cellSet);
catch (Exception ex)
 Context.Logger.Error("Sensor Write Error", ex.Message);
```

#### 13. Save the modified **Bolt.cs** code file.

**Note**: The connection between the Storm and HBase clusters in this lab is made over the Internet, even though both clusters are in the same Azure subscription and data center. This keeps the lab setup simple, and enables you to focus on learning the specific of implementing a Storm topology in C#. In a real, production solution, you would provision both the Storm and HBase clusters in a virtual network so they can communicate directly without passing traffic out of the Azure data center across the Internet. For an example of deploying an HBase cluster in a virtual network, see <a href="https://azure.microsoft.com/en-us/documentation/articles/hdinsight-hbase-provision-vnet/">https://azure.microsoft.com/en-us/documentation/articles/hdinsight-hbase-provision-vnet/</a>.

Additionally, the code in this lab has been deliberately minimized to help you focus on learning the key principles of creating a Storm topology. In production code, you should store the cluster name and credentials in a configuration file and read them at run-time instead of hard-coding them. For a more comprehensive example of a Storm topology that writes data to HBase using best practices, create a new Visual Studio project based on the **Storm HBase Writer Sample** template.

# Modify the Topology Initialization Code

Now that you have made changes to the event tuple schema, you must modify the code used to initiate the topology.

**Tip**: You can copy and paste code in the following instructions from **Program.txt** in the **Lab02\C#** folder.

1. In the **Program.cs** code file, modify the contents of the **GetTopologyBuilder** function to match the following code:

```
TopologyBuilder topologyBuilder = new
TopologyBuilder("SensorStream");
topologyBuilder.SetSpout(
"SensorReader Spout",
Spout.Get,
new Dictionary<string, List<string>>()
 {Constants.DEFAULT STREAM ID,
 new List<string>(){"readingTime", "sensorName", "sensorValue"}}
},
1);
topologyBuilder.SetBolt(
"SensorWriter Bolt",
Bolt.Get,
new Dictionary<string, List<string>>(),
4).shuffleGrouping("SensorReader Spout");
return topologyBuilder;
```

This code renames the spout and bolt to be more descriptive, modifies the stream schema to match the sensor reading data, and configures the parallelism hint for the bolt so that 4 executors are created.

2. Save the modified Program.cs file.

#### Submit the Toplogy

The default code in the Storm Application template defines a valid topology that can be submitted to a Storm cluster and started. In this procedure, you will submit the topology to see it running.

- 1. On the **Build** menu, click **Build Solution**.
- 2. In the Solution Explorer pane, right-click the **SensorStream** project and click **Submit to Storm on HDInsight**. If you are prompted to sign into your Azure account, do so using your Microsoft account credentials. Then, when prompted, select your Storm cluster and click **Submit**.
- 3. After the storm topology has been submitted, in the Storm Topology window that is automatically opened, select the SensorStream topology to view its status. The topology should show the SensorReader\_Spout spout transferring default tuples to the SensorWriter\_Bolt bolt, where they are executed. Click the Refresh icon at the top of the page to see an updated indication of the uptime.
- 4. Refresh the view a few times until the uptime shows more than 30s.

#### Query the HBase Table

Now that your Storm topology has captured and processed some sensor readings, you can view the readings in the HBase table.

1. In the SSH console window, in the HBase shell, enter the following command to retrieve the data in the Sensors table

```
scan 'Sensors'
```

- 2. View the results, noting that they show the most recently captured value for each sensor.
- 3. Scan the table again, and observe that the values are being updated in real-time by the Storm topology.
- 5. Switch to Visual Studio and on the toolbar in the Storm Topology page, click **Kill** to stop and delete the topology; and when prompted to confirm, click **OK**.
- 4. Switch back to the SSH console and scan the table once more. The data is now static.
- 5. Minimize the SSH console window. You will return to the HBase shell in the next exercise.

# Implement Retry Logic

In the previous exercise, you created and submitted a Storm topology that captures simulated sensor readings and stores them in an HBase table. However, the topology is not transactional and has no retry logic; and in the event of a bolt being unable to write a sensor reading to HBase (for example, due to intermittent network connectivity issues), some data may be lost. In this exercise, you will enhance the topology to add retry logic to help mitigate tuple processing failures.

#### Enable the Acker

In order to implement retry logic in a non-transactional topology, you must enable the Storm *Acker* for the topology. This configuration setting enables downstream bolts to call the **Ack** method when a tuple has been processed successfully. Conversely, if processing fails for any reason, the downstream bolt can call the **Fail** method. The Acker routes these calls to the upstream spout or bolt that emitted the tuple to verify that a tuple has been processed or to initiate retry logic.

**Tip**: You can copy and paste code in the following instructions from **Program (Ack).txt** in the **Lab02\C#** folder.

- 1. In Visual Studio, in the **SensorStream** project, view the **Program.cs** file.
- 2. Modify the code in the **GetTopologyBuilder** function by adding an **enableAck** parameter with the value true to the **SetSpout** and **SetBolt** method calls as shown by the code in **bold** below.

```
topologyBuilder.SetBolt(
   "SensorWriter_Bolt",
   Bolt.Get,
   new Dictionary<string, List<string>>(),
   4, true).shuffleGrouping("SensorReader_Spout");
return topologyBuilder;
}
```

3. Save Program.cs.

## Modify the Bolt to Call Ack or Fail if Ack is Enabled

To initiate retry logic, the bolt in your topology must determine if the Acker is enabled; and if so, it must call **Ack** for each successfully processed tuple, or **Fail** if an exception occurs.

**Tip**: You can copy and paste code in the following instructions from **Bolt (Ack).txt** in the **Lab02\C#** folder.

1. Open the **Bolt.cs** file, and in the **Bolt** class declaration, under the existing variable declarations for the HBase cluster URL and credentials, add the following variable declaration:

```
private bool enableAck = false;
```

2. In the public **Bolt** initializer function, add the following code under the existing code that declares the component schema to set the **enableAck** variable based on the bolt configuration:

3. In the **Execute** function, at the end of the **try** block, after the existing code that writes the data to HBase, add the following code to call **Ack** when the tuple has been successfully processed.

```
if (enableAck)
{
  ctx.Ack(tuple);
}
```

4. In the **Execute** function, in the **catch** block, after the existing code to log the error message, add the following code to call **Fail** if the tuple is not processed successfully.

```
if (enableAck)
{
  ctx.Fail(tuple);
}
```

5. Save Bolt.cs.

#### Modify the Spout to Add Retry Logic

The code to actually implement retry logic in your topology must be added to the spout. The basic approach is to maintain a cache of tuples that have been emitted until an Ack for those tuples is received. Each tuple emitted is identified by a sequence number so that tuples that have been

successfully processed by all downstream bolts can be removed from the cache. If processing for a tuple fails, the spout retrieves the tuple from the cache and re-emits it.

**Tip**: You can copy and paste code in the following instructions from **Spout (Ack).txt** in the **Lab02\C#** folder.

1. Open the Spout.cs file, and in the **Spout** class declaration, under the existing variable declaration for the context, add the following variable declarations:

```
private bool enableAck = false;
private long tupSeqId = 0;
Dictionary<long, Values> cachedTuples = new Dictionary<long, Values>();
```

6. In the public **Spout** initializer function, add the following code under the existing code that declares the component schema to set the **enableAck** variable based on the spout configuration:

2. In the **NextTuple** function, replace the existing code with the following code. This checks to see if the Acker is enabled; and if so, increments the sequence ID and includes it with the emitted tuple.

```
Values sensorReading = Sensor.GetSensorReading();

if (enableAck)
{
    // If ack is enabled, include a sequence ID
    tupSeqId++;
    cachedTuples.Add(tupSeqId, sensorReading);
    ctx.Emit(Constants.DEFAULT_STREAM_ID, sensorReading, tupSeqId);
}
else
{
    ctx.Emit(Constants.DEFAULT_STREAM_ID, sensorReading);
}
```

3. In the Ack function, add the following code to remove the cached tuple after it has been successfully processed:

```
// remove cached tuple
if (enableAck)
{
  cachedTuples.Remove(seqId);
}
```

4. In the **Fail** function, add the following code to retrieve the cached tuple and re-emit it if processing fails:

```
// retry failed tuple
if (cachedTuples.ContainsKey(seqId))
```

```
{
  ctx.Emit(Constants.DEFAULT_STREAM_ID, cachedTuples[seqId], seqId);
}
```

5. Save Spout.cs.

# Test the Toplogy

- In the Solution Explorer pane, right-click the SensorStream project and click Submit to Storm on HDInsight. If you are prompted to sign into your Azure account, do so using your Microsoft account credentials. Then, when prompted, select your Storm cluster and click Submit.
- 2. After the storm topology has been submitted, in the Storm Topology window that is automatically opened, select the **SensorStream** topology to view its status. Click the **Refresh** icon at the top of the page to see an updated indication of the uptime for the topology.
- 3. Select the **Show Acker** checkbox, and refresh the topology until the uptime is more than 30s.
- 4. Click **Kill** to stop and delete the topology; and when prompted to confirm, click **OK**. Then keep refreshing the topology until the number of acks is indicated in the topology diagram.
- 5. Keep Visual Studio open, you will return to the SensorStream project in the next exercise.

# Implement a Sliding Window

A common requirement in streaming data analysis is to aggregate data over a temporal period. For example, you may need to build an application that tracks the top ten trending hashtags over the previous hour. You can build this kind of solution by implementing a sliding window pattern in which the data within the required timeframe is aggregated at periodic intervals (for example, by determining the most commonly used hashtags for the last every hour at ten minute intervals).

In this exercise, you will implement a simple sliding window topology to count the number of readings generated by each sensor in the past minute. The counts will be updated every ten seconds.

#### Create a Bolt to Count Sensor Readings

**Tip**: You can copy and paste code in the following instructions from **Counter\_Bolt.txt** in the **Lab02\C#** folder.

- 1. In Visual Studio, in Solution Explorer, right-click the **SensorStream** project, point to **Add**, and click **New Item**. Then add a new **Storm Bolt** named **Counter\_Bolt.cs**.
- 2. In the new **Counter\_Bolt.cs** class file, replace the existing **using** statements with the following code:

```
using System;
using System.Collections.Generic;
using System.Linq;
using System.Text;
using Microsoft.SCP;
using Microsoft.HBase.Client;
using org.apache.hadoop.hbase.rest.protobuf.generated;
```

3. In the **Counter\_Bolt** class declaration, before the **Execute** function, add the following variable declarations, substituting the name of your HDInsight HBase cluster, your HBase cluster user name, and your HBase cluster password where indicated:

```
// context
private Context ctx;
```

This code includes a dictionary that will be used to store an entry for each sensor, containing the sensor name as a key and a list of DateTime values that indicate the reading time for each sensor reading.

4. In the **Counter\_Bolt** class, before the **Execute** function, add the following initializer function:

This code defines two input schemas for the bolt. A default input schema that contains the sensor reading tuples emitted by the spout, and an input schema for the *tick tuple* stream that is sent to the bolt at a specified interval by Storm.

5. In the **Counter\_Bolt** class, after the initializer function, add the following static function to return an instance of the bolt when initializing the topology.

6. In the **Counter\_Bolt** class, after the **Get** function, add the following static function to determine whether a cached reading is stale (readings are considered stale if they are older than a minute).

```
private static bool StaleReading(DateTime d)
{
  return d < DateTime.Now.Subtract(new TimeSpan(0, 1, 0));
}</pre>
```

7. In the **Counter\_Bolt** class, in the **Execute** function, add the following code.

```
var isTickTuple =
  tuple.GetSourceStreamId().Equals(Constants.SYSTEM TICK STREAM ID);
if (!isTickTuple)
  // Get data from tuple
 readingTime = (DateTime) tuple.GetValue(0);
  sensorName = tuple.GetString(1);
  // cache this reading
  if (sensors.ContainsKey(sensorName))
   sensors[sensorName].Add(readingTime);
  }
 else
   sensors.Add(sensorName, new List<DateTime>() { readingTime });
else
  // process each sensor for which we have readings
 foreach (KeyValuePair<string, List<DateTime>> readings in sensors)
    // remove readings over a minute old
    readings. Value. RemoveAll (StaleReading);
    // count remaining readings
    int numReadings = readings.Value.Count();
    // write reading count to HBase
    ClusterCredentials creds = new ClusterCredentials(
                                   new Uri(clusterURL),
                                   hadoopUsername,
                                   hadoopUserPassword);
   HBaseClient hbaseClient = new HBaseClient(creds);
    CellSet cellSet = new CellSet();
    CellSet.Row cellSetRow =
     new CellSet.Row { key = Encoding.UTF8.GetBytes(readings.Key) };
    cellSet.rows.Add(cellSetRow);
    Cell valueCell =
     new Cell { column = Encoding.UTF8.GetBytes("Reading:Count"),
      data = Encoding.UTF8.GetBytes(numReadings.ToString()) };
   cellSetRow.values.Add(valueCell);
   hbaseClient.StoreCellsAsync("Sensors", cellSet);
  }
}
```

This code checks the input stream to determine if a tick tuple has been received. If not, the code processes a default tuple by adding the sensor reading time to the cached list of reading times for the specified sensor name.

If a tick tuple has been received, the code processes each sensor by removing all readings that are over a minute old, counting the remaining readings, and writing the count value to a column named **Reading:Count** in the **Sensors** HBase table.

8. Save Counter\_Bolt.cs.

## Add the Counter Bolt to the Topology

Now that you have implemented a bolt to count readings, you must add it to the topology.

**Tip**: You can copy and paste code in the following instructions from **Program (Counter).txt** in the **Lab02\C#** folder.

 Open Program.cs, and in the GetToplogyBuilder function, after the existing toplogyBuilder.SetBolt statement but before the return toplogyBuilder statement, add the following code to define a configuration setting that enables a tick tuple every 10 seconds:

```
var boltConfig = new StormConfig();
boltConfig.Set("topology.tick.tuple.freq.secs", "10");
```

2. After the code you just added, but before the **return toplogyBuilder** statement, add the following code to include the counter bolt in the topology.

```
topologyBuilder.SetBolt(
   "Counter_Bolt",
   Counter_Bolt.Get,
   new Dictionary<string, List<string>>(),
   1).fieldsGrouping("SensorReader_Spout",
        new List<int>() { 1 }).addConfigurations(boltConfig);
```

This code adds the **Counter\_Bolt** class as a bolt, connecting it to the **Sensor\_Reader** spout using a **fieldGrouping** connection so that all readings for a given **sensorName** field value are sent to the same instance of the bolt. This is necessary to ensure that there is a single, definitive count of readings for each sensor without having to collate results from multiple bolt instances. The configuration for the tick tuple is also added to this bolt.

3. Save Program.cs.

# Test the Sliding Window

- 1. On the **Build** menu, click **Build Solution**.
- In the Solution Explorer pane, right-click the SensorStream project and click Submit to Storm on HDInsight. If you are prompted to sign into your Azure account, do so using your Microsoft account credentials. Then, when prompted, select your Storm cluster and click Submit.
- 3. After the storm topology has been submitted, in the Storm Topology window that is automatically opened, select the SensorStream topology to view its status. The topology should show the SensorReader\_Spout spout transferring default tuples to the SensorWriter\_Bolt and Counter\_Bolt bolts, where they are executed. Click the Refresh icon at the top of the page to see an updated indication of the uptime.
- 4. Refresh the view a few times until the uptime is over 30s.
- 6. In the SSH console window, in the HBase shell, enter the following command to retrieve the data in the Sensors table

```
scan 'Sensors'
```

- 7. View the results, noting that they now include a **Reading:Count** value for each sensor.
- 8. Scan the table again, and observe that the values are being updated every ten seconds by the Storm topology.

- 5. Enter **quit** to exit the HBase shell, close the Hadoop Command Line window, and close the SSH console.
- 6. In Visual Studio, on the toolbar in the Storm Topology page, click **Kill** to stop and delete the topology; and when prompted to confirm, click **OK**.
- 9. Close Visual Studio.

# Clean Up

Now that you have finished using Storm and HBase, you can delete your clusters. This ensures that you avoid being charged for cluster resources when you are not using them. If you are using a trial Azure subscription that includes a limited free credit value, deleting the clusters maximizes your credit and helps to prevent using it all before the free trial period has ended.

## Delete the Resource group

- 1. In the Azure portal, on the **Resource groups** menu, select the resource group you created for your clusters. This resource group contains your clusters and the associated storage account.
- 2. In the blade for your resource group, click **Delete**. When prompted to confirm the deletion, enter the resource group name and click **Delete**.
- 3. Wait for a notification that your resource group has been deleted.
- 4. Close the browser.