10 types of students

There are only 10 types of students

- those that understand binary
- those that don't understand binary

Decimal Representation

Can interpret decimal number 4705 as:

$$4\times 10^3 + 7\times 10^2 + 0\times 10^1 + 5\times 10^0$$

- The base or radix is 10 Digits 0 – 9
- Place values:

 1000	100	10	1
 10^{3}	10^{2}	10^1	100

- Write number as 4705₁₀
 - Note use of subscript to denote base

Representation in Other Bases

- base 10 is an arbitrary choice
- can use any base
- e.g. could use base 7
- Place values:

Write number as 1216₇ and interpret as:

$$1 \times 7^3 + 2 \times 7^2 + 1 \times 7^1 + 6 \times 7^0 == 454_{10}$$

Binary Representation

- Modern computing uses binary numbers
 - because digital devices can easily produce high or low level voltages which can represent 1 or 0.
- The base or radix is 2
 Digits 0 and 1
- Place values:

• Write number as 1011₂ and interpret as:

$$1 \times 2^3 + 0 \times 2^2 + 1 \times 2^1 + 1 \times 2^0 == 11_{10}$$

Hexadecimal Representation

- Binary numbers hard for humans to read too many digits
- Conversion to decimal awkward and hides bit values
- Solution wirte the number in hexadecimal!
- The base or radix is 16
 Digits 0,1,2,3,4,5,6,7,8,9,A,B,C,D,E,F
- Place values:

• Write number as $3AF1_{16}$ and interpret as:

$$3 \times 16^3 + 10 \times 16^2 + 15 \times 16^1 + 1 \times 16^0 == 15089_{10}$$

• in C 0x denotes hexadecimal, e.g. 0x3AF1

Octal & Binary C constants

- Octal (based 8) representation used to be popular for binary numbers
- Similar advantages to hexadecimal
- in C a leading 0 denotes octal, e.g. 07563
- standard C doesn't have a way to write binary constants
- some C compilers let you write 0b
 - OK to use 0b in experimental code but don't use in important code

```
printf("%d", 0x2A); // prints 42
printf("%d", 052); // prints 42
printf("%d", 0b101010); // sometimes compiles and prints 42
```

Binary Constants

In hexadecimal, each digit represents 4 bits

```
0100 1000 1111 1010 1011 1100 1001 0111
0x 4 8 F A B C 9 7
```

In octal, each digit represents 3 bits

In binary, each digit represents 1 bit

0b010010001111101010111110010010111

Binary to Hexadecimal

- Example: Convert 10111111000101001₂ to Hex:
- Example: Convert 10111101011100_2 to Hex:

Hexadecimal to Binary

- Reverse the previous process
- Convert each hex digit into equivalent 4-bit binary representation
- Example: Convert *AD*5₁₆ to Binary:

Representing Negative Integers

- modern computers almost always use twos complement to represent integers
- positive integers and zero represented in obvious way
- negative integers represented in clever way to make arithmetic in silicon fast/simpler
- for an n-bit binary number the representation of -b is $2^n b$
- e.g. in 8-bit two's complement -5 is represented as $2^8 5 == 11111011_2$

Code example: printing all 8 bit twos complement bit patterns

• Some simple code to examine all 8 bit twos complement bit patterns.

for (int i = -128; i < 128; i++) {

printf("%4d ", i);
print bits(i, 8);

```
printf("\n");
}
source code for 8_bit_twos_complement.c

source code for print_bits.c source code for print_bits.h

$ dcc 8_bit_twos_complement.c print_bits.c -o 8_bit_twos_complement.
```

Code example: printing all 8 bit twos complement bit patterns

```
$ ./8_bit_twos_complement
-128 10000000
-127 10000001
-126 10000010
  -3 11111101
  -2 11111110
  -1 11111111
   0 00000000
   1 00000001
   2 00000010
   3 00000011
 125 01111101
 126 01111110
 127 01111111
```

Code example: printing bits of int

```
int a = 0;
printf("Enter an int: ");
scanf("%d", &a);
// sizeof returns number of bytes, a byte has 8 bits
int n bits = 8 * sizeof a;
print bits(a, n bits);
printf("\n");
source code for print bits of int.c
$ dcc print_bits_of_int.c print_bits.c -o print_bits_of_int
$ ./print_bits_of_int
Enter an int: 42
$ ./print_bits_of_int
Enter an int: -42
1111111111111111111111111111111010110
```

Code example: printing bits of int

```
$ ./print_bits_of_int
Enter an int: 0
$ ./print_bits_of_int
Enter an int: 1
$ ./print bits of int
Enter an int: -1
11111111111111111111111111111111111
$ ./print bits of int
Enter an int: 2147483647
01111111111111111111111111111111111
$ ./print bits of int
Enter an int: -2147483648
$
```

Bits in Bytes in Words

- Many hardware operations works with bytes: 1 byte == 8 bits
- C's sizeof gives you number of bytes used for variable or type
- sizeof variable returns number of bytes to store variable
- sizeof (type) returns number of bytes to store type
- On CSE servers, C types have these sizes
 - char = 1 byte = 8 bits, 42 is 00101010
 - short = 2 bytes = 16 bits, 42 is 000000000101010
 - int = 4 bytes = 32 bits, 42 is 000000000000000000000000101010
 - double = 8 bytes = 64 bits, 42 = ?
- above are common sizes but not universal on a small embedded CPU sizeof (int) might be 2 (bytes)

Code example: integer_types.c - exploring integer types

We can use sizeof and limits.h to explore the range of value can be represented by standard C integer types on our machine.

```
$ dcc integer_types.c -o integer_types
$ ./integer_types
           Type Bytes Bits
           char 1 8
     signed char 1 8
   unsigned char 1 8
          short 2 16
   unsigned short 2 16
            int 4 32
    unsigned int 4 32
           long
                  8 64
    unsigned long 8 64
       long long 8 64
unsigned long long
                  8
                     64
```

Code example: integer_types.c - exploring integer types

Type	Min	Max
char	-128	127
signed char	-128	127
unsigned char	0	255
short	-32768	32767
unsigned short	0	65535
int	-2147483648	2147483647
unsigned int	0	-1
long	-9223372036854775808	9223372036854775807
unsigned long	0	18446744073709551615
long long	-9223372036854775808	9223372036854775807
unsigned long long	0	18446744073709551615

source code for integer_types.c

stdint.h - integer types with guaranteed sizes

#include stdint.h

- to get below integer types (and more) with guaranteed sizes
- we will use these heavily in COMP1521

```
// range of values for type
                       minimum
                                                maximum
int8 t i1; //
                               -128
                                                    127
uint8_t i2; //
                                                    255
int16_t i3; //
                                                  32767
                            -32768
uint16 t i4; //
                                                  65535
int32_t i5; //
                     -2147483648
                                            2147483647
uint32_t i6; //
                                             4294967295
int64 t i7; // -9223372036854775808 9223372036854775807
                                  0 18446744073709551615
uint64 t i8; //
```

source code for stdint.c

Code example: char_bug.c

source code for char bug.c

```
Common C bug:
char c: // c should be declared int
while ((c = getchar()) != EOF) {
    putchar(c);
Typically stdio.h contains:
#define EOF -1

    most platforms: char is signed (-128..127)

    loop will incorrectly exit for a byte containing 0xFF

    rare platforms: char is unsigned (0..255)

    loop will never exit
```