



## Operating Systems

Lecture 8: Virtual Memory

Jinpengchen

Email: jpchen@bupt.edu.cn



- Background
- Demand Paging
- Page Replacement
- Allocation of Frames
- Thrashing



- Instructions must be loaded into memory before execution.
- Solutions in last chapter : Program entire→Physical memory
- Sometimes, jobs may be too big or too many.

How to expand the main memory?

- Physically? COST TOO HIGH!
- Logically?



- Virtual memory: Why and How?
  - Some code may get no, or only little, opportunity of execution,

for example, code for error handlers


- Some data may get no opportunity of access
- Locality of reference (程序的局部性原理), 1968, Denning
  - ✓ Temporal locality (时间局部性)
  - ✓ Spatial locality (空间局部性)
- Idea: partly loading (部分装入)、demand loading (按需装入)、replacement (置换)



- ♥ Virtual Memory(虚拟存储器)是指具有请求调页功能和置换功能
  - ,能从逻辑上对内存容量加以扩充的一种存储器系统
  - Logical size:
    - 从系统角度看:内存容量+外存容量
    - 从进程角度看:地址总线宽度范围内;内存容量+外存容量
  - Speed: close to main memory
  - Cost per bit: close to secondary storage (disks)
- Virtual memory: separation of user logical memory from physical memory.
  - only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - Allows for more efficient process creation



Virtual Memory That is Larger Than Physical Memory






- Virtual memory can be implemented via:
  - Demand paging
    - ✓ Paging technology + pager (请求调页) and page replacement
    - ✓ Pager VS. swapper the unit of swapping in/out is not the entire process but page.
  - Demand segmentation



- ♥ 虚拟存储器的特征
  - 多次性: 最重要的特征
    - ✓ 一个作业被分成多次装入内存运行
  - 12 对换性
    - ✓ 允许在进程运行的过程中,(部分)换入换出
  - 虚 虚拟性
    - ✓ 逻辑上的扩充
  - 虚拟性是以多次性和对换性为基础的。
  - 多次性和对换性是建立在离散分配的基础上的




- ♥ Virtual-address Space (虚拟 地址空间)
  - The virtual address space of a process refers to the logical (or virtual) view of how a process is stored in memory.
    - ✓ Typically: 0 xxx & exists in contiguous memory
  - In fact, the physical memory are organized (partitioned) in page frames & the page frames assigned to a process may not be contiguous ⇒ MMU





- Some benefits
  - Shared library using virtual memory



- Shared memory
- Speeding up process creation



#### Some benefits

- Programmers need not care about memory limitations
- More programs could be run simultaneously
- Less I/O needed, each user program would run faster



- Background
- Demand Paging
- Page Replacement
- Allocation of Frames
- Thrashing



Do not load the entire program in physical memory at program execution time.

NO NEED!

- Bring a page into memory only when it is needed
  - Less I/O needed
  - Less memory needed
  - Faster response
  - More users
- ♠ A page is needed 

  Reference to it
  - Invalid reference ⇒ Abort
  - Not-in-memory ⇒Bring to memory




## 🌣 Swapper VS. Pager

- A swapper manipulates the entire processes
- Lazy swapper

Never swaps a page into memory unless the page will be needed

✓ Swapper that deals with individual pages is a pager

Transfer of a Paged Memory to Contiguous Disk Space






- Basic Concepts (Hardware support)
  - The modified page table mechanism
  - Page fault
  - Address translation
  - Secondary memory (as swap space)



## The modified page table mechanism

- Valid-Invalid Bit (PRESENT bit)
  - ✓ With each page table entry a valid-invalid bit is associated
    - $v \Rightarrow in\text{-memory}, i \Rightarrow not\text{-in-memory}$
  - ✓ Initially valid—invalid bit is set to i on all entries
  - ✓ During address translation, if
    valid-invalid bit in page table entry
    is i ⇒ page fault
- Reference bits (for pager out)
- Modify bit (or dirty bit)
- Secondary storage info (for pager in)




page table



## The modified page table mechanism


Page table when some pages are not in main memory





## ◆ Page Fault (缺页故障)

- First reference to a page will trap to OS:
  - ✓ page fault(缺页故障/异常/中断)
- ₽ Page fault trap (缺页异常)
  - ✓ Exact exception (trap), 精确异常
    Restart the process in exactly the same place and state.
    Re-execute the instruction which triggered the trap
- Execution of one instruction may cause multiply page faults



- Page fault may occur at every memory reference
- One instruction may cause multiply page faults while fetching instruction or r/w operators

Example: One instruction and 6 page faults




## ◆ Page Fault (缺页故障)

- ₽ Page Fault Handling:
  - ✓ OS looks at an internal table to decide:
    - Invalid reference ⇒ abort
  - Just not in memory ⇒ bring to memory
  - ✓ Get an empty frame from the free frame list
  - ✓ Swap page into frame
    - Pager out & pager in
  - ✓ Modify the internal tables & Set validation bit = v
  - ✓ Restart the instruction that caused the page fault



- ◆ Page Fault (缺页故障)
  - Steps in Handling a Page Fault





## ◆ Page Fault (缺页故障)

Restart instruction

```
C = A + B
```

- ✓ 1. fetch the instruction
- ✓ 2. fetch A
- ✓ 3. fetch B
- ✓ 4. Add A and B
- ✓ 5. Store the sum in C (C not in memory)
- Problem can be ignored
  - ✓ Repetition
  - ✓ 1 instruction causes N page faults



- Address translation
  - ✓ Address translation hardware + page fault handling
- Resume the execution
  - Context save (保存现场)

Before OS handling the page fault, the state of the process must be saved

- ✓ Example: record its register values, PC
- Context restore (恢复现场)

The saved state allows the process to be resumed from the line where it was interrupted.

- NOTE: distinguish the following two situations
  - ✓ Illegal reference ⇒ The process is terminated
  - ✓ Page fault ⇒ Load in or pager in

# Demand Paging

- Performance of Demand Paging
  - Let p = Page Fault Rate  $(0 \le p \le 1.0)$ 
    - $\checkmark$  If p = 0, no page faults
    - ✓ If p = 1.0, every reference is a fault, Pure Demand Page
  - Effective Access Time (EAT)
    EAT = (1 − p) × memory access
    + p × page fault time
    - page fault time = page fault overhead
      - + swap page out(optional)
      - + swap page in
      - + restart overhead



## Performance of Demand Paging

#### Example

- ✓ Memory access time = 200ns
- ✓ Average page-fault service time = 8ms EAT =  $(1-p) \times 200 + p \times 8ms = (1 - p) \times 200 + p \times 8,000,000$ =  $200 + p \times 7,999,800$
- ✓ If one access out of 1,000 causes a page fault, then p = 0.001 EAT = 8, 199.8ns = 8.2 $\mu$ s

This is a slowdown by a factor of 8.2us/200ns = 40!!

✓ If we want performance degradation < 10%, then

EAT = 
$$200 + p \times 7$$
, 999,  $800 < 200 (1 + 10\%) = 220$   
p × 7, 999,  $800 < 20$ 

 $p < 20/7, 999, 800 \approx 0.0000025$ 



## Performance of Demand Paging

- Method for better performance
  - ✓ To keep the fault time low
    - Swap space, faster than file system
    - Only dirty page is swapped out, or
    - Demand paging only from the swap space, or
  - Initially demand paging from the file system, swap out to swap space, and all subsequent paging from swap space
  - ✓ Keep the fault rate extremely low
    - Localization of program executing
       Time, space



- Background
- Demand Paging
- Page Replacement
- Allocation of Frames
- Thrashing




- What happens if there is no free frame?
  - Find some page in memory, but not really in use, swap it out
    - ✓ Algorithm?
    - ✓ Performance?
    - ✓ Want an algorithm which will result in minimum number of page faults
    - ✓ Same page may be brought into memory several times



## ◆ Need of Page Replacement (页面置换)

- Free page frame is managed by OS using free-frame-list
- over-allocation: No free frames; All memory is in use.





- What happens if there is no free frame?
  - Solution:
  - Page replacement (页面置换)
  - Prevent over-allocation of memory by modifying pagefault service routine to include page replacement




## Basic Page Replacement

- Find the location of the desired page on disk
- Find a free frame:
  - ✓ If there is a free frame, use it
  - ✓ If there is no free frame, use a page replacement algorithm to select a victim frame
- Bring the desired page into the (newly) free frame; Update the page and frame tables
- Restart the process



## Basic Page Replacement



3/12/2018 BUPTSSE 31



#### Basic Page Replacement

- NO MODIFY, NO WRITTEN (to disk/swap space)
- Use modify (dirty) bit to reduce overhead of page transfers
  - ✓ Only modified pages are written to disk
- This technique also applies to read-only pages
  - ✓ For example, pages of binary code
- Page replacement completes separation between logical memory and physical memory
  - ✓ Large virtual memory can be provided on a smaller physical memory
- Demand paging, to lowest page-fault rate, two major problems
  - ✓ Frame-allocation algorithms
  - ✓ Page-replacement algorithms



#### Page Replacement Algorithms


- **GOAL:** to lowest page-fault rate
- Different algorithms are evaluated by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
- A reference string is a sequence of addresses referenced by a program

#### Example:

- ✓ An address reference string:
- √ 0100 0432 0101 0612 0102 0103 0104 0101 0611 0103 0104 0101 0610 0102 0103 0104 0101 0609 0102 0105
- $\checkmark$  Assuming page size = 100 B, then its corresponding page reference string is:
  - 1 4 1 6 1 6 1 6 1 6 1



- Page Replacement Algorithms
  - How many page faults?
    - ✓ Determined by the number of page frames assigned to the process
    - ✓ For the upper example: 1 4 1 6 1 6 1 6 1 6 1
      - If  $\geqslant$  3, then only 3 page faults
      - If = 1, 11 pages faults



Graph of Page Faults Versus The Number of Frames

3/12/2018 BUPTSSE 34




## Page Replacement Algorithms

In all our examples, the reference strings are  $\checkmark 1$ , 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5

## First-In-First-Out (FIFO) Algorithm

- The simplest page-replacement algorithm: FIFO
  - For each page: a time when it was brought into memory
  - For replacement: the oldest page is chosen
  - Data structure: a FIFO queue
    - ✓ Replace the page at the head of the queue
    - ✓ Insert a new page at the end of the queue
  - Example 1: 15 page faults, 12 page replacements reference string



page frames


#### First-In-First-Out (FIFO) Algorithm

- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
  - 3 frames (3 pages can be in memory at a time per process)

4 frames

#### First-In-First-Out (FIFO) Algorithm

- ♣ More memory, better performance? MAY BE NOT!!
  Belady's anomaly (贝莱迪异常现象):
  - more frames ⇒ more page faults






Optimal page-replacement algorithm:

Replace page that will not be used for longest period of time


- It has the lowest page-fault rate
- It will never suffer from Belady's anomaly
- Example 1: 9 page faults, 6 page replacements



3/12/2018 BUPTSSE 39



- 4 frames example
  - 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5




- OPT: Difficult to implement
  - How to know the future knowledge of the reference string?
- So, it is only used for measuring how well other algorithm performs

### Least Recently Used (LRU) Algorithm

- LRU: an approximation of the OPT algorithm

  Use the recent past as an approximation of the near future
  - To replace the page that has not been used for the longest period of time
  - For each page: a time of its last use
  - For replace: the oldest time value
- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5




8 page faults

# Least Recently Used (LRU) Algorithm

- # HOW to implement LRU replacement?
  - Counter implementation
    - ✓ Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
    - ✓ When a page needs to be changed, look at the counters to determine which are to be changed
  - Stack implementation-keep a stack of page numbers in a double link form:
    - ✓ When page referenced: Move it to the top
      - Requires 6 pointers to be changed
    - ✓ Each update is a bit more expensive
    - ✓ No search for replacement

## Least Recently Used (LRU) Algorithm

Use of a Stack to Record the Most Recent Page References reference string



# LRU Approximation Algorithms

- Reference bit
  - HW associate with each page a bit, initially = 0
  - When page is referenced, bit is set to 1
  - Replace the one which is 0 (if one exists)
    - ✓ We do not know the order, however
- Additional-Reference-Bits Algorithm:
  - Record each entry of a page table entry with a 8-bit byte
  - At a regular interval, a timer interrupt transfers the control to the OS

Reference bits + time ordering, for example: 8 bits


- ✓ HW modifies the highest bit, only
- ✓ Periodically, right shift the 8 bits for each page
- √ 00000000, ..., 01110111, ..., 11000100, ..., 11111111


# LRU Approximation Algorithms

- Second chance (clock) Algorithm
  - № Need only 1 reference bit, modified FIFO algorithm
  - Clock replacement
  - First, a page is selected by FIFO
  - If page to be replaced (in clock order) has reference bit = 0, then replace
  - If page to be replaced (in clock order) has reference bit = 1, then:
    - ✓ set reference bit 0
    - ✓ leave page in memory
    - ✓ replace next page (in clock order), subject to same rules

#### LRU Approximation Algorithms

- Second chance (clock) Algorithm
  - Implementation: Clock replacement
    - ✓ Clock order







#### Counting algorithms:

Keep a counter of the number of references that have been made to each page

- LFU(Least Frequently Used) Algorithm: replaces page with smallest count
  - ✓ Problem: heavily used initially, then never used
  - ✓ Shift the counts right by 1 bit to decay average usage count
- on the argument that the page with the smallest count was probably just brought in and has yet to be used



- Background
- Demand Paging
- Page Replacement
- Allocation of Frames
- Thrashing



- Minimum number of pages
  - Each process needs minimum number of pages
  - Determined by ISA (Instruction-Set Architecture )
    - ✓ We must have enough frames to hold all the different pages that any single instruction can reference
  - Example: IBM 370
    - 6 pages to handle MOVC instruction:
    - ✓ Instruction is 6 bytes, might span 2 pages
    - ✓ 2 pages to handle from
    - $\checkmark$  2 pages to handle to
  - Two major allocation schemes
    - ✓ Fixed allocation; priority allocation
  - Two replacement policy
    - ✓ Global vs. local

#### Allocation of Frames Fixed allocation

- Equal allocation
  - For example, if there are 100 frames and 5 processes, give each process 20 frames.



- Proportional allocation
  - Allocate according to the size of process example:

$$s_i = \text{size of process } p_i$$

$$S = \sum s_i$$

m = total number of frames

$$a_i$$
 = allocation for  $p_i = \frac{s_i}{S} \times m$ 

$$m = 64$$

$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \times 64 \approx 5$$

$$a_2 = \frac{127}{137} \times 64 \approx 59$$



#### Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- If process Pi generates a page fault,
  - ✓ Select for replacement one of its frames
  - ✓ Select for replacement a frame from a process with lower priority number



- Replacement policy: Global vs. Local Allocation
  - Global replacement
  - process selects a replacement frame from the set of all frames; one process can take a frame from another
    - ✓ Problem: a process cannot control its own page-fault rate
  - Local replacement
    - ✓ each process selects from only its own set of allocated frames
    - ✓ Problem: less used pages of memory



- Background
- Demand Paging
- Page Replacement
- Allocation of Frames
- Thrashing


0



- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
  - Low CPU utilization
  - OS thinks that it needs to increase the degree of multiprogramming
  - Another process added to the system, getting worse!
- Thrashing = a process is busy swapping pages in and out



• Cause of trashing: unreasonable degree of multiprogramming (不合理的多道程序度)





- How to limit the effects of thrashing
  - Local replacement algorithm? not entirely solved.
  - We must provide a process with as many frames as it needs—locality
  - How do we know how many frames are needed?
- Locality model: This is the reason why demand paging works
  - Process migrates from one locality to another
  - Localities may overlap
- Why does thrashing occur?
  Σ size of locality > total memory size



- ♥ Working-Set Model (工作集模型)
  - The working-set model is based on the assumption of locality.
  - Let

 $\Delta \equiv \text{working-set window}$ 

≡ a fixed number of page references

For example: 10,000 instructions

♥ Working set (工作集):

The set of pages in the most recent  $\Delta$  page references.


An approximation of the program's locality.




- ♥ Working-Set Model (工作集模型)
  - Example:  $\Delta = 10$

page reference table

... 261577775162341234443434441323444344...





 $WS(t_2) = \{3,4\}$ 

Working set size:

 $WSS_i$  (working set of Process  $P_i$ ) = total number of pages referenced in the most recent  $\Delta$  (varies in time)

- $\checkmark$  Varies in time, depend on the selection of  $\Delta$ 
  - if  $\Delta$  too small  $\Rightarrow$  will not encompass entire locality
  - if  $\Delta$  too large  $\Rightarrow$  will encompass several localities
  - if  $\Delta$  = ∞ ⇒ will encompass entire program



• For all processes in the system, currently

 $D = \Sigma WSS_i \equiv \text{total demand frames}$ 

m: total number of available frames

- $\mathbf{E} \mathbf{D} > \mathbf{m} \Rightarrow \mathbf{Thrashing}$
- Policy:

if D > m, then suspend one of the processes



- Keeping Track of the Working Set
  - Approximate with: fixed interval timer + reference bits
  - Example:  $\Delta = 10,000$ 
    - ✓ Timer interrupts after every 5000 time units
    - ✓ Keep in memory 2 bits for each page
    - ✓ Whenever a timer interrupts, copy and sets the values of all reference bits to 0
    - ✓ If one of the bits in memory = 1 ⇒ page in working set
  - Why is this not completely accurate?
    - ✓ IN!! But where?
  - Improvement:
    - ✓ 10 bits and interrupt every 1000 time units

3/12/2018 BUPTSSE 61



- ◆ Page-Fault Frequency (缺页频率): helpful for controlling trashing
  - Trashing has a high page-fault rate.
  - Establish "acceptable" page-fault rate
    - ✓ If actual rate too low, process loses frame
    - ✓ If actual rate too high, process gains frame

