

COVE DATA PROTECTION

N-SIGHT INTEGRATION

INTRODUCTION	2
REQUIREMENTS	2
PREPARATION	2
STEP 1: UPLOAD THE AUTOMATION SCRIPT.....	3
STEP 2: UPLOAD THE SCRIPT	4
STEP 3: ADD TASK TO CLIENT, SITE OR DEVICE	5
STEP 4: SELECT AUTOMATION TASK	6
STEP 5: SELECT DEVICE TYPES FOR THE TASK	7
STEP 6: GET THE CUSTOMER UID FROM THE COVE PORTAL	8
STEP 7: ENTER DETAILS IN THE AUTOMATED TASK	9
STEP 8: SELECT TASK FREQUENCY.....	11
STEP 9: TASK OPTIONS	12
STEP 10: SELECT DEVICES FOR TASK	13
STEP 11: WAIT FOR THE TASK TO BE CREATED	14
STEP 12: RUN THE AUTOMATED TASK.....	15
STEP 13: CHECK INSTALLATION STATUS.....	16
STEP 14: (OPTIONAL) ADJUST DEFAULT VALUES POLICY – INSTALL AUTOMATION MANAGER	17
STEP 15: (OPTIONAL) ADJUST DEFAULT VALUES POLICY – CHANGE INPUT SETTINGS	18
SUMMARY.....	21

INTRODUCTION

With use of the following guide, you'll be able to roll out Cove Data Protection into your N-sight devices with just a few mouse clicks. After the roll-out, the software is not only installed, but also configured with a profile and product of your choice, optionally an archiving schedule and bandwidth limitations.

The automation policy is going to:

- Download the latest Cove Backup Manager
- Save the download in a local temporary folder
- Execute the download with extra parameters for a silent install with a profile and product and all extra settings attached.
- Remove the downloaded installer after installation

REQUIREMENTS

For Servers: Windows 2012R2 or higher, .NET framework 4.5 or higher

For Workstations: Windows 10 or higher, NET framework 4.5 or higher

PREPARATION

Before running this automation task, please make sure you have available or add:

- access to the Cove Data Protection portal, at <https://backup.management>
- a Profile in the Cove Data Protection portal
- a Product in the Cove Data Protection portal
- the customer(s) created in the Cove Data Protection portal

STEP 1: UPLOAD THE AUTOMATION SCRIPT

Login to your N-sight dashboard, click on Settings and select Script Manager.

The screenshot shows the N-sight dashboard interface. On the left, there is a sidebar with various icons and a search bar. The main menu at the top includes File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. The Settings menu is currently selected. In the center, under the Monitoring and Management section, the Script Manager is highlighted. The right side of the screen displays a table titled "Script Manager" with columns for Device (Workstations, Mixed, Mobile Devices, Network Devices, Networks), Client, Site, Server, Description, and Agent Version. The table lists several entries, such as European Software HQ, ATO Services Client X, and Asian Pacific Tech HQ. At the bottom of the table, it says "Displaying 1 - 50 of 71". Below the table, there are tabs for Outages, Checks, Notes, Tasks, Assets, Patches, and Web, with the Checks tab selected. The Checks section shows a list of tasks with columns for Description, More Information, Date/Time, and Assigned Tasks. Some tasks listed include "Antivirus Update Ch..." (Status: Product not found, Date: 26-Oct-2022 06:00), "Critical Events Chec..." (Status: 0 event(s) found, Date: 26-Oct-2022 06:00), and "Disk Space Check - ..." (Status: Total: 239.66 GB, F..., Date: 26-Oct-2022 21:38).

STEP 2: UPLOAD THE SCRIPT

Enter the name for the script, open for own input. Select both the Automated Task and Windows checkbox. Browse to the Cove Data Protection Agent Deploy .amp file you received and click save.

The screenshot shows the N-SIGHT interface with the 'Script Manager' module selected. On the left, there's a sidebar with various monitoring and reporting icons. The main area displays a table of existing scripts under 'Script Manager'. A modal window titled 'Add User Defined Scripts' is open in the center. In this window, the 'Name' field is set to 'Cove - Installation script'. The 'Type' section has 'Automated Task' checked. The 'OS' section has 'Windows' checked. In the 'Upload a script' section, a file named 'Cove Data Protection Agent Deploy v22.07.amp' is selected for upload. Below the file upload field, it says 'Supported script types: sh, js, vbs, cmd, bat, pl, php, py, rb, ps1, amp'. At the bottom of the modal, there are 'Save' and 'Cancel' buttons. To the right of the modal, a separate window titled 'Automation Manager' is visible, showing a list of scripts with columns for 'Script ...', 'Auto...', and 'Type'.

STEP 3: ADD TASK TO CLIENT, SITE OR DEVICE

Right click on the Client, Site or Device you want to execute this task. Select Task and Add.

The screenshot shows the N-SIGHT monitoring interface. The left sidebar has icons for File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. The top navigation bar includes File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, Community, and status indicators for 7/71, 7/27, and 13. The main area is titled 'Monitoring and Management' with tabs for Servers, Workstations, Mixed, Mobile Devices, Network Devices, and Networks. A search bar is at the top of the main content area. Below it is a table of server details:

	Client	Site	Server	Description	Agent Version	
<input type="checkbox"/>	Asian Pacific Tech	HQ	2016-XMN	2016-XMN	v10.13.0	
<input type="checkbox"/>	Asian Pacific Tech	HQ	2008R2-MEL	2008R2-MEL	v10.13.0	
<input type="checkbox"/>	Asian Pacific Tech	HQ	2012R-DEL	Administrator	v10.13.0	
<input type="checkbox"/>	Asian Pacific Tech	HQ	2016-NRT	2016-NRT	v10.13.0	
<input type="checkbox"/>	Asian Pacific Tech	HQ	2016-SZX	Administrator	v10.13.0	
<input type="checkbox"/>	Asian Pacific Tech	HQ	2019-BOM	Administrator	v10.13.0	

Below the table is a 'Run' button and a page navigation bar (Page 1 of 1). The bottom section is titled 'Add' and shows a table of active issues:

Category	Check	Issues	Date/Time
Backup	Backup Check - Cov...	Backup: Successful...	09-Dec-2022 06:00
Critical Events	Critical Events Chec...	5 event(s) found	09-Dec-2022 06:00
Critical Events	Critical Events Chec...	0 event(s) found	09-Dec-2022 06:00
Critical Events	Critical Events Chec...	1 event(s) found	09-Dec-2022 06:00
Disk Space	Disk Space Check - ...	Total: 126.45 GB, F...	09-Dec-2022 14:08
Drive Space	Drive Space Chang...	Total: 126.45 GB, F...	09-Dec-2022 06:00
Failed Login	Failed Login Check	No Failed Logins	09-Dec-2022 06:00
Antivirus	Managed Antivirus ...	More information	09-Dec-2022 14:21

STEP 4: SELECT AUTOMATION TASK

Enter the script name in the search field and select the script.

The screenshot shows the N-SIGHT software interface. On the left is a sidebar with various icons and a search bar. The main menu bar includes File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. A top right corner displays statistics: 7/71, 7/27, and 13. The central area has tabs for Servers, Workstations, Mixed, Mobile Devices, Network Devices, and Networks. A modal window titled "Add Automated Task" is open, showing a search result for "Cove - Installation". The result is listed under "User Defined" and is highlighted. Below the search bar in the modal is a "Description" section containing the following text:

Script requires Agent v10.3.0 and .NET 4.5 or above. PowerShell v3 or above is recommended for future compatibility.

At the bottom of the modal are "Next" and "Cancel" buttons. The main interface background shows a list of assigned tasks with columns for "Assigned Tasks" and "Last Run". The status bar at the bottom right shows the date and time: 09-Dec-2022 14:21, along with the text "Manage, secure and protect all things IT".

STEP 5: SELECT DEVICE TYPES FOR THE TASK

If you selected a Client or Site for the task, you'll get a popup asking if you want to run the task on Servers and/or Workstations. Select the right option for your situation and select Next.

The screenshot shows the N-SIGHT application interface. On the left, there's a sidebar with various icons and a tree view under 'Monitoring and Management' titled 'Global SE Production / All Clients'. The main area displays a table of servers with columns for Agent Version and status indicators. Below the table is a list of recent checks, each with a status icon, date, and brief description. At the bottom, there's a footer bar with links like 'Summary', 'Outages', 'Checks', 'Notes', etc., and a message: 'Manage, secure and protect all things IT'.

Server	Agent Version	Status
ASIAN PACIFIC TECH HQ	v10.13.0	Green
ASIAN PACIFIC TECH BOM	v10.13.0	Green
ASIAN PACIFIC TECH BOM	v10.13.0	Green
ASIAN PACIFIC TECH BOM	v10.13.0	Green
ASIAN PACIFIC TECH BOM	v10.13.0	Green
ASIAN PACIFIC TECH BOM	v10.13.0	Green

Check Type	Description	Date
Backup Check	Backup Check - Cov... Backup: Successful...	09-Dec-2022 06:00
Critical Events Check	Critical Events Chec... 5 event(s) found	09-Dec-2022 06:00
Critical Events Check	Critical Events Chec... 0 event(s) found	09-Dec-2022 06:00
Critical Events Check	Critical Events Chec... 1 event(s) found	09-Dec-2022 06:00
Disk Space Check	Disk Space Check - ... Total: 126.45 GB, F...	09-Dec-2022 14:08
Drive Space Change	Drive Space Chang... Total: 126.45 GB, F...	09-Dec-2022 06:00
Failed Login Check	Failed Login Check No Failed Logins	09-Dec-2022 06:00
Managed Antivirus	Managed Antivirus ... More information	09-Dec-2022 14:21

STEP 6: GET THE CUSTOMER UID FROM THE COVE PORTAL

Please login to the Cove Data Protection portal, make sure you have the customers (Clients in N-sight) created. Find the corresponding partner under Customer Management and click on the 3 dots. Select Copy customer UID from the menu. Customer names don't have to match the exact names in N-sight.

The screenshot shows the 'Customer management' section of the Cove Data Protection portal. On the left, there's a sidebar with 'Customer management' highlighted. The main area displays a list of 'ALL CUSTOMERS' with a search bar at the top. A context menu is open over the entry 'SEDEMO (8)', specifically over the 'Asian Pacific Tech' item. The menu includes options like 'Copy customer name', 'Copy customer UID', and 'Edit customer'. To the right, a table lists various customers with their IDs and names.

Customer ID	Customer
298917	Africa Industries
298918	Asian Pacific Tech
298926	European Software Services
1799860	German Industrie
298930	Latin American Experts
298932	Middle East Information Systems
298933	North American Technologies
297876	SEDEMO
683851	United Kingdom Tech

STEP 7: ENTER DETAILS IN THE AUTOMATED TASK

This step is where you configure the complete setup. Don't use quotes or double quotes, names with spaces can be entered without quotes.

- Descriptive Name: enter your own reference to the Task name
Cove Customer UID: paste the Customer UID from the Cove portal over the example
Set Backup Profile: enter true or false, depending on if you'd prefer to use a Profile
Backup Profile Name: enter the exact Profile name that exists in your Cove portal
Set Backup Product: enter true or false, depending on if you'd prefer to use a Product
Backup Product Name: enter the exact Product name that exists in your Cove portal
Set Archiving: enter true or false, depending on if you'd prefer to use Archiving
Archive Day of Month: enter your preferred day of month the Archive will run, e.g. **last**
Set Bandwidth: enter true or false, depending on if you'd prefer to use Bandwidth throttling
Throttle start: enter the time the throttle will start to be active (24 hour format)
Throttle stop: enter the time the throttle will stop to be active (24 hour format)
Unlimited weekends: enter true or false, true if you don't want the weekends to be throttled.
Upload Kbps: enter the upload limit in Kbps; 5120 equals 5 Mbit/s
Download Kbps: enter the download limit in Kbps; Unlimited is normally the preferred option.

The screenshot shows the N-SIGHT software interface. On the left, there's a sidebar with icons for monitoring, reports, settings, and community. The main menu bar includes File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. The top right corner displays statistics: 7 / 71, 7 / 27, and 13 alerts. The central part of the screen shows a 'Monitoring and Management' section with a tree view of clients: Global SE Production / All Clients, Africa Industries, Asian Pacific Tech, ATO Services, European Software Services, German Industrie, Middle East Information Systems, United Kingdom Tech, AV ONLY, Latin American Experts, North American Technologies, and South America. A modal dialog box titled 'Cove - Installation script' is open, prompting for task details. The 'Select' tab is selected, showing checkboxes for 'Server' and 'Workstation'. The 'Script Parameters' section includes fields for 'Descriptive Name' (Cove - Deployment), 'Cove Customer UID' (i.e. 9696c2af4-678a-4727-9b6b-fc1a217e38ec), 'Set Backup Profile (true/false)' (true), 'Backup Profile Name' (Case Sensitive Profile Name), 'Set Backup Product (true/false)' (true), and 'Backup Product Name' (All-In). Below the dialog is a link to 'Click here for help setting up the Automated Tasks'. To the right of the dialog, there are two tabs: 'Search Servers' and 'All Servers'. The 'Search Servers' tab shows a list of servers with columns for Agent Version (v10.13.0 for most, v10.13.0 for one), Action (Edit, Delete, Refresh), and Status (OK, OK, OK, OK, OK, OK, OK, OK). The 'All Servers' tab shows a list of tasks with columns for Task Name, Date/Time, and Assigned Tasks. The bottom right corner of the interface has a footer: 'Manage, secure and protect all things IT'.

N-SIGHT

File Edit View Reports Settings Mail Templates Agent Remote Access Backup & Recovery External Links Community

7 / 71 7 / 27 13

Monitoring and Management

Search

Global SE Production / All Clients

- Africa Industries
- Asian Pacific Tech
- ATO Services
- European Software Services
- German Industrie
- Middle East Information Systems
- United Kingdom Tech
- AV ONLY
- Latin American Experts
- North American Technologies
- SouthAmerica

Add Task **Cove - Installation script**

Select Server Workstation

Descriptive Name: Cove - Deployment

Script Parameters

Set Archiving (true|false): false

Archive Day of Month: 1,15 or Last

Set Bandwidth (true|false): false

Throttle Start: 08:00

Throttle Stop: 17:00

[Click here for help setting up the Automated Tasks](#)

< Previous Next > Cancel

Managed Antivirus ... More information

Displaying 1 - 6 of 6

Antivirus Web Alert Columns

Information	Date/Time	Assigned Tasks
ccessful...	09-Dec-2022 06:00	
found	09-Dec-2022 06:00	
found	09-Dec-2022 06:00	
found	09-Dec-2022 06:00	
45 GB, F...	09-Dec-2022 14:08	
45 GB, F...	09-Dec-2022 06:00	
ogins	09-Dec-2022 06:00	
	09-Dec-2022 14:21	

Manage, secure and protect all things IT

N-SIGHT

File Edit View Reports Settings Mail Templates Agent Remote Access Backup & Recovery External Links Community

7 / 71 7 / 27 13

Monitoring and Management

Search

Global SE Production / All Clients

- Africa Industries
- Asian Pacific Tech
- ATO Services
- European Software Services
- German Industrie
- Middle East Information Systems
- United Kingdom Tech
- AV ONLY
- Latin American Experts
- North American Technologies
- SouthAmerica

Add Task **Cove - Installation script**

Select Server Workstation

Descriptive Name: Cove - Deployment

Script Parameters

08:00

Throttle Stop: 17:00

Unlimited Weekends (true|false): false

Upload Kbps: 5120

Download Kbps: Unlimited

[Click here for help setting up the Automated Tasks](#)

< Previous Next > Cancel

Managed Antivirus ... More information

Displaying 1 - 6 of 6

Antivirus Web Alert Columns

Information	Date/Time	Assigned Tasks
ccessful...	09-Dec-2022 06:00	
found	09-Dec-2022 06:00	
found	09-Dec-2022 06:00	
found	09-Dec-2022 06:00	
45 GB, F...	09-Dec-2022 14:08	
45 GB, F...	09-Dec-2022 06:00	
ogins	09-Dec-2022 06:00	
	09-Dec-2022 14:21	

Manage, secure and protect all things IT

STEP 8: SELECT TASK FREQUENCY

Change the Frequency method dropdown to Manual.

The screenshot shows the N-SIGHT application interface. On the left, there's a sidebar with various icons and a main menu bar with options like File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. A purple ribbon-like bar at the top left says 'N-SIGHT'. In the center, a modal window titled 'Cove - Installation script' is open. Inside the modal, there's a dropdown menu labeled 'Select' with 'Manual' selected under 'Frequency Method'. Below this, there are two checked checkboxes: 'Server' and 'Workstation'. At the bottom of the modal, there's a link 'Click here for help setting up the Automated Tasks' and three buttons: '< Previous', 'Next >', and 'Cancel'. To the right of the modal, there's a sidebar with a search bar and a table titled 'Search Servers' showing results for 'All Servers'. The table includes columns for 'Name', 'Agent Version', and 'Last Scan'. There are six rows listed, all showing 'v10.13.0' in the 'Agent Version' column and '2022-12-09' in the 'Last Scan' column. The sidebar also includes tabs for 'Antivirus' and 'Web' and a section for 'Alert Columns'. At the bottom right of the screen, there's a footer bar with the text 'Manage, secure and protect all things IT'.

STEP 9: TASK OPTIONS

Deselect the Set permissions permitted execution time checkbox.

The screenshot shows the N-SIGHT software interface. On the left, there's a sidebar with various icons and a search bar. The main menu at the top includes File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. On the right, there are status indicators for 7/71, 7/27, and 13. Below the menu, a table lists servers with their agent versions: Global SE Production / All Clients (v10.13.0), EL (v10.13.0), tor (v10.13.0), cancel (v10.13.0), Administrator (v10.13.0), and Administrator (v10.13.0). A modal window titled 'Add Task' is open, showing 'Cove - Installation script'. It has sections for 'Select' (with checkboxes for Server and Workstation) and 'Options' (with an unchecked checkbox for 'Set maximum permitted execution time'). A 'Disclaimer' section cautions users about the responsibility for user-defined script contents. At the bottom of the modal, there's a link 'Click here for help setting up the Automated Tasks' and navigation buttons (< Previous, Next >, Cancel). The footer of the application reads 'Manage, secure and protect all things IT'.

STEP 10: SELECT DEVICES FOR TASK

If you have selected a site or client with multiple devices, you are being prompted with a pop-up where you can select or deselect the devices you want to run the task. Please select the right device(s) and click Add Task.

The screenshot shows the N-SIGHT software interface. On the left is a sidebar with various icons and a search bar. The main menu bar includes File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. A top right corner displays statistics: 7 / 71, 7 / 27, and 13. The central area is titled "Monitoring and Management" and contains a tree view under "Global SE Production / All Clients". The tree shows "Africa Industries", "Asian Pacific Tech", "ATO Services", "European Software Services", "German Industrie", "Middle East Information", "United Kingdom Tech", "AV ONLY", "Latin American Experts", "North American Technolo", and "SouthAmerica". A modal dialog box titled "Add Task Device Confirmation" is open, prompting the user to "Confirm which devices you want to apply the Add Task Update to:". It lists eight devices in a table:

	Client	Site	Name	Description
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	2008R2-MEL	2008R2-MEL
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	2012R-DEL	Administrator
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	2016-NRT	2016-NRT
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	2016-SZX	Administrator
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	2016-XMN	2016-XMN
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	2019-BOM	Administrator
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	10-CTU	SEDEMO
<input checked="" type="checkbox"/>	Asian Pacific Tech	HQ	10-MNL	SEDEMO

At the bottom of the dialog are "Add Task" and "Cancel" buttons. Below the dialog, there are several small icons and status messages: Managed Antivirus ..., More information, 09-Dec-2022 14:21, and Manage, secure and protect all things IT. To the right of the dialog, there is a sidebar with sections for Servers, Alert Columns, and Assigned Tasks, along with a list of dates from 06:00 to 14:08.

STEP 11: WAIT FOR THE TASK TO BE CREATED

After you've added the task, it can take up to one minute before the task shows up in the N-sight dashboard under the devices it's added to. Since the task is created as manual, please proceed to step 12 for execution.

The screenshot shows the N-SIGHT monitoring interface. On the left, there's a sidebar with various icons and a search bar. The main area is titled "Monitoring and Management" and has tabs for "Servers", "Workstations", "Mixed", "Mobile Devices", "Network Devices", and "Networks". A "Search" field is present above the server list. The server list table has columns for Client, Site, Server, Description, Agent Version, and several action icons. Below the table, it says "Displaying 1 - 6 of 6". At the bottom, there's a table for "Tasks" with columns for Description, Status, Output, Last Run Time, Schedule, and Assigned Check. One task is listed: "Cove - Installation sc! Stopped" with status "Awaiting first run".

Client	Site	Server	Description	Agent Version
Asian Pacific Tech	HQ	2012R-DEL	Administrator	v10.13.0
Asian Pacific Tech	HQ	2008R2-MEL	2008R2-MEL	v10.13.0
Asian Pacific Tech	HQ	2016-NRT	2016-NRT	v10.13.0
Asian Pacific Tech	HQ	2016-SZX	Administrator	v10.13.0
Asian Pacific Tech	HQ	2016-XMN	2016-XMN	v10.13.0
Asian Pacific Tech	HQ	2019-BOM	Administrator	v10.13.0

Description	Status	Output	Last Run Time	Schedule	Assigned Check
Cove - Installation sc!	Stopped	Awaiting first run	Has not run	Manual	

STEP 12: RUN THE AUTOMATED TASK

Select the task and right click on it. Select Run Automated Task. At that moment the device is going to download the Cove Backup Manager to a local temp folder and will be executed with the extra parameters provided in the task creation. Depending on the download speed, this process should take a few mins. The download is a little under 100MB, so it should not take very long.

The screenshot shows the N-SIGHT monitoring interface. On the left is a sidebar with various icons. The main area has a title bar 'N-SIGHT' and a navigation bar with links like File, Edit, View, Reports, Settings, Mail Templates, Agent, Remote Access, Backup & Recovery, External Links, and Community. There are also status indicators for 7/71, 7/27, and 13. Below the navigation is a search bar and a 'Monitoring and Management' section titled 'Global SE Production / All Clients'. This section lists several client groups: Africa Industries, Asian Pacific Tech (which is selected), ATO Services, European Software Services, German Industrie, Middle East Information Systems, United Kingdom Tech, AV ONLY, Latin American Experts, North American Technologies, and SouthAmerica. To the right of this is a table of servers, showing columns for Client, Site, Server, Description, Agent Version, and various action icons. The table lists six entries for 'Asian Pacific Tech' with HQ locations. Below the table is a pagination bar showing 'Page 1 of 1' and 'Displaying 1 - 6 of 6'. At the bottom of the interface is a footer with links for Summary, Outages, Checks, Notes, Tasks, Assets, Patches, Antivirus, and Web, along with a 'Run Automated Task' button and a context menu with options: Run Automated Task, Edit Automated Task, and Delete Automated Task. The URL 'https://www.systemmonitor.co.uk/dashboard/#' is visible at the bottom left, and the tagline 'Manage, secure and protect all things IT' is at the bottom right.

STEP 13: CHECK INSTALLATION STATUS

In the N-sight dashboard, a green check with the mouse over **Active (Cove Data Protection)** should appear in the grid with checks in the column Backup & Recovery. When this message appears, the software is correctly installed and is visible in your backup portal through <https://backup.management>.

The screenshot shows the N-sight Monitoring and Management interface. On the left, there's a sidebar with various icons. The main area has a title bar "Monitoring and Management". Below it, a search bar and a tree view titled "Global SE Production / All Clients" are shown. The tree view lists several regions and their headquarters: Africa Industries, Asian Pacific Tech, ATO Services, European Software Services, German Industrie, Middle East Information Systems, United Kingdom Tech, AV ONLY, Latin American Experts, North American Technologies, and South America. The main content area displays a table of servers. The columns are Client, Site, Server, Description, Agent Version, and several status icons. One server entry for "Asian Pacific Tech HQ" is highlighted with a yellow background and has a tooltip "Active (Cove Data Protection)" over its status icon. At the bottom of the table, it says "Displaying 1 - 50 of 71". Below the table, there are tabs for Summary, Outages, Checks, Notes, Tasks, Assets, Patches, Antivirus, and Web. Under the Tasks tab, there's a section for "Automated Task" with one item listed: "Cove - Installation scri Stopped" with status "Awaiting first run", "Has not run", and "Manual". The footer of the interface includes the text "Manage, secure and protect all things IT".

STEP 14: (OPTIONAL) ADJUST DEFAULT VALUES POLICY – INSTALL AUTOMATION MANAGER

You can manually adjust the default values in the automation policy by editing the file in Automation Manager. If you don't have the Automation Manager installed, login to your N-sight dashboard, click on Settings and select Script Manager.


Device	Type	Site	Server	Description	Agent Version
European Software...	HQ	BROWN	Administrator	v10.13.0	
ATO Services	Client X	LAB-SCOM-V1801	Administrator - ...	v10.13.0	
Asian Pacific Tech	HQ	2012R-DEL	Administrator	v10.13.0	
Middle East Info...	HQ	2022-DOK	Administrator	v10.13.0	
United Kingdom Tech	ESXi	2022-GCT	Administrator	v10.13.1	
United Kingdom Tech	Emmeloord- Th...	2016-FRA	Administrator	v10.13.0	
United Kingdom Tech	HQ	2010-SHA	Administrator	v10.13.0	

You can download the Automation Manager through the button in the top right, in the Script Manager popup screen.


OS	Name	Description	Usage Notes	Script ...	Auto...	Type
Windows	Check file sizes of loca...			Yes	No	ps1
Windows	EDR install script			No	Yes	ps1
Windows	**Registry test for HK...			No	Yes	amp
Windows	**COPY**			No	Yes	bat
Windows	**SSL certificates**			Yes	No	amp
Windows	Uninstall SWI Backup			No	Yes	bat
Windows	**migration**			Yes	Yes	ps1
Windows	C:\Data removal			No	Yes	bat
Windows	reinstall N-central agent fix for problem devices			No	Yes	ps1
Windows	ncentral agent install			No	Yes	ps1
Windows	**install software**			No	Yes	ps1

STEP 15: (OPTIONAL) ADJUST DEFAULT VALUES POLICY – CHANGE INPUT SETTINGS


After installing the Automation Manager, you can start the Automation Manager and open the Cove Data Protection Agent Deploy .amp file you received by selecting the Open policy option.




When you opened the automation policy, you can click on the blue INPUT button in the top.



You can select one of the lines you would like to edit. Click on the EDIT button to open the edit screen.



In the Edit Input Parameter, you can change the values for the **Value:** line. Editing the Customer UID is only advised if you would enter the top level reseller UID. With that configuration, all devices will be created directly under the reseller level. You can move the devices after installation to the correct end user.



Editing the Profile, Product, Archive and Bandwidth throttling to your company default settings will improve and simplify the deployment. If you work with multiple service levels, you could create separate automation policies with the right Profile/Product/Archive/Throttling settings. Save the different options as separate automation policies and import all policies under a unique name in N-sight. From that point on the deployment for multiple service levels is even easier and quicker.

SUMMARY

After finalizing this guide, you've uploaded the Automation Policy, created a task for a Client, Site or Device and executed the automatic deployment and configuration. In the N-sight dashboard, a daily check for the Backups is also added.

We advise to use the portal at <https://backup.management> for further configuration changes, such as fine tuning the profiles. For daily management we also advice to use that portal, it gives you a highly detailed view of all of your backups and (automated) restores in one view. If you'd like additional help in setting that up, please reach out to us.