CFLIB - Flexible Configuration Library Patchlevel 21

Generated by Doxygen 1.8.0

Wed Feb 27 2013 14:19:51

CONTENTS

Contents

1	CFL	IB Documentation	1
	1.1	Introduction and General Issues	1
	1.2	Basic Usage	1
	1.3	Retrieval Functions	2
	1.4	Setting Parameters and Saving the Configuration	2
	1.5	General Utilities	3
	1.6	Advanced Usage	3
		1.6.1 Error Handling	3
		1.6.2 Report Generation	3
		1.6.3 Configuration Debugging	3
		1.6.4 Get Information About a Configuration Parameter:	3
		1.6.5 Other Functions and Features	3
	1.7	Compilation and Development Issues	3
	1.8	Help and Support	4
2	CFL	IB License	4
3	Purp	pose of CFLIB	7
4	Gen	eral Notes	7
	4.1	The names "CFLIB", "libcf", "*cf*"	7
	4.2	Input and Output	7
	4.3	General (future) tasks	7
	4.4	Other general issues	8
5	Sim	ple Usage Example	8
6	Con	figuration Initializer	8
	6.1	Parameter Name	9
	6.2	Parameter Default Value	9
	6.3	Commandline Option for Parameter	9
	6.4	Special Option Flags Mask for Parameter	9
7	Con	figuration Parsing Levels and Source/Origin Options	10
	7.1	Origin Window	10
	7.2	Parsing Levels	10
	7.3	Parsing Levels in the Initialization Process	10
		7.3.1 Parsing Level Priorities	11
	7.4	Parsing of Configuration Files	11
	7.5	Residual Items	12

CONTENTS

8	Con	figuration Files	12
	8.1	Configuration File Format	12
	8.2	Reading Configuration Files	13
	8.3	Writing a (private) Configuration File	13
9	Туре	es of Parameters	13
	9.1	Parameter Data Types	13
	9.2	Special Processing Instructions	13
	9.3	Special Handling Instructions	14
	9.4	CFLIB Parameters	14
	9.5	FLAG Parameter Type	14
10	Adva	anced Usage Example	15
11	Com	pilation and Development	16
	11.1	Library Versions	16
	11.2	Platforms	16
	11.3	Building the Library	17
	11.4	Binaries and Executables	17
	11.5	Minimal CFLIB Replacement	17
	11.6	System and Compiler dependent Defines	17
12	Todo	D List	18
	Todo		18 19
13	Bug		
13	Bug	List	19
13 14	Bug Mod 14.1	List ule Index	19 19
13 14	Mod 14.1 Data	List ule Index Modules	19 19 19
13 14 15	Mod 14.1 Data 15.1	List ule Index Modules	19 19 19
13 14 15	Bug Mod 14.1 Data 15.1	List ule Index Modules	19 19 19
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1	List ule Index Modules	19 19 19 19
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1 Mod	List ule Index Modules Structure Index Data Structures Index File List	19 19 19 19 19
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1 Mod	List ule Index Modules Structure Index Data Structures Index File List ule Documentation	19 19 19 19 19 19 20
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1 Mod 17.1	List ule Index Modules Structure Index Data Structures Index File List ule Documentation Flexible Configuration Library	19 19 19 19 19 20
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1 Mod 17.1	List ule Index Modules Structure Index Data Structures Index File List ule Documentation Flexible Configuration Library 17.1.1 Detailed Description	19 19 19 19 19 20 20
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1 Mod 17.1	List ule Index Modules Structure Index Data Structures Index File List ule Documentation Flexible Configuration Library 17.1.1 Detailed Description Core Features	19 19 19 19 19 20 20 22
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1 Mod 17.1	List ule Index Modules Structure Index Data Structures Index File List ule Documentation Flexible Configuration Library 17.1.1 Detailed Description Core Features 17.2.1 Detailed Description	19 19 19 19 19 20 20 22 23
13 14 15	Bug Mod 14.1 Data 15.1 File 16.1 Mod 17.1	List ule Index Modules Structure Index Data Structures Index File List ule Documentation Flexible Configuration Library 17.1.1 Detailed Description Core Features 17.2.1 Detailed Description 17.2.2 Define Documentation	19 19 19 19 19 20 20 22 23 23

1 CFLIB Documentation 1

		17.3.2 Function Documentation	26
	17.4	General Utilities	28
		17.4.1 Detailed Description	28
		17.4.2 Function Documentation	28
	17.5	Special Options Mask	31
		17.5.1 Detailed Description	32
	17.6	Error Handling	33
		17.6.1 Detailed Description	35
		17.6.2 Function Documentation	35
	17.7	Advanced Features	37
		17.7.1 Detailed Description	37
		17.7.2 Function Documentation	37
	17.8	Information Retrieval	39
		17.8.1 Detailed Description	39
		17.8.2 Define Documentation	39
		17.8.3 Function Documentation	42
	17.9	Setting and Saving the Configuration	45
		17.9.1 Detailed Description	45
		17.9.2 Define Documentation	45
		17.9.3 Function Documentation	45
18	Data	Structure Documentation	48
	18.1	CONFERR Struct Reference	48
		18.1.1 Detailed Description	48
	18.2	CONFIG Struct Reference	48
		18.2.1 Detailed Description	48
19	File I	Documentation	48
	19.1	include/cf.h File Reference	48
		19.1.1 Detailed Description	55

1 **CFLIB Documentation**

1.1 Introduction and General Issues

CFLIB is a small, simple, flexible and portable ANSI C Library to be used as configuration interface for user programs. CFLIB builds and maintains a compact database structure consisting of a list of parameters with their name, content and some additional information about each parameter.

CFLIB targets the basic needs of technical, scientific or other programmers who want to spend minimal time on coding input, output, variable parsing, report generation and the like but still have a simple to use, reliable, flexible and portable configuration interface for their programs.

1.2 Basic Usage 2

Main Features:

- · Commandline, environment and terminal input parsing
 - Configuration files
 - File search
 - Template driven report generation
 - Automatic time and date update

See also

- · Purpose of CFLIB
- CFLIB License
- The names "CFLIB", "libcf", "*cf*"
- General Notes

Project Homepage:

• http://cflib.berlios.de

1.2 Basic Usage

- 1. Include cf.h
- 1. Define the Configuration Initializer, an array of CONFIG structures
- Call cfinit() with Configuration Initializer and Commandline. The most compact initialization is done by cfstart(), a wrapper function for cfinit() that includes error reporting, usage message and (optional) debugging output. On initialization the following data sources are inspected or parsed in the order presented:
- Commandline Arguments (or compatible structure given to cfinit()) according to the description in Commandline Option for Parameter
 - Environment Variables
 - Configuration Files
 - Built-in User-defined Default from Configuration Initializer: Parameter Default Value
 - Get parameter value from Standard Input stdin, if required
- 1. Use the Retrieval Functions cfget*() to access configuration parameters
- Compile your program, linking the appropriate CFLIB library file for your platform and setup, usually the file name is *libcf.a* which means the library is referred to as "cf". You can change the names to fit into your setup: See The names "CFLIB", "libcf", "*cf*"
- 1. Run your program, test CFLIB functionality and adjust the Configuration Initializer according to your needs

See also

Simple Usage Example Configuration Parsing Levels and Source/Origin Options Core Features 1.3 Retrieval Functions 3

1.3 Retrieval Functions

- 1. Get CFLIB Version and Copyright Information: cfgetvers(), cfgetsubvers(), cfgetcpr()
- 1. Get Usage Message for Output: cfgetusg()
- 1. Get Configuration Parameter Value:
- Get parameter value: cfget(), interpretation of content and return type depend on the type setting in the parameter's Special Options Mask

Get string value: cfgetstr()
Get integer value: cfgetnum()
Get real/float value: cfgetreal()
Inquire flag/switch status: cfgetflag()

- Get value of (next) residual command line argument: cfgetres()

Note

All of these functions except cfgetres() require the parameter name as argument

1.4 Setting Parameters and Saving the Configuration

- cfput(): Update or Add a Parameter.
- cfputstr(): cfputstr() Update or Add Parameter name with string content
- cfputtime(): cfputtime() Set all Time and/or Date entries in CFLIB DB to now or today
- cfnosave(): cfnosave() Alter or query the CF NOSAVE Flag of Parameter name
- cfsave(): cfsave() Write configuration data to a Configuration File or stdout
- · See Configuration Files for details

1.5 General Utilities

These functions and Macros are used in the library but do not depend on the configuration database or any cf*() functions. They are (small) general tools that you can use in your program if you like.

• String Manipulation: EatWhiteSpace(), RemoveCR(), RemoveTrailSpace()

File Utilities: FindFile(), BackupFile()

- Other Tools: IsATerminal(), DelFlag(), SetFlag()

1.6 Advanced Usage

1.6.1 Error Handling

CFLIB maintains a simple global Error Stack that is used by library functions like cfinit() when multiple errors can occur. Error Items consist of a numeric Error Code and (optionally) an Error Message string. Repeated calls to cfgeterr() will successively return error entries while deleting them from the stack until the list is empty. User programs may also use the CFLIB error stack by calling cfputerr() without the need to initialize a configuration.

For more details see: Error Handling - Error Codes, Functions and Structures.

1.6.2 Report Generation

Generate Output from Template and current parameter values: cfform()

1.6.3 Configuration Debugging

These functions are thought to be used by the programmer working with CFLIB during development and testing of a program.

- Dump Configuration DB in human readable form: cfdump()
 - Test and Dump Configuration Initializer: cfdinichk()

1.6.4 Get Information About a Configuration Parameter:

- Get source/origin of the parameter's value: cfgetsrc()
- Inquire Bit from parameter's Special Options Mask by Offset: cfflaginq()

1.6.5 Other Functions and Features

- Exit Configuration: cfexit()
- Expand User Home Directory in a File Path Parameter: cfhomexp()
- General (internal) retrieval function: cfgetent()

1.7 Compilation and Development Issues

- Platforms
- Binaries and Executables
- · Building the Library
- · System and Compiler dependent Defines
- · Minimal CFLIB Replacement

1.8 Help and Support

- · Help is this documentation
- Support is the (open) source code
- The project is maintained from time to time as needed ;-)
- Comments, Bug Reports or (better) Bug Fixes are welcome!
- See CFLIB License
- · ... Have Fun!

2 CFLIB License 5

2 CFLIB License

This file is part of **CFLIB** - Flexible Configuration Library.

Author

Stefan Habermehl stefan.habermehl@mcff.de

Copyright:

(c) 1994,1995,1996,1997,1998,2006,2007,2008,2009,2013 Stefan Habermehl

CFLIB is free software: you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version

CFLIB is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with CFLIB (see LICENSE.txt). If not, see http://www.gnu.org/licenses/.

GNU LESSER GENERAL PUBLIC LICENSE Version 3, 29 June 2007

Copyright (C) 2007 Free Software Foundation, Inc. http://fsf.org/
Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

This version of the GNU Lesser General Public License incorporates the terms and conditions of version 3 of the GNU General Public License, supplemented by the additional permissions listed below.

0. Additional Definitions.

As used herein, "this License" refers to version 3 of the GNU Lesser General Public License, and the "GNU GPL" refers to version 3 of the GNU General Public License.

"The Library" refers to a covered work governed by this License, other than an Application or a Combined Work as defined below.

An "Application" is any work that makes use of an interface provided by the Library, but which is not otherwise based on the Library. Defining a subclass of a class defined by the Library is deemed a mode of using an interface provided by the Library.

A "Combined Work" is a work produced by combining or linking an Application with the Library. The particular version of the Library with which the Combined Work was made is also called the "Linked Version".

The "Minimal Corresponding Source" for a Combined Work means the Corresponding Source for the Combined Work, excluding any source code for portions of the Combined Work that, considered in isolation, are based on the Application, and not on the Linked Version.

The "Corresponding Application Code" for a Combined Work means the object code and/or source code for the Application, including any data and utility programs needed for reproducing the Combined Work from the Application, but excluding the System Libraries of the Combined Work.

1. Exception to Section 3 of the GNU $\ensuremath{\mathtt{GPL}}.$

You may convey a covered work under sections 3 and 4 of this License without being bound by section 3 of the GNU GPL.

- 2. Conveying Modified Versions.
- If you modify a copy of the Library, and, in your modifications, a facility refers to a function or data to be supplied by an Application that uses the facility (other than as an argument passed when the facility is invoked), then you may convey a copy of the modified version:
 - a) under this License, provided that you make a good faith effort to ensure that, in the event an Application does not supply the function or data, the facility still operates, and performs whatever part of its purpose remains meaningful, or
 - b) under the GNU GPL, with none of the additional permissions of this License applicable to that copy.
 - 3. Object Code Incorporating Material from Library Header Files.

The object code form of an Application may incorporate material from a header file that is part of the Library. You may convey such object code under terms of your choice, provided that, if the incorporated material is not limited to numerical parameters, data structure layouts and accessors, or small macros, inline functions and templates (ten or fewer lines in length), you do both of the following:

- a) Give prominent notice with each copy of the object code that the Library is used in it and that the Library and its use are covered by this License.
- b) Accompany the object code with a copy of the GNU GPL and this license document.
- 4. Combined Works.

You may convey a Combined Work under terms of your choice that, taken together, effectively do not restrict modification of the portions of the Library contained in the Combined Work and reverse engineering for debugging such modifications, if you also do each of the following:

- a) Give prominent notice with each copy of the Combined Work that the Library is used in it and that the Library and its use are covered by this License.
- b) Accompany the Combined Work with a copy of the GNU GPL and this license document.
- c) For a Combined Work that displays copyright notices during execution, include the copyright notice for the Library among these notices, as well as a reference directing the user to the copies of the GNU GPL and this license document.
- d) Do one of the following:
 - O) Convey the Minimal Corresponding Source under the terms of this License, and the Corresponding Application Code in a form suitable for, and under terms that permit, the user to recombine or relink the Application with a modified version of the Linked Version to produce a modified Combined Work, in the manner specified by section 6 of the GNU GPL for conveying Corresponding Source.
 - 1) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (a) uses at run time a copy of the Library already present on the user's computer system, and (b) will operate properly with a modified version of the Library that is interface-compatible with the Linked Version.
- e) Provide Installation Information, but only if you would otherwise be required to provide such information under section 6 of the GNU GPL, and only to the extent that such information is necessary to install and execute a modified version of the

3 Purpose of CFLIB 7

Combined Work produced by recombining or relinking the Application with a modified version of the Linked Version. (If you use option 4d0, the Installation Information must accompany the Minimal Corresponding Source and Corresponding Application Code. If you use option 4d1, you must provide the Installation Information in the manner specified by section 6 of the GNU GPL for conveying Corresponding Source.)

5. Combined Libraries.

You may place library facilities that are a work based on the Library side by side in a single library together with other library facilities that are not Applications and are not covered by this License, and convey such a combined library under terms of your choice, if you do both of the following:

- a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities, conveyed under the terms of this License.
- b) Give prominent notice with the combined library that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.
- 6. Revised Versions of the GNU Lesser General Public License.

The Free Software Foundation may publish revised and/or new versions of the GNU Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library as you received it specifies that a certain numbered version of the GNU Lesser General Public License "or any later version" applies to it, you have the option of following the terms and conditions either of that published version or of any later version published by the Free Software Foundation. If the Library as you received it does not specify a version number of the GNU Lesser General Public License, you may choose any version of the GNU Lesser General Public License ever published by the Free Software Foundation.

If the Library as you received it specifies that a proxy can decide whether future versions of the GNU Lesser General Public License shall apply, that proxy's public statement of acceptance of any version is permanent authorization for you to choose that version for the Library.

3 Purpose of CFLIB

This library started as a Beginner Project in "C Library Building" following practical needs arising from scientific/technical modeling projects.

Most of the library code has been created in 1994/95 on an Atari ST4/16 MHz under TOS 2.05/MiNT 1.12 with gcc 2.5.8 and the Mintlibs Patchlevel 46. The C coding is probably not the best possible ;-) but the source as well as the executable and allocated memory structures are very compact, simple to modify and still fine for many applications that need a stable, portable and small configuration interface.

'Mission Statement' from 1994/95 README file:

CFLIB is meant to be a flexible, sound and easy to use tool for C programmers. It provides a set of functions for a standard method for feeding a C program with all the (external) information it needs to perform as desired with a minimum of expense for both the programmer and the user: arguments, commands, program input, configurable and/or installation dependent features, system settings and a lot more can be passed to the program through different interfaces: command line, environment, configuration files or sections within them, interactive input and last but not least a built-in default. So it should be a fast and easy task for both the programmer and the user to build and change a configuration. The library will always take more space and perform slower than code that is written and optimized for a specific requirement, but this will only be a noticeable disadvantage in some

4 General Notes 8

cases. The library also provides some special features such as file search, time and date handling, generating simple, text template driven reports, etc. It is suitable for creating a comfortable and/or individual user interface for existing programs that don't have one. Some basic ideas for the library came from looking at the *termcap* library for easy and portable terminal I/O.

4 General Notes

4.1 The names "CFLIB", "libcf", "*cf*"

All "names" in this library source and documentation are nothing but technical acronyms just as "src", "inc", "C" and are **not** registered names, trademarks or anything like that ;-) You may change the names of the library, the include file and on compilation the function names and defines to whatever you like :-)

4.2 Input and Output

CFLIB is designed to be usable as a Filter program that reads from stdin and writes to stdout wherever it was desirable.

None of the library functions will produce any terminal output (to stdout or stderr) unless:

- The CF_QUERY flag is set in the Special Options Mask of an entry and the parameter value is still unassigned after parsing all other possible sources in cfinit().
- You call a function that reads from or writes to files with arguments that trigger the use of stdin, stdout, stderr etc. according to the function's documentation.

4.3 General (future) tasks

Todo Make proper Man Pages with function references etc.

Make Doxygen Developer Documentation

More Modularization! Still very similar code in various functions

See also

Bug List

4.4 Other general issues

Library Versions

5 Simple Usage Example

```
/*
  * Find a File in Path

*
  * Input: Commandline or Environment

*
  * Output: File path, Help message or Error message

*
  * Compile: gcc fifi.c -o fifi -lcf -L../../lib<platform>
  * Run: ./fifi -h
  * Test: ./fifi gcc
*/
```

```
#include <stdio.h>
#include "../../include/cf.h"
int main( int argc, char **argv )
   int ret; char *tmp;
   CONFIG setting[] =
        /* Name, Default Content, Commandline Option, Special Option Flags */
       { "PROGNAME", NULL, '1', CF_FINDFILE|CF_SET_ARG|CF_NO_OPT_ARG, }
       { "FF_PATH", NULL,
                                 '', CF_PATH,
       { "help", CF_FLAG_OFF, 'h', CF_FLAG|CF_LAST,
   } ;
   if ( !( ret = cfstart( setting, argc, argv, "help", CFS_USG ) ) ){
       if( (tmp = cfgetstr("PROGNAME") ) != NULL )
           fprintf( stdout, "%s\n", tmp );
   }
   return ret;
```

6 Configuration Initializer

The "Configuration Initializer" is the major interface between the user program and CFLIB.

It is an Array of CONFIG items, just as the CFLIB Configuration Database itself.

Every parameter is characterized by:

- Parameter Name (CONFIG::name)
- Parameter Default Value (CONFIG::inhalt)
- Commandline Option for Parameter (CONFIG::option)
- Special Option Flags Mask for Parameter (CONFIG::flag)

An example initializer may look like this:

The Configuration Initializer controls the behavior and actions of all **cf***() functions, starting with the control of Parsing Levels in the Initialization Process.

6.1 Parameter Name 10

6.1 Parameter Name

Every entry in the initializer must have a name, that is a non-empty string, which is searched for in the environment and in the configuration files and which is used as an argument to the inquiry functions. Parameters that have a name beginning with "CF_" may have special meaning, see CFLIB Parameters.

6.2 Parameter Default Value

As the default content of an entry you can specify a NULL pointer or a string, which may be empty. If CF_FLAG is set for that entry you should use the CF_FLAG_ON or CF_FLAG_OFF macros.

6.3 Commandline Option for Parameter

You can control whether and how an entry's content can be set from the Commandline by setting one of the following "Option Specifier" Characters (and Special Option Flags where indicated):

- " (blank)
 - No Commandline Option for this Parameter
- 'c' (c = any "normal" character)
 - Looks for '-c < string>' on the Commandline
 - Looks for '-c<string>' on the Commandline, if Flag CF CONCAT is set in the Special Options Mask
 - Looks for '-c<char>' on the Commandline, if Flag CF_FLAG is set in the Special Options Mask
- '#' (# = a positive number = 1, 2, 3, ...)
 - Looks for the 1st, 2nd, 3rd, ... '<string>' that is not part of an option, if Flag CF_NO_OPT_ARG is set in the Special Options Mask

6.4 Special Option Flags Mask for Parameter

Most of the magic happens here! ;-) The "Special Options Mask" is a Bitmask of type CFFLAGTYP in Configuration Entry Structure Member CONFIG::flag containing Type, Instruction and Information Flags for a Parameter. See Special Options Mask for details.

See also

Types of Parameters
Configuration Parsing Levels and Source/Origin Options

Attention

The last entry in the initializer list must have the CF_LAST Flag set!

7 Configuration Parsing Levels and Source/Origin Options

CFLIB is designed to give you a maximum of possibilities for feeding parameters and parameter values into the configuration.

7.1 Origin Window

7.1 Origin Window

The library remembers the source/origin of all parameter values by setting one of the "Source Flags" in the "-Origin Window" of the Special Options Mask ranging from Bit Offset 8 to 15 (see Parsing Levels). On initialization the Origin Window Flags CF_SET_* of an entry in the Configuration Initializer are used to control Parsing Level Priorities.

7.2 Parsing Levels

"Parsing Levels" are equal to the Relative Bit Offset of the corresponding CF_SET_* Bit within the "Origin Window":

Parsing Level: Description (Source Flag)

```
    0 = CFP_PUT : Function Call or Automatic Initialization. (CF_SET_PUT)
    1 = CFP_ARG : Commandline. (CF_SET_ARG)
    2 = CFP_ENV : Environment. (CF_SET_ENV)
    3 = CFP_PRIV : Private Configuration File. (CF_SET_PRIV)
    4 = CFP_SYS : System Configuration File. (CF_SET_SYS)
    5 : CFP_DEF : Built-in Default. (CF_SET_DEF)
    6 : CFP_QRY : Standard Input Channel. (CF_SET_QRY)
    7 : CFP_RESERVED : Reserved for CFLIB Subprojects
```

7.3 Parsing Levels in the Initialization Process

On initialization the Parsing Levels 1 through 6 are processed by cfinit() in that order and priority. If a Parameter is found that has been defined in the Configuration Initializer, its content is included as String Content of that parameter in the configuration database.

Whether and how the **Commandline** Arguments are used to get a parameter value depends on the **CONFIG**::option setting for that parameter and the Special Option Flags:

```
    CF_CONCAT : Argument is concatenated to option.
```

```
- CF_NO_OPT_ARG: Commandline argument not following an option.
```

See details under Commandline Option for Parameter.

The Environment can be excluded as a possible source of a parameter value by setting the Special Option Flag

• CF_IGN_ENV : Do not look for Environment Variable

Configuration Files are only used when corresponding entries are defined in the Configuration Initializer, see Parsing of Configuration Files for details.

Interactive queries are not performed by default. If cfinit() shall ask the user for interactive input of items that are still unresolved after parsing all lower levels, you must set Special Option Flag:

CF_QUERY: Ask the user for unresolved item after configuration parsing.

If an entry may not be empty (NULL or string "") after initialization, you can have cfinit() produce an appropriate error by setting the Special Option Flag:

CF_MUST : Entry may not be empty (NULL or "")

7.3.1 Parsing Level Priorities

More precise control of parsing levels priorities and origin control for a parameter is available through setting one of the Flags in the "Origin Window" of the parameter's Special Options Mask in the Configuration Initializer:

- CF_SET_PUT: Must be set by a function call / automatic processing: Set this Flag on Time or Date Types of Parameters for automatic initialization with now or today
- CF SET ARG: Force initialization from commandline, ignore anything else
- CF_SET_ENV: Let environment variable override earlier setting
- CF SET PRIV: Let variable from private configuration file override earlier setting
- CF SET SYS: Let variable from system configuration file override earlier setting
- CF SET DEF: Let default from Configuration Initializer override earlier setting
- CF_SET_QRY: Force setting from interactive Query (stdin)

7.4 Parsing of Configuration Files

To indicate that an entry in the initializer list given to cfinit() represents the filename of one of the Configuration Files, set one of the following Flags for that parameter:

- CF_SETFILE : Entry is Private Configuration File.
 - CF_SYS_SETFILE: Entry is System Configuration File.

Within the system configuration file you can choose a section, from which information is read as from a single file. To specify an entry in the list referring to the name of that section give this entry the flag

CF_SECTION : Section in Configuration File.

As the filenames for the two configuration files are themselves entries in the database, these levels are revisited, if neccessary, in reverse order after parsing the built-in default.

7.5 Residual Items

Any commandline argument that did not match conditions for a parameter will be included in the configuration database as parameter without name marked with Flag CF_RESID in the Special Options Mask. These additional entries from the command line can be accessed by successive calls to cfgetres().

Residual items from one of the configuration files will also be accumulated in the database and can be accessed through inquiry by name with one of the Retrieval Functions. This is especially useful together with the report generation function cfform().

8 Configuration Files

A major task of the library is handling import and export of configuration parameters from/to files.

CFLIB knows two types of configuration files:

- "Private Configuration File" User and/or program specific file in simple format to be read on initialization and optionally be updated by cfsave()
- "System Configuration File" System and/or project specific file in extended format (supporting sections, see below) will only be used as a data source by cfinit() and will not be touched by cfsave() unless you explicitly specify the filename.

8.1 Configuration File Format

In a configuration file lines beginning with ' #' are treated as comments and are ignored. Blank lines are ignored, too. A valid line in the file is of the form:

```
<name> = <entry>
```

Blank chars around the '=' are ignored. The name must match one of the entry's names in the initializer. In fact, any line not containing a '=' will be ignored, but it's better to indicate comments with ' #'!

The optional sections in the system configuration file begin with a line like:

```
[<sectionname>]
```

and end with another line like this or with the file's last line. Anything after the closing bracket is ignored.

A simple example of a valid configuration file could look like this:

```
# This is my private configuration file for Project 1356 Branch C in spe
Search_Path = /my/subproject/directory:/general/settings/directory
Section = project_1356
Outfile = my_subproject.cnf
ask_if_empty =
My_Flag = ON
VERBOSITY = 1
```

The corresponding system configuration file could look like this:

```
# This is a system wide configuration file
[some_other_program]
blah = blubber
...
[project_1356]
# Settings for Project 1356 Branch B
VERBOSITY = 3
Outfile = project_1356b.cnf
X_EUR_USD=1.4562
[some_other_project]
...
```

8.2 Reading Configuration Files

A search for configuration files and import of data from these sources is only performed by the function cfinit() on initialization and only when appropriate Special Option Flags are set as described under Parsing of Configuration Files.

Configuration files are read once when the configuration database is initialized by a call to cfinit() or cfstart() using the internal function cfreadfile().

8.3 Writing a (private) Configuration File

Parameter export does not depend on any specific setting and can be performed whenever and as often as you like. For writing a configuration file call cfsave() with either the name of the file or NULL, in which case the current value of the "Private Configuration File" parameter will be used, if it exists. If an entry has the CF_NOSAVE flag set, it is excluded from saving. The "System Configuration File" may not be referred to directly.

9 Types of Parameters 14

Attention

Writing section marks is not supported!

9 Types of Parameters

The internal format of a parameter's content CONFIG::inhalt is always a String (char Pointer).

The use and interpretation of parameters is controlled by a number of Flags in the Special Options Mask:

9.1 Parameter Data Types

```
CF_STR : Entry is String. (Default).CF_INT : Entry is Integer.
```

• CF_REAL : Entry is Float.

CF_FLAG : FLAG Parameter Type

9.2 Special Processing Instructions

Specific processing of a String Parameter's Value/Content in various CFLIB functions can be triggered by these Flags:

You can mark a parameter as Time **or** Date. These parameters will be initialized with *now* or *today* by cfinit() when Parsing Level Priorities are controlled by a CF_SET_PUT Flag in the Special Options Mask or on call of cfputtime():

```
CF_TIME : Time string.CF_DATE : Date string.
```

• CF_FINDFILE: Entry is filename to be searched for in the path. FindFile() will be used on initialization to search the file in the **path** found in Environment Variable **PATH**. You can specify an alternative search path for this functionality in another database parameter with Flag CF_PATH set in the corresponding Configuration Initializer entry. Depending on the Operating System a list of possible of **extensions** of executables will be tried, if no extension is given with the filename:

```
Linux, Unix: "sh", "pl"DOS, Windows, OS2: "exe", "com", "bat", "cmd"TOS, MinT: "ttp", "tos", "prg", "app", "gtp"
```

• CF_EXPHOME : Expand Home Directory. See cfhomexp(). Configuration Files will have home directory expanded by default

9.3 Special Handling Instructions

A parameter can be marked as a "volatile" entry that is not saved by cfsave():

• CF_NOSAVE : Don't include in savefile / mark entry.

9.4 CFLIB Parameters 15

9.4 CFLIB Parameters

Some String Parameters in the configuration database are used by the library itself and are marked by one of the following Flags:

CF_PRGNAME: Running Program's Name from commandline. This parameter always exists as the first
entry in a configuration database successfully initialized by cfinit(). The default parameter name used if there
was no corresponding entry in the Initializer is "CF_PRGNAME".

```
    CF_SETFILE: Entry is Private Configuration File. See Configuration Files
    CF_SYS_SETFILE: Entry is System Configuration File. See Configuration Files
    CF_SECTION: Section in Configuration File. See Configuration Files
    CF_PATH: Search Path (for FindFile feature) See CF_FINDFILE and FindFile()
    CF_USAGE: Usage Message format string. See cfgetusg()
```

Optional Parameters for fine tuning CFLIB behavior without Special Option Flag, characterized by Parameter Name:

• "CF_DUMPVERB" - Non-Default Verbosity Mode for cfdump()

9.5 FLAG Parameter Type

The entry is treated like a boolean variable and the string content set from any of the Configuration Parsing Levels and Source/Origin Options except the default setting is interpreted as follows:

```
CF_FLAG_OFF: String Content is:
beginning with a '-'
"OFF" or "off"
"FALSE" or "false"
CF FLAG ON: any other case
```

Example:

- Initializer entry: { "extended_message", CF_FLAG_OFF, 'x', CF_FLAG, }
- · Commandline: myprog -x-
- Configuration file: extended_message = OFF

10 Advanced Usage Example

Setup Configuration Initializer, generate Report and save Configuration Files

```
#include "../../include/cf.h"
#define DEF_SETFILE "~/fill.cnf"
#define DEF_SYS_SETFILE "/etc/cfcommon.cnf"
int main( int argc, char **argv )
    int ecode;
   char *save, *infile, *outfile, line[CF_MAXERRSTR+1];
    char *savemode = "w";
   FILE *error_log = stderr;
    /* Hardcoded Configuration Setup and Defaults */
    CONFIG setting[] =
    { "FILL_INFILE",
                           NULL,
                                             'i', 0x0,
                                                                               }
        { "FILL_OUTFILE", NULL,
                                             'o', 0x0,
                                             'l', CF_CONCAT,
        { "FILL_VARDELIM", "$()",
                                             'v', CF_IGN_ENV|CF_FLAG,
        { "verb",
                          CF_FLAG_OFF,
        { "help",
                           CF_FLAG_OFF,
                                             'h', CF_IGN_ENV|CF_FLAG|CF_NOSAVE,
        { "query",
                           CF_FLAG_OFF,
                                             'q', CF_IGN_ENV|CF_FLAG,
                                             't', CF_TIME|CF_SET_PUT,
        { "TIME",
                           NULL,
                                                                               }
        { "DATE".
                                             'd', CF_DATE|CF_SET_PUT,
                           NULL
                                                                               }
        { "FILL_CNF",
                           DEF_SETFILE,
                                             'p', CF_SETFILE,
        { "FILL_SAVE",
                           NULL,
                                             's', CF_IGN_ENV|CF_CONCAT,
        { "SAVE_DATA",
                           CF_FLAG_OFF,
                                             'x', CF_FLAG|CF_IGN_ENV,
                           DEF_SYS_SETFILE, '', CF_SYS_SETFILE,
        { "SFILE".
        { "FILL_SECTION", "fill_default",
                                             'c', CF_SECTION|CF_LAST,
    };
    /* Initialize with Error Reporting */
    if( cfinit(setting,argc,argv) < 0 ){</pre>
       while( (ecode=cfgeterr(line, 0)) == TRUE )
           fprintf( error_log, "error %d: %s", ecode, line );
        fflush(error_log);
        fputs( cfgetusg(), stderr );
        return (-1);
    }
    /* User Help and Configuration Overview */
    if( cfgetflag("help") ){
        fputs( cfgetusg(), stderr );
        if( cfgetflag("verbose") ){
            fprintf( stderr, "\nConfiguration Library PL %d - %s\n\nCurrent
       Configuration:\n\n",
                             cfgetvers(), cfgetcpr() );
            cfdump(stderr);
           fputs( "\nSources: 1=update function call, 2=commandline argument,
       4=environment variable,\n", stderr );
            fputs ( " 8=private setfile, 10=system setfile,
       20=built-in default, 40=interactive terminal input\n", stderr );
        return (1);
    }
        cfform( infile = cfgetstr("FILL_INFILE"),
                outfile = cfgetstr("FILL_OUTFILE"),
                cfgetstr("FILL_VARDELIM"),
                cfgetflag("query") )
   ) {
```

```
case CFE_FNF:
           fprintf(stderr, "read access error: %s\n", infile); break;
        case CFE_WAE:
            fprintf(stderr, "write access error: %s\n", outfile); break;
   }
   if( cfgetflag("verb") ){
        if( outfile == NULL ) outfile = "<stdout>";
        fprintf( stderr, "blank form: %s, filled form: %s\n", infile, outfile )
     ;
   if( cfgetflag("SAVE_DATA") ){
        cfnosave(NULL, CF_FLAG_ON);
       cfnosave("TIME", CF_FLAG_OFF);
       cfnosave("DATE", CF_FLAG_OFF);
   if( (save = cfgetstr("FILL_SAVE")) != NULL ) {
        if( cfgetflag("SAVE_DATA") ) savemode = "a";
        if( \starsave == ' \setminus 0' )
            cfsave( NULL, savemode );
        else if( *save == '+' )
           cfsave( "", savemode );
        else
            cfsave( save, savemode );
   }
   return (0);
}
```

11 Compilation and Development

11.1 Library Versions

There is no strict versioning of the library. A Library "Patchlevel" is defined as an Integer Number counting "Major Versions". See cfgetvers().

The individual source files contain more detailed version information and they all support a file version identifier \$Id\$ for automatic update by SVN and other Source Management Tools. See cfgetsubvers().

11.2 Platforms

The library source code is fairly simple ANSI C code and should compile and link without problems on most platforms. Most of the development has been done with different versions of the "GNU C Compiler" gcc and related tools. All source modules compile free of errors and warnings with:

```
"gcc -pedantic -pedantic-errors -Wall -Werror -ansi ..."
```

So, if you have gcc, use it! Any other ANSI C compiler should also work, at least after minimal adaption to the library setup, see System and Compiler dependent Defines.

until now the library has been built and used under the following setups:

- · gcc, Linux, Intel PC
 - gcc, MinGW, MS Windows NT/XP, Intel PC
 - gcc, MinT/TOS Atari ST
 - cc, Unix, IBM AIX
 - cc, Unix, SGI
 - MSC, MS DOS/Windows Intel PC
 - MSC, OS/2 Intel PC

11.3 Building the Library

Compiling the source modules and building the library should be a "straight forward" task:

- Make all objects from C sources, including cf.h and cflib.h
- · Link the objects with ar or another tools to get a library executable

See also

Makefiles under CFLIB project tree and System and Compiler dependent Defines

11.4 Binaries and Executables

- The library project should be seen as "pure" source/text code on distribution. Compile a library executable with a C compiler of your choice with appropriate setup for your platform.
- Binary and executable versions of the library found in the project tree should be seen as examples that worked under one specific setup but have not been intensively tested and may even not be up to date. If it works for you, feel free to use them. If you build a library executable which is not too ;-) dependent on a specific setup, you can include it as example in the project tree.

11.5 Minimal CFLIB Replacement

In project directory *src/examples* you may find a source file *cf_minimal.c.* You can adapt this example to your need and include it in your C source list on compilation instead of linking the library executable. This makes user programs that use CFLIB functions independent of the library at the price of very reduced functionality, which may be desirable for specific executables or if you have problems with building the library on the target platform.

11.6 System and Compiler dependent Defines

The following Defines are used in the library source to decide whether to include certain header files and use certain functions or defines:

- _HAS_PWD : If defined, include <pwd.h> and make use of function getpwnam() in cfhomexp() to find a user's home directory
 - _HAS_ISATTY : If defined, use function isatty() to determine whether a stream is a terminal (for interactive query/input) in function IsATerminal()
 - _ HAS_LIMITS : If defined, include limits.h> and use PATH_MAX defined therein in function Find-File()

The following Defines can be used to control, which features or functions shall be excluded from the library build:

- _CF_NOFINDFILE : Function FindFile(), component findfile.c
 - _CF_NOSAVING : Functions cfsave() and BackupFile(), component cfwrite.c
 - _CF_NODEBUGGING: Functions cfdinichk() and cfdump(), component cfdebug.c

The following Defines can be used to switch on certain Debug Features:

- DEBUG_DINICHK: Debug cfdinichk()
 - DEBUG_ERROR : Debug cfputerr()

12 Todo List 19

- DEBUG_TIME : Debug cfputtime()
 DEBUG_NOSAVE : Debug cfsave()
 DEBUG_BACKUP : Debug BackupFile()
- DEBUG_FINDFILE : Debug FindFile() usage in cfinit()
- DEBUG_FORM : Debug cfform()

The following Defines can be used to switch on certain other Features:

- _PREFER_BACKSLASH: Prefer Backslash as Directory Separator in function FindFile()
 - _PATHSEP_SEMICOLON : Use Semicolon as Path Separator in function FindFile(), usually on systems
 where a ":" can appear in a directory path
 - _PATHSEP_COMMA: Test Comma as Alternative Path Separator in function FindFile()
 - _CF_RESID_FREE : Remove residual arguments after having read them all in cfgetent()?

The following Platform dependent Defines are used in the library code:

- unx
 - linux
 - atarist
 - MINT

12 Todo List

Global cfdinichk (CONFIG *set)

Make cfdinichk() work as reliable, complete tool with much more testing and Special Options Mask validation!

Global cfform (char *infile, char *outfile, char *vardelim, int mode)

Make cfform() work with buffers instead of files

Page General Notes

Make proper Man Pages with function references etc.

Make Doxygen Developer Documentation

More Modularization! Still very similar code in various functions

13 Bug List

Group errors

There are still errors without entry in error stack

Global IsATerminal (FILE *fp)

ANSI C doesn't have function isatty(), we always return TRUE

14 Module Index

14.1 Modules

Here is a list of all modules:

Flexible Configuration Library

15 Data Structure Index 20

	Core Features	22
	Report Generation	26
	General Utilities	28
	Special Options Mask	31
	Error Handling	33
	Advanced Features	37
	Information Retrieval	39
	Setting and Saving the Configuration	45
15	Data Structure Index	
15.1	Data Structures	
Here	are the data structures with brief descriptions:	
C	ONFERR Library Internal: Error List Item	48
C	ONFIG CFLIB Configuration Database Entry	48
16	File Index	
16.1	File List	
Here	is a list of all documented files with brief descriptions:	
in	clude/cf.h C Header File for CFLIB Flexible Configuration Library	48

17 Module Documentation

17.1 Flexible Configuration Library

CFLIB is a small, simple, flexible and portable ANSI C Library to be used as configuration interface for user programs.

Modules

Core Features

Basic CFLIB Setup.

Report Generation

Process templates doing variable substitution and file inclusion.

· General Utilities

General Utility Macros and Functions.

Special Options Mask

The "Special Options Mask" is a Bitmask of type CFFLAGTYP in Configuration Entry Structure Member CONFIG-::flag containing Type, Instruction and Information Flags for a Parameter.

Error Handling

Error Codes, Functions and Structures.

· Advanced Features

Debugging and Utility Functions.

· Information Retrieval

These functions and macros read entries from an initialized CFLIB database.

Setting and Saving the Configuration

Set/Update Parameter Values or Save a Configuration File.

17.1.1 Detailed Description

CFLIB is a small, simple, flexible and portable ANSI C Library to be used as configuration interface for user programs. CFLIB builds and maintains a compact database structure consisting of a list of parameters with their name, content and some additional information about each parameter.

CFLIB targets the basic needs of technical, scientific or other programmers who want to spend minimal time on coding input, output, variable parsing, report generation and the like but still have a simple to use, reliable, flexible and portable configuration interface for their programs.

Main Features

- · Commandline, environment and terminal input parsing
 - Configuration files
 - File search
 - Template driven report generation
 - Automatic time and date update

Author

Stefan Habermehl

License:

http://www.gnu.org/licenses GNU General Public License v3 or later

Project Homepage:

Detailed information, source code and maybe updates are available from the library homepage:

• http://cflib.berlios.de

Local References:

- · Include file: cf.h
 - Library file: libcf.a
 - Documentation: Flexible Configuration Library

17.2 Core Features

Basic CFLIB Setup.

Data Structures

struct CONFIG

CFLIB Configuration Database Entry.

Defines

• #define Patchlevel "21"

CFLIB Identification.

• #define MAXCONF 4096

Maximum number of entries in configuration database.

• #define CF MAXERRSTR 512

Maximum string length for error message.

#define CF_MAXLINE 20480

Maximum string length for setfile and form parsing.

• #define CF_MAXQLINE 512

Maximum string length for query.

• #define CF_MAXUSAGE 1024

Maximum string length for usage string.

• #define CF_USG_DEFCOLS 80

Default terminal width for usage string.

• #define CF_MAXTIMEBUF 256

Buffer size for time and day.

• #define FALSE 0

< TRUE, if not defined

#define NULL (void *)(0L)

NULL, if not defined.

#define CF_FLAG_ON "\1"

Flag is set.

• #define CF_FLAG_OFF ""

Flag is not set.

#define CF_NO_OPTION ' '

Option is not set.

• #define TABLEN 8

TAB length.

• #define CFP PUT 0

Function Call or Automatic Initialization.

• #define CFP ARG 1

Commandline.

#define CFP_ENV 2

Environment.

• #define CFP_PRIV 3

Private Configuration File.

#define CFP_SYS 4

System Configuration File.

• #define CFP_DEF 5

Built-in Default.

• #define CFP_QRY 6

Standard Input Channel.

• #define CFP RESERVED 7

Reserved for Subprojects.

• #define CFS_NOT 0

Error Response Modes for cfstart()

• #define CFS ALL 1

Start Mode: All error messages.

• #define CFS_NEG 2

Start Mode: Only severe errors.

• #define CFS_USG 3

Start Mode: Usage message if error was negative, error output like CFS_NEG.

• #define CFS_DEBUG 4

Start Mode: Output like CFS_USG plus raw dump of configuration.

Functions

int cfinit (CONFIG *set, int argc, char **argv)

cfinit() Initialize Configuration Database

· void cfexit (void)

cfexit() Free allocated memory and reset configuration database and error stack

int cfstart (CONFIG *set, int ac, char **av, char *help, int mode)

cfstart() Start Configuration Database (with error reporting and usage message)

Variables

CONFIG * _conf [MAXCONF+1]

Library Internal: CFLIB Configuration Database with at most MAXCONF parameters.

17.2.1 Detailed Description

Basic CFLIB Setup.

- · General Defines
- · Parsing Levels
- · Configuration Entries (aka Parameters)
- Configuration Database: Array of Configuration Entries
- · Initialization of the Configuration Database
- · Resetting the Configuration Database

17.2.2 Define Documentation

17.2.2.1 #define FALSE 0

< TRUE, if not defined

FALSE, if not defined

17.2.2.2 #define CFS_NOT 0

Error Response Modes for cfstart()

Start Mode: No action on error

17.2.3 Function Documentation

17.2.3.1 int cfinit (CONFIG * set, int ac, char ** av)

cfinit() Initialize Configuration Database

Initialize CFLIB Configuration Database and parse possible sources for database entries according to the settings in set.

Parameters

set	set Configuration Initializer: Pointer to Array of CONFIG items containing parameter name, defaul	
	value, Commandline Option for Parameter and Special Options Mask	
ac	ac Argument Count from commandline or compatible	
av	Argument String array from commandline or compatible structure	

Returns

- 0 : configuration database initialized successfully
- >0 : Count of non fatal errors
- <0 : Fatal error(s) occurred:
 - CFE MCF: Memory allocation for Configuration Failed.
 - CFE_MEF: Memory allocation in Error routine Failed.
 - any other absolute value is total error count

See also

Configuration Parsing Levels and Source/Origin Options

17.2.3.2 void cfexit (void)

cfexit() Free allocated memory and reset configuration database and error stack

Free allocated memory and reset the configuration database and error stack.

This function should be used before a repeated call to cfinit() or cfstart(). Furthermore, it may be desired to call cfexit() when the configuration database occupies a lot of memory and is no longer needed.

17.2.3.3 int cfstart (CONFIG * setting, int ac, char ** av, char * help, int mode)

cfstart() Start Configuration Database (with error reporting and usage message)

Setup Configuration Database.

Check errors and output usage message, if required

Parameters

setting	pointer to initializer	
ac	ac argument count from commandline or compatible	
av	argument string array from comandline or compatible	
help	Help/Usage String	
	 Name of a FLAG Parameter Type entry to cause a usage message, if flag is set Omit, if NULL 	

mode | How to handle cfinit() return:

- CFS_NOT Error Response Modes for cfstart()
- CFS_ALL Start Mode: All error messages.
- CFS_NEG Start Mode: Only severe errors.
- CFS_USG Start Mode: Usage message if error was negative, error output like CFS_NEG.
- CFS_DEBUG Start Mode: Output like CFS_USG plus raw dump of configuration.

Returns

- 0 : configuration database has been initialized successfully, no help or usage message required, no fatal errors
- 1 : no fatal errors occurred, usage message displayed
- −1 : fatal error(s) occurred

17.3 Report Generation

Process templates doing variable substitution and file inclusion.

Defines

- #define CF_DEF_VARDELIM "\$()"
 Default variable delimiter for cfform()
- #define CF_MAXINC 8

Maximum number of nested includes for cfform()

Functions

• int cfform (char *infile, char *outfile, char *vardelim, int mode)

cfform() Process a Template from file or stdin and write generated Report to File or stdout

17.3.1 Detailed Description

Process templates doing variable substitution and file inclusion.

17.3.2 Function Documentation

```
17.3.2.1 int cfform ( char * file, char * outfile, char * vd, int mode )
```

cfform() Process a Template from file or stdin and write generated Report to File or stdout

Process a Template from file or stdin and write generated Report to File or stdout.

The Report Template contains Variables like '\$(ident)' or whatever you set in vd. ident may refer to a:

- Parameter Name like '\$(name)' : Substitute variable by parameter's value (from DB)
 - Include File Path like '\$(FILE:/my/path/to/incfile)' : Substitute variable by content of include file
 - File Path and Section Include like '\$(FILE:incfile#sect)': Include section from include file between [sect] and next [...]
 - Variable File Include like '\$(FILE::varname)' : Include file from location given in parameter varname

See also

Advanced Usage Example

Todo Make cfform() work with buffers instead of files

Parameters

file	Name of Template File, NULL for stdin	
outfile	Name of Output File, NULL for stdout	
vd	Variable Delimiters: string containing the three variable delimiters in the first three chars: to	
	have variables like '\$(name)', let the string be '\$()'. This is also the default, if vd is NULL or	
	string length $<$ 3	
mode	Mode Mask:	
	• 0 : Normal	
	ullet 1 : Query for unresolved variables, (try to) include them in database	
	• 2 : Unset CF_NOSAVE flag for parsed vars	
Generated on Wed Feb 27	4 : Outfile Write append, else write 2013 14:19:51 for CFLIB - Flexible Configuration Library by Doxygen	

Returns

- $\ensuremath{\text{0}}$: Configuration has been saved to file successfully
- !=0 : An error occurred:
 - CFE_NCA : No Configuration database Available.
 - CFE_FNF: File Not Found, read access error.
 - CFE_WAE : Write Access Error.

17.4 General Utilities 28

17.4 General Utilities

General Utility Macros and Functions.

Defines

• #define CF_BACKBUFLEN 102400

File copy buffer for BackupFile()

#define DelFlag(a, b) a&=(~b)

Delete bits of Mask b from Mask a.

• #define SetFlag(a, b) a = b

Set bits of Mask b in Mask a.

Functions

int BackupFile (const char *file, char *modus)

BackupFile() Copy or Rename File "file" to Backup File "file~" or "file.bak"

void RemoveCR (char *string)

Strip Carriage Return at end of string (after fgets) by introducing zero byte at CR position.

• void RemoveTrailSpace (char *string)

Strip whitespaces at end of string by introducing zero byte after last non-whitespace character.

char * EatWhiteSpace (char *string)

EatWhiteSpace() Set pointer to next non-whitespace-character in string.

int IsATerminal (FILE *fp)

IsATerminal() Test whether stream is a terminal

• char * FindFile (const char *fname, const char *fpath, const char *const *fext)

FindFile() Find a File in Path trying Extensions

17.4.1 Detailed Description

General Utility Macros and Functions.

17.4.2 Function Documentation

17.4.2.1 int BackupFile (const char * file, char * modus)

BackupFile() Copy or Rename File "file" to Backup File "file~" or "file.bak"

Copy or Rename File "file" to Backup File "file \sim " or "file .bak".

Parameters

file	Name of regular file to be opened
modus	Backup Mode:
	• "r" Rename
	• "d" Duplicate, Copy
	• "@e ?" Default "d"
	• "@e ?d" docs-style (.bak)
	• "@e ?c", "??" Un∗x Style (∼)

17.4 General Utilities 29

Returns

- · 0 : Configuration has been saved to file successfully
- !=0 : An error occurred:
 - CFE BOF: Invalid filename / open error
 - CFE_BMF :Backup: Memory allocation Failed.
 - CFE BRF : Rename file failed
 - CFE_BBF : Source file open error
 - CFE BWF: Target file write error

17.4.2.2 void RemoveCR (char * ptr)

Strip Carriage Return at end of string (after fgets) by introducing zero byte at CR position.

String Utility Function.

Strip Carriage Return at end of string (after fgets) by introducing zero byte at CR position. Original source was "STELM" by Kees and Lemmens.

Author

Kees and Lemmens

Parameters

ptr	pointer to beginning of string

17.4.2.3 void RemoveTrailSpace (char * ptr)

Strip whitespaces at end of string by introducing zero byte after last non-whitespace character.

Parameters

ptr	Pointer to beginning of string

```
17.4.2.4 char * EatWhiteSpace ( char * ptr )
```

EatWhiteSpace() Set pointer to next non-whitespace-character in string.

Set pointer to next non-whitespace-character in string.

Original source was "STELM" by Kees and Lemmens.

Author

Kees and Lemmens

Parameters

ptr	Pointer to beginning of string

Returns

Pointer to next non-whitespace-character in string

17.4.2.5 int IsATerminal (FILE * fp)

IsATerminal() Test whether stream is a terminal

Test whether stream is a terminal.

17.4 General Utilities 30

Parameters

fp File/Stream Pointer	

Returns

 ${\tt TRUE} \; or \; {\tt FALSE} \\$

Bug ANSI C doesn't have function isatty(), we always return TRUE

17.4.2.6 char * FindFile (const char * fname, const char * fpath, const char * const char * const char * fext)

FindFile() Find a File in Path trying Extensions

Find a File in Path trying Extensions.

Author

Eric R. Smith

License:

Public Domain

Parameters

fname	File Name
fpath	Search Path: String of Directories separated by PATHSEP1 (':' or ';') or PATHSEP2 (nothing
	or ',')
fext	Array of possible Extensions (optional, default is OS dependent)

Returns

The name by which the file was found or \mathtt{NULL}

17.5 Special Options Mask

The "Special Options Mask" is a Bitmask of type CFFLAGTYP in Configuration Entry Structure Member CONFI-G::flag containing Type, Instruction and Information Flags for a Parameter.

Defines

```
• #define CF_LAST 0x0001
```

Last entry in settings array.

• #define CF_PATH 0x0002

Search Path (for FindFile feature)

• #define CF_SETFILE 0x0004

Entry is Private Configuration File.

#define CF_SYS_SETFILE 0x0008

Entry is System Configuration File.

• #define CF SECTION 0x0010

Section in Configuration File.

#define CF PRGNAME 0x0020

Running Program's Name from commandline.

#define CF TIME 0x0040

Time string.

#define CF_DATE 0x0080

Date string.

• #define CF SET PUT 0x0100

Source: Function Call.

#define CF_SET_ARG 0x0200

Source: Commandline Argument.

#define CF_SET_ENV 0x0400

Source: Environment Variable.

• #define CF_SET_PRIV 0x0800

Source: Private Configuration File.

#define CF_SET_SYS 0x1000

Source: System Configuration File.

#define CF_SET_DEF 0x2000

Source: Built-in Default.

• #define CF_SET_QRY 0x4000

Source: Interactive Terminal Input.

#define CF_NO_OPT_ARG 0x10000

Commandline argument not following an option.

• #define CF_CONCAT 0x20000

Argument is concatenated to option.

• #define CF_IGN_ENV 0x40000

Do not check environment for variable.

• #define CF QUERY 0x80000

Ask the user for unresolved item after configuration parsing.

#define CF_STR 0x100000

Entry is String.

#define CF_INT 0x200000

Entry is Integer.

• #define CF FLAG 0x400000

Entry is Flag.

• #define CF_REAL 0x800000

Entry is Float.

• #define CF FINDFILE 0x1000000

Entry is filename to be searched for in the path.

#define CF_MUST 0x2000000

Entry may not be empty (NULL or "")

• #define CF RESID 0x4000000

Residual/additional entry from commandline/setfile/cfput.

#define CF_USAGE 0x8000000

Usage Message format string.

• #define CF EXPHOME 0x10000000

Expand Home Directory.

#define CF_MALLOC 0x20000000

Space for entry's content was mallocated.

#define CF_FORCED 0x40000000

Setting has been forced (already)

#define CF_NOSAVE 0x80000000

Don't include in savefile / mark entry.

#define CF_SRC (CF_INT|CF_FLAG)

Type for source/origin inquiry.

#define CF_FLGINQ (CF_STR|CF_FLAG)

Type for options mask inquiry.

#define CF_DOUBLE (CF_REAL|CF_FLAG)

Type for double inquiry.

#define CF_TD (CF_DATE|CF_TIME)

Date or Time entry.

Typedefs

 typedef unsigned long CFFLAGTYP Special Options Mask Type.

17.5.1 Detailed Description

The "Special Options Mask" is a Bitmask of type CFFLAGTYP in Configuration Entry Structure Member CONFI-G::flag containing Type, Instruction and Information Flags for a Parameter.

- Special CFLIB properties: CFLIB Parameters
- · Source/Origin: Parsing Levels
- · Initialization options: Parsing Levels in the Initialization Process
- Type/Interpretation Flags: Parameter Data Types
- · Special Processing Instructions
- · Special Handling Instructions
- Information/Status markers:
 - CF_LAST must appear in the Configuration Initializer
 - CF_RESID marks one of the Residual Items
 - CF_MALLOC and CF_FORCED are for library internal use

17.6 Error Handling 33

17.6 Error Handling

Error Codes, Functions and Structures.

Data Structures

struct CONFERR

Library Internal: Error List Item.

Defines

• #define CFE_INIT 0

INITialize error input.

• #define CFE_OK 0

No error / everything OKay.

• #define CFE_NEP 1

New Entry successfully Put into DB.

#define CFE_EXIT 1

Finish error input.

#define CFE_ORA 20

Option Requires an Argument.

• #define CFE_UKO 25

UnKnown Option.

• #define CFE_FNF 30

File Not Found, read access error.

• #define CFE NSE 40

No Section specifier End found, missing "]".

• #define CFE_NSC 50

No private Setfile Configured.

• #define CFE WAE 60

Write Access Error.

• #define CFE_IFP 61

Invalid Filename entry for Private setfile.

• #define CFE_EWN 70

Entry Without Name.

#define CFE_ICF 80

Invalid Combination of Flags.

• #define CFE_EWC 90

Entry Without Content.

• #define CFE_UOS 100

Unlikely Option Specifier.

#define CFE_IFC 110

Invalid Flag Combination.

#define CFE_NLE 120

No Last Entry flag found.

• #define CFE_TIN 130

Error reTurn from stdIN query.

• #define CFE_EFE 140

Empty string in content for Filename Entry.

• #define CFE_USG 200

Entries missing: USaGge advice.

17.6 Error Handling 34

```
• #define CFE_URI 210
          UnResolved Item (CF_MUST was set!)
    • #define CFE FBF -500
          File Backup Failed.
    • #define CFE_BMF -510
          Backup: Memory allocation Failed.
    • #define CFE BOF 520
          Backup: Open source file Failed.
    • #define CFE_BBF 530
          Backup: open target Backup file Failed.
    • #define CFE_BRF 540
          Backup: Rename Failed.
    • #define CFE_BWF 550
          Backup: Write Failed.
    • #define CFE_NCA -10
          No Configuration database Available.
    • #define CFE_NEA -20
          No Entry with that name Available.
    • #define CFE_NSS -30
          No Source/origin is Set.
    • #define CFE ECP -40
          Entry's Content is a NULL Pointer.
    • #define CFE MEF -100
          Memory allocation in Error routine Failed.
    • #define CFE MCF -200
          Memory allocation for Configuration Failed.

 #define CFE INF -9999

          Integer iNquiry Failed (?!)

    #define CFE RNF -999.999

          Real/float iNquiry Failed (?!)
Functions
    • int cfgeterr (char *string, size_t len)
          cfgeterr() Error Code and Message Inquiry Function
    • int cfputerr (int ecode, char *string,...)
          cfputerr() Init, exit or append to Error List
    · void cfclearerr (void)
          cfclearerr() Free all entries in error list

    int cfreverr (void)

          cfreverr() Revert order of entries in error list from last->first to first->last
Variables
    • CONFERR * _cferr = NULL
          Library Internal: Error List Pointer.
    • int errcnt = 0
```

Library Internal: Error List Counter.

17.6 Error Handling 35

17.6.1 Detailed Description

Error Codes, Functions and Structures.

· Error Codes and their mnemonic descriptions

Bug There are still errors without entry in error stack

- · Library Internal Error Variables
 - Error Functions

17.6.2 Function Documentation

```
17.6.2.1 int cfgeterr ( char * string, size_t len )
```

cfgeterr() Error Code and Message Inquiry Function

Error Code and Message Inquiry Function.

Parameters

	Pointer to a string, to which the error message should be copied. Giving it a \mathtt{NULL} pointer will omit message return
len	Size of string, if 0 CF_MAXERRSTR will be used

Returns

- 0 : if no error is available, everything is alright
- !=0 : error code of the next error in list

17.6.2.2 int cfputerr (int ecode, char * string, ...)

cfputerr() Init, exit or append to Error List

Init, exit or append to Error List.

Parameters

ecode	Error Code of the error that occurred
string	Error message format string. Giving it a \mathtt{NULL} pointer results in an empty error message string
	Arguments list according to format string

Returns

- <0 : A fatal error occurred (malloc failed)
- >0 : Number of errors in error list

17.6.2.3 void cfclearerr (void)

cfclearerr() Free all entries in error list

Free all entries in error list.

17.6.2.4 int cfreverr (void)

cfreverr() Revert order of entries in error list from last->first to first->last

Revert order of entries in error list from last->first to first->last.

17.6 Error Handling 36

- >=0: Number of errors in error list
- $\bullet\ <$ 0 : Inconsistency with old error count, absolute value is new error counter

17.7 Advanced Features 37

17.7 Advanced Features

Debugging and Utility Functions.

Defines

• #define CFD_CFDUMP 0

Dump Mask Minimal.

• #define CFD_LIBHEAD 1

Dump option CFLIB header.

• #define CFD COLHEAD 2

Dump option Column headers.

#define CFD_SRCFLAGS 4

Dump option Source flag description.

• #define CFD FLAGS 8

Dump option All Flags description.

#define CFD_DEFAULT CFD_COLHEAD|CFD_SRCFLAGS

Dump Mask Default.

Functions

char * cfhomexp (char *name)

cfhomexp() Expand ~ or ~user in parameter content

int cfdinichk (CONFIG *set)

cfdinichk() Debugging Function (experimental)

int cfdump (FILE *fout)

cfdump() Dump CFLIB DB content to fout

17.7.1 Detailed Description

Debugging and Utility Functions. Modes for cfdump()

17.7.2 Function Documentation

```
17.7.2.1 char * cfhomexp ( char * name )
```

cfhomexp() Expand ~ or ~user in parameter content

Expand \sim or $\sim\!\!\mathtt{user}$ in parameter content.

This function is used by default when reading Configuration Files and on initialization of parameters with the Special Option Flag CF_EXPHOME set.

- The environment is checked for the variables LOGNAME or USER, if no user name is given ("~/....")
 - The ${\tt passwd}$ file is searched for the users home directory, if possible
 - Otherwise the environment variable HOME is checked
 - If all that fails, \sim will be omitted, \sim user will expand to "./user"

Parameters

name Entry's name

17.7 Advanced Features 38

Returns

- NULL : an error occurred:
 - No Configuration database Available.
 - Entry's Content is a NULL Pointer.
 - Memory allocation for Configuration Failed.
- !=NULL: String pointer to original or expanded filename

```
17.7.2.2 int cfdinichk ( CONFIG * set )
```

cfdinichk() Debugging Function (experimental)

Debugging Function (experimental)

Initialize CFLIB DB using the default given by set, checking validity and plausibility of entries

Parameters

```
set Pointer to initializing CONFIG-Array
```

Returns

- 0 : No error occurred
- !=0 : An error occurred

Todo Make cfdinichk() work as reliable, complete tool with much more testing and Special Options Mask validation!

```
17.7.2.3 int cfdump ( FILE * fout )
```

cfdump() Dump CFLIB DB content to fout

Dump CFLIB DB content to fout.

Debugging Function

Configuration options:

Set integer bitmask CFLIB variable "CF_DUMPVERB" to

```
@arg = @ref CFD_CFDUMP : Minimal
@arg & @ref CFD_LIBHEAD : CFLIB header
@arg & @ref CFD_COLHEAD : Column headers
@arg & @ref CFD_SRCFLAGS : Source flag description
@arg = @ref CFD_DEFAULT : Default dump verbosity
```

Parameters

```
fout | Pointer to File opened for writing or stdout/stderr/...
```

- >0 : Number of entries in CFLIB DB
- <0 : An error occurred:
 - CFE_NCA : No configuration database available

17.8 Information Retrieval

These functions and macros read entries from an initialized CFLIB database.

Defines

• #define cfget(a) cfgetent(a,0)

Get value (content) of named entry.

#define cfgetstr(a) ((char *)cfgetent(a,CF_STR))

Inquire CFLIB DB for String in content of named entry.

#define cfgetnum(a) (*(int *)cfgetent(a,CF_INT))

Inquire CFLIB DB for Integer value in content of named entry.

#define cfgetreal(a) (*(float *)cfgetent(a,CF_REAL))

Inquire CFLIB DB for Float (Real) value in content of named entry.

#define cfgetdouble(a) (*(double *)cfgetent(a,CF_DOUBLE))

Inquire CFLIB DB for Double value in content of named entry.

• #define cfgetflag(a) (*(int *)cfgetent(a,CF_FLAG))

Inquire CFLIB DB for Flag value in content of named entry.

#define cfflaginq(a, b) (*(int *)cfgetent(a,CF_FLGINQ|(31&b)))

Inquire CFLIB DB for Bit set in entry's Special Options Flag CONFIG::flag.

#define cfgetsrc(a) (*(int *)cfgetent(a,CF_SRC))

Inquire CFLIB DB for Source of named entry's content.

#define cfgetres() ((char *)cfgetent("",CF_RESID))

Get next Residual Command Line Argument from CFLIB DB.

#define cfgetcpr() "CFLIB (c) 1994-2012 Stefan Habermehl"
 Get CFLIB Copyright Notice.

Functions

void * cfgetent (char *name, CFFLAGTYP typ)

cfgetent() Inquire configuration database for content of entry name

• int cfgetvers (void)

cfgetvers() Get Library Version/Patchlevel

• char * cfgetsubvers (void)

cfgetsubvers() Get Library Subversion Details

char * cfgetusg (void)

cfgetusg() Get Usage Message for (Terminal) Output

17.8.1 Detailed Description

These functions and macros read entries from an initialized CFLIB database. The exact name of the required parameter must be given as argument, where indicated.

17.8.2 Define Documentation

17.8.2.1 #define cfget(a) cfgetent(a,0)

Get value (content) of named entry.

Parameters

a Entry's name

Returns

Depending on configured type, see cfgetent() and Macro Definitions!

17.8.2.2 #define cfgetstr(a) ((char *)cfgetent(a,CF_STR))

Inquire CFLIB DB for String in content of named entry.

Parameters

```
a Entry's name
```

Returns

- NULL: An error occurred:
 - No configuration database available
 - No entry of this name available
 - Content is really NULL, Check that with cfgetflag() !!
- · Any other: Pointer to string in content of entry name

```
17.8.2.3 #define cfgetnum( a) (*(int *)cfgetent(a,CF_INT))
```

Inquire CFLIB DB for Integer value in content of named entry.

Parameters

```
a Entry's name
```

Returns

- CFE_INF: Integer inquiry failed because of
 - No configuration database available
 - No entry of this name available
 - Content doesn't begin with digit
 - Content is a NULL pointer
 - Content is really CFE_INF, Check that with cfgetstr() !!
- · Any other: Integer value for named entry

17.8.2.4 #define cfgetreal(a) (*(float *)cfgetent(a,CF_REAL))

Inquire CFLIB DB for Float (Real) value in content of named entry.

Parameters

```
a Entry's name
```

- CFE_RNF: Real/float value inquiry failed because of
 - No configuration database available
 - No entry of this name available
 - Content doesn't begin with digit or signum (+/-)
 - Content is a NULL pointer
 - Content is really CFE_RNF, Check that with cfgetstr() !!
- · Any other : Float value for named entry

17.8.2.5 #define cfgetflag(a) (*(int *)cfgetent(a,CF_FLAG))

Inquire CFLIB DB for Flag value in content of named entry.

Parameters

```
a Entry's name
```

Returns

- TRUE (1): Flag is set
- FALSE (0): Flag is not set
- <0 : An error occurred:
 - CFE NCA: No configuration database available
 - CFE_NEA: No entry of this name available
 - CFE_ECP : Entry's content is a NULL pointer

17.8.2.6 #define cfflaginq(a, b) (*(int *)cfgetent(a,CF_FLGINQ|(31&b)))

Inquire CFLIB DB for Bit set in entry's Special Options Flag CONFIG::flag.

Inquire CFLIB DB for Bit set in entry's Special Options Fag CONFIG::flag.

Debugging Function

Parameters

а	Entry's name
b	Bit Offset, 0<=b<=31

Returns

- TRUE (1): Flag is set
- FALSE (0): Flag is not set
- <0 : An error occurred:
 - CFE_NCA: No Configuration database Available.
 - CFE_NEA: No Entry with that name Available.

17.8.2.7 #define cfgetsrc(a) (*(int *)cfgetent(a,CF_SRC))

Inquire CFLIB DB for Source of named entry's content.

Parameters

```
a Entry's name
```

- 0-6 : Source of entry's content:
 - 0 : cfputstr() call
 - 1 : Command line / Arguments
 - 2 : Environment
 - 3 : Private Configuration File
 - 4 : System Configuration File
 - 5 : Default setting
 - 6 : Interactive input (query)

- <0 : An error occurred:
 - CFE NCA: No configuration database available
 - CFE_NEA: No entry of this name available
 - CFE_NSS: No source set (should not happen!)

17.8.2.8 #define cfgetres() ((char *)cfgetent("",CF_RESID))

Get next Residual Command Line Argument from CFLIB DB.

Returns

- NULL: An error occurred:
 - No Configuration database Available.
 - No more residual arguments available
- · Any other : Pointer to string content

See also

Residual Items

17.8.2.9 #define cfgetcpr() "CFLIB (c) 1994-2012 Stefan Habermehl"

Get CFLIB Copyright Notice.

Get Copyright Notice.

Returns

Pointer to Copyright Message String

17.8.3 Function Documentation

17.8.3.1 void * cfgetent (char * name, CFFLAGTYP typ)

cfgetent() Inquire configuration database for content of entry name

Library internal function, use appropriate Macro functions!

Inquire configuration database for content of entry name

Parameters

name	Entry's name
typ	Expected/required type of content:
	0 : Get type from entry's flag
	CF_INT : Integer
	CF_REAL : Real
	CF_FLAG : Flag
	CF_STR : String
	CF_SRC : Source
	CF_FLGINQ : Bit in entry flag (bit no. in lowest bytes)
	CF_RESID : Residual argument
	Anything else : String

43

Returns

- for CF_STR, CF_RESID or default:
- NULL: An error occurred or nothing available:
 - No configuration database available
 - No entry of this name available
 - The entry's content is really NULL, Check that with cfgetflag()!!
 - No more residual argument (for CF_RESID)
- · any other pointer to string in content of entry name
- · for others: Pointer to return values of the corresponding macro function

```
17.8.3.2 int cfgetvers (void)
```

cfgetvers() Get Library Version/Patchlevel

Get Library Version/Patchlevel.

Returns

```
• >0 : Libary Patchlevel
```

• <=0 : Error

```
17.8.3.3 char * cfgetsubvers (void)
```

cfgetsubvers() Get Library Subversion Details

Get Library Subversion Details.

The Patchlevel returned by this function should match Patchlevel in the public include file cf.h

Returns

Libary Patchlevel and Subversion (Source Revision marked by library internal header file cflib.h.

The return value is "burned" into the library executable and looks like:

```
CFLIB PL 20 $LastChangedRevision: 65 $

17.8.3.4 char * cfgetusg ( void )

cfgetusg() Get Usage Message for (Terminal) Output
```

Get Usage Message for (Terminal) Output.

There are two flavours:

- Let CFLIB do the job: Usage message is generated based on settings for commandline parsing and Special Options Mask found in the database
- 1. Deliver your own Usage Message: Just set the CF_USAGE Flag in the Special Options Mask of one parameter in the database to get a custom usage message (from hardcoded default, configuration file or environment). The delivered custom message string is taken as a format string for the printf() function: Use "%s" in the message string to have the program name inserted that CFLIB got from the default parameter "CF_PR-GNAME" which by default is set to the name of the running program from the commandline at startup.

Returns

- · Pointer to usage string
- NULL : An error occurred:
 - No Configuration database Available.
 - malloc() for usage string failed

See also

CF_MAXUSAGE: Maximum string length for usage string.
CF_USG_DEFCOLS: Default terminal width for usage string.

17.9 Setting and Saving the Configuration

Set/Update Parameter Values or Save a Configuration File.

Defines

#define cfput(a, b) cfputstr(a,(char *)b)
 Update or Add a Parameter.

Functions

• int cfnosave (char *name, const char *onoff)

cfnosave() Alter or query the CF_NOSAVE Flag of Parameter name

• int cfputstr (char *name, char *content)

cfputstr() Update or Add Parameter name with string content

int cfputtime (CFFLAGTYP td)

cfputtime() Set all Time and/or Date entries in CFLIB DB to now or today

• int cfsave (char *fname, const char *savemode)

cfsave() Write configuration data to a Configuration File or stdout

17.9.1 Detailed Description

Set/Update Parameter Values or Save a Configuration File.

17.9.2 Define Documentation

17.9.2.1 #define cfput(a, b) cfputstr(a,(char *)b)

Update or Add a Parameter.

Update or Add Parameter (Utility Function Macro)

Parameters

а	Parameter Name
b	New Content (Type casted to expected Char Pointer)

Returns

int cfputstr()

17.9.3 Function Documentation

17.9.3.1 int cfnosave (char * name, const char * onoff)

cfnosave() Alter or query the CF_NOSAVE Flag of Parameter name

Alter or query the CF_NOSAVE Flag of Parameter name.

When the configuration database is saved to a configuration file, the function cfsave() will exclude all items with the CF_NOSAVE flag set from the output.

The CF_NOSAVE flag can be set in the Special Option Mask CONFIG::flag for every entry in the Configuration Initializer given to cfinit() or cfstart() or later be set with this function for parameters in the current configuration database _conf

Residual Items will have the CF_NOSAVE flag set by default.

Parameters

name	Entry's name
	• "" : All entries
	NULL : All hardcoded entries
onoff	
	CF_FLAG_ON : Set Flag
	CF_FLAG_OFF : Delete Flag
	• "i": Inquire Flag

Returns

- 0 : Entry updated successfully / Flag is OFF (for "i")
- 1 : Flag is ON (for "i")
- !=0 or 1 : An Error occurred:
 - CFE_NCA : No Configuration database Available.
 - CFE_NEA: No Entry with that name Available.

17.9.3.2 int cfputstr (char * name, char * content)

cfputstr() Update or Add Parameter name with string content

Update or Add Parameter name with string content.

Parameters

name	Parameter Name
content	New (String) Content

Returns

- CFE_NEP: New Entry successfully Put into DB.
- 0 : Entry updated successfully
- <0 : An error occurred:
 - CFE_NCA : No Configuration database Available.
 - CFE_MCF : Memory allocation for Configuration Failed.

17.9.3.3 int cfputtime (CFFLAGTYP td)

cfputtime() Set all Time and/or Date entries in CFLIB DB to now or today

Set all Time and/or Date entries in CFLIB DB to now or today.

Parameters

td	Target Selection Mask:
	CF_TIME : Set Time
	CF_DATE : Set Date
	CF_TD : Set Time and Date

Returns

- ullet >0 : Number of entries updated successfully
- $\leq = 0$: An error occurred:
 - CFE_NCA : No Configuration database Available.
 - CFE_MCF : Memory allocation for Configuration Failed.
 - CFE_NEA: No Entry with that name Available.

17.9.3.4 int cfsave (char * file, const char * savemode)

cfsave() Write configuration data to a Configuration File or stdout

Write configuration data to a Configuration File or stdout.

Entries with the CF_NOSAVE flag will be excluded from the output. Use cfnosave() to inquire or alter that flag for an entry.

Parameters

file	
	 <string> : Name of regular file to be opened</string>
	• "": Write configuration to stdout
	 NULL: Private configuration file will be overwritten or created, if an appropriate entry exists
savemode	File open mode:
	• "w" : Overwrite
	• "a" : Append

- 0 : Configuration has been saved to file successfully
- !=0 : An error occurred:
 - CFE_NCA :No Configuration database Available.
 - CFE IFP :Invalid Filename entry for Private setfile.
 - CFE_WAE :Write Access Error.

18 Data Structure Documentation

18.1 CONFERR Struct Reference

Library Internal: Error List Item.

Data Fields

• struct _cfe * next

Next Error Pointer.

· int errcode

Numeric Error Code.

• char errstr [CF_MAXERRSTR]

Error Message String of maximum length CF_MAXERRSTR.

18.1.1 Detailed Description

Library Internal: Error List Item.

18.2 CONFIG Struct Reference

CFLIB Configuration Database Entry.

Data Fields

• char * name

Parameter Name

• char * inhalt

Parameter Content, see Parameter Default Value.

char option

Commandline Option for Parameter

CFFLAGTYP flag

Special Options Mask

18.2.1 Detailed Description

CFLIB Configuration Database Entry.

19 File Documentation

19.1 include/cf.h File Reference

C Header File for CFLIB Flexible Configuration Library.

Data Structures

struct CONFIG

CFLIB Configuration Database Entry.

Defines

#define Patchlevel "21"

CFLIB Identification.

• #define MAXCONF 4096

Maximum number of entries in configuration database.

#define CF_MAXERRSTR 512

Maximum string length for error message.

• #define CF MAXLINE 20480

Maximum string length for setfile and form parsing.

• #define CF_MAXQLINE 512

Maximum string length for query.

• #define CF_MAXUSAGE 1024

Maximum string length for usage string.

• #define CF_USG_DEFCOLS 80

Default terminal width for usage string.

#define CF_MAXTIMEBUF 256

Buffer size for time and day.

• #define FALSE 0

< TRUE, if not defined

#define NULL (void *)(0L)

NULL, if not defined.

• #define CF FLAG ON "\1"

Flag is set.

#define CF FLAG OFF ""

Flag is not set.

#define CF NO OPTION ' '

Option is not set.

• #define TABLEN 8

TAB length.

#define CFP_PUT 0

Function Call or Automatic Initialization.

• #define CFP_ARG 1

Commandline.

#define CFP_ENV 2

Environment.

• #define CFP_PRIV 3

Private Configuration File.

• #define CFP_SYS 4

System Configuration File.

#define CFP_DEF 5

Built-in Default.

#define CFP_QRY 6

Standard Input Channel.

#define CFP RESERVED 7

Reserved for Subprojects.

#define CF_DEF_VARDELIM "\$()"

Default variable delimiter for cfform()

• #define CF MAXINC 8

Maximum number of nested includes for cfform()

• #define CF_BACKBUFLEN 102400

File copy buffer for BackupFile() #define CF_LAST 0x0001 Last entry in settings array. • #define CF PATH 0x0002 Search Path (for FindFile feature) #define CF_SETFILE 0x0004 Entry is Private Configuration File. #define CF SYS SETFILE 0x0008 Entry is System Configuration File. #define CF_SECTION 0x0010 Section in Configuration File. • #define CF_PRGNAME 0x0020 Running Program's Name from commandline. • #define CF_TIME 0x0040 Time string. • #define CF_DATE 0x0080 Date string. • #define CF_SET_PUT 0x0100 Source: Function Call. #define CF SET ARG 0x0200 Source: Commandline Argument. #define CF_SET_ENV 0x0400 Source: Environment Variable. #define CF_SET_PRIV 0x0800 Source: Private Configuration File. • #define CF_SET_SYS 0x1000 Source: System Configuration File. #define CF_SET_DEF 0x2000 Source: Built-in Default. • #define CF SET QRY 0x4000 Source: Interactive Terminal Input. #define CF_NO_OPT_ARG 0x10000 Commandline argument not following an option. #define CF_CONCAT 0x20000 Argument is concatenated to option. #define CF_IGN_ENV 0x40000 Do not check environment for variable. #define CF_QUERY 0x80000 Ask the user for unresolved item after configuration parsing. #define CF_STR 0x100000 Entry is String. #define CF INT 0x200000 Entry is Integer. #define CF_FLAG 0x400000 Entry is Flag. #define CF_REAL 0x800000 Entry is Float. #define CF_FINDFILE 0x1000000 Entry is filename to be searched for in the path.

#define CF_MUST 0x2000000

Entry may not be empty (NULL or "")

 #define CF_RESID 0x4000000 Residual/additional entry from commandline/setfile/cfput. • #define CF USAGE 0x8000000 Usage Message format string. #define CF_EXPHOME 0x10000000 Expand Home Directory. • #define CF MALLOC 0x20000000 Space for entry's content was mallocated. #define CF_FORCED 0x40000000 Setting has been forced (already) #define CF NOSAVE 0x80000000 Don't include in savefile / mark entry. #define CF_SRC (CF_INT|CF_FLAG) Type for source/origin inquiry. #define CF_FLGINQ (CF_STR|CF_FLAG) Type for options mask inquiry. #define CF_DOUBLE (CF_REAL|CF_FLAG) Type for double inquiry. #define CF_TD (CF_DATE|CF_TIME) Date or Time entry. #define CFE_INIT 0 INITialize error input. • #define CFE OK 0 No error / everything OKay. • #define CFE_NEP 1 New Entry successfully Put into DB. • #define CFE EXIT 1 Finish error input. • #define CFE_ORA 20 Option Requires an Argument. • #define CFE UKO 25 UnKnown Option. • #define CFE_FNF 30 File Not Found, read access error. • #define CFE NSE 40 No Section specifier End found, missing "]". • #define CFE NSC 50 No private Setfile Configured. #define CFE_WAE 60 Write Access Error. #define CFE IFP 61 Invalid Filename entry for Private setfile. • #define CFE_EWN 70 Entry Without Name. • #define CFE ICF 80 Invalid Combination of Flags. • #define CFE_EWC 90 Entry Without Content. #define CFE UOS 100 Unlikely Option Specifier. #define CFE_IFC 110

• #define CFE_NLE 120

Invalid Flag Combination.

```
No Last Entry flag found.
• #define CFE TIN 130
     Error reTurn from stdIN query.
• #define CFE EFE 140
     Empty string in content for Filename Entry.

    #define CFE USG 200

     Entries missing: USaGge advice.
• #define CFE_URI 210
     UnResolved Item (CF MUST was set!)
• #define CFE_FBF -500
     File Backup Failed.
• #define CFE_BMF -510
     Backup: Memory allocation Failed.
• #define CFE BOF 520
     Backup: Open source file Failed.
• #define CFE BBF 530
     Backup: open target Backup file Failed.

    #define CFE BRF 540

     Backup: Rename Failed.
• #define CFE_BWF 550
     Backup: Write Failed.
• #define CFE_NCA -10
     No Configuration database Available.
• #define CFE_NEA -20
     No Entry with that name Available.

    #define CFE_NSS -30

     No Source/origin is Set.
• #define CFE ECP -40
     Entry's Content is a NULL Pointer.
• #define CFE MEF -100
     Memory allocation in Error routine Failed.
• #define CFE MCF -200
     Memory allocation for Configuration Failed.
• #define CFE_INF -9999
     Integer iNquiry Failed (?!)
• #define CFE_RNF -999.999
     Real/float iNquiry Failed (?!)

    #define CFS_NOT 0

     Error Response Modes for cfstart()
• #define CFS ALL 1
     Start Mode: All error messages.

    #define CFS_NEG 2

     Start Mode: Only severe errors.
• #define CFS_USG 3
     Start Mode: Usage message if error was negative, error output like CFS_NEG.
• #define CFS_DEBUG 4
     Start Mode: Output like CFS_USG plus raw dump of configuration.

    #define CFD_CFDUMP 0

     Dump Mask Minimal.
```

```
    #define CFD_LIBHEAD 1

     Dump option CFLIB header.
• #define CFD COLHEAD 2
     Dump option Column headers.

    #define CFD_SRCFLAGS 4

     Dump option Source flag description.
• #define CFD FLAGS 8
     Dump option All Flags description.
• #define CFD_DEFAULT CFD_COLHEAD CFD_SRCFLAGS
     Dump Mask Default.
• #define cfget(a) cfgetent(a,0)
      Get value (content) of named entry.
• #define cfgetstr(a) ((char *)cfgetent(a,CF_STR))
     Inquire CFLIB DB for String in content of named entry.

    #define cfgetnum(a) (*(int *)cfgetent(a,CF_INT))

     Inquire CFLIB DB for Integer value in content of named entry.

    #define cfgetreal(a) (*(float *)cfgetent(a,CF_REAL))

     Inquire CFLIB DB for Float (Real) value in content of named entry.

    #define cfgetdouble(a) (*(double *)cfgetent(a,CF_DOUBLE))

     Inquire CFLIB DB for Double value in content of named entry.

    #define cfgetflag(a) (*(int *)cfgetent(a,CF_FLAG))

     Inquire CFLIB DB for Flag value in content of named entry.

    #define cfflaginq(a, b) (*(int *)cfgetent(a,CF_FLGINQ|(31&b)))

     Inquire CFLIB DB for Bit set in entry's Special Options Flag CONFIG::flag.

    #define cfgetsrc(a) (*(int *)cfgetent(a,CF SRC))

     Inquire CFLIB DB for Source of named entry's content.

    #define cfgetres() ((char *)cfgetent("",CF_RESID))

      Get next Residual Command Line Argument from CFLIB DB.
• #define cfgetcpr() "CFLIB (c) 1994-2012 Stefan Habermehl"
      Get CFLIB Copyright Notice.

    #define cfput(a, b) cfputstr(a,(char *)b)

      Update or Add a Parameter.

    #define DelFlag(a, b) a&=(~b)
```

Delete bits of Mask b from Mask a.

#define SetFlag(a, b) a = b

Set bits of Mask b in Mask a.

#define __CF_H__

Marker: cf.h has been included.

Typedefs

typedef unsigned long CFFLAGTYP
 Special Options Mask Type.

Functions

```
    int cfinit (CONFIG *set, int argc, char **argv)

      cfinit() Initialize Configuration Database
· void cfexit (void)
      cfexit() Free allocated memory and reset configuration database and error stack

    int cfstart (CONFIG *set, int ac, char **av, char *help, int mode)

      cfstart() Start Configuration Database (with error reporting and usage message)

    void * cfgetent (char *name, CFFLAGTYP typ)

      cfgetent() Inquire configuration database for content of entry name

    int cfgetvers (void)

      cfgetvers() Get Library Version/Patchlevel
• char * cfgetsubvers (void)
      cfgetsubvers() Get Library Subversion Details

    char * cfgetusg (void)

      cfgetusg() Get Usage Message for (Terminal) Output

    int cfgeterr (char *string, size t len)

      cfgeterr() Error Code and Message Inquiry Function

    int cfputerr (int ecode, char *string,...)

      cfputerr() Init, exit or append to Error List

    void cfclearerr (void)

      cfclearerr() Free all entries in error list

    int cfreverr (void)

      cfreverr() Revert order of entries in error list from last->first to first->last
char * cfhomexp (char *name)
      \textit{cfhomexp()} Expand \sim \textit{or} \sim \textit{user} in parameter content

    int cfdinichk (CONFIG *set)

      cfdinichk() Debugging Function (experimental)

    int cfdump (FILE *fout)

      cfdump() Dump CFLIB DB content to fout

    int cfnosave (char *name, const char *onoff)

      cfnosave() Alter or query the CF_NOSAVE Flag of Parameter name
• int cfputstr (char *name, char *content)
      cfputstr() Update or Add Parameter name with string content

    int cfputtime (CFFLAGTYP td)

      cfputtime() Set all Time and/or Date entries in CFLIB DB to now or today
• int cfsave (char *fname, const char *savemode)
      cfsave() Write configuration data to a Configuration File or stdout

    int BackupFile (const char *file, char *modus)

      BackupFile() Copy or Rename File "file" to Backup File "file~" or "file.bak"
• int cfform (char *infile, char *outfile, char *vardelim, int mode)
      cfform() Process a Template from file or stdin and write generated Report to File or stdout

    void RemoveCR (char *string)

      Strip Carriage Return at end of string (after fgets) by introducing zero byte at CR position.

    void RemoveTrailSpace (char *string)

      Strip whitespaces at end of string by introducing zero byte after last non-whitespace character.

    char * EatWhiteSpace (char *string)

      EatWhiteSpace() Set pointer to next non-whitespace-character in string.

    int IsATerminal (FILE *fp)

      IsATerminal() Test whether stream is a terminal

    char * FindFile (const char *fname, const char *fpath, const char *const *fext)
```

FindFile() Find a File in Path trying Extensions

19.1.1 Detailed Description

C Header File for CFLIB Flexible Configuration Library. Public Functions and Definitions

Note

Include this file in the source code and link with the library executable, usually referring to libcf.a by calling " (g) cc -lcf ..."

Version

```
SVN: $Id: cf.h 67 2013-02-27 11:24:49Z stefan_x $
```

Author

```
Stefan Habermehl stefan.habermehl@mcff.de
```

Copyright:

```
(c) 1994,1995,1996,1997,1998,2006,2007,2008,2009,2013 Stefan Habermehl
```

License:

http://www.gnu.org/licenses GNU Lesser General Public License version 3.0 (LGPLv3)

Index

Advanced Features, 37	cfput
cfdinichk, 38	Setting and Saving the Configuration, 45
ofdump, 38	cfputerr
cfhomexp, 37	Error Handling, 35
BackupFile	cfputstr
General Utilities, 28	Setting and Saving the Configuration, 46
deficial offitties, 20	cfputtime
CFS NOT	Setting and Saving the Configuration, 46
Core Features, 23	cfreverr
CONFERR, 48	Error Handling, 35
CONFIG. 48	cfsave
cfclearerr	Setting and Saving the Configuration, 47
Error Handling, 35	cfstart
cfdinichk	Core Features, 24
	Core Features, 22
Advanced Features, 38	CFS_NOT, 23
cfdump	cfexit, 24
Advanced Features, 38	cfinit, 24
cfexit	cfstart, 24
Core Features, 24	FALSE, 23
cfflaging	
Information Retrieval, 41	EatWhiteSpace
cfform	General Utilities, 29
Report Generation, 26	Error Handling, 33
cfget	cfclearerr, 35
Information Retrieval, 39	cfgeterr, 35
cfgetcpr	cfputerr, 35
Information Retrieval, 42	cfreverr, 35
cfgetent	
Information Retrieval, 42	FALSE
cfgeterr	Core Features, 23
Error Handling, 35	FindFile
cfgetflag	General Utilities, 30
Information Retrieval, 40	Flexible Configuration Library, 20
cfgetnum	
Information Retrieval, 40	General Utilities, 28
cfgetreal	BackupFile, 28
Information Retrieval, 40	EatWhiteSpace, 29
cfgetres	FindFile, 30
Information Retrieval, 42	IsATerminal, 29
cfgetsrc	RemoveCR, 29
Information Retrieval, 41	RemoveTrailSpace, 29
cfgetstr	
Information Retrieval, 40	include/cf.h, 48
cfgetsubvers	Information Retrieval, 39
Information Retrieval, 43	cfflaginq, 41
cfgetusg	cfget, 39
Information Retrieval, 43	cfgetcpr, 42
cfgetvers	cfgetent, 42
Information Retrieval, 43	cfgetflag, 40
	cfgetnum, 40
cfhomexp	cfgetreal, 40
Advanced Features, 37	cfgetres, 42
cfinit	cfgetsrc, 41
Core Features, 24	cfgetstr, 40
cfnosave	cfgetsubvers, 43
Setting and Saving the Configuration, 45	3.g3.333.3.3, 10

INDEX 57

```
cfgetusg, 43
    cfgetvers, 43
IsATerminal
    General Utilities, 29
RemoveCR
    General Utilities, 29
RemoveTrailSpace
    General Utilities, 29
Report Generation, 26
    cfform, 26
Setting and Saving the Configuration, 45
    cfnosave, 45
    cfput, 45
    cfputstr, 46
    cfputtime, 46
    cfsave, 47
Special Options Mask, 31
```