P4 HLIR 0.9.22 Specification

Table of Contents

```
Table of Contents
Overview
Brief Requirements Review
Generating the HLIR and accessing its objects
p4 header
p4 expression
p4 sized integer
p4 header instance
p4 field
p4 field list
p4 field list calculation
p4 parse state
p4 parse value set
p4 action
p4 node
p4 table
p4 conditional node
p4 action profile
p4 action selector
p4 counter
p4 meter
p4 register
p4 parser exception
Dep
      ReverseReadDep
      SuccessorDep
      ActionDep
      MatchDep
```

Overview

This document describes the structure of the high-level intermediate representation (HLIR) that the P4 compiler generates based on P4 program input. This HLIR is what is used by the compiler backends to implement a forwarding element that is functionally equivalent to what the P4 program specifies, and to generate code and APIs for interacting with that forwarding element.

Brief Requirements Review

The frontend of the compiler must produce a set of Python objects as described below. This set of objects:

- Must entirely specify the functionality of a P4 program, including any standard library objects that may be referenced (such as common header types like IPv4, and target-specific primitive actions like modify field(...))
- Is assumed to be entirely valid and conform to semantic rules established by the official P4 specification
- Should be usable across all backends of the compiler, ranging from the actual Tofino target to the C API auto-generator
 - If an abstraction extracted from the P4 program is used across many targets (like the table graph extracted from control functions) it should be in the HLIR and generated by the frontend

Generating the HLIR and accessing its objects

To build the HLIR, use the following Python code:

```
from p4_hlir.main import HLIR
h = HLIR(<list of p4 sources>)
h.build()
```

For each type of P4 object (e.g. table), the HLIR defines a Python class (e.g. p4_table). For each P4 object (e.g. table ipv4_lpm), the appropriate class is instantiated and the instance is placed in a Python OrderedDict, using the name of the P4 object as the key and the instance as the value. The dictionaries exist as attributes of the HLIR object.

In the above example, one can access the tables defined in the P4 program using the following code:

```
for table_name, table in h.p4_tables.items():
    pass
```

The following OrderedDict's are exposed by the HLIR. A dictionary whose name is p4 <name>s contains Python objects of type p4 <name>.

OrderedDict's name	P4 object type
p4_actions	action
p4_tables	table
p4_conditional_nodes	None, this is used to represent conditions contained in the

	control flow
p4_action_profiles	action_profile
p4_action_selectors	action_selector
p4_nodes	None, this is an "abstract" class that is inherited by both p4_table and p4_conditional_node
p4_headers	header_type
p4_header_instances	header and metadata
p4_fields	None, this is used to refer to a field in a header_instance
p4_field_lists	field_list
p4_field_list_calculations	field_list_calculation
p4_parse_states	parser
p4_parse_value_sets	parser_value_set
p4_parser_exceptions	parser_exception
p4_counters	counter
p4_meters	meter
p4_registers	register

In addition to the above OrderedDict's, the HLIR class also exposes these two attributes:

- p4_ingress_ptr: a Python dictionary which maps p4_node objects to the corresponding Python set of p4_parse_state objects. If a parse state is included in the set, it means that this parse state can return the p4_node key as a control flow entry point
- p4_egress_ptr: the one p4_node control flow entry point for the egress pipeline

The rest of this document describes the different Python classes instantiated from the P4 program, and their attributes.

p4_header

There is one p4_header object for each header_type/layout object in the P4 program. The original P4 name is used as a key in the HLIR object dictionary. Each contains the following attributes:

name

the header type's name, as taken from the P4 program

layout

An OrderedDict (from the Python collections module) representing the order and width of the header type's fields. The key represents the field name, and the value represents the field's width in *bits*. The value can also optionally be the special value p4_AUTO_WIDTH, meaning the width was '*' in the P4 program. The order of the name:width pairs represents the order in which they appear on the wire.

attributes

An <code>OrderedDict</code> (from the Python <code>collections</code> module) representing the order and attributes of the header type's fields. The key represents the field name, and the value is a set of attributes which can include $p4_SIGNED$ and $p4_SATURATING$. The order of this dictionary is the same as for <code>layout</code>.

length

The header's length, in *bytes*, as either an int or a p4_expression. The latter is an object representing an expression referencing the values of the header's fields at runtime.

max_length

The header's maximum allowable length, in bytes, as an int

p4_expression

Expressions from the P4 program (header type length attributes and conditions in control function if statements) are represented as trees of p4_expression objects, each of which represents a binary or unary operation with the following attributes:

left

The left-hand operand of a binary operation. For unary operations, this has the value None. May be an int, p4 header instance, or p4 field.

• right

The right-hand operand of a binary operation, or the sole operand of a unary operation. May be an int, p4 header instance, or p4 field.

op

The operation being performed, as one of the following strings:

- o "+"
- o "-"
- o "*"
- o "/"
- o "%"

"**" "<<" o ">>" o "|" "Λ" o **"&"** o **"~**" o "==" o "!=" o "<" o "<=" o ">" o ">=" o "not" o "or" o "and"

o "valid"

p4_sized_integer

Inherits from the Python base int type. It annotates an int with an explicit width attribute. If the P4 program explicitly specifies a width, then this value is used and the integer is truncated if needed. If no width is specified in the P4 program, then the width attribute is inferred from the integer value. Note that as of now, this is only used for integer field list entries.

p4_header_instance

P4 instances declared with the header and metadata keywords are both represented by p4_header_instance objects. Instance arrays appear as a series of separate p4_header_instance objects, along with special p4_header_instance objects for special P4 index values like next and latest. The instance's key in the p4_header_instances HLIR dictionary is the string that would be used to refer to it in the original P4 program. For example, the P4 declaration "header my_type my_inst;" adds the following pair to the p4_header_instances HLIR dictionary:

```
{ "my_inst" : <p4_header_instance object> }
```

While the declaration "header my type my array[3];" would add the following:

```
{ "my array[0]" : <p4 header instance object>,
```

```
"my_array[1]" : <p4_header_instance object>,
"my_array[2]" : <p4_header_instance object>,
"my_array[next]" : <p4_header_instance object>,
"my_array[latest]" : <p4_header_instance object> }
```

Each p4 header instance has the following attributes:

name

The header instance's name, in the same form that the header would be referenced from P4. From the example above, this would be something like "my_inst" or "my array[2]", etc.

• base_name

The header instance's name without any array subscripts. For example, a header instance "my_array[2]" would have base_name "my_array". This is useful for accessing other headers in the same array, by concatenating the appropriate square-bracketed subscript. For non-array instances, name and base_name are equal.

fields

An ordered list of p4 field objects referring to each field in the instance

header_type

A reference to the p4_header object representing the P4 header type this object is an instance of

metadata

A boolean set to True if the instance was declared with the P4 metadata keyword, and False if with the header keyword

index

If the instance is part of an array, this attribute contains the instance's array position. Either an int or the special values P4_NEXT or P4_LATEST. If the instance is not part of an array, this attribute has the value None.

max index

If the instance is part of an array, this attribute contains the size of the array as the maximum allowable integer index into it. For example, an array declared as "header my_tag my_array[5]" would have a max_index of 4. If the instance is not part of an array, this attribute has the value None.

virtual

A boolean value. If True, the instance is a special reference (like P4_NEXT or P4_LATEST) and thus does not need space allocated in the PHV. Otherwise, the instance is allocated space in the PHV. Elements of instance arrays with integer indices are not virtual, and neither are instances that are not part of arrays.

• initializer

A dictionary mapping field names (as present in the associated header type's layout) to integer values. The values are written to the corresponding fields between packets. Only metadata header instances will have initializers.

p4_field

There is one p4_field object for every field of every header instance in the P4 program. The field's key in the object collection is the string that would be used to refer to the field in P4 (eg, an IP ttl would be retrieved with " $my_ipv4_instance.ttl$ " while an MPLS label in a stack would be retrieved with " $my_ipv4_instance.ttl$ "). Each has the following attributes:

name

The field's name (eg, "my mpls stack[3].label" would have the name "label")

instance

A reference to the p4 header instance object that this field belongs to

width

An int recording the field's width, in bits. If the field is of variable-width, has the special value P4 AUTO WIDTH.

attributes

A set recording the field's attributes. It is a subset of {P4 SIGNED, P4 SATURATING}

offset

An int recording the field's starting offset in the parent header instance, in bits. If there is a variable-width field in the header and normal fields come after it, those normal fields at the end have *negative* offsets indicating the distance in bits between the start of that field and the end of the header.

default

If the field is part of a metadata instance, an int recording the initial value the field should have before being written to. If the P4 program did not specify an initial value in the metadata instance declaration, the default default is 0. If the field in question is part of a non-metadata header instance, the value is None.

ingress_read, ingress_write, egress_read, egress_write

Boolean flags indicating accesses to this field during ingress and egress pipelines.

calculation

If the field has been bound to field list calculations, this attribute is an ordered list of tuples with values, in order:

- a Python string which can either be "update" or "verify", indicating whether the field value should be verified against the calculation, or updated from the calculation
- b. the p4 field list calculation producing the value
- c. the boolean condition expression deciding whether to perform the update or verify operation, as a p4_expression object (or None if no condition)

 If the field has not been bound like this, the attribute's value is an empty list.

p4_field_list

There is one p4_field_list object for each field_list defined in the P4 program. The original P4 name is used as a key in the corresponding HLIR dictionary. Each contains the following attributes:

name

The field list's name.

• fields

An ordered list of references to the $p4_field$ objects contained by the field list. May also contain $p4_sized_integer$ objects and the special value $P4_PAYLOAD$. Elements in this list may not be unique.

If the P4 object contained whole headers or other field lists, they have been expanded out here into all of their component fields (recursively expanded, in the case of field lists referencing other field lists). Recursive/cyclic references between field lists are detected and disallowed by the frontend.

p4_field_list_calculation

There is one p4_field_list_calculation object for each field_list_calculation defined in the P4 program. The original P4 name is used as a key in the corresponding HLIR dictionary. Each contains the following attributes:

name

The calculation's name.

• input

An ordered list of references to the p4_field_list objects included in the calculation

output_width

An int representing the width of the calculation's result in bits

algorithm

A string representing the calculation algorithm to use. Could be anything, and it's up to the target to check, but the P4 spec defines these common name/algorithm pairs:

"xor16

The XOR of the input bytes, taken two at a time.

o "csum16"

The IPv4 header checksum described in https://tools.ietf.org/html/rfc791#page-14

o "crc16"

See http://en.wikipedia.org/wiki/Crc16

o "crc32"

See http://en.wikipedia.org/wiki/Crc32

"programmable_crc"

An arbitrary CRC polynomial. See http://en.wikipedia.org/wiki/Cyclic_redundancy_check.

p4_parse_state

There is one p4_parse_state object for each parser function defined in the P4 program. The original P4 name is used as a key in the corresponding HLIR dictionary. Each contains the following attributes:

name

The parse state's name, as taken from the P4 program

call_sequence

An ordered list of the operations performed in the parse state. These include header instance extractions, metadata field writes, and counter operations. Each list element is a tuple of the form (operation, arg, [further_args, ...]) where the operation is a special enum value that dictates the meaning of the following arguments. The different values for operation are:

- o parse call.extract
 - A P4 extract() operation. The next tuple element is a reference to the p4 header instance being extracted to
- o parse call.set

A P4 $set_metadata()$ operation. The second tuple element is a reference to the p4_field being written to. The third tuple element is the value to write, which is either:

- An integer
- A (bit offset, bit width) tuple representing a call to current ()
- A p4 field reference from a previously extracted header

• branch_on

Either:

- The empty list [], in which case the branch is unconditional and the branch_to attribute will contain a single entry with the default key
- A list of fields to be concatenated together into a compound word to branch on, with smaller list indices corresponding to the **more** significant side of the compound word. Each element is either:
- o Ap4 field reference from a previously extracted header
- A (bit offset, bit width) tuple representing a call to current()

branch_to

A OrderedDict representing the case: destination pairs of the original P4 select function.

The key may be:

- An int
- A (value, mask) tuple where both elements are ints
- o Ap4 parse value set object
- The special value P4 DEFAULT

The value may be:

- A p4 parse state object
- A p4_table or p4_conditional_node object, in which case the branch is terminal and the parser passes control to the indicated point in the match+action pipeline
- A p4_parser_exception object, in which case the branch is terminal and the packet will either be dropped or passed on to the match+action pipeline

prev

An OrderedSet listing all parse states that can branch to this one.

p4_parse_value_set

There is one p4_parse_value_set object for each parser_value_set object defined in the P4 program. The original P4 name is used as a key in the object collection. Each contains the following attributes:

name

The value set's name, as taken from the P4 program

p4_action

There is one p4_action object for each action function defined in the P4 program. The original P4 name is used as a key in the corresponding HLIR dictionary. Each contains the following attributes:

name

The action's name, as taken from the P4 program

• signature

An ordered list of the parameter names the function accepts

signature widths

For P4-programmer-defined actions, each element in this list is an int recording the bit width of the action's argument at the corresponding index in the signature

attribute. Use to determine the width of table entry data when the action is invoked directly by a table. Values in this list may be <code>None</code> if the argument is never used, or if the action is a primitive.

signature_flags

For P4-programmer-defined actions, this attribute is an empty dictionary. For primitives, this dictionary maps parameter names (from the signature attribute) to a nested dictionary of parameter properties. These properties can include:

- tvpe
 - A Python set of the acceptable argument types for the parameter. In most cases this is some subset of $p4_field$, int, and $p4_table_entry_data$. The int type indicates an immediate value provided by the programmer within the P4 program itself, while $p4_table_entry_data$ indicates a value provided at runtime by the matching table entry which invoked the action. This key must be present with a non-empty set for every parameter in the primitive.
- access
 - An indication about whether the argument is written to or read by the primitive (eg, whether it is a source or destination field). If present, one of the special values P4_READ, P4_WRITE, or P4_READ_WRITE. If not present, it is assumed to be P4_READ_WRITE.
- optional
 - A boolean indicating whether or not the argument is optional. If not present, it is assumed to be False. Once a parameter has been marked as optional, all parameters following it in the signature must also be marked as optional.
- o data_width Specifies how to infer the width of the current parameter, should it end up being provided by table data. Can either be an integer, in which case this integer represents the width in bits of the parameter, or a string referring to another parameter whose width can be inferred (e.g. the other parameter can be bound to a header instance's field, whose width is known at compile time). This is how the frontend populates the signature widths attribute described above.

For example, in the action <code>add_to_field</code> (dst, value), the value parameter would have property "data_width": "dst". If the action was called with a 48-bit field as its dst and value to be specified at runtime, the API generator could use this property to infer that the API must accept a 48-bit value when installing table entries that invoke the action.

• call sequence

A list of tuples, each representing a call to another action, ordered as they were written in the original code. Each tuple contains, in this order:

- o The p4 action object being called
- An ordered list of the arguments being passed to the action. This list is guaranteed to contain at least the target's required parameters, but may not

contain values for all optional parameters. Elements of this list may potentially be:

- Python objects (ints, p4 fields, etc)
- References to the calling action's own arguments, as p4_signature_ref
 objects. These have an idx attribute which specifies the argument being
 referenced

• flat_call_sequence

Similar to the <code>call_sequence</code> attribute, except all calls to non-primitive actions have been recursively expanded such that the list is entirely composed of primitives and their arguments.

Each tuple in the list also has a third element reporting the call stack originally taken to get to this primitive, for error reporting purposes. This element is in the form of a list of $(p4_action, int)$ tuples where the $p4_action$ records a parent action and the int records the position of the call in that action's unflattened call sequence.

Actions with empty call sequences are implicitly action primitives.

Actions are only validated if they are invoked directly or indirectly by a table. If they are not, the action is effectively unused and is trimmed out before the HLIR is presented to the compiler backend.

It is guaranteed by the frontend that any primitive arguments that are not of type p4 table entry data have been bound to concrete values at compile-time.

p4_node

There is one $p4_node$ object for each table and control flow condition defined in the P4 program. This class has 2 subclasses: $p4_table$ and $p4_conditional_node$. This class defines the following attributes:

name

see description for p4 table and p4 conditional node

next

see description for p4 table and p4 conditional node

• control_flow_parent

A string recording the name of the inner-most control flow function containing this node in the original P4 program, for debugging and error reporting purposes.

• conditional barrier

A Python tuple with 2 members. The first member is the inner-most p4_node object on which the execution of the current p4_node is dependent. The second member

indicates what the output of that p4_node needs to be in order for the current p4_node to be executed. This second member can either be:

- o a boolean value if the barrier is a p4 conditional node,
- o a Python set of p4 actions objects,
- Python strings "hit" or "miss"

prev

An OrderedSet listing all p4_node objects that point to this one. May also contain p4 parse state objects if the parser can exit directly to this table.

The set order is arbitrary and not guaranteed to be consistent across compiler runs.

• dependencies to

A Python dictionary whose keys are the p4_node objects on which this node has a dependency. The associated key is a Dep object describing the type of dependency.

• dependencies_for

A Python dictionary whose keys are the p4_node objects for which this table is a dependency. The associated value is a Dep object describing the type of dependency. We can note that if table_1 is in table_2.dependencies_to then table_2 is in table 1.dependencies for.

p4_table

There is one p4_table object for each table defined in the P4 program. The original P4 name is used as a key in the object collection. p4_table is a subclass of p4_node. It defines the following additional attributes:

name

The table's name, as taken from the P4 program

match_fields

A list of (field, type, mask) tuples where the field is a reference to the p4_field being used in the match key, the type is a p4_match_type enum value recording the type of match, and the mask is either an int or None representing a static mask that is ANDed with the field, regardless of match type, before actually matching. The list may be empty. The type value can be one of the following:

```
    p4_match_type.P4_MATCH_EXACT
    p4_match_type.P4_MATCH_TERNARY
    p4_match_type.P4_MATCH_LPM
    p4_match_type.P4_MATCH_RANGE
    p4_match_type.P4_MATCH_VALID
```

actions

A list of p4 action references representing the possible actions the table can invoke

because of a match. For every packet presented to the table, one of these actions *must* be invoked on it (even on a miss).

• action_profile

A p4_action_profile reference for tables with action indirection. None if the attribute was not present in the P4 table declaration.

• min size

An int specifying the hard requirement minimum number of entries that must be installable in the table. None if the attribute was not present in the P4 table declaration.

max size

An int specifying the upper bound maximum number of entries the programmer expects to be installed into the table. None if the attribute was not present in the P4 table declaration.

next_

This attribute can be one of two objects:

o An OrderedDict which maps actions that the table can execute to the next node in the table graph which must follow that action (either a p4_table or a p4_conditional_node, see below). A table is guaranteed to have one key for each element in its actions attribute. Values may be None, meaning that the packet has reached the end of the current pipeline and should enter the queueing or egress systems.

The dictionary order is arbitrary and not guaranteed to be consistent across compiler runs.

o An OrderedDict which maps Python strings "hit" and "miss" to the next nodes in the table graph which must follow a table hit and a table miss. Values may be None, meaning that the packet has reached the end of the current pipeline and should enter the queueing or egress systems.

The dictionary order is arbitrary and not guaranteed to be consistent across compiler runs.

• support timeout

A boolean value. True indicates that the table supports ageing. The runtime is in charge of exposing APIs to set the time-to-live value for entries.

attached_counters

The p4 counter objects bound to this table.

• attached_meters

The p4 meter objects bound to this table.

• attached registers

The p4 register objects bound to this table.

p4_conditional_node

P4 control functions do not exist in the HLIR. The flow of a P4 program is *entirely* represented by the set of p4_tables and special p4_conditional_node classes. Each conditional branch (if statement) in the P4 program is modeled by a p4_conditional_node object. p4_conditional_node is a subclass of p4_node. It defines the following additional attributes:

name

A unique string name assigned to the conditional node, of the form "_condition_N", where N is an arbitrary integer

condition

The boolean condition expression deciding whether to take the True path or the False path, as a p4 expression object

next_

An OrderedDict mapping possible result values of the condition expression to the table graph node (a p4_table or p4_conditional_node) which is visited in that case. Presently, since only boolean conditions are allowed, the only possible keys are True and False. A node is guaranteed to have both keys, though their values may be None (indicating an exit from the current pipeline).

If either code block of the branch was empty, the appropriate next value points to the node which followed the whole statement in the original control flow program.

The name attribute of each node is used as a key in the p4_conditional_node object collection.

p4_action_profile

name

The action profile's name, as taken from the P4 program

actions

A list of p4 action references included in this action profile.

SIZE

An int specifying the upper bound maximum number of entries the programmer expects to be installed into the table.

• selector

The $p4_action_selector$ that can be used to select a member (i.e. an action entry) from within a group in the action table. None if no selector is to be used with the action profile.

p4_action_selector

selection_key

The p4 field list calculation to use to choose members from groups.

• selection_mode

Either "resilient" or "non-resilient".

p4_counter

There is one p4_counter object for each counter object defined in the P4 program. The original P4 name is used as a key in the object collection. Each contains the following attributes:

name

The counter array's name, as taken from the P4 program

type

Either the special value P4_COUNTER_BYTES or P4_COUNTER_PACKETS, indicating whether the counter counts bytes or packets

• min width

The minimum width in bits, as an int, that the compiler must allocate per cell in the counter array

saturating

A boolean recording whether or not the counters should saturate

The number of cells in the array is determined either through the binding attribute or the instance_count attribute. The frontend guarantees that exactly one will be defined, and the other will have the value <code>None</code>:

binding

A tuple (binding_type, table_ref) where binding_type is one of the special values P4_DIRECT or P4_STATIC, and table_ref is a reference to the p4_table object the counter array is bound to. If direct mapped, the frontend guarantees that this counter object is not referenced by any action in the program. If statically mapped, the frontend guarantees that this counter object is only referenced by actions invoked by the table it is bound to.

• instance_count

The number of cells in the array, as an int.

p4_meter

There is one p4_meter object for each meter object defined in the P4 program. The original P4 name is used as a key in the object collection. Each contains the following attributes:

name

The meter array's name, as taken from the P4 program

type

Either the special value P4_COUNTER_BYTES or P4_COUNTER_PACKETS, indicating whether the meter is measuring bytes or packets

The number of cells in the array is determined either through the binding attribute or the instance_count attribute. The frontend guarantees that exactly one will be defined, and the other will have the value <code>None</code>:

• binding

A tuple (binding_type, table_ref) where binding_type is one of the special values P4_DIRECT or P4_STATIC, and table_ref is a reference to the p4_table object the meter array is bound to. If direct mapped, the frontend guarantees that this meter object is not referenced by any action in the program. If statically mapped, the frontend guarantees that this meter object is only referenced by actions invoked by the table it is bound to.

• instance_count

The number of cells in the array, as an int.

• result

The field where the meter status (usually called a color) is stored.

p4_register

There is one p4_register object for each register object defined in the P4 program. The original P4 name is used as a key in the object collection. Each contains the following attributes:

name

The register array's name, as taken from the P4 program

saturating

A boolean recording whether or not the registers should saturate

signed

A boolean recording whether or not the registers are signed

The register layout is determined either through the layout attribute or the width attribute. The frontend guarantees that exactly one will be defined, and the other will have the value None:

width

Each register cell in the array is a bit string with this bitwidth

layout

This is a reference to a header_type object. Each register cell in the array has the same layout as the header type.

The number of cells in the array is determined either through the binding attribute or the instance_count attribute. The frontend guarantees that exactly one will be defined, and the other will have the value <code>None</code>:

binding

A tuple (binding_type, table_ref) where binding_type is one of the special values P4_DIRECT or P4_STATIC, and table_ref is a reference to the p4_table object the register array is bound to. If direct mapped, the frontend guarantees that this register object is not referenced by any action in the program. If statically mapped, the frontend guarantees that this register object is only referenced by actions invoked by the table it is bound to.

• instance count

The number of cells in the array, as an int.

p4_parser_exception

There is one p4_parser_exception object for each parser_exception object defined in the P4 program. The original P4 name is used as a key in the object collection. Each contains the following attributes:

name

The parser exception name, as taken from the P4 program

• set statements

An ordered list of the P4 set_metadata operations performed in the parser exception. Each operation is represented by a 3-tuple. The first element is always parse_call.set. The second tuple element is a reference to the p4_field being written to. The third tuple element is the value to write, which is either:

- o **An** int.
- A (bit offset, bit width) tuple representing a call to current()
- o Ap4 field reference from a previously extracted header

return_or_drop

The action to take when this exception is raised. It can either be the special value P4_PARSER_DROP if the packet is dropped or a $p4_node$ ($p4_table$ or $p4_conditional_node$) object if the packet needs to be submitted to a control flow node.

Dep

The Dep Python class defines the following attributes:

• from

The parent node for the dependency.

• to

The child node for the dependency.

• fields

A list of p4 field objects which induce the dependency between the two nodes.

dependency_type

One of Dep.REVERSE READ, Dep.SUCCESSOR, Dep.ACTION, Dep.MATCH.

Dep should be used as an abstract class. It defines the following subclasses which can be instantiated:

ReverseReadDep

SuccessorDep

value: the value that conditions whether the child node will be executed. It is a boolean if from is a p4_conditional_node, a set of p4_action objects (or "hit" / "miss") if from is a p4_table

ActionDep

MatchDep

In all cases, these objects have filename and lineno attributes recording where in the original code they showed up. An optional doc attribute contains a programmer-provided docstring.

The frontend guarantees that the HLIR contains a parse state entitled start, and that the parse graph anchored at start exits to a table graph node at some point. A global variable $p4_ingress_ptr$ stores a dict whose keys are all possible table graph nodes the parser can exit to. The key's value is a set of the parse states which can branch to it. Another global variable, $p4_egress_ptr$, points directly to the first table graph node in the egress pipeline, if it exists (None if not).