# BCurve

### P. Baillehache

# April 21, 2018

# Contents

1	Definitions	2
	1.1 BCurve definition	2
	1.2 BCurve from cloud points	3
	1.3 BBody definition	3
2	Interface	4
3	Code	18
	3.1 bcurve.c	18
	3.2 bcurve-inline.c	41
4	Makefile	74
5	Unit tests	<b>7</b> 5
6	Unit tests output	110

# Introduction

BCurve is C library to manipulate geometry based on Bezier curves of any dimension and order.

It offers function to create, clone, load, save and modify a geometry, to print it, to scale, rotate (in 2D) or translate it, to get the weights (coefficients of each control point given the value of the parameter of the curve), and to get the bounding box.

BCurve objects are Bezier curves from 1D to ND. For BCurve object, the library offers functions to get its approximate length (sum of distance between control points), and to create a BCurve connecting points of a point cloud.

SCurve objects are a set of BCurve (called segments) continuously connected and has the same interface as for a BCurve, plus function to add and remove segments.

BBody objects are extension of BCurve objects for the case MD to ND. If M equals 1 it is equivalent to a BCurve. If M equals 2 it is equivalent to a surface in ND. If M equals 3 it is equivalent of a volume. Note that by using one dimension as the time dimension one can describes the movement of a curve, surface, etc... over time. The library offers the same functions for a BBody as for a BCurve.

It uses the PBErr, PBMath, GSet, Shapoid libraries.

### 1 Definitions

#### 1.1 BCurve definition

A BCurve B is defined by its dimension  $D \in \mathbb{N}_+^*$ , its order  $O \in \mathbb{N}_+$  and its (O+1) control points  $\overrightarrow{C_i} \in \mathbb{R}^D$ . The curve in dimension D associated to the BCurve B is defined by  $\overrightarrow{B(t)}$ :

$$\begin{cases}
\overrightarrow{B(t)} = \sum_{i=0}^{O} W_i^O(t) \overrightarrow{C_i} & \text{if } t \in [0.0, 1.0] \\
\overrightarrow{B(t)} = \overrightarrow{C_0} & \text{if } t < 0.0 \\
\overrightarrow{B(t)} = \overrightarrow{C_O} & \text{if } t > 1.0
\end{cases} \tag{1}$$

where, if O = 0

$$W_0^0(t) = 1.0 (2)$$

and if  $O \neq 0$ 

$$\begin{cases} W_0^1(t) = 1.0 - t \\ W_1^1(t) = t \\ W_{-1}^i(t) = 0.0 \\ W_j^i(t) = (1.0 - t)W_j^{i-1}(t) + tW_{j-1}^{i-1}(t) \text{ for } i \in [2, O], j \in [0, i] \end{cases}$$
(3)

### 1.2 BCurve from cloud points

Given the cloud points made of N points  $\overrightarrow{P_i}$ , the  $\overrightarrow{BCurve}$  of order N-1 passing through the N points (in the same order  $\overrightarrow{P_0}, \overrightarrow{P_1}, \overrightarrow{P_2}, \dots$  as given in input) can be obtained as follow.

If N=1 the solution is trivial:  $\overrightarrow{C_0}=\overrightarrow{P_0}$ . As well, if N=2 the solution is trivial:  $\overrightarrow{C_0}=\overrightarrow{P_0}$  and  $\overrightarrow{C_1}=\overrightarrow{P_1}$ .

 $(\overrightarrow{B(t_i)} = \overrightarrow{P_i})$ , we need first to define the N values  $t_i$  corresponding to each  $\overrightarrow{P_i}$ 

$$t_i = \frac{L(\overrightarrow{P_i})}{L(\overrightarrow{P_{N-1}})} \tag{4}$$

where

$$\begin{cases}
L(P_0) = 0.0 \\
L(P_i) = \sum_{j=1}^{i} \left| \left| \overrightarrow{P_{j-1}} \overrightarrow{P_j} \right| \right|
\end{cases}$$
(5)

then we can calculate the  $C_i$  as follow. We have  $\overrightarrow{C_0} = \overrightarrow{P_0}$  and  $\overrightarrow{C_{N-1}} = \overrightarrow{P_{N-1}}$ , and others  $\overrightarrow{C_i}$  can be obtained by solving the linear system below for each dimension:

$$\begin{bmatrix} W_{1}^{N-1}(t_{1}) & \dots & W_{N-2}^{N-1}(t_{1}) \\ \dots & \dots & \dots \\ W_{1}^{N-1}(t_{N-2}) & \dots & W_{N-2}^{N-1}(t_{N-2}) \end{bmatrix} \begin{bmatrix} C_{1} \\ \dots \\ C_{N-2} \end{bmatrix} = \\ \begin{bmatrix} P_{1} - \left(W_{0}^{N-1}(t_{1})P_{0} + W_{N-1}^{N-1}(t_{1})P_{N-1}\right) \\ \dots \\ P_{N-2} - \left(W_{0}^{N-1}(t_{N-2})P_{0} + W_{N-1}^{N-1}(t_{N-2})P_{N-1}\right) \end{bmatrix}$$

$$(6)$$

# 1.3 BBody definition

A BBody A is defined by its input dimension  $D_i \in \mathbb{N}_+^*$ , its output dimension  $D_o \in \mathbb{N}_+^*$ , its order  $O \in \mathbb{N}_+$  and its  $(O+1)^{D_i}$  control points  $\overrightarrow{C}_i \in \mathbb{R}^{D_o}$ . Control points indices are ordered as follow (for an example BBody with  $D_i = 3$ ): (0,0,0),(0,0,1),...,(0,0,0+1),(0,1,0),(0,1,1),...

Note that if  $D_i$  is equal to 1, a BBody is equivalent to a BCurve.

The function  $\overrightarrow{A}():[0.0,1.0]^{D_i}\mapsto \mathbb{R}^{D_o}$  associated to the BBody A is defined by:

$$\overrightarrow{A}(\overrightarrow{u}) = \overrightarrow{R_A}(\overrightarrow{0}, \overrightarrow{u}, 0) \tag{7}$$

where

$$\begin{cases}
\overrightarrow{R_A}(\overrightarrow{c}, \overrightarrow{u}, d) = \overrightarrow{B_{\{\overrightarrow{C}_{I(\overrightarrow{c}, d)}\}}}(u_d) & \text{if } d = D_i - 1 \\
\overrightarrow{R_A}(\overrightarrow{c}, \overrightarrow{u}, d) = \overrightarrow{B_{\{\overrightarrow{R_S}(\{\overrightarrow{c}\}_d, \overrightarrow{u}, d+1)\}}}(u_d) & \text{if } d \neq D_i - 1
\end{cases}$$
(8)

where  $\overrightarrow{B_{\{\bullet\}}}$  is the BCurve of dimension  $D_o$ , order O and control points  $\bullet$ . And  $\{\overrightarrow{C}_{I(\overrightarrow{c},d)}\}$  is the set of control points of S of indices:

$$\{I(\overrightarrow{c},d)\} = \{ \sum_{i \in [0,D_i-1]|i \neq d} \left( O^{(D_i-1-i)} c_i \right) + O^{(D_i-1-d)} j \}_{j \in [0,O]}$$
 (9)

and  $\{\overrightarrow{R_A}(\{\overrightarrow{c}\}_d, \overrightarrow{u}, d')\}$  is the set of intermediate control points calculated for:

$$\{\overrightarrow{c}\}_d = \{(\overrightarrow{c_0, c_1, ..., c_{d-1}, j, c_{d+1}, ..., c_{D_i-1}})\}_{j \in [0, O]}$$
(10)

### 2 Interface

```
// ====== BCURVE.H =======
#ifndef BCURVE_H
#define BCURVE_H
// ========== Include =========
#include <stdlib.h>
#include <stdio.h>
#include <math.h>
#include <string.h>
#include <stdbool.h>
#include "pberr.h"
#include "pbmath.h"
#include "gset.h"
#include "shapoid.h"
// ====== Define ========
// ----- BCurve
// ========= Data structure ==========
typedef struct BCurve {
 // Order
 int _order;
 // Dimension
 int _dim;
 // array of (_order + 1) control points (vectors of dimension _dim)
 // defining the curve
 VecFloat** _ctrl;
```

```
} BCurve;
// ======== Functions declaration ==========
// Create a new BCurve of order 'order' and dimension 'dim'
BCurve* BCurveCreate(int order, int dim);
// Clone the BCurve
BCurve* BCurveClone(BCurve* that);
// Load the BCurve from the stream
// If the BCurve is already allocated, it is freed before loading
// Return true upon success, false else
bool BCurveLoad(BCurve** that, FILE* stream);
// Save the BCurve to the stream
// Return true upon success, false else
bool BCurveSave(BCurve* that, FILE* stream);
// Free the memory used by a BCurve
void BCurveFree(BCurve** that);
// Print the BCurve on 'stream'
void BCurvePrint(BCurve* that, FILE* stream);
// Set the value of the iCtrl-th control point to \boldsymbol{v}
#if BUILDMODE != 0
inline
#endif
void BCurveSetCtrl(BCurve* that, int iCtrl, VecFloat* v);
// Get a copy of the iCtrl-th control point
#if BUILDMODE != 0
inline
#endif
VecFloat* BCurveGetCtrl(BCurve* that, int iCtrl);
// Get the iCtrl-th control point
#if BUILDMODE != 0
inline
#endif
VecFloat* BCurveCtrl(BCurve* that, int iCtrl);
// Get the value of the BCurve at paramater 'u'
// u can extend beyond [0.0, 1.0]
VecFloat* BCurveGet(BCurve* that, float u);
// Get the order of the BCurve
#if BUILDMODE != 0
inline
#endif
int BCurveGetOrder(BCurve* that);
// Get the dimension of the BCurve
#if BUILDMODE != 0
inline
int BCurveGetDim(BCurve* that);
// Get the approximate length of the BCurve (sum of dist between
// control points)
#if BUILDMODE != 0
```

```
inline
#endif
float BCurveGetApproxLen(BCurve* that);
// Return the center of the BCurve (average of control points)
#if BUILDMODE != 0
inline
#endif
VecFloat* BCurveGetCenter(BCurve* that);
// Rotate the curve CCW by 'theta' radians relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void BCurveRotOrigin(BCurve* that, float theta);
// Rotate the curve CCW by 'theta' radians relatively to its
// first control point
#if BUILDMODE != 0
inline
#endif
void BCurveRotStart(BCurve* that, float theta);
// Rotate the curve CCW by 'theta' radians relatively to its
// center
#if BUILDMODE != 0
inline
#endif
void BCurveRotCenter(BCurve* that, float theta);
// Scale the curve by 'v' relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleOriginVector(BCurve* that, VecFloat* v);
// Scale the curve by 'c' relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleOriginScalar(BCurve* that, float c);
// Scale the curve by 'v' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleStartVector(BCurve* that, VecFloat* v);
// Scale the curve by 'c' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
void _BCurveScaleStartScalar(BCurve* that, float c);
// Scale the curve by 'v' relatively to its center
// (average of control points)
#if BUILDMODE != 0
```

```
inline
#endif
void _BCurveScaleCenterVector(BCurve* that, VecFloat* v);
// Scale the curve by 'c' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleCenterScalar(BCurve* that, float c);
// Translate the curve by 'v'
#if BUILDMODE != 0
inline
#endif
void _BCurveTranslate(BCurve* that, VecFloat* v);
// Create a BCurve which pass through the points given in the GSet 'set'
// The GSet must contains VecFloat of same dimensions
// The BCurve pass through the points in the order they are given
// in the GSet. The points don't need to be uniformly distributed
// The created BCurve is of same dimension as the VecFloat and of order
// equal to the number of VecFloat in 'set' minus one
// Return NULL if it couldn't create the BCurve
BCurve* BCurveFromCloudPoint(GSetVecFloat* set);
// Get a VecFloat of dimension equal to the number of control points
// Values of the VecFloat are the weight of each control point in the
// BCurve given the curve's order and the value of 't' (in [0.0,1.0])
VecFloat* BCurveGetWeightCtrlPt(BCurve* that, float t);
// Get the bounding box of the BCurve.
// Return a Facoid whose axis are aligned on the standard coordinate
// system.
Facoid* BCurveGetBoundingBox(BCurve* that);
// ----- SCurve
// ======= Data structure =========
typedef struct SCurve {
  // Order
  int _order;
  // Dimension
  int _dim;
  // Number of segments (one segment equals one BCurve)
  int _nbSeg;
  // Set of BCurve
  GSetBCurve _seg;
  // Set of control points
  GSetVecFloat _ctrl;
} SCurve;
// ======= Functions declaration ===========
// Create a new SCurve of dimension 'dim', order 'order' and
// 'nbSeg' segments
SCurve* SCurveCreate(int order, int dim, int nbSeg);
// Clone the SCurve
SCurve* SCurveClone(SCurve* that);
```

```
// Return a new SCurve as a copy of the SCurve 'that' with
// dimension changed to 'dim'
// if it is extended, the values of new components are 0.0
// If it is shrinked, values are discarded from the end of the vectors
SCurve* SCurveGetNewDim(SCurve* that, int dim);
// Load the SCurve from the stream
// If the SCurve is already allocated, it is freed before loading
// Return true in case of success, false else
bool SCurveLoad(SCurve** that, FILE* stream);
// Save the SCurve to the stream
// Return true upon success, false else
bool SCurveSave(SCurve* that, FILE* stream);
// Free the memory used by a SCurve
void SCurveFree(SCurve** that);
// Print the SCurve on 'stream'
void SCurvePrint(SCurve* that, FILE* stream);
// Get the number of BCurve in the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetNbSeg(SCurve* that);
// Get the dimension of the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetDim(SCurve* that);
// Get the order of the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetOrder(SCurve* that);
// Get the number of control point in the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetNbCtrl(SCurve* that);
// Get a clone of the 'iCtrl'-th control point
#if BUILDMODE != 0
inline
#endif
VecFloat* SCurveGetCtrl(SCurve* that, int iCtrl);
// Set the 'iCtrl'-th control point to 'v'
#if BUILDMODE != 0
inline
#endif
void SCurveSetCtrl(SCurve* that, int iCtrl, VecFloat* v);
// Get the 'iCtrl'-th control point
#if BUILDMODE != 0
inline
#endif
VecFloat* SCurveCtrl(SCurve* that, int iCtrl);
```

```
// Get the GSet of control points of the SCurve 'that'
#if BUILDMODE != 0
inline
#endif
GSetVecFloat* SCurveCtrls(SCurve* that);
// Get a clone of the 'iSeg'-th segment
#if BUILDMODE != 0
inline
#endif
BCurve* SCurveGetSeg(SCurve* that, int iSeg);
// Get the 'iSeg'-th segment
#if BUILDMODE != 0
inline
#endif
BCurve* SCurveSeg(SCurve* that, int iSeg);
// Get the GSet of segments of the SCurve 'that'
#if BUILDMODE != 0
inline
#endif
GSetBCurve* SCurveSegs(SCurve* that);
\ensuremath{//} Add one segment at the end of the curve (controls are set to
// vectors null, except the first one which the last one of the current
// last segment)
void SCurveAddSegTail(SCurve* that);
// Add one segment at the head of the curve (controls are set to
// vectors null, except the last one which the first one of the current
// first segment)
void SCurveAddSegHead(SCurve* that);
// Remove the fist segment of the curve (which must have more than one
// segment)
void SCurveRemoveHeadSeg(SCurve* that);
// Remove the last segment of the curve (which must have more than one
// segment)
void SCurveRemoveTailSeg(SCurve* that);
// Get the approximate length of the SCurve (sum of approxLen
// of its BCurves)
#if BUILDMODE != 0
inline
#endif
float SCurveGetApproxLen(SCurve* that);
// Return the center of the SCurve (average of control points)
#if BUILDMODE != 0
inline
#endif
VecFloat* SCurveGetCenter(SCurve* that);
// Get the value of the SCurve at paramater 'u'
// The value is equal to the value of the floor(u)-th segment at
// value (u - floor(u))
// u can extend beyond [0.0, _nbSeg]
#if BUILDMODE != 0
inline
```

```
#endif
VecFloat* SCurveGet(SCurve* that, float u);
// Return the max value for the parameter 'u' of SCurveGet
#if BUILDMODE != 0
inline
#endif
float SCurveGetMaxU(SCurve* that);
// Get the bounding box of the SCurve.
// Return a Facoid whose axis are aligned on the standard coordinate
// system.
Facoid* SCurveGetBoundingBox(SCurve* that);
// Rotate the curve CCW by 'theta' radians relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void SCurveRotOrigin(SCurve* that, float theta);
// Rotate the curve CCW by 'theta' radians relatively to its
// first control point
#if BUILDMODE != 0
inline
#endif
void SCurveRotStart(SCurve* that, float theta);
// Rotate the curve CCW by 'theta' radians relatively to its
// center
#if BUILDMODE != 0
inline
#endif
void SCurveRotCenter(SCurve* that, float theta);
// Scale the curve by 'v' relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleOriginVector(SCurve* that, VecFloat* v);
// Scale the curve by 'c' relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleOriginScalar(SCurve* that, float c);
// Scale the curve by 'v' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleStartVector(SCurve* that, VecFloat* v);
// Scale the curve by 'c' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleStartScalar(SCurve* that, float c);
```

```
// Scale the curve by 'v' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleCenterVector(SCurve* that, VecFloat* v);
// Scale the curve by 'c' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleCenterScalar(SCurve* that, float c);
// Translate the curve by 'v'
#if BUILDMODE != 0
inline
#endif
void _SCurveTranslate(SCurve* that, VecFloat* v);
// Create a new SCurve from the outline of the Shapoid 'shap'
// The Shapoid must be of dimension 2
// Control points are ordered CCW of the Shapoid
#if BUILDMODE != 0
inline
#endif
SCurve* SCurveCreateFromShapoid(Shapoid* shap);
// Create a new SCurve from the outline of the Facoid 'shap'
// The Facoid must be of dimension 2
// Control points are ordered CCW of the Shapoid
SCurve* SCurveCreateFromFacoid(Facoid* shap);
// Create a new SCurve from the outline of the Pyramidoid 'shap'
// The Pyramidoid must be of dimension 2
// Control points are ordered CCW of the Shapoid
SCurve* SCurveCreateFromPyramidoid(Pyramidoid* shap);
// Create a new SCurve from the outline of the Spheroid 'shap'
// The Spheroid must be of dimension 2
// Control points are ordered CCW of the Shapoid
// Calculate an approximation as there is no exact solution
SCurve* SCurveCreateFromSpheroid(Spheroid* shap);
// Get the distance between the SCurve 'that' and the SCurve 'curve'
// The distance is defined as the integral of
// ||'that'(u(t))-'curve'(v(t))|| where u and v are the relative
// positions on the curve over t varying from 0.0 to 1.0
float SCurveGetDistToCurve(SCurve* that, SCurve* curve);
// ----- SCurveIter
// ======== Data structure ==========
typedef struct SCurveIter {
  // Attached SCurve
  SCurve* _curve;
  // Current position
  float _curPos;
  // Step delta
  float _delta;
```

```
} SCurveIter;
// ======== Functions declaration ==========
// Create a new SCurveIter attached to the SCurve 'curve' with a step
// of 'delta'
SCurveIter SCurveIterCreateStatic(SCurve* curve, float delta);
// Set the attached SCurve of the SCurveIter 'that' to 'curve'
#if BUILDMODE != 0
inline
#endif
void SCurveIterSetCurve(SCurveIter* that, SCurve* curve);
// Set the delta of the SCurveIter 'that' to 'delta'
#if BUILDMODE != 0
inline
#endif
void SCurveIterSetDelta(SCurveIter* that, float delta);
// Get the attached curve of the SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
SCurve* SCurveIterCurve(SCurveIter* that);
// Get the delta of the SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
float SCurveIterGetDelta(SCurveIter* that);
// Init the SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
void SCurveIterInit(SCurveIter* that);
// Step the SCurveIter 'that'
// Return false if it couldn't step, true else
#if BUILDMODE != 0
inline
#endif
bool SCurveIterStep(SCurveIter* that);
// Step back the SCurveIter 'that'
// Return false if it couldn't step, true else
#if BUILDMODE != 0
inline
#endif
bool SCurveIterStepP(SCurveIter* that);
// Get the current value of the internal parameter of the
// SCurveIter 'that'
#if BUILDMODE != 0
inline
float SCurveIterGetPos(SCurveIter* that);
// Get the current value of the attached SCurve at the current
// internal position of the SCurveIter 'that'
#if BUILDMODE != 0
```

```
inline
#endif
VecFloat* SCurveIterGet(SCurveIter* that);
// ----- BBody
// ====== Data structure =========
typedef struct BBody {
  // Order
  int _order;
  // Dimensions (input/output) (for example (2,3) gives a surface in 3D)
  VecShort2D _dim;
  // ((_order + 1) ^ _dim[0]) control points of the surface
  // they are ordered as follow:
  // (0,0,0),(0,0,1),...,(0,0,order+1),(0,1,0),(0,1,1),...
  VecFloat** _ctrl;
} BBody;
// ========= Functions declaration ==========
// Create a new BBody of order 'order' and dimension 'dim'
// Controls are initialized with null vectors
BBody* BBodyCreate(int order, VecShort2D* dim);
// Free the memory used by a BBody
void BBodyFree(BBody** that);
// Set the value of the iCtrl-th control point to v
#if BUILDMODE != 0
inline
#endif
void _BBodySetCtrl(BBody* that, VecShort* iCtrl, VecFloat* v);
// Get the value of the BBody at paramater 'u'
// u can extend beyond [0.0, 1.0]
VecFloat* _BBodyGet(BBody* that, VecFloat* u);
// Get the number of control points of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
int BBodyGetNbCtrl(BBody* that);
// Get the the 'iCtrl'-th control point of 'that'
#if BUILDMODE != 0
inline
#endif
VecFloat* _BBodyCtrl(BBody* that, VecShort* iCtrl);
// Get the index in _ctrl of the 'iCtrl' control point of 'that'
#if BUILDMODE != 0
inline
#endif
int _BBodyGetIndexCtrl(BBody* that, VecShort* iCtrl);
// Get the order of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
int BBodyGetOrder(BBody* that);
```

```
// Get the dimensions of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
VecShort2D* BBodyDim(BBody* that);
// Get a copy of the dimensions of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
VecShort2D BBodyGetDim(BBody* that);
// Return a clone of the BBody 'that'
BBody* BBodyClone(BBody* that);
// Print the BBody 'that' on the stream 'stream'
void BBodyPrint(BBody* that, FILE* stream);
// Load the BBody from the stream
// If the BBody is already allocated, it is freed before loading
// Return true upon success, false else
bool BBodyLoad(BBody** that, FILE* stream);
// Save the BBody to the stream
// Return true upon success, false else
bool BBodySave(BBody* that, FILE* stream);
// Return the center of the BBody (average of control points)
#if BUILDMODE != 0
inline
#endif
VecFloat* BBodyGetCenter(BBody* that);
// Translate the BBody by 'v'
#if BUILDMODE != 0
inline
#endif
void _BBodyTranslate(BBody* that, VecFloat* v);
// Scale the curve by 'v' relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleOriginVector(BBody* that, VecFloat* v);
// Scale the curve by 'c' relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleOriginScalar(BBody* that, float c);
// Scale the curve by 'v' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleStartVector(BBody* that, VecFloat* v);
// Scale the curve by 'c' relatively to its origin
// (first control point)
```

```
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleStartScalar(BBody* that, float c);
// Scale the curve by 'v' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleCenterVector(BBody* that, VecFloat* v);
// Scale the curve by 'c' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleCenterScalar(BBody* that, float c);
\ensuremath{//} Get the bounding box of the BBody.
// Return a Facoid whose axis are aligned on the standard coordinate
// system.
Facoid* BBodyGetBoundingBox(BBody* that);
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around 'axis'
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotAxisOrigin(BBody* that, VecFloat3D* axis, float theta);
// Rotate the BBody by 'theta' relatively to the center
// of the body around 'axis'
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotAxisCenter(BBody* that, VecFloat3D* axis, float theta);
// Rotate the BBody by 'theta' relatively to the first control point
\label{eq:condition} \parbox{$^{\prime\prime}$ of the body around 'axis'}
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotAxisStart(BBody* that, VecFloat3D* axis, float theta);
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around {\tt X}
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotXOrigin(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the center
// of the body around X
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
```

```
void BBodyRotXCenter(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the first control point
// of the body around X
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotXStart(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around {\tt Y}
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotYOrigin(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the center
// of the body around Y
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotYCenter(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the first control point
// of the body around Y
// \dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotYStart(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around Z
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotZOrigin(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the center
// of the body around Z
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotZCenter(BBody* that, float theta);
// Rotate the BBody by 'theta' relatively to the first control point
// of the body around Z
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotZStart(BBody* that, float theta);
// ======== Polymorphism =========
#define BCurveTranslate(Curve, Vec) _Generic(Vec, \
  VecFloat*: _BCurveTranslate, \
```

```
VecFloat2D*: _BCurveTranslate, \
 VecFloat3D*: _BCurveTranslate, \
 default: PBErrInvalidPolymorphism)(Curve, (VecFloat*)(Vec))
#define SCurveTranslate(Curve, Vec) _Generic(Vec, \
 VecFloat*: _SCurveTranslate, \
 VecFloat2D*: _SCurveTranslate, \
 VecFloat3D*: _SCurveTranslate, \
 default: PBErrInvalidPolymorphism)(Curve, (VecFloat*)(Vec))
#define BBodyTranslate(Body, Vec) _Generic(Vec, \
 VecFloat*: _BBodyTranslate, \
 VecFloat2D*: _BBodyTranslate, \
 VecFloat3D*: _BBodyTranslate, \
 default: PBErrInvalidPolymorphism)(Body, (VecFloat*)(Vec))
#define BCurveScaleOrigin(Curve, Scale) _Generic(Scale, \
 VecFloat*: _BCurveScaleOriginVector, \
 float: _BCurveScaleOriginScalar, \
 default: PBErrInvalidPolymorphism)(Curve, Scale)
#define BCurveScaleStart(Curve, Scale) _Generic(Scale, \
 VecFloat*: _BCurveScaleStartVector, \
 float: _BCurveScaleStartScalar, \
 default: PBErrInvalidPolymorphism)(Curve, Scale)
#define BCurveScaleCenter(Curve, Scale) _Generic(Scale, \
 VecFloat*: _BCurveScaleCenterVector, \
 float: _BCurveScaleCenterScalar, \
 default: PBErrInvalidPolymorphism)(Curve, Scale)
#define BBodyScaleOrigin(Body, Scale) _Generic(Scale, \
 VecFloat*: _BBodyScaleOriginVector, \
 float: _BBodyScaleOriginScalar, \
 default: PBErrInvalidPolymorphism)(Body, Scale)
#define BBodyScaleStart(Body, Scale) _Generic(Scale, \
 VecFloat*: _BBodyScaleStartVector, \
 float: _BBodyScaleStartScalar, \
 default: PBErrInvalidPolymorphism)(Body, Scale)
#define BBodyScaleCenter(Body, Scale) _Generic(Scale, \
 VecFloat*: _BBodyScaleCenterVector, \
 float: _BBodyScaleCenterScalar, \
 default: PBErrInvalidPolymorphism) (Body, Scale)
VecFloat*: _SCurveScaleOriginVector, \
 float: _SCurveScaleOriginScalar, \
 default: PBErrInvalidPolymorphism)(Curve, Scale)
#define SCurveScaleStart(Curve, Scale) _Generic(Scale, \
 VecFloat*: _SCurveScaleStartVector, \
 float: _SCurveScaleStartScalar, \
 default: PBErrInvalidPolymorphism)(Curve, Scale)
#define SCurveScaleCenter(Curve, Scale) _Generic(Scale, \
 VecFloat*: _SCurveScaleCenterVector, \
 float: _SCurveScaleCenterScalar, \
 default: PBErrInvalidPolymorphism)(Curve, Scale)
#define BBodyGetIndexCtrl(Body, ICtrl) _Generic(ICtrl, \
```

```
VecShort*: _BBodyGetIndexCtrl, \
  VecShort2D*: _BBodyGetIndexCtrl, \
  VecShort3D*: _BBodyGetIndexCtrl, \
VecShort4D*: _BBodyGetIndexCtrl, \
  default: PBErrInvalidPolymorphism)(Body, (VecShort*)(ICtrl))
#define BBodyGet(Body, U) _Generic(U, \
  VecFloat*: _BBodyGet, \
  VecFloat2D*: _BBodyGet, \
  VecFloat3D*: _BBodyGet, \
  default: PBErrInvalidPolymorphism)(Body, (VecFloat*)(U))
#define BBodyCtrl(Body, ICtrl) _Generic(ICtrl, \
  VecShort*: _BBodyCtrl, \
  VecShort2D*: _BBodyCtrl, \
  VecShort3D*: _BBodyCtrl, \
VecShort4D*: _BBodyCtrl, \
  default: PBErrInvalidPolymorphism)(Body, (VecShort*)(ICtrl))
#define BBodySetCtrl(Body, ICtrl, Vec) _Generic(ICtrl, \
  VecShort*: _Generic(Vec, \
    VecFloat*: _BBodySetCtrl, \
    VecFloat2D*: _BBodySetCtrl, \
    VecFloat3D*: _BBodySetCtrl, \
    default: PBErrInvalidPolymorphism), \
  VecShort2D*: _Generic(Vec, \
    VecFloat*: _BBodySetCtrl, \
    VecFloat2D*: _BBodySetCtrl, \
VecFloat3D*: _BBodySetCtrl, \
    default: PBErrInvalidPolymorphism), \
  VecShort3D*: _Generic(Vec, \
    VecFloat*: _BBodySetCtrl, \
    VecFloat2D*: _BBodySetCtrl, \
    VecFloat3D*: _BBodySetCtrl, \
    default: PBErrInvalidPolymorphism), \
  VecShort4D*: _Generic(Vec, \
    VecFloat*: _BBodySetCtrl, \
    VecFloat2D*: _BBodySetCtrl, \
VecFloat3D*: _BBodySetCtrl, \
    default: PBErrInvalidPolymorphism), \
  default: PBErrInvalidPolymorphism)(Body, (VecShort*)(ICtrl), \
    (VecFloat*)(Vec))
// ======= Inliner ========
#if BUILDMODE != 0
#include "bcurve-inline.c"
#endif
```

### 3 Code

#endif

### 3.1 bcurve.c

```
// ====== BCURVE.C =======
```

```
// ========== Include =========
#include "bcurve.h"
#if BUILDMODE == 0
#include "bcurve-inline.c"
// ----- BCurve
// ====== Functions implementation ========
// Create a new BCurve of order 'order' and dimension 'dim'
BCurve* BCurveCreate(int order, int dim) {
#if BUILDMODE == 0
  if (order < 0) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Invalid order (%d>=0)", order);
   PBErrCatch(BCurveErr);
  if (dim < 1) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Invalid dimension (%d>=1)", dim);
    PBErrCatch(BCurveErr);
#endif
  // Allocate memory
  BCurve* that = PBErrMalloc(BCurveErr, sizeof(BCurve));
  // Set the values
  that->_dim = dim;
  that->_order = order;
  // Allocate memory for the array of control points
  that->_ctrl = PBErrMalloc(BCurveErr, sizeof(VecFloat*) * (order + 1));
  // For each control point
  for (int iCtrl = order + 1; iCtrl--;)
    // Allocate memory
    that->_ctrl[iCtrl] = VecFloatCreate(dim);
  // Return the new BCurve
 return that;
// Clone the BCurve
BCurve* BCurveClone(BCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
  // Allocate memory for the clone
  BCurve* clone = PBErrMalloc(BCurveErr, sizeof(BCurve));
  \ensuremath{//} Clone the properties
  clone->_dim = that->_dim;
  clone->_order = that->_order;
  \ensuremath{//} Allocate memory for the array of control points
  clone->_ctrl = PBErrMalloc(BCurveErr, sizeof(VecFloat*) *
    (clone->_order + 1));
  // For each control point
  for (int iCtrl = clone->_order + 1; iCtrl--;)
    // Clone the control point
    clone->_ctrl[iCtrl] = VecClone(that->_ctrl[iCtrl]);
  // Return the clone
```

```
return clone;
}
// Load the BCurve from the stream
// If the BCurve is already allocated, it is freed before loading
// Return true upon success, false else
bool BCurveLoad(BCurve** that, FILE* stream) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (stream == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'stream' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  // If 'that' is already allocated
  if (*that != NULL)
    // Free memory
    BCurveFree(that);
  // Read the order and dimension
  int order;
  int dim;
  int ret = fscanf(stream, "%d %d", &order, &dim);
  // If we couldn't read
  if (ret == EOF)
   return false;
  // Allocate memory
  *that = BCurveCreate(order, dim);
  // For each control point
  for (int iCtrl = 0; iCtrl < (order + 1); ++iCtrl) {</pre>
    // Load the control point
    ret = VecLoad((*that)->_ctrl + iCtrl, stream);
    // If we couldn't read the control point or the control point
    // is not of the correct dimension
    if (ret == false || VecGetDim((*that)->_ctrl[iCtrl]) != (*that)->_dim)
      return false;
  // Return success code
 return true;
// Save the BCurve to the stream
// Return true upon success, false else
bool BCurveSave(BCurve* that, FILE* stream) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (stream == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'stream' is null");
   PBErrCatch(BCurveErr);
  }
#endif
  \ensuremath{//} Save the order and dimension
  int ret = fprintf(stream, "%d %d\n", that->_order, that->_dim);
```

```
// If the fprintf failed
  if (ret < 0)
    // Stop here
    return false;
  // For each control point
  for (int iCtrl = 0; iCtrl < that->_order + 1; ++iCtrl) {
    // Save the control point
    ret = VecSave(that->_ctrl[iCtrl], stream);
    // If we couldn't save the control point
    if (ret == false)
      // Stop here
      return false;
  // Return success code
 return true;
// Free the memory used by a BCurve
void BCurveFree(BCurve** that) {
  // Check argument
  if (that == NULL || *that == NULL)
   return;
  // If there are control points
  if ((*that)->_ctrl != NULL)
    // For each control point
    for (int iCtrl = (*that)->_order + 1; iCtrl--;)
      // Free the control point
      VecFree((*that)->_ctrl + iCtrl);
  // Free the array of control points
  free((*that)->_ctrl);
  // Free memory
  free(*that);
  *that = NULL;
}
// Print the BCurve on 'stream'
void BCurvePrint(BCurve* that, FILE* stream) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (stream == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'stream' is null");
   PBErrCatch(BCurveErr);
#endif
  // Print the order and dim
  fprintf(stream, "order(%d) dim(%d) ", that->_order, that->_dim);
  // For each control point
  for (int iCtrl = 0; iCtrl < that->_order + 1; ++iCtrl) {
    VecPrint(that->_ctrl[iCtrl], stream);
    if (iCtrl < that->_order)
      fprintf(stream, " ");
}
// Get the value of the BCurve at paramater 'u'
// u can extend beyond [0.0, 1.0]
VecFloat* BCurveGet(BCurve* that, float u) {
```

```
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
  // Allocate memory for the result
  VecFloat* v = VecFloatCreate(that->_dim);
  // Declare a variable for calcul
  VecFloat* val = VecFloatCreate(that->_order + 1);
  // Loop on dimension
  for (int dim = that->_dim; dim--;) {
    // Initialise the temporary variable with the value in current
    // dimension of the control points
    for (int iCtrl = 0; iCtrl < that->_order + 1; ++iCtrl)
      VecSet(val, iCtrl, VecGet(that->_ctrl[iCtrl], dim));
    // Loop on order
    int subOrder = that->_order;
    while (subOrder != 0) {
      // Loop on sub order
      for (int order = 0; order < subOrder; ++order)</pre>
        VecSet(val, order,
          (1.0 - u) * VecGet(val, order) + u * VecGet(val, order + 1));
      --subOrder;
    // Set the value for the current dim
    VecSet(v, dim, VecGet(val, 0));
  // Free memory
  VecFree(&val);
  // Return the result
 return v;
}
// Create a BCurve which pass through the points given in the GSet 'set'
// The GSet must contains VecFloat of same dimensions
// The BCurve pass through the points in the order they are given
// in the GSet. The points don't need to be uniformly distributed
// The created BCurve is of same dimension as the VecFloat and of order
// equal to the number of VecFloat in 'set' minus one
// Return NULL if it couldn't create the BCurve
BCurve* BCurveFromCloudPoint(GSetVecFloat* set) {
#if BUILDMODE == 0
  if (set == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'set' is null");
    PBErrCatch(BCurveErr);
  if (GSetNbElem(set) < 1) {</pre>
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'set' is empty");
    PBErrCatch(BCurveErr);
#endif
  // Declare a variable to memorize the result
  int order = GSetNbElem(set) - 1;
  int dim = VecGetDim(GSetGetFirst(set));
  BCurve* curve = BCurveCreate(order, dim);
  // Set the first control point to the first point in the point cloud
  BCurveSetCtrl(curve, 0, GSetGetFirst(set));
  // If the order is greater than 0
```

```
if (order > 0) {
  \ensuremath{//} Set the last control point to the last point in the point cloud
  BCurveSetCtrl(curve, order, GSetGetLast(set));
  // If the order is greater than 1
  if (order > 1) {
    // Calculate the t values for intermediate control points
    \ensuremath{//} They are equal to the relative distance on the polyline
    // linking the point in the point cloud
    // Declare a variable to memorize the dimension of the matrix
    // in the linear system to solve
    VecShort2D dimMat = VecShortCreateStatic2D();
    // Declare a variable to memorize the t values
    VecFloat* t = VecFloatCreate(GSetNbElem(set));
    // Set the dimensions of the matrix of the linear system
    VecSet(&dimMat, 0, order - 1);
    VecSet(&dimMat, 1, order - 1);
    // For each point
   GSetElem* elem = GSetGetElem(set, 1);
    int iPoint = 1;
    while (elem != NULL) {
      // Get the distance from the previous point
      float d = VecDist((VecFloat*)(elem->_prev->_data),
        (VecFloat*)(elem->_data));
      VecSet(t, iPoint, d + VecGet(t, iPoint - 1));
      ++iPoint;
      elem = elem->_next;
    // Normalize t
   for (iPoint = 1; iPoint <= order; ++iPoint)</pre>
     VecSet(t, iPoint, VecGet(t, iPoint) / VecGet(t, order));
    // For each dimension
    for (int iDim = dim; iDim--;) {
      // Declare a variable to memorize the matrix and vector
      // of the linear system
      MatFloat* m = MatFloatCreate(&dimMat);
      VecFloat* v = VecFloatCreate(order - 1);
      // Set the values of the linear system
      // For each line (equivalent to each intermediate point
      // in point cloud)
      for (VecSet(&dimMat, 1, 0);
        VecGet(&dimMat, 1) < order - 1;</pre>
        VecSetAdd(&dimMat, 1, 1)) {
        // Get the weight of the control point at the value
        // of t for this point
        VecFloat* weight =
          BCurveGetWeightCtrlPt(curve, VecGet(t,
          VecGet(&dimMat, 1) + 1));
        // For each intermediate control point
        for (VecSet(&dimMat, 0, 0);
          VecGet(&dimMat, 0) < order - 1;</pre>
          VecSetAdd(&dimMat, 0, 1))
          // Set the matrix value with the corresponding
          // weight
          MatSet(m, &dimMat, VecGet(weight,
           VecGet(&dimMat, 0) + 1));
        // Set the vector value with the corresponding point
        // coordinate
        float x = VecGet((VecFloat*)(GSetGet(set,
          VecGet(&dimMat, 1) + 1)), iDim);
        x -= VecGet(weight, 0) * VecGet(GSetGetFirst(set), iDim);
        x -= VecGet(weight, order) *
          VecGet(GSetGetLast(set), iDim);
```

```
VecSet(v, VecGet(&dimMat, 1), x);
          // Free memory
          VecFree(&weight);
        // Declare a variable to memorize the linear system
        SysLinEq* sys = SysLinEqCreate(m, v);
        // Solve the system
        VecFloat* solSys = SysLinEqSolve(sys);
        // If we could solve the linear system
        if (solSys != NULL) {
         // Memorize the values of control points for the
          // current dimension
         for (int iCtrl = 1; iCtrl < order; ++iCtrl)</pre>
            VecSet(curve->_ctrl[iCtrl], iDim,
             VecGet(solSys, iCtrl - 1));
          // Free memory
         VecFree(&solSys);
        } else {
          // Free memory
         SysLinEqFree(&sys);
         VecFree(&v);
         MatFree(&m);
         VecFree(&t);
         BCurveFree(&curve);
          // Return NULL
         return NULL;
        // Free memory
       SysLinEqFree(&sys);
        VecFree(&v);
       MatFree(&m);
     // Free memory
     VecFree(&t);
 // Return the result
 return curve;
// Get a VecFloat of dimension equal to the number of control points
// Values of the VecFloat are the weight of each control point in the
// BCurve given the curve's order and the value of 't' (in [0.0,1.0])
VecFloat* BCurveGetWeightCtrlPt(BCurve* that, float t) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
   sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (t < 0.0 - PBMATH_EPSILON || t > 1.0 + PBMATH_EPSILON) {
   BCurveErr->_type = PBErrTypeInvalidArg;
   sprintf(BCurveErr->\_msg, "'t' is invalid (0.0<=\%f<=1.0)", t);\\
   PBErrCatch(BCurveErr);
 }
#endif
 // Declare a variable to memorize the result
 VecFloat* res = VecFloatCreate(that->_order + 1);
 // Initilize the two first weights
 VecSet(res, 0, 1.0 - t);
 VecSet(res, 1, t);
 // For each higher order
```

```
for (int order = 1; order < that->_order; ++order) {
    // For each control point at this order, starting by the last one
    // to avoid using a temporary buffer
    for (int iCtrl = order + 2; iCtrl-- && iCtrl != 0;)
      // Calculate the weight of this control point
      VecSet(res, iCtrl,
        (1.0 - t) * VecGet(res, iCtrl) + t * VecGet(res, iCtrl - 1));
    // Calculate the weight of the first control point
    VecSet(res, 0, (1.0 - t) * VecGet(res, 0));
  // Return the result
 return res;
// Get the bounding box of the BCurve.
// Return a Facoid whose axis are aligned on the standard coordinate
// system.
Facoid* BCurveGetBoundingBox(BCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
  // Declare a variable to memorize the result
  Facoid* res = FacoidCreate(that->_dim);
  // For each dimension
  for (int iDim = that->_dim; iDim--;) {
    // Initialise the bounding box in this dimension
    VecSet(res->_s._pos, iDim, VecGet(that->_ctrl[0], iDim));
    VecSet(res->_s._axis[iDim], iDim, VecGet(that->_ctrl[0], iDim));
    // For each control point
    for (int iCtrl = that->_order + 1; iCtrl--;) {
      // Update the bounding box
      if (VecGet(that->_ctrl[iCtrl], iDim) <</pre>
        VecGet(res->_s._pos, iDim))
        VecSet(res->_s._pos, iDim, VecGet(that->_ctrl[iCtrl], iDim));
      if (VecGet(that->_ctrl[iCtrl], iDim) >
        VecGet(ShapoidAxis(res, iDim), iDim))
        VecSet(ShapoidAxis(res, iDim), iDim,
          VecGet(that->_ctrl[iCtrl], iDim));
    VecSetAdd(ShapoidAxis(res, iDim), iDim,
      -1.0 * VecGet(ShapoidPos(res), iDim));
  // Return the result
  return res;
// ----- SCurve
// ====== Functions implementation =========
// Create a new SCurve of dimension 'dim', order 'order' and
// 'nbSeg' segments
SCurve* SCurveCreate(int order, int dim, int nbSeg) {
#if BUILDMODE == 0
  if (order < 0) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Invalid order (%d>=0)", order);
    PBErrCatch(BCurveErr);
```

```
if (\dim < 1) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Invalid dimension (%d>=1)", dim);
   PBErrCatch(BCurveErr);
 if (nbSeg < 1) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Invalid number of segment (%d>=1)", nbSeg);
   PBErrCatch(BCurveErr);
#endif
  // Allocate memory
 SCurve* that = PBErrMalloc(BCurveErr, sizeof(SCurve));
  // Set the values
  that->_dim = dim;
 that->_order = order;
  that->_nbSeg = nbSeg;
  // Create the GSet
  that->_ctrl = GSetVecFloatCreateStatic();
  that->_seg = GSetBCurveCreateStatic();
  // For each segment
  for (int iSeg = nbSeg; iSeg--;) {
    // Create a segment
   BCurve* seg = BCurveCreate(order, dim);
    // If it's not the first added segment
    if (iSeg != nbSeg - 1) {
      // Replace the last control points by the current first
      VecFree(seg->_ctrl + order);
     seg->_ctrl[order] = GSetGetFirst(&(that->_ctrl));
      // Add the control points
      for (int iCtrl = order; iCtrl--;)
        GSetPush(&(that->_ctrl), BCurveCtrl(seg, iCtrl));
    // Else, it's the first segment
    } else {
      // Add the control points
      for (int iCtrl = order + 1; iCtrl--;)
        GSetPush(&(that->_ctrl), BCurveCtrl(seg, iCtrl));
    // Add the segment
    GSetPush(&(that->_seg), seg);
 // Return the new SCurve
 return that;
// Clone the SCurve
SCurve* SCurveClone(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 SCurve* clone = SCurveCreate(SCurveGetOrder(that), SCurveGetDim(that),
   SCurveGetNbSeg(that));
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  GSetIterForward iterClone =
   GSetIterForwardCreateStatic(&(clone->_ctrl));
  do {
```

```
VecFloat* ctrl = GSetIterGet(&iter);
    VecFloat* ctrlClone = GSetIterGet(&iterClone);
    VecCopy(ctrlClone, ctrl);
 } while (GSetIterStep(&iter) && GSetIterStep(&iterClone));
 return clone;
// Return a new SCurve as a copy of the SCurve 'that' with
// dimension changed to 'dim'
// if it is extended, the values of new components are 0.0
// If it is shrinked, values are discarded from the end of the vectors
SCurve* SCurveGetNewDim(SCurve* that, int dim) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 }
  if (dim <= 0) {
   PBMathErr->_type = PBErrTypeInvalidArg;
    sprintf(PBMathErr->_msg, "'dim' is invalid match (%d>0)", dim);
   PBErrCatch(PBMathErr);
 }
#endif
 // If the new dimension is equals to the current one
  if (SCurveGetDim(that) == dim) {
    // Return the clone of the initial curve
   return SCurveClone(that);
  } else {
    // Clone the initial curve
    SCurve* ret =
     SCurveCreate(SCurveGetOrder(that), dim, SCurveGetNbSeg(that));
    // Convert the dimension of each control point
    GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
    GSetIterForward iterNew =
     GSetIterForwardCreateStatic(&(ret->_ctrl));
    do {
      VecFloat* newCtrl =
        VecGetNewDim((VecFloat*)GSetIterGet(&iter), dim);
     VecFree((VecFloat**)&(GSetIterGetElem(&iterNew)->_data));
     GSetIterGetElem(&iterNew)->_data = newCtrl;
    } while (GSetIterStep(&iter) && GSetIterStep(&iterNew));
    // Correct the dimension and control points of each segment
    GSetIterSetGSet(&iter, &(ret->_seg));
    int iSeg = 0;
    do {
     BCurve* seg = GSetIterGet(&iter);
      seg->_dim = dim;
     for (int iCtrl = SCurveGetOrder(that) + 1; iCtrl--;)
        seg->_ctrl[iCtrl] =
          SCurveCtrl(ret, SCurveGetOrder(that) * iSeg + iCtrl);
     ++iSeg;
    } while (GSetIterStep(&iter));
    // Set the dimension of the curve
    ret->_dim = dim;
    // Return the new curve
    return ret;
// Load the SCurve from the stream \,
// If the SCurve is already allocated, it is freed before loading
```

```
// Return true in case of success, false else
bool SCurveLoad(SCurve** that, FILE* stream) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (stream == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'stream' is null");
   PBErrCatch(BCurveErr);
#endif
 // If 'that' is already allocated
 if (*that != NULL)
   // Free memory
   SCurveFree(that);
  // Read the number of segment, order and dimension
 int nbSeg;
 int order;
  int dim;
 int ret = fscanf(stream, "%d %d %d", &order, &dim, &nbSeg);
  // If we couldn't read
 if (ret == EOF)
   return false;
  // If data are invalid
 if (nbSeg < 1 || order < 0 || dim < 1)
   return false;
  // Allocate memory
 *that = SCurveCreate(order, dim, nbSeg);
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&((*that)->_ctrl));
  do {
   // Load the control point
   VecFloat* loadCtrl = NULL;
   ret = VecLoad(&loadCtrl, stream);
    // If we couldn't read the control point or the control point
    // is not of the correct dimension
    if (ret == false || VecGetDim(loadCtrl) != (*that)->_dim)
     return false;
    // Set the loaded control point into the set of control point
    // and segment
    VecCopy((VecFloat*)GSetIterGet(&iter), loadCtrl);
    // Free memory used by the loaded control
    VecFree(&loadCtrl);
  } while (GSetIterStep(&iter));
  // Return success code
 return true;
// Save the SCurve to the stream
// Return true upon success, false else
bool SCurveSave(SCurve* that, FILE* stream) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
 if (stream == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
```

```
sprintf(BCurveErr->_msg, "'stream' is null");
   PBErrCatch(BCurveErr);
#endif
  // Save the nb of segment, order and dimension
 int ret = fprintf(stream, "%d %d %d\n",
   that->_order, that->_dim, that->_nbSeg);
  // If the fprintf failed
 if (ret < 0)
   // Stop here
   return false;
  // For each control point
 GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
 do {
   VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
    // Save the control point
   ret = VecSave(ctrl, stream);
    // If we couldn't save the control point
    if (ret == false)
     // Stop here
     return false;
 } while (GSetIterStep(&iter));
 // Return success code
 return true;
// Free the memory used by a SCurve
void SCurveFree(SCurve** that) {
 // Check argument
 if (that == NULL || *that == NULL)
   return;
  // For each control point
 GSetIterForward iter = GSetIterForwardCreateStatic(&((*that)->_ctrl));
   VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
    // Free the memory used by the control point
   VecFree(&ctrl);
  } while (GSetIterStep(&iter));
  // Free the memory used by the set of control point
  GSetFlush(&((*that)->_ctrl));
  // For each segment
  iter = GSetIterForwardCreateStatic(&((*that)->_seg));
   BCurve* seg = (BCurve*)GSetIterGet(&iter);
    // Disconnect the control points which have been already freed
    // or doesn't need to be freed (the last one)
   for (int iCtrl = 0; iCtrl <= (*that)->_order; ++iCtrl)
     seg->_ctrl[iCtrl] = NULL;
    // Free the meory used by the segment
   BCurveFree(&seg);
  } while (GSetIterStep(&iter));
  // Free the memory used by the set of segment
 GSetFlush(&((*that)->_seg));
  // Free memory
 free(*that);
 *that = NULL;
// Print the SCurve on 'stream'
void SCurvePrint(SCurve* that, FILE* stream) {
#if BUILDMODE == 0
 if (that == NULL) {
```

```
BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (stream == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'stream' is null");
    PBErrCatch(BCurveErr);
#endif
  // Print the order and dim
  fprintf(stream, "order(%d) dim(%d) nbSeg(%d) ",
    that->_order, that->_dim, that->_nbSeg);
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  int iMark = 0;
  do {
    VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
    if (iMark == 0)
      fprintf(stream, "<");</pre>
    //VecPrint(ctrl, stream);
    VecFloatPrint(ctrl, stream, 6);
    if (iMark == 0)
     fprintf(stream, ">");
    if (GSetIterIsLast(&iter) == false)
      fprintf(stream, " ");
    if (iMark == that->_order)
      iMark = 0;
 } while (GSetIterStep(&iter));
// Add one segment at the end of the curve (controls are set to
// vectors null, except the first one which the last one of the current
// last segment)
void SCurveAddSegTail(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
  // Create the new segment
  BCurve* seg = BCurveCreate(that->_order, that->_dim);
  // Free memory used by the first control point
  VecFree(seg->_ctrl);
  // Replace it with the current last control
  seg->_ctrl[0] = GSetGetLast(&(that->_ctrl));
  // Add the segment to the set of segment
  GSetAppend(&(that->_seg), seg);
  // Add the new control points to the set of control points
  for (int iCtrl = 1; iCtrl <= that->_order; ++iCtrl)
    GSetAppend(&(that->_ctrl), seg->_ctrl[iCtrl]);
  // Update the number of segment
  ++(that->_nbSeg);
// Add one segment at the head of the curve (controls are set to
// vectors null, except the last one which the first one of the current
// first segment)
void SCurveAddSegHead(SCurve* that) {
```

```
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
  // Create the new segment
  BCurve* seg = BCurveCreate(that->_order, that->_dim);
  // Free memory used by the last control point
  VecFree(seg->_ctrl + that->_order);
  // Replace it with the current first control
  seg->_ctrl[that->_order] = GSetGetFirst(&(that->_ctrl));
  // Add the segment to the set of segment
  GSetPush(&(that->_seg), seg);
  // Add the new control points to the set of control points
  for (int iCtrl = that->_order; iCtrl--;)
    GSetPush(&(that->_ctrl), seg->_ctrl[iCtrl]);
  // Update the number of segment
  ++(that->_nbSeg);
// Remove the first segment of the curve (which must have more than one
// segment)
void SCurveRemoveHeadSeg(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (that->_nbSeg < 2) \{
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'that' has only one segment");
    PBErrCatch(BCurveErr);
  }
#endif
  // Remove the control points from the set of control points
  for (int iCtrl = 0; iCtrl < that->_order; ++iCtrl) {
    VecFloat* ctrl = (VecFloat*)GSetPop(&(that->_ctrl));
    VecFree(&ctrl);
  // Remove the first segment
  BCurve* seg = (BCurve*)GSetPop(&(that->_seg));
  // Disconnect the control points which have been already freed
  // or doesn't need to be freed (the last one)
  for (int iCtrl = 0; iCtrl <= that->_order; ++iCtrl)
    seg->_ctrl[iCtrl] = NULL;
  // Free the memory used by the segment
  BCurveFree(&seg);
  // Update the number of segment
  --(that->_nbSeg);
}
// Remove the last segment of the curve (which must have more than one
// segment)
void SCurveRemoveTailSeg(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
```

```
if (that->_nbSeg < 2) \{
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'that' has only one segment");
   PBErrCatch(BCurveErr);
#endif
  // Remove the control points from the set of control points
 for (int iCtrl = 0; iCtrl < that->_order; ++iCtrl) {
   VecFloat* ctrl = (VecFloat*)GSetDrop(&(that->_ctrl));
    VecFree(&ctrl);
  // Remove the last segment
 BCurve* seg = (BCurve*)GSetDrop(&(that->_seg));
  \ensuremath{//} Disconnect the control points which have been already freed
  // or doesn't need to be freed (the first one)
 for (int iCtrl = 0; iCtrl <= that->_order; ++iCtrl)
    seg->_ctrl[iCtrl] = NULL;
  // Free the memory used by the segment
 BCurveFree(&seg);
  // Update the number of segment
  --(that->_nbSeg);
// Get the bounding box of the SCurve.
// Return a Facoid whose axis are aligned on the standard coordinate
// TODO : better solution possible, refer to
// https://pomax.github.io/bezierinfo/#circles_cubic
Facoid* SCurveGetBoundingBox(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 }
#endif
  // Declare a set to memorize the bounding box of each segment
 GSetShapoid set = GSetShapoidCreateStatic();
  // For each segment
 GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_seg));
 do {
    // Add the bounding box of this segment to the set
   GSetPush(&set.
     BCurveGetBoundingBox((BCurve*)GSetIterGet(&iter)));
  } while (GSetIterStep(&iter));
  // Get the bounding box of all the segment's bounding box
  Facoid* bound = ShapoidGetBoundingBoxSet(&set);
  // Free the memory used by the bounding box of each segment
  iter = GSetIterForwardCreateStatic(&set);
  do {
   Facoid* facoid = (Facoid*)GSetIterGet(&iter);
   ShapoidFree(&facoid);
  } while (GSetIterStep(&iter));
 GSetFlush(&set);
  // Return the bounding box
 return bound;
// Create a new SCurve from the outline of the Facoid 'shap'
// The Facoid must be of dimension 2
// Control points are ordered CCW of the Shapoid
```

```
SCurve* SCurveCreateFromFacoid(Facoid* shap) {
#if BUILDMODE == 0
  if (shap == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'shap' is null");
    PBErrCatch(BCurveErr);
  if (ShapoidGetDim(shap) != 2) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg,
      "'shap' 's dimension is invalid (%d==2)",
      ShapoidGetDim(shap));
    PBErrCatch(BCurveErr);
#endif
  // Create the curve
  SCurve* ret = SCurveCreate(1, 2, 4);
  // Set the coordinates of the control points according to the
  for (int i = 5; i--;)
    VecCopy(SCurveCtrl(ret, i), ShapoidPos(shap));
  VecOp(SCurveCtrl(ret, 1), 1.0, ShapoidAxis(shap, 0), 1.0);
  VecOp(SCurveCtrl(ret, 2), 1.0, ShapoidAxis(shap, 0), 1.0);
  VecOp(SCurveCtrl(ret, 2), 1.0, ShapoidAxis(shap, 1), 1.0);
  VecOp(SCurveCtrl(ret, 3), 1.0, ShapoidAxis(shap, 1), 1.0);
  // Return the curve
  return ret;
// Create a new SCurve from the outline of the Pyramidoid 'shap'
// The Pyramidoid must be of dimension 2
// Control points are ordered CCW of the Shapoid
SCurve* SCurveCreateFromPyramidoid(Pyramidoid* shap) {
#if BUILDMODE == 0
  if (shap == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'shap' is null");
    PBErrCatch(BCurveErr);
  if (ShapoidGetDim(shap) != 2) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg,
      "'shap' 's dimension is invalid (%d==2)",
      ShapoidGetDim(shap));
    PBErrCatch(BCurveErr);
  }
#endif
  // Create the curve
  SCurve* ret = SCurveCreate(1, 2, 3);
  // Set the coordinates of the control points according to the
  // Facoid
  for (int i = 4; i--;)
    VecCopy(SCurveCtrl(ret, i), ShapoidPos(shap));
  VecOp(SCurveCtrl(ret, 1), 1.0, ShapoidAxis(shap, 0), 1.0);
VecOp(SCurveCtrl(ret, 2), 1.0, ShapoidAxis(shap, 1), 1.0);
  // Return the curve
  return ret;
}
// Create a new SCurve from the outline of the Spheroid 'shap'
// The Spheroid must be of dimension 2
// Control points are ordered CCW of the Shapoid
```

```
// Calculate an approximation as there is no exact solution
SCurve* SCurveCreateFromSpheroid(Spheroid* shap) {
#if BUILDMODE == 0
  if (shap == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'shap' is null");
    PBErrCatch(BCurveErr);
  if (ShapoidGetDim(shap) != 2) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg,
      "'shap' 's dimension is invalid (%d==2)",
      ShapoidGetDim(shap));
    PBErrCatch(BCurveErr);
  }
#endif
  // Create the curve
  SCurve* ret = SCurveCreate(3, 2, 4);
  // Set the control points
  // The anchors of the curve can be easily calculated from the
  // position and axis of the Spheroid
  int iAxis = 0;
  float coeff = 0.5;
  for (int i = 0; i < 12; i += 3) {
    VecCopy(SCurveCtrl(ret, i), ShapoidPos(shap));
    if (i == 6)
      coeff *= -1.0;
    VecOp(SCurveCtrl(ret, i), 1.0, ShapoidAxis(shap, iAxis), coeff);
    if (i > 0)
      VecCopy(SCurveCtrl(ret, i - 1), SCurveCtrl(ret, i));
    if (i < 11)
      VecCopy(SCurveCtrl(ret, i + 1), SCurveCtrl(ret, i));
    iAxis = (iAxis == 0 ? 1 : 0);
  VecCopy(SCurveCtrl(ret, 12), SCurveCtrl(ret, 0));
  VecCopy(SCurveCtrl(ret, 11), SCurveCtrl(ret, 0));
  // Calculate the others control points by transforming the
  // quadratic approximation of a quarter of the unit circle :
  // A(1,0), B(1,4(sqrt(2)-1)/3), C(4(sqrt(2)-1)/3,1), D(0,1)
  // toward the Spheroid
  float c = 0.276142;
  VecOp(SCurveCtrl(ret, 1), 1.0, ShapoidAxis(shap, 1), c);
  VecOp(SCurveCtrl(ret, 2), 1.0, ShapoidAxis(shap, 0), c);
  VecOp(SCurveCtrl(ret, 4), 1.0, ShapoidAxis(shap, 0), -1.0 * c);
VecOp(SCurveCtrl(ret, 5), 1.0, ShapoidAxis(shap, 1), c);
  VecOp(SCurveCtrl(ret, 7), 1.0, ShapoidAxis(shap, 1), -1.0 * c);
  VecOp(SCurveCtrl(ret, 8), 1.0, ShapoidAxis(shap, 0), -1.0 * c);
  VecOp(SCurveCtrl(ret, 10), 1.0, ShapoidAxis(shap, 0), c);
  VecOp(SCurveCtrl(ret, 11), 1.0, ShapoidAxis(shap, 1), -1.0 * c);
  // Return the curve
  return ret;
// Get the distance between the SCurve 'that' and the SCurve 'curve'
// The distance is defined as the integral of
// ||'that'(u(t))-'curve'(v(t))|| where u and v are the relative
// positions on the curve over t varying from 0.0 to 1.0
{\tt float \ SCurve Get Dist To Curve} ({\tt SCurve * \ that, \ SCurve * \ curve}) \ \{
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'shap' is null");
```

```
PBErrCatch(BCurveErr);
  }
  if (curve == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'shap' is null");
   PBErrCatch(BCurveErr);
  if (SCurveGetDim(that) != SCurveGetDim(curve)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg,
      "dimensions of 'that' and 'curve' differ (%d==%d)",
      SCurveGetDim(that), SCurveGetDim(curve));
   PBErrCatch(BCurveErr);
 }
#endif
  // Declare a variable to memorize the result
  float res = 0.0;
  // Declare a variable to memorize the step over parameter
  float dt = 0.01;
  int nb = (int)floor(1.0 / dt);
  float t = 0.0;
  // Loop over the parameter
  for (int i = nb; i--;) {
    \ensuremath{//} Calculate the relative parameter for both curves
    float u = t * SCurveGetMaxU(that);
    float v = t * SCurveGetMaxU(curve);
    // Get the value of both curve at these relative parameters
    VecFloat* valA = SCurveGet(that, u);
    VecFloat* valB = SCurveGet(curve, v);
    // Get the distance between value
    float dist = VecDist(valA, valB);
    // Add to result
    res += dist * dt;
    // Step the parameter
    t += dt;
    // Free memory
    VecFree(&valA);
    VecFree(&valB);
  // Return the result
 return res;
// ----- SCurveIter
// ======== Functions implementation ==========
// Create a new SCurveIter attached to the SCurve 'curve' with a step
// of 'delta'
SCurveIter SCurveIterCreateStatic(SCurve* curve, float delta) {
#if BUILDMODE == 0
  if (curve == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'curve' is null");
   PBErrCatch(BCurveErr);
  if (delta <= 0.0) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'delta' is invalid (%f>0)", delta);
   PBErrCatch(BCurveErr);
 }
#endif
```

```
// Declare the new SCurveIter
 SCurveIter iter;
  // Set the properties
 iter._curve = curve;
 iter._curPos = 0.0;
 iter._delta = delta;
 \ensuremath{//} Return the new iterator
 return iter;
// ---- BBody
// ====== Functions declaration ========
// Recursive function to calculate the value of a BBody
VecFloat* BBodyGetRec(BBody *that, BCurve *curve,
 VecShort *iCtrl, VecFloat *u, int iDimIn);
// ======= Functions implementation ==========
// Create a new BBody of order 'order' and dimension 'dim'
// Controls are initialized with null vectors
BBody* BBodyCreate(int order, VecShort2D* dim) {
#if BUILDMODE == 0
 if (order < 0) {
   BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Invalid order (%d>=0)", order);
   PBErrCatch(BCurveErr);
 if (dim == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'dim' is null");
   PBErrCatch(BCurveErr);
 for (int iDim = 2; iDim--;) {
   if (VecGet(dim, iDim) <= 0) {</pre>
     BCurveErr->_type = PBErrTypeInvalidArg;
     sprintf(BCurveErr->_msg, "Dimension is invalid (dim[%d]:%d>0)",
       iDim, VecGet(dim, iDim));
     PBErrCatch(BCurveErr);
 }
#endif
  // Allocate memory for the new BBody
 BBody *that = PBErrMalloc(BCurveErr, sizeof(BBody));
 // Init pointers
 that->_dim = VecShortCreateStatic2D();
 that->_ctrl = NULL;
 // Init properties
 that->_order = order;
  that->_dim = *dim;
  // Init the control
 int nbCtrl = BBodyGetNbCtrl(that);
  that->_ctrl = PBErrMalloc(BCurveErr, sizeof(VecFloat*) * nbCtrl);
 for (int iCtrl = nbCtrl; iCtrl--;)
    that->_ctrl[iCtrl] = VecFloatCreate(VecGet(dim, 1));
  // Return the new BBody
 return that;
// Free the memory used by a BBody
void BBodyFree(BBody** that) {
```

```
// Check arguments
  if (that == NULL || *that == NULL)
   return;
  // Get the number of ctrl
  int nbCtrl = BBodyGetNbCtrl(*that);
  // Free memory
  for (int iCtrl = nbCtrl; iCtrl--;)
    VecFree((*that)->_ctrl + iCtrl);
  free((*that)->_ctrl);
 free(*that);
  *that = NULL;
// Get the value of the BBody at paramater 'u'
// u can extend beyond [0.0, 1.0]
VecFloat* _BBodyGet(BBody* that, VecFloat* u) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (u == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'u' is null");
   PBErrCatch(BCurveErr);
 if (VecGetDim(u) != VecGet(&(that->_dim), 0)) {
   BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'u' is invalid (%d=%d)",
      VecGetDim(u), VecGet(&(that->_dim), 0));
   PBErrCatch(BCurveErr);
 }
#endif
 // Declare variables to memorize the nb of dimension
 int nbDimIn = VecGet(&(that->_dim), 0);
 int nbDimOut = VecGet(&(that->_dim), 1);
  // Create a clone of u to be checked for components interval
 VecFloat *uSafe = VecClone(u);
  // Declare a vector to memorize the index of the ctrl
  VecShort *iCtrl = VecShortCreate(nbDimIn);
  // Declare a BCurve used for calculation
  BCurve *curve = BCurveCreate(that->_order, nbDimOut);
  // Calculate recursively the result value
 VecFloat *res = BBodyGetRec(that, curve, iCtrl, uSafe, 0);
  // Free memory
 VecFree(&uSafe);
 VecFree(&iCtrl);
 BCurveFree(&curve);
  // Return the result
 return res;
// Recursive function to calculate the value of SCurve
VecFloat* BBodyGetRec(BBody* that, BCurve* curve,
 VecShort* iCtrl, VecFloat* u, int iDimIn) {
  // Declare a variable for the result
 VecFloat *res = NULL;
 // If we are at the last dimension in the recursion,
 // the curve controls are the controls of the surface at current
  // position in control's space
  if (iDimIn == VecGet(&(that->_dim), 0) - 1) {
```

```
for (int i = that->_order + 1; i--;) {
     VecSet(iCtrl, iDimIn, i);
     BCurveSetCtrl(curve, i, BBodyCtrl(that, iCtrl));
  // Else, we are not at the last dimension in control's space
  } else {
    // Clone the position (to edit the lower dimension at lower
    // level of the recursion)
    VecShort *jCtrl = VecClone(iCtrl);
    // Declare an array of VecFloat to memorize the control at
    // the current level
    VecFloat **tmpCtrl =
     PBErrMalloc(BCurveErr, sizeof(VecFloat*) * (that->_order + 1));
    // For each control
    for (int i = that->_order + 1; i--;) {
      // Update the control position
     VecSet(jCtrl, iDimIn, i);
      // Get recursively the control (equal to the BCurve value at
      // lower level)
      tmpCtrl[i] =
       BBodyGetRec(that, curve, jCtrl, u, iDimIn + 1);
    // Set the control of the curve at current level
    // Use a temporary instead of affecting directly into curve
    // because it is shared between recursion level and affecting
    // directly would lead to overwritting during the process
    for (int i = that->_order + 1; i--;)
     BCurveSetCtrl(curve, i, tmpCtrl[i]);
    // Free the temporary Vecfloat for the controls
    for (int i = that->_order + 1; i--;)
     VecFree(tmpCtrl + i);
    free(tmpCtrl);
    // Free the temporary position in control space
   VecFree(&jCtrl);
 // Here we have the curve set up with the appropriate control at the
  // current recursion level
  // Calculate its value at the parameters value for the current
  // dimension
 res = BCurveGet(curve, VecGet(u, iDimIn));
  // Return the result
 return res;
// Return a clone of the BBody 'that'
BBody* BBodyClone(BBody* that) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 // Declare the clone
 BBody* clone = BBodyCreate(BBodyGetOrder(that), BBodyDim(that));
  // For each control
 for (int iCtrl = BBodyGetNbCtrl(clone); iCtrl--;)
    // Copy the control values
    VecCopy(clone->_ctrl[iCtrl], that->_ctrl[iCtrl]);
  // Return the clone
 return clone;
```

```
// Print the BBody 'that' on the stream 'stream'
void BBodyPrint(BBody* that, FILE* stream) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (stream == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'stream' is null");
    PBErrCatch(BCurveErr);
#endif
  // Print the order and dim
  fprintf(stream, "order(%d) dim(", that->_order);
  VecPrint(&(that->_dim), stream);
  fprintf(stream, ") ");
  // For each control point
  for (int iCtrl = 0; iCtrl < BBodyGetNbCtrl(that); ++iCtrl) {</pre>
    VecPrint(that->_ctrl[iCtrl], stream);
    if (iCtrl < that->_order)
      fprintf(stream, " ");
  }
}
// Load the BBody from the stream
// If the BBody is already allocated, it is freed before loading
// Return true upon success, false else
bool BBodyLoad(BBody** that, FILE* stream) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (stream == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'stream' is null");
    PBErrCatch(BCurveErr);
#endif
  // If 'that' is already allocated
if (*that != NULL)
    // Free memory
    BBodyFree(that);
  // Read the order and dimension
  int order;
  VecShort* dim = NULL;
  int ret = fscanf(stream, "%d", &order);
  // If we couldn't read
  if (ret == EOF)
   return false;
  ret = VecLoad(&dim, stream);
  // If we couldn't read
  if (ret == EOF ||
    VecGetDim(dim) != 2) {
    VecFree(&dim);
    return false;
  // Allocate memory
```

```
*that = BBodyCreate(order, (VecShort2D*)dim);
  // Free memory
  VecFree(&dim);
  // For each control point
  for (int iCtrl = 0; iCtrl < BBodyGetNbCtrl(*that); ++iCtrl) {</pre>
    // Load the control point
   ret = VecLoad((*that)->_ctrl + iCtrl, stream);
   // If we couldn't read the control point or the control point
    // is not of the correct dimension
   if (ret == false ||
     VecGetDim((*that)->_ctrl[iCtrl]) != VecGet(&((*that)->_dim), 1))
     return false;
 // Return success code
 return true;
// Save the BBody to the stream
// Return true upon success, false else
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (stream == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
sprintf(BCurveErr->_msg, "'stream' is null");
   PBErrCatch(BCurveErr);
 }
#endif
 // Save the order and dimension
 int ret = fprintf(stream, "%d\n", that->_order);
  VecSave(&(that->_dim), stream);
 // If the fprintf failed
 if (ret < 0)
   // Stop here
   return false;
  // For each control point
 for (int iCtrl = 0; iCtrl < BBodyGetNbCtrl(that); ++iCtrl) {</pre>
   // Save the control point
   ret = VecSave(that->_ctrl[iCtrl], stream);
    // If we couldn't save the control point
   if (ret == false)
     // Stop here
     return false;
 // Return success code
 return true;
// Get the bounding box of the BBody.
// Return a Facoid whose axis are aligned on the standard coordinate
// system.
Facoid* BBodyGetBoundingBox(BBody* that) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
```

```
#endif
  // Declare a variable to memorize the result
 Facoid* res = FacoidCreate(VecGet(BBodyDim(that), 1));
 // For each dimension
  for (int iDim = VecGet(BBodyDim(that), 1); iDim--;) {
    // Initialise the bounding box in this dimension
    VecSet(res->_s._pos, iDim, VecGet(that->_ctrl[0], iDim));
    VecSet(res->_s._axis[iDim], iDim, VecGet(that->_ctrl[0], iDim));
    // For each control point except the first one
    for (int iCtrl = BBodyGetNbCtrl(that); iCtrl-- && iCtrl != 0;) {
     // Update the bounding box
      if (VecGet(that->_ctrl[iCtrl], iDim) < VecGet(res->_s._pos, iDim))
        VecSet(res->_s._pos, iDim, VecGet(that->_ctrl[iCtrl], iDim));
      if (VecGet(that->_ctrl[iCtrl], iDim) >
        VecGet(ShapoidAxis(res, iDim), iDim))
        VecSet(ShapoidAxis(res, iDim), iDim,
          VecGet(that->_ctrl[iCtrl], iDim));
    VecSetAdd(ShapoidAxis(res, iDim), iDim,
      -1.0 * VecGet(ShapoidPos(res), iDim));
  // Return the result
 return res;
```

## 3.2 bcurve-inline.c

```
// ====== BCURVE-INLINE.C ========
// ======= Functions implementation ==========
// Set the value of the iCtrl-th control point to {\tt v}
#if BUILDMODE != 0
inline
#endif
void BCurveSetCtrl(BCurve* that, int iCtrl, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
   PBErrCatch(BCurveErr);
 if (iCtrl < 0 || iCtrl > that->_order) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    {\tt sprintf(BCurveErr->\_msg, "'iCtrl' is invalid (0<=\%d<\%d)",}
     iCtrl, that->_order);
   PBErrCatch(BCurveErr);
  if (VecGetDim(v) != BCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'v' 's dimension is invalid (%d<%d)",
     VecGetDim(v), BCurveGetDim(that));
    PBErrCatch(BCurveErr);
```

```
}
#endif
  // Set the values
  VecCopy(that->_ctrl[iCtrl], v);
// Get a copy of the iCtrl-th control point
#if BUILDMODE != 0
inline
#endif
VecFloat* BCurveGetCtrl(BCurve* that, int iCtrl) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (iCtrl < 0 || iCtrl > that->_order) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'iCtrl' is invalid (0<=%d<%d)",
      iCtrl, that->_order);
   PBErrCatch(BCurveErr);
 }
#endif
  // Return a copy of the control point
 return VecClone(that->_ctrl[iCtrl]);
// Get the iCtrl-th control point
#if BUILDMODE != 0
inline
#endif
VecFloat* BCurveCtrl(BCurve* that, int iCtrl) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (iCtrl < 0 || iCtrl > that->_order) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'iCtrl' is invalid (0<=%d<%d)",
      iCtrl, that->_order);
   PBErrCatch(BCurveErr);
#endif
  \ensuremath{//} Return the control point
 return that->_ctrl[iCtrl];
// Get the order of the BCurve
#if BUILDMODE != 0
inline
#endif
int BCurveGetOrder(BCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 }
#endif
```

```
return that->_order;
// Get the dimension of the BCurve
#if BUILDMODE != 0
inline
#endif
int BCurveGetDim(BCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 }
#endif
 return that->_dim;
// Get the approximate length of the BCurve (sum of dist between
// control points)
#if BUILDMODE != 0
inline
#endif
float BCurveGetApproxLen(BCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
 }
#endif
  // Declare a variable to calculate the length
  float res = 0.0;
  // Calculate the length
  for (int iCtrl = that->_order; iCtrl--;)
   res += VecDist(that->_ctrl[iCtrl], that->_ctrl[iCtrl + 1]);
  // Return the length
 return res;
}
// Return the center of the BCurve (average of control points)
#if BUILDMODE != 0
inline
#endif
VecFloat* BCurveGetCenter(BCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
  \ensuremath{//} Sum all the control points
  VecFloat* center = VecClone(that->_ctrl[that->_order]);
  for (int iCtrl = that->_order; iCtrl--;)
    VecOp(center, 1.0, that->_ctrl[iCtrl], 1.0);
  // Get the average
  VecScale(center, 1.0 / (float)(that->_order + 1));
  // Return the result
  return center;
```

```
// Rotate the curve CCW by 'theta' radians relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void BCurveRotOrigin(BCurve* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (that->_dim != 2) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=2)",
      that->_dim);
   PBErrCatch(BCurveErr);
  }
#endif
  // For each control point
  for (int iCtrl = that->_order + 1; iCtrl--;)
    // Rotate the control point
    VecRot(that->_ctrl[iCtrl], theta);
// Rotate the curve CCW by 'theta' radians relatively to its
// first control point
#if BUILDMODE != 0
inline
#endif
void BCurveRotStart(BCurve* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  }
  if (that->_dim != 2) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=2)",
      that->_dim);
   PBErrCatch(BCurveErr);
  }
#endif
  // For each control point except the first one
  for (int iCtrl = that->_order + 1; iCtrl-- && iCtrl != 0;) {
    \ensuremath{//} Translate the control point
    VecOp(that->_ctrl[iCtrl], 1.0, that->_ctrl[0], -1.0);
    // Rotate the control point
    VecRot(that->_ctrl[iCtrl], theta);
    // Translate back the control point
    VecOp(that->_ctrl[iCtrl], 1.0, that->_ctrl[0], 1.0);
 }
// Rotate the curve CCW by 'theta' radians relatively to its
// center
#if BUILDMODE != 0
inline
#endif
void BCurveRotCenter(BCurve* that, float theta) {
#if BUILDMODE == 0
```

```
if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (that->_dim != 2) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=2)",
      that->_dim);
    PBErrCatch(BCurveErr);
  }
#endif
  // Get the center
  VecFloat* center = BCurveGetCenter(that);
  // For each control point
  for (int iCtrl = that->_order + 1; iCtrl--;) {
   // Translate the control point
    VecOp(that->_ctrl[iCtrl], 1.0, center, -1.0);
    // Rotate the control point
    VecRot(that->_ctrl[iCtrl], theta);
    // Translate back the control point
    VecOp(that->_ctrl[iCtrl], 1.0, center, 1.0);
  // Free memory
  VecFree(&center);
// Scale the curve by 'v' relatively to the origin
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleOriginVector(BCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
   PBErrCatch(BCurveErr);
  if (VecGetDim(v) != BCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
      VecGetDim(v), BCurveGetDim(that));
    PBErrCatch(BCurveErr);
 }
#endif
  // For each control point
  for (int iCtrl = that->_order + 1; iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Scale the control point
    for (int dim = 0; dim < VecGetDim(ctrl); ++dim)</pre>
      VecSet(ctrl, dim, VecGet(ctrl, dim) * VecGet(v, dim));
}
// Scale the curve by 'c' relatively to the origin
#if BUILDMODE != 0
inline
```

```
void _BCurveScaleOriginScalar(BCurve* that, float c) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  // For each control point
  for (int iCtrl = that->_order + 1; iCtrl--;)
    // Scale the control point
    VecScale(that->_ctrl[iCtrl], c);
// Scale the curve by 'v' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleStartVector(BCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
   PBErrCatch(BCurveErr);
  if (VecGetDim(v) != BCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
      VecGetDim(v), BCurveGetDim(that));
   PBErrCatch(BCurveErr);
#endif
  // For each control point except the first one
  for (int iCtrl = that->_order + 1; iCtrl-- && iCtrl != 0;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], -1.0);
    // Scale the control point
    for (int dim = 0; dim < VecGetDim(that->_ctrl[iCtrl]); ++dim)
      VecSet(ctrl, dim, VecGet(ctrl, dim) * VecGet(v, dim));
    // Translate back the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], 1.0);
 }
// Scale the curve by 'c' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
void _BCurveScaleStartScalar(BCurve* that, float c) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
```

```
PBErrCatch(BCurveErr);
  }
#endif
  // For each control point except the first one
  for (int iCtrl = that->_order + 1; iCtrl-- && iCtrl != 0;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], -1.0);
    // Scale the control point
    VecScale(ctrl, c);
    // Translate back the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], 1.0);
// Scale the curve by 'v' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleCenterVector(BCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
   PBErrCatch(BCurveErr);
  if (VecGetDim(v) != BCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
      VecGetDim(v), BCurveGetDim(that));
   PBErrCatch(BCurveErr);
#endif
  VecFloat* center = BCurveGetCenter(that);
  // For each control point
  for (int iCtrl = that->_order + 1; iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Scale the control point
    for (int dim = 0; dim < VecGetDim(that->_ctrl[iCtrl]); ++dim)
      VecSet(ctrl, dim, VecGet(ctrl, dim) * VecGet(v, dim));
    // Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  // Free memory
  VecFree(&center);
// Scale the curve by 'c' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _BCurveScaleCenterScalar(BCurve* that, float c) {
#if BUILDMODE == 0
```

```
if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* center = BCurveGetCenter(that);
  // For each control point
  for (int iCtrl = that->_order + 1; iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Scale the control point
    VecScale(ctrl, c);
    // Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  // Free memory
  VecFree(&center);
// Translate the curve by 'v'
#if BUILDMODE != 0
inline
#endif
void _BCurveTranslate(BCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (VecGetDim(v) != BCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    {\tt sprintf(BCurveErr->\_msg,\ "Dimension\ of\ 'v'\ is\ invalid\ (\%d=\%d)",}
      VecGetDim(v), BCurveGetDim(that));
    PBErrCatch(BCurveErr);
  }
#endif
  // For each control point
  for (int iCtrl = that->_order + 1; iCtrl--;)
    // Translate the control point
    VecOp(that->_ctrl[iCtrl], 1.0, v, 1.0);
// ----- SCurve
// ====== Functions implementation =========
// Get the number of BCurve in the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetNbSeg(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
```

```
sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 return that->_nbSeg;
// Get the dimension of the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetDim(SCurve* that) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 return that->_dim;
// Get the order of the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetOrder(SCurve* that) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 }
#endif
return that->_order;
}
// Get a clone of the 'iCtrl'-th control point
#if BUILDMODE != 0
inline
#endif
VecFloat* SCurveGetCtrl(SCurve* that, int iCtrl) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (iCtrl < 0 || iCtrl >= SCurveGetNbCtrl(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'iCtrl' is invalid (0<=%d<%d)",
      iCtrl, SCurveGetNbCtrl(that));
   PBErrCatch(BCurveErr);
 }
#endif
 return VecClone(GSetGet(&(that->_ctrl), iCtrl));
// Get the 'iCtrl'-th control point
#if BUILDMODE != 0
inline
```

```
#endif
VecFloat* SCurveCtrl(SCurve* that, int iCtrl) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (iCtrl < 0 || iCtrl >= SCurveGetNbCtrl(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->\_msg, "'iCtrl' is invalid (0<=\%d<\%d)",\\
      iCtrl, SCurveGetNbCtrl(that));
   PBErrCatch(BCurveErr);
#endif
 return (VecFloat*)GSetGet(&(that->_ctrl), iCtrl);
// Get the set of control point of the SCurve 'that'
#if BUILDMODE != 0
inline
#endif
GSetVecFloat* SCurveCtrls(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 return &(that->_ctrl);
// Get a clone of the 'iSeg'-th segment
#if BUILDMODE != 0
inline
#endif
BCurve* SCurveGetSeg(SCurve* that, int iSeg) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (iSeg < 0 || iSeg >= that->_nbSeg) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'iSeg' is invalid (0<=%d<%d)",
      iSeg, that->_nbSeg);
   PBErrCatch(BCurveErr);
  }
#endif
 return BCurveClone((BCurve*)GSetGet(&(that->_seg), iSeg));
// Get the 'iSeg'-th segment
#if BUILDMODE != 0
inline
#endif
BCurve* SCurveSeg(SCurve* that, int iSeg) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
```

```
sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (iSeg < 0 || iSeg >= that->_nbSeg) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'iSeg' is invalid (0<=%d<%d)",
      iSeg, that->_nbSeg);
    PBErrCatch(BCurveErr);
#endif
 return (BCurve*)GSetGet(&(that->_seg), iSeg);
// Get the GSet of segments of the SCurve 'that'
#if BUILDMODE != 0
inline
#endif
GSetBCurve* SCurveSegs(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 return &(that->_seg);
// Return the center of the SCurve (average of control points)
#if BUILDMODE != 0
inline
#endif
VecFloat* SCurveGetCenter(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 }
#endif
  // Sum all the control points
  VecFloat* center = VecFloatCreate(that->_dim);
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  do {
   VecOp(center, 1.0, (VecFloat*)GSetIterGet(&iter), 1.0);
  } while (GSetIterStep(&iter));
  // Get the average
  VecScale(center, 1.0 / (float)GSetNbElem(&(that->_ctrl)));
  // Return the result
 return center;
// Return the max value for the parameter 'u' of SCurveGet
#if BUILDMODE != 0
inline
#endif
float SCurveGetMaxU(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
```

```
}
#endif
 return (float)(that->_nbSeg);
// Get the number of control point in the SCurve
#if BUILDMODE != 0
inline
#endif
int SCurveGetNbCtrl(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 return that->_nbSeg * that->_order + 1;
// Rotate the curve CCW by 'theta' radians relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void SCurveRotOrigin(SCurve* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  do {
    // Rotate the control point
    VecRot((VecFloat*)GSetIterGet(&iter), theta);
 } while (GSetIterStep(&iter));
// Rotate the curve CCW by 'theta' radians relatively to its
// first control point
#if BUILDMODE != 0
inline
#endif
void SCurveRotStart(SCurve* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* origin = GSetGetFirst(&(that->_ctrl));
  // For each control point except the first one
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  if (GSetIterStep(&iter)) {
      VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
      // Translate the control point
      VecOp(ctrl, 1.0, origin, -1.0);
```

```
// Rotate the control point
      VecRot(ctrl, theta);
      // Translate back the control point
      VecOp(ctrl, 1.0, origin, 1.0);
    } while (GSetIterStep(&iter));
 }
// Rotate the curve CCW by 'theta' radians relatively to its
// center
#if BUILDMODE != 0
inline
#endif
void SCurveRotCenter(SCurve* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
 }
#endif
  // Get the center
  VecFloat* center = SCurveGetCenter(that);
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
    VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Rotate the control point
    VecRot(ctrl, theta);
    // Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  } while (GSetIterStep(&iter));
  // Free memory
  VecFree(&center);
// Scale the curve by 'v' relatively to the origin
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleOriginVector(SCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  }
#endif
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
    VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
    // Scale the control point
    for (int iDim = SCurveGetDim(that); iDim--;)
      VecSet(ctrl, iDim, VecGet(ctrl, iDim) * VecGet(v, iDim));
 } while (GSetIterStep(&iter));
// Scale the curve by 'c' relatively to the origin
```

```
// of the coordinates system
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleOriginScalar(SCurve* that, float c) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
    // Scale the control point
    VecScale((VecFloat*)GSetIterGet(&iter), c);
 } while (GSetIterStep(&iter));
// Scale the curve by 'v' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleStartVector(SCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (VecGetDim(v) != SCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' 's dimension is invalid (%d=%d)",
      VecGetDim(v), SCurveGetDim(that));
    PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* origin = GSetGetFirst(&(that->_ctrl));
  // For each control point except the first one
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  if (GSetIterStep(&iter)) {
    do {
      VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
      // Translate the control point
      VecOp(ctrl, 1.0, origin, -1.0);
      // Scale the control point
      for (int iDim = SCurveGetDim(that); iDim--;)
       VecSet(ctrl, iDim, VecGet(ctrl, iDim) * VecGet(v, iDim));
      // Translate back the control point
      VecOp(ctrl, 1.0, origin, 1.0);
    } while (GSetIterStep(&iter));
// Scale the curve by 'c' relatively to its origin
```

```
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleStartScalar(SCurve* that, float c) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* origin = GSetGetFirst(&(that->_ctrl));
  // For each control point except teh first one
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  if (GSetIterStep(&iter)) {
    do {
      VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
      // Translate the control point
      VecOp(ctrl, 1.0, origin, -1.0);
      // Scale the control point
      VecScale(ctrl, c);
      // Translate back the control point
      VecOp(ctrl, 1.0, origin, 1.0);
    } while (GSetIterStep(&iter));
}
// Scale the curve by 'v' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleCenterVector(SCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  }
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
   PBErrCatch(BCurveErr);
  if (VecGetDim(v) != SCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' 's dimension is invalid (%d=%d)",
      VecGetDim(v), SCurveGetDim(that));
    PBErrCatch(BCurveErr);
#endif
  VecFloat* center = SCurveGetCenter(that);
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
  do {
    VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Scale the control point
    for (int iDim = SCurveGetDim(that); iDim--;)
      VecSet(ctrl, iDim, VecGet(ctrl, iDim) * VecGet(v, iDim));
```

```
// Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  } while (GSetIterStep(&iter));
  // Free memory
  VecFree(&center);
// Scale the curve by 'c' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _SCurveScaleCenterScalar(SCurve* that, float c) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
  VecFloat* center = SCurveGetCenter(that);
  // For each control point
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
    VecFloat* ctrl = (VecFloat*)GSetIterGet(&iter);
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Scale the control point
    VecScale(ctrl, c);
    // Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  } while (GSetIterStep(&iter));
  // Free memory
  VecFree(&center);
// Translate the curve by 'v'
#if BUILDMODE != 0
inline
#endif
void _SCurveTranslate(SCurve* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (VecGetDim(v) != SCurveGetDim(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    \label{eq:continuous} {\tt sprintf(BCurveErr->\_msg, "Dimension of 'v' is invalid (%d=%d)",}
      VecGetDim(v), SCurveGetDim(that));
    PBErrCatch(BCurveErr);
#endif
  // Translate all the control points
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_ctrl));
```

```
VecOp((VecFloat*)GSetIterGet(&iter), 1.0, v, 1.0);
 } while (GSetIterStep(&iter));
// Get the value of the SCurve at paramater 'u'
// The value is equal to the value of the floor(u)-th segment at
// value (u - floor(u))
// u can extend beyond [0.0, _nbSeg]
#if BUILDMODE != 0
inline
#endif
VecFloat* SCurveGet(SCurve* that, float u) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  \ensuremath{//} Declare a variable to memorize the relevant segment
  int iSeg = 0;
  // Get the segment the corresponding to 'u'
  if (u < 0.0)
    iSeg = 0;
  else if (u >= that->_nbSeg) {
    iSeg = that->_nbSeg - 1;
    u -= (float)(that->_nbSeg - 1);
  } else {
    iSeg = (int)floor(u);
    u -= (float)iSeg;
  }
  // Get the value of the BCurve
 return BCurveGet(SCurveSeg(that, iSeg), u);
// Get the approximate length of the SCurve (sum of approxLen
// of its BCurves)
#if BUILDMODE != 0
inline
#endif
float SCurveGetApproxLen(SCurve* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  // Declare a variable to memorize the length
  float length = 0.0;
  // For each segment
  GSetIterForward iter = GSetIterForwardCreateStatic(&(that->_seg));
  do {
    // Add the length of this segment
    length += BCurveGetApproxLen((BCurve*)GSetIterGet(&iter));
  } while (GSetIterStep(&iter));
  // Return the result
  return length;
// Set the 'iCtrl'-th control point to 'v'
#if BUILDMODE != 0
```

```
inline
#endif
void SCurveSetCtrl(SCurve* that, int iCtrl, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (iCtrl < 0 || iCtrl >= SCurveGetNbCtrl(that)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'iCtrl' is invalid (0<=%d<%d)",
      iCtrl, SCurveGetNbCtrl(that));
    PBErrCatch(BCurveErr);
 }
#endif
  VecCopy((VecFloat*)GSetGet(&(that->_ctrl), iCtrl), v);
}
// Create a new SCurve from the outline of the Shapoid 'shap'
// The Shapoid must be of dimension 2
// Control points are ordered CCW of the Shapoid
#if BUILDMODE != 0
inline
#endif
SCurve* SCurveCreateFromShapoid(Shapoid* shap) {
#if BUILDMODE == 0
  if (shap == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'shap' is null");
    PBErrCatch(BCurveErr);
  if (ShapoidGetDim(shap) != 2) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg,
      "'shap' 's dimension is invalid (%d==2)",
      ShapoidGetDim(shap));
    PBErrCatch(BCurveErr);
#endif
  // Declare the new curve
  SCurve* ret = NULL;
  // Call the appropriate function accoring to the type of the Shapoid
  switch (ShapoidGetType(shap)) {
    case ShapoidTypeFacoid:
      ret = SCurveCreateFromFacoid((Facoid*)shap);
      break:
    case ShapoidTypePyramidoid:
      ret = SCurveCreateFromPyramidoid((Pyramidoid*)shap);
      break;
    {\tt case \ ShapoidTypeSpheroid:}
      ret = SCurveCreateFromSpheroid((Spheroid*)shap);
      break:
    default:
      break;
  // Return the new curve
```

```
return ret;
// ----- SCurveIter
// ====== Functions implementation ========
// Set the attached SCurve of the SCurveIter 'that' to 'curve'
#if BUILDMODE != 0
{\tt inline}
#endif
void SCurveIterSetCurve(SCurveIter* that, SCurve* curve) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  }
  if (curve == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'curve' is null");
   PBErrCatch(BCurveErr);
 }
#endif
 that->_curve = curve;
// Set the delta of the SCurveIter 'that' to 'delta'
#if BUILDMODE != 0
inline
#endif
void SCurveIterSetDelta(SCurveIter* that, float delta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (delta <= 0.0) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "'delta' is invalid (%f>0)", delta);
   PBErrCatch(BCurveErr);
  }
#endif
  that->_delta = delta;
// Get the attached curve of the SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
SCurve* SCurveIterCurve(SCurveIter* that) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 7
#endif
 return that->_curve;
```

```
// Get the delta of the SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
float SCurveIterGetDelta(SCurveIter* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
 return that->_delta;
// Init the SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
void SCurveIterInit(SCurveIter* that) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
 that->_curPos = 0.0;
// Step the SCurveIter 'that'
// Return false if it couldn't step, true else
#if BUILDMODE != 0
inline
#endif
bool SCurveIterStep(SCurveIter* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
  if (that->_curPos >
    SCurveGetMaxU(SCurveIterCurve(that)) - PBMATH_EPSILON)
   return false;
  that->_curPos += that->_delta;
  if (that->_curPos > SCurveGetMaxU(SCurveIterCurve(that)))
    that->_curPos = SCurveGetMaxU(SCurveIterCurve(that));
 return true;
// Step back the SCurveIter 'that'
// Return false if it couldn't step, true else
#if BUILDMODE != 0
inline
bool SCurveIterStepP(SCurveIter* that) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
```

```
PBErrCatch(BCurveErr);
  }
#endif
  if (that->_curPos < PBMATH_EPSILON)</pre>
    return false;
  that->_curPos -= that->_delta;
  if (that->_curPos < 0.0)
    that->_curPos = 0.0;
 return true;
// Get the current value of the internal parameter of the
// SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
float SCurveIterGetPos(SCurveIter* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
 }
#endif
 return that->_curPos;
// Get the current value of the attached SCurve at the current
// internal position of the SCurveIter 'that'
#if BUILDMODE != 0
inline
#endif
VecFloat* SCurveIterGet(SCurveIter* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
 }
#endif
 return SCurveGet(SCurveIterCurve(that), that->_curPos);
// ----- BBody
// ======== Functions implementation ==========
// Set the value of the iCtrl-th control point to {\tt v}
#if BUILDMODE != 0
inline
#endif
void _BBodySetCtrl(BBody* that, VecShort* iCtrl, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (iCtrl == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
sprintf(BCurveErr->_msg, "'iCtrl' is null");
    PBErrCatch(BCurveErr);
```

```
if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (VecGetDim(iCtrl) != VecGet(&(that->_dim), 0)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'iCtrl' is invalid (%d=%d)",
      VecGetDim(iCtrl), VecGet(&(that->_dim), 0));
    PBErrCatch(BCurveErr);
  if (VecGetDim(v) != VecGet(&(that->_dim), 1)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
      VecGetDim(v), VecGet(&(that->_dim), 1));
    PBErrCatch(BCurveErr);
  }
#endif
  // Get the index of the ctrl
  int index = BBodyGetIndexCtrl(that, iCtrl);
  // If we could get the index
  if (index !=-1)
    // Set the ctrl
    VecCopy(that->_ctrl[index], v);
// Get the number of control points of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
int BBodyGetNbCtrl(BBody* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
#endif
  // Return the number of control points
 return powi(that->_order + 1, VecGet(&(that->_dim), 0));
// Get the the 'iCtrl'-th control point of 'that'
#if BUILDMODE != 0
inline
#endif
VecFloat* _BBodyCtrl(BBody* that, VecShort* iCtrl) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (iCtrl == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'iCtrl' is null");
   PBErrCatch(BCurveErr);
  if (VecGetDim(iCtrl) != VecGet(&(that->_dim), 0)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'iCtrl' is invalid (%d=%d)",
```

```
VecGetDim(iCtrl), VecGet(&(that->_dim), 0));
    PBErrCatch(BCurveErr);
#endif
  // Get the index
  int index = BBodyGetIndexCtrl(that, iCtrl);
  // If we could get the index
  if (index !=-1)
   // Return the control
    return that->_ctrl[index];
  // Else, we couldn't get the index
  else
    // Return NULL
    return NULL;
}
// Get the index in _ctrl of the 'iCtrl' control point of 'that'
#if BUILDMODE != 0
#endif
int _BBodyGetIndexCtrl(BBody* that, VecShort* iCtrl) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (iCtrl == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'iCtrl' is null");
   PBErrCatch(BCurveErr);
  if (VecGetDim(iCtrl) != VecGet(&(that->_dim), 0)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'iCtrl' is invalid (%d=%d)",
      VecGetDim(iCtrl), VecGet(&(that->_dim), 0));
   PBErrCatch(BCurveErr);
#endif
  for (int iDim = VecGetDim(iCtrl); iDim--;)
   if (VecGet(iCtrl, iDim) < 0 ||</pre>
      VecGet(iCtrl, iDim) > that->_order)
      return -1;
  // Declare a variable to memorize the dimension of input
  int dim = VecGetDim(iCtrl);
  // Get the index
  int index = 0;
  for (int iDim = 0; iDim < dim; ++iDim)</pre>
    index += index * that->_order + VecGet(iCtrl, iDim);
  // return the index
 return index;
// Get the order of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
int BBodyGetOrder(BBody* that) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
```

```
PBErrCatch(BCurveErr);
  }
#endif
 return that->_order;
// Get the dimensions of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
VecShort2D* BBodyDim(BBody* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
 return &(that->_dim);
// Get a copy of the dimensions of the BBody 'that'
#if BUILDMODE != 0
inline
#endif
VecShort2D BBodyGetDim(BBody* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
 return that->_dim;
// Return the center of the BBody (average of control points)
#if BUILDMODE != 0
inline
#endif
VecFloat* BBodyGetCenter(BBody* that) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
#endif
  // Sum all the control points
  VecFloat* center = VecFloatCreate(VecGet(BBodyDim(that), 1));
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;)
    VecOp(center, 1.0, that->_ctrl[iCtrl], 1.0);
  // Get the average
  VecScale(center, 1.0 / (float)(BBodyGetNbCtrl(that)));
  // Return the result
 return center;
// Translate the BBody by 'v'
#if BUILDMODE != 0
inline
#endif
```

```
void _BBodyTranslate(BBody* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (VecGetDim(v) != VecGet(BBodyDim(that), 1)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
      VecGetDim(v), VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
  }
#endif
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;)
    // Translate the control point
    VecOp(that->_ctrl[iCtrl], 1.0, v, 1.0);
// Scale the BBody by 'v' relatively to the origin
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleOriginVector(BBody* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (VecGetDim(v) != VecGet(BBodyDim(that), 1)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
      VecGetDim(v), VecGet(BBodyDim(that), 1));
   PBErrCatch(BCurveErr);
#endif
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Scale the control point
    for (int dim = 0; dim < VecGetDim(ctrl); ++dim)</pre>
      VecSet(ctrl, dim, VecGet(ctrl, dim) * VecGet(v, dim));
}
// Scale the BBody by 'c' relatively to the origin
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleOriginScalar(BBody* that, float c) {
```

```
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
#endif
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;)
    // Scale the control point
    VecScale(that->_ctrl[iCtrl], c);
// Scale the BBody by 'v' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleStartVector(BBody* that, VecFloat* v) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
    PBErrCatch(BCurveErr);
  if (VecGetDim(v) != VecGet(BBodyDim(that), 1)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
      VecGetDim(v), VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
 }
#endif
  // For each control point except the first one
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl-- && iCtrl != 0;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], -1.0);
    // Scale the control point
    for (int dim = 0; dim < VecGetDim(that->_ctrl[iCtrl]); ++dim)
      VecSet(ctrl, dim, VecGet(ctrl, dim) * VecGet(v, dim));
    // Translate back the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], 1.0);
// Scale the BBody by 'c' relatively to its origin
// (first control point)
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleStartScalar(BBody* that, float c) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
```

```
#endif
  // For each control point except the first one
 for (int iCtrl = BBodyGetNbCtrl(that); iCtrl-- && iCtrl != 0;) {
   VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], -1.0);
    // Scale the control point
    VecScale(ctrl, c);
    // Translate back the control point
    VecOp(ctrl, 1.0, that->_ctrl[0], 1.0);
// Scale the BBody by 'v' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleCenterVector(BBody* that, VecFloat* v) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (v == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'v' is null");
   PBErrCatch(BCurveErr);
 if (VecGetDim(v) != VecGet(BBodyDim(that), 1)) {
    BCurveErr->_type = PBErrTypeInvalidArg;
    sprintf(BCurveErr->_msg, "Dimension of 'v' is invalid (%d=%d)",
     VecGetDim(v), VecGet(BBodyDim(that), 1));
   PBErrCatch(BCurveErr);
 }
#endif
  VecFloat* center = BBodyGetCenter(that);
  // For each control point
 for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
   VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Scale the control point
    for (int dim = 0; dim < VecGetDim(that->_ctrl[iCtrl]); ++dim)
     VecSet(ctrl, dim, VecGet(ctrl, dim) * VecGet(v, dim));
    // Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  // Free memory
 VecFree(&center);
// Scale the BBody by 'c' relatively to its center
// (average of control points)
#if BUILDMODE != 0
inline
#endif
void _BBodyScaleCenterScalar(BBody* that, float c) {
#if BUILDMODE == 0
 if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
```

```
sprintf(BCurveErr->_msg, "'that' is null");
         PBErrCatch(BCurveErr);
#endif
    VecFloat* center = BBodyGetCenter(that);
     // For each control point
    for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
         VecFloat* ctrl = that->_ctrl[iCtrl];
         // Translate the control point
         VecOp(ctrl, 1.0, center, -1.0);
         // Scale the control point
         VecScale(ctrl, c);
         // Translate back the control point
         VecOp(ctrl, 1.0, center, 1.0);
    }
     // Free memory
    VecFree(&center);
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around 'axis'
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
\verb|void BBodyRotAxisOrigin(BBody* that, VecFloat3D* axis, float theta)| \{ | (BBodyRotAxisOrigin(BBody* that, VecFloat3D* axis, float theta) \} | (BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOrigin(BBodyRotAxisOri
#if BUILDMODE == 0
    if (that == NULL) {
         BCurveErr->_type = PBErrTypeNullPointer;
         sprintf(BCurveErr->_msg, "'that' is null");
        PBErrCatch(BCurveErr);
    if (axis == NULL) {
         BCurveErr->_type = PBErrTypeNullPointer;
         sprintf(BCurveErr->_msg, "'axis' is null");
         PBErrCatch(BCurveErr);
    if (VecGet(BBodyDim(that), 1) != 3) {
         BCurveErr->_type = PBErrTypeNullPointer;
         sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
             VecGet(BBodyDim(that), 1));
         PBErrCatch(BCurveErr);
    }
#endif
     // For each control point
    for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
         VecFloat* ctrl = that->_ctrl[iCtrl];
         // Rotate the control point
         VecRotAxis((VecFloat3D*)ctrl, axis, theta);
   }
}
// Rotate the BBody by 'theta' relatively to the center
// of the body around 'axis'
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotAxisCenter(BBody* that, VecFloat3D* axis, float theta) {
#if BUILDMODE == 0
    if (that == NULL) {
         BCurveErr->_type = PBErrTypeNullPointer;
```

```
sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (axis == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'axis' is null");
   PBErrCatch(BCurveErr);
 if (VecGet(BBodyDim(that), 1) != 3) {
   BCurveErr->_type = PBErrTypeNullPointer;
    {\tt sprintf(BCurveErr->\_msg,\ "'that'\ 's\ dimension\ is\ invalid\ (\%d=3)",}
     VecGet(BBodyDim(that), 1));
   PBErrCatch(BCurveErr);
 }
#endif
 VecFloat* center = BBodyGetCenter(that);
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Rotate the control point
    VecRotAxis((VecFloat3D*)ctrl, axis, theta);
    // Translate back the control point
   VecOp(ctrl, 1.0, center, 1.0);
  // Free memory
 VecFree(&center);
// Rotate the BBody by 'theta' relatively to the first control point
// of the body around 'axis'
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotAxisStart(BBody* that, VecFloat3D* axis, float theta) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (axis == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'axis' is null");
   PBErrCatch(BCurveErr);
 if (VecGet(BBodyDim(that), 1) != 3) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
   PBErrCatch(BCurveErr);
#endif
 VecFloat* start = that->_ctrl[0];
  // For each control point except the first one
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl-- && iCtrl != 0;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, start, -1.0);
    // Rotate the control point
```

```
VecRotAxis((VecFloat3D*)ctrl, axis, theta);
    // Translate back the control point
    VecOp(ctrl, 1.0, start, 1.0);
}
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around X
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotXOrigin(BBody* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
#endif
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Rotate the control point
    VecRotX((VecFloat3D*)ctrl, theta);
 }
// Rotate the BBody by 'theta' relatively to the center
// of the body around X
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotXCenter(BBody* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    {\tt sprintf(BCurveErr->\_msg, "'that' 's \ dimension \ is \ invalid \ (\%d=3)",}
      VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* center = BBodyGetCenter(that);
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Rotate the control point
    VecRotX((VecFloat3D*)ctrl, theta);
```

```
// Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  // Free memory
  VecFree(&center);
// Rotate the BBody by 'theta' relatively to the first control point
// of the body around X
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotXStart(BBody* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
   PBErrCatch(BCurveErr);
 }
#endif
  VecFloat* start = that->_ctrl[0];
  // For each control point except the first one
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl-- && iCtrl != 0;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, start, -1.0);
    // Rotate the control point
    VecRotX((VecFloat3D*)ctrl, theta);
    // Translate back the control point
    VecOp(ctrl, 1.0, start, 1.0);
}
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around Y
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotYOrigin(BBody* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
  }
#endif
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
```

```
VecFloat* ctrl = that->_ctrl[iCtrl];
    // Rotate the control point
    VecRotY((VecFloat3D*)ctrl, theta);
}
// Rotate the BBody by 'theta' relatively to the center
// of the body around Y
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotYCenter(BBody* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* center = BBodyGetCenter(that);
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
   VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Rotate the control point
    VecRotY((VecFloat3D*)ctrl, theta);
    // Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
  }
  // Free memory
  VecFree(&center);
// Rotate the BBody by 'theta' relatively to the first control point
// of the body around Y
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotYStart(BBody* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* start = that->_ctrl[0];
```

```
// For each control point except the first one
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl-- && iCtrl != 0;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, start, -1.0);
    // Rotate the control point
    VecRotY((VecFloat3D*)ctrl, theta);
    // Translate back the control point
    VecOp(ctrl, 1.0, start, 1.0);
}
// Rotate the BBody by 'theta' relatively to the origin
// of the coordinates system around Z
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotZOrigin(BBody* that, float theta) {
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
     VecGet(BBodyDim(that), 1));
    PBErrCatch(BCurveErr);
  }
#endif
  // For each control point
  for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
    VecFloat* ctrl = that->_ctrl[iCtrl];
    // Rotate the control point
    VecRotZ((VecFloat3D*)ctrl, theta);
}
// Rotate the BBody by 'theta' relatively to the center
// of the body around Z
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
#if BUILDMODE == 0
  if (that == NULL) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
    PBErrCatch(BCurveErr);
  }
  if (VecGet(BBodyDim(that), 1) != 3) {
    BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
   PBErrCatch(BCurveErr);
  }
#endif
  VecFloat* center = BBodyGetCenter(that);
  // For each control point
```

```
for (int iCtrl = BBodyGetNbCtrl(that); iCtrl--;) {
   VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, center, -1.0);
    // Rotate the control point
    VecRotZ((VecFloat3D*)ctrl, theta);
    // Translate back the control point
    VecOp(ctrl, 1.0, center, 1.0);
 // Free memory
 VecFree(&center);
// Rotate the BBody by 'theta' relatively to the first control point
// of the body around Z
// dim[1] of BBody must be 3
#if BUILDMODE != 0
inline
#endif
void BBodyRotZStart(BBody* that, float theta) {
#if BUILDMODE == 0
 if (that == NULL) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' is null");
   PBErrCatch(BCurveErr);
 if (VecGet(BBodyDim(that), 1) != 3) {
   BCurveErr->_type = PBErrTypeNullPointer;
    sprintf(BCurveErr->_msg, "'that' 's dimension is invalid (%d=3)",
      VecGet(BBodyDim(that), 1));
   PBErrCatch(BCurveErr);
#endif
 VecFloat* start = that->_ctrl[0];
  // For each control point except the first one
 for (int iCtrl = BBodyGetNbCtrl(that); iCtrl-- && iCtrl != 0;) {
   VecFloat* ctrl = that->_ctrl[iCtrl];
    // Translate the control point
    VecOp(ctrl, 1.0, start, -1.0);
    // Rotate the control point
    VecRotZ((VecFloat3D*)ctrl, theta);
    // Translate back the control point
    VecOp(ctrl, 1.0, start, 1.0);
```

### 4 Makefile

```
#directory
PBERRDIR=../PBErr

# Build mode
# 0: development (max safety, no optimisation)
# 1: release (min safety, optimisation)
# 2: fast and furious (no safety, optimisation)
BUILDMODE=1
include $(PBERRDIR)/Makefile.inc
```

```
INCPATH=-I./ -I$(PBERRDIR)/
BUILDOPTIONS=$(BUILDPARAM) $(INCPATH)
# compiler
COMPILER=gcc
#rules
all : main
main: main.o pberr.o pbmath.o Makefile
$(COMPILER) main.o pberr.o pbmath.o $(LINKOPTIONS) -o main
main.o : main.c $(PBERRDIR)/pberr.h pbmath.h pbmath-inline.c Makefile
$(COMPILER) $(BUILDOPTIONS) -c main.c
pbmath.o : pbmath.c pbmath.h pbmath-inline.c Makefile
$(COMPILER) $(BUILDOPTIONS) -c pbmath.c
pberr.o : $(PBERRDIR)/pberr.c $(PBERRDIR)/pberr.h Makefile
$(COMPILER) $(BUILDOPTIONS) -c $(PBERRDIR)/pberr.c
clean :
rm -rf *.o main
valgrind :
valgrind -v --track-origins=yes --leak-check=full --gen-suppressions=yes --show-leak-kinds=all ./main
main > unitTest.txt; diff unitTest.txt unitTestRef.txt
```

# 5 Unit tests

```
#include <stdlib.h>
#include <stdio.h>
#include <time.h>
#include <string.h>
#include <time.h>
#include <unistd.h>
#include <sys/time.h>
#include "pberr.h"
#include "bcurve.h"
#define RANDOMSEED 0
void UnitTestBCurveCreateCloneFree() {
  int order = 3;
  int dim = 2;
  BCurve* curve = BCurveCreate(order, dim);
  if (curve->_dim != dim || curve->_order != order){
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveCreate failed");
   PBErrCatch(BCurveErr);
  VecFloat* v = VecFloatCreate(dim);
  for (int iCtrl = order + 1; iCtrl--;) {
    if (VecIsEqual(curve->_ctrl[iCtrl], v) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveCreate failed");
```

```
PBErrCatch(BCurveErr);
   }
 for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
     VecSet(v, iDim, iCtrl * dim + iDim);
   BCurveSetCtrl(curve, iCtrl, v);
 BCurve* clone= BCurveClone(curve);
  if (clone->_dim != dim || clone->_order != order){
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveClone failed");
   PBErrCatch(BCurveErr);
 for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
     VecSet(v, iDim, iCtrl * dim + iDim);
    if (VecIsEqual(clone->_ctrl[iCtrl], v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveClone failed");
     PBErrCatch(BCurveErr);
   }
 }
 BCurveFree(&curve);
 if (curve != NULL) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveFree failed");
   PBErrCatch(BCurveErr);
 BCurveFree(&clone);
 VecFree(&v);
 printf("UnitTestBCurveCreateCloneFree OK\n");
void UnitTestBCurveLoadSavePrint() {
 int order = 3:
 int dim = 2:
 BCurve* curve = BCurveCreate(order, dim);
 VecFloat* v = VecFloatCreate(dim);
  for (int iCtrl = order + 1; iCtrl--;) {
   for (int iDim = dim; iDim--;)
     VecSet(v, iDim, iCtrl * dim + iDim);
   BCurveSetCtrl(curve, iCtrl, v);
 BCurvePrint(curve, stdout);
 printf("\n");
 FILE* file = fopen("./bcurve.txt", "w");
  if (BCurveSave(curve, file) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveSave failed");
   PBErrCatch(BCurveErr);
 BCurve* load = BCurveCreate(order, dim);
 fclose(file);
 file = fopen("./bcurve.txt", "r");
  if (BCurveLoad(&load, file) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveLoad failed");
   PBErrCatch(BCurveErr);
 fclose(file);
 if (load->_dim != dim || load->_order != order) {
```

```
BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveLoad failed");
   PBErrCatch(BCurveErr);
 for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
     VecSet(v, iDim, iCtrl * dim + iDim);
    if (VecIsEqual(load->_ctrl[iCtrl], v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveLoad failed");
     PBErrCatch(BCurveErr);
 BCurveFree(&curve);
 BCurveFree(&load);
 VecFree(&v);
 printf("UnitTestBCurveLoadSavePrint OK\n");
void UnitTestBCurveGetSetCtrl() {
 int order = 3;
  int dim = 2;
 BCurve* curve = BCurveCreate(order, dim);
 VecFloat* v = VecFloatCreate(dim);
 for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
      VecSet(v, iDim, iCtrl * dim + iDim);
    BCurveSetCtrl(curve, iCtrl, v);
    if (VecIsEqual(curve->_ctrl[iCtrl], v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveSetCtrl failed");
     PBErrCatch(BCurveErr);
    VecFloat* w = BCurveGetCtrl(curve, iCtrl);
    if (VecIsEqual(w, v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveGetCtrl failed");
     PBErrCatch(BCurveErr);
    VecFree(&w);
    if (VecIsEqual(BCurveCtrl(curve, iCtrl), v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveCtrl failed");
     PBErrCatch(BCurveErr);
   }
 BCurveFree(&curve);
 VecFree(&v);
 printf("UnitTestBCurveGetSetCtrl OK\n");
void UnitTestBCurveGet() {
 int order = 3;
  int dim = 2;
 BCurve* curve = BCurveCreate(order, dim);
 VecFloat* v = VecFloatCreate(dim);
 for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
      VecSet(v, iDim, iCtrl * dim + iDim);
   BCurveSetCtrl(curve, iCtrl, v);
 for (float u = 0.0; u < 1.0 + PBMATH_EPSILON; u += 0.1) {
```

```
VecFloat* w = BCurveGet(curve, u);
    if (ISEQUALF(VecGet(w, 0), u * 6.0) == false ||
      ISEQUALF(VecGet(w, 1), u * 6.0 + 1.0) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveGet failed");
      PBErrCatch(BCurveErr);
    VecFree(&w);
  BCurveFree(&curve);
  VecFree(&v);
  printf("UnitTestBCurveGet OK\n");
void UnitTestBCurveGetOrderDim() {
  int order = 3;
  int dim = 2;
  BCurve* curve = BCurveCreate(order, dim);
  if (BCurveGetOrder(curve) != order) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveGetOrder failed");
   PBErrCatch(BCurveErr);
  }
  if (BCurveGetDim(curve) != dim) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveGetDim failed");
    PBErrCatch(BCurveErr);
  BCurveFree(&curve);
 printf("UnitTestBCurveGetOrderDim OK\n");
void UnitTestBCurveGetApproxLenCenter() {
  int order = 3;
  int dim = 2;
  BCurve* curve = BCurveCreate(order, dim);
  VecFloat* v = VecFloatCreate(dim);
  for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
      VecSet(v, iDim, iCtrl * dim + iDim);
   BCurveSetCtrl(curve, iCtrl, v);
  float len = BCurveGetApproxLen(curve);
  if (ISEQUALF(len, 8.485281) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveGetApproxLen failed");
   PBErrCatch(BCurveErr);
  VecFloat* center = BCurveGetCenter(curve);
  VecSet(v, 0, 3.0);
  VecSet(v, 1, 4.0);
  if (VecIsEqual(v, center) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveGetCenter failed");
   PBErrCatch(BCurveErr);
  VecFree(&center);
  BCurveFree(&curve);
  VecFree(&v);
  printf("UnitTestBCurveGetApproxLenCenter OK\n");
```

```
void UnitTestBCurveRot() {
  int order = 3;
  int dim = 2;
  BCurve* curve = BCurveCreate(order, dim);
  VecFloat* v = VecFloatCreate(dim);
  for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
      VecSet(v, iDim, iCtrl * dim + iDim);
   BCurveSetCtrl(curve, iCtrl, v);
  float theta = PBMATH_HALFPI;
  BCurveRotOrigin(curve, theta);
  float pa[8] = \{-1.0, 0.0, -3.0, 2.0, -5.0, 4.0, -7.0, 6.0\};
  for (int iCtrl = order + 1; iCtrl--;)
    for (int iDim = dim; iDim--;)
      if (ISEQUALF(VecGet(BCurveCtrl(curve, iCtrl), iDim),
        pa[iCtrl * dim + iDim]) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "BCurveRotOrigin failed");
        PBErrCatch(BCurveErr);
      }
  BCurveRotStart(curve, theta);
  float pb[8] = \{-1.0, 0.0, -3.0, -2.0, -5.0, -4.0, -7.0, -6.0\};
  for (int iCtrl = order + 1; iCtrl--;)
    for (int iDim = dim; iDim--;)
      if (ISEQUALF(VecGet(BCurveCtrl(curve, iCtrl), iDim),
        pb[iCtrl * dim + iDim]) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "BCurveRotStart failed");
        PBErrCatch(BCurveErr);
  BCurveRotCenter(curve, theta);
  float pc[8] = \{-7.0, 0.0, -5.0, -2.0, -3.0, -4.0, -1.0, -6.0\};
  for (int iCtrl = order + 1; iCtrl--;)
    for (int iDim = dim; iDim--;)
      if (ISEQUALF(VecGet(BCurveCtrl(curve, iCtrl), iDim),
        pc[iCtrl * dim + iDim]) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "BCurveRotCenter failed");
        PBErrCatch(BCurveErr);
  BCurveFree(&curve);
  VecFree(&v);
  printf("UnitTestBCurveRot OK\n");
void UnitTestBCurveScale() {
  int order = 3;
  int dim = 2;
  BCurve* curve = BCurveCreate(order, dim);
  VecFloat* v = VecFloatCreate(dim);
  for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
      VecSet(v, iDim, iCtrl * dim + iDim);
    BCurveSetCtrl(curve, iCtrl, v);
  float scale = 2.0;
  BCurveScaleOrigin(curve, scale);
  float pa[8] = {0.0,2.0, 4.0, 6.0, 8.0, 10.0, 12.0, 14.0};
  for (int iCtrl = order + 1; iCtrl--;)
    for (int iDim = dim; iDim--;)
      if (ISEQUALF(VecGet(BCurveCtrl(curve, iCtrl), iDim),
```

```
pa[iCtrl * dim + iDim]) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "BCurveScaleOrigin failed");
       PBErrCatch(BCurveErr);
 BCurveScaleStart(curve, scale);
  float pb[8] = {0.0, 2.0, 8.0, 10.0, 16.0, 18.0, 24.0, 26.0};
  for (int iCtrl = order + 1; iCtrl--;)
   for (int iDim = dim; iDim--;)
      if (ISEQUALF(VecGet(BCurveCtrl(curve, iCtrl), iDim),
       pb[iCtrl * dim + iDim]) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "BCurveScaleStart failed");
        PBErrCatch(BCurveErr);
 BCurveScaleCenter(curve, scale);
 float pc[8] = \{-12.0, -10.0, 4.0, 6.0, 20.0, 22.0, 36.0, 38.0\};
  for (int iCtrl = order + 1; iCtrl--;)
    for (int iDim = dim; iDim--;)
      if (ISEQUALF(VecGet(BCurveCtrl(curve, iCtrl), iDim),
        pc[iCtrl * dim + iDim]) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "BCurveScaleCenter failed");
       PBErrCatch(BCurveErr);
 BCurveFree(&curve);
 VecFree(&v);
 printf("UnitTestBCurveScale OK\n");
void UnitTestBCurveTranslate() {
 int order = 3;
 int dim = 2;
 BCurve* curve = BCurveCreate(order, dim);
  VecFloat* v = VecFloatCreate(dim);
 for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;)
     VecSet(v, iDim, iCtrl * dim + iDim);
   BCurveSetCtrl(curve, iCtrl, v);
 VecSet(v, 0, -1.0);
 VecSet(v, 1, -2.0);
  BCurveTranslate(curve, v);
 for (int iCtrl = order + 1; iCtrl--;) {
    for (int iDim = dim; iDim--;) {
      VecSet(v, iDim, iCtrl * dim + iDim);
      if (ISEQUALF(VecGet(BCurveCtrl(curve, iCtrl), iDim),
        VecGet(v, iDim) - (float)(iDim + 1)) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "BCurveTranslate failed");
       PBErrCatch(BCurveErr);
   }
 BCurveFree(&curve);
 VecFree(&v);
 printf("UnitTestBCurveTranslate OK\n");
void UnitTestBCurveFromCloudPoint() {
 int order = 2;
 int dim = 2;
```

```
BCurve* curve = BCurveCreate(order, dim);
 VecFloat* vA = VecFloatCreate(dim);
 VecSet(vA, 0, 0.0); VecSet(vA, 1, 0.0);
 BCurveSetCtrl(curve, 0, vA);
 VecFloat* vB = VecFloatCreate(dim);
 VecSet(vB, 0, 0.5); VecSet(vB, 1, 1.0);
 BCurveSetCtrl(curve, 1, vB);
 VecFloat* vC = VecFloatCreate(dim);
 VecSet(vC, 0, 1.0); VecSet(vC, 1, 0.0);
 BCurveSetCtrl(curve, 2, vC);
 GSetVecFloat* set = GSetVecFloatCreate();
 VecFree(&vB);
 vB = BCurveGet(curve, 0.5);
 GSetAppend(set, vA);
 GSetAppend(set, vB);
 GSetAppend(set, vC);
 BCurve* cloud = BCurveFromCloudPoint(set);
 if (cloud == NULL) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BCurveFromCloudPoint failed");
   PBErrCatch(BCurveErr);
 for (float u = 0.0; u < 1.0 + PBMATH_EPSILON; u += 0.1) {
   VecFloat* wA = BCurveGet(curve, u);
   VecFloat* wB = BCurveGet(cloud, u);
   if (VecIsEqual(wA, wB) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "BCurveFromCloudPoint failed");
     PBErrCatch(BCurveErr);
   VecFree(&wA);
   VecFree(&wB);
 GSetFree(&set);
 BCurveFree(&curve);
 BCurveFree(&cloud):
 VecFree(&vA);
 VecFree(&vB);
 VecFree(&vC):
 printf("UnitTestBCurveFromCloudPoint OK\n");
void UnitTestBCurveGetWeightCtrlPt() {
 int order = 2:
 int dim = 2:
 BCurve* curve = BCurveCreate(order, dim);
 VecFloat* vA = VecFloatCreate(dim);
 VecSet(vA, 0, 0.0); VecSet(vA, 1, 0.0);
 BCurveSetCtrl(curve, 0, vA);
 VecFloat* vB = VecFloatCreate(dim);
 VecSet(vB, 0, 0.5); VecSet(vB, 1, 1.0);
 BCurveSetCtrl(curve, 1, vB):
 VecFloat* vC = VecFloatCreate(dim);
 VecSet(vC, 0, 1.0); VecSet(vC, 1, 0.0);
 BCurveSetCtrl(curve, 2, vC);
 float pa[11] =
   \{1.0, 0.81, 0.64, 0.49, 0.36, 0.25, 0.16, 0.09, 0.04, 0.01, 0.0\};
 float pb[11] =
   \{0.0, 0.18, 0.32, 0.42, 0.48, 0.5, 0.48, 0.42, 0.32, 0.18, 0.0\};
 float pc[11] =
   \{0.0, 0.01, 0.04, 0.09, 0.16, 0.25, 0.36, 0.49, 0.64, 0.81, 1.0\};
 int iArr = 0;
```

```
for (float u = 0.0; u < 1.0 + PBMATH_EPSILON; u += 0.1, ++iArr) {
    VecFloat* w = BCurveGetWeightCtrlPt(curve, u);
    if (ISEQUALF(VecGet(w, 0), pa[iArr]) == false ||
      ISEQUALF(VecGet(w, 1), pb[iArr]) == false ||
      ISEQUALF(VecGet(w, 2), pc[iArr]) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BCurveGetWeightCtrlPt failed");
     PBErrCatch(BCurveErr);
   VecFree(&w);
 BCurveFree(&curve);
 VecFree(&vA);
  VecFree(&vB);
 VecFree(&vC);
 printf("UnitTestBCurveGetWeightCtrlPt OK\n");
void UnitTestBCurveGetBoundingBox() {
 int order = 3:
 int dim = 2;
 BCurve* curve = BCurveCreate(order, dim);
 VecFloat* v = VecFloatCreate(dim);
 VecSet(v, 0, -0.5); VecSet(v, 1, -0.5);
 BCurveSetCtrl(curve, 0, v);
 VecSet(v, 0, 0.0); VecSet(v, 1, 1.0);
  BCurveSetCtrl(curve, 1, v);
  VecSet(v, 0, 1.0); VecSet(v, 1, 1.5);
 BCurveSetCtrl(curve, 2, v);
  VecSet(v, 0, 1.5); VecSet(v, 1, 0.0);
 BCurveSetCtrl(curve, 3, v);
 Facoid* bound = BCurveGetBoundingBox(curve);
 Facoid* check = FacoidCreate(dim);
  float scale = 2.0;
  ShapoidScale(check, scale);
 VecSet(v, 0, -0.5); VecSet(v, 1, -0.5);
  ShapoidTranslate(check, v);
  if (ShapoidIsEqual(bound, check) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BCurveGetBoundingBox failed");
   PBErrCatch(BCurveErr);
 ShapoidFree(&bound);
 ShapoidFree(&check);
 BCurveFree(&curve);
 VecFree(&v);
 \verb|printf("UnitTestBCurveGetBoundingBox OK\n");|\\
void UnitTestBCurve() {
  UnitTestBCurveCreateCloneFree();
 UnitTestBCurveLoadSavePrint();
 UnitTestBCurveGetSetCtrl();
 UnitTestBCurveGet();
 UnitTestBCurveGetOrderDim();
 UnitTestBCurveGetApproxLenCenter();
  UnitTestBCurveRot();
 UnitTestBCurveScale();
  UnitTestBCurveTranslate();
 UnitTestBCurveFromCloudPoint();
 UnitTestBCurveGetWeightCtrlPt();
 UnitTestBCurveGetBoundingBox();
```

```
printf("UnitTestBCurve OK\n");
void UnitTestSCurveCreateCloneFree() {
 int order = 3;
 int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 if (curve->_dim != dim || curve->_order != order ||
   curve->_nbSeg != nbSeg ||
   GSetNbElem(&(curve->_ctrl)) != 1 + order * nbSeg){
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveCreate failed");
   PBErrCatch(BCurveErr);
 VecFloat* v = VecFloatCreate(dim);
 GSetIterForward iter = GSetIterForwardCreateStatic(&(curve->_ctrl));
 do {
   VecFloat* ctrl = GSetIterGet(&iter);
   if (VecIsEqual(ctrl, v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "SCurveCreate failed");
     PBErrCatch(BCurveErr);
 } while (GSetIterStep(&iter));
 iter = GSetIterForwardCreateStatic(&(curve->_seg));
 VecFloat* prevCtrl = (VecFloat*)(curve->_ctrl._set._head->_data);
 do {
   BCurve* seg = GSetIterGet(&iter);
   if (seg->_ctrl[0] != prevCtrl) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "SCurveCreate failed");
     PBErrCatch(BCurveErr);
   }
   prevCtrl = seg->_ctrl[order];
 } while (GSetIterStep(&iter));
 iter = GSetIterForwardCreateStatic(&(curve->_ctrl));
 int iCtrl = 0;
 do {
   VecFloat* ctrl = GSetIterGet(&iter);
   for (int iDim = dim; iDim--;)
     VecSet(ctrl, iDim, iCtrl * dim + iDim);
 } while (GSetIterStep(&iter));
 SCurve* clone= SCurveClone(curve);
 if (clone->_dim != dim || clone->_order != order ||
   clone->_nbSeg != nbSeg){
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveClone failed");
   PBErrCatch(BCurveErr);
 iter = GSetIterForwardCreateStatic(&(curve->_ctrl));
 GSetIterForward iterClone =
   GSetIterForwardCreateStatic(&(clone->_ctrl));
 do {
   VecFloat* ctrl = GSetIterGet(&iter);
   VecFloat* ctrlClone = GSetIterGet(&iterClone);
   if (VecIsEqual(ctrl, ctrlClone) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "SCurveClone failed");
     PBErrCatch(BCurveErr);
```

```
} while (GSetIterStep(&iter) && GSetIterStep(&iterClone));
  SCurveFree(&curve);
  if (curve != NULL) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveFree failed");
   PBErrCatch(BCurveErr);
  SCurveFree(&clone);
  VecFree(&v);
 printf("UnitTestSCurveCreateCloneFree OK\n");
void UnitTestSCurveLoadSavePrint() {
  int order = 3;
  int dim = 2:
  int nbSeg = 3;
  SCurve* curve = SCurveCreate(order, dim, nbSeg);
  GSetIterForward iter = GSetIterForwardCreateStatic(&(curve->_ctrl));
  do {
    VecFloat* ctrl = GSetIterGet(&iter);
    for (int iDim = dim; iDim--;)
      VecSet(ctrl, iDim, iCtrl * dim + iDim);
  } while (GSetIterStep(&iter));
  SCurvePrint(curve, stdout);
  printf("\n");
  FILE* file = fopen("./scurve.txt", "w");
  if (SCurveSave(curve, file) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveSave failed");
   PBErrCatch(BCurveErr);
  SCurve* load = SCurveCreate(order, dim, nbSeg);
  fclose(file);
  file = fopen("./scurve.txt", "r");
if (SCurveLoad(&load, file) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveLoad failed");
    PBErrCatch(BCurveErr);
  fclose(file);
  if (load->_dim != dim || load->_order != order ||
    load->_order != order) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveLoad failed");
   PBErrCatch(BCurveErr);
  iter = GSetIterForwardCreateStatic(&(curve->_ctrl));
  GSetIterForward iterLoad =
    GSetIterForwardCreateStatic(&(load->_ctrl));
  do {
    VecFloat* ctrl = GSetIterGet(&iter);
    VecFloat* ctrlLoad = GSetIterGet(&iterLoad);
    if (VecIsEqual(ctrl, ctrlLoad) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveLoad failed");
      PBErrCatch(BCurveErr);
  } while (GSetIterStep(&iter) && GSetIterStep(&iterLoad));
  SCurveFree(&curve);
  SCurveFree(&load);
```

```
printf("UnitTestSCurveLoadSavePrint OK\n");
void UnitTestSCurveGetSetCtrl() {
 int order = 3;
  int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
  VecFloat* v = VecFloatCreate(dim);
  if (SCurveCtrls(curve) != &(curve->_ctrl)) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveCtrls failed");
   PBErrCatch(BCurveErr);
 if (SCurveSegs(curve) != &(curve->_seg)) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveSegs failed");
   PBErrCatch(BCurveErr);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
    for (int iDim = dim; iDim--;)
     VecSet(v, iDim, iCtrl * dim + iDim);
    SCurveSetCtrl(curve, iCtrl, v);
 GSetIterForward iter = GSetIterForwardCreateStatic(&(curve->_ctrl));
 int iCtrl = 0;
  do {
   for (int iDim = dim; iDim--;)
     VecSet(v, iDim, iCtrl * dim + iDim);
    VecFloat* ctrl = GSetIterGet(&iter);
    if (VecIsEqual(ctrl, v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "SCurveSetCtrl failed");
     PBErrCatch(BCurveErr);
    if (ctrl != SCurveCtrl(curve, iCtrl)) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveCtrl failed");
     PBErrCatch(BCurveErr);
   }
    ctrl = SCurveGetCtrl(curve, iCtrl);
    if (VecIsEqual(ctrl, v) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveGetCtrl failed");
     PBErrCatch(BCurveErr);
    VecFree(&ctrl);
    ++iCtrl;
  } while (GSetIterStep(&iter));
 VecFree(&v);
 SCurveFree(&curve);
 printf("UnitTestSCurveGetSetCtrl OK\n");
void UnitTestSCurveGetAddRemoveSeg() {
 int order = 3;
 int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
  VecFloat* v = VecFloatCreate(dim);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   for (int iDim = dim; iDim--;)
```

```
VecSet(v, iDim, iCtrl * dim + iDim);
  SCurveSetCtrl(curve, iCtrl, v);
for (int iSeg = SCurveGetNbSeg(curve); iSeg--;) {
  BCurve* seg = SCurveGetSeg(curve, iSeg);
  if (BCurveGetDim(seg) != dim || BCurveGetOrder(seg) != order) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetSeg failed");
   PBErrCatch(BCurveErr);
  for (int iCtrl = order + 1; iCtrl--;) {
    int jCtrl = iSeg * order + iCtrl;
    if (VecIsEqual(BCurveCtrl(seg, iCtrl),
      SCurveCtrl(curve, jCtrl)) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveGetSeg failed");
     PBErrCatch(BCurveErr);
    if (BCurveCtrl(SCurveSeg(curve, iSeg), iCtrl) !=
      SCurveCtrl(curve, jCtrl)) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveSeg failed");
     PBErrCatch(BCurveErr);
 BCurveFree(&seg);
SCurveAddSegHead(curve);
SCurveAddSegTail(curve);
for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
  for (int iDim = dim; iDim--;)
   VecSet(v, iDim, iCtrl * dim + iDim);
  SCurveSetCtrl(curve, iCtrl, v);
for (int iSeg = SCurveGetNbSeg(curve); iSeg--;) {
 BCurve* seg = SCurveGetSeg(curve, iSeg);
  if (BCurveGetDim(seg) != dim || BCurveGetOrder(seg) != order) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetSeg failed1");
   PBErrCatch(BCurveErr);
  for (int iCtrl = order + 1; iCtrl--;) {
    int jCtrl = iSeg * order + iCtrl;
    if (VecIsEqual(BCurveCtrl(seg, iCtrl),
      SCurveCtrl(curve, jCtrl)) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveGetSeg failed2");
     PBErrCatch(BCurveErr);
    if (BCurveCtrl(SCurveSeg(curve, iSeg), iCtrl) !=
      SCurveCtrl(curve, jCtrl)) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveSeg failed");
      PBErrCatch(BCurveErr);
 }
 BCurveFree(&seg);
SCurveRemoveHeadSeg(curve);
SCurveRemoveTailSeg(curve);
for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
  for (int iDim = dim; iDim--;)
```

```
VecSet(v, iDim, iCtrl * dim + iDim);
    SCurveSetCtrl(curve, iCtrl, v);
  for (int iSeg = SCurveGetNbSeg(curve); iSeg--;) {
    BCurve* seg = SCurveGetSeg(curve, iSeg);
    if (BCurveGetDim(seg) != dim || BCurveGetOrder(seg) != order) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveGetSeg failed");
      PBErrCatch(BCurveErr);
    for (int iCtrl = order + 1; iCtrl--;) {
      int jCtrl = iSeg * order + iCtrl;
      if (VecIsEqual(BCurveCtrl(seg, iCtrl),
        SCurveCtrl(curve, jCtrl)) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "SCurveGetSeg failed");
        PBErrCatch(BCurveErr);
      if (BCurveCtrl(SCurveSeg(curve, iSeg), iCtrl) !=
        SCurveCtrl(curve, jCtrl)) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
        sprintf(BCurveErr->_msg, "SCurveSeg failed");
        PBErrCatch(BCurveErr);
    BCurveFree(&seg);
  VecFree(&v):
  SCurveFree(&curve);
 printf("UnitTestSCurveGetAddRemoveSeg OK\n");
void UnitTestSCurveGet() {
  int order = 3;
  int dim = 2;
  int nbSeg = 3;
  SCurve* curve = SCurveCreate(order, dim, nbSeg);
  for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
    for (int iDim = dim; iDim--;)
      VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
  for (float u = 0.0; u < SCurveGetMaxU(curve) + PBMATH_EPSILON;</pre>
    u += 0.1) {
    VecFloat* v = SCurveGet(curve, u);
    if (ISEQUALF(VecGet(v, 0), u * 6.0) == false ||
      ISEQUALF(VecGet(v, 1), 1.0 + u * 6.0) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveGet failed");
      PBErrCatch(BCurveErr);
    VecFree(&v);
  SCurveFree(&curve);
 printf("UnitTestSCurveGet OK\n");
void UnitTestSCurveGetOrderDimNbSegMaxUNbCtrl() {
  int order = 3;
  int dim = 2;
  int nbSeg = 3;
  SCurve* curve = SCurveCreate(order, dim, nbSeg);
  for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
```

```
for (int iDim = dim; iDim--;)
      VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
 if (SCurveGetOrder(curve) != order) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetOrder failed");
   PBErrCatch(BCurveErr);
 if (SCurveGetDim(curve) != dim) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetDim failed");
   PBErrCatch(BCurveErr);
 if (SCurveGetNbSeg(curve) != nbSeg) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetNbSeg failed");
   PBErrCatch(BCurveErr);
  if (ISEQUALF(SCurveGetMaxU(curve), (float)(curve->_nbSeg)) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetMaxU failed");
   PBErrCatch(BCurveErr);
  if (SCurveGetNbCtrl(curve) != nbSeg * order + 1) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetNbCtrl failed");
    PBErrCatch(BCurveErr);
 SCurveFree(&curve);
 printf("UnitTestSCurveGetOrderDimNbSegMaxUNbCtrl OK\n");
void UnitTestSCurveGetApproxLenCenter() {
 int order = 3;
  int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
    for (int iDim = dim; iDim--;)
      VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
 VecFloat* center = SCurveGetCenter(curve);
  VecFloat* check = VecFloatCreate(dim);
  VecSet(check, 0, 9.0);
 VecSet(check, 1, 10.0);
  if (VecIsEqual(center, check) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetCenter failed");
   PBErrCatch(BCurveErr);
  VecFree(&check);
 VecFree(&center):
  float len = 25.455843;
  if (ISEQUALF(SCurveGetApproxLen(curve), len) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveGetApproxLen failed");
   PBErrCatch(BCurveErr);
 SCurveFree(&curve);
 printf("UnitTestSCurveGetApproxLenCenter OK\n");
```

```
void UnitTestSCurveRot() {
   int order = 3;
    int dim = 2;
   int nbSeg = 3;
   SCurve* curve = SCurveCreate(order, dim, nbSeg);
    for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
       for (int iDim = dim; iDim--;)
           VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
    float theta = PBMATH_HALFPI;
    SCurveRotStart(curve, theta);
    -10.0, 11.0, -12.0, 13.0, -14.0, 15.0, -16.0, 17.0, -18.0, 19.0};
    for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
       if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
           pa[iCtrl * 2]) == false ||
           ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
           pa[iCtrl * 2 + 1]) == false) {
           BCurveErr->_type = PBErrTypeUnitTestFailed;
           sprintf(BCurveErr->_msg, "SCurveRotStart failed");
           PBErrCatch(BCurveErr);
   SCurveRotOrigin(curve, theta);
   float pb[20] = {-1.0, 0.0, -3.0, -2.0, -5.0, -4.0, -7.0, -6.0, -9.0,
            -8.0, -11.0, -10.0, -13.0, -12.0, -15.0, -14.0, -17.0, -16.0,
           -19.0, -18.0};
   for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
       if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
           pb[iCtrl * 2]) == false ||
            ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
           pb[iCtrl * 2 + 1]) == false) {
           BCurveErr->_type = PBErrTypeUnitTestFailed;
           sprintf(BCurveErr->_msg, "SCurveRotOrigin failed");
           PBErrCatch(BCurveErr);
   }
   SCurveRotCenter(curve, theta);
    float pc[20] = \{-19.0, 0.0, -17.0, -2.0, -15.0, -4.0, -13.0, -6.0, -4.0, -13.0, -6.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -13.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.0, -6.
           -11.0, -8.0, -9.0, -10.0, -7.0, -12.0, -5.0, -14.0, -3.0, -16.0,
            -1.0, -18.0};
    for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
       if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
           pc[iCtrl * 2]) == false ||
           ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
           pc[iCtrl * 2 + 1]) == false) {
           BCurveErr->_type = PBErrTypeUnitTestFailed;
           sprintf(BCurveErr->_msg, "SCurveRotCenter failed");
           PBErrCatch(BCurveErr);
       }
   SCurveFree(&curve);
   printf("UnitTestSCurveRot OK\n");
void UnitTestSCurveScale() {
   int order = 3;
   int dim = 2;
    int nbSeg = 3;
   SCurve* curve = SCurveCreate(order, dim, nbSeg);
   for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
       for (int iDim = dim; iDim--;)
```

```
VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
}
float scale = 2.0;
SCurveScaleStart(curve, scale);
float pa[20] = {0.0, 1.0, 4.0, 5.0, 8.0, 9.0, 12.0, 13.0, 16.0, 17.0,
  20.0, 21.0, 24.0, 25.0, 28.0, 29.0, 32.0, 33.0, 36.0, 37.0};
for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
  if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
   pa[iCtrl * 2]) == false ||
    ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
   pa[iCtrl * 2 + 1]) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveScaleStart failed");
   PBErrCatch(BCurveErr);
 }
SCurveScaleOrigin(curve, scale);
float pb[20] = {0.0, 2.0, 8.0, 10.0, 16.0, 18.0, 24.0, 26.0, 32.0,
    34.0, 40.0, 42.0, 48.0, 50.0, 56.0, 58.0, 64.0, 66.0, 72.0, 74.0};
for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
  if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
   pb[iCtrl * 2]) == false ||
    ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
   pb[iCtrl * 2 + 1]) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveScaleOrigin failed");
   PBErrCatch(BCurveErr);
 }
SCurveScaleCenter(curve, scale);
float pc[20] = \{-36.0, -34.0, -20.0, -18.0, -4.0, -2.0, 12.0, 14.0, 
    28.0, 30.0, 44.0, 46.0, 60.0, 62.0, 76.0, 78.0, 92.0, 94.0,
    108.0, 110.0};
for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
  if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
   pc[iCtrl * 2]) == false ||
    ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
   pc[iCtrl * 2 + 1]) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveScaleCenter failed");
   PBErrCatch(BCurveErr);
 }
SCurveFree(&curve):
curve = SCurveCreate(order, dim, nbSeg);
for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
 for (int iDim = dim; iDim--;)
    VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
VecFloat* v = VecFloatCreate(dim);
VecSet(v, 0, 2.0);
VecSet(v. 1. -1.0):
SCurveScaleStart(curve, v);
float pd[20] = {0.0, 1.0, 4.0, -1.0, 8.0, -3.0, 12.0, -5.0, 16.0,
   -7.0, 20.0, -9.0, 24.0, -11.0, 28.0, -13.0, 32.0, -15.0, 36.0,
    -17.0};
for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
  if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
   pd[iCtrl * 2]) == false ||
    ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
    pd[iCtrl * 2 + 1]) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
```

```
sprintf(BCurveErr->_msg, "SCurveScaleStart failed");
     PBErrCatch(BCurveErr);
 SCurveScaleOrigin(curve, v);
  float pe[20] = \{0.0, -1.0, 8.0, 1.0, 16.0, 3.0, 24.0, 5.0, 32.0,
     7.0, 40.0, 9.0, 48.0, 11.0, 56.0, 13.0, 64.0, 15.0, 72.0, 17.0};
  for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
     pe[iCtrl * 2]) == false ||
      ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
     pe[iCtrl * 2 + 1]) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "SCurveScaleOrigin failed");
     PBErrCatch(BCurveErr);
 SCurveScaleCenter(curve, v);
  float pf[20] = {-36.0, 17.0, -20.0, 15.0, -4.0, 13.0, 12.0, 11.0,
     28.0, 9.0, 44.0, 7.0, 60.0, 5.0, 76.0, 3.0, 92.0, 1.0, 108.0,
      -1.0}:
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
    if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
     pf[iCtrl * 2]) == false ||
      ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
      pf[iCtrl * 2 + 1]) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveScaleCenter failed");
     PBErrCatch(BCurveErr);
   }
 }
 SCurveFree(&curve);
 VecFree(&v);
 printf("UnitTestSCurveScale OK\n");
void UnitTestSCurveTranslate() {
 int order = 3;
 int dim = 2;
  int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   for (int iDim = dim; iDim--;)
     VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
  VecFloat* v = VecFloatCreate(dim);
 VecSet(v, 0, -1.0);
  VecSet(v, 1, 2.0);
  SCurveTranslate(curve, v);
  float p[20] = \{-1.0, 3.0, 1.0, 5.0, 3.0, 7.0, 5.0, 9.0, 7.0, 11.0,
    9.0, 13.0, 11.0, 15.0, 13.0, 17.0, 15.0, 19.0, 17.0, 21.0};
  for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
    if (ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 0),
     p[iCtrl * 2]) == false ||
      ISEQUALF(VecGet(SCurveCtrl(curve, iCtrl), 1),
     p[iCtrl * 2 + 1]) == false) {
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "SCurveTranslate failed");
     PBErrCatch(BCurveErr);
 SCurveFree(&curve);
```

```
VecFree(&v);
 printf("UnitTestSCurveTranslate\ OK\n");\\
void UnitTestSCurveGetBoundingBox() {
 int order = 3;
 int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   VecSet(SCurveCtrl(curve, iCtrl), 0,
      cos(PBMATH_QUARTERPI * (float)iCtrl * 0.5));
   VecSet(SCurveCtrl(curve, iCtrl), 1,
     sin(PBMATH_QUARTERPI * (float)iCtrl * 0.5));
 Facoid* bound = SCurveGetBoundingBox(curve);
 if (ISEQUALF(VecGet(ShapoidPos(bound), 0), -1.0) == false ||
   ISEQUALF(VecGet(ShapoidPos(bound), 1), -0.382683) == false ||
   ISEQUALF(VecGet(ShapoidAxis(bound, 0), 0), 2.0) == false ||
   ISEQUALF(VecGet(ShapoidAxis(bound, 0), 1), 0.0) == false ||
   ISEQUALF(VecGet(ShapoidAxis(bound, 1), 0), 0.0) == false ||
   ISEQUALF(VecGet(ShapoidAxis(bound, 1), 1), 1.382683) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveGetBoundingBox failed");
   PBErrCatch(BCurveErr);
 ShapoidFree(&bound);
 SCurveFree(&curve):
 printf("UnitTestSCurveGetBoundingBox OK\n");
void UnitTestSCurveGetNewDim() {
 int order = 3;
 int dim = 3;
 int nbSeg = 2;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   VecSet(SCurveCtrl(curve, iCtrl), 0, (float)iCtrl);
   VecSet(SCurveCtrl(curve, iCtrl), 1, (float)iCtrl + 1);
   VecSet(SCurveCtrl(curve, iCtrl), 2, (float)iCtrl + 2);
 SCurve* curveA = SCurveGetNewDim(curve, 2);
 if (SCurveGetDim(curveA) != 2 ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 0), 0), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 0), 1), 1.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 1), 0), 1.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 1), 1), 2.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 2), 0), 2.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 2), 1), 3.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 3), 0), 3.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 3), 1), 4.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 4), 0), 4.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 4), 1), 5.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 5), 0), 5.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 5), 1), 6.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 6), 0), 6.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveA, 6), 1), 7.0) == false | |
   BCurveCtrl(SCurveSeg(curveA, 0), 0) != SCurveCtrl(curveA, 0) ||
   BCurveCtrl(SCurveSeg(curveA, 0), 1) != SCurveCtrl(curveA, 1) ||
   BCurveCtrl(SCurveSeg(curveA, 0), 2) != SCurveCtrl(curveA, 2) ||
   BCurveCtrl(SCurveSeg(curveA, 0), 3) != SCurveCtrl(curveA, 3) ||
   BCurveCtrl(SCurveSeg(curveA, 1), 0) != SCurveCtrl(curveA, 3) ||
```

```
BCurveCtrl(SCurveSeg(curveA, 1), 1) != SCurveCtrl(curveA, 4) ||
   BCurveCtrl(SCurveSeg(curveA, 1), 2) != SCurveCtrl(curveA, 5) ||
   BCurveCtrl(SCurveSeg(curveA, 1), 3) != SCurveCtrl(curveA, 6)) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveGetNewDim failed");
   PBErrCatch(BCurveErr);
 SCurve* curveB = SCurveGetNewDim(curve, 4);
 if (SCurveGetDim(curveB) != 4 ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 0), 0), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 0), 1), 1.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 0), 2), 2.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 0), 3), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 1), 0), 1.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 1), 1), 2.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 1), 2), 3.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 1), 3), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 2), 0), 2.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 2), 1), 3.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 2), 2), 4.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 2), 3), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 3), 0), 3.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 3), 1), 4.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 3), 2), 5.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 3), 3), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 4), 0), 4.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 4), 1), 5.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 4), 2), 6.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 4), 3), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 5), 0), 5.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 5), 1), 6.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 5), 2), 7.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 5), 3), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 6), 0), 6.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 6), 1), 7.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 6), 2), 8.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curveB, 6), 3), 0.0) == false ||
   BCurveCtrl(SCurveSeg(curveB, 0), 0) != SCurveCtrl(curveB, 0) ||
   BCurveCtrl(SCurveSeg(curveB, 0), 1) != SCurveCtrl(curveB, 1) ||
   BCurveCtrl(SCurveSeg(curveB, 0), 2) != SCurveCtrl(curveB, 2) ||
   BCurveCtrl(SCurveSeg(curveB, 0), 3) != SCurveCtrl(curveB, 3) ||
   BCurveCtrl(SCurveSeg(curveB, 1), 0) != SCurveCtrl(curveB, 3) ||
   BCurveCtrl(SCurveSeg(curveB, 1), 1) != SCurveCtrl(curveB, 4) ||
   BCurveCtrl(SCurveSeg(curveB, 1), 2) != SCurveCtrl(curveB, 5) ||
   BCurveCtrl(SCurveSeg(curveB, 1), 3) != SCurveCtrl(curveB, 6)) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveGetNewDim failed");
   PBErrCatch(BCurveErr);
 SCurveFree(&curve);
 SCurveFree(&curveA):
 SCurveFree(&curveB):
 printf("UnitTestSCurveGetNewDim OK\n");
void UnitTestSCurveCreateFromShapoid() {
 Facoid* facoid = FacoidCreate(2);
 Pyramidoid* pyramidoid = PyramidoidCreate(2);
 Spheroid* spheroid = SpheroidCreate(2);
 VecFloat2D v = VecFloatCreateStatic2D();
 VecSet(&v, 0, 1.0); VecSet(&v, 1, 2.0);
 ShapoidSetPos(facoid, &v);
```

```
ShapoidSetPos(pyramidoid, &v);
ShapoidSetPos(spheroid, &v);
VecSet(&v, 0, 3.0); VecSet(&v, 1, 4.0);
ShapoidSetAxis(facoid, 0, &v);
ShapoidSetAxis(pyramidoid, 0, &v);
ShapoidSetAxis(spheroid, 0, &v);
VecSet(&v, 0, -5.0); VecSet(&v, 1, 6.0);
ShapoidSetAxis(facoid, 1, &v);
ShapoidSetAxis(pyramidoid, 1, &v);
ShapoidSetAxis(spheroid, 1, &v);
SCurve* curve = SCurveCreateFromShapoid((Shapoid*)facoid);
if (curve == NULL || SCurveGetDim(curve) != 2 ||
  SCurveGetOrder(curve) != 1 || SCurveGetNbSeg(curve) != 4) {
  BCurveErr->_type = PBErrTypeUnitTestFailed;
  sprintf(BCurveErr->_msg, "SCurveCreateFromFacoid failed");
  PBErrCatch(BCurveErr);
if (ISEQUALF(VecGet(SCurveCtrl(curve, 0), 0), 1.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 0), 1), 2.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 1), 0), 4.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 1), 1), 6.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 2), 0), -1.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 2), 1), 12.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 3), 0), -4.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 3), 1), 8.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 4), 0), 1.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 4), 1), 2.0) == false) {
  BCurveErr->_type = PBErrTypeUnitTestFailed;
  sprintf(BCurveErr->_msg, "SCurveCreateFromFacoid failed");
  PBErrCatch(BCurveErr);
SCurveFree(&curve);
curve = SCurveCreateFromShapoid((Shapoid*)pyramidoid);
if (curve == NULL || SCurveGetDim(curve) != 2 ||
  SCurveGetOrder(curve) != 1 || SCurveGetNbSeg(curve) != 3) {
  BCurveErr->_type = PBErrTypeUnitTestFailed;
  sprintf(BCurveErr->_msg, "SCurveCreateFromPyramidoid failed");
  PBErrCatch(BCurveErr);
if (ISEQUALF(VecGet(SCurveCtrl(curve, 0), 0), 1.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 0), 1), 2.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 1), 0), 4.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 1), 1), 6.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 2), 0), -4.0) == false ||
ISEQUALF(VecGet(SCurveCtrl(curve, 2), 1), 8.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 3), 0), 1.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 3), 1), 2.0) == false) {
  BCurveErr->_type = PBErrTypeUnitTestFailed;
  sprintf(BCurveErr->_msg, "SCurveCreateFromPyramidoid failed");
  PBErrCatch(BCurveErr);
SCurveFree(&curve):
curve = SCurveCreateFromShapoid((Shapoid*)spheroid);
if (curve == NULL || SCurveGetDim(curve) != 2 ||
  SCurveGetOrder(curve) != 3 || SCurveGetNbSeg(curve) != 4) {
  BCurveErr->_type = PBErrTypeUnitTestFailed;
  sprintf(BCurveErr->_msg, "SCurveCreateFromSpheroid failed");
  PBErrCatch(BCurveErr);
if (ISEQUALF(VecGet(SCurveCtrl(curve, 0), 0), 2.5) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 0), 1), 4.0) == false ||
  ISEQUALF(VecGet(SCurveCtrl(curve, 1), 0), 1.119290) == false ||
```

```
ISEQUALF(VecGet(SCurveCtrl(curve, 1), 1), 5.656852) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 2), 0), -0.671574) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 2), 1), 6.104568) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 3), 0), -1.5) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 3), 1), 5.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 4), 0), -2.328426) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 4), 1), 3.895432) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 5), 0), -1.880710) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 5), 1), 1.656852) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 6), 0), -0.5) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 6), 1), 0.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 7), 0), 0.880710) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 7), 1), -1.656852) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 8), 0), 2.671574) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 8), 1), -2.104568) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 9), 0), 3.5) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 9), 1), -1.0) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 10), 0), 4.328426) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 10), 1), 0.104568) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 11), 0), 3.880710) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 11), 1), 2.343148) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 12), 0), 2.5) == false ||
   ISEQUALF(VecGet(SCurveCtrl(curve, 12), 1), 4.0) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveCreateFromSpheroid failed");
   PBErrCatch(BCurveErr);
 SCurveFree(&curve):
 ShapoidFree(&facoid);
 ShapoidFree(&pyramidoid);
 ShapoidFree(&spheroid);
 printf("UnitTestSCurveCreateFromShapoid OK\n");
void UnitTestSCurveGetDistToCurve() {
 int order = 1:
 int dim = 2:
 int nbSeg = 1;
 SCurve* curveA = SCurveCreate(order, dim, nbSeg);
 SCurve* curveB = SCurveCreate(order, dim, nbSeg);
 VecSet(SCurveCtrl(curveA, 0), 0, 0.0);
 VecSet(SCurveCtrl(curveA, 0), 1, 0.0);
 VecSet(SCurveCtrl(curveA, 1), 0, 1.0);
 VecSet(SCurveCtrl(curveA, 1), 1, 0.0);
 VecSet(SCurveCtrl(curveB, 0), 0, 0.0);
 VecSet(SCurveCtrl(curveB, 0), 1, 2.0);
 VecSet(SCurveCtrl(curveB, 1), 0, 1.0);
 VecSet(SCurveCtrl(curveB, 1), 1, 2.0);
 float dist = SCurveGetDistToCurve(curveA, curveB);
 if (ISEQUALF(dist, 2.0) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveGetDistToCurve failed");
   PBErrCatch(BCurveErr);
 SCurveFree(&curveA);
 SCurveFree(&curveB);
 printf("UnitTestSCurveGetDDistToCurve OK\n");
void UnitTestSCurve() {
 UnitTestSCurveCreateCloneFree();
 UnitTestSCurveLoadSavePrint();
```

```
UnitTestSCurveGetSetCtrl();
 UnitTestSCurveGetAddRemoveSeg();
 UnitTestSCurveGet();
 UnitTestSCurveGetOrderDimNbSegMaxUNbCtrl();
 UnitTestSCurveGetApproxLenCenter();
 UnitTestSCurveRot();
 UnitTestSCurveScale();
 UnitTestSCurveTranslate();
 UnitTestSCurveGetBoundingBox();
 UnitTestSCurveGetNewDim();
 UnitTestSCurveCreateFromShapoid();
 UnitTestSCurveGetDistToCurve();
 printf("UnitTestSCurve OK\n");
void UnitTestSCurveIterCreate() {
 int order = 3;
 int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   for (int iDim = dim; iDim--;)
     VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
 float delta = 0.2;
 SCurveIter iter = SCurveIterCreateStatic(curve, delta);
 if (iter._curve != curve || ISEQUALF(iter._curPos, 0.0) == false ||
   ISEQUALF(iter._delta, delta) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterCreateStatic failed");
   PBErrCatch(BCurveErr);
 SCurveFree(&curve);
 printf("UnitTestSCurveIterCreate OK\n");
void UnitTestSCurveIterSetGet() {
 int order = 3;
 int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   for (int iDim = dim; iDim--;)
     VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
 float delta = 0.2;
 SCurveIter iter = SCurveIterCreateStatic(curve, delta);
 SCurve* curveB = SCurveCreate(order, dim, nbSeg);
 SCurveIterSetCurve(&iter, curveB);
 if (iter._curve != curveB) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterSetCurve failed");
   PBErrCatch(BCurveErr);
 if (SCurveIterCurve(&iter) != curveB) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterCurve failed");
   PBErrCatch(BCurveErr);
 float deltaB = 0.3;
 SCurveIterSetDelta(&iter, deltaB);
 if (iter._delta != deltaB) {
```

```
BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterSetDelta failed");
   PBErrCatch(BCurveErr);
 if (SCurveIterGetDelta(&iter) != deltaB) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterGetDelta failed");
   PBErrCatch(BCurveErr);
 SCurveIterSetCurve(&iter, curve);
 iter._curPos = 0.5;
 if (SCurveIterGetPos(&iter) != 0.5) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterGetPos failed");
   PBErrCatch(BCurveErr);
 VecFloat* pos = SCurveIterGet(&iter);
 if (ISEQUALF(VecGet(pos, 0), 3.0) == false ||
   ISEQUALF(VecGet(pos, 1), 4.0) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterGet failed");
   PBErrCatch(BCurveErr);
 VecFree(&pos);
 SCurveFree(&curve);
 SCurveFree(&curveB);
 printf("UnitTestSCurveIterSetGet OK\n");
void UnitTestSCurveIterStep() {
 int order = 3;
 int dim = 2;
 int nbSeg = 3;
 SCurve* curve = SCurveCreate(order, dim, nbSeg);
 for (int iCtrl = SCurveGetNbCtrl(curve); iCtrl--;) {
   for (int iDim = dim; iDim--;)
     VecSet(SCurveCtrl(curve, iCtrl), iDim, iCtrl * dim + iDim);
 float delta = 3.0;
 SCurveIter iter = SCurveIterCreateStatic(curve, delta);
 bool ret = SCurveIterStep(&iter);
 if (ISEQUALF(SCurveIterGetPos(&iter), 3.0) == false ||
   ret == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterStep failed");
   PBErrCatch(BCurveErr);
 ret = SCurveIterStep(&iter);
 if (ISEQUALF(SCurveIterGetPos(&iter), 3.0) == false ||
   ret == true) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterStep failed");
   PBErrCatch(BCurveErr);
 ret = SCurveIterStepP(&iter);
 if (ISEQUALF(SCurveIterGetPos(&iter), 0.0) == false ||
   ret == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "SCurveIterStepP failed");
   PBErrCatch(BCurveErr);
 ret = SCurveIterStepP(&iter);
```

```
if (ISEQUALF(SCurveIterGetPos(&iter), 0.0) == false ||
    ret == true) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "SCurveIterStepP failed");
   PBErrCatch(BCurveErr);
 SCurveFree(&curve);
 printf("UnitTestSCurveStep OK\n");
void UnitTestSCurveIter() {
 UnitTestSCurveIterCreate();
 UnitTestSCurveIterSetGet();
 UnitTestSCurveIterStep();
 printf("UnitTestSCurveIter OK\n");
void UnitTestBBodyCreateFree() {
 int order = 1;
  VecShort2D dim = VecShortCreateStatic2D();
  VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
  if (VecGet(\&(surf->_dim), 0) != VecGet(\&dim, 0) ||
    VecGet(&(surf->_dim), 1) != VecGet(&dim, 1) ||
    surf->_order != order) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyCreate failed");
   PBErrCatch(BCurveErr);
 BBodyFree(&surf);
 printf("UnitTestBBodyCreateFree OK\n");
void UnitTestBBodyGetSet() {
 int order = 1;
  VecShort2D dim = VecShortCreateStatic2D();
  VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
  if (BBodyGetOrder(surf) != 1) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyGetOrder failed");
    PBErrCatch(BCurveErr);
  if (VecIsEqual(BBodyDim(surf), &dim) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyDim failed");
   PBErrCatch(BCurveErr);
 VecShort2D dimB = VecShortCreateStatic2D();
  dimB = BBodyGetDim(surf);
  if (VecIsEqual(&dimB, &dim) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyGetDim failed");
   PBErrCatch(BCurveErr);
  if (BBodyGetNbCtrl(surf) != 4) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyGetNbCtrl failed");
   PBErrCatch(BCurveErr);
  VecShort2D iCtrl = VecShortCreateStatic2D();
```

```
VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
  if (BBodyGetIndexCtrl(surf, &iCtrl) != 2) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyGetIndexCtrl failed");
   PBErrCatch(BCurveErr);
 if (BBodyCtrl(surf, &iCtrl) != surf->_ctrl[2]) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyCtrl failed");
   PBErrCatch(BCurveErr);
  VecFloat3D v = VecFloatCreateStatic3D();
  VecSet(&v, 0, 1.0); VecSet(&v, 1, 2.0); VecSet(&v, 2, 3.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  if (VecIsEqual(BBodyCtrl(surf, &iCtrl), (VecFloat*)&v) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodySetCtrl failed");
   PBErrCatch(BCurveErr);
 BBodyFree(&surf);
 printf("UnitTestBBodyGetSet OK\n");
void UnitTestBBodyGet() {
 int order = 1;
  VecShort2D dim = VecShortCreateStatic2D();
  VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
  BBody* surf = BBodyCreate(order, &dim);
  VecShort2D iCtrl = VecShortCreateStatic2D();
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
  VecFloat3D v = VecFloatCreateStatic3D();
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
  VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecFloat2D u = VecFloatCreateStatic2D();
  float du = 0.2;
  int iCheck = 0;
  float check[75] = {
    0.0,0.0,0.0,0.0,0.2,0.0,0.0,0.4,0.0,0.0,0.6,0.0,0.0,0.8,0.0,
    0.2, 0.0, 0.0, 0.16, 0.16, 0.04, 0.12, 0.32, 0.08, 0.08, 0.48, 0.12, 0.04,\\
    0.64, 0.16, 0.4, 0.0, 0.0, 0.32, 0.12, 0.08, 0.24, 0.24, 0.16, 0.16, 0.36,
    0.24, 0.08, 0.48, 0.32, 0.6, 0.0, 0.0, 0.48, 0.08, 0.12, 0.36, 0.16, 0.24,
    0.24,0.24,0.36,0.12,0.32,0.48,0.8,0.0,0.0,0.64,0.04,0.16,0.48,
    0.08, 0.32, 0.32, 0.12, 0.48, 0.16, 0.16, 0.64
   };
  for (VecSet(&u, 0, 0.0); VecGet(&u, 0) < 1.0;
    VecSet(&u, 0, VecGet(&u, 0) + du)) {
    for (VecSet(\&u, 1, 0.0); VecGet(\&u, 1) < 1.0;
      VecSet(&u, 1, VecGet(&u, 1) + du)) {
     VecFloat* p = BBodyGet(surf, &u);
      if (ISEQUALF(p->_val[0], check[iCheck]) == false ||
        ISEQUALF(p->_val[1], check[iCheck + 1]) == false ||
        ISEQUALF(p->_val[2], check[iCheck + 2]) == false) {
        BCurveErr->_type = PBErrTypeUnitTestFailed;
```

```
sprintf(BCurveErr->_msg, "BBodyGet failed");
       PBErrCatch(BCurveErr);
     iCheck += 3:
     VecFree(&p);
 BBodyFree(&surf);
 printf("UnitTestBBodyGet OK\n");
void UnitTestBBodyClone() {
  int order = 1;
  VecShort2D dim = VecShortCreateStatic2D();
  VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
 VecShort2D iCtrl = VecShortCreateStatic2D();
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
  VecFloat3D v = VecFloatCreateStatic3D();
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
  VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  BBody* clone = BBodyClone(surf);
  if (BBodyGetOrder(clone) != BBodyGetOrder(surf)) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyClone failed");
   PBErrCatch(BCurveErr);
  if (VecIsEqual(BBodyDim(clone), BBodyDim(surf)) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyClone failed");
   PBErrCatch(BCurveErr);
 for (int iCtrl = BBodyGetNbCtrl(clone); iCtrl--;) {
    if (VecIsEqual(clone->_ctrl[iCtrl], surf->_ctrl[iCtrl]) == false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BBodyClone failed");
     PBErrCatch(BCurveErr);
   }
 BBodyFree(&surf);
 BBodyFree(&clone);
 printf("UnitTestBBodyClone OK\n");
void UnitTestBBodyPrint() {
 int order = 1;
  VecShort2D dim = VecShortCreateStatic2D();
  VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
  VecShort2D iCtrl = VecShortCreateStatic2D();
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
 VecFloat3D v = VecFloatCreateStatic3D();
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
```

```
BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
  VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
 BBodySetCtrl(surf, &iCtrl, &v);
  BBodyPrint(surf, stdout);
  printf("\n");
 BBodyFree(&surf);
 printf("UnitTestBBodyPrint OK\n");
void UnitTestBBodyLoadSave() {
 int order = 1;
  VecShort2D dim = VecShortCreateStatic2D();
 VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
  VecShort2D iCtrl = VecShortCreateStatic2D();
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
  VecFloat3D v = VecFloatCreateStatic3D();
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
  VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
  BBodySetCtrl(surf, &iCtrl, &v);
 FILE* file = fopen("./bbody.txt", "w");
  if (BBodySave(surf, file) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodySave failed");
   PBErrCatch(BCurveErr);
 fclose(file);
  BBody* clone = NULL;
  file = fopen("./bbody.txt", "r");
  if (BBodyLoad(&clone, file) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyLoad failed");
   PBErrCatch(BCurveErr);
 fclose(file);
  if (BBodyGetOrder(clone) != BBodyGetOrder(surf)) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyLoadSave failed");
   PBErrCatch(BCurveErr);
  if (VecIsEqual(BBodyDim(clone), BBodyDim(surf)) == false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyLoadSave failed");
    PBErrCatch(BCurveErr);
 for (int iCtrl = BBodyGetNbCtrl(clone); iCtrl--;) {
    if (VecIsEqual(clone->_ctrl[iCtrl], surf->_ctrl[iCtrl]) == false) {
```

```
BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BBodyLoadSave failed");
     PBErrCatch(BCurveErr);
   }
 BBodyFree(&surf);
 BBodyFree(&clone);
 printf("UnitTestBBodyLoadSave OK\n");
void UnitTestBBodyGetCenter() {
 int order = 1;
 VecShort2D dim = VecShortCreateStatic2D();
 VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
 VecShort2D iCtrl = VecShortCreateStatic2D();
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
 VecFloat3D v = VecFloatCreateStatic3D();
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
 VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecFloat* center = BBodyGetCenter(surf);
 VecSet(&v, 0, 0.25); VecSet(&v, 1, 0.25); VecSet(&v, 2, 0.25);
 if (VecIsEqual(center, (VecFloat*)&v) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyGetCenter failed");
   PBErrCatch(BCurveErr);
 BBodyFree(&surf);
 VecFree(&center);
 printf("UnitTestBBodyGetCenter OK\n");
void UnitTestBBodyTranslate() {
 int order = 1;
 VecShort2D dim = VecShortCreateStatic2D();
 VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
 VecShort2D iCtrl = VecShortCreateStatic2D();
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
 VecFloat3D v = VecFloatCreateStatic3D();
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
 VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&v, 0, 1.0); VecSet(&v, 1, 2.0); VecSet(&v, 2, 3.0);
 BBodyTranslate(surf, &v);
```

```
float check[12] = {
   1.0,2.0,3.0,
    1.0,3.0,3.0,
   2.0,2.0,3.0,
    1.0,2.0,4.0
   }:
  for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
    if (ISEQUALF(check[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
     false ||
     ISEQUALF(check[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
     false ||
     ISEQUALF(check[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BBodyTranslate failed");
     PBErrCatch(BCurveErr);
 BBodyFree(&surf);
 printf("UnitTestBBodyTranslate OK\n");
void UnitTestBBodyScale() {
 int order = 1;
  VecShort2D dim = VecShortCreateStatic2D();
 VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
  BBody* surf = BBodyCreate(order, &dim);
  VecShort2D iCtrl = VecShortCreateStatic2D();
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
  VecFloat3D v = VecFloatCreateStatic3D();
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
  VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
  VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
  BBodySetCtrl(surf, &iCtrl, &v);
  VecSet(&v, 0, 1.0); VecSet(&v, 1, 2.0); VecSet(&v, 2, 3.0);
  BBodyScaleCenter(surf, (VecFloat*)&v);
  float checka[12] = {
   0.0,-0.25,-0.5,
   0.0,1.75,-0.5,
   1.0,-0.25,-0.5,
   0.0,-0.25,2.5
   };
  for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
    if (ISEQUALF(checka[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
     false ||
      ISEQUALF(checka[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
      false ||
     ISEQUALF(checka[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
     false) {
     BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BBodyScaleCenter failed");
     PBErrCatch(BCurveErr);
  BBodyScaleOrigin(surf, (VecFloat*)&v);
```

```
float checkb[12] = {
   0.0,-0.5,-1.5,
   0.0,3.5,-1.5,
   1.0,-0.5,-1.5,
   0.0, -0.5, 7.5
   }:
 for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
   if (ISEQUALF(checkb[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
     false ||
     ISEQUALF(checkb[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
     false ||
     ISEQUALF(checkb[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "BBodyScale failed");
     PBErrCatch(BCurveErr);
 BBodyScaleStart(surf, (VecFloat*)&v);
 float checkc[12] = {
   0.0,-0.5,-1.5,
   0.0, 7.5, -1.5,
   1.0,-0.5,-1.5,
   0.0,-0.5,25.5
   };
 for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
   if (ISEQUALF(checkc[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
     false ||
     ISEQUALF(checkc[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
     false ||
     ISEQUALF(checkc[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
     BCurveErr->_type = PBErrTypeUnitTestFailed;
     sprintf(BCurveErr->_msg, "BBodyScale failed");
     PBErrCatch(BCurveErr);
 BBodyFree(&surf);
 printf("UnitTestBBodyScale OK\n");
void UnitTestBBodyGetBoundingBox() {
 int order = 1;
 VecShort2D dim = VecShortCreateStatic2D();
 VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
 VecShort2D iCtrl = VecShortCreateStatic2D();
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
 VecFloat3D v = VecFloatCreateStatic3D();
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
 VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 BBodyScaleCenter(surf, (float)2.0);
 Facoid* bound = BBodyGetBoundingBox(surf);
```

```
VecSet(&v, 0, -0.25); VecSet(&v, 1, -0.25); VecSet(&v, 2, -0.25);
 if (VecIsEqual(ShapoidPos(bound), (VecFloat*)&v) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyGetBoundingBox failed");
   PBErrCatch(BCurveErr);
 VecSet(&v, 0, 2.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 if (VecIsEqual(ShapoidAxis(bound, 0), (VecFloat*)&v) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyGetBoundingBox failed");
   PBErrCatch(BCurveErr);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 2.0); VecSet(&v, 2, 0.0);
 if (VecIsEqual(ShapoidAxis(bound, 1), (VecFloat*)&v) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyGetBoundingBox failed");
   PBErrCatch(BCurveErr);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 2.0);
 if (VecIsEqual(ShapoidAxis(bound, 2), (VecFloat*)&v) == false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyGetBoundingBox failed");
   PBErrCatch(BCurveErr);
 ShapoidFree(&bound);
 BBodyFree(&surf);
 printf("UnitTestBBodyGetBoundingBox OK\n");
void UnitTestBBodyRotate() {
 int order = 1;
 VecShort2D dim = VecShortCreateStatic2D();
 VecSet(&dim, 0, 2); VecSet(&dim, 1, 3);
 BBody* surf = BBodyCreate(order, &dim);
 VecShort2D iCtrl = VecShortCreateStatic2D();
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 0);
 VecFloat3D v = VecFloatCreateStatic3D();
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 0);
 VecSet(&v, 0, 1.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 0); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 1.0); VecSet(&v, 2, 0.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 VecSet(&iCtrl, 0, 1); VecSet(&iCtrl, 1, 1);
 VecSet(&v, 0, 0.0); VecSet(&v, 1, 0.0); VecSet(&v, 2, 1.0);
 BBodySetCtrl(surf, &iCtrl, &v);
 float theta = PBMATH_HALFPI;
 BBodyRotXCenter(surf, theta);
 float checka[12] = {
   0.0,0.5,0.0,
   0.0,0.5,1.0,
   1.0,0.5,0.0,
   0.0, -0.5, 0.0
 for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
   if (ISEQUALF(checka[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
     ISEQUALF(checka[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
     false ||
     ISEQUALF(checka[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
```

```
BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyRotXCenter failed");
   PBErrCatch(BCurveErr);
BBodyRotXOrigin(surf, theta);
float checkb[12] = {
 0.0,0.0,0.5,
 0.0,-1.0,0.5,
 1.0,0.0,0.5,
 0.0,0.0,-0.5
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checkb[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   ISEQUALF(checkb[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   false ||
    ISEQUALF(checkb[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyRotXOrigin failed");
   PBErrCatch(BCurveErr);
BBodyRotXStart(surf, theta);
float checkc[12] = {
 0.0,0.0,0.5,
 0.0,0.0,-0.5,
 1.0,0.0,0.5,
 0.0,1.0,0.5
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checkc[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   ISEQUALF(checkc[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   false ||
    ISEQUALF(checkc[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyRotXStart failed");
   PBErrCatch(BCurveErr);
BBodyRotYCenter(surf, theta);
float checkd[12] = {
 0.5,0.0,0.5,
  -0.5,0.0,0.5,
 0.5,0.0,-0.5,
 0.5,1.0,0.5
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checkd[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   false ||
   ISEQUALF(checkd[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   false ||
   ISEQUALF(checkd[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyRotYCenter failed");
   PBErrCatch(BCurveErr);
```

```
BBodyRotYOrigin(surf, theta);
float checke[12] = {
 0.5,0.0,-0.5,
  0.5,0.0,0.5,
  -0.5,0.0,-0.5,
 0.5,1.0,-0.5
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checke[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   ISEQUALF(checke[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   false ||
    ISEQUALF(checke[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyRotYOrigin failed");
   PBErrCatch(BCurveErr);
BBodyRotYStart(surf, theta);
float checkf[12] = {
 0.5,0.0,-0.5,
  1.5,0.0,-0.5,
 0.5,0.0,0.5,
 0.5,1.0,-0.5
 };
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checkf[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   false ||
   ISEQUALF(checkf[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   false ||
   ISEQUALF(checkf[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyRotYStart failed");
   PBErrCatch(BCurveErr);
BBodyRotZCenter(surf, theta);
float checkg[12] = {
 1.0,0.0,-0.5,
  1.0,1.0,-0.5,
 1.0,0.0,0.5,
 0.0,0.0,-0.5
 };
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checkg[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   false ||
    ISEQUALF(checkg[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   ISEQUALF(checkg[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
   sprintf(BCurveErr->_msg, "BBodyRotZCenter failed");
   PBErrCatch(BCurveErr);
BBodyRotZOrigin(surf, theta);
float checkh[12] = {
 0.0,1.0,-0.5,
  -1.0,1.0,-0.5,
```

```
0.0,1.0,0.5,
 0.0,0.0,-0.5
 };
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checkh[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   false ||
   ISEQUALF(checkh[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   ISEQUALF(checkh[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   false) {
    BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyRotZOrigin failed");
   PBErrCatch(BCurveErr);
BBodyRotZStart(surf, theta);
float checki[12] = {
 0.0,1.0,-0.5,
  0.0,0.0,-0.5,
 0.0,1.0,0.5,
 1.0,1.0,-0.5
 }:
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checki[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   false ||
   ISEQUALF(checki[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
    false ||
    ISEQUALF(checki[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   false) {
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyRotZStart failed");
   PBErrCatch(BCurveErr);
VecFloat3D axis = VecFloatCreateStatic3D();
VecSet(&axis, 0, 1.0); VecSet(&axis, 1, 1.0); VecSet(&axis, 2, 1.0);
VecNormalise(&axis);
BBodyRotAxisCenter(surf, &axis, theta);
float checkj[12] = {
  -0.122009,0.666667,-0.044658,
  0.122008,0.333334,-0.955342,
 0.788675,0.422650,0.288675,
  0.211325,1.577350,-0.288675
 }:
for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
  if (ISEQUALF(checkj[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
   false ||
    ISEQUALF(checkj[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
   false ||
   ISEQUALF(checkj[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
   BCurveErr->_type = PBErrTypeUnitTestFailed;
    sprintf(BCurveErr->_msg, "BBodyRotAxisCenter failed");
   PBErrCatch(BCurveErr);
 }
BBodyRotAxisOrigin(surf, &axis, theta);
float checkk[12] = {
  -0.244017,0.122008,0.622008,
  -0.910684,0.455342,-0.044658,
 0.422650,0.788675,0.288675,
  -0.577350,0.788675,1.288675
```

```
};
  for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
    if (ISEQUALF(checkk[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
      false ||
      ISEQUALF(checkk[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
      false ||
      ISEQUALF(checkk[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BBodyRotAxisOrigin failed");
      PBErrCatch(BCurveErr);
  BBodyRotAxisStart(surf, &axis, theta);
  float checkl[12] = {
    -0.244017,0.122008,0.622008,
    -1.154700,-0.211325,0.866026,
    -0.488034,1.032692,0.955342,
    0.089317,-0.122008,1.532692
    };
  for (int iCtrl = BBodyGetNbCtrl(surf); iCtrl--;) {
    if (ISEQUALF(checkl[3 * iCtrl], surf->_ctrl[iCtrl]->_val[0]) ==
      false ||
      ISEQUALF(checkl[3 * iCtrl + 1], surf->_ctrl[iCtrl]->_val[1]) ==
      false ||
      ISEQUALF(checkl[3 * iCtrl + 2], surf->_ctrl[iCtrl]->_val[2]) ==
      BCurveErr->_type = PBErrTypeUnitTestFailed;
      sprintf(BCurveErr->_msg, "BBodyRotAxisStart failed");
      PBErrCatch(BCurveErr);
   }
  BBodyFree(&surf);
 printf("UnitTestBBodyRotate OK\n");
void UnitTestBBody() {
  UnitTestBBodyCreateFree();
  UnitTestBBodyGetSet();
  UnitTestBBodyGet();
  UnitTestBBodyClone();
  UnitTestBBodyPrint();
  UnitTestBBodyLoadSave();
  UnitTestBBodyGetCenter();
  UnitTestBBodyTranslate();
  UnitTestBBodyScale();
  UnitTestBBodyGetBoundingBox();
  UnitTestBBodyRotate();
 printf("UnitTestBBody OK\n");
void UnitTestAll() {
  UnitTestBCurve();
  UnitTestSCurve();
  UnitTestSCurveIter();
  UnitTestBBody();
 printf("UnitTestAll OK\n");
int main() {
  UnitTestAll();
  // Return success code
```

```
return 0;
```

## 6 Unit tests output

```
UnitTestBCurveCreateCloneFree OK
order(3) dim(2) <0.000,1.000> <2.000,3.000> <4.000,5.000> <6.000,7.000>
UnitTestBCurveLoadSavePrint OK
UnitTestBCurveGetSetCtrl OK
UnitTestBCurveGet OK
UnitTestBCurveGetOrderDim OK
UnitTestBCurveGetApproxLenCenter OK
UnitTestBCurveRot OK
UnitTestBCurveScale OK
UnitTestBCurveTranslate OK
UnitTestBCurveFromCloudPoint OK
UnitTestBCurveGetWeightCtrlPt OK
UnitTestBCurveGetBoundingBox OK
UnitTestBCurve OK
UnitTestSCurveCreateCloneFree OK
order(3) dim(2) nbSeg(3) <<0.000000,1.000000>> <2.000000,3.000000> <4.000000,5.000000> <<6.000000,7.000000>> <8.00000
{\tt UnitTestSCurveLoadSavePrint\ OK}
UnitTestSCurveGetSetCtrl OK
{\tt UnitTestSCurveGetAddRemoveSeg\ OK}
UnitTestSCurveGet OK
UnitTestSCurveGetOrderDimNbSegMaxUNbCtrl OK
{\tt UnitTestSCurveGetApproxLenCenter\ OK}
UnitTestSCurveRot OK
UnitTestSCurveScale OK
{\tt UnitTestSCurveTranslate\ OK}
UnitTestSCurveGetBoundingBox OK
{\tt UnitTestSCurveGetNewDim\ OK}
{\tt UnitTestSCurveCreateFromShapoid\ OK}
UnitTestSCurveGetDDistToCurve OK
UnitTestSCurve OK
UnitTestSCurveIterCreate OK
UnitTestSCurveIterSetGet OK
UnitTestSCurveStep OK
UnitTestSCurveIter OK
{\tt UnitTestBBodyCreateFree\ OK}
{\tt UnitTestBBodyGetSet\ OK}
UnitTestBBodyGet OK
UnitTestBBodyClone OK
order(1) dim(<2,3>) <0.000,0.000,0.000> <0.000,1.000,0.000><1.000,0.000,0.000,0.000><0.000,1.000>
UnitTestBBodyPrint OK
{\tt UnitTestBBodyLoadSave\ OK}
UnitTestBBodyGetCenter OK
{\tt UnitTestBBodyTranslate\ OK}
UnitTestBBodyScale OK
UnitTestBBodyGetBoundingBox OK
UnitTestBBodyRotate OK
UnitTestBBody OK
UnitTestAll OK
```

bcurve.txt:

```
3 2
2 0.000000 1.000000
2 2.000000 3.000000
2 4.000000 5.000000
2 6.000000 7.000000
```

#### scurve.txt:

```
3 2 3
2 0.000000 1.000000
2 2.000000 3.000000
2 4.000000 5.000000
2 6.000000 7.000000
2 8.000000 9.000000
2 10.000000 11.000000
2 12.000000 13.000000
2 14.000000 15.000000
2 16.000000 17.000000
2 18.000000 19.000000
```

#### bbody.txt:

```
1
2 2 3
3 0.000000 0.000000 0.000000
3 0.000000 1.000000 0.000000
3 1.000000 0.000000 0.000000
3 0.000000 0.000000 1.000000
```