### **NAME**

ssh\_config — OpenSSH SSH client configuration files

#### DESCRIPTION

ssh(1) obtains configuration data from the following sources in the following order:

- 1. command-line options
- 2. user's configuration file (~/.ssh/config)
- 3. system-wide configuration file (/etc/ssh/ssh\_config)

For each parameter, the first obtained value will be used. The configuration files contain sections separated by **Host** specifications, and that section is only applied for hosts that match one of the patterns given in the specification. The matched host name is usually the one given on the command line (see the **CanonicalizeHostname** option for exceptions).

Since the first obtained value for each parameter is used, more host-specific declarations should be given near the beginning of the file, and general defaults at the end.

Note that the Debian **openssh-client** package sets several options as standard in /etc/ssh/ssh\_config which are not the default in ssh(1):

- SendEnv LANG LC\_\*
- HashKnownHosts yes
- GSSAPIAuthentication yes

The file contains keyword-argument pairs, one per line. Lines starting with '#' and empty lines are interpreted as comments. Arguments may optionally be enclosed in double quotes (") in order to represent arguments containing spaces. Configuration options may be separated by whitespace or optional whitespace and exactly one '='; the latter format is useful to avoid the need to quote whitespace when specifying configuration options using the **ssh**, **scp**, and **sftp** -o option.

The possible keywords and their meanings are as follows (note that keywords are case-insensitive and arguments are case-sensitive):

**Host** Restricts the following declarations (up to the next **Host** or **Match** keyword) to be only for those hosts that match one of the patterns given after the keyword. If more than one pattern is provided, they should be separated by whitespace. A single '\*' as a pattern can be used to provide global defaults for all hosts. The host is usually the *hostname* argument given on the command line (see the **CanonicalizeHostname** keyword for exceptions).

A pattern entry may be negated by prefixing it with an exclamation mark ('!'). If a negated entry is matched, then the **Host** entry is ignored, regardless of whether any other patterns on the line match. Negated matches are therefore useful to provide exceptions for wildcard matches.

See **PATTERNS** for more information on patterns.

Match Restricts the following declarations (up to the next Host or Match keyword) to be used only when the conditions following the Match keyword are satisfied. Match conditions are specified using one or more criteria or the single token all which always matches. The available criteria keywords are: canonical, final, exec, host, originalhost, user, and localuser. The all criteria must appear alone or immediately after canonical or final. Other criteria may be combined arbitrarily. All criteria but all, canonical, and final require an argument. Criteria may be negated by prepending an exclamation mark ('!').

The **canonical** keyword matches only when the configuration file is being re-parsed after host-name canonicalization (see the **CanonicalizeHostname** option). This may be useful to specify conditions that work with canonical host names only.

The **final** keyword requests that the configuration be re-parsed (regardless of whether **CanonicalizeHostname** is enabled), and matches only during this final pass. If **CanonicalizeHostname** is enabled, then **canonical** and **final** match during the same pass.

The **exec** keyword executes the specified command under the user's shell. If the command returns a zero exit status then the condition is considered true. Commands containing whitespace characters must be quoted. Arguments to **exec** accept the tokens described in the **TOKENS** section.

The other keywords' criteria must be single entries or comma-separated lists and may use the wild-card and negation operators described in the **PATTERNS** section. The criteria for the **host** keyword are matched against the target hostname, after any substitution by the **Hostname** or **CanonicalizeHostname** options. The **originalhost** keyword matches against the hostname as it was specified on the command-line. The **user** keyword matches against the target username on the remote host. The **localuser** keyword matches against the name of the local user running ssh(1) (this keyword may be useful in system-wide **ssh\_config** files).

## AddKeysToAgent

Specifies whether keys should be automatically added to a running ssh-agent(1). If this option is set to **yes** and a key is loaded from a file, the key and its passphrase are added to the agent with the default lifetime, as if by ssh-add(1). If this option is set to **ask**, ssh(1) will require confirmation using the SSH\_ASKPASS program before adding a key (see ssh-add(1) for details). If this option is set to **confirm**, each use of the key must be confirmed, as if the **-c** option was specified to ssh-add(1). If this option is set to **no**, no keys are added to the agent. The argument must be **yes**, **confirm**, **ask**, or **no** (the default).

### AddressFamily

Specifies which address family to use when connecting. Valid arguments are **any** (the default), **inet** (use IPv4 only), or **inet6** (use IPv6 only).

### BatchMode

If set to **yes**, passphrase/password querying will be disabled. In addition, the **ServerAliveInterval** option will be set to 300 seconds by default (Debian-specific). This option is useful in scripts and other batch jobs where no user is present to supply the password, and where it is desirable to detect a broken network swiftly. The argument must be **yes** or **no** (the default).

#### BindAddress

Use the specified address on the local machine as the source address of the connection. Only useful on systems with more than one address.

#### BindInterface

Use the address of the specified interface on the local machine as the source address of the connection

# CanonicalDomains

When **CanonicalizeHostname** is enabled, this option specifies the list of domain suffixes in which to search for the specified destination host.

### CanonicalizeFallbackLocal

Specifies whether to fail with an error when hostname canonicalization fails. The default, **yes**, will attempt to look up the unqualified hostname using the system resolver's search rules. A value of **no** will cause ssh(1) to fail instantly if **CanonicalizeHostname** is enabled and the target hostname cannot be found in any of the domains specified by **CanonicalDomains**.

#### CanonicalizeHostname

Controls whether explicit hostname canonicalization is performed. The default, **no**, is not to perform any name rewriting and let the system resolver handle all hostname lookups. If set to **yes** then, for connections that do not use a **ProxyCommand** or **ProxyJump**, ssh(1) will attempt to canonicalize the hostname specified on the command line using the **CanonicalDomains** suffixes and **CanonicalizePermittedCNAMEs** rules. If **CanonicalizeHostname** is set to **always**, then canonicalization is applied to proxied connections too.

If this option is enabled, then the configuration files are processed again using the new target name to pick up any new configuration in matching **Host** and **Match** stanzas.

## CanonicalizeMaxDots

Specifies the maximum number of dot characters in a hostname before canonicalization is disabled. The default, 1, allows a single dot (i.e. hostname.subdomain).

#### CanonicalizePermittedCNAMEs

Specifies rules to determine whether CNAMEs should be followed when canonicalizing hostnames. The rules consist of one or more arguments of <code>source\_domain\_list:target\_domain\_list</code>, where <code>source\_domain\_list</code> is a pattern-list of domains that may follow CNAMEs in canonicalization, and <code>target\_domain\_list</code> is a pattern-list of domains that they may resolve to.

For example, "\*.a.example.com:\*.b.example.com,\*.c.example.com" will allow hostnames matching "\*.a.example.com" to be canonicalized to names in the "\*.b.example.com" or "\*.c.example.com" domains.

#### CASignatureAlgorithms

Specifies which algorithms are allowed for signing of certificates by certificate authorities (CAs). The default is:

```
ecdsa-sha2-nistp256.ecdsa-sha2-nistp384,ecdsa-sha2-nistp521, ssh-ed25519,rsa-sha2-512,rsa-sha2-256,ssh-rsa
```

ssh(1) will not accept host certificates signed using algorithms other than those specified.

## CertificateFile

Specifies a file from which the user's certificate is read. A corresponding private key must be provided separately in order to use this certificate either from an **IdentityFile** directive or **-i** flag to ssh(1), via ssh-agent(1), or via a **PKCS11Provider**.

Arguments to **CertificateFile** may use the tilde syntax to refer to a user's home directory or the tokens described in the **TOKENS** section.

It is possible to have multiple certificate files specified in configuration files; these certificates will be tried in sequence. Multiple **CertificateFile** directives will add to the list of certificates used for authentication.

### ${\tt ChallengeResponseAuthentication}$

Specifies whether to use challenge-response authentication. The argument to this keyword must be **yes** (the default) or **no**.

#### CheckHostIP

If set to **yes** (the default), ssh(1) will additionally check the host IP address in the known\_hosts file. This allows it to detect if a host key changed due to DNS spoofing and will add addresses of destination hosts to ~/.ssh/known\_hosts in the process, regardless of the setting of **StrictHostKeyChecking**. If the option is set to **no**, the check will not be executed.

#### Ciphers

Specifies the ciphers allowed and their order of preference. Multiple ciphers must be comma-separated. If the specified value begins with a '+' character, then the specified ciphers will be appended to the default set instead of replacing them. If the specified value begins with a '-' character, then the specified ciphers (including wildcards) will be removed from the default set instead of replacing them.

The supported ciphers are:

```
3des-cbc
aes128-cbc
aes192-cbc
aes256-cbc
aes128-ctr
aes192-ctr
aes256-ctr
aes128-gcm@openssh.com
aes256-gcm@openssh.com
chacha20-poly1305@openssh.com
```

#### The default is:

```
chacha20-poly1305@openssh.com,
aes128-ctr,aes192-ctr,aes256-ctr,
aes128-gcm@openssh.com,aes256-gcm@openssh.com
```

The list of available ciphers may also be obtained using "ssh -Q cipher".

#### ClearAllForwardings

Specifies that all local, remote, and dynamic port forwardings specified in the configuration files or on the command line be cleared. This option is primarily useful when used from the ssh(1) command line to clear port forwardings set in configuration files, and is automatically set by scp(1) and sftp(1). The argument must be **yes** or **no** (the default).

# Compression

Specifies whether to use compression. The argument must be **yes** or **no** (the default).

# ConnectionAttempts

Specifies the number of tries (one per second) to make before exiting. The argument must be an integer. This may be useful in scripts if the connection sometimes fails. The default is 1.

#### ConnectTimeout

Specifies the timeout (in seconds) used when connecting to the SSH server, instead of using the default system TCP timeout. This value is used only when the target is down or really unreachable, not when it refuses the connection.

#### ControlMaster

Enables the sharing of multiple sessions over a single network connection. When set to **yes**, ssh(1) will listen for connections on a control socket specified using the **ControlPath** argument. Additional sessions can connect to this socket using the same **ControlPath** with **ControlMaster** set to **no** (the default). These sessions will try to reuse the master instance's network connection rather than initiating new ones, but will fall back to connecting normally if the control socket does not exist, or is not listening.

Setting this to **ask** will cause ssh(1) to listen for control connections, but require confirmation using ssh-askpass(1). If the **ControlPath** cannot be opened, ssh(1) will continue without connecting to a master instance.

X11 and ssh-agent(1) forwarding is supported over these multiplexed connections, however the display and agent forwarded will be the one belonging to the master connection i.e. it is not possible to forward multiple displays or agents.

Two additional options allow for opportunistic multiplexing: try to use a master connection but fall back to creating a new one if one does not already exist. These options are: **auto** and **autoask**. The latter requires confirmation like the **ask** option.

#### ControlPath

Specify the path to the control socket used for connection sharing as described in the **ControlMaster** section above or the string **none** to disable connection sharing. Arguments to **ControlPath** may use the tilde syntax to refer to a user's home directory or the tokens described in the **TOKENS** section. It is recommended that any **ControlPath** used for opportunistic connection sharing include at least %h, %p, and %r (or alternatively %C) and be placed in a directory that is not writable by other users. This ensures that shared connections are uniquely identified.

#### ControlPersist

When used in conjunction with **ControlMaster**, specifies that the master connection should remain open in the background (waiting for future client connections) after the initial client connection has been closed. If set to **no**, then the master connection will not be placed into the background, and will close as soon as the initial client connection is closed. If set to **yes** or 0, then the master connection will remain in the background indefinitely (until killed or closed via a mechanism such as the "ssh-O exit"). If set to a time in seconds, or a time in any of the formats documented in sshd\_config(5), then the backgrounded master connection will automatically terminate after it has remained idle (with no client connections) for the specified time.

### DynamicForward

Specifies that a TCP port on the local machine be forwarded over the secure channel, and the application protocol is then used to determine where to connect to from the remote machine.

The argument must be [bind\_address:]port. IPv6 addresses can be specified by enclosing addresses in square brackets. By default, the local port is bound in accordance with the **GatewayPorts** setting. However, an explicit bind\_address may be used to bind the connection to a specific address. The bind\_address of **localhost** indicates that the listening port be bound for local use only, while an empty address or '\*' indicates that the port should be available from all interfaces.

Currently the SOCKS4 and SOCKS5 protocols are supported, and ssh(1) will act as a SOCKS server. Multiple forwardings may be specified, and additional forwardings can be given on the command line. Only the superuser can forward privileged ports.

### EnableSSHKeysign

Setting this option to **yes** in the global client configuration file /etc/ssh/ssh\_config enables the use of the helper program ssh-keysign(8) during **HostbasedAuthentication**. The argument must be **yes** or **no** (the default). This option should be placed in the non-hostspecific section. See ssh-keysign(8) for more information.

#### EscapeChar

Sets the escape character (default: '~'). The escape character can also be set on the command line. The argument should be a single character, '^' followed by a letter, or **none** to disable the escape character entirely (making the connection transparent for binary data).

### ExitOnForwardFailure

Specifies whether ssh(1) should terminate the connection if it cannot set up all requested dynamic, tunnel, local, and remote port forwardings, (e.g. if either end is unable to bind and listen on a specified port). Note that **ExitOnForwardFailure** does not apply to connections made over port

forwardings and will not, for example, cause ssh(1) to exit if TCP connections to the ultimate forwarding destination fail. The argument must be **yes** or **no** (the default).

### FingerprintHash

Specifies the hash algorithm used when displaying key fingerprints. Valid options are: **md5** and **sha256** (the default).

#### ForwardAgent

Specifies whether the connection to the authentication agent (if any) will be forwarded to the remote machine. The argument must be **yes** or **no** (the default).

Agent forwarding should be enabled with caution. Users with the ability to bypass file permissions on the remote host (for the agent's Unix-domain socket) can access the local agent through the forwarded connection. An attacker cannot obtain key material from the agent, however they can perform operations on the keys that enable them to authenticate using the identities loaded into the agent.

# ForwardX11

Specifies whether X11 connections will be automatically redirected over the secure channel and DISPLAY set. The argument must be **yes** or **no** (the default).

X11 forwarding should be enabled with caution. Users with the ability to bypass file permissions on the remote host (for the user's X11 authorization database) can access the local X11 display through the forwarded connection. An attacker may then be able to perform activities such as keystroke monitoring if the **ForwardX11Trusted** option is also enabled.

### ForwardX11Timeout

Specify a timeout for untrusted X11 forwarding using the format described in the **TIME FORMATS** section of sshd\_config(5). X11 connections received by ssh(1) after this time will be refused. Setting **ForwardX11Timeout** to zero will disable the timeout and permit X11 forwarding for the life of the connection. The default is to disable untrusted X11 forwarding after twenty minutes has elapsed.

### ForwardX11Trusted

If this option is set to **yes**, (the Debian-specific default), remote X11 clients will have full access to the original X11 display.

If this option is set to **no** (the upstream default), remote X11 clients will be considered untrusted and prevented from stealing or tampering with data belonging to trusted X11 clients. Furthermore, the xauth(1) token used for the session will be set to expire after 20 minutes. Remote clients will be refused access after this time.

See the X11 SECURITY extension specification for full details on the restrictions imposed on untrusted clients.

### GatewayPorts

Specifies whether remote hosts are allowed to connect to local forwarded ports. By default, ssh(1) binds local port forwardings to the loopback address. This prevents other remote hosts from connecting to forwarded ports. **GatewayPorts** can be used to specify that ssh should bind local port forwardings to the wildcard address, thus allowing remote hosts to connect to forwarded ports. The argument must be **yes** or **no** (the default).

### GlobalKnownHostsFile

Specifies one or more files to use for the global host key database, separated by whitespace. The default is /etc/ssh/ssh\_known\_hosts, /etc/ssh/ssh\_known\_hosts2.

#### GSSAPIAuthentication

Specifies whether user authentication based on GSSAPI is allowed. The default is **no**.

#### GSSAPIClientIdentity

If set, specifies the GSSAPI client identity that ssh should use when connecting to the server. The default is unset, which means that the default identity will be used.

### GSSAPIDelegateCredentials

Forward (delegate) credentials to the server. The default is **no**.

### GSSAPIKeyExchange

Specifies whether key exchange based on GSSAPI may be used. When using GSSAPI key exchange the server need not have a host key. The default is "no".

### GSSAPIRenewalForcesRekey

If set to "yes" then renewal of the client's GSSAPI credentials will force the rekeying of the ssh connection. With a compatible server, this will delegate the renewed credentials to a session on the server.

Checks are made to ensure that credentials are only propagated when the new credentials match the old ones on the originating client and where the receiving server still has the old set in its cache.

The default is "no".

For this to work **GSSAPIKeyExchange** needs to be enabled in the server and also used by the client.

### GSSAPIServerIdentity

If set, specifies the GSSAPI server identity that ssh should expect when connecting to the server. The default is unset, which means that the expected GSSAPI server identity will be determined from the target hostname.

## GSSAPITrustDns

Set to "yes" to indicate that the DNS is trusted to securely canonicalize the name of the host being connected to. If "no", the hostname entered on the command line will be passed untouched to the GSSAPI library. The default is "no".

### GSSAPIKexAlgorithms

The list of key exchange algorithms that are offered for GSSAPI key exchange. Possible values are

```
gss-gex-shal-,
gss-groupl-shal-,
gss-group14-shal-,
gss-group14-sha256-,
gss-group16-sha512-,
gss-nistp256-sha256-,
gss-curve25519-sha256-
```

The default is "gss-gex-sha1-,gss-group14-sha1-". This option only applies to protocol version 2 connections using GSSAPI.

#### HashKnownHosts

Indicates that ssh(1) should hash host names and addresses when they are added to ~/.ssh/known\_hosts. These hashed names may be used normally by ssh(1) and sshd(8), but they do not reveal identifying information should the file's contents be disclosed. The default is no. Note that existing names and addresses in known hosts files will not be converted automatically, but may be manually hashed using ssh-keygen(1). Use of this option may break facilities such as tab-completion that rely on being able to read unhashed host names from

```
~/.ssh/known_hosts.
```

#### HostbasedAuthentication

Specifies whether to try rhosts based authentication with public key authentication. The argument must be **yes** or **no** (the default).

### HostbasedKeyTypes

Specifies the key types that will be used for hostbased authentication as a comma-separated list of patterns. Alternately if the specified value begins with a '+' character, then the specified key types will be appended to the default set instead of replacing them. If the specified value begins with a '-' character, then the specified key types (including wildcards) will be removed from the default set instead of replacing them. The default for this option is:

```
ecdsa-sha2-nistp256-cert-v01@openssh.com,
ecdsa-sha2-nistp384-cert-v01@openssh.com,
ecdsa-sha2-nistp521-cert-v01@openssh.com,
ssh-ed25519-cert-v01@openssh.com,
rsa-sha2-512-cert-v01@openssh.com,
rsa-sha2-512-cert-v01@openssh.com,
ecdsa-sha2-nistp256,ecdsa-sha2-nistp384,ecdsa-sha2-nistp521,
ssh-ed25519,rsa-sha2-512,rsa-sha2-256,ssh-rsa
```

The -Q option of ssh(1) may be used to list supported key types.

#### HostKeyAlgorithms

Specifies the host key algorithms that the client wants to use in order of preference. Alternately if the specified value begins with a '+' character, then the specified key types will be appended to the default set instead of replacing them. If the specified value begins with a '-' character, then the specified key types (including wildcards) will be removed from the default set instead of replacing them. The default for this option is:

```
ecdsa-sha2-nistp256-cert-v01@openssh.com,
ecdsa-sha2-nistp384-cert-v01@openssh.com,
ecdsa-sha2-nistp521-cert-v01@openssh.com,
ssh-ed25519-cert-v01@openssh.com,
rsa-sha2-512-cert-v01@openssh.com,
rsa-sha2-512-cert-v01@openssh.com,
ecdsa-sha2-nistp256,ecdsa-sha2-nistp384,ecdsa-sha2-nistp521,
ssh-ed25519,rsa-sha2-512,rsa-sha2-256,ssh-rsa
```

If hostkeys are known for the destination host then this default is modified to prefer their algorithms.

The list of available key types may also be obtained using "ssh -Q key".

### HostKeyAlias

Specifies an alias that should be used instead of the real host name when looking up or saving the host key in the host key database files and when validating host certificates. This option is useful for tunneling SSH connections or for multiple servers running on a single host.

### HostName

Specifies the real host name to log into. This can be used to specify nicknames or abbreviations for hosts. Arguments to **HostName** accept the tokens described in the **TOKENS** section. Numeric IP addresses are also permitted (both on the command line and in **HostName** specifications). The default is the name given on the command line.

#### **IdentitiesOnly**

Specifies that ssh(1) should only use the authentication identity and certificate files explicitly configured in the  $ssh\_config$  files or passed on the ssh(1) command-line, even if  $ssh\_agent(1)$  or a **PKCS11Provider** offers more identities. The argument to this keyword must be **yes** or **no** (the default). This option is intended for situations where ssh-agent offers many different identities.

### IdentityAgent

Specifies the UNIX-domain socket used to communicate with the authentication agent.

This option overrides the SSH\_AUTH\_SOCK environment variable and can be used to select a specific agent. Setting the socket name to **none** disables the use of an authentication agent. If the string "SSH\_AUTH\_SOCK" is specified, the location of the socket will be read from the SSH\_AUTH\_SOCK environment variable. Otherwise if the specified value begins with a '\$' character, then it will be treated as an environment variable containing the location of the socket.

Arguments to **IdentityAgent** may use the tilde syntax to refer to a user's home directory or the tokens described in the **TOKENS** section.

#### IdentityFile

Specifies a file from which the user's DSA, ECDSA, Ed25519 or RSA authentication identity is read. The default is ~/.ssh/id\_dsa, ~/.ssh/id\_ecdsa, ~/.ssh/id\_ed25519 and ~/.ssh/id\_rsa. Additionally, any identities represented by the authentication agent will be used for authentication unless **IdentitiesOnly** is set. If no certificates have been explicitly specified by **CertificateFile**, ssh(1) will try to load certificate information from the filename obtained by appending -cert.pub to the path of a specified **IdentityFile**.

Arguments to **IdentityFile** may use the tilde syntax to refer to a user's home directory or the tokens described in the **TOKENS** section.

It is possible to have multiple identity files specified in configuration files; all these identities will be tried in sequence. Multiple **IdentityFile** directives will add to the list of identities tried (this behaviour differs from that of other configuration directives).

**IdentityFile** may be used in conjunction with **IdentitiesOnly** to select which identities in an agent are offered during authentication. **IdentityFile** may also be used in conjunction with **CertificateFile** in order to provide any certificate also needed for authentication with the identity.

### IgnoreUnknown

Specifies a pattern-list of unknown options to be ignored if they are encountered in configuration parsing. This may be used to suppress errors if **ssh\_config** contains options that are unrecognised by ssh(1). It is recommended that **IgnoreUnknown** be listed early in the configuration file as it will not be applied to unknown options that appear before it.

#### Include

Include the specified configuration file(s). Multiple pathnames may be specified and each pathname may contain glob(7) wildcards and, for user configurations, shell-like "references to user home directories. Files without absolute paths are assumed to be in "/.ssh if included in a user configuration file or /etc/ssh if included from the system configuration file. **Include** directive may appear inside a **Match** or **Host** block to perform conditional inclusion.

IPQoS Specifies the IPv4 type-of-service or DSCP class for connections. Accepted values are af11, af12, af13, af21, af22, af23, af31, af32, af33, af41, af42, af43, cs0, cs1, cs2, cs3, cs4, cs5, cs6, cs7, ef, lowdelay, throughput, reliability, a numeric value, or none to use the operating system default. This option may take one or two arguments, separated by whitespace. If one argument is specified, it is used as the packet class unconditionally. If two values are specified, the first is automatically selected for interactive sessions and the second for non-

interactive sessions. The default is **lowdelay** for interactive sessions and **throughput** for non-interactive sessions.

#### KbdInteractiveAuthentication

Specifies whether to use keyboard-interactive authentication. The argument to this keyword must be **yes** (the default) or **no**.

#### KbdInteractiveDevices

Specifies the list of methods to use in keyboard-interactive authentication. Multiple method names must be comma-separated. The default is to use the server specified list. The methods available vary depending on what the server supports. For an OpenSSH server, it may be zero or more of: **bsdauth** and **pam**.

#### KexAlgorithms

Specifies the available KEX (Key Exchange) algorithms. Multiple algorithms must be comma-separated. Alternately if the specified value begins with a '+' character, then the specified methods will be appended to the default set instead of replacing them. If the specified value begins with a '-' character, then the specified methods (including wildcards) will be removed from the default set instead of replacing them. The default is:

```
curve25519-sha256, curve25519-sha256@libssh.org, ecdh-sha2-nistp256, ecdh-sha2-nistp384, ecdh-sha2-nistp521, diffie-hellman-group-exchange-sha256, diffie-hellman-group16-sha512, diffie-hellman-group18-sha512, diffie-hellman-group14-sha256, diffie-hellman-group14-sha1
```

The list of available key exchange algorithms may also be obtained using "ssh -Q kex".

#### LocalCommand

Specifies a command to execute on the local machine after successfully connecting to the server. The command string extends to the end of the line, and is executed with the user's shell. Arguments to **LocalCommand** accept the tokens described in the **TOKENS** section.

The command is run synchronously and does not have access to the session of the ssh(1) that spawned it. It should not be used for interactive commands.

This directive is ignored unless **PermitLocalCommand** has been enabled.

# LocalForward

Specifies that a TCP port on the local machine be forwarded over the secure channel to the specified host and port from the remote machine. The first argument must be [bind\_address:]port and the second argument must be host:hostport. IPv6 addresses can be specified by enclosing addresses in square brackets. Multiple forwardings may be specified, and additional forwardings can be given on the command line. Only the superuser can forward privileged ports. By default, the local port is bound in accordance with the GatewayPorts setting. However, an explicit bind\_address may be used to bind the connection to a specific address. The bind\_address of localhost indicates that the listening port be bound for local use only, while an empty address or '\* indicates that the port should be available from all interfaces.

#### LogLeve1

Gives the verbosity level that is used when logging messages from ssh(1). The possible values are: QUIET, FATAL, ERROR, INFO, VERBOSE, DEBUG, DEBUG1, DEBUG2, and DEBUG3. The default is INFO. DEBUG and DEBUG1 are equivalent. DEBUG2 and DEBUG3 each specify higher levels of verbose output.

MACs Specifies the MAC (message authentication code) algorithms in order of preference. The MAC algorithm is used for data integrity protection. Multiple algorithms must be comma-separated. If the specified value begins with a '+' character, then the specified algorithms will be appended to the default set instead of replacing them. If the specified value begins with a '-' character, then the specified algorithms (including wildcards) will be removed from the default set instead of replacing them.

The algorithms that contain "-etm" calculate the MAC after encryption (encrypt-then-mac). These are considered safer and their use recommended.

The default is:

```
umac-64-etm@openssh.com, umac-128-etm@openssh.com, hmac-sha2-256-etm@openssh.com, hmac-sha2-512-etm@openssh.com, hmac-sha1-etm@openssh.com, umac-64@openssh.com, umac-128@openssh.com, hmac-sha2-256, hmac-sha2-512, hmac-sha1
```

The list of available MAC algorithms may also be obtained using "ssh -Q mac".

#### NoHostAuthenticationForLocalhost

Disable host authentication for localhost (loopback addresses). The argument to this keyword must be **yes** or **no** (the default).

### NumberOfPasswordPrompts

Specifies the number of password prompts before giving up. The argument to this keyword must be an integer. The default is 3.

### PasswordAuthentication

Specifies whether to use password authentication. The argument to this keyword must be **yes** (the default) or **no**.

### PermitLocalCommand

Allow local command execution via the **LocalCommand** option or using the ! command escape sequence in ssh(1). The argument must be **yes** or **no** (the default).

# PKCS11Provider

Specifies which PKCS#11 provider to use or **none** to indicate that no provider should be used (the default). The argument to this keyword is a path to the PKCS#11 shared library ssh(1) should use to communicate with a PKCS#11 token providing keys for user authentication.

**Port** Specifies the port number to connect on the remote host. The default is 22.

### PreferredAuthentications

Specifies the order in which the client should try authentication methods. This allows a client to prefer one method (e.g. **keyboard-interactive**) over another method (e.g. **password**). The default is:

```
gssapi-with-mic, hostbased, publickey,
keyboard-interactive, password
```

#### ProxyCommand

Specifies the command to use to connect to the server. The command string extends to the end of the line, and is executed using the user's shell exec directive to avoid a lingering shell process.

Arguments to **ProxyCommand** accept the tokens described in the **TOKENS** section. The command can be basically anything, and should read from its standard input and write to its standard output. It should eventually connect an sshd(8) server running on some machine, or execute **sshd** -i somewhere. Host key management will be done using the HostName of the host being connected (defaulting to the name typed by the user). Setting the command to **none** disables this op-

tion entirely. Note that **CheckHostIP** is not available for connects with a proxy command.

This directive is useful in conjunction with nc(1) and its proxy support. For example, the following directive would connect via an HTTP proxy at 192.0.2.0:

```
ProxyCommand /usr/bin/nc -X connect -x 192.0.2.0:8080 %h %p
```

### ProxyJump

Specifies one or more jump proxies as either [user@]host[:port] or an ssh URI. Multiple proxies may be separated by comma characters and will be visited sequentially. Setting this option will cause ssh(1) to connect to the target host by first making a ssh(1) connection to the specified **ProxyJump** host and then establishing a TCP forwarding to the ultimate target from there.

Note that this option will compete with the **ProxyCommand** option - whichever is specified first will prevent later instances of the other from taking effect.

Note also that the configuration for the destination host (either supplied via the command-line or the configuration file) is not generally applied to jump hosts. ~/.ssh/config should be used if specific configuration is required for jump hosts.

### ProxyUseFdpass

Specifies that **ProxyCommand** will pass a connected file descriptor back to ssh(1) instead of continuing to execute and pass data. The default is **no**.

#### PubkeyAcceptedKeyTypes

Specifies the key types that will be used for public key authentication as a comma-separated list of patterns. Alternately if the specified value begins with a '+' character, then the key types after it will be appended to the default instead of replacing it. If the specified value begins with a '-' character, then the specified key types (including wildcards) will be removed from the default set instead of replacing them. The default for this option is:

```
ecdsa-sha2-nistp256-cert-v01@openssh.com,
ecdsa-sha2-nistp384-cert-v01@openssh.com,
ecdsa-sha2-nistp521-cert-v01@openssh.com,
ssh-ed25519-cert-v01@openssh.com,
rsa-sha2-512-cert-v01@openssh.com,
rsa-sha2-512-cert-v01@openssh.com,
ssh-rsa-cert-v01@openssh.com,
ecdsa-sha2-nistp256,ecdsa-sha2-nistp384,ecdsa-sha2-nistp521,
ssh-ed25519,rsa-sha2-512,rsa-sha2-256,ssh-rsa
```

The list of available key types may also be obtained using "ssh -Q key".

## PubkeyAuthentication

Specifies whether to try public key authentication. The argument to this keyword must be  $\mathbf{yes}$  (the default) or  $\mathbf{no}$ .

#### RekeyLimit

Specifies the maximum amount of data that may be transmitted before the session key is renegotiated, optionally followed a maximum amount of time that may pass before the session key is renegotiated. The first argument is specified in bytes and may have a suffix of 'K', 'M', or 'G' to indicate Kilobytes, Megabytes, or Gigabytes, respectively. The default is between '1G' and '4G', depending on the cipher. The optional second value is specified in seconds and may use any of the units documented in the TIME FORMATS section of <code>sshd\_config(5)</code>. The default value for <code>RekeyLimit</code> is <code>default none</code>, which means that rekeying is performed after the cipher's default amount of data has been sent or received and no time based rekeying is done.

#### RemoteCommand

Specifies a command to execute on the remote machine after successfully connecting to the server. The command string extends to the end of the line, and is executed with the user's shell. Arguments to **RemoteCommand** accept the tokens described in the **TOKENS** section.

#### RemoteForward

Specifies that a TCP port on the remote machine be forwarded over the secure channel. The remote port may either be forwarded to a specified host and port from the local machine, or may act as a SOCKS 4/5 proxy that allows a remote client to connect to arbitrary destinations from the local machine. The first argument must be [bind\_address:]port If forwarding to a specific destination then the second argument must be host:hostport, otherwise if no destination argument is specified then the remote forwarding will be established as a SOCKS proxy.

IPv6 addresses can be specified by enclosing addresses in square brackets. Multiple forwardings may be specified, and additional forwardings can be given on the command line. Privileged ports can be forwarded only when logging in as root on the remote machine.

If the port argument is 0, the listen port will be dynamically allocated on the server and reported to the client at run time.

If the bind\_address is not specified, the default is to only bind to loopback addresses. If the bind\_address is '\*' or an empty string, then the forwarding is requested to listen on all interfaces. Specifying a remote bind\_address will only succeed if the server's **GatewayPorts** option is enabled (see sshd\_config(5)).

#### RequestTTY

Specifies whether to request a pseudo-tty for the session. The argument may be one of: **no** (never request a TTY), **yes** (always request a TTY when standard input is a TTY), **force** (always request a TTY) or **auto** (request a TTY when opening a login session). This option mirrors the **-t** and **-T** flags for ssh(1).

### RevokedHostKeys

Specifies revoked host public keys. Keys listed in this file will be refused for host authentication. Note that if this file does not exist or is not readable, then host authentication will be refused for all hosts. Keys may be specified as a text file, listing one public key per line, or as an OpenSSH Key Revocation List (KRL) as generated by ssh-keygen(1). For more information on KRLs, see the KEY REVOCATION LISTS section in ssh-keygen(1).

#### SendEnv

Specifies what variables from the local environ(7) should be sent to the server. The server must also support it, and the server must be configured to accept these environment variables. Note that the TERM environment variable is always sent whenever a pseudo-terminal is requested as it is required by the protocol. Refer to **AcceptEnv** in sshd\_config(5) for how to configure the server. Variables are specified by name, which may contain wildcard characters. Multiple environment variables may be separated by whitespace or spread across multiple **SendEnv** directives.

See PATTERNS for more information on patterns.

It is possible to clear previously set **SendEnv** variable names by prefixing patterns with –. The default is not to send any environment variables.

#### ServerAliveCountMax

Sets the number of server alive messages (see below) which may be sent without ssh(1) receiving any messages back from the server. If this threshold is reached while server alive messages are being sent, ssh will disconnect from the server, terminating the session. It is important to note that the use of server alive messages is very different from **TCPKeepAlive** (below). The server alive messages are sent through the encrypted channel and therefore will not be spoofable. The TCP

keepalive option enabled by **TCPKeepAlive** is spoofable. The server alive mechanism is valuable when the client or server depend on knowing when a connection has become inactive.

The default value is 3. If, for example, **ServerAliveInterval** (see below) is set to 15 and **ServerAliveCountMax** is left at the default, if the server becomes unresponsive, ssh will disconnect after approximately 45 seconds.

#### ServerAliveInterval

Sets a timeout interval in seconds after which if no data has been received from the server, ssh(1) will send a message through the encrypted channel to request a response from the server. The default is 0, indicating that these messages will not be sent to the server, or 300 if the **BatchMode** option is set (Debian-specific). **ProtocolKeepAlives** and **SetupTimeOut** are Debian-specific compatibility aliases for this option.

#### SetEnv

Directly specify one or more environment variables and their contents to be sent to the server. Similarly to **SendEnv**, the server must be prepared to accept the environment variable.

#### StreamLocalBindMask

Sets the octal file creation mode mask (umask) used when creating a Unix-domain socket file for local or remote port forwarding. This option is only used for port forwarding to a Unix-domain socket file.

The default value is 0177, which creates a Unix-domain socket file that is readable and writable only by the owner. Note that not all operating systems honor the file mode on Unix-domain socket files.

### StreamLocalBindUnlink

Specifies whether to remove an existing Unix-domain socket file for local or remote port forwarding before creating a new one. If the socket file already exists and **StreamLocalBindUnlink** is not enabled, **ssh** will be unable to forward the port to the Unix-domain socket file. This option is only used for port forwarding to a Unix-domain socket file.

The argument must be **yes** or **no** (the default).

# StrictHostKeyChecking

If this flag is set to **yes**, ssh(1) will never automatically add host keys to the ~/.ssh/known\_hosts file, and refuses to connect to hosts whose host key has changed. This provides maximum protection against man-in-the-middle (MITM) attacks, though it can be annoying when the /etc/ssh/ssh\_known\_hosts file is poorly maintained or when connections to new hosts are frequently made. This option forces the user to manually add all new hosts.

If this flag is set to "accept-new" then ssh will automatically add new host keys to the user known hosts files, but will not permit connections to hosts with changed host keys. If this flag is set to "no" or "off", ssh will automatically add new host keys to the user known hosts files and allow connections to hosts with changed hostkeys to proceed, subject to some restrictions. If this flag is set to ask (the default), new host keys will be added to the user known host files only after the user has confirmed that is what they really want to do, and ssh will refuse to connect to hosts whose host key has changed. The host keys of known hosts will be verified automatically in all cases.

# SyslogFacility

Gives the facility code that is used when logging messages from ssh(1). The possible values are: DAEMON, USER, AUTH, LOCAL0, LOCAL1, LOCAL2, LOCAL3, LOCAL4, LOCAL5, LOCAL6, LOCAL7. The default is USER.

### **TCPKeepAlive**

Specifies whether the system should send TCP keepalive messages to the other side. If they are sent, death of the connection or crash of one of the machines will be properly noticed. This option

only uses TCP keepalives (as opposed to using ssh level keepalives), so takes a long time to notice when the connection dies. As such, you probably want the **ServerAliveInterval** option as well. However, this means that connections will die if the route is down temporarily, and some people find it annoying.

The default is **yes** (to send TCP keepalive messages), and the client will notice if the network goes down or the remote host dies. This is important in scripts, and many users want it too.

To disable TCP keepalive messages, the value should be set to **no**. See also **ServerAliveInterval** for protocol-level keepalives.

#### Tunnel

Request tun(4) device forwarding between the client and the server. The argument must be **yes**, **point-to-point** (layer 3), **ethernet** (layer 2), or **no** (the default). Specifying **yes** requests the default tunnel mode, which is **point-to-point**.

#### TunnelDevice

Specifies the tun(4) devices to open on the client (local\_tun) and the server (remote\_tun).

The argument must be <code>local\_tun[:remote\_tun]</code>. The devices may be specified by numerical ID or the keyword <code>any</code>, which uses the next available tunnel device. If <code>remote\_tun</code> is not specified, it defaults to <code>any</code>. The default is <code>any:any</code>.

### UpdateHostKeys

Specifies whether ssh(1) should accept notifications of additional hostkeys from the server sent after authentication has completed and add them to **UserKnownHostsFile**. The argument must be **yes**, **no** (the default) or **ask**. Enabling this option allows learning alternate hostkeys for a server and supports graceful key rotation by allowing a server to send replacement public keys before old ones are removed. Additional hostkeys are only accepted if the key used to authenticate the host was already trusted or explicitly accepted by the user. If **UpdateHostKeys** is set to **ask**, then the user is asked to confirm the modifications to the known\_hosts file. Confirmation is currently incompatible with **ControlPersist**, and will be disabled if it is enabled.

Presently, only sshd(8) from OpenSSH 6.8 and greater support the "hostkeys@openssh.com" protocol extension used to inform the client of all the server's hostkeys.

**User** Specifies the user to log in as. This can be useful when a different user name is used on different machines. This saves the trouble of having to remember to give the user name on the command line.

# UserKnownHostsFile

Specifies one or more files to use for the user host key database, separated by whitespace. The default is ~/.ssh/known\_hosts, ~/.ssh/known\_hosts2.

## VerifyHostKeyDNS

Specifies whether to verify the remote key using DNS and SSHFP resource records. If this option is set to **yes**, the client will implicitly trust keys that match a secure fingerprint from DNS. Insecure fingerprints will be handled as if this option was set to **ask**. If this option is set to **ask**, information on fingerprint match will be displayed, but the user will still need to confirm new host keys according to the **StrictHostKeyChecking** option. The default is **no**.

See also **VERIFYING HOST KEYS** in ssh(1).

### VisualHostKey

If this flag is set to **yes**, an ASCII art representation of the remote host key fingerprint is printed in addition to the fingerprint string at login and for unknown host keys. If this flag is set to **no** (the default), no fingerprint strings are printed at login and only the fingerprint string will be printed for unknown host keys.

#### XAuthLocation

Specifies the full pathname of the xauth(1) program. The default is /usr/bin/xauth.

#### **PATTERNS**

A pattern consists of zero or more non-whitespace characters, '\*' (a wildcard that matches zero or more characters), or '?' (a wildcard that matches exactly one character). For example, to specify a set of declarations for any host in the ".co.uk" set of domains, the following pattern could be used:

```
Host *.co.uk
```

The following pattern would match any host in the 192.168.0.[0-9] network range:

```
Host 192.168.0.?
```

A *pattern-list* is a comma-separated list of patterns. Patterns within pattern-lists may be negated by preceding them with an exclamation mark ('!'). For example, to allow a key to be used from anywhere within an organization except from the "dialup" pool, the following entry (in authorized\_keys) could be used:

```
from="!*.dialup.example.com, *.example.com"
```

Note that a negated match will never produce a positive result by itself. For example, attempting to match "host3" against the following pattern-list will fail:

```
from="!host1,!host2"
```

The solution here is to include a term that will yield a positive match, such as a wildcard:

```
from="!host1,!host2,*"
```

### **TOKENS**

Arguments to some keywords can make use of tokens, which are expanded at runtime:

- %% A literal '%'.
- %C Hash of %l%h%p%r.
- %d Local user's home directory.
- %h The remote hostname.
- %i The local user ID.
- %L The local hostname.
- %l The local hostname, including the domain name.
- %n The original remote hostname, as given on the command line.
- %p The remote port.
- %r The remote username.
- %T The local tun(4) or tap(4) network interface assigned if tunnel forwarding was requested, or "NONE" otherwise.
- %u The local username.

Match exec accepts the tokens %%, %h, %i, %L, %l, %n, %p, %r, and %u.

 $\textbf{CertificateFile} \ accepts \ the \ tokens \ \%\%, \ \%d, \ \%h, \ \%i, \ \%l, \ \%r, \ and \ \%u.$ 

ControlPath accepts the tokens %%, %C, %h, %i, %L, %l, %n, %p, %r, and %u.

**HostName** accepts the tokens %% and %h.

IdentityAgent and IdentityFile accept the tokens %%, %d, %h, %i, %l, %r, and %u.

 $\textbf{LocalCommand} \ accepts \ the \ tokens \ \%\%, \ \%C, \ \%d, \ \%h, \ \%i, \ \%l, \ \%n, \ \%p, \ \%r, \ \%T, \ and \ \%u.$ 

**ProxyCommand** accepts the tokens %%, %h, %p, and %r.

RemoteCommand accepts the tokens %%, %C, %d, %h, %i, %l, %n, %p, %r, and %u.

## **FILES**

# ~/.ssh/config

This is the per-user configuration file. The format of this file is described above. This file is used by the SSH client. Because of the potential for abuse, this file must have strict permissions: read/write for the user, and not writable by others. It may be group-writable provided that the group in question contains only the user.

```
/etc/ssh/ssh_config
```

Systemwide configuration file. This file provides defaults for those values that are not specified in the user's configuration file, and for those users who do not have a configuration file. This file must be world-readable.

### **SEE ALSO**

ssh(1)

### **AUTHORS**

OpenSSH is a derivative of the original and free ssh 1.2.12 release by Tatu Ylonen. Aaron Campbell, Bob Beck, Markus Friedl, Niels Provos, Theo de Raadt and Dug Song removed many bugs, re-added newer features and created OpenSSH. Markus Friedl contributed the support for SSH protocol versions 1.5 and 2.0.