### **NAME**

pthread\_getattr\_default\_np, pthread\_setattr\_default\_np, - get or set default thread-creation attributes

# **SYNOPSIS**

Compile and link with -pthread.

### DESCRIPTION

The **pthread\_setattr\_default\_np()** function sets the default attributes used for creation of a new thread—that is, the attributes that are used when **pthread\_create(3)** is called with a second argument that is NULL. The default attributes are set using the attributes supplied in \*attr, a previously initialized thread attributes object. Note the following details about the supplied attributes object:

- \* The attribute settings in the object must be valid.
- \* The stack address attribute must not be set in the object.
- \* Setting the *stack size* attribute to zero means leave the default stack size unchanged.

The **pthread\_getattr\_default\_np**() function initializes the thread attributes object referred to by *attr* so that it contains the default attributes used for thread creation.

### **ERRORS**

### **EINVAL**

(**pthread\_setattr\_default\_np**()) One of the attribute settings in *attr* is invalid, or the stack address attribute is set in *attr*.

### **ENOMEM**

```
(pthread_setattr_default_np()) Insufficient memory.
```

## **VERSIONS**

These functions are available in glibc since version 2.18.

# **ATTRIBUTES**

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
pthread_getattr_default_np(),	Thread safety	MT-Safe
pthread_setattr_default_np()		

### **CONFORMING TO**

These functions are nonstandard GNU extensions; hence the suffix "\_np" (nonportable) in their names.

### **EXAMPLE**

The program below uses **pthread\_getattr\_default\_np()** to fetch the default thread-creation attributes and then displays various settings from the returned thread attributes object. When running the program, we see the following output:

### \$ ./a.out

```
Stack size: 8388608
Guard size: 4096
Scheduling policy: SCHED_OTHER
Scheduling priority: 0
```

Detach state: JOINABLE Inherit scheduler: INHERIT

# Program source

```
#define _GNU_SOURCE
```

```
#include <pthread.h>
#include <stdio.h>
#include <stdlib.h>
#include <errno.h>
#define errExitEN(en, msg) \
                        do { errno = en; perror(msg); \
                             exit(EXIT_FAILURE); } while (0)
static void
display_pthread_attr(pthread_attr_t *attr)
    int s;
   size_t stacksize;
   size_t guardsize;
    int policy;
    struct sched_param schedparam;
    int detachstate;
    int inheritsched;
    s = pthread_attr_getstacksize(attr, &stacksize);
    if (s != 0)
        errExitEN(s, "pthread_attr_getstacksize");
                                 %zd\n", stacksize);
    printf("Stack size:
    s = pthread_attr_getquardsize(attr, &guardsize);
    if (s != 0)
        errExitEN(s, "pthread_attr_getguardsize");
    printf("Guard size:
                                %zd\n", quardsize);
    s = pthread_attr_getschedpolicy(attr, &policy);
   if (s != 0)
        errExitEN(s, "pthread_attr_getschedpolicy");
    printf("Scheduling policy: %s\n",
            (policy == SCHED_FIFO) ? "SCHED_FIFO" :
            (policy == SCHED_RR) ? "SCHED_RR" :
            (policy == SCHED_OTHER) ? "SCHED_OTHER" : "[unknown]");
    s = pthread_attr_getschedparam(attr, &schedparam);
    if (s != 0)
        errExitEN(s, "pthread_attr_getschedparam");
   printf("Scheduling priority: %d\n", schedparam.sched\_priority);\\
    s = pthread_attr_getdetachstate(attr, &detachstate);
    if (s != 0)
        errExitEN(s, "pthread_attr_getdetachstate");
    printf("Detach state:
                                %s\n",
            (detachstate == PTHREAD_CREATE_DETACHED) ? "DETACHED" :
            (detachstate == PTHREAD_CREATE_JOINABLE) ? "JOINABLE" :
            "???");
    s = pthread_attr_getinheritsched(attr, &inheritsched);
    if (s != 0)
        errExitEN(s, "pthread_attr_getinheritsched");
```

# **SEE ALSO**

 $pthread\_attr\_getaffinity\_np(3), pthread\_attr\_getdetachstate(3), pthread\_attr\_getguardsize(3), pthread\_attr\_getsched(3), pthread\_attr\_getschedparam(3), pthread\_attr\_getschedpolicy(3), pthread\_attr\_getscope(3), pthread\_attr\_getstack(3), pthread\_attr\_getstackaddr(3), pthread\_attr\_getstacksize(3), pthread\_attr\_init(3), pthread\_create(3), pthreads(7)\\$ 

### **COLOPHON**

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2019-03-06 3