Chapter 9: Filesystems

Introduction

Till this point, we have seen how a kernel of an operating system works as a resource manager. Given that both the processor and the main memory are resources in the system, 539kernel manages these resources ¹ and provides them to the different processes in the system. Another role of a kernel is to provide a way to communicate with external devices, such as the keyboard and hard disk. Device drivers are the way of realizing this role of the kernel ². The details of the external devices and how to communicate with them are low-level and may be changed at any time. The goal of a device driver is to communicate with a given device by using the device's own language and the other goal of a device driver is to provide an interface for any other component of the system that wish to use the given device, most probably the low-level details of this given device will be hidden behind the interface that the device driver provides, that means the user of the device drivers doesn't need to know anything about how the device really work.

The matter of hiding the low-level details with something higher-level is too important and can be found in, basically, everywhere in computing and the kernels are not an exception of that. Of course, there is virtually no limit of providing higher-level concepts based a previous lower-level concept, also upon something that we consider as a high-level concept we can build something even higher-level. Beside the previous example of device drivers, one of obvious example where the kernels fulfill the role of hiding the low-level details and providing something higher-level, in other words, providing an *abstraction*, is a filesystem which provides the well-known abstraction, a file.

In this chapter we are going to cover these two topics, device drivers and filesystem by using 539kernel. As you may recall, it turned out that accessing to the hard disk is an important aspect for virtual memory, so, to be able to implement virtual memory, the kernel itself needs to access the hard disk which makes it an important component in the kernel, so, we are going to implement a device driver that communicate with the hard disk in this chapter. After getting the ability of reading from the hard disk or writing to it, we can explore the idea of providing abstractions by the kernel through writing a filesystem that uses the hard disk device driver and provides a higher-level view of the hard disk, that we all familiar with, instead of the physical view of the hard disk which has been described previously in chapter. The final result of this chapter is version NE of 539kernel which has as we mentioned a hard disk device driver and a filesystem.

 $^{^1{\}rm Incompletely}$ of course, to keep 539 kernel as simple as possible, only the basic parts of resources management were presented.

²At least a monolithic kernel.

ATA Device Driver

No need to say the hard disks are too common devices that are used as secondary storage devices. Also, there are a lot of manufacturers that manufacture hard disks and sell them. Imagine for a moment that each hard disk from a different manufacturer use its own way for the communication, that is, the method X should be used to be able to communicate with hard disks from manufacturer A while the method Y should be used with hard disks from manufacturer B. Given that there are too many manufacturers, this will be a nightmare. Each hard disk will need its own device driver which talks a different language from the other hard disk device drivers. Fortunately, this is not the case, at least for the hard disks, in this type of situations, standards are here to the rescue. A manufacturer may design the hard disk hardware in anyway, but when it comes to the part of the communication between the hard disk and the outside world, a standard can be used, so, any device driver that works with this given standard, will be able to communicate with this new hard disk. There are many well-known standards that are related to the hard disks, small computer system interface (SCSI) is one of them, another one is advanced technology attachment (ATA). While the latter one is more common in personal computers we are going to focus on it here and write a device driver for it, the former one is more common in servers.

As in PIC which is been discussed in chapter, ATA hard disks can be communicated with by using port-mapped I/O communication through the instructions in and out that we have covered previously. But before discussing the ATA commands that let us to issue a read or write request to the hard disk, let's write two routines in assembly that can be used in C code and perform the same functionality for the instructions in and out. If you didn't recall, the instruction out is used to write some bytes to a given port number, so, if we know the port number that a device receives that commands from, we can use the instruction out to write a valid command to that port, on the other hand, the instruction in reads data from a given port, for example, sometimes after we send a command to a device, it responds through writing something on a specific port, the instruction in can be used to read this value. The assembly code of the both routines that we are going to define next should reside in starter.asm anywhere between bits 32 and the beginning of start_kernel routine. As we have said previously, the goal of these two routines is to make it possible for C code to use the instructions in and out through calling these routines. The following is the code of dev write which can be used by C kernel code to write to a given port. In C, we can see that it has this prototype: dev write(int port, int cmd).

```
; Part 2
xor edx, edx
xor eax, eax

; Part 3
mov dx, [esp + 12]
mov al, [esp + 16]

; Part 4
out dx, al

; Part 5
pop eax
pop edx
ret
```

The core part of this routine is part four which contains the instruction out that send the value which is stored in al to the port number which is stored in dx. Because we are using these two registers ³, we push their previous values into the stack as we did in the first part of the routine, pushing the previous values of these registers lets us restore them easily after the routine finishes its work, this restoration is performed in the fifth part of the routine right before returning from the routine, this is an important step to make sure that when the routine returns, the environment of the caller is same as the one before calling the routine. After storing the previous values of eax and edx we can use them freely, so, the first step after that is to clear their previous values by setting the value 0 to the both of them, as you can see, we have used xor and the both operands of it are the same register that we wish to clear, this is a well-known way in assembly programming to clear the value of a register ⁴. After that, we can move the values that have been passed to the routine as parameters to the correct registers to be used with out instruction, this is performed in the third part of the routine ⁵. The following is the code of the routine dev read which uses the instruction in to read the data from a given port and return them to the caller, its prototype can be imagined as char dev_read(int port).

```
dev_read:
    push edx
    xor edx, edx
    xor eax, eax
```

³Which are as you know parts of the registers eax and edx respectively.

⁴To my best knowledge its more performant than the normal way of using mov.

⁵The readers who have previous knowledge in x86 assembly programming may notice that I've omitted the epilogue of routines which creates a new stack frame, this decision has been made to make the matters simpler and you are absolutely free to use the calling convention.

```
mov dx, [esp + 8]
in al, dx
pop edx
ret
```

For the same reason of restoring the previous environment when returning to the caller, the routine pushes the value of edx into the stack, then both of edx and eax are cleared since they will be used by the instruction in. After that, the value of the passed parameter which represents the port number that caller wishes to read from, is stored in dx. Finally, in is called, the result is stored in al, the previous value of edx is restored and the routine returns. You may ask, why did we only stored and restored the previous value of edx while the register eax is also used also, why didn't we store and restore the previous value of eax? The reason is that dev_read is a function that returns a value, and according to cdecl convention the returned values should be stored in the register in eax, so, the value of eax is intended to be changed when return to the caller, therefore, it will not be correct, logically, to restore the the previous value of eax when dev_read returns. The ultimate goal of defining both dev_write and dev_read is to make them available to be used in C code, so, the lines global dev_write and global dev_read should be written in the beginning of starter.asm.