indent.pl

Chris Hughes

March 31, 2013

Abstract

indent.pl is a Perl script that indents .tex files according to an indentation scheme that the user can modify to suit their taste. Environments, including those with alignment delimiters (such as tabular), commands, including those that can split braces and brackets across lines, are usually handled correctly by the script.

Contents

1	Bef	ore we begin	2
	1.1	Thanks	2
	1.2	No warranty	2
	1.3	Required Perl modules	2
2	Den	nonstration: before and after	3
3	Hov	v to use the script	3
	3.1	From the command line	3
	3.2	From arara	4
4	defa	ault, user, and local settings	4
	4.1	defaultSettings.yaml	4
	4.2	indentconfig.yaml (for user settings)	8
	4.3	localSettings.yaml	9
	4.4	Settings load order	9
5	Kno	own limitations	9
		nos	9
	Kno		2
		nos	
	istir	${f lgs}$ helloworld.plx	2
	$\inf_{rac{1}{2}}$	ngs helloworld.plx	2 4
	$\inf_{1\atop 2\atop 3}$	lgs helloworld.plx	2 4 5
	istir 1 2 3 4	ngs helloworld.plx arara samples lookForAlignDelims verbatimEnvironments	2 4 5 6
	istir 1 2 3 4 5	ngs helloworld.plx arara samples lookForAlignDelims verbatimEnvironments noIndentBlock	2 4 5 6 6
	istir 1 2 3 4 5 6	helloworld.plx	2 4 5 6 6 6
	istir 1 2 3 4 5 6 7	ngs helloworld.plx arara samples lookForAlignDelims verbatimEnvironments noIndentBlock noIndentBlock demonstration noAdditionalIndent	2 4 5 6 6 6 6
	istir 1 2 3 4 5 6 7 8	helloworld.plx arara samples lookForAlignDelims verbatimEnvironments noIndentBlock noIndentBlock demonstration noAdditionalIndent indentRules	2 4 5 6 6 6 6 7
	istir 1 2 3 4 5 6 7 8	helloworld.plx	2 4 5 6 6 6 6 7 7

13	mysettings.yaml $(ext{example})$	8
14	localSettings.yaml (example)	Ç

1 Before we begin

1.1 Thanks

I first created indent.pl for helping me to format chapter files in a big project. After I blogged about it on the TEX stack exchange [?] I received some positive feedback and follow-up feature requests. A big thank you to Harish Kumar who has really helped to drive the script forward and has put it through a number of challenging tests— I look forward to more challenges in the future Harish!



The yaml-based interface of indent.pl was inspired by the wonderful arara tool; any similarities are deliberate, and I hope that it is perceived as the compliment that it is. Thank you to Paulo Cereda and the team for releasing this awesome tool; I initially worried that I was going to have to make a GUI for indent.pl, but the release of arara has meant there is no need. Thank you to Paulo for all of your advice and encouragement.

1.2 No warranty

indent.pl has the option to overwrite your .tex files. It will always make at least one backup (you can choose how many it makes, see page 5) but you should still be careful when using it. The script has been tested on many files, but there are some known limitations (see Section 5). You, the user, are responsible for ensuring that you maintain backups of your files before running indent.pl on them. I think it is important at this stage to restate an important part of the license here:

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

There is certainly no malicious intent in releasing this script, and I do hope that it works as you expect it to—if it does not, please first of all make sure that you have the correct settings, and then feel free to let me know with a complete minimum working example as I would like to improve the code as much as possible.

Before you try the script on anything important (like your thesis), test it out on the sample files that come with it.

1.3 Required Perl modules

indent.pl requires a few standard modules—if you can run the following minimum code (perl helloworld.pl) then you will be able to run indent.pl, otherwise you may need to install the missing modules.

LISTING 1: helloworld.pl

```
1 #!/usr/bin/perl
2
3 use strict;
4 use warnings;
5 use FindBin;
6 use YAML::Tiny;
7 use File::Copy;
```

```
8 use File::Basename;
9 use Getopt::Std;
10 use POSIX qw/strftime/;
11 use File::HomeDir;
12
13 print "hello_world";
14 exit;
```

Note that my default installation on Ubuntu 12.04 did *not* come with all of these modules as standard.

2 Demonstration: before and after

3 How to use the script

There are two ways to use indent.pl: from the command line, and using arara. We will discuss how to change the settings and behaviour of the script in Section 4.

3.1 From the command line

indent.pl has a number of different switches/flags/options, which can be combined in any way that you like. indent.pl produces a .log file, indent.log every time it is run. There is a base of information that is written to indent.log, but other additional information will be written depending on which of the following options are used.

```
indent.pl myfile.tex
```

This will simply output to your terminal; myfile.tex will not be changed in any way using this command.

```
-w indent.pl -w myfile.tex
```

This will overwrite myfile.tex, but it will make a copy of myfile.tex first. You can control the name of the extension (default is .bak), and how many different back-ups are made—more on this in Section 4; see backupExtension and onlyOneBackUp.

Note that if indent.pl can not create the backup, then it will exit without touching your original file; an error message will be given asking you to check the permissions of the backup file.

```
-o indent.pl -o myfile.tex outputfile.tex
```

This will indent myfile.tex and output it to outputfile.tex, overwriting it (outputfiletex) if it already exists. Note that if indent.pl is called with both the -w and -o switches, then -w will be ignored and -o will take priority (this seems safer than the other way round).

Note that using -o is equivalent to using indent.pl myfile.tex > outputfile. \hookrightarrow tex

```
-s indent.pl -s myfile.tex
```

Silent mode: no output will be given to the terminal.

```
-t indent.pl -t myfile.tex
```

Tracing mode: verbose output will be given to indent.log. This is useful if indent.pl has made a mistake and you're trying to find out where and why.

-l indent.pl -l myfile.tex

Local settings: you might like to read Section 4 before using this switch. indent -- .pl will always load defaultSettings.yaml and if it is called with the -l switch and it finds localSettings.yaml in the same directory as myfile.tex then these settings will be added to the indentation scheme.

3.2 From arara

Using indent.pl from the command line is fine for some folks, but others may find it easier to use from arara. indent.pl ships with an arara rule, indent.yaml, which you can either copy it to the directory of your other arara rules, or otherwise add the indent.pl directory to your araraconfig.yaml file.

Once you have told arara where to find your indent rule, you can use it any of the following ways (or combinations thereof).

LISTING 2: arara samples

```
1  % arara: indent
2  % arara: indent: {overwrite: yes}
3  % arara: indent: {output: myfile.tex}
4  % arara: indent: {silent: yes}
5  % arara: indent: {trace: yes}
6  % arara: indent: {localSettings: yes}
7  \documentclass{article}
8  ...
```

Hopefully the use of these rules is fairly self-explanatory, but for completeness Table 1 shows the relationship between arran orb-tags and the switches given in Section 3.1.

Table 1: arara orb tags and corresponding switches

arara orb tags	switch
overwrite	-w
output	-0
silent	-s
trace	-t
localSettings	-1

4 default, user, and local settings

indent.pl loads its settings from defaultSettings.yaml (rhymes with camel). The idea is to separate the behaviour of the script from the internal working—this is very similar to the way that we separate content from form when writing our documents in LATEX.

4.1 defaultSettings.yaml

If you look in defaultSettings.yaml you'll find the switches that govern the behaviour of indent.pl. The code is commented, but here is a description of what each switch is designed to do. The default value is given in each case.

You can certainly feel free to edit defaultSettings.yaml, but this is not ideal as it may be overwritten when you update your distribution—all of your hard work tweaking the script would be undone! Don't worry, there's a solution—feel free to peek ahead to Section 4.2 if you like.

defaultIndent "\t"

This is the default indentation (\t means a tab) used in the absence of other details for the command or environment we are working with—see indentRules for more details (page 7).

backupExtension .bak

If you call indent.pl with the -w switch (to overwrite myfile.tex) then it will create a backup file before doing any indentation: myfile.bak0

By default, every time you call indent.pl after this with the -w switch it will create myfile.bak1, myfile.bak2, etc.

onlyOneBackUp 0

If you don't want a backup for every time that you call indent.pl (so you don't want myfile.bak1, myfile.bak2, etc) and you simply want myfile.bak (or whatever you chose backupExtension to be) then change onlyOneBackUp to 1.

indentPreamble 0

The preamble of a document can sometimes contain some trickier code for indent → .pl to work with. By default, indent.pl won't try to operate on the preamble, but if you'd like it to try then change indentPreamble to 1.

alwaysLookforSplitBraces 1

This switch tells indent.pl to look for commands that can split braces across lines, such as parbox, tikzset, etc. In older versions of indent.pl you had to specify each one in checkunmatched—this clearly became tedious, hence the introduction of alwaysLookforSplitBraces.

As long as you leave this switch on (set to 1) you don't need to specify which commands can split braces across lines—you can ignore the fields checkunmatched and checkunmatchedELSE described later.

alwaysLookforSplitBrackets 1

This switch tells indent.pl to look for commands that can split *brackets* across lines, such as psSolid, pgfplotstabletypeset, etc. In older versions of indent pl you had to specify each one in checkunmatchedbracket—this clearly became tedious, hence the introduction of alwaysLookforSplitBraces.

As long as you leave this switch on (set to 1) you don't need to specify which commands can split brackets across lines—you can ignore checkunmatchedbracket described later.

indentAfterDocument 0

This switch tells indent.pl to indent after \end{document} or not.

lookForAlignDelims This is the first example of a field in defaultSettings.yaml that has more than one line; listing 3 shows more details.

LISTING 3: lookForAlignDelims

- 1 lookForAlignDelims:
- 2 tabular: 1
- 3 align: 1

```
4
       align*: 1
 5
       alignat: 1
 6
       alignat*: 1
 7
       cases: 1
 8
       dcases: 1
 9
       aligned: 1
10
       pmatrix: 1
       listabla: 1
11
```

You can populate this field with any other environments that you have that contain &. If you change your mind, just turn them off by setting them to 0 instead.

verbatimEnvironments A field that contains a list of environments that you would like left completely alone—no indentation will be done to environments that you have specified in this field—see listing 4.

LISTING 4: verbatimEnvironments

```
1 verbatimEnvironments:
2 verbatim: 1
3 lstlisting: 1
```

noIndentBlock If you have a block of code that you don't want indent.pl to touch (even if it is not a verbatim-like environment) then you can wrap it in an environment from noIndentBlock; you can use any name you like for this, provided you populate it as demonstrate in listing 5.

LISTING 5: noIndentBlock

```
1 noIndentBlock:
2 noindent: 1
3 cmhtest: 1
```

Of course, you don't want to have to specify these as null environments in your code, so you use them with a comment symbol, %, followed by as many spaces (possibly none) as you like; see listing 6 for example.

LISTING 6: noIndentBlock demonstration

noAdditionalIndent If you would prefer some of your environments or commands not to receive any additional indent, then populate noAdditionalIndent; see listing 7. Note that these environments will still receive the *current* level of indentation unless they belong to verbatimEnvironments, or noIndentBlock.

LISTING 7: noAdditionalIndent

```
1 noAdditionalIndent:
2 document: 1
```

```
3
       pccexample: 1
 4
       pccdefinition: 1
 5
       problem: 1
 6
       exercises: 1
 7
       pccsolution: 1
 8
       foreach: 0
9
       widepage: 1
10
       comment: 1
       \[: 0
11
       frame: 0
12
```

indentRules If you would prefer to specify individual rules for certain environments or commands, just populate indentRules; see listing 8

LISTING 8: indentRules

```
1 indentRules:
2 myenvironment: "\t\t"
3 anotherenvironment: "\t\t\t\t"
4 \[: "\t"
```

!!! The following fields are marked in red, as they are not necessary unless you wish to micro manage your indentation scheme.

checkunmatched Assuming you keep alwaysLookforSplitBraces set to 1 (which is the default) then
 you don't need to worry about checkunmatched.

Should you wish to deactivate alwaysLookforSplitBraces by setting it to 0, then you can populate checkunmatched with commands that can split braces across lines—see listing 9.

LISTING 9: checkunmatched

```
1 checkunmatched:
2 parbox: 1
3 vbox: 1
```

checkunmatchedELSE Similarly, assuming you keep alwaysLookforSplitBraces set to 1 (which is the default) then you don't need to worry about checkunmatchedELSE.

As in checkunmatched, should you wish to deactivate alwaysLookforSplitBraces by setting it to 0, then you can populate checkunmatchedELSE with commands that can split braces across lines and have an 'else' statement—see listing 10.

LISTING 10: checkunmatchedELSE

```
1 checkunmatchedELSE:
2 pgfkeysifdefined: 1
3 DTLforeach: 1
4 ifthenelse: 1
```

Should you wish to deactivate alwaysLookforSplitBrackets by setting it to 0, then you can populate checkunmatchedbracket with commands that can split *brackets* across lines—see listing 11.

LISTING 11: checkunmatchedbracket

```
1 checkunmatchedbracket:
2  psSolid: 1
3  pgfplotstablecreatecol: 1
4  pgfplotstablesave: 1
5  pgfplotstabletypeset: 1
6  mycommand: 1
```

4.2 indentconfig.yaml (for user settings)

A better way to change the settings is to set up your own settings file, mysettings.yaml (or any name you like, provided it ends with .yaml). The only thing you have to do is tell indent.pl where to find it.

indent.pl will always check your home directory for indentconfig.yaml, which is a plain text file you can create that contains the *absolute* paths for any settings files that you wish indent.pl to load—see listing 12 for a sample.

LISTING 12: indentconfig.yaml

```
1 # Paths to user settings for indent.pl
2 #
3 # Note that the settings will be read in the order you
4 # specify here- each successive settings file will overwrite
5 # the variables that you specify
6
7 paths:
8 - /home/cmhughes/Documents/yamlfiles/mysettings.yaml
9 - /home/cmhughes/folder/othersettings.yaml
10 - /some/other/folder/anynameyouwant.yaml
```

Note that the .yaml files you specify in indentconfig.yaml will be loaded in the order that you write them in. Each file doesn't have to have every switch from defaultSettings .yaml; in fact, I recommend that you only keep the switches that you want to *change* in your settings files.

LISTING 13: mysettings.yaml (example)

```
1  # Default value of indentation
2  defaultIndent: "\t\t\t\"
3
4  # environments that have tab delimiters, add more
5  # as needed
```

```
6 lookForAlignDelims:
7 tabbing: 1
```

You can make sure that your settings are loaded by checking indent.log for details—if you have specified a path that indent.pl doesn't recognize then you'll get a warning, otherwise you'll get confirmation that indent.pl has read your settings file.

FIX

4.3 localSettings.yaml

You may remember on page 4 we discussed the -1 switch that tells indent.pl to look for localSettings.yaml in the *same directory* as myfile.tex. This settings file will be read *after* defaultSettings.yaml and, assuming they exist, user settings.

In contrast to the *user* settings which can be named anything you like (provided that they are detailed in indentconfig.yaml), the *local* settings file must be called localSettings.yaml. It can contain any switches that you'd like to change—a sample is shown in listing 14.

LISTING 14: localSettings.yaml (example)

```
1  # Default value of indentation
2  defaultIndent: " "
3
4  # environments that have tab delimiters, add more
5  # as needed
6  lookForAlignDelims:
7   tabbing: 0
8
9  # verbatim environments- environments specified
10  # in this hash table will not be changed at all!
11 verbatimEnvironments:
12  cmhenvironment: 0
```

You can make sure that your local settings are loaded by checking indent.log for details—if localSettings.yaml can not be read then you will get a warning, otherwise you'll get confirmation that indent.pl has read localSettings.yaml.

4.4 Settings load order

indent.pl loads the settings files in the following order:

- 1. defaultSettings.yaml (always loaded, can not be renamed)
- anyUserSettings.yaml (and any other arbitrarily-named files specified in indentconfig
 .yaml)
- 3. localSettings.yaml (if found in same directory as myfile.tex and called with -1 switch; can not be renamed)

5 Known limitations

nested align delimiter blocks tables with multicolumn