## Docking Frames 1.0.5 - FAQ

# Benjamin Sigg

# April 20, 2008

# Contents

1	$\mathbf{Wr}$	iting a	pplications		
	1.1	How to write a close-button?			
		1.1.1	Solution 1: FDockable		
		1.1.2	Solution 2: DockFrontend		
		1.1.3	Solution 3: CloseAction		
		1.1.4	Solution 4: New DockAction		
	1.2	How o	do I layout the contents of a SplitDockStation?		
		1.2.1	Solution 1: SplitDockProperty		
		1.2.2	Solution 2: SplitDockPathProperty		
		1.2.3	Solution 3: SplitDockTree		
		1.2.4	Solution 4: SplitDockGrid		
		1.2.5	Solution 5: Start and store		

#### Abstract

Some questions that are frequently asked.

## 1 Writing applications

This section deals with questions that are related to writing code.

## 1.1 How to write a close-button?

A "close-button" is some button, most times a cross in the upper right edge, that closes a Dockable when pressed.

#### 1.1.1 Solution 1: FDockable

When using the common-project, then you can use DefaultSingleCDockable or DefaultMultipleCDockable. Both CDockables contain a method setCloseable. Call that method with true.

```
DefaultSingleCDockable dockable = ...
dockable.setCloseable( true );
```

If you implement the interface SingleCDockable or MultipleCDockable directly, then ensure that isCloseable returns true.

#### 1.1.2 Solution 2: DockFrontend

When using a DockFrontend, register the Dockable at the DockFrontend and call setHideable.

```
DockFrontend frontend = ...
Dockable dockable = ...

frontend.add( dockable, "a_unique_id" );
frontend.setHideable( dockable, true );
```

## 1.1.3 Solution 3: CloseAction

If you use the common-project, then a DockAction called CloseAction is available. Add the action to the Dockables which should be closeable, for example you could use an ActionGuard:

```
public class CloseGuard implements ActionGuard {
2
3
         private DockActionSource source;
         public CloseGuard( DockController controller ){
    DockAction close = new CloseAction( controller );
 4
5
 6
7
              source = new DefaultDockActionSource(
                   new Location Hint (
8
9
10
                        Location Hint ACTION_GUARD,
                        Location Hint.RIGHT_OF_ALL ),
                   close );
11
         }
12
         public boolean react( Dockable dockable ) {
14
              return true;
15
16
17
         public DockActionSource getSource( Dockable dockable ) {
              return source;
         }
18
19
    }
```

And later:

```
1 DockController controller = ...
2 controller.addActionGuard( new CloseGuard( controller ));
```

#### 1.1.4 Solution 4: New DockAction

If CloseAction of the common-project can't be used, then a new DockAction must be written.

This action is then used as described in the third solution.

## 1.2 How do I layout the contents of a SplitDockStation?

The SplitDockStation has a complex layout. How can new Dockables be added to SplitDockStation such that they have a certain location and size?

### 1.2.1 Solution 1: SplitDockProperty

A SplitDockProperty describes the size and location of a Dockable on a SplitDockStation by storing the x, y coordinates, and the width and height. All the properties are normalized such that they are between 0 and 1.

A client can create new SplitDockPropertys and call drop:

```
SplitDockStation station = ...
Dockable alpha = ...
Dockable beta = ...

if( !station.drop( alpha , SplitDockProperty.NORTH ) )
station.drop( alpha );

if( !station.drop( beta , new SplitDockProperty( 0 , 0 , 1 , 1 )))
station.drop( beta );
```

A few words to this code: in lines 5 and 8, the result of drop needs to be checked. It is possible, that SplitDockStation refuses to add a Dockable.

SplitDockStation internally has a binary tree in whose leafs the Dockables are stored, and the nodes determine the proportions between the Dockables. Each drop adds a new branch into that tree. The SplitDockProperty is only a hint where to insert the branch, and will not be stored for later use. So this station does **not** work like a LayoutManager, the order in which the Dockables are dropped is important. The first Dockable will always get boundaries of 0,0,1,1.

#### 1.2.2 Solution 2: SplitDockPathProperty

As set earlier, SplitDockStation is internally organized as a binary tree. A SplitDockPathProperty is the description of the exact location of a branch. It is used like SplitDockProperty:

```
SplitDockStation station = ...
Dockable dockable = ...

SplitDockPathProperty path = new SplitDockPathProperty();
path.add( SplitDockPathProperty.Location.BOTTOM, 0.4 );
path.add( SplitDockPathProperty.Location.LEFT, 0.25 );
if( !station.drop( dockable, path ))
station.drop( dockable );
```

In lines 5,6 a branch to the bottom left edge is created.

### 1.2.3 Solution 3: SplitDockTree

A SplitDockTree is an exact model of the internal binary tree that every SplitDockStation has. When calling dropTree, all Dockables will be removed from the station, and the new tree will replace the old one.

```
SplitDockStation station = ...
    Dockable [] dockables = ...
3
4
    SplitDockTree tree = new SplitDockTree();
5
    tree.root(
6
         tree.horizontal(
             tree.vertical(
                  dockables [0],
                  dockables [1],
                  0.4 ),
10
             tree.vertical(
11
                  tree.put(
dockables[2]),
12
13
                  tree.put(
                       dockables [3],
dockables [4] ) )
15
16
17
        )
18
    station.dropTree( tree );
```

Note that several Dockables can be put at the same location as shown in lines 14-16.

### 1.2.4 Solution 4: SplitDockGrid

A SplitDockGrid is an algorithm that takes several Dockables and their desired location, and creates a SplitDockTree that matches these locations as good as possible.

The use is straight forward:

```
1    SplitDockStation station = ...
2    Dockable[] dockables = ...
3
4    SplitDockGrid grid = new SplitDockGrid();
5    grid.addDockable( 0.0, 0.0, 0.5, 0.5, dockables[0] );
6    grid.addDockable( 0.0, 0.5, 0.5, 0.5, dockables[1] );
7    grid.addDockable( 0.5, 0.0, 0.5, 0.5, dockables[2] );
8    grid.addDockable( 0.5, 0.5, 0.5, 0.5, dockables[3] );
9    station.dropTree( grid.toTree() );
```

There is also the possibility to model the layout with a String:

```
\begin{array}{lll} {\rm SplitDockStation} & {\rm station} = \ldots \\ {\rm Dockable} \left[\right] & {\rm dockables} = \ldots \end{array}
 1 2
 3
        \label{eq:map_string} \begin{array}{lll} Map < String \;,\;\; Dockable[] > map = \textbf{new} \;\; HashMap < String \;,\;\; Dockable[] > () \;; \\ \textbf{for} ( \;\; \textbf{int} \;\; i \; = \; 0; \;\; i \; < \; dockables.length \;; \;\; i+\!\!\!\!+ \;) \; \{ \end{array}
 6
7
                   map.put(
                            String.valueOf( i ),
new Dockable[]{ dockables[i] });
 8
9
         }
10
         String layout =
"0022\n"+
"0022\n"+
"1133\n"+
"1133";
11
12
13
14
15
16
         {\tt SplitDockGrid\ grid\ =\ new\ SplitDockGrid\ (\ layout\ ,\ map\ )\ ;}
          station.dropTree( grid.toTree() );
```

The layout is defined in lines 12-15, just image a raster where the characters tell which Dockable should overlap a given cell.

## 1.2.5 Solution 5: Start and store

If your application is able to store the layout, then just start the application, make the layout by hand, and store the layout.

The common-project or  ${\tt DockFrontend}$  can help you storing one or several layouts.