

# Dr. Hakim Mellah Department of Computer Science & Software Engineering Concordia University, Montreal, Canada

# Lecture 10: Virtual Memory

**COMP 346: Operating Systems** 

These slides has been extracted, modified and updated from original slides of:

Operating System Concepts, 10th Edition, by: Silberschatz/Galvin/Gagne, published by John Wiley & Sons

## Chapter 10: Virtual Memory

- **≻**Background
- ➤ Demand Paging
- ➤ Copy-on-Write
- ➤ Page Replacement
- ➤ Allocation of Frames
- **≻**Thrashing
- **≻**Other Considerations

## Background

- ➤ Code needs to be in memory to execute, but entire program rarely used
  - ❖ Error code, unusual routines, large data structures
- ➤ Entire program code not needed at same time
- ➤ Consider ability to execute partially-loaded program
  - ❖ Program no longer constrained by limits of physical memory
  - ❖ Each program takes less memory while running -> more programs run at the same time
    - ✓ Increased CPU utilization and throughput with no increase in response time or turnaround time
  - Less I/O needed to load or swap programs into memory -> each user program runs faster


## Background (Cont.)

- ➤ Virtual memory separation of user logical memory from physical memory
  - ❖Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - ❖Allows address spaces to be shared by several processes
  - ❖ Allows for more efficient process creation
  - ❖ More programs running concurrently
  - ❖Less I/O needed to load or swap processes

## Background (Cont.)


- ➤ Virtual address space logical view of how process is stored in memory
  - ❖Usually start at address 0, contiguous addresses until end of space
  - ❖Meanwhile, physical memory organized in page frames
  - ❖MMU must map logical to physical
- ➤ Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation

#### Virtual Memory That is Larger Than Physical Memory




## Virtual-address Space

- Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
  - Maximizes address space use
  - Unused address space between the two is hole
    - No physical memory needed until heap or stack grows to a given new page
- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages readwrite into virtual address space
- Pages can be shared during fork(), speeding process creation




## **Shared Library Using Virtual Memory**



## **Demand Paging**

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
  - ❖Less I/O needed, no unnecessary I/O
  - Less memory needed
  - Faster response
  - More users
- Similar to paging system with swapping (diagram on right)
- ➤ Page is needed ⇒ reference to it
  - **❖**invalid reference ⇒ abort
  - ❖not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a pager




#### **Basic Concepts**

- ➤ With swapping, pager guesses which pages will be used before swapping out again
- ➤Instead, pager brings in only those pages into memory
- How to determine that set of pages?
  - ❖ Need new MMU functionality to implement demand paging
- ▶If pages needed are already memory resident
  - ❖ No difference from non demand-paging
- ▶If page needed and not memory resident
  - ❖ Need to detect and load the page into memory from storage
    - ✓ Without changing program behavior
    - ✓ Without programmer needing to change code


#### Valid-Invalid Bit

- With each page table entry a valid—invalid bit is associated (v ⇒ in-memory – memory resident, i ⇒ not-in-memory)
- ➤ Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:



ightharpoonup During MMU address translation, if valid—invalid bit in page table entry is ightharpoonup page fault

#### Page Table When Some Pages Are Not in Main Memory




#### Page Fault

➤ If there is a reference to a page, first reference to that page will trap to operating system:

#### page fault

- 1. Operating system looks at another table to decide:
  - ♣ Invalid reference ⇒ abort
  - Just not in memory
- 2. Find free frame
- 3. Swap page into frame via scheduled disk operation
- 4.Reset tables to indicate page now in memory Set validation bit = v
- 5. Restart the instruction that caused the page fault

## Steps in Handling a Page Fault




## **Aspects of Demand Paging**

- Extreme case start process with *no* pages in memory
  - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
  - ❖ And for every other process pages on first access
  - **❖** Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
  - ❖ Pain decreased because of locality of reference
- Hardware support needed for demand paging
  - ❖ Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Instruction restart

#### **Instruction Restart**

- >Consider an instruction that could access several different locations
  - ❖block move



- ❖auto increment/decrement location
- ❖ Restart the whole operation?
  - ✓ What if source and destination overlap?

#### Performance of Demand Paging

#### ➤ Stages in Demand Paging (worse case)

- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
  - 1. Wait in a queue for this device until the read request is serviced
  - Wait for the device seek and/or latency time
  - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

## Performance of Demand Paging (Cont.)

- Three major activities
  - Service the interrupt careful coding means just several hundred instructions needed
  - ❖ Read the page lots of time
  - ❖ Restart the process again just a small amount of time
- $\triangleright$  Page Fault Rate  $0 \le p \le 1$ 
  - $\Leftrightarrow$  if p = 0 no page faults
  - $\Leftrightarrow$  if p = 1, every reference is a fault
- ➤ Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in )
```

## **Demand Paging Example**

- ➤ Memory access time = 200 nanoseconds
- ➤ Average page-fault service time = 8 milliseconds
- ArrEAT = (1 p) x 200ns + p (8 milliseconds) = (1 - p) x 200ns + p x 8,000,000ns = 200ns + p x 7,999,800ns
- ➤ If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- ➤ If want performance degradation < 10 percent
  - **❖** 220 > 200 + 7,999,800 x p 20 > 7,999,800 x p
  - **❖**p < .0000025
  - < one page fault in every 400,000 memory accesses</p>

#### **Demand Paging Optimizations**

- ➤ Swap space I/O faster than file system I/O even if on the same device
  - ❖Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
  - ❖Then page in and out of swap space
  - ❖ Used in older BSD Unix
- ➤ Demand page in from program binary on disk, but discard rather than paging out when freeing frame
  - ❖Used in Solaris and current BSD
  - Still need to write to swap space
    - ✓ Pages not associated with a file (like stack and heap) anonymous memory
    - ✓ Pages modified in memory but not yet written back to the file system
- ➤ Mobile systems
  - ❖Typically don't support swapping
  - ❖Instead, demand page from file system and reclaim read-only pages (such as code)


#### What Happens if There is no Free Frame?

- ➤ Used up by process pages
- ➤ Also in demand from the kernel, I/O buffers, etc
- ➤ How much to allocate to each?
- ➤ Page replacement find some page in memory, but not really in use, page it out
  - ❖Algorithm terminate? swap out? replace the page?
  - ❖Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times

## Page Replacement

- ➤ Prevent over-allocation of memory by modifying pagefault service routine to include page replacement
- ➤ Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- ➤ Page replacement completes separation between logical memory and physical memory large virtual memory can be provided on a smaller physical memory

## Need For Page Replacement



#### Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
  - If there is a free frame, use it
  - If there is no free frame, use a page replacement algorithm to select a victim frame
    - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap


Note now potentially 2 page transfers for page fault – increasing EAT

#### Page and Frame Replacement Algorithms

- > Frame-allocation algorithm determines
  - ❖ How many frames to give each process
  - ❖Which frames to replace
- **→** Page-replacement algorithm
  - ❖ Want lowest page-fault rate on both first access and re-access
- ➤ Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
  - ❖String is just page numbers, not full addresses
  - ❖ Repeated access to the same page does not cause a page fault
  - \*Results depend on number of frames available
- ➤ In all our examples, the reference string of referenced page numbers is


7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

#### Graph of Page Faults Versus The Number of Frames



## First-In-First-Out (FIFO) Algorithm


- > Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- >3 frames (3 pages can be in memory at a time per process)



15 page faults


- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
  - Adding more frames can cause more page faults!
    - √ Belady's Anomaly
- ➤ How to track ages of pages?
  - ❖ Just use a FIFO queue

## FIFO Illustrating Belady's Anomaly




#### Optimal Algorithm

- ➤ Replace page that will not be used for longest period of time ❖ 9 is optimal for the example
- ➤ How do you know this?
  - Can't read the future
- Used for measuring how well your algorithm performs



## Least Recently Used (LRU) Algorithm

- ➤ Use past knowledge rather than future
- > Replace page that has not been used in the most amount of time
- Associate time of last use with each page




- ▶12 faults better than FIFO but worse than OPT
- ➤ Generally good algorithm and frequently used
- ➤ But how to implement?

## LRU Algorithm (Cont.)

- ➤ Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
  - When a page needs to be changed, look at the counters to find smallest value
    - √ Search through table needed
- ➤ Stack implementation
  - ❖ Keep a stack of page numbers in a double link form:
  - **❖** Page referenced:
    - ✓ move it to the top
    - √ requires 6 pointers to be changed
  - But each update more expensive
  - ❖ No search for replacement
- ➤ LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly

#### Use Of A Stack to Record Most Recent Page References




#### LRU Approximation Algorithms

- > LRU needs special hardware and still slow
- > Reference bit
  - ❖With each page associate a bit, initially = 0
  - ❖When page is referenced bit set to 1
  - ❖ Replace any with reference bit = 0 (if one exists)
    - ✓ We do not know the order, however

#### **≻**Second-chance algorithm

- ❖Generally FIFO, plus hardware-provided reference bit
- Clock replacement
- ❖ If page to be replaced has
  - ✓ Reference bit = 0 -> replace it
  - ✓ reference bit = 1 then:
    - set reference bit 0, leave page in memory
    - replace next page, subject to same rules

#### Second-Chance (clock) Page-Replacement Algorithm



#### **Enhanced Second-Chance Algorithm**

- Improve algorithm by using reference bit and modify bit (if available) in concert
- ➤ Take ordered pair (reference, modify)
- 1.(0, 0) neither recently used not modified best page to replace
- 2.(0, 1) not recently used but modified not quite as good, must write out before replacement
- 3.(1, 0) recently used but clean probably will be used again soon
- 4.(1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- ➤ When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
  - Might need to search circular queue several times

#### **Counting Algorithms**

- ➤ Keep a counter of the number of references that have been made to each page
  - ❖ Not common
- ➤ Least Frequently Used (LFU) Algorithm: replaces page with smallest count
- ➤ Most Frequently Used (MFU) Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used

## Page-Buffering Algorithms

- ➤ Keep a pool of free frames, always
  - ❖Then frame available when needed, not found at fault time
  - Read page into free frame and select victim to evict and add to free pool
  - ❖When convenient, evict victim
- ➤ Possibly, keep list of modified pages
  - When backing store otherwise idle, write pages there and set to nondirty
- ➤ Possibly, keep free frame contents intact and note what is in them
  - If referenced again before reused, no need to load contents again from disk
  - Generally useful to reduce penalty if wrong victim frame selected

#### **Allocation of Frames**

- Each process needs *minimum* number of frames
- > Maximum of course is total frames in the system
- ➤ Two major allocation schemes
  - ❖ fixed allocation
  - priority allocation
- ➤ Many variations

#### **Fixed Allocation**

- ➤ Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
  - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
  - Dynamic as degree of multiprogramming, process sizes change

- 
$$s_i$$
 = size of process  $p_i$   $m = 62$   
-  $S = \sum s_i$   $s_1 = 10$   
-  $m$  = total number of frames  
-  $a_i$  = allocation for  $p_i = \frac{s_i}{S} \times m$   $a_1 = \frac{10}{137} \cdot 62 \gg 4$   
-  $a_2 = \frac{127}{137} \cdot 62 \gg 57$ 

## **Priority Allocation**

- ➤ Use a proportional allocation scheme using priorities rather than size
- $\triangleright$  If process  $P_i$  generates a page fault,
  - ❖ select for replacement one of its frames
  - select for replacement a frame from a process with lower priority number


#### Global vs. Local Allocation

- ➤ Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
  - ❖ But then process execution time can vary greatly
  - ❖ But greater throughput so more common
- Local replacement each process selects from only its own set of allocated frames
  - ❖ More consistent per-process performance
  - ❖ But possibly underutilized memory

## Thrashing

- ➤If a process does not have "enough" pages, the page-fault rate is very high
  - ❖ Page fault to get page
  - ❖ Replace existing frame
  - ❖But quickly need replaced frame back
  - ❖This leads to:
    - ✓ Low CPU utilization
    - ✓ Operating system thinking that it needs to increase the degree of multiprogramming
    - ✓ Another process added to the system
- **>Thrashing** ≡ a process is busy swapping pages in and out

# Thrashing (Cont.)



## Demand Paging and Thrashing

- ➤ Why does demand paging work?
  - **Locality model** 
    - ❖ Process migrates from one locality to another
    - Localities may overlap
- ➤ Why does thrashing occur?
  - $\Sigma$  size of locality > total memory size
    - ❖Limit effects by using local or priority page replacement

#### Locality In A Memory-Reference Pattern

