
SOME THINGS TO CONSIDER WHEN USING MOVE SEMANTICS

Mantid Developer Meeting 2016

Anton Piccardo-Selg


MOVE SEMANTICS 101



1. DEAD VARIABLES

std::move

```
std::unique_ptr<Foo> source(new Foo);
...
std::unique_ptr<Foo> destination = std::move(source);
```



```
source->doSomething(); // Error, source is equal to nullptr
```

2. SPECIAL MEMBER FUNCTION GENERATION

- move-constructor + move-assignment operator
- rule of five
- rules have become considerably more complex
- ...

Example:

```
Foo createFoo () {
  return Foo();
}

class Foo {
public:
  void doSomething() {...};
};

...
auto foo = createFoo(); // <- Move assignment</pre>
```

```
class Foo {
public:
    void doSomething() {...};
    ~Foo() {...}; // Want to do some logging
};
...
auto foo = createFoo(); // <- Copy assignment !!!</pre>
```

3. RVALUE OVERLOADS

Method overloading via rvalue references:

```
class Foo {
public:
     void doSomething(Bar& input);
     void doSomething(Bar&& input);
}
```

```
class Bar {
public:
     void doSomething()&;
     void doSomething()&&;
}
```

Example:

```
class MANTID API DLL MatrixWorkspace : public IMDWorkspace{
public:
        MatrixWorkspace uptr clone() const {...}
MatrixWorkspace uptr ws1 = ws->clone(); //Ok
MatrixWorkspace sptr ws2 = ws1; // Error
```

```
MatrixWorkspace sptr ws3 = ws1->clone(); // Ok
```

Overloaded of move-assignment operator

```
template<class Y, class D>
shared ptr& operator=(std::unique ptr<Y, D>&& r)
```