CygSSH User Guide

© Copyright 2020-2023 by Bill Stewart

 $CygSSH\ is\ a\ convenient\ packaging\ of\ the\ Cygwin\ version\ of\ OpenSSH\ that\ provides\ a\ simple\ way\ to\ install\ and\ use\ the\ Cygwin\ version\ of\ OpenSSH\ on\ Windows.$

This software is covered by the license agreements listed in appendix F.

Contents

Chapter 1: Installing the Package .																			4
1.1 License Agreement																			5
1.2 Information																			5
1.3 Select Destination Location																			5
1.4 Select Setup Type																			5
1.5 Select Start Menu Folder .																			5
1.6 Select Additional Tasks .																			6
Chapter 2: Reinstalling, Upgrading or I	owng	radi	ng																7
2.1 Reinstalling or Upgrading .																			7
2.2 Downgrading																			7
Chapter 3: Uninstalling the Package																			8
Chapter 4: Client Authentication																			9
4.1 Using the SSH Client Comma	nds																		9
4.2 Using Other SSH Clients .																			10
Chapter 5: Server Authentication .																			11
5.1 Using the Local Access Group																			11
5.2 Using Password Authentication	n .																		11
5.3 Using Public Key Authenticat	ion																		12
5.3.1 Create the Directories	on th	e Se	rve	r															12
5.3.2 Grant the Account Per	missi	on to	o th	e D	ire	cto	rie	s											12
5.3.3 Add the Account's Pu	olic K	ey to	o th	e a	ut	ho	ri	ze	d_	ke	ys	Fil	le						13
5.4 Configuring an SFTP-Only A	ccoun	t																	13
Chapter 6: Public Key Cryptography																			15
6.1 Host Keys																			15
6.2 Public Key Authentication																			15

6.2.1 Creating a Key Pair .			•					•								•			15
6.2.1.1 Creating a Key Pa	ir (Jsiı	ng t	he	Ne	w-\$	SSI	HK	ey.	ps]	1 S	crip	ot						16
6.2.1.2 Create a Key Pair	Us	ing	Pu	ТТ	Υg	en													16
6.2.2 Updating a Private Key																			17
Chapter 7: About Cygwin																			18
7.1 Cygwin File System Permissions																			18
7.2 Cygwin Account Names																			18
7.3 POSIX Path Names																			19
7.4 The Cygwin Home Directory																			19
Appendix A: The ChrootDirectory Setting																			20
Appendix B: Using rsync with SSH																			21
Appendix C: Documentation Links																			22
Appendix D: Windows PowerShell Scripts																			23
Appendix E: Acknowledgments																			24
Appendix F: License Agreements																			25
Appendix G: Open Source Source Code																			26
Appendix H: Version History																			27
Index																			30

Chapter 1: Installing the Package

The system requirements are the following:

• Windows 8.1 64-bit or Windows Server 2012 R2 or later

The installer performs the following tasks:

- Creates the needed directories and copies the files
- Configures file and directory access control lists (ACLs)
- Configures the fstab file to disable Cygwin file system permission changes (see section 7.1)

The installer also performs the following tasks if the setup type is **full** (see section 1.4):

- Creates the OpenSSH server host keys (see section 6.1)
- Creates the local sshd account (see appendix A)
- Creates the local access group and updates the sshd_config file (see section 5.1)
- · Adds a rule to the Windows firewall to allow communication to the OpenSSH server service
- If the **startservice** task is selected (see section 1.6), starts the OpenSSH server service

Regardless of the setup type, the installer then performs any other tasks selected on the **Select Additional Tasks** page (see section 1.6).

The installer package is built using the Inno Setup installer, so it supports all of Inno Setup's command line parameters.

Example installation command:

CygSSH-Setup-version /SILENT /CLOSEAPPLICATIONS /SUPPRESSMSGBOXES

Replace *version* with the version (e.g., **9.3.2**).

The above command installs the package silently (i.e., without user interaction). The /CLOSEAPPLICATIONS parameter automatically stops running services and closes programs so that the installer can reinstall or upgrade the files. Stopped services will be automatically restarted after the installation completes. The /SUPPRESSMSGBOXES parameter suppresses message dialog boxes that would normally appear in an interactive installation.

If you want to prevent the installer from displaying its progress window during a silent install, use /VERYSILENT instead of /SILENT.

The installer also supports non-administrative install mode, which installs only the client files for the current user (does not require administrator privileges). To run in non-administrative install mode, use the /CURRENTUSER parameter on the command line.

You can also force the installer to uninstall the installed version before proceeding with installation; to do this, specify

the /FORCEUNINSTALL parameter on the command line. When you use this parameter, the installer detects if the package is already installed and automatically uninstalls it before proceeding with the installation.

The following sections describe the pages of the installer wizard.

1.1 License Agreement

The **License Agreement** page of the installer wizard lists the license agreements used by the various software components. Installing the software implies an acceptance of all license agreements (see appendix F).

1.2 Information

The **Information** page of the installer wizard lists release notes for the current version of the package.

1.3 Select Destination Location

The **Select Destination Location** page of the installer wizard allows you to specify the directory path where the package will be installed. This is C:\Program Files\CygSSH by default (if C: is the system drive). If you started the installer using the /CURRENTUSER parameter, the default path will be like C:\Users\username\AppData\Local\Programs\CygSSH (i.e., install only for the current user).

You can specify a different destination path on the installer's command line by using the /DIR="installpath" command line parameter (where installpath is the directory path name).

Throughout this documentation, the installation directory is referred to as *installpath*.

Note that this page doesn't appear if you are reinstalling or upgrading.

1.4 Select Setup Type

The **Select Setup Type** page of the installer wizard allows you to choose the setup type. The setup types are as follows:

- full Full installation (server and client files)
- **client** Client installation (client files only)

You can specify the setup type on the command line using the /TYPE="type" command line parameter (where type is either **full** or **client**). The default setup type is **full**, so the only reason to use the /TYPE command line parameter is if you want to specify /TYPE="client" as the default (typically for a silent install).

Note that this page doesn't appear under the following conditions:

- If you specified / CURRENTUSER on the installer's command line, because / CURRENTUSER implies the **client** setup type
- If you previously installed using the full setup type, because selecting the client setup type does not remove the server files

1.5 Select Start Menu Folder

The **Select Start Menu Folder** page of the installer wizard allows you to specify the name of the Start menu folder where it will install application shortcut icons.

You can specify the folder name on the command line using the /GROUP="name" command line parameter (where name is the folder name). Alternatively, you can specify /NOICONS to prevent creation of any Start menu shortcuts.

Note that this page doesn't appear if you are reinstalling or upgrading.

1.6 Select Additional Tasks

The **Select Additional Tasks** page of the installer wizard allows you to select additional tasks the installer should perform. The additional tasks are as follows:

- **startservice** Corresponds to the **Start OpenSSH server service** check box. Starts the OpenSSH server service. This task is not applicable if the setup type is **client** (see section 1.4). This task is selected by default.
- **modifypath** Corresponds to the **Add to system Path** (or **Add to user Path**) check box. Adds the *installpath*\bin directory to the system or user Path environment variable if it does not already exist. This task is selected by default. (This task does not appear if *installpath*\bin is already in the system or user Path.)
- **resetconfig** Restores the OpenSSH configuration files (ssh_config and/or sshd_config) to default values. Use this task with caution if you have made any customizations to the etc\ssh_config and/or etc\sshd_config files. When you select this task, the installer renames the existing ssh_config and/or sshd_config files with -timestamp appended (where timestamp is the current year, month, day, hour, minute, and second) before installing default copies of the configuration file(s). This task is not selected by default.

You can specify one or more of the additional tasks on the command line using the /TASKS="task[,task[...]]" command line parameter (where task is one or more of the above task names, separated by , characters).

For an interactive (i.e., not silent) installation, the /TASKS parameter specifies which tasks are selected by default; you can change the defaults on the page as you install.

For a silent installation, the /TASKS parameter dictates the list of tasks the installer will perform. For example, if you specify /TASKS="startservice" /SILENT on the installer's command line, the installer will **only** perform the startservice task.

To indicate 'no tasks', specify /TASKS="" on the installer's command line.

Note that if you do not select the modifypath task when you install, you will need to do one of the following before running commands:

- Change to the *installpath*\bin directory before running the command
- Specify the path to the command when you want to run it

Chapter 2: Reinstalling, Upgrading or Downgrading

This chapter describes how to reinstall, upgrade, and downgrade the package.

2.1 Reinstalling or Upgrading

Reinstalling or upgrading the package is as simple as running the installer:

- If the installer is the same version as the installed version, it will reinstall the installed version.
- If the installer is a newer version than the installed version, it will upgrade the installed version.

A reinstall or upgrade cannot proceed if the OpenSSH server service or any of the programs in the package are currently running. If any are running, the installer will prompt for permission to stop running services and close any programs.

You can prevent the prompt from appearing by specifying the /CLOSEAPPLICATIONS parameter on the installer's command line. This is particularly useful when using the /SILENT parameter (see chapter 1).

2.2 Downgrading

In order to perform a downgrade, you can do one of the following:

- Uninstall the installed version (see chapter 3) and install the older version, or
- Use the /FORCEUNINSTALL parameter (see chapter 1).

If you are installing an older version of the package that doesn't support the /FORCEUNINSTALL parameter, you will need to uninstall and reinstall.

Chapter 3: Uninstalling the Package

To uninstall the package, use the standard means of accessing installed applications on your version of Windows (e.g., the **Programs and Features** applet in the Control Panel), and uninstall it from there.

If you want to uninstall silently (without user interaction), do the following:

- 1. Determine the filename of the uninstall program. The file is in *installpath* and is named like unins*nnn*.exe (where *nnn* is 3 digits normally 000).
- 2. Run the executable with the /SILENT command line parameter.

For example, if the uninstaller executable is C:\Program Files\CygSSH\unins000.exe, the command line to uninstall silently is the following:

"C:\Program Files\CygSSH\unins000.exe" /SILENT

You can also replace /SILENT with /VERYSILENT to prevent the uninstaller from displaying its progress window.

The uninstall program does not remove the following items:

- Configuration files in the etc directory
- The lastlog file in the var\log directory
- The users\SYSTEM\.ssh directory or its contents
- Any other user created files
- The local sshd user account

Chapter 4: Client Authentication

This chapter describes how to authenticate to an OpenSSH server using SSH client software.

4.1 Using the SSH Client Commands

The CygSSH package provides several SSH client commands:

- The scp command copies files to an SSH server
- The **ssh** command establishes an interactive shell session with an SSH server
- The **sftp** command establishes a file transfer session with an SSH server

Note: It's recommended to run the **ssh** and **sftp** SSH client commands using the **mintty** command (e.g., **mintty ssh** rather than just **ssh**). If you run these SSH client commands without the **mintty** command, line wrapping and other features may not work as expected.

Example 1:

```
mintty sftp COMPUTER1+localuser@computer1
```

This command establishes a file transfer session to computer1 using the account COMPUTER1+localuser.

Example 2:

```
mintty ssh -i /cygdrive/c/Users/KenDyer/.ssh/kenprivkey KenDyer@computer2
```

This command establishes an interactive shell session to computer 2 using the KenDyer account using public key authentication (see section 6.2), using the file C:\Users\KenDyer\.ssh\kenprivkey as the private key.

Example 3:

```
scp "/cygdrive/C/Program\ Files/CygSSH/etc/sshd_config"
   "bkpsvc@server1:/cygdrive/C/Program\ Files\CygSSH\etc"
```

(All on one line) This command copies the sshd_config file from the current computer to a remote computer.

When using the Cygwin SSH client commands, note that path names must be in POSIX format, using the \ character to 'escape' spaces where necessary (see section 7.3).

If you haven't connected to an SSH server before, the command will prompt you to store the server's host key (see section 6.1) in the known_hosts file. The default path of the known_hosts file is in the .ssh directory in the user's home directory (see section 7.4).

You can also use the **rsync** command over an SSH connection to transfer files more efficiently (see appendix B).

See appendix C for links to the documentation for the ssh, scp, sftp, and rsync commands.

4.2 Using Other SSH Clients

See the documentation for the SSH client for more information on how to use it to connect to an SSH server.

Popular Windows SSH clients include the following:

PuTTY - https://www.chiark.greenend.org.uk/~sgtatham/

WinSCP - https://winscp.net/

Chapter 5: Server Authentication

This chapter describes how to configure the OpenSSH server service to permit logons using password authentication (see section 5.2) or public key authentication (see section 5.3).

5.1 Using the Local Access Group

By default, the OpenSSH server service only allows accounts that are members of the SSH Users local group to log on. The installer (see chapter 1) will create the SSH Users local group if it does not exist. This local group is referred to as the *local access group*.

The local access group is empty by default, which means you must explicitly add accounts to the local access group to allow logon via SSH.

If the computer is an Active Directory domain member, nested domain groups are supported. For example, you can add a domain group as a member of the SSH Users local group, and all members of the domain group will be granted access to log on using SSH.

If you have an Active Directory domain, you can manage the membership of the SSH Users local group using a Group Policy Object (GPO).

The installer (see chapter 1) automatically updates the sshd_config file at installation time with the following line:

```
AllowGroups "[computername+]SSH Users"
```

If the computer is a domain member, the installer adds the computer name and + prefix (see section 7.2). Otherwise, the computer name and + prefix are not used.

If the computer name changes, or if the computer is removed as a domain member, you will need to manually edit the sshd_config file as follows:

- If the computer name changes, update the computer name on the AllowGroups line of the file.
- If the computer is removed as a domain member, remove the computer name and + character on the AllowGroups line.

Once complete, save the sshd config file and restart the OpenSSH server service.

5.2 Using Password Authentication

Once an account is a member of the local access group on the OpenSSH server (see section 5.1), that account can log on using an SSH client using the account's password. No further configuration is required.

The account name must use Cygwin format (see section 7.2).

5.3 Using Public Key Authentication

Public key authentication is a means of authenticating an SSH logon without needing the account's password (see section 6.2).

To authenticate an account using a public key instead of a password, you must first create a key pair (see section 6.2.1).

Once you have a key pair, you will need to complete all of the following configuration steps to enable public key authentication for the account:

- Ensure the account is a member of the local access group (see section 5.1)
- Create the directories on the server (see section 5.3.1)
- Grant the account permission to the directories (see section 5.3.2)
- Add the account's public key to the authorized_keys file (see section 5.3.3)

5.3.1 Create the Directories on the Server

To allow an account to authenticate using a public key (see section 5.3), you must create a directory named for the account in the *installpath*\users directory, and a .ssh directory within that directory.

This section also applies to setting up an SFTP-only account (see section 5.4).

The account name must use Cygwin format (see section 7.2).

For example, suppose the current computer is a domain member, and you want to allow the KenDyer account in the computer's domain to authenticate.

In this example you would create the following directories on the server:

- installpath\users\KenDyer
- installpath\users\KenDyer\.ssh

5.3.2 Grant the Account Permission to the Directories

To allow an account to authenticate using a public key (see section 5.3), you must update the directory's access control list (ACL) to grant the account at least read (\mathbf{RX}) access to the directory and its subdirectories.

This section also applies to setting up an SFTP-only account (see section 5.4).

You can use the **icacls** command to grant the permissions.

First, open an elevated PowerShell console (i.e., right-click the PowerShell icon and choose Run as administrator).

Run a command like the following:

```
icacls "installpath\users\cygwinaccountname"
/grant "windowsaccountname:(CI)(OI)access"
```

(All on one line)

Replace *cygwinaccountname* with the Cygwin account name (see section 7.2), replace *windowsaccountname* with the Windows account name, and replace *access* with either **M** for modify access or **RX** for read-only access.

For example, suppose the current computer is a member of the FABRIKAM domain and you are setting the permissions

for the KenDyer account in that domain. The command to grant modify access would be as follows:

```
icacls "C:\Program Files\CygSSH\users\KenDyer"
  /grant "FABRIKAM\KenDyer:(CI)(OI)M"

(All on one line)

If you want to grant read-only access instead:
icacls "C:\Program Files\CygSSH\users\KenDyer"
  /grant "FABRIKAM\KenDyer:(CI)(OI)RX"
```

(All on one line)

5.3.3 Add the Account's Public Key to the authorized_keys File

To allow an account to authenticate using a public key (see section 5.3), you must add the account's public key to the authorized keys file.

The authorized_keys file is a text file in the account's .ssh directory that contains one line for each public key for the account. (The OpenSSH documentation describes the authorized_keys file format.)

If you use the **New-SSHKey.ps1** script to generate a key pair (see section 6.2.1.1), you can use the generated public key (.pub) file as the authorized_keys file for the account.

If you use **PuTTYgen** to generate a key pair (see section 6.2.1.2), you can use the text box labeled **Public key for pasting into OpenSSH authorized_keys file** as the content of the authorized_keys file. If you have a .ppk file, open it in **PuTTYgen**. It will put the public key in the text box, and you can copy it from there (make sure there are no line breaks).

For example, suppose the current computer is a member of the FABRIKAM domain, and you want to allow the KenDyer account in that domain to authenticate.

In this example, the file <code>installpath\users\KenDyer\.ssh\authorized_keys</code> would contain the public key(s) used to authenticate the <code>KenDyer</code> account.

5.4 Configuring an SFTP-Only Account

This section describes how to configure an SFTP-only account (i.e., the account can only connect to the OpenSSH server using a file transfer client such as **sftp** or **WinSCP**).

To configure an SFTP-only account, first create the directories for it (see section 5.3.1) and set the permissions (see section 5.3.2).

Next, create an sftp directory inside the account's directory.

Next, add lines like the following to the end of the sshd config file:

```
Match User accountname
X11Forwarding no
AllowTcpForwarding no
PermitTTY no
ChrootDirectory /users/%u/sftp
ForceCommand internal-sftp
```

Replace accountname with the account's Cygwin account name (see section 7.2).

The ChrootDirectory setting is not a true security control on Windows and is used only to limit the file system view on SFTP-only accounts (see appendix A).

Once complete, save the sshd_config file and restart the OpenSSH server service.

Note: You can't prevent the cygdrive and dev directories from appearing on the client side of the SFTP connection, but they don't cause any problems, either.

Example configuration:

Suppose the current computer is a domain member named COMPUTER1, and local account sftponly will be an SFTP-only account.

In this example, first create the following directories on the OpenSSH server:

- installpath\users\COMPUTER1+sftponly
- installpath\users\COMPUTER1+sftponly\sftp

Next, grant the sftponly account at least read (\mathbf{RX}) access to the $installpath \setminus \mathsf{users} \setminus \mathsf{COMPUTER1} + \mathsf{sftponly}$ directory and its subdirectories.

Then, add the following lines to the end of the sshd_config file:

```
Match User COMPUTER1+sftponly
X11Forwarding no
AllowTcpForwarding no
PermitTTY no
ChrootDirectory /users/%u/sftp
ForceCommand internal-sftp
```

If the account will authenticate using a public key instead of a password (see section 5.3), add the AuthenticationMethods publickey setting; e.g.:

```
Match User COMPUTER1+sftponly
AuthenticationMethods publickey
X11Forwarding no
AllowTcpForwarding no
PermitTTY no
ChrootDirectory /users/%u/sftp
ForceCommand internal-sftp
```

(You must also add the authorized_keys file to the account's .ssh directory, as described in section 5.3.3.)

Once complete, save the sshd_config file and restart the OpenSSH server service.

Chapter 6: Public Key Cryptography

Public key cryptography, sometimes also called *asymmetric cryptography*, is an encryption technique that uses two cryptographically related signatures—a *public key* and a *private key*. (The public key and private key are typically referred to as a *key pair*.) The public key is used to encrypt, and the private key is used to decrypt. It is not computationally feasible to generate a private key based on a public key.

OpenSSH uses public key cryptography to ensure the communication between an SSH client and the OpenSSH server are encrypted.

6.1 Host Keys

A host key is a cryptographic signature that uniquely identifies an OpenSSH server to SSH clients.

The installer (see chapter 1) automatically creates the necessary host key files at installation time.

The files containing the host keys are stored in <code>installpath\etc</code> and are named using the format <code>ssh_host_keytype_key[.pub]</code>, where <code>keytype</code> is <code>ecdsa</code>, <code>ed25519</code>, or <code>rsa</code>. The .pub suffix indicates the public key. Each key type represents an encryption algorithm supported by OpenSSH.

For example, the file ssh_host_ed25519_key contains the private host key for the ED25519 encryption algorithm, and the file ssh_host_ed25519_key.pub contains its associated public key.

The private key files are configured with restricted access control lists (ACLs) to prevent unauthorized access (SYSTEM:F and Administrators:F only).

SSH clients can store an SSH server's host key for later comparison. If the host key is different the next time the client connects, it may indicate the server has been compromised. Host keys are a mechanism to validate the identity of the server to which you're connecting.

The Cygwin SSH client commands (see section 4.1) store known host keys in the known_hosts file in the current user's home directory (see section 7.4).

6.2 Public Key Authentication

Public key authentication is a means of authenticating an SSH logon without needing the account's password.

To use public key authentication to authenticate an account in OpenSSH, you will need to create a key pair. The private key is used on the client side of the SSH connection, and the public key is used on the server side.

The account name must use Cygwin format (see section 7.2).

6.2.1 Creating a Key Pair

This section describes different ways to create a key pair.

6.2.1.1 Creating a Key Pair Using the New-SSHKey.ps1 Script

The **New-SSHKey.ps1** script is a wrapper for the **ssh-keygen** command. Using the script is straightforward: Open a PowerShell command window, run the script, it will prompt for the information it needs:

- 1. It will prompt you to enter the name of the private key file. The default path is the .ssh directory in the current user's home directory (see section 7.4). Press Enter without entering anything to use the default file name or enter a new file name.
- 2. It will prompt you to enter a passphrase. If you specify a passphrase, you must enter it every time you want to use the key.
- 3. It will prompt you to enter a comment. The comment is intended to help you identify the key. Press Enter without entering anything to use the default comment, or enter a new comment.

Sample command output follows:

```
PS C:\Users\accountname> New-SSHKey
Key type: ed25519
Enter file in which to save the key (C:\Users\accountname\.ssh\id_ed25519):
Enter passphrase (leave empty for no passphrase):
Confirm passphrase (leave empty for no passphrase):
Comment (accountname@hostname): My SSH key
Generating public/private ed25519 key pair.
Your identification has been saved in /cygdrive/c/Users/accountname/.ssh/id_ed25519.
Your public key has been saved in /cygdrive/c/Users/accountname/.ssh/id_ed25519.pub.
The key fingerprint is:
SHA256:w5UB4i5qymXdQX/7ErHgbglow77s6Q6h/kaN0iavKbA My SSH key
The key's randomart image is:
+--[ED25519 256]--+
  E...+o+.=o.
 . 00 0+ =.=0
 . =.0* . ...
 o Bo .. =
  = + . S
 = . = 0 0
 0 0 = .
  . +.+
    0.0.
+----[SHA256]----+
Restricted permissions on file 'C:\Users\accountname\.ssh\id_ed25519'.
```

The **New-SSHKey.ps1** script will attempt to restrict the permissions on the private key file to protect it from unauthorized access, but it may not be able to do this if the private key file is saved in a location where you don't have sufficient permissions to change the file's access control list (ACL). It's strongly recommended to store the private key in a location where you have permission to change the file's ACL so it will be protected from unauthorized access.

The file paths output by the **ssh-keygen** command are in POSIX format (see section 7.3).

6.2.1.2 Create a Key Pair Using PuTTYgen

To create a key pair using PuTTYgen, do the following:

- 1. Open the **PuTTYgen** program.
- 2. At the bottom of the **PuTTYgen** window, select **ED25519** as the type of key to generate.
- 3. Click the Generate button.

- 4. Move the mouse in the **PuTTYgen** window to generate randomness.
- 5. The text box near the top of the **PuTTYgen** window (labeled **Public key for pasting into OpenSSH authorized_keys file**) contains the public key for use on the OpenSSH server. (The line of text in this text box corresponds to the .pub file generated using the **New-SSHKey.ps1** script.)
- 6. You can specify a comment and/or a passphrase in the corresponding text boxes.
- 7. Click the Save button to save the private key in PuTTY (.ppk) format.

It's strongly recommended to store the private key file in a location with a restricted access control list (ACL), particularly if the private key is not protected with a passphrase.

6.2.2 Updating a Private Key

You can use the **Edit-SSHKey.ps1** script to update the passphrase or comment of a private key file. The command syntax is as follows:

```
Edit-SSHKey "filename" -Passphrase
or:
Edit-SSHKey "filename" -Comment
```

Replace *filename* with the name of the private key file.

The script will prompt you to enter a new passphrase or comment.

If you specify -Comment, the script will create a replacement public key file with a new comment (same filename but with .pub appended).

Hint: If you lose the public key file associated with a private key file, simply run **Edit-SSHKey.ps1** with the -Comment parameter. Enter an updated comment, and a new public key file will be created (same filename as private key, but with . pub appended).

Chapter 7: About Cygwin

Cygwin is a set of Windows DLLs (dynamically linked libraries) that provides substantial POSIX-compatible API (application programming interface) compatibility.

In effect, Cygwin is a POSIX emulation layer that allows programmers to compile POSIX-compatible source code into Windows executables with minimal changes.

This has several effects on programs that use the Cygwin emulation layer, as described in the following sections.

7.1 Cygwin File System Permissions

By default, Cygwin programs will attempt to reproduce POSIX-style file permissions using Windows access control lists (ACLs). This can result in unexpected permission problems when running Cygwin-based file management tools such as **rsync**.

To avoid this problem, the installer (see chapter 1) configures the file systems in the *installpath*\fstab file to use the noacl option for all directories.

Please see the following references in the Cygwin documentation for more information:

- File Permissions https://cygwin.com/cygwin-ug-net/ntsec.html#ntsec-files
- The Cygwin Mount Table https://cygwin.com/cygwin-ug-net/using.html#mount-table

7.2 Cygwin Account Names

Account names in Windows use the following format: [authorityname\]accountname (where authorityname is a computer name or domain name). The authority name isn't used in all circumstances (such as with the BUILTIN and NT AUTHORITY authorities).

Cygwin programs use the + rather than the \ character to separate authority names from account names.

Cygwin's account naming rules are as follows:

- Well-known and built-in accounts will be named as in Windows, without an authority name. Examples:
 Administrators or SYSTEM
- If the computer **is not** a domain member, the authority name is not used. Example: Administrator (not COMPUTERNAME+Administrator)
- If the computer **is** a domain member, accounts from the computer's domain are used without an authority name. Example: kendyer (not DOMAIN1+kendyer)
- Accounts from other domains use the domain name as the authority name. Example: DOMAIN2+lynndyer
- Local computer accounts of a domain member computer use the computer name as the authority. Example: COMPUTERNAME+localuser

See the Cygwin documentation for more details about how Cygwin maps between Windows and POSIX account names.

The Get-AccountName.ps1 script outputs one or more account names in both Windows and Cygwin formats:

- The script will output the Windows and Cygwin account names for the current account if you run it without parameters
- The script will out the Windows and Cygwin account names for one or more accounts if you provide the account name(s) as a parameter (the script also accepts pipeline input)

Run the command Get-Help Get-AccountName for more information about the script.

Note: OpenSSH server versions older than 8.0 required that Cygwin account names be specified using *exact case*. This requirement was removed starting in OpenSSH version 8.0.

7.3 POSIX Path Names

Cygwin programs use POSIX path names (such as /etc/fstab) rather than Windows path names (such as C:\Program Files\CygSSH\etc\fstab).

For example, the root directory (/) corresponds to installpath (e.g., C:\Program Files\CygSSH).

Windows drive letters (e.g., C:) are found in the /cygdrive directory (e.g., /cygdrive/c corresponds to C:).

The **cygpath** command allows you to easily translate Windows path names into a POSIX path names and vice-versa. Use the -w parameter to tell **cygpath** you want the Windows path.

```
Example Command

cygpath "C:\Program Files" /cygdrive/c/Program Files

cygpath C:\Users\KenDyer /cygdrive/c/Users/KenDyer

cygpath -w / C:\Program Files\CygSSH

cygpath -w /etc/fstab C:\Program Files\CygSSH\etc\fstab
```

In the first example, note that the quotes are required since the path name contains spaces.

If you need to specify a path name that contains spaces on a Cygwin program's command line, it may be necessary, depending on the command, to 'escape' the spaces in the path using the \ character (see section 4.1 for an example).

7.4 The Cygwin Home Directory

A user's *home directory* is the default path location for files owned by that user. By default, Cygwin maps the user's home directory to /home/accountname (see section 7.3 for more about POSIX path names).

The default can cause confusion, though, because it means that Cygwin and Windows have two separate home directory paths. For example, the Windows home directory for the KenDyer account might be C:\Users\KenDyer but the default Cygwin home directory would be something like C:\Program Files\CygSSH\home\KenDyer.

To avoid the confusion, the CygSSH package uses the nsswitch.conf file to set Cygwin's home directory to the same home directory that Windows uses. The file contains the following line:

```
db_home: /%H
```

The %H placeholder means 'Windows home directory in POSIX format.'

See the Cygwin documentation for more details about the nsswitch.conf file.

Appendix A: The ChrootDirectory Setting

On a POSIX-compliant operating system (e.g., Linux), the OpenSSH ChrootDirectory setting uses the chroot system call to restrict an account's access to a specific path in the file system: The account cannot access any file or directory outside of that specific path. In POSIX terminology, this is sometimes referred to as a *chroot jail*.

The Cygwin emulation layer used by OpenSSH on Windows (see chapter 7) has a limited implementation of chroot because the Windows operating system does not have a direct equivalent of this system call. Consequently, Cygwin's limited implementation of chroot is not a true security control because it can sometimes permit the account to 'escape' from the 'jail.' (It's important to understand that even if the account 'escapes' from the 'jail,' the account is still restricted by Windows security controls; it's just that the limited Cygwin chroot jail isn't enforced as an *additional* security control.)

Even though Cygwin's implementation chroot is not a true security control, we can still use the ChrootDirectory setting in sshd_config to restrict the file system view for an SFTP-only account (see section 5.4).

Using the ChrootDirectory setting in sshd_config requires the following two items be in place:

- 1. The passwd file in the etc directory must specify that the Windows SYSTEM account is user number 0 (this corresponds to the POSIX root user account)
- 2. The local sshd account (known as the *privsep account*) must exist, and it must be **enabled** (it must *not* be disabled as stated in the OpenSSH documentation)

These two items are taken care of automatically at installation time (they don't need to be configured manually).

Appendix B: Using rsync with SSH

The **rsync** command is an efficient file and directory replication tool that supports replication over an SSH connection so that the data is encrypted in transit.

The syntax for replicating data to a remote computer using an SSH connection is as follows:

```
rsync options -e "ssh [sshoptions]" "source" "accountname@hostname:dest"
```

Where:

- options is one or more command line options for the **rsync** command
- sshoptions is one or more command line options for the ssh command
- source is the source path in POSIX format (see section 7.3); do not use \ to escape spaces in the source path
- accountname is the account name to connect with, in Cygwin format (see section 7.2)
- *hostname* is the remote computer name
- *dest* is the destination path in POSIX format (see section 7.3); escape spaces in the destination path using \undersup unless using **rsync**'s **-s** option (recommended)

Example command 1:

```
rsync -lrstvz -e "ssh" "/cygdrive/c/Users/KenDyer/Backup Files/"
   "KenDyer@computer3:/cygdrive/c/Users/KenDyer/Backup Files"
```

(All on one line) This command replicates the C:\Users\KenDyer\Backup Files directory to the same path on computer3 using the KenDyer account.

Example command 2:

```
rsync -lrstvz -e "ssh -i /cygdrive/c/Users/filerepl/.ssh/ed25519"
  "/cygdrive/c/ProgramData/App Name/"
  "filerepl@server2:/cygdrive/c/ProgramData/App Name"
```

(All on one line) This command replicates the directory C:\Program Data\App Name to the computer server2 using the filerepl account. Note the use of a private key file, specified as a POSIX path (see section 7.3).

Note that the source path in the example commands uses a trailing / to prevent creating a new directory in the destination path.

See appendix C for a link to **rsync**'s documentation.

Appendix C: Documentation Links

OpenSSH - https://www.openssh.com/manual.html

 $\pmb{Cygwin} - https://www.cygwin.com/cygwin-ug-net/cygwin-ug-net.html$

rsync - https://rsync.samba.org/documentation.html

Inno Setup - http://www.jrsoftware.org/ishelp/

Appendix D: Windows PowerShell Scripts

The following list describes the Windows PowerShell scripts provided by the CygSSH package.

Edit-SSHKey.ps1 - Updates a private key file's comment or passphrase (see section 6.2.2)

Get-AccountName.ps1 - Outputs an account's name in both Cygwin and Windows format (see section 7.2)

New-SSHKey.ps1 - Creates a key pair (see section 6.2.1)

Set-FstabConfig.ps1 - Used by the installer to create a default fstab file (see section 7.1)

Set-SSHGroup.ps1 - Used by the installer to create the local access group and update the sshd_config file (see section 5.1)*

Set-SSHHostKey.ps1 - Used by the installer to create the OpenSSH server host keys (see section 6.1)*

Set-SSHService.ps1 - Used by the installer to install, start, stop, and uninstall the OpenSSH server service*

* Only installed when setup type is **full** (see section 1.4)

Note: Use the Get-Help cmdlet to get online help information for any of the PowerShell scripts.

Appendix E: Acknowledgments

Special thanks to the authors of the following software packages for their generous contributions:

Cygwin - https://www.cygwin.com/

OpenSSH - https://www.openssh.com/

winpty - https://github.com/rprichard/winpty/

rsync - https://rsync.samba.org/

Inno Setup - http://www.jrsoftware.org/

Halibut - https://www.chiark.greenend.org.uk/~sgtatham/halibut/

PathMgr.dll - https://github.com/Bill-Stewart/PathMgr/

Appendix F: License Agreements

This package contains software from multiple sources:

- Cygwin https://www.cygwin.com/licensing.html
- **OpenSSH** https://cvsweb.openbsd.org/src/usr.bin/ssh/LICENCE?rev=HEAD
- **rsync** https://rsync.samba.org/GPL.html
- winpty https://github.com/rprichard/winpty/blob/master/LICENSE
- **PathMgr.dll** https://github.com/Bill-Stewart/PathMgr/
- UninsIS.dll https://github.com/Bill-Stewart/UninsIS/

See appendix G for source code availability for software components that require making the source code available.

Windows PowerShell Script License

In addition to the above, the package contains a set of Windows PowerShell scripts written by Bill Stewart that are used for installing and managing the software. The Windows PowerShell scripts are covered by the MIT license:

Copyright © 2019-2023 by Bill Stewart.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Appendix G: Open Source Source Code

Some of the software components used by the CygSSH package have a license that requires the agent (a person or organization) who distributes the software to provide the source code for the software being distributed.

To meet this requirement for the CygSSH package, a zip file archive of the source code for the included software components covered by this kind of license is available at the following URL:

https://github.com/Bill-Stewart/CygSSH/tree/master/usr/src

From that page, do the following:

- 1. Click the **History** button to view the history of the **src** directory.
- 2. Click the **View at this point in the history** button for the desired version to view the **src** directory for that version.
- 3. Click the **source.zip** file to download that version of the source code files.

The source code is generally of interest only to developers.

Appendix H: Version History

9.4.1 (2023-08-10)

• Updated to OpenSSH 9.4p1-1 and latest Cygwin packages.

9.3.2 (2023-07-27)

- Updated to OpenSSH 9.3-p2-1 and latest Cygwin packages.
- Corrected installer bug: PathMgr.dll file not installed in per-user installation.
- Corrected installer bug: cygserver files installed in per-user installation.

9.3 (2023-03-28)

• Installer version synchronized with OpenSSH version.

9.2.3.0 (2023-02-04)

• Updated to OpenSSH 9.2 and latest packages (Cygwin, etc.).

3.0 (2022-12-06)

- Updated to OpenSSH 9.1, Cygwin 3.4, and rsync 3.2.7.
- Removed 32-bit and downlevel OS support.
- Removed downloadsource task.
- Minor tweaks.

2.2 (2022-08-11)

- Updated to OpenSSH 9.0.
- Updated Cygwin and Cygwin packages.

2.2 (2022-03-29)

- Updated to OpenSSH 8.9.
- Updated Cygwin packages.
- Uninstall fix: Only delete **PathMgr.dll** when package is uninstalled.

2.1 (2022-01-20)

• Updated Cygwin packages.

 Fix: Avoid multiple downloads of source code if downloadsource task is selected and user navigates backward then forward through setup wizard.

2.0 (2021-11-01)

- Updated to OpenSSH 8.8.
- Updated Cygwin packages.
- Added downloadsource installer task to download the source code during the installation process (see section 1.6).
- Added optional resetconfig installer task to reset the ssh_config and/or sshd_config files.
- Added support for /FORCEUNINSTALL installer command-line parameter (see chapter 1 and section 2.2).
- Updated installer to use more secure permissions for the usr and tmp directories.
- Added elevation check to Set-FstabConfig.ps1 and Set-SSHHostKey.ps1.
- Changed permission update commands to use the Windows icacls command.
- Moved automatic executable detection to a more appropriate stage in the install process.

1.7 (2021-03-12)

- Updated Cygwin packages.
- Installer behavior change: If adding to the Path is selected, the installer will add to the beginning of the Path rather than the end. This change was made because newer versions of Windows have OpenSSH client utilities in the system Path by default that can cause compatibility problems with the Cygwin programs. (Note that this change will not be effective if installing in non-administrative installation mode because the directories in the system Path always appear before the current user Path.)
- Removed clickable hyperlinks in RTF documents displayed by the installer to prevent accidental launching of an
 elevated browser.

1.6 (2021-03-05)

• Updated to OpenSSH 8.5 and mintty 3.4.6.

1.6 (2021-02-04)

- Dropped support for Windows Vista/Windows Server 2008 to increase the security of the installer.
- · Updated Cygwin packages.
- Updated installer to use **PathMgr.dll** for system/user Path management.
- Updated PowerShell scripts to avoid informational messages from PowerShell parsers and to improve readibility.
- Fixed typo in New-SSHKey.ps1 script that caused an error message "Bits has bad value 0 (too small)".
- Updated documentation to mention addition of Windows firewall rule addition and fixed some typos.

1.5

Added missing DLLs that broke rsync.

1.4

- Updated OpenSSH to version 8.4.
- Updated rsync to version 3.2.3.
- Updated Cygwin and associated packages.
- Added default nanorc configuration file.

1.3

- Updated Cygwin and associated packages.
- Updated runposh tool to 1.3 (compile using FPC 3.2.0).
- Installer tweak: Clean \usr\share and \usr\src directories when installing.
- Package standardization: Installed application version matches installer version.

1.2

- Updated OpenSSH to version 8.3.
- Added mkgroup, mkpasswd, and ssh-pageant tools.
- Updated **runposh** tool to version 1.2.
- Added default cygserver.conf and virc configuration files.

1.1

- Updated OpenSSH service not to use the Windows ConPTY API calls in newer versions of Windows by setting the disable_pcon setting in the CYGWIN environment variable. (The CygSSH package doesn't need the ConPTY support since it uses winpty.) See https://cygwin.com/cygwin-ug-net/using-cygwinenv.html for details.
- Added recommendation to run **ssh** and **sftp** using **mintty**.
- Updated **runposh** tool to version 1.1.

1.0

Initial version.

Index

Access Control List (ACL)	12, 18	icons	5
access group, local	11	Inno Setup	4, 22
account names, Cygwin	18	installation, client	5
acknowledgments	24	installation, full	5
Active Directory	11	installer additional taks	6
additional tasks (installer)	6	installer setup type	5
AllowGroups setting	11	installpath	5
AllowTcpForwarding setting	13	install, silent	4
AuthenticationMethods setting	14	interactive shell	9
authentication, public key	15	jail (chroot)	20
authorized_keys file	13	key comment	17
case-sensitive account names	19	key pairs	15
chroot	20	key passphrase	17
ChrootDirectory setting	13, 20	known_hosts file	9, 15
chroot jail	20	license agreements	25
client installation	5	links, documentation	22
/CLOSEAPPLICATIONS parameter	4, 7	local access group	11
comment, key	17	Match User setting	14
ConPTY	29	mintty	9, 29
cryptography, public key	15	modifypath installer task	6
/CURRENTUSER parameter	4, 5, 6	New-SSHKey.ps1	16, 23
cygdrive directory (SFTP-only)	14	noacl option (fstab file)	18
cygpath command	19	non-administrative install mode	4
Cygwin	18, 22	nsswitch.conf file	19
Cygwin account names	18	open source	26
CYGWIN environment variable	29	OpenSSH	22
dev directory (SFTP-only)	14	passphrase, key	17
disable_pcon	29	passwd file	20
documentation links	22	password authentication, using	11
Edit-SSHKey.ps1	17, 23	path (environment variable)	6
emulation	18	path names, POSIX	19
firewall	4	permissions	12, 18
ForceCommand setting	13	POSIX	18
/FORCEUNINSTALL parameter	4, 28	POSIX path names	19
fstabfile	18	PowerShell scripts	23
full installation	5	.ppk file	17
Get-AccountName.ps1	19, 23	private key	15
Group Policy (GPO)	11	privsep account	20
home directory	19	. pub file	16
host keys	15	public key	15
icacls	12	public key authentication	15

public key authentication, using	12
public key cryptography	15
PuTTY	10
PuTTYgen	16
release history	27
root user account	20
rsync	18, 21, 22
scp command	9
service, start	6
Set-FstabConfig.ps1	23
Set-SSHGroup.ps1	23
Set-SSHHostKey.ps1	23
Set-SSHService.ps1	23
setup type (installer)	5
sftp command	9
SFTP-only	13
shell (interactive)	9
shortcuts	5
silent install	4
/SILENT parameter	4, 7
silent uninstall	8
source code	26
ssh command	9
ssh_config file	6
sshd account	4, 8, 20
sshd_config file	4, 6, 11, 13
.ssh directory	9, 12, 13
ssh-keygen command	16
SSH Users (local access group)	11
Start menu	5
startservice installer task	6
/SUPPRESSMSGBOXES parameter	4
system Path	6
system requirements	4
uninstall	8
user Path	6
using password authentication	11
using public key authentication	12
version history	27
Windows PowerShell scripts	23
WinSCP	10