RD-Analyzer 4/8/2016

# **RD-Analyzer**

*In silico* region of difference (RD) analysis of *Mycobacterium tuberculosis* complex from sequence reads

#### **Files**

**RD-Analyzer.py:** the standard RD-Analyzer used for deletion prediction of previously defined RD markers and strain identification of *Mycobacterium tuberculosis* complex based on these markers.

**RD-Analyzer-extended.py:** the extended RD-Analyzer used for deletion prediction of user-specified RD sequences.

**Reference/RDs30.fasta:** sequences of previously defined RD markers used in the standard RD-Analyzer.

**Reference/Lineage4.fasta:** sequences of potential Lineage 4 markers identified in the manuscript.

### **Prerequisite**

Python 2.7

# Standard RD-Analyzer

#### Usage:

```
1. python2.7 RD-Analyzer.py [options] FASTQ_1 FASTQ_2(optional)
```

#### **Options:**

```
--version
                         show program version number and exit
       -h, --help
                         show this help message and exit
3.
       -d, --debug
                         enable debug mode, keeping all intermediate files
5.
       -O OUTDIR, --outdir=OUTDIR
             output directory [Default: running directory]
6.
       -o OUTPUT, --output=OUTPUT
             basename of output files [Default: RD-Analyzer]
       -p, --personalized
             use personalized cut-offs
       -m MIN, --min=MIN
             read depth cut-off (in the unit of average depth, 0-1), used when '-p' is
       set
       -c COVERAGE, --coverage=COVERAGE
14.
             sequence coverage cut-off (0-1), used when '-p' is set
```

#### Suggestions:

RD-Analyzer 4/8/2016

Users are suggested to use the default cut-offs which are optimized by us.

## **Extended RD-Analyzer**

#### Usage:

```
1. python2.7 RD-Analyzer-extended.py [options] REF.FASTA FASTQ_1 FASTQ_2(optional)
```

#### **Options:**

```
    --version show program version number and exit
    -h, --help show this help message and exit
    -d, --debug enable debug mode, keeping all intermediate files
    -0 OUTDIR, --outdir=OUTDIR

            output directory [Default: running directory]

    -0 OUTPUT, --output=OUTPUT

            basename of output files [Default: RD-Analyzer]
```

#### Input files:

REF.FASTA - Reference sequences used should be in a fasta file with the header lines prepared as below:

- Four fields are reuiqred in the header line, which should be separated with '-'.
- Field one: reference sequence name
- Filed two: read-depth cutoff to be used (in the unit of average depth, in a 0-1 scale). Specify 'default' if want to use default parameters (0.09)
- Field three: sequence coverage cut-off (in a 0-1 scale). Specify 'default' if want to use default parameters (0.5)
- Flled four: descriptive information of the RD to be shown if the RD is detected.
- An example header line: >Lineage4.6.1.2/1-default-default-Lineage4.6.1.2/1
- Notice: 1. Don't include space in the header file. 2. Don't use '-' unless as filed deliminator