Blotch3D

Generated by Doxygen 1.8.14

Contents

1	Blot	CH3D	1
	1.1	Quick start	1
	1.2	Introduction	1
	1.3	Project structure	3
	1.4	Development	3
	1.5	Making 3D models	5
	1.6	Dynamically changing a sprite's orientation and position	5
	1.7	Matrix internals	6
	1.8	A Short Glossary of 3D Graphics Terms	9
	1.9	Troubleshooting	10
	1.10	Rights	10
2	Nam	nespace Index	11
	2.1	Packages	11
3	Hiera	archical Index	13
	3.1	Class Hierarchy	13
4	Clas	s Index	15
	4.1	Class List	15
5	Nam	espace Documentation	17
	5.1	Blotch Namespace Reference	17

ii CONTENTS

6	Clas	s Docui	mentation		19
	6.1	Blotch.	BIGraphics	DeviceManager Class Reference	19
		6.1.1	Detailed I	Description	22
		6.1.2	Construct	or & Destructor Documentation	22
			6.1.2.1	BIGraphicsDeviceManager()	22
		6.1.3	Member F	Function Documentation	23
			6.1.3.1	AdjustCameraDolly()	23
			6.1.3.2	AdjustCameraPan()	23
			6.1.3.3	AdjustCameraRotation()	23
			6.1.3.4	AdjustCameraTruck()	24
			6.1.3.5	AdjustCameraZoom()	24
			6.1.3.6	CalculateRay()	24
			6.1.3.7	CloneTexture2D()	25
			6.1.3.8	Dispose()	25
			6.1.3.9	DoDefaultGui()	25
			6.1.3.10	DrawText()	26
			6.1.3.11	DrawTexture()	27
			6.1.3.12	ExtendClippingTo()	27
			6.1.3.13	GetWindowCoordinates()	27
			6.1.3.14	Initialize()	28
			6.1.3.15	LoadFromImageFile()	28
			6.1.3.16	PrepareDraw()	28
			6.1.3.17	ResetCamera()	29
			6.1.3.18	SetCameraRollToZero()	29
			6.1.3.19	SetCameraToSprite()	29
			6.1.3.20	SetSpriteToCamera()	29
			6.1.3.21	TextToTexture()	30
		6.1.4	Member I	Data Documentation	30
			6.1.4.1	AmbientLightColor	30
			6.1.4.2	Aspect	30

CONTENTS

	6.1.4.3	AutoRotate	31
	6.1.4.4	CameraSpeed	31
	6.1.4.5	CameraUp	31
	6.1.4.6	ClearColor	31
	6.1.4.7	DefGuiMaxLookZ	31
	6.1.4.8	DefGuiMinLookZ	31
	6.1.4.9	DepthStencilStateDisabled	32
	6.1.4.10	DepthStencilStateEnabled	32
	6.1.4.11	FarClip	32
	6.1.4.12	FogColor	32
	6.1.4.13	fogEnd	33
	6.1.4.14	fogStart	33
	6.1.4.15	FramePeriod	33
	6.1.4.16	IsDisposed	33
	6.1.4.17	Lights	33
	6.1.4.18	NearClip	33
	6.1.4.19	Projection	34
	6.1.4.20	SpriteBatch	34
	6.1.4.21	TargetEye	34
	6.1.4.22	TargetLookAt	34
	6.1.4.23	View	34
	6.1.4.24	Window	34
	6.1.4.25	Zoom	35
6.1.5	Property	Documentation	35
	6.1.5.1	CameraForward	35
	6.1.5.2	CameraForwardMag	35
	6.1.5.3	CameraForwardNormalized	35
	6.1.5.4	CameraRight	35
	6.1.5.5	CurrentAspect	36
	6.1.5.6	CurrentFarClip	36

iv CONTENTS

		6.1.5.7	CurrentNearClip	 	36
		6.1.5.8	Eye	 	36
		6.1.5.9	LookAt	 	36
		6.1.5.10	MaxCamDistance	 	36
		6.1.5.11	MinCamDistance	 	37
6.2	Blotch.	.BIGuiCont	trol Class Reference	 	37
	6.2.1	Detailed	Description	 	38
	6.2.2	Member	Function Documentation	 	38
		6.2.2.1	HandleInput()	 	38
		6.2.2.2	OnMouseChangeDelegate()	 	38
	6.2.3	Member	Data Documentation	 	38
		6.2.3.1	OnMouseOver	 	38
		6.2.3.2	Position	 	39
		6.2.3.3	PrevMouseState	 	39
		6.2.3.4	Texture	 	39
		6.2.3.5	Window	 	39
6.3	Blotch.	.BIMipmap	Class Reference	 	39
	6.3.1	Detailed	Description	 	40
	6.3.2	Construc	ctor & Destructor Documentation	 	40
		6.3.2.1	BIMipmap()	 	40
	6.3.3	Member	Function Documentation	 	41
		6.3.3.1	Dispose()	 	41
	6.3.4	Member	Data Documentation	 	41
		6.3.4.1	IsDisposed	 	41
6.4	Blotch.	.BISprite C	Class Reference	 	41
	6.4.1	Detailed	Description	 	45
	6.4.2	Member	Enumeration Documentation	 	45
		6.4.2.1	PreDrawCmd	 	45
		6.4.2.2	PreLocalCmd	 	46
		6.4.2.3	PreMeshDrawCmd	 	46

CONTENTS

	6.4.2.4	PreSubspritesCmd	46
6.4.3	Member	Function Documentation	46
	6.4.3.1	Add()	47
	6.4.3.2	CompareTo()	47
	6.4.3.3	Dispose()	47
	6.4.3.4	DoesRayIntersect()	47
	6.4.3.5	Draw()	48
	6.4.3.6	DrawCleanupType()	48
	6.4.3.7	FrameProcType()	48
	6.4.3.8	GetRayIntersections()	49
	6.4.3.9	GetViewCoords()	49
	6.4.3.10	NearestPointOnLine()	49
	6.4.3.11	PreDrawType()	50
	6.4.3.12	PreLocalType()	50
	6.4.3.13	PreMeshDrawType()	51
	6.4.3.14	PreSubspritesType()	51
	6.4.3.15	SetAllMaterialBlack()	51
6.4.4	Member	Data Documentation	51
	6.4.4.1	_FrameProc	52
	6.4.4.2	AbsoluteMatrix	52
	6.4.4.3	BoundSphere	52
	6.4.4.4	Color	52
	6.4.4.5	ConstSize	52
	6.4.4.6	CylindricalBillboardX	53
	6.4.4.7	CylindricalBillboardY	53
	6.4.4.8	CylindricalBillboardZ	53
	6.4.4.9	DrawCleanup	53
	6.4.4.10	EmissiveColor	53
	6.4.4.11	Flags	54
	6.4.4.12	FlagsParameter	54

vi

	6.4.4.13	Graphics	. 54
	6.4.4.14	IncludeInAutoClipping	. 54
	6.4.4.15	IsDisposed	. 54
	6.4.4.16	LastWorldMatrix	. 54
	6.4.4.17	LODs	. 55
	6.4.4.18	LodScale	. 55
	6.4.4.19	Matrix	. 55
	6.4.4.20	Mipmap	. 55
	6.4.4.21	MipmapScale	. 56
	6.4.4.22	Name	. 56
	6.4.4.23	PreDraw	. 56
	6.4.4.24	PreLocal	. 56
	6.4.4.25	PreMeshDraw	. 56
	6.4.4.26	PreSubsprites	. 56
	6.4.4.27	SpecularColor	. 57
	6.4.4.28	SpecularPower	. 57
	6.4.4.29	SphericalBillboard	. 57
6.4.5	Property	Documentation	. 57
	6.4.5.1	ApparentSize	. 57
	6.4.5.2	CamDistance	. 57
	6.4.5.3	FrameProc	. 58
	6.4.5.4	LodTarget	. 58
	6.4.5.5	VerticesEffect	. 58
Blotch.	BlWindow	3D Class Reference	. 58
6.5.1	Detailed	Description	. 60
6.5.2	Construc	ctor & Destructor Documentation	. 60
	6.5.2.1	BIWindow3D()	. 60
6.5.3	Member	Function Documentation	. 60
	6.5.3.1	Command()	. 60
	6.5.3.2	Dispose()	. 60
	Blotch. 6.5.1 6.5.2	6.4.4.14 6.4.4.15 6.4.4.16 6.4.4.17 6.4.4.18 6.4.4.19 6.4.4.20 6.4.4.21 6.4.4.22 6.4.4.23 6.4.4.24 6.4.4.25 6.4.4.25 6.4.4.26 6.4.4.27 6.4.4.28 6.4.4.29 6.4.5.1 6.4.5.2 6.4.5.3 6.4.5.4 6.4.5.5 Blotch.BlWindow 6.5.1 Detailed 6.5.2 Construct 6.5.2.1 6.5.3 Member 6.5.3.1	6.4.4.14 IncludeInAutoClipping 6.4.4.15 IsDisposed 6.4.4.16 LastWorldMatrix 6.4.4.17 LODs. 6.4.4.18 LodScale 6.4.4.19 Matrix 6.4.4.20 Mipmap 6.4.4.21 MipmapScale 6.4.4.22 Name. 6.4.4.23 PreDraw 6.4.4.24 PreLocal 6.4.4.25 PreMeshDraw 6.4.4.26 PreSubsprites 6.4.4.27 SpecularColor 6.4.4.28 SpecularPower 6.4.4.29 SphericalBiliboard 6.4.5 Property Documentation 6.4.5.1 ApparentSize 6.4.5.2 CamDistance 6.4.5.3 FrameProc 6.4.5.4 LodTarget 6.4.5.5 VerticesEffect Blotch_BIWindow3D Class Reference 6.5.1 Detailed Description 6.5.2 Constructor & Destructor Documentation 6.5.2.1 BiWindow3D() 6.5.3 Member Function Documentation 6.5.3.1 Command()

CONTENTS vii

		6.5.3.3	Draw()	61
		6.5.3.4	EnqueueCommand()	61
		6.5.3.5	EnqueueCommandBlocking()	61
		6.5.3.6	FrameDraw()	61
		6.5.3.7	FrameProc()	62
		6.5.3.8	Initialize()	62
		6.5.3.9	LoadContent()	62
		6.5.3.10	Setup()	62
		6.5.3.11	Update()	62
	6.5.4	Member	Data Documentation	63
		6.5.4.1	FrameProcSprites	63
		6.5.4.2	Graphics	63
		6.5.4.3	GuiControls	63
		6.5.4.4	IsDisposed	63
6.6	Blotch.	BIGraphic	sDeviceManager.Light Class Reference	64
	6.6.1	Detailed	Description	64

Chapter 1

Blotch3D

Create real-time 3D graphics with just a few lines of C# code.

1.1 Quick start

- 1. Get the installer for the latest release of MonoGame from http://www.monogame.net/downloads/and run it. (Do NOT get the current development version nor the NuGet package.)
- 2. Get the Blotch3D repository zip from https://github.com/Blotch3D/Blotch3D and unzip it.
- 3. Open the Visual Studio solution file (Blotch3D.sln).
- 4. Build and run the example projects. (For other platforms, you'll need the appropriate Visual Studio add-on and you will need to create a separate project for that platform.)
- 5. Use IntelliSense to see the reference documentation, or view the Doxygen output of it in "Blotch3D_ \leftarrow Reference_Manual.pdf".

1.2 Introduction

Blotch3D is a C# library that vastly simplifies many of the tasks in developing 3D applications and games.

Examples are provided that show how with just a few lines of code you can...

- Load standard 3D model file types as "sprites", and display and move thousands of them in 3D at high frame rates.
- · Set a sprite's material, texture, and lighting response.
- · Load textures from standard image files.
- Show 2D and in-world (as a texture) text in any font, size, color, etc. at any 2D or 3D position, and make text follow a sprite in 2D or 3D.
- Attach sprites to other sprites to create 'sprite trees' as large as you want. Child sprite orientation and position
 is relative to its parent sprite's orientation and position, and can be changed dynamically (i.e. the sprite trees
 are dynamic scene graphs.)
- Override all steps in the drawing of each sprite.

2 Blotch3D

• You can give the user easy control over all aspects of the camera (zoom, pan, truck, dolly, rotate, etc.).

- · Easily control all aspects of the camera programmatically.
- · Create billboard sprites.
- · Connect sprites to the camera to implement HUD models and text.
- · Connect the camera to a sprite to implement 'cockpit view', etc.
- Implement GUI controls (as dynamic 2D text or image rectangles) in the 3D window.
- · Implement a skybox.
- Get a list of sprites touching a ray, to implement weapons fire, etc.
- · Get a list of sprites under the mouse position, to implement mouse selection, tooltips, pop-up menus, etc.
- · Implement levels-of-detail.
- · Implement mipmaps.
- Implement translucent sprites and textures with an alpha channel.
- Create sprite models programmatically (custom vertices).
- · Use with WPF and WinForms, on Microsoft Windows.
- Access and override many window features and functions using the provided WinForms Form object of the window (Microsoft Windows only).
- · Detect collisions between sprites.
- · Implement fog
- Define ambient lighting, and up to three point-light sources. (More lights can be defined if a custom shader is used.)
- Build for many platforms (currently supports all Microsoft Windows platforms, iOS, Android, MacOS, Linux, PS4, PSVita, Xbox One, and Switch).

Blotch3D sits on top of MonoGame. MonoGame is a widely used 3D library for C#. It is free, fast, cross platform, actively developed by a large community, and it's used in many professional games. There is a plethora of Mono \leftarrow Game documentation, tutorials, examples, and discussions on line. All MonoGame features remain available. For example, custom shaders can be written to override the default shader.

All reference documentation of Blotch3D (classes, methods, fields, properties, etc.) is available through Visual Studio IntelliSense, and it is also available in Doxygen output file "Blotch3D_Reference_Manual.pdf". (Note: To support Doxygen, links in the IntelliSense comments are preceded with '#'. Also, this document is prepended to that Doxygen output, but for some reason the reference links within this document don't work when it is embedded in that reference manual.)

See MonoGame.net for the official MonoGame documentation. When searching on-line for other MonoGame documentation and discussions, be sure to note the MonoGame version being discussed. Documentation of earlier versions may not be compatible with the latest.

MonoGame fully implements Microsoft's (no longer supported) XNA 4 engine, but for multiple platforms. It also implements features beyond XNA 4. Therefore XNA 4 documentation you come across may not show you the best way to do something, and documentation of earlier versions of XNA (versions 2 and 3) will often not be correct. For conversion of XNA 3 to XNA 4 see http://www.nelsonhurst. \leftarrow com/xna-3-1-to-xna-4-0-cheatsheet/.

Note that to support all the platforms, certain limitations were necessary. Currently you can only have one 3D window. Also, there is no official cross-platform way to specify an existing window to use as the 3D window—MonoGame must create it. See below for details and work-arounds.

1.3 Project structure 3

1.3 Project structure

The provided Visual Studio solution file contains both the Blotch3D library project with source, and the example projects.

"BlotchExample01_Basic" is a bare-bones Blotch3D application, where Example.cs contains the example code. Other example projects also contain an Example.cs, which is similar to the one from the basic example but with a few additions to it to demonstrate a certain feature. In fact, you can do a diff between the "BlotchExample01_Basic" source file and another example's source file to see what extra code must be added to implement the features it demonstrates [TBD: the "full" example needs to be split to several simpler examples].

All the provided projects are configured to build for the Microsoft Windows x64 platform. See below for other platforms.

To create a new project, you can just copy the basic example and rename the project, or you can create the project from scratch like this:

- 1. If you haven't already done it, install MonoGame as described in the Quick start section.
- 2. If you are building for a platform other than Microsoft Windows, install the Visual Studio add-ons, etc. for that platform. (For example, for Android you'd need Xamarin for Android.)
- 3. Create a new project for a platform that is compatible with MonoGame.
- 4. Add a reference to MonoGame. (For .NET Framework, you would add something like \Program Files (x86)\MonoGame\v3.0\Assemblies\Windows\MonoGame.Framework.dll)
- 5. If the Blotch3D project is not in the solution, add a reference to the Blotch3D assembly (like Blotch3D.dll on Microsoft Windows).
- 6. Follow the procedure in the 'Making 3D models' section to add a content folder and the pipeline manager so that you have a way to add content.
- 7. You'll probably want to set the output type to 'Console Application' for now, so you can see any debug messages. You can change this to 'Windows Application' later, if you like.
- 8. To create a 3D window, follow the guidelines in the Development section.

The above process works for Microsoft Windows. Generally this should be close to the procedure you need for other platforms.

If you are copying the Blotch3D assembly (like Blotch3D.dll on Microsoft Windows) to a project or packages folder so you don't have to include the source code of the library in your solution, be sure to also copy Blotch3D.xml so you still get the IntelliSense. You shouldn't have to copy any other binary file from the Blotch3D output folder if you've installed MonoGame on the destination machine. Otherwise you should copy the entire project output folder. For example, you'd probably want to copy everything in the output folder when you are distributing your app.

1.4 Development

See the examples.

To make a 3D window, you must derive a class from BlWindow3D and override the Setup, FrameProc, and Frame← Draw methods.

When it comes time to open the 3D window, you instantiate that class and call its "Run" method *from the same thread* that instantiated it. The Run method will call the Setup, FrameProc, and FrameDraw methods when appropriate (explained below), and not return until the window closes.

4 Blotch3D

The thread that instantiates the BlWindow3D-derived class, calls the Run method, etc., we will call the "3D thread".

All code that accesses 3D resources must be done in the 3D thread, including code that creates and uses all Blotch3D and MonoGame objects. Note that this rule also applies to any code structure that may internally use other threads, as well. Do not use Parallel, async, etc. code structures that access 3D resources.

This pattern and these rules are also used by MonoGame. In fact, the BlWindow3D class inherits from Mono ← Game's "Game" class. But instead of overriding certain "Game" class methods, you override BlWindow3D's Setup, FrameProc, and FrameDraw methods. Other "Game" class methods and events can still be overridden, if needed.

All this is necessary because certain 3D subsystems (OpenGL, DirectX, etc.) generally require that 3D resources be accessed by a single thread. (There are some platform-specific exceptions, but MonoGame does not use them.)

The Setup, FrameProc, and FrameDraw override methods are called by the 3D thread as follows:

The Setup method is called by the 3D thread once at the beginning of instantiation of the BlWindow3D-derived object. You might put time-consuming initialization of persistent things in there like loading of persistent content (sprite models, fonts, etc.), creation of persistent BlSprites, etc.

The FrameProc method is called by the 3D thread once per frame. For single-threaded applications this is typically where the bulk of application code resides, except the actual drawing code. For multi-threaded applications, this is where all application code resides that does anything with 3D resources.

The FrameDraw method is called by the 3D thread every frame, but only if there is enough CPU for the thread. Otherwise it calls it less frequently. This is where you put drawing code (BISprite.Draw, BIGraphicsDeviceManager.← DrawText, etc. You can also put app code here as long as it's aware that calls to it may not be periodic.

A single-threaded application would have all its code in those three overridden methods.

If you are developing a multithreaded app, then when other threads need to create, change, or destroy 3D resources or otherwise do something in a thread-safe way with the 3D thread, they can pass a delegate to EnqueueCommand or EnqueueCommandBlocking. Those methods make sure the code is done by the 3D thread sequentially at the end of the next FrameProc call.

MonoGame does not support multiple 3D windows because that isn't conducive on certain platforms. On Microsoft Windows (and possibly certain other platforms) you *can* create them, but they don't work correctly and in certain situations will crash. If you want to be able to "close" and "re-open" a window, you can just hide and show the same window. (On Microsoft Windows, you can use the BlWindow3D.Form object for that.)

To make the MonoGame window be a child window of an existing GUI, you need to explicitly size, position, and convey Z order so that it is overlaid at the right screen location. The easiest way to do that would be to overlay the 3D window on an existing child window by getting the current attributes of that child window, whenever they change. On Microsoft Windows, the window's Form object (BIWindow3D.Form) may be of help in this. There may also be a way to specify that an existing window be used as the 3D window, but it probably isn't portable and may not work in later MonoGame releases.

Most Blotch3D objects must be Disposed when you are done with them and you are not otherwise terminating the program.

See the examples and use IntelliSense for more information.

1.5 Making 3D models 5

1.5 Making 3D models

There are several primitive models available with Blotch3D. The easiest way to add them to your project is to...

- 1. Copy the Content folder from the Blotch3D project folder to your project folder
- 2. Add the "Content.mgcb" file in that folder to your project
- 3. Right-click it and select "Properties"
- 4. Set the "Build Action" to "MonoGameContentReference"

You can get the names of the content files by starting the MonoGame pipeline manager (double-click Content/← Content.mgcb). You can also add more content via the pipeline manager (see http://rbwhitaker.← wikidot.com/monogame-managing-content). See the examples for details on how to load and display models, fonts, etc.

If no existing model meets your needs, you can either programmatically create a model by specifying the vertices and normals (see the example that uses custom Vertices), or create a model with, for example, the Blender 3D modeler and then add it to the project with the pipeline manager. The pipeline manager can import several model file types. You can also instruct Blender to include texture (UV) mapping by using one of the countless tutorials online, like $\frac{\text{https:}}{\text{www.youtube.com/watch?v=2xTzJIaKQFY}} \text{ or } \frac{\text{https:}}{\text{https:}} = \frac{\text{https:}}{\text{models from the web.}}$

1.6 Dynamically changing a sprite's orientation and position

Each sprite has a "Matrix" member that defines its orientation and position relative to its parent sprite, or to an unmodified coordinate system if there is no parent. There are many static and instance methods of the Matrix class that let you easily set and change the scaling, translation, rotation, etc. of a matrix.

When you change anything about a sprite's matrix, you also change the orientation and position of its child sprites, if any. That is, subsprites reside in the parent sprite's coordinate system. For example, if a child sprite's matrix scales it by 3, and its parent sprite's matrix scales by 4, then the child sprite will be scaled by 12. Likewise, rotation, shear, and translation are inherited, as well.

There are also static and instance Matrix methods and operator overloads to combine (multiply) matrices to form a single matrix which combines the effects of multiple matrices. For example, a rotate matrix and a scale matrix can be multiplied to form a single rotate-scale matrix. But mind the multiplication order because matrix multiplication is not commutative. See below for details, but novices can simply try the operation one way (like A times B) and, if it doesn't work the way you wanted, do it the other way (B times A).

For a good introduction (without the math), see http://rbwhitaker.wikidot.com/monogame-basic-matrices.

The rest of this section should be studied only when you need a deeper knowledge.

6 Blotch3D

1.7 Matrix internals

Here we'll introduce the internals of 2D matrices. 3D matrices simply have one more dimension.

Let's imagine a model that has one vertex at (4,1) and another vertex at (3,3). (This is a very simple model comprised of only two vertices!)

You can move the model by moving each of those vertices by the same amount, and without regard to where each is relative to the origin. To do that, just add an offset vector to each vertex. For example, we could add the vector (2,1) to each of those original vertices, which would result in final model vertices of (6,2) and (5,4). In that case we have *translated* (moved) the model.

Matrices certainly support translation. But first let's talk about moving a vertex *relative to its current position from the origin*, because that's what gives matrices the power to shear, rotate, and scale a model about the origin. This is because those operations affect each vertex differently depending on its relationship to the origin.

If we want to scale (stretch) the X relative to the origin, we can multiply the X of each vertex by 2.

For example,

X' = 2X (where X is the initial value, and X' is the final value)

... which, when applied to each vertex, would change the above vertices from (4,1) and (3,3) to (8,1) and (6,3).

We might want to define how to change each X according to the original X value of each vertex and also according to the original Y value, like this:

$$X' = aX + bY$$

For example, if a=0 and b=1, then this would set the new X of each vertex to its original Y value.

Finally, we might also want to define how to create a new Y for each vertex according to its original X and original Y. So, the equations for both the new X and new Y are:

$$X' = aX + bY$$

$$Y' = cX + dY$$

(Remember, the idea is to apply this to every vertex.)

By convention we might write the four matrix elements (a, b, c, and d) in a 2x2 matrix, like this:

a b

c d

This should all be very easy to understand.

But why are we even talking about it? Because now we can define the elements of a matrix that, if applied to each vertex of a model, define any type of *transform* in the position and orientation of that model.

For example, if we apply the following matrix to each of the model's vertices:

10

0 1

...then the vertices are unchanged, because...

1.7 Matrix internals 7

X' = 1X + 0Y

Y' = 0X + 1Y

...sets X' to X and Y' to Y.

This matrix is called the *identity* matrix because the output (X',Y') is the same as the input (X,Y).

We can create matrices that scale, shear, and even rotate points. To make a model three times as large (relative to the origin), use the matrix:

30

03

To scale only X by 3 (stretch a model in the X direction about the origin), then use the matrix:

30

0 1

The following matrix flips (mirrors) the model vertically about the origin:

10

0 -1

Below is a matrix to rotate a model counterclockwise by 90 degrees about the origin:

0 -1

10

Here is a matrix that rotates a model counterclockwise by 45 degrees about the origin:

0.707 -0.707

0.707 0. 707

Note that '0.707' is the sine of 45 degrees.

A matrix can be created to rotate any amount about any axis.

(The Matrix class provides functions that make it easy to create a rotation matrix from a rotation axis and angle, or pitch and yaw and roll, or something called a quaternion, since otherwise we'd have to call sine and cosine functions, ourselves, to create the matrix elements.)


Since we often also want to translate (move) points *without* regard to their current distances from the origin as we did at the beginning of this section, we add more numbers to the matrix just for that purpose. And since many mathematical operations on matrices work only if the matrix has the same number of rows as columns, we add more elements simply to make the rows and columns the same size. And since Blotch3D/MonoGame works in 3-space, we add even more numbers to handle the Z dimension. So, the final matrix size in 3D graphics is 4x4.

Specifically:

$$X' = aX + bY + cZ + d$$

$$Y' = eX + fY + gZ + h$$

Blotch3D



(i.e. multiply by a matrix inverse) matrices to, for example, solve for a matrix that was used in a previous matrix multiply, or otherwise isolate one operation from another. Welcome to linear algebra! We won't get in to how matrix multiplication and division specifically process the individual elements of the matrices because the Matrix class already provides those static or instance functions.

As was previously mentioned, each sprite has a matrix describing how that sprite and its children are transformed from the parent sprite's coordinate system. Specifically, Blotch3D does a matrix-multiply of the parent's matrix by the child's matrix to create the final matrix used to draw that child, and it is also used as the parent matrix for the subsprites of that child.

Because of confusion in coordinate system handedness (chirality), multiplication/division order, row vs. column notation (mathematicians use the opposite notation of that used by 3D graphics people), and the order of element storage in memory; on occasion it may be easier to try things one way and, if it doesn't work as expected, try it another way. But for details see http://seanmiddleditch.← com/matrices-handedness-pre-and-post-multiplication-row-vs-column-major-and-notations.

1.8 A Short Glossary of 3D Graphics Terms

Vertex\ A point in space. Typically, a point at which the line segments of a polygon meet. That is, a corner of a polygon. A corner of a model. Most visible models are described as a set of vertices. Each vertex can have a color, texture coordinate, and normal.

Polygon\ A visible surface described by a set of vertices that define its corners. A triangle is a polygon with three vertices, a quad is a polygon with four. One side of a polygon is a "face".

Ambient lighting\ A 3D scene has one ambient light setting. The intensity of ambient lighting on the surface of a polygon is unrelated to the orientation of the polygon or the camera.

Diffuse lighting\ Directional or point source lighting. You can have multiple directional or point light sources. Its intensity depends on the orientation of the polygon relative to the light.

Texture\ A 2D image applied to the surface of a model. For this to work, each vertex of the model must have a texture coordinate associated with it, which is an X,Y coordinate of the 2D bitmap image that should be aligned with that vertex. Pixels across the surface of a polygon are interpolated from the texture coordinates specified for each vertex.

Normal\ In mathematics, the word "normal" means a vector that is perpendicular to a surface. In 3D graphics, "normal" means a vector that indicates from what direction light will cause a surface to be brightest. Normally they would mean the same thing. However, by defining a normal at some angle other than perpendicular, you can somewhat cause the illusion that a surface lies at a different angle. Each vertex of a polygon has a normal vector associated with it and the brightness across the surface of a polygon is interpolated from the normals of its vertices. So, a single flat polygon can have a gradient of brightness across it giving the illusion of curvature. In this way a model composed of fewer polygons can still be made to look quite smooth.

X-axis\ The axis that extends right from the origin.

Y-axis\ The axis that extends forward from the origin.

Z-axis\ The axis that extends up from the origin.

Translation\ Movement. The placing of something at a different location from its original location.

Rotation\ The circular movement of each vertex of a model about the same axis.

Scale\ A change in the width, height, and/or depth of a model.

Shear (skew)\ A pulling of one side of a model in one direction, and the opposite side in the opposite direction, without rotation, such that the model is distorted rather than rotated. A parallelogram is a rectangle that has experienced shear. If you apply another shear along an orthogonal axis of the first shear, you rotate the model.

Yaw\ Rotation about the Y-axis

Pitch\ Rotation about the X-axis, after any Yaw has been applied.

Roll\ Rotation about the Z-axis, after any Pitch has been applied.

Euler angles\ The yaw, pitch, and roll of a model, applied in that order.

Matrix\ An array of 16 numbers that describes the position and orientation of a sprite. Specifically, a matrix describes a difference, or transform, in the orientation (coordinate system) of one model from another. See <code>Dynamically changing a sprite's orientation and position</code>.

Origin\ The center of a coordinate system. The point in the coordinate system that is, by definition, at (0,0).

Frame\ In this document, \'Frame\' means a complete still scene. It is analogous to a movie frame. A moving 3D scene is created by drawing successive frames—typically at about 15 to 60 times per second.

Depth buffer\ 3D systems must keep track of the depth of the polygon surface (if any) at each 2D pixel so that they know to draw the nearer pixel over the farther pixel in the 2D display. The depth buffer is an array with one element per 2D screen pixel, where each element is (typically) a 32-bit floating point value indicating the depth of the nearest polygon surface at that pixel. See 'near clip' and 'far clip'.

Near clipping plane (near clip)\ The distance from the camera at which a depth buffer element is equal to zero. Nearer surfaces are not drawn.

Far clipping plane (far clip)\ The distance from the camera at which a depth buffer element is equal to the maximum possible floating-point value. Farther surfaces are not drawn.

10 Blotch3D

1.9 Troubleshooting

Q: When I set a billboard attribute of a flat sprite (like a plane), I can no longer see it.\ A: Perhaps the billboard orientation is such that you are looking at the plane from the side or back. Try setting a rotation in the sprite's matrix (and make sure it doesn't just rotate it on the axis intersecting your eye point).

- Q: When I'm inside a sprite, I can't see it.\ A: By default, Blotch3D draws only the outside of a sprite. Try doing a "Graphics.GraphicsDevice.RasterizerState = RasterizerState.CullClockwise" (or set it to CullNone to see both the inside and outside) in the BISprite.PreDraw delegate, and set it back to CullCounterClockwise in the BISprite.

 DrawCleanup delegate.
- Q: I set a sprite's matrix so one of the dimensions has a scale of zero, but then the sprite becomes black.\ A: A sprite's matrix also affects its normals. By setting a dimension's scale to zero, you may have caused some of the normals to be zero'd out as well.
- Q: When I am zoomed-in a large amount, sprite and camera movement jumps.\ A: You are experiencing floating point precision errors in the positioning algorithms. About all you can do is "fake" being that zoomed in by, instead, moving the camera forward temporarily. Or simply don't allow zoom to go to that extreme.
- Q: Sometimes I see the polygons and parts polygons of sprites appear and disappear randomly as the camera or sprite moves.\ A: The floating-point precision limitation of the depth buffer can cause this. Try increasing your near clip and/or decreasing your far clip so the depth buffer doesn't have to cover so much dynamic range.
- Q: I have a sprite that I want to always be visible, but I think its invisible because its outside the depth buffer.\ A: Try doing a "Graphics.GraphicsDevice.DepthStencilState = Graphics.DepthStencilStateDisabled" in the BISprite.Pre Draw delegate, and set it back to DepthStencilStateEnabled in the BISprite.DrawCleanup delegate.

1.10 Rights

Blotch3D (formerly GWin3D) is Copyright © 1999-2018 by Kelly Loum

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, IN ← CLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Chapter 2

Namespace Index

2.1	Packag	es

Here are the packages with brief descriptions (if available):					
Blotch	17				

12 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Blotch.BlGuiControl	37
Dictionary	
Blotch.BISprite	41
Game	
Blotch.BIWindow3D	58
GraphicsDeviceManager	
Blotch.BlGraphicsDeviceManager	19
ICloneable	
Blotch.BlGraphicsDeviceManager	19
IComparable Comparable	
Blotch.BISprite	41
IDisposable	
Blotch.BIMipmap	
Blotch.BISprite	
Blotch.BlGraphicsDeviceManager.Light	64
List	
Blotch.BIMipmap	39

14 Hierarchical Index

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Blotch.BlGraphicsDeviceManager	
This holds everything having to do with an output device. BIWindow3D creates one of these for	
itself.	19
Blotch.BlGuiControl	
A 2D GUI control. To create a GUI control: instantiate one of these, set its initial Texture (remember to create it in the 3D thread context), window position, and delegate, and then add it to BIWindow3D::GuiControls. (Any member can be dynamically changed.) The texture will be displayed, and then each frame the mouse is over it the delegate will be called. The delegate typically would examine the current mouse state (Mouse.GetState()) and the PrevMouseState member to detect button changes, etc. and perform an action. The delegate is called in the context of the window's 3D thread after the BIWindow3D::FrameProc method. You can use BIGraphicsDeviceManager::TextToTexture to create a textual textures, or just load a texture from a content file. Remember to Dispose textures when you are done with them.	37
Blotch.BIMipmap	•
A mipmap of textures for a given BISprite. You could load this from an image file and then assign it to a BISprite::Mipmap. Note that this is a software mipmap (i.e. it isn't implemented in the 3D hardware). That is, only one resolution texture is used at time.	39
Blotch.BISprite	
A BISprite is a single 3D object. Each sprite can also hold any number of subsprites, so you can make a sprite tree (a scene graph). In that case the child sprites 'follow' the orientation and position of the parent sprite. That is, they exist in the coordinate system of the parent sprite. The location and orientation of a sprite in its parent's coordinate system is defined by the sprite's Matrix member. Subsprites, LODs, and Mipmap are NOT disposed when the sprite is disposed, so you can assign the same one to multiple sprites.	41
Blotch.BlWindow3D	
To make a 3D window, you must derive a class from BIWindow3D and override the Setup, FrameProc, and FrameDraw methods. When it comes time to open the 3D window, you instantiate that class and call its "Run" method from the same thread that instantiated it. The Run method will call the Setup, FrameProc, and FrameDraw methods when appropriate, and not return until the window closes. All code that accesses 3D resources must be done in that thread, including code that creates and uses all Blotch3D and MonoGame objects. Note that this rule also applies to any code structure that may internally use other threads, as well. Do not use Parallel, async, etc. code structures that access 3D resources. Other threads that need to access 3D resources can do so by passing a delegate to EnqueueCommand and EnqueueCommandBlocking	58
Blotch.BlGraphicsDeviceManager.Light	
Defines a light. See the Lights field. The default BasicShader supports up to three lights	64

16 Class Index

Chapter 5

Namespace Documentation

5.1 Blotch Namespace Reference

Classes

· class BIDebug

This static class holds the debug flags. Many flags are initialized according to whether its a Debug build or Release build. Some flags enable exceptions for probable errors, and many flags cause warning messages to be sent to the console window, if it exist. For this reason you should first test your app as a debug build console app.

· class BIGraphicsDeviceManager

This holds everything having to do with an output device. BIWindow3D creates one of these for itself.

class BlGuiControl

A 2D GUI control. To create a GUI control: instantiate one of these, set its initial Texture (remember to create it in the 3D thread context), window position, and delegate, and then add it to BIWindow3D::GuiControls. (Any member can be dynamically changed.) The texture will be displayed, and then each frame the mouse is over it the delegate will be called. The delegate typically would examine the current mouse state (Mouse.GetState()) and the PrevMouseState member to detect button changes, etc. and perform an action. The delegate is called in the context of the window's 3D thread after the BIWindow3D::FrameProc method. You can use BIGraphicsDeviceManager::TextToTexture to create a textual textures, or just load a texture from a content file. Remember to Dispose textures when you are done with them.

class BIMipmap

A mipmap of textures for a given BlSprite. You could load this from an image file and then assign it to a BlSprite::Mipmap. Note that this is a software mipmap (i.e. it isn't implemented in the 3D hardware). That is, only one resolution texture is used at time.

· class BISprite

A BISprite is a single 3D object. Each sprite can also hold any number of subsprites, so you can make a sprite tree (a scene graph). In that case the child sprites 'follow' the orientation and position of the parent sprite. That is, they exist in the coordinate system of the parent sprite. The location and orientation of a sprite in its parent's coordinate system is defined by the sprite's Matrix member. Subsprites, LODs, and Mipmap are NOT disposed when the sprite is disposed, so you can assign the same one to multiple sprites.

class BlWindow3D

To make a 3D window, you must derive a class from BIWindow3D and override the Setup, FrameProc, and FrameDraw methods. When it comes time to open the 3D window, you instantiate that class and call its "Run" method from the same thread that instantiated it. The Run method will call the Setup, FrameProc, and FrameDraw methods when appropriate, and not return until the window closes. All code that accesses 3D resources must be done in that thread, including code that creates and uses all Blotch3D and MonoGame objects. Note that this rule also applies to any code structure that may internally use other threads, as well. Do not use Parallel, async, etc. code structures that access 3D resources. Other threads that need to access 3D resources can do so by passing a delegate to EnqueueCommand and EnqueueCommandBlocking.


Chapter 6

Class Documentation

6.1 Blotch.BlGraphicsDeviceManager Class Reference

This holds everything having to do with an output device. BIWindow3D creates one of these for itself.

Inheritance diagram for Blotch.BlGraphicsDeviceManager:



Classes

· class Light

Defines a light. See the Lights field. The default BasicShader supports up to three lights.

Public Member Functions

- BlGraphicsDeviceManager (BlWindow3D window)
- · void Initialize ()

For internal use only. Apps should not normally call this. This initializes some values AFTER the BIWindow3D has been created.

void ExtendClippingTo (BISprite s)

Informs the auto-clipping code of an object that should be included in the clipping region. This is mainly for internal use. Application code should control clipping with NearClip and FarClip.

• void SetSpriteToCamera (BISprite sprite)

Sets a sprite's BISprite::Matrix to the current camera position and orientation. You could use this to implement a HUD, for example. Note: This only works correctly if the sprite has no parent (and is thus drawn directly) or it's parents are untransformed. If all you want is to set the sprite's position (but NOT orientation) to the camera, then set the sprite's Matrix.Translation = graphics.Eye

void SetCameraToSprite (BISprite sprite)

Sets the camera position and orientation to the current position and orientation of a sprite. You could use for cockpit view, for example. Note that the camera will lag sprite movement unless the following is done: For every frame you must first calculate the sprite's position and orientation, call this function, and then draw everything.

20 Class Documentation

· void AdjustCameraZoom (double dif)

Sets the Zoom. If dif is zero, then there is no change in zoom. Normally one would set zoom with the Zoom field. This is mainly for internal use.

void AdjustCameraDolly (double dif)

Migrates the current camera dolly (distance from LookAt) according to dif. If dif is zero, then there is no change in dolly.

void AdjustCameraTruck (double difX, double difY=0)

Adjusts camera truck (movement relative to camera direction) according to difX and difY. if difX and difY are zero, then truck position isn't changed.

void AdjustCameraRotation (double difX, double difY=0)

Adjusts camera rotation about the LookAt point according to difX and difY. if difX and difY are zero, then rotation isn't changed.

• void AdjustCameraPan (double difX, double difY=0)

Adjusts camera pan (changing direction of camera) according to difX and difY. if difX and difY are zero, then pan direction isn't changed.

• Ray DoDefaultGui ()

Updates Eye, LookAt, etc. according to mouse and certain key input. Specifically: Wheel=Dolly, CTRL-wheel=Zoom, Left-drag=Truck, Right-drag=Rotate, CTRL-left-drag=Pan, Esc=Reset. Also, SHIFT causes all the previous controls to be fine rather than coarse. If CTRL is pressed and mouse left or right button is clicked, then returns a ray into window at mouse position.

void ResetCamera ()

Sets Eye. LookAt, etc. back to default starting position.

void SetCameraRollToZero ()

Sets the camera 'roll' to be level with the XY plane

Ray CalculateRay (Vector2 windowPosition)

Returns a ray that that goes from the near clipping plane to the far clipping plane, at the specified window position.

Vector3 GetWindowCoordinates (BISprite sprite)

Returns the window coordinates of the specified sprite.

 Texture2D TextToTexture (string text, SpriteFont font, Microsoft.Xna.Framework.Color? color=null, Microsoft.Xna.Framework.Color? backColor=null)

Returns a Texture2D containing the specified text. It's up to the caller to Dispose the returned texture.

• void DrawTexture (Texture2D texture, Rectangle windowRect, Microsoft.Xna.Framework.Color? color=null)

void DrawText (string text, SpriteFont font, Vector2 windowPos, Microsoft.Xna.Framework.Color? color=null)

Draws text on the window.

Draws a texture in the window.

• Texture2D LoadFromImageFile (string fileName)

Loads a texture directly from an image file.

void PrepareDraw (bool firstCallInDraw=true)

This is automatically called once at the beginning of your BlWindow3D::FrameDraw method. It calculates the latest View and Projection settings according to the current camera specifications (Zoom, Aspect, Eye, LookAt, etc.), and if firstCallInDraw is true it also may sleep in order to obey FramePeriod. It must also be called explicitly after any changes to the camera settings made later in the BlWindow3D::FrameDraw method. Only in the first call should firstCallInDraw be true, and in any subsequent calls it should be false.

Texture2D CloneTexture2D (Texture2D tex)

Returns a deepcopy of the texture

- object Clone ()
- new void Dispose ()

When finished with the object, you should call <code>Dispose()</code> from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if <code>BIDebug::EnableDisposeErrors</code> is true (it is true by default for <code>Debug</code> builds), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (OpenGL, etc.) often requires 3D resources to be managed only by one thread.

Public Attributes

Microsoft.Xna.Framework.Matrix View

This is the view matrix. Normally you would use the higher-level functions Eye, LookAt, CameraUp, SetCameraToSprite, and DoDefaultGui intead of changing this directly.

Microsoft.Xna.Framework.Matrix Projection

The Projection matrix. Normally you would use the higher-level functions Zoom, Aspect, NearClip, or FarClip intead of changing this directly.

Vector3 CameraUp

Camera Up vector. Initially set to +Z. ResetCamera and SetCameraToSprite updates this.

double DefGuiMinLookZ = -1

Causes DoDefaultGui to prevent the Z component of CameraForwardNormalized from falling below this value. For example, set this to zero so that DoDefaultGui won't allow the camera to look downward

• double DefGuiMaxLookZ = 1

Caues DoDefaultGui to prevent the Z component of CameraForwardNormalized from rising above this value. For example, set this to zero so that DoDefaultGui won't allow the camera to look upward

DepthStencilState DepthStencilStateEnabled

Assign DepthStencilState to this to enable depth buffering

DepthStencilState DepthStencilStateDisabled

Assign DepthStencilState to this to disable depth buffering

Vector3 TargetEye

The point that Eye migrates to, according to CameraSpeed. See Eye for more information.

Vector3 TargetLookAt

The point that LookAt migrates to, according to CameraSpeed. See LookAt for more information.

• double CameraSpeed = .4

The responsiveness of the camera position to changes in TargetEye and TargetLookAt. A value of 0 means it doesn't respond to changes, 1 means it immediately responds. See Eye and LookAt for more information.

double Zoom =45

The field of view, in degrees.

• double Aspect =2

The aspect ratio.

• double NearClip = 0

The near clipping plane, or 0 = autoclip.

• double FarClip = 0

The far clipping plane, or 0 = autoclip.

Microsoft.Xna.Framework.Color ClearColor = new Microsoft.Xna.Framework.Color(0,0,.1f)

The background color.

double AutoRotate = 0

How fast DoDefaultGui should auto-rotate the scene.

• double FramePeriod = 1/60.0

How much time between consecutive frames.

List< Light > Lights = new List<Light>()

The directional lights. Note: The BasicEffect shader only supports the first three. To handle more lights, you'll need to write your own shader.

Vector3 AmbientLightColor = new Vector3(.1f, .1f, .1f)

The ambient light color. If null, no ambient light is enabled. Note: There is no ambient color for a BISprite. Both diffuse and ambient light illuminates the model's Color. See the BISprite::Color member.

Vector3 FogColor = null

If not null, color of fog.

• float fogStart = 1

How far away fog starts. See FogColor.

• float fogEnd = 10

22 Class Documentation

How far away fog ends. See FogColor.

• BlWindow3D Window

The BIWindow3D associated with this object.

• SpriteBatch SpriteBatch =null

A SpriteBatch for use by certain text and teture drawing methods.

• bool IsDisposed = false

Set when the object is Disposed.

Properties

• Vector3 CameraForward [get]

The vector between Eye and LookAt. Writes to Eye and LookAt and calls to SetCameraToSprite cause this to be updated. Also see CameraForwardNormalized and CameraForwardMag.

• Vector3 CameraForwardNormalized [get]

Normalized form of CameraForward. Writes to Eye and LookAt, and calls to SetCameraToSprite cause this to be updated. Also see CameraForward and CameraForwardMag.

• float CameraForwardMag [get]

The magnitude of CameraForward. Writes to Eye and LookAt, and calls to SetCameraToSprite cause this to be updated. Also see CameraForward and CameraForwardNormalized.

Vector3 CameraRight [get]

Camera Right vector. Writes to Eye and LookAt, and calls to SetCameraToSprite cause this to be updated.

• Vector3 Eye [get]

The current camera position. Note: To change the camera position, set TargetEye. Also see CameraSpeed.

Vector3 LookAt [get]

The current camera LookAt position. Note: To change the camera LookAt, set TargetLookAt. Also see CameraSpeed.

• double CurrentAspect [get]

Current aspect ratio. Same as Aspect unless Aspect==0.

double CurrentNearClip [get]

Current value of near clipping plane. See NearClip.

• double CurrentFarClip [get]

Current value of far clipping plane. See FarClip.

• double MinCamDistance [get]

Distance to the nearest sprite, less its radius. Note this is set to a very large number by PrepareDraw, and then as BIWindow3D::FrameDraw is called it is set more reasonably.

• double MaxCamDistance [get]

Distance to the farthest sprite, plus its radius. Note this is set to a very small number by PrepareDraw, and then as BIWindow3D::FrameDraw is called it is set more reasonably.

6.1.1 Detailed Description

This holds everything having to do with an output device. BIWindow3D creates one of these for itself.

6.1.2 Constructor & Destructor Documentation

6.1.2.1 BIGraphicsDeviceManager()

Parameters

window	The BIWindow3D object for which this is to be the BIGraphicsDeviceManager
VVIIIUUVV	The bivilluowab object for which this is to be the bigraphicabevice manager

6.1.3 Member Function Documentation

6.1.3.1 AdjustCameraDolly()

```
void Blotch.BlGraphicsDeviceManager.AdjustCameraDolly ( \mbox{double } \mbox{\it dif })
```

Migrates the current camera dolly (distance from LookAt) according to dif. If dif is zero, then there is no change in dolly.

Parameters

```
dif How much to dolly camera (plus = toward LookAt, minus = away)
```

6.1.3.2 AdjustCameraPan()

```
void Blotch.BlGraphicsDeviceManager.AdjustCameraPan ( double difX, double difY = 0 )
```

Adjusts camera pan (changing direction of camera) according to difX and difY. if difX and difY are zero, then pan direction isn't changed.

Parameters

difX	How much to pan horizontally	
difY	difY How much to pan vertically	

6.1.3.3 AdjustCameraRotation()

```
void Blotch.BlGraphicsDeviceManager.AdjustCameraRotation ( double difX, double difY = 0 )
```

Adjusts camera rotation about the LookAt point according to difX and difY. if difX and difY are zero, then rotation isn't changed.

24 Class Documentation

Parameters

difX	How much to rotate the camera horizontally
difY How much to rotate the camera vertically	

6.1.3.4 AdjustCameraTruck()

```
void Blotch.BlGraphicsDeviceManager.AdjustCameraTruck ( \mbox{double } difX, \mbox{double } difY = 0 \mbox{ )}
```

Adjusts camera truck (movement relative to camera direction) according to difX and difY. if difX and difY are zero, then truck position isn't changed.

Parameters

	How much to truck the camera horizontally	
difY	How much to truck the camera vertically	

6.1.3.5 AdjustCameraZoom()

```
void Blotch.BlGraphicsDeviceManager.AdjustCameraZoom ( double dif )
```

Sets the Zoom. If dif is zero, then there is no change in zoom. Normally one would set zoom with the Zoom field. This is mainly for internal use.

Parameters

```
dif How much to zoom camera (plus = magnify, minus = reduce)
```

6.1.3.6 CalculateRay()

Returns a ray that that goes from the near clipping plane to the far clipping plane, at the specified window position.

Parameters

windowPosition	The window's pixel coordinates
	in a minate of pinter ever amount of

Returns

The Ray into the window at the specified pixel coordinates

6.1.3.7 CloneTexture2D()

```
Texture2D Blotch.BlGraphicsDeviceManager.CloneTexture2D ( {\tt Texture2D}\ tex\ )
```

Returns a deepcopy of the texture

Parameters

tex The t	exture to deepcopy
-----------	--------------------

Returns

A deepcopy of tex

6.1.3.8 Dispose()

```
new void Blotch.BlGraphicsDeviceManager.Dispose ( )
```

When finished with the object, you should call Dispose() from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if BIDebug::EnableDisposeErrors is true (it is true by default for Debug builds), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (OpenGL, etc.) often requires 3D resources to be managed only by one thread.

6.1.3.9 DoDefaultGui()

```
Ray Blotch.BlGraphicsDeviceManager.DoDefaultGui ( )
```

Updates Eye, LookAt, etc. according to mouse and certain key input. Specifically: Wheel=Dolly, CTR ← L-wheel=Zoom, Left-drag=Truck, Right-drag=Rotate, CTRL-left-drag=Pan, Esc=Reset. Also, SHIFT causes all the previous controls to be fine rather than coarse. If CTRL is pressed and mouse left or right button is clicked, then returns a ray into window at mouse position.

Returns

If a mouse left or right click occurred, returns the Ray into the screen at that position. Otherwsie returns null

26 Class Documentation

6.1.3.10 DrawText()

Draws text on the window.

Parameters

text	The text to draw	
font	The font to use (typically created from SpriteFont content with Content.Load <spritefont>())</spritefont>	
windowPos	The X and Y window location, in pixels	
color Foreground color of the font		

6.1.3.11 DrawTexture()

Draws a texture in the window.

Parameters

texture	The texture to draw
windowRect	The X and Y window location, in pixels
color	Foreground color of the font

6.1.3.12 ExtendClippingTo()

```
void Blotch.BlGraphicsDeviceManager.ExtendClippingTo ( {\tt BlSprite}\ s\ )
```

Informs the auto-clipping code of an object that should be included in the clipping region. This is mainly for internal use. Application code should control clipping with NearClip and FarClip.

Parameters

```
s The sprite that should be included in the auto-clipping code
```

6.1.3.13 GetWindowCoordinates()

```
\label{thm:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:problem:p
```

Returns the window coordinates of the specified sprite.

Parameters

sprite	The sprite to get the window coordinates of
--------	---

Returns

The window coordinates of the sprite, in pixels

6.1.3.14 Initialize()

```
{\tt void Blotch.BlGraphicsDeviceManager.Initialize \ (\ )}
```

For internal use only. Apps should not normally call this. This initializes some values AFTER the BlWindow3D has been created.

6.1.3.15 LoadFromImageFile()

```
\label{thm:condition} \begin{tabular}{ll} Texture 2D & Blotch.BlGraphics Device Manager.Load From Image File ( \\ & string & file Name ) \end{tabular}
```

Loads a texture directly from an image file.

Parameters

fileName	An image file of any standard type supported by MonoGame (jpg, png, etc.)

Returns

The texture that was loaded

6.1.3.16 PrepareDraw()

This is automatically called once at the beginning of your BlWindow3D::FrameDraw method. It calculates the latest View and Projection settings according to the current camera specifications (Zoom, Aspect, Eye, LookAt, etc.), and if firstCallInDraw is true it also may sleep in order to obey FramePeriod. It must also be called explicitly after any changes to the camera settings made later in the BlWindow3D::FrameDraw method. Only in the first call should firstCallInDraw be true, and in any subsequent calls it should be false.

Parameters

firstCallInDraw True inc	dicates this method should also sleep in order to obey FramePeriod.
--------------------------	---

6.1.3.17 ResetCamera()

```
void Blotch.BlGraphicsDeviceManager.ResetCamera ( )
```

Sets Eye. LookAt, etc. back to default starting position.

6.1.3.18 SetCameraRollToZero()

```
void Blotch.BlGraphicsDeviceManager.SetCameraRollToZero ( )
```

Sets the camera 'roll' to be level with the XY plane

6.1.3.19 SetCameraToSprite()

```
void Blotch.BlGraphicsDeviceManager.SetCameraToSprite ( {\tt BlSprite}\ sprite\ )
```

Sets the camera position and orientation to the current position and orientation of a sprite. You could use for cockpit view, for example. Note that the camera will lag sprite movement unless the following is done: For every frame you must first calculate the sprite's position and orientation, call this function, and then draw everything.

Parameters

sprite	The sprite that the camera should be connected to
--------	---

6.1.3.20 SetSpriteToCamera()

```
void Blotch.BlGraphicsDeviceManager.SetSpriteToCamera ( {\tt BlSprite}\ sprite\ )
```

Sets a sprite's BISprite::Matrix to the current camera position and orientation. You could use this to implement a HUD, for example. Note: This only works correctly if the sprite has no parent (and is thus drawn directly) or it's parents are untransformed. If all you want is to set the sprite's position (but NOT orientation) to the camera, then set the sprite's Matrix.Translation = graphics.Eye

Parameters

sprite	The sprite that should be connected to the camera
--------	---

6.1.3.21 TextToTexture()

Returns a Texture2D containing the specified text. It's up to the caller to Dispose the returned texture.

Parameters

text	The text to write to the texture	
font	Font to use	
color	If specified, color of the text. (Default is white)	
backColor	If specified, background color, like Color.Transparent. If null, then do not clear the background)	

Returns

The texture (as a RenderTarget2D). Caller is responsible for Disposing this!

6.1.4 Member Data Documentation

6.1.4.1 AmbientLightColor

```
Vector3 Blotch.BlGraphicsDeviceManager.AmbientLightColor = new Vector3(.1f, .1f)
```

The ambient light color. If null, no ambient light is enabled. Note: There is no ambient color for a BISprite. Both diffuse and ambient light illuminates the model's Color. See the BISprite::Color member.

6.1.4.2 Aspect

```
double Blotch.BlGraphicsDeviceManager.Aspect =2
```

The aspect ratio.

6.1.4.3 AutoRotate

double Blotch.BlGraphicsDeviceManager.AutoRotate = 0

How fast DoDefaultGui should auto-rotate the scene.

6.1.4.4 CameraSpeed

```
double Blotch.BlGraphicsDeviceManager.CameraSpeed = .4
```

The responsiveness of the camera position to changes in TargetEye and TargetLookAt. A value of 0 means it doesn't respond to changes, 1 means it immediately responds. See Eye and LookAt for more information.

6.1.4.5 CameraUp

Vector3 Blotch.BlGraphicsDeviceManager.CameraUp

Camera Up vector. Initially set to +Z. ResetCamera and SetCameraToSprite updates this.

6.1.4.6 ClearColor

 $\label{local_model} \begin{tabular}{ll} Microsoft.Xna.Framework.Color Blotch.BlGraphicsDeviceManager.ClearColor = new Microsoft.Xna.} \\ \end{tabular}$ Framework.Color (0,0,.1f)

The background color.

6.1.4.7 DefGuiMaxLookZ

```
double Blotch.BlGraphicsDeviceManager.DefGuiMaxLookZ = 1
```

Caues DoDefaultGui to prevent the Z component of CameraForwardNormalized from rising above this value. For example, set this to zero so that DoDefaultGui won't allow the camera to look upward

6.1.4.8 DefGuiMinLookZ

```
double Blotch.BlGraphicsDeviceManager.DefGuiMinLookZ = -1
```

Causes DoDefaultGui to prevent the Z component of CameraForwardNormalized from falling below this value. For example, set this to zero so that DoDefaultGui won't allow the camera to look downward

6.1.4.9 DepthStencilStateDisabled

DepthStencilState Blotch.BlGraphicsDeviceManager.DepthStencilStateDisabled

Initial value:

Assign DepthStencilState to this to disable depth buffering

6.1.4.10 DepthStencilStateEnabled

 ${\tt DepthStencilState\ Blotch.BlGraphicsDeviceManager.DepthStencilStateEnabled}$

Initial value:

Assign DepthStencilState to this to enable depth buffering

6.1.4.11 FarClip

```
double Blotch.BlGraphicsDeviceManager.FarClip = 0
```

The far clipping plane, or 0 = autoclip.

6.1.4.12 FogColor

Vector3 Blotch.BlGraphicsDeviceManager.FogColor = null

If not null, color of fog.

6.1.4.13 fogEnd

float Blotch.BlGraphicsDeviceManager.fogEnd = 10

How far away fog ends. See FogColor.

6.1.4.14 fogStart

float Blotch.BlGraphicsDeviceManager.fogStart = 1

How far away fog starts. See FogColor.

6.1.4.15 FramePeriod

double Blotch.BlGraphicsDeviceManager.FramePeriod = 1/60.0

How much time between consecutive frames.

6.1.4.16 IsDisposed

bool Blotch.BlGraphicsDeviceManager.IsDisposed = false

Set when the object is Disposed.

6.1.4.17 Lights

```
List<Light> Blotch.BlGraphicsDeviceManager.Lights = new List<Light>()
```

The directional lights. Note: The BasicEffect shader only supports the first three. To handle more lights, you'll need to write your own shader.

6.1.4.18 NearClip

double Blotch.BlGraphicsDeviceManager.NearClip = 0

The near clipping plane, or 0 = autoclip.

6.1.4.19 Projection

Microsoft.Xna.Framework.Matrix Blotch.BlGraphicsDeviceManager.Projection

The Projection matrix. Normally you would use the higher-level functions Zoom, Aspect, NearClip, or FarClip intead of changing this directly.

6.1.4.20 SpriteBatch

SpriteBatch Blotch.BlGraphicsDeviceManager.SpriteBatch =null

A SpriteBatch for use by certain text and teture drawing methods.

6.1.4.21 TargetEye

Vector3 Blotch.BlGraphicsDeviceManager.TargetEye

The point that Eye migrates to, according to CameraSpeed. See Eye for more information.

6.1.4.22 TargetLookAt

Vector3 Blotch.BlGraphicsDeviceManager.TargetLookAt

The point that LookAt migrates to, according to CameraSpeed. See LookAt for more information.

6.1.4.23 View

Microsoft.Xna.Framework.Matrix Blotch.BlGraphicsDeviceManager.View

This is the view matrix. Normally you would use the higher-level functions Eye, LookAt, CameraUp, SetCameraToSprite, and DoDefaultGui intead of changing this directly.

6.1.4.24 Window

BlWindow3D Blotch.BlGraphicsDeviceManager.Window

The BIWindow3D associated with this object.

6.1.4.25 Zoom

double Blotch.BlGraphicsDeviceManager.Zoom =45

The field of view, in degrees.

6.1.5 Property Documentation

6.1.5.1 CameraForward

Vector3 Blotch.BlGraphicsDeviceManager.CameraForward [get]

The vector between Eye and LookAt. Writes to Eye and LookAt and calls to SetCameraToSprite cause this to be updated. Also see CameraForwardNormalized and CameraForwardMag.

6.1.5.2 CameraForwardMag

float Blotch.BlGraphicsDeviceManager.CameraForwardMag [get]

The magnitude of CameraForward. Writes to Eye and LookAt, and calls to SetCameraToSprite cause this to be updated. Also see CameraForward and CameraForwardNormalized.

6.1.5.3 CameraForwardNormalized

Vector3 Blotch.BlGraphicsDeviceManager.CameraForwardNormalized [get]

Normalized form of CameraForward. Writes to Eye and LookAt, and calls to SetCameraToSprite cause this to be updated. Also see CameraForward and CameraForwardMag.

6.1.5.4 CameraRight

Vector3 Blotch.BlGraphicsDeviceManager.CameraRight [get]

Camera Right vector. Writes to Eye and LookAt, and calls to SetCameraToSprite cause this to be updated.

6.1.5.5 CurrentAspect

```
double Blotch.BlGraphicsDeviceManager.CurrentAspect [get]
```

Current aspect ratio. Same as Aspect unless Aspect==0.

6.1.5.6 CurrentFarClip

```
double Blotch.BlGraphicsDeviceManager.CurrentFarClip [get]
```

Current value of far clipping plane. See FarClip.

6.1.5.7 CurrentNearClip

double Blotch.BlGraphicsDeviceManager.CurrentNearClip [get]

Current value of near clipping plane. See NearClip.

6.1.5.8 Eye

```
Vector3 Blotch.BlGraphicsDeviceManager.Eye [get]
```

The current camera position. Note: To change the camera position, set TargetEye. Also see CameraSpeed.

6.1.5.9 LookAt

```
Vector3 Blotch.BlGraphicsDeviceManager.LookAt [get]
```

The current camera LookAt position. Note: To change the camera LookAt, set TargetLookAt. Also see CameraSpeed.

6.1.5.10 MaxCamDistance

```
double Blotch.BlGraphicsDeviceManager.MaxCamDistance [get]
```

Distance to the farthest sprite, plus its radius. Note this is set to a very small number by PrepareDraw, and then as BlWindow3D::FrameDraw is called it is set more reasonably.

6.1.5.11 MinCamDistance

double Blotch.BlGraphicsDeviceManager.MinCamDistance [get]

Distance to the nearest sprite, less its radius. Note this is set to a very large number by PrepareDraw, and then as BIWindow3D::FrameDraw is called it is set more reasonably.

The documentation for this class was generated from the following file:

• C:/Users/kloum/Desktop/Source/Blotch3D/src/BlGraphicsDeviceManager.cs

6.2 Blotch.BlGuiControl Class Reference

A 2D GUI control. To create a GUI control: instantiate one of these, set its initial Texture (remember to create it in the 3D thread context), window position, and delegate, and then add it to BIWindow3D::GuiControls. (Any member can be dynamically changed.) The texture will be displayed, and then each frame the mouse is over it the delegate will be called. The delegate typically would examine the current mouse state (Mouse.GetState()) and the PrevMouseState member to detect button changes, etc. and perform an action. The delegate is called in the context of the window's 3D thread after the BIWindow3D::FrameProc method. You can use BIGraphicsDeviceManager::TextToTexture to create a textual textures, or just load a texture from a content file. Remember to Dispose textures when you are done with them.

Public Member Functions

- · delegate void OnMouseChangeDelegate (BlGuiControl guiCtrl)
 - Delegates for a BIGuiControl are of this type
- BIGuiControl (BIWindow3D window)
- bool HandleInput ()

Periodically called by BlWindow3D. You shouldn't need to call this.

Public Attributes

• Texture2D Texture = null

The texture to display for this control. Don't forget to dispose it when done.

• Vector2 Position = Vector2.Zero

The pixel position in the BlWindow3D of this control

OnMouseChangeDelegate OnMouseOver = null

The delegate to call each frame (from the 3D thread) when the mouse is over the control. A typical delegate would make a decision according to PrevMouseState and the current mouse state (Mouse.GetState).

MouseState PrevMouseState = new MouseState()

The previous mouse state. A delegte typiclly uses this along with the current mouse state to make a decision.

• BIWindow3D Window = null

The window this BlGuiControl is in.

6.2.1 Detailed Description

A 2D GUI control. To create a GUI control: instantiate one of these, set its initial Texture (remember to create it in the 3D thread context), window position, and delegate, and then add it to BIWindow3D::GuiControls. (Any member can be dynamically changed.) The texture will be displayed, and then each frame the mouse is over it the delegate will be called. The delegate typically would examine the current mouse state (Mouse.GetState()) and the PrevMouseState member to detect button changes, etc. and perform an action. The delegate is called in the context of the window's 3D thread after the BIWindow3D::FrameProc method. You can use BIGraphicsDeviceManager::TextToTexture to create a textual textures, or just load a texture from a content file. Remember to Dispose textures when you are done with them.

6.2.2 Member Function Documentation

6.2.2.1 HandleInput()

```
bool Blotch.BlGuiControl.HandleInput ( )
```

Periodically called by BlWindow3D. You shouldn't need to call this.

Returns

True if mouse is over any control, false otherwise.

6.2.2.2 OnMouseChangeDelegate()

Delegates for a BIGuiControl are of this type

Parameters

guiCtrl

6.2.3 Member Data Documentation

6.2.3.1 OnMouseOver

OnMouseChangeDelegate Blotch.BlGuiControl.OnMouseOver = null

The delegate to call each frame (from the 3D thread) when the mouse is over the control. A typical delegate would make a decision according to PrevMouseState and the current mouse state (Mouse.GetState).

6.2.3.2 Position

Vector2 Blotch.BlGuiControl.Position = Vector2.Zero

The pixel position in the BIWindow3D of this control

6.2.3.3 PrevMouseState

MouseState Blotch.BlGuiControl.PrevMouseState = new MouseState()

The previous mouse state. A delegte typically uses this along with the current mouse state to make a decision.

6.2.3.4 Texture

Texture2D Blotch.BlGuiControl.Texture = null

The texture to display for this control. Don't forget to dispose it when done.

6.2.3.5 Window

BlWindow3D Blotch.BlGuiControl.Window = null

The window this BlGuiControl is in.


The documentation for this class was generated from the following file:

• C:/Users/kloum/Desktop/Source/Blotch3D/src/BlGuiControl.cs

6.3 Blotch.BlMipmap Class Reference

A mipmap of textures for a given BISprite. You could load this from an image file and then assign it to a BISprite::Mipmap. Note that this is a software mipmap (i.e. it isn't implemented in the 3D hardware). That is, only one resolution texture is used at time.

Inheritance diagram for Blotch.BlMipmap:



Public Member Functions

• BlMipmap (BlGraphicsDeviceManager graphics, Texture2D tex, int numMaps=999, bool reverseX=false, bool reverseY=false)

Creates the mipmaps.

· void Dispose ()

When finished with the object, you should call <code>Dispose()</code> from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if <code>BIDebug.EnableDisposeErrors</code> is true (it is true by default for <code>Debug builds</code>), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (<code>OpenGL</code>, etc.) often requires 3D resources to be managed only by one thread.

Public Attributes

• bool IsDisposed = false

Set when the object is Disposed.

6.3.1 Detailed Description

A mipmap of textures for a given BISprite. You could load this from an image file and then assign it to a BISprite::Mipmap. Note that this is a software mipmap (i.e. it isn't implemented in the 3D hardware). That is, only one resolution texture is used at time.

6.3.2 Constructor & Destructor Documentation

6.3.2.1 BIMipmap()

Creates the mipmaps.

Parameters

graphics	Graphics device (typically the one owned by your BlWindow3D)	
tex	Texture from which to create mipmaps, typically gotten from BIGraphics::LoadFromImageFile.	
numMaps	Maximum number of mipmaps to create (none are created with lower resolution than 16x16)	
reverseX	reverseX Whether to reverse pixels horizontally	
reverseY	Whether to reverse pixels vertically	

6.3.3 Member Function Documentation

6.3.3.1 Dispose()

```
void Blotch.BlMipmap.Dispose ( )
```

When finished with the object, you should call <code>Dispose()</code> from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if <code>BIDebug.EnableDisposeErrors</code> is true (it is true by default for <code>Debug builds</code>), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (OpenGL, etc.) often requires 3D resources to be managed only by one thread.

6.3.4 Member Data Documentation

6.3.4.1 IsDisposed

```
bool Blotch.BlMipmap.IsDisposed = false
```

Set when the object is Disposed.


The documentation for this class was generated from the following file:

• C:/Users/kloum/Desktop/Source/Blotch3D/src/BlMipmap.cs

6.4 Blotch.BISprite Class Reference

A BISprite is a single 3D object. Each sprite can also hold any number of subsprites, so you can make a sprite tree (a scene graph). In that case the child sprites 'follow' the orientation and position of the parent sprite. That is, they exist in the coordinate system of the parent sprite. The location and orientation of a sprite in its parent's coordinate system is defined by the sprite's Matrix member. Subsprites, LODs, and Mipmap are NOT disposed when the sprite is disposed, so you can assign the same one to multiple sprites.

Inheritance diagram for Blotch.BISprite:



Public Types

enum PreDrawCmd { PreDrawCmd.Continue, PreDrawCmd.Abort, PreDrawCmd.UseCurrentAbsoluteMatrix }

Return code from PreDraw callback. This tells Draw what to do next.

enum PreSubspritesCmd { PreSubspritesCmd.Continue, PreSubspritesCmd.Abort, PreSubspritesCmd.DontDrawSubsprites
 }

Return code from PreSubsprites callback. This tells Draw what to do next.

enum PreMeshDrawCmd { PreMeshDrawCmd.Continue, PreMeshDrawCmd.Abort, PreMeshDrawCmd.Skip

Return code from PreSubsprites callback. This tells Draw what to do next.

enum PreLocalCmd { PreLocalCmd.Continue, PreLocalCmd.Abort }

Return code from PreSubsprites callback. This tells Draw what to do next.

Public Member Functions

delegate void FrameProcType (BISprite sprite)

See FrameProc

delegate PreDrawCmd PreDrawType (BISprite sprite)

See PreDraw

delegate PreSubspritesCmd PreSubspritesType (BISprite sprite)

See PreSubsprites

delegate PreMeshDrawCmd PreMeshDrawType (BISprite sprite, ModelMesh mesh)

See PreMeshDraw

delegate PreLocalCmd PreLocalType (BISprite sprite)

See PreLocal

delegate void DrawCleanupType (BISprite sprite)

See DrawCleanup

- BISprite (BIGraphicsDeviceManager graphicsIn, string name)
- void Add (BISprite s)

Add a subsprite. (A BISprite inherits from a Dictionary of BISprites. This wrapper method to the dictionary's Add method simply adds the sprite where the key is the sprite's Name.)

Vector2 GetViewCoords ()

Returns the current view coordinates of the sprite (for passing to DrawText, for example), or null if it's behind the camera.

void SetAllMaterialBlack ()

Sets all material colors to black.

double DoesRayIntersect (Ray ray)

Returns the distance along the ray to the first point the ray enters the bounding sphere (BoundSphere), or null if it doesn't enter the sphere.

Returns a list of subsprites that the ray hit (i.e. those that were within their radius of the ray)

Draws the sprite and the subsprites.

- override string ToString ()
- int CompareTo (object obj)

This makes a Sort operation sort sprites far to near. That is, the nearer sprites are later in the list. For sorting near to far, use something like myList.Sort(new Comparison < EsSprite> ((b, a) => a.CompareTo(b)));

· void Dispose ()

When finished with the object, you should call <code>Dispose()</code> from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if <code>BIDebug.EnableDisposeErrors</code> is true (it is true by default for <code>Debug builds</code>), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (OpenGL, etc.) often requires 3D resources to be managed only by one thread.

Static Public Member Functions

• static Vector3 NearestPointOnLine (Vector3 point1, Vector3 point2, Vector3 nearPoint)

Returns the point on the line between point1 and point2 that is nearest to nearPoint

Public Attributes

• ulong Flags = 0xFFFFFFFFFFFFFF

The Flags field can be used by callbacks of Draw (PreDraw, PreSubsprites, PreLocal, and PreMeshDraw) to indicate various user attributes of the sprite. Also, GetRayIntersections won't hit if the bitwise AND of this value and the flags argument passed to it is zero.

List< object > LODs = new List<object>()

The object drawn for this sprite. Specifically, this is a list of levels of detail (LOD), where only one is drawn depending on the ApparentSize. Each element can be a Model, a triangle list (VertexPositionNormalTexture[]), or null (indicating nothing should be drawn). Elements with lower indices are higher LODs. So index 0 is the highest, index 1 is second highest, etc. LOD decreases (the index increases) for every halving of the object's apparent size. You can adjust how close the LODs must be to the camera with LodScale. When the calculated LOD index is higher than the last element, then the last element is used. So the simplest way to use this is to add a single element of the object you want drawn. You can also add multiple references of the same object so multiple consecutive LODs draw the same object. You can also set an element to null so it doesn't draw anything, which is typically the last element. A model can be assigned to multiple sprites. These are NOT disposed when the sprite is disposed.

• double LodScale = 9

Defines the LOD scaling. The higher this value, the closer you must be to see a given LOD. A value of 9 (default) indicates that the highest LOD (LODs[0]) occurs when an object with a diameter of 1 roughly fills the window.

• BIMipmap Mipmap = null

Mipmap textures to apply to the model. These work the same as LODs (see LODs for more information). The texture used depends on the apparent size of the model. The next higher mipmap is used for every doubling of model size, where element zero is the highest resolution, used when the apparent size is largest. If a mipmap is not available for the apparent size, the next higher available on is used. So, for example, you can specify only one texture to be used as all mipmaps if you like. Note that for a texture to display, the model must include texture coordinates. Most graphics subsystems do support mipmaps, but these are supported at the app level. Therefore only one image is used over a model for a given model apparent size, rather than nearer portions of the model showing higher-level mipmaps. These are NOT disposed when the sprite is disposed. A given BIMipmap may be assigned to multiple sprites.

• double MipmapScale = 5

Defines the mipmap (Textures) scaling. The higher this value, the closer you must be to see a given mipmap.

• BoundingSphere BoundSphere = null

The bounding sphere for this sprite. This is automatically updated when a model is drawn, but not if vertices are drawn. In that case you should set/update it explicitly if any of the internal functions may need it to be roughly correct, like if auto-clipping is enabled or a mouse selection or ray may hit the sprite and the hit be properly detected.

• bool SphericalBillboard = false

Spherically billboard the model. Specifically, keep the model's 'forward' direction pointing at the camera and keep its 'Up' direction pointing in the same direction as the camera's 'Up' direction. Also see CylindricalBillboardX, CylindricalBillboardZ, and ConstSize.

Vector3 CylindricalBillboardX = Vector3.Zero

If non-zero, this is the rotation vector and magnitude of cylindrical billboarding where the angle calculation assumes this vector is the X axis, even though it may not be. The more this varies from that axis, the more eccentric the billboarding behavior. The amount of billboarding is equal to: $2*mag^2 - 1/mag^2$. So if this vector's magnitude is unity (1), then full cylindrical billboarding occurs. A vector magnitude of 0.605 produces double reverse cylindrical billboarding. Also see SphericalBillboard, CylindricalBillboardY, CylindricalBillboardZ, and ConstSize.

Vector3 CylindricalBillboardY = Vector3.Zero

If non-zero, this is the rotation vector and magnitude of cylindrical billboarding where the angle calculation assumes this vector is the Y axis, even though it may not be. The more this varies from that axis, the more eccentric the billboarding behavior. The amount of billboarding is equal to: $2*mag^2 - 1/mag^2$. So if this vector's magnitude is unity (1), then full cylindrical billboarding occurs. A vector magnitude of 0.605 produces double reverse cylindrical billboarding. Also see SphericalBillboard, CylindricalBillboardX, CylindricalBillboardZ, and ConstSize.

Vector3 CylindricalBillboardZ = Vector3.Zero

If non-zero, this is the rotation vector and magnitude of cylindrical billboarding where the angle calculation assumes this vector is the Z axis, even though it may not be. The more this varies from that axis, the more eccentric the billboarding behavior. The amount of billboarding is equal to: $2*mag^2 - 1/mag^2$. So if this vector's magnitude is unity (1), then full cylindrical billboarding occurs. A vector magnitude of 0.605 produces double reverse cylindrical billboarding. Also see SphericalBillboard, CylindricalBillboardX, CylindricalBillboardY, and ConstSize.

bool ConstSize = false

If true, maintain a constant apparent size for the sprite regardless of camera distance or zoom. This is typically used along with one of the Billboarding effects (see SphericalBillboard, CylindricalBillboardX, etc.). If both ConstSize and any Billboarding is enabled and you have asymmetric scaling (different scaling for each dimension), then you'll need to separate those operations into different levels of the sprite tree to obtain the desired behavior. You'll also probably want to disable the depth stencil buffer and control which sprite is drawn first so that certain sprites are 'always on top'. See the examples.

Matrix AbsoluteMatrix = Matrix.Identity

The Draw method takes an incoming 'world' matrix parameter which is the coordinate system of its parent. AbsoluteMatrix is that incoming world matrix parameter times the Matrix member and altered according to Billboarding and ConstSize. This is not read-only because a callback (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw) may need to change it from within the Draw method. This is the matrix that is also passed to subsprites as their 'world' matrix.

• Matrix Matrix = Matrix.Identity

The matrix for this sprite. This defines the sprite's orientation and position relative to the parent coordinate system. For more detailed information, see AbsoluteMatrix.

• BIGraphicsDeviceManager Graphics = null

Current incoming graphics parameter to the Draw method. Typically this would be of interest to a callback function (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw).

• Matrix LastWorldMatrix = null

Current incoming world matrix parameter to the Draw method. Typically this would be of interest to a callback function (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw).

bool IncludeInAutoClipping = true

Whether to use depth testing, and whether to participate in autoclipping calculations when they are enabled.

• ulong FlagsParameter = 0

Current incoming flags parameter to the Draw method. Typically this would be of interest to a callback function (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw).

Vector3 Color = new Vector3(.5f, .5f, 1)

The color of the material. This is lit by both diffuse and ambient light. If null, MonoGame's default color is kept.

• Vector3 EmissiveColor = new Vector3(.1f, .1f, .2f)

The emissive color. If null, MonoGame's default is kept.

Vector3 SpecularColor = null

The specular color. If null, MonoGame's default is kept.

• float SpecularPower = 8

If a specular color is specified, this is the specular power.

• FrameProcType _FrameProc = null

Internal use only. Do not alter.

• PreDrawType PreDraw = null

If not null, Draw method calls this at the beginning before doing anything else. From this function one might examine and/or alter any public writable BISprite field, and/or control the further execution of the Draw method.

PreSubspritesType PreSubsprites = null

If not null, Draw method calls this after the matrix calculations for AbsoluteMatrix (including billboards, CamDistance, ConstSize, etc.) but before drawing the subsprites or local model. From this function one might examine and/or alter any public writable BlSprite field.

• PreMeshDrawType PreMeshDraw = null

If not null, Draw method calls this before each model mesh is drawn for the local model. From this function one might examine and/or alter any public writable BISprite field. If the return value is true, then the mesh will not be drawn.

• PreLocalType PreLocal = null

If not null, Draw method calls this after drawing subsprites (if appropriate) but before drawing the local model. From this function one might examine and/or alter any public writable BISprite field, and/or abort the Draw method.

• DrawCleanupType DrawCleanup = null

If not null, Draw method calls this at the end.

· string Name

The name of the BISprite

• bool IsDisposed = false

Set when the object is Disposed.

Properties

double ApparentSize [get]

This is proportional to the apparent 2D size of the sprite. (Calculated from the last Draw operation that occurred, but before any effect of ConstSize)

• double LodTarget [get]

This read-only value is the log of the reciprocal of ApparentSize. It is used in the calculation of the LOD and the mipmap level. See LODs and Mipmap for more information.

• BasicEffect VerticesEffect [get, set]

BasicEffect used to draw vertices. If not explicitly set, then use a default BasicEffect and dispose it when the BISprite is disposed. If explicitly set, then don't dispose it when the BISprite is disposed.

• double CamDistance [get]

Distance to the camera.

• FrameProcType FrameProc [get, set]

Called once per frame just after BlWindow3D::FrameProc is called. You can update a sprite here, or update it in BlWindow3D::FrameProc. Doing it here makes the code more encapsulated.

6.4.1 Detailed Description

A BISprite is a single 3D object. Each sprite can also hold any number of subsprites, so you can make a sprite tree (a scene graph). In that case the child sprites 'follow' the orientation and position of the parent sprite. That is, they exist in the coordinate system of the parent sprite. The location and orientation of a sprite in its parent's coordinate system is defined by the sprite's Matrix member. Subsprites, LODs, and Mipmap are NOT disposed when the sprite is disposed, so you can assign the same one to multiple sprites.

6.4.2 Member Enumeration Documentation

6.4.2.1 PreDrawCmd

```
enum Blotch.BlSprite.PreDrawCmd [strong]
```

Return code from PreDraw callback. This tells Draw what to do next.

Enumerator

Continue	Continue Draw method execution
Abort	Draw should immediately return
UseCurrentAbsoluteMatrix	Continue Draw method execution, but don't bother re-calculating AbsoluteMatrix. One would typically return this if, for example, its known that AbsoluteMatrix will not change from its current value because the Draw parameters will be the same as they were the last time Draw was called. This happens, for example, when
Generated by Doxygen	multiple calls are being made in the same draw iteration for graphic operations that require multiple passes, like proper handling of translucency, etc.

6.4.2.2 PreLocalCmd

```
enum Blotch.BlSprite.PreLocalCmd [strong]
```

Return code from PreSubsprites callback. This tells Draw what to do next.

Enumerator

Continue	Continue Draw method execution
Abort	Draw should immediately return

6.4.2.3 PreMeshDrawCmd

```
enum Blotch.BlSprite.PreMeshDrawCmd [strong]
```

Return code from PreSubsprites callback. This tells Draw what to do next.

Enumerator

Continue	Continue Draw method execution
Abort	Draw should immediately return
Skip	Draw should skip the current mesh

6.4.2.4 PreSubspritesCmd

```
enum Blotch.BlSprite.PreSubspritesCmd [strong]
```

Return code from PreSubsprites callback. This tells Draw what to do next.

Enumerator

Continue Continue Draw method execu	
Abort	Draw should immediately return
DontDrawSubsprites	Skip drawing subsprites

6.4.3 Member Function Documentation

6.4.3.1 Add()

```
void Blotch.BlSprite.Add ( BlSprite \ s )
```

Add a subsprite. (A BISprite inherits from a Dictionary of BISprites. This wrapper method to the dictionary's Add method simply adds the sprite where the key is the sprite's Name.)

Parameters



6.4.3.2 CompareTo()

```
int Blotch.BlSprite.CompareTo ( object \ obj )
```

This makes a Sort operation sort sprites far to near. That is, the nearer sprites are later in the list. For sorting near to far, use something like myList.Sort(new Comparison<EsSprite>((b, a) => a.CompareTo(b)));

Parameters



Returns

6.4.3.3 Dispose()

```
void Blotch.BlSprite.Dispose ( )
```

When finished with the object, you should call Dispose() from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if BIDebug.EnableDisposeErrors is true (it is true by default for Debug builds), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (OpenGL, etc.) often requires 3D resources to be managed only by one thread.

6.4.3.4 DoesRayIntersect()

```
double Blotch.BlSprite.DoesRayIntersect ( {\tt Ray} \ ray \ )
```

Returns the distance along the ray to the first point the ray enters the bounding sphere (BoundSphere), or null if it doesn't enter the sphere.

Parameters

ray	
boundingSphere	

Returns

How far along the ray till the first intersection, or null oif it didn't intersect

6.4.3.5 Draw()

Draws the sprite and the subsprites.

Parameters

world⇔	Defines the position and orientation of the sprite
MatrixIn	
flagsIn	Copied to LastFlags for use by any callback of Draw (PreDraw, PreSubspriteDraw, PreLocalDraw, and PreMeshDraw) that wants it

6.4.3.6 DrawCleanupType()

See DrawCleanup

Parameters

sprite

6.4.3.7 FrameProcType()

See FrameProc

Parameters

sprite

6.4.3.8 GetRayIntersections()

Returns a list of subsprites that the ray hit (i.e. those that were within their radius of the ray)

Parameters

ray	The ray we are searching
flags	Check for a hit only if flags & BISprite::Flags is non-zero
sprites	An existing sprite list to load. If null, then this allocates a new sprite list.

Returns

A list of subsprites that the ray hit

6.4.3.9 GetViewCoords()

```
Vector2 Blotch.BlSprite.GetViewCoords ( )
```

Returns the current view coordinates of the sprite (for passing to DrawText, for example), or null if it's behind the camera.

Returns

The view coords of the sprite

6.4.3.10 NearestPointOnLine()

Returns the point on the line between point1 and point2 that is nearest to nearPoint

Parameters

point1	
point2	
nearPoint	

Returns

Point on the line nearest to nearPoint

6.4.3.11 PreDrawType()

See PreDraw

Parameters

sprite

Returns

6.4.3.12 PreLocalType()

```
delegate PreLocalCmd Blotch.BlSprite.PreLocalType ( {\tt BlSprite}\ sprite\ )
```

See PreLocal

Parameters

sprite

Returns

6.4.3.13 PreMeshDrawType()

See PreMeshDraw

Parameters

sprite mesh

Returns

6.4.3.14 PreSubspritesType()

See PreSubsprites

Parameters

sprite

Returns

6.4.3.15 SetAllMaterialBlack()

```
void Blotch.BlSprite.SetAllMaterialBlack ( )
```

Sets all material colors to black.

6.4.4 Member Data Documentation

6.4.4.1 FrameProc

```
FrameProcType Blotch.BlSprite._FrameProc = null
```

Internal use only. Do not alter.

6.4.4.2 AbsoluteMatrix

```
Matrix Blotch.BlSprite.AbsoluteMatrix = Matrix.Identity
```

The Draw method takes an incoming 'world' matrix parameter which is the coordinate system of its parent. AbsoluteMatrix is that incoming world matrix parameter times the Matrix member and altered according to Bill-boarding and ConstSize. This is not read-only because a callback (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw) may need to change it from within the Draw method. This is the matrix that is also passed to subsprites as their 'world' matrix.

6.4.4.3 BoundSphere

```
BoundingSphere Blotch.BlSprite.BoundSphere = null
```

The bounding sphere for this sprite. This is automatically updated when a model is drawn, but not if vertices are drawn. In that case you should set/update it explicitly if any of the internal functions may need it to be roughly correct, like if auto-clipping is enabled or a mouse selection or ray may hit the sprite and the hit be properly detected.

6.4.4.4 Color

```
Vector3 Blotch.BlSprite.Color = new Vector3(.5f, .5f, 1)
```

The color of the material. This is lit by both diffuse and ambient light. If null, MonoGame's default color is kept.

6.4.4.5 ConstSize

```
bool Blotch.BlSprite.ConstSize = false
```

If true, maintain a constant apparent size for the sprite regardless of camera distance or zoom. This is typically used along with one of the Billboarding effects (see SphericalBillboard, CylindricalBillboardX, etc.). If both ConstSize and any Billboarding is enabled and you have asymmetric scaling (different scaling for each dimension), then you'll need to separate those operations into different levels of the sprite tree to obtain the desired behavior. You'll also probably want to disable the depth stencil buffer and control which sprite is drawn first so that certain sprites are 'always on top'. See the examples.

6.4.4.6 CylindricalBillboardX

```
Vector3 Blotch.BlSprite.CylindricalBillboardX = Vector3.Zero
```

If non-zero, this is the rotation vector and magnitude of cylindrical billboarding where the angle calculation assumes this vector is the X axis, even though it may not be. The more this varies from that axis, the more eccentric the billboarding behavior. The amount of billboarding is equal to: $2*mag^2 - 1/mag^2$. So if this vector's magnitude is unity (1), then full cylindrical billboarding occurs. A vector magnitude of 0.605 produces double reverse cylindrical billboarding. Also see SphericalBillboard, CylindricalBillboardY, CylindricalBillboardZ, and ConstSize.

6.4.4.7 CylindricalBillboardY

```
Vector3 Blotch.BlSprite.CylindricalBillboardY = Vector3.Zero
```

If non-zero, this is the rotation vector and magnitude of cylindrical billboarding where the angle calculation assumes this vector is the Y axis, even though it may not be. The more this varies from that axis, the more eccentric the billboarding behavior. The amount of billboarding is equal to: $2*mag^2 - 1/mag^2$. So if this vector's magnitude is unity (1), then full cylindrical billboarding occurs. A vector magnitude of 0.605 produces double reverse cylindrical billboarding. Also see SphericalBillboard, CylindricalBillboardX, CylindricalBillboardZ, and ConstSize.

6.4.4.8 CylindricalBillboardZ

```
Vector3 Blotch.BlSprite.CylindricalBillboardZ = Vector3.Zero
```

If non-zero, this is the rotation vector and magnitude of cylindrical billboarding where the angle calculation assumes this vector is the Z axis, even though it may not be. The more this varies from that axis, the more eccentric the billboarding behavior. The amount of billboarding is equal to: $2*mag^2 - 1/mag^2$. So if this vector's magnitude is unity (1), then full cylindrical billboarding occurs. A vector magnitude of 0.605 produces double reverse cylindrical billboarding. Also see SphericalBillboard, CylindricalBillboardX, CylindricalBillboardY, and ConstSize.

6.4.4.9 DrawCleanup

```
DrawCleanupType Blotch.BlSprite.DrawCleanup = null
```

If not null, Draw method calls this at the end.

6.4.4.10 EmissiveColor

```
Vector3 Blotch.BlSprite.EmissiveColor = new Vector3(.1f, .1f, .2f)
```

The emissive color. If null, MonoGame's default is kept.

6.4.4.11 Flags

The Flags field can be used by callbacks of Draw (PreDraw, PreSubsprites, PreLocal, and PreMeshDraw) to indicate various user attributes of the sprite. Also, GetRayIntersections won't hit if the bitwise AND of this value and the flags argument passed to it is zero.

6.4.4.12 FlagsParameter

```
ulong Blotch.BlSprite.FlagsParameter = 0
```

Current incoming flags parameter to the Draw method. Typically this would be of interest to a callback function (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw).

6.4.4.13 Graphics

```
BlGraphicsDeviceManager Blotch.BlSprite.Graphics = null
```

Current incoming graphics parameter to the Draw method. Typically this would be of interest to a callback function (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw).

6.4.4.14 IncludeInAutoClipping

```
bool Blotch.BlSprite.IncludeInAutoClipping = true
```

Whether to use depth testing, and whether to participate in autoclipping calculations when they are enabled.

6.4.4.15 IsDisposed

```
bool Blotch.BlSprite.IsDisposed = false
```

Set when the object is Disposed.

6.4.4.16 LastWorldMatrix

```
Matrix Blotch.BlSprite.LastWorldMatrix = null
```

Current incoming world matrix parameter to the Draw method. Typically this would be of interest to a callback function (see PreDraw, PreSubsprites, PreLocal, and PreMeshDraw).

6.4.4.17 LODs

```
List<object> Blotch.BlSprite.LODs = new List<object>()
```

The object drawn for this sprite. Specifically, this is a list of levels of detail (LOD), where only one is drawn depending on the ApparentSize. Each element can be a Model, a triangle list (VertexPositionNormalTexture[]), or null (indicating nothing should be drawn). Elements with lower indices are higher LODs. So index 0 is the highest, index 1 is second highest, etc. LOD decreases (the index increases) for every halving of the object's apparent size. You can adjust how close the LODs must be to the camera with LodScale. When the calculated LOD index is higher than the last element, then the last element is used. So the simplest way to use this is to add a single element of the object you want drawn. You can also add multiple references of the same object so multiple consecutive LODs draw the same object. You can also set an element to null so it doesn't draw anything, which is typically the last element. A model can be assigned to multiple sprites. These are NOT disposed when the sprite is disposed.

6.4.4.18 LodScale

```
double Blotch.BlSprite.LodScale = 9
```

Defines the LOD scaling. The higher this value, the closer you must be to see a given LOD. A value of 9 (default) indicates that the highest LOD (LODs[0]) occurs when an object with a diameter of 1 roughly fills the window.

6.4.4.19 Matrix

```
Matrix Blotch.BlSprite.Matrix = Matrix.Identity
```

The matrix for this sprite. This defines the sprite's orientation and position relative to the parent coordinate system. For more detailed information, see AbsoluteMatrix.

6.4.4.20 Mipmap

```
BlMipmap Blotch.BlSprite.Mipmap = null
```

Mipmap textures to apply to the model. These work the same as LODs (see LODs for more information). The texture used depends on the apparent size of the model. The next higher mipmap is used for every doubling of model size, where element zero is the highest resolution, used when the apparent size is largest. If a mipmap is not available for the apparent size, the next higher available on is used. So, for example, you can specify only one texture to be used as all mipmaps if you like. Note that for a texture to display, the model must include texture coordinates. Most graphics subsystems do support mipmaps, but these are supported at the app level. Therefore only one image is used over a model for a given model apparent size, rather than nearer portions of the model showing higher-level mipmaps. These are NOT disposed when the sprite is disposed. A given BIMipmap may be assigned to multiple sprites.

6.4.4.21 MipmapScale

```
double Blotch.BlSprite.MipmapScale = 5
```

Defines the mipmap (Textures) scaling. The higher this value, the closer you must be to see a given mipmap.

6.4.4.22 Name

```
string Blotch.BlSprite.Name
```

The name of the BISprite

6.4.4.23 PreDraw

```
PreDrawType Blotch.BlSprite.PreDraw = null
```

If not null, Draw method calls this at the beginning before doing anything else. From this function one might examine and/or alter any public writable BISprite field, and/or control the further execution of the Draw method.

6.4.4.24 PreLocal

```
PreLocalType Blotch.BlSprite.PreLocal = null
```

If not null, Draw method calls this after drawing subsprites (if appropriate) but before drawing the local model. From this function one might examine and/or alter any public writable BISprite field, and/or abort the Draw method.

6.4.4.25 PreMeshDraw

```
PreMeshDrawType Blotch.BlSprite.PreMeshDraw = null
```

If not null, Draw method calls this before each model mesh is drawn for the local model. From this function one might examine and/or alter any public writable BISprite field. If the return value is true, then the mesh will not be drawn.

6.4.4.26 PreSubsprites

```
PreSubspritesType Blotch.BlSprite.PreSubsprites = null
```

If not null, Draw method calls this after the matrix calculations for AbsoluteMatrix (including billboards, CamDistance, ConstSize, etc.) but before drawing the subsprites or local model. From this function one might examine and/or alter any public writable BISprite field.

6.4.4.27 SpecularColor

Vector3 Blotch.BlSprite.SpecularColor = null

The specular color. If null, MonoGame's default is kept.

6.4.4.28 SpecularPower

```
float Blotch.BlSprite.SpecularPower = 8
```

If a specular color is specified, this is the specular power.

6.4.4.29 SphericalBillboard

bool Blotch.BlSprite.SphericalBillboard = false

Spherically billboard the model. Specifically, keep the model's 'forward' direction pointing at the camera and keep its 'Up' direction pointing in the same direction as the camera's 'Up' direction. Also see CylindricalBillboardX, CylindricalBillboardZ, and ConstSize.

6.4.5 Property Documentation

6.4.5.1 ApparentSize

```
double Blotch.BlSprite.ApparentSize [get]
```

This is proportional to the apparent 2D size of the sprite. (Calculated from the last Draw operation that occurred, but before any effect of ConstSize)

6.4.5.2 CamDistance

double Blotch.BlSprite.CamDistance [get]

Distance to the camera.

6.4.5.3 FrameProc

```
FrameProcType Blotch.BlSprite.FrameProc [get], [set]
```

Called once per frame just after BlWindow3D::FrameProc is called. You can update a sprite here, or update it in BlWindow3D::FrameProc. Doing it here makes the code more encapsulated.

6.4.5.4 LodTarget

```
double Blotch.BlSprite.LodTarget [get]
```

This read-only value is the log of the reciprocal of ApparentSize. It is used in the calculation of the LOD and the mipmap level. See LODs and Mipmap for more information.

6.4.5.5 VerticesEffect

```
BasicEffect Blotch.BlSprite.VerticesEffect [get], [set]
```

BasicEffect used to draw vertices. If not explicitly set, then use a default BasicEffect and dispose it when the BISprite is disposed. If explicitly set, then don't dispose it when the BISprite is disposed.


The documentation for this class was generated from the following file:

• C:/Users/kloum/Desktop/Source/Blotch3D/src/BlSprite.cs

6.5 Blotch.BlWindow3D Class Reference

To make a 3D window, you must derive a class from BlWindow3D and override the Setup, FrameProc, and FrameDraw methods. When it comes time to open the 3D window, you instantiate that class and call its "Run" method from the same thread that instantiated it. The Run method will call the Setup, FrameProc, and FrameDraw methods when appropriate, and not return until the window closes. All code that accesses 3D resources must be done in that thread, including code that creates and uses all Blotch3D and MonoGame objects. Note that this rule also applies to any code structure that may internally use other threads, as well. Do not use Parallel, async, etc. code structures that access 3D resources. Other threads that need to access 3D resources can do so by passing a delegate to EnqueueCommand and EnqueueCommandBlocking.

Inheritance diagram for Blotch.BIWindow3D:



Public Member Functions

delegate void Command (BlWindow3D win)

See EnqueueCommand, EnqueueCommandBlocking, and BIWindow3D for more info

BIWindow3D ()

See BIWindow3D for details.

void EnqueueCommand (Command cmd)

Since all operations accessing 3D resources must be done by the 3D thread, this allows other threads to send commands to execute in the 3D thread. For example, you might need another thread to be able to create, move, and delete BISprites. You can also use this for general thred safety of various operations. This method does not block. Also see BIWindow3D and the (blocking) EnqueueCommandBlocking for more details.

void EnqueueCommandBlocking (Command cmd)

Since all operations accessing 3D resources must be done by the 3D thread, this allows other threads to send commands to execute in the 3D thread. For example, you might need another thread to be able to create, move, and delete BISprites. You can also use this for general thred safety of various operations. This method blocks until the command has executed. Also see BIWindow3D and the (non-blocking) EnqueueCommand for more details.

• new void Dispose ()

When finished with the object, you should call Dispose() from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if BIDebug.EnableDisposeErrors is true (it is true by default for Debug builds), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (OpenGL, etc.) often requires 3D resources to be managed only by one thread.

Public Attributes

• BIGraphicsDeviceManager Graphics

The BIGraphicsDeviceManager associated with this window. This is automatically created when you create the BIWindow3D.

List< BISprite > FrameProcSprites = new List<BISprite>()

Internal use only. Do not write. Holds the sprites that currently have a BISprite::FrameProc defined.

 ConcurrentDictionary< string, BIGuiControl > GuiControls = new ConcurrentDictionary<string, BIGuiControl>()

The GUI controls for this window. See BIGuiControl for details.

• bool IsDisposed = false

Set when the object is Disposed.

Protected Member Functions

• override void Initialize ()

Used internally, Do NOT override. Use Setup instead.

override void LoadContent ()

Used internally, Do NOT override. Use Setup instead.

virtual void Setup ()

Override this and put all initialization and global content creation code in it. See BlWindow3D for details.

override void Update (GameTime timeInfo)

Used internally, Do NOT override. Use FrameProc instead.

• virtual void FrameProc (GameTime timeInfo)

See BIWindow3D for details.

override void Draw (GameTime timeInfo)

Used internally, Do NOT override. Use FrameDraw instead.

virtual void FrameDraw (GameTime timeInfo)

See BIWindow3D for details.

6.5.1 Detailed Description

To make a 3D window, you must derive a class from BlWindow3D and override the Setup, FrameProc, and FrameDraw methods. When it comes time to open the 3D window, you instantiate that class and call its "Run" method from the same thread that instantiated it. The Run method will call the Setup, FrameProc, and FrameDraw methods when appropriate, and not return until the window closes. All code that accesses 3D resources must be done in that thread, including code that creates and uses all Blotch3D and MonoGame objects. Note that this rule also applies to any code structure that may internally use other threads, as well. Do not use Parallel, async, etc. code structures that access 3D resources. Other threads that need to access 3D resources can do so by passing a delegate to EnqueueCommand and EnqueueCommandBlocking.

6.5.2 Constructor & Destructor Documentation

6.5.2.1 BIWindow3D()

```
Blotch.BlWindow3D.BlWindow3D ( )
```

See BIWindow3D for details.

6.5.3 Member Function Documentation

6.5.3.1 Command()

See EnqueueCommand, EnqueueCommandBlocking, and BlWindow3D for more info

Parameters

```
win The BlWindow3D object
```

6.5.3.2 Dispose()

```
new void Blotch.BlWindow3D.Dispose ( )
```

When finished with the object, you should call <code>Dispose()</code> from the same thread that created the object. You can call this multiple times, but once is enough. If it isn't called before the object becomes inaccessible, then the destructor will call it and, if <code>BIDebug.EnableDisposeErrors</code> is true (it is true by default for <code>Debug builds</code>), then it will get an exception saying that it wasn't called by the same thread that created it. This is because the platform's underlying 3D library (OpenGL, etc.) often requires 3D resources to be managed only by one thread.

6.5.3.3 Draw()

```
override void Blotch.BlWindow3D.Draw ( {\tt GameTime}~timeInfo~)~[protected]
```

Used internally, Do NOT override. Use FrameDraw instead.

Parameters

timeInfo

6.5.3.4 EnqueueCommand()

Since all operations accessing 3D resources must be done by the 3D thread, this allows other threads to send commands to execute in the 3D thread. For example, you might need another thread to be able to create, move, and delete BISprites. You can also use this for general thred safety of various operations. This method does not block. Also see BIWindow3D and the (blocking) EnqueueCommandBlocking for more details.

Parameters

cmd

6.5.3.5 EnqueueCommandBlocking()

Since all operations accessing 3D resources must be done by the 3D thread, this allows other threads to send commands to execute in the 3D thread. For example, you might need another thread to be able to create, move, and delete BISprites. You can also use this for general thred safety of various operations. This method blocks until the command has executed. Also see BIWindow3D and the (non-blocking) EnqueueCommand for more details.

Parameters

cmd

6.5.3.6 FrameDraw()

See BlWindow3D for details.

Parameters

timeInfo

```
6.5.3.7 FrameProc()
```

```
virtual void Blotch.BlWindow3D.FrameProc ( {\tt GameTime}\ timeInfo\ )\ \ [protected],\ [virtual]
```

See BIWindow3D for details.

Parameters

timeInfo

```
6.5.3.8 Initialize()
```

```
override void Blotch.BlWindow3D.Initialize ( ) [protected]
```

Used internally, Do NOT override. Use Setup instead.

```
6.5.3.9 LoadContent()
```

```
override void Blotch.BlWindow3D.LoadContent ( ) [protected]
```

Used internally, Do NOT override. Use Setup instead.

```
6.5.3.10 Setup()
```

```
virtual void Blotch.BlWindow3D.Setup ( ) [protected], [virtual]
```

Override this and put all initialization and global content creation code in it. See BlWindow3D for details.

```
6.5.3.11 Update()
```

```
override void Blotch.BlWindow3D.Update ( {\tt GameTime}\ timeInfo\ ) \quad [{\tt protected}]
```

Used internally, Do NOT override. Use FrameProc instead.

Parameters

timeInfo

6.5.4 Member Data Documentation

6.5.4.1 FrameProcSprites

```
List<BlSprite> Blotch.BlWindow3D.FrameProcSprites = new List<BlSprite>()
```

Internal use only. Do not write. Holds the sprites that currently have a BISprite::FrameProc defined.

6.5.4.2 Graphics

BlGraphicsDeviceManager Blotch.BlWindow3D.Graphics

The BIGraphicsDeviceManager associated with this window. This is automatically created when you create the BIWindow3D.

6.5.4.3 GuiControls

ConcurrentDictionary<string, BlGuiControl> Blotch.BlWindow3D.GuiControls = new Concurrent← Dictionary<string, BlGuiControl>()

The GUI controls for this window. See BIGuiControl for details.

6.5.4.4 IsDisposed

bool Blotch.BlWindow3D.IsDisposed = false

Set when the object is Disposed.

The documentation for this class was generated from the following file:

• C:/Users/kloum/Desktop/Source/Blotch3D/src/BlWindow3D.cs

6.6 Blotch.BlGraphicsDeviceManager.Light Class Reference

Defines a light. See the Lights field. The default BasicShader supports up to three lights.

Public Attributes

- Vector3 LightDirection = new Vector3(1, 0, 0)
- Vector3 LightDiffuseColor = new Vector3(1, 0, 1)
- Vector3 LightSpecularColor = new Vector3(0, 1, 0)

6.6.1 Detailed Description

Defines a light. See the Lights field. The default BasicShader supports up to three lights.

The documentation for this class was generated from the following file:

• C:/Users/kloum/Desktop/Source/Blotch3D/src/BlGraphicsDeviceManager.cs