TADtool

TADtool is an interactive tool for the identification of meaningful parameters in topologically-associating domains (TADs) algorithms for Hi-C data.



- TADtool
 - Quick start
 - Installation
 - ∘ <u>Usage</u>
 - plot
 - Launching from the command line
 - Interactive plotting window
 - Hi-C plot
 - ∘ Index plot
 - Heatmap
 - Export buttons
 - <u>tads</u>

Quick start

Installation:

```
pip install tadtool
```

Run sample data from GitHub repo:

tadtool plot examples/chr12_20-35Mb.matrix.txt examples/chr12_20-35Mb_regions.bed chr12:31000000-33000000

This should open the interactive plotting window (see above). Start exploring by clicking in plots - the effects should be self-explanatory.

Installation

You can install TADtool from the command line using PyPI

```
pip install tadtool
```

or download the source from our GitHub repo and install manually

This should install both the Python 2 package and a command-line executable called tadtool.

Test the installation running

```
tadtool -h
```

and you should see a brief help message.

Usage

TADtool has two basic commands: plot, which invokes the plotting window, and tads, which can be used to call TADs with predefined parameters.

plot

Launching from the command line

Here is the help output from tadtool plot -h:

```
usage: tadtool plot [-h] [-w WINDOW SIZES [WINDOW SIZES ...]] [-a ALGORITHM]
                    [-m MAX DIST] [-d DATA]
                    matrix regions plotting region
Main interactive TADtool plotting window
positional arguments:
                        Square Hi-C Matrix as tab-delimited or .npy file
 matrix
                        (created with numpy.save)
                        BED3 file (no header) with regions corresponding to
  regions
                        the number of rows in the provided matrix.
                        Region of the Hi-C matrix to display in plot. Format:
 plotting region
                        <chromosome>:<start>-<end>, e.g.
                        chr12:31000000-33000000
optional arguments:
                        show this help message and exit
 -w WINDOW SIZES [WINDOW SIZES ...], --window-sizes WINDOW SIZES [WINDOW SIZES
                        Window sizes in base pairs used for TAD calculation.
                        You can pass (1) a filename with whitespace-delimited
                        window sizes, (2) three integers denoting start, stop,
                        and step size to generate a range of window sizes, or
                        (3) more than three integers to define window sizes
                        directly. If left at default, window sizes will be
                        logarithmically spaced between 10**4 and 10**6, or
                        10**6.5 for the insulation and directionality index,
                        respectively.
  -a ALGORITHM, --algorithm ALGORITHM
                        TAD-calling algorithm. Options: insulation,
                        ninsulation, directionality. Default: insulation.
  -m MAX DIST, --max-distance MAX DIST
```

Maximum distance in base-pairs away from the diagonal to be shown in Hi-C plot. Default: 3000000 -d DATA, --data DATA Matrix with index data. Rows correspond to window sizes, columns to Hi-C matrix bins. If provided, suppresses inbuilt index calculation.

plot takes three mandatory (positional) arguments:

- A (square) Hi-C matrix file, which can be either simply a tab-delimited text file, or a numpy .npy file. The latter is for the tech-savvy and can be created with the numpy. save method in Python. It is possible to load large matrices at high resolution, but bear in mind that a large matrix will consume more memory and may slow down TAD calculations. We recommend using intra-chromosomal matrices of a single chromosome for the best experience. Alternatively, it is possible to use several smaller sub-matrices to identify suitable TAD-calling parameters in the interactive tool, and to call TADs on the whole matrix (or individual chromosome matrices) using the non-interactive tads command (see below).
- A BED3 file with region information for the Hi-C matrix, i.e. a tab-delimited file where each row contains chromosome name, start, and end coordinates (inclusive) of the region. This file must not contain any headers.
- A region selector string to inform TADtool about the region it is supposed to plot. The string must be of the format <chromosome>:<start>-<end>, where <end> is inclusive. Examples: chr5:34000000-37000000, chrIX:300000-1000000

When called with only these three arguments

```
tadtool plot /path/to/matrix.txt /path/to/regions.bed chr1:1000000-3000000
```

TADtool will calculate the insulation index for a range of automatically selected window sizes.

Optional arguments give you more control about the data that is generated:

- -w lets you define a custom range of window sizes, either as a file (txt or npy), a range, or specific values.
- -a lets you select the directionality index instead of the insulation index or, by using ninsulation, the insulation index can be normalised to a chromosomal or region average.
- -m lets you specify a distance away from the Hi-C matrix diagonal that should be omitted from the plot.
- -d lets you bypass the TAD-calling calculation completely by providing a file with precomputed index data.

Interactive plotting window

After starting TADtool with the plot option as instructed above, the interactive plotting window will open.



The window consists of four parts: the Hi-C plot with bars indicating the currently called TADs, a line plot with the insulation or directionality index at the current window size, a heatmap with the insulation or directionality index for all specified window sizes, and a row of buttons to save the currently displayed data.

You can use the toolbar at the very bottom of the window to zoom and pan each plot (they will be synchronized) or to save the figure window in its current state.

Hi-C plot



This triangular plot shows a Hi-C map in the selected region from the command line. Use the slider on the top to adjust the color intensity as appropriate. On the bottom you will find bars that indicate the currently called TADs as calculated with the selected parameters.

Index plot



This plot shows the insulation or directionality index for each region in the Hi-C matrix at the currently selected window size. The red line(s) indicate the cutoff that is used to call TADs in this plot. Clicking within the plotting area moves the cutoff and simultaneously recalculates the TADs with the new cutoff. By default, for non-symmetric indexes (insulation index), the cutoff is set directly between the maximum and minimum of the y axis. For symmetric indexes (ninsulation, directionality), the cutoff is set to +/- half the maximum of the y axis.

Heatmap



The heatmap shows all insulation/directionality indexes for each specified window size simultaneously in a condensed form. Every row corresponds to one window size. A red bar indicates the currently chosen window size. Clicking within the plotting area changes the current window size and updates the index plot and TAD indicators. By default, the window size is set to the middle of all calculated window sizes.

Export buttons



At the bottom of the plotting window you will find three buttons that allow you to export TADs, index data, and the index matrix, respectively. Exported values are calculated for the whole supplied matrix, not just the visible region.

tads

This command allows the calculation of TADs directly using one of the provided algorithms. This may be useful for quick TAD calculations when parameters are already known, or to fine-tune

parameters estimated from the main TADtool plot. Here is the help output from tadtool tads -h:

```
usage: tadtool tads [-h] [-a ALGORITHM]
                    matrix regions window size cutoff [output]
Call TADs with pre-defined parameters
positional arguments:
 matrix
                        Square Hi-C Matrix as tab-delimited or .npy file
                        (created with numpy.save)
                       BED3 file (no header) with regions corresponding to
 regions
                       the number of rows in the provided matrix.
 window_size
                      Window size in base pairs
Cutoff for TAD-calling algorithm at given window size.
 cutoff
                       Optional output file to save TADs.
 output
optional arguments:
                       show this help message and exit
   -a ALGORITHM, --algorithm ALGORITHM
                        TAD-calling algorithm. Options: insulation,
                        ninsulation, directionality. Default: insulation.
  -n NORMALISATION WINDOW, --normalisation-window NORMALISATION WINDOW
                        Normalisation window in number of regions. Only
                        affects ninsulation algorithm. If not specified,
                        window will be the whole chromosome.
```

As plot, tads needs a Hi-C matrix and a regions BED file as input. In addition, it requires a window size in base pairs and a cutoff (floating point). Optionally, the user can specify an output file to save TAD regions, otherwise TADs will be written to the command line. For further parameters, see plot.