
## 电容器的电能

$$dW = Udq = \frac{q}{C}dq$$

$$W = \frac{1}{C} \int_0^{Q} q \, \mathrm{d}q = \frac{Q^2}{2C}$$

由
$$C = \frac{Q}{U}$$
 得:

$$W_{\rm e} = \frac{Q^2}{2C} = \frac{1}{2}QU = \frac{1}{2}CU^2$$







# 二 静电场的能量 能量密度

$$W_{\rm e} = \frac{1}{2}CU^2 = \frac{1}{2}\frac{\varepsilon S}{d}(Ed)^2 = \frac{1}{2}\varepsilon E^2 Sd$$

### 电场能量密度

$$w_{\rm e} = \frac{1}{2} \varepsilon E^2 = \frac{1}{2} ED$$

## 电场空间所存储的能量


$$W_{\rm e} = \int_{V} w_{\rm e} dV = \int_{V} \frac{1}{2} \varepsilon E^{2} dV$$





例1 如图所示, 球形电容器的内、外半径分别为 $R_1$ 和 $R_2$ ,所带电荷为±Q. 若在两球壳间充以电容率为 $\varepsilon$ 的电介质,问此电容器

贮存的电场能量为多少?





$$\mathbf{F} = \frac{1}{4\pi\varepsilon} \frac{Q}{r^2}$$


$$w_{\rm e} = \frac{1}{2} \varepsilon E^2 = \frac{Q^2}{32 \pi^2 \varepsilon r^4}$$

$$dW_{e} = w_{e}dV = \frac{Q^{2}}{8\pi \varepsilon r^{2}} dr$$

$$W_{e} = \int dW_{e} = \frac{Q^{2}}{8\pi\varepsilon} \int_{R_{1}}^{R_{2}} \frac{dr}{r^{2}}$$

$$= \frac{Q^{2}}{8\pi\varepsilon} \left(\frac{1}{R_{1}} - \frac{1}{R_{2}}\right)$$

$$R$$





$$W_e = \frac{Q^2}{8\pi\varepsilon} \left(\frac{1}{R_1} - \frac{1}{R_2}\right)$$

$$W_e = \frac{Q^2}{2C}$$


$$R_1 = \frac{Q}{R_2}$$

(1) 
$$W_{\rm e} = \frac{Q^2}{2 C}$$

$$C = 4\pi\varepsilon \frac{R_2 R_1}{R_2 - R_1}$$

(球形电容器)


(2) 
$$R_2 \rightarrow \infty$$
  $W_e = \frac{Q^2}{8\pi \varepsilon R_1}$  (孤立导体球)







例2 圆柱形空气电容器 中,空气的击穿场强是  $E_b=3\times10^6\,\mathrm{V\cdot m^{-1}}$ ,设导体圆 筒的外半径 $R_2 = 10^{-2} \,\mathrm{m}$ . 在空 气不被击穿的情况下,长圆 柱导体的半径R<sub>1</sub>取多大值可 使电容器存储能量最多?




$$\mathbf{\widetilde{F}} \quad E = \frac{\lambda}{2\pi\varepsilon_0 r} \quad (R_1 < r < R_2)$$

$$E_{\rm b} = \frac{\lambda_{\rm max}}{2\pi \, \varepsilon_0 R_1}$$

$$U = \frac{\lambda}{2\pi\varepsilon_0} \int_{R_1}^{R_2} \frac{\mathrm{d}r}{r}$$

$$= \frac{\lambda}{2\pi\varepsilon_0} \ln \frac{R_2}{R_1}$$




$$U = \frac{\lambda}{2\pi \varepsilon_0} \ln \frac{R_2}{R_1}$$
  
单位长度的电场能量

$$W_{e} = \frac{1}{2} \lambda U = \frac{\lambda^{2}}{4\pi \varepsilon_{0}} \ln \frac{R_{2}}{R_{1}}$$

$$E_{b} = \frac{\lambda_{\text{max}}}{2\pi \varepsilon_{0} R_{1}}$$

$$\lambda = \lambda_{\text{max}} = 2\pi \varepsilon_{0} E_{b} R_{1}$$

$$W_{e} = \pi \varepsilon_{0} E_{b}^{2} R_{1}^{2} \ln \frac{R_{2}}{R_{1}}$$



$$W_{e} = \pi \varepsilon_{0} E_{b}^{2} R_{1}^{2} \ln \frac{R_{2}}{R_{1}}$$


$$\frac{dW_{e}}{dR_{1}} = \pi \varepsilon_{0} E_{b}^{2} R_{1} (2 \ln \frac{R_{2}}{R_{1}} - 1) = 0$$

$$R_{1} = \frac{R_{2}}{\sqrt{e}} \approx 6.07 \times 10^{-3} \text{ m}$$

$$U_{\text{max}} = E_{b} R_{1} \ln \frac{R_{2}}{R_{1}} = \frac{E_{b} R_{2}}{2\sqrt{e}}$$

$$= 9.10 \times 10^{3} \text{ V}$$

$$E_{b} = 3 \times 10^{6} \text{ V} \cdot \text{m}^{-1} , R_{2} = 10^{-2} \text{ m}$$



# 选择进入下一节:

- 6-0 教学基本要求
- 6-1 静电场中的导体
- 6-2 静电场中的电介质
- 6-3 电位移 有介质时的高斯定理
- 6-4 电容 电容器
- 6-5 静电场的能量和能量密度