

About

Realtime Cloud Messaging uses the Pub/Sub (publish/subscribe) messaging pattern, where senders of messages, called publishers, do not program the messages to be sent directly to specific receivers, called subscribers.

Instead, published messages are published to topic channels, without knowledge of what, if any, subscribers there may be. Similarly, subscribers express interest in one or more topic channels, and only receive messages that are of interest, without knowledge of what, if any, publishers there are.

This pattern provides greater network scalability and a more dynamic network topology.

Before you dive into your preferred SDK please take a few minutes to read this starting guide. For your convenience it's divided into nine small chapters that will guide you through the main concepts and best practices for optimal use of Realtime Cloud Messaging, also known as ORTC (Open Realtime Connectivity).

Requirements

Unity 4.6 or greater

Supported Platforms

Standalone, Android, iOS

Installation

The Realtime Messaging Client for Untiy3d is distributed as a **.unityPackage**. Here are the steps needed to install the Realtime Messaing Client.

Installation

- Download the Realtime Messaging Client .unityPackage
- Open Unity. It is suggested you start a new project.
- Double click the .unityPackage
- You will be prompted with an import dialog. Import the package.
- Move the Plugin Package to root
 - From /Assets/Realtime/Plugins --> /Assets/Plugins

Configuration

Now that the product has been installed, you must configure it. Configuration is managed by a scriptable object. This object may be accessed by using the **Realtime/Messenger Settings** main menu command.

Account

- Application Key: Identifies your application. This may be acquired from the your account information on the Realtime website.
- Private Key: A secret token used for authorizing clients. If you want to use network security and wish to authenticate directly from the client you will need this.

Service Url

• Service Url: The location of the realtime server

• Is Cluster: Is this server a cluster instance?

Authentication

- Authentication Time: If using Client Authentication, this is how long a authentication session will be valid. This is a sliding expression.
 - Is Private: Limits the authentication token to a single client instance.

Publishing

Socket and Bridge clients

- Unity requires a pro license to use sockets on the mobile platform. If you do not have a pro license you must hide all use of *System.Net.Sockets* or else the build will fail.
- In the /Tools/RealtimeMessaging configuration check the hide sockets toggle to hide all socket references to and use a native bridge client.
- You will need to uncheck this toggle when you finish publishing since all other platforms (including the editor) use the socket client.
- Again, this step is only necessary if you *lack* a Unity Pro Mobile license.

Publishing on Desktop

• Be sure to **use** the Socket client.

Publishing on Webplayer

Be sure to use the Socket client.

Publishing on Android

- Android Free requires an Api level of 9 or above.
- If you do not have Android Pro, be sure to *hide* the Socket client
- Internet access is required
 - Build Settings / Player Settings / Other Settings

Publishing on iOS

- If you do not have IOS Pro, be sure to *hide* the Socket client
- The IOS version requires several XCODE project settings.
- In XCODE Select the Unity Product in Project Settings
- In Project Settings / Build Phases / Libraries add the following libraries
 - <u>libicucore.dylib</u>
 - Security.Framework
- In Project Settings / Linker Settings / Other Linker Flags
 - o add the "-ObjC" linker flag
 - This is case sensitive
 - Forgetting this will cause NSInvalidArgumentExceptions.

Quick Start

Life cycle

The general life cycle of the messenger client is as follows

- **Create** a new messenger client
- Connect the client to the gateway
- AddListeners to receive messages by the client
- RemoveListeners to stop receipt of messages
- **Subscribe** the client to various topic channels
- Send messages
- When complete, **Disconnect** the client
- If the application is pausing call **Pause**. Pause will disconnect the client but cache the subscribed channels.
- When the application resumes call **Resume**. This will reconnect the client and resubscribe to subscribed channels

Tasks

The messenger client makes use of tasks as a strategy to deal with long running operations. Tasks are like Coroutines with return results. In your code it is suggested you use coroutines when interacting with the messenger. Take for instance the connection task.

Example Use

Under **Assets/RealtimeDemos** there is a demonstration scene named "**RealtimeTest**" this scene shows all functionality of the realtime messaging. This scene has a single relevant script "RealTimeTest.cs". The remainder of this documentation will explain this script.

Create

On Awake we create an instance of our RealTimeMessenger object. This object is the main interface object to the realtime network.

```
private RealtimeMessenger Messenger { get; set; }
protected void Awake()
{
          Messenger = new RealtimeMessenger();
}
```

Next, It is suggested that you subscribe to the messenger's events. This will allow you to read messages from the network as they are published.

Authorize

If you require authentication, now is the time to authenticate. Authentication, like most Messenger methods make use of tasks. Tasks require to co-routines to start properly.

Connect

Now that the client has been authorized, it is time to connect to the network.

Disconnect

Likewise, disconnection works the same way.

Subscribe / Unsubscribe

Realtime uses a pub/sub messaging pattern. You will need to subscribe to channels to begin receiving messages. You may also unsubscribe to channels at will.

Sending

Now it is time to send messages.

```
IEnumerator Send()
{
    var task = Messenger.Send(Channel, Message);
    yield return StartCoroutine(task.WaitRoutine());
}
```

Presence

Presence is a way of knowing who is online. The presence response includes the client metadata.