# **Chapter 8: Main Memory**





## **Chapter 8: Memory Management**

Background

Swapping

**Contiguous Memory Allocation** 

Segmentation

Paging

Structure of the Page Table

Example: The Intel 32 and 64-bit Architectures

Example: ARM Architecture





## **Objectives**

To provide a detailed description of various ways of organizing memory hardware

To discuss various memory-management techniques, including paging and segmentation

To provide a detailed description of the Intel Pentium, which supports both pure segmentation and segmentation with paging





## **Background**

Program must be brought (from disk) into memory and placed within a process for it to be run

Main memory and registers are only storage CPU can access directly

Memory unit only sees a stream of addresses + read requests, or address + data and write requests

Register access in one CPU clock (or less)

Main memory can take many cycles, causing a stall

Cache sits between main memory and CPU registers

Protection of memory required to ensure correct operation





## **Background**

#### Jeff Dean:


## Numbers Everyone Should Know

	0 5
L1 cache reference	0.5 ns
Branch mispredict	5 ns
L2 cache reference	7 ns
Mutex lock/unlock	100 ns
Main memory reference	100 ns
Compress 1K bytes with Zippy	10,000 ns
Send 2K bytes over 1 Gbps network	20,000 ns
Read 1 MB sequentially from memory	250,000 ns
Round trip within same datacenter	500,000 ns
Disk seek	10,000,000 ns
Read 1 MB sequentially from network	10,000,000 ns
Read 1 MB sequentially from disk	30,000,000 ns
Send packet CA->Netherlands->CA	150,000,000 ns



## **Base and Limit Registers**


A pair of **base** and **limit registers** define the logical address space CPU must check every memory access generated in user mode to be sure it is between base and limit for that user







### **Hardware Address Protection**







## **Address Binding**

Programs on disk, ready to be brought into memory to execute form an input queue

Without support, must be loaded into address 0000

Inconvenient to have first user process physical address always at 0000

How can it not be?

Further, addresses represented in different ways at different stages of a program's life

Source code addresses usually symbolic

Compiled code addresses **bind** to relocatable addresses

i.e. "14 bytes from beginning of this module"

Linker or loader will bind relocatable addresses to absolute addresses

• i.e. 74014

Each binding maps one address space to another





### **Binding of Instructions and Data to Memory**

Address binding of instructions and data to memory addresses can happen at three different stages

**Compile time**: If memory location known a priori, **absolute code** can be generated; must recompile code if starting location changes

**Load time**: Must generate **relocatable code** if memory location is not known at compile time


**Execution time**: Binding delayed until run time if the process can be moved during its execution from one memory segment to another

 Need hardware support for address maps (e.g., base and limit registers)





### **Binding of Instructions and Data to Memory**








# **Binding of Instructions and Data to Memory**

	PF Explorer Disa	ssembler - <c·\users< th=""><th>\Hank\Document</th><th>s\Visual Studio 2010\Projects\test123\Debug\test1</th></c·\users<>	\Hank\Document	s\Visual Studio 2010\Projects\test123\Debug\test1
	'	3501115101 40.103013	(Harik (Bocarrieric	s (visual studio 2010 (i rojects (test 125 (5 es ug (test 1
🔓   🔚   ʊ 🔟	CODE Z P LP UC OFF BYTE WRD DW QW GUID	] 🎤 🖏 🐴 ▼ 🗣 🗎 🔇 🥝	)   🗊   🕖	
004111BD		SUB_L004111BD	:	
004111BD	E95E0A0000		jmp	L00411C20
004111C2	cccccccccccccccc+	L00411380:	Align	32
00411380 00411380	55	L00411360:	push	ebp
00411381	8BEC		mov	ebp,esp
00411383	81ECC0000000		sub	esp,000000C0h
00411389	53		push	ebx
0041138A	56		push	esi
0041138B	57		push	edi
0041138C	8DBD40FFFFFF		lea	edi,[ebp-000000C0h]
00411392	B930000000		mov	ecx,00000030h
00411397	вессоссос		mov	eax,CCCCCCCCh
0041139C 0041139E	F3AB 8B4508		rep stosd	eax,[ebp+08h]
0041137E	030500704100		mov add	eax,[L00417000]
004113A7	5F		POP	edi
004113A8	5E		рор	esi
004113A9	5B		рор	ebx
004113AA	8BE5		mov	esp,ebp
004113AC	5D		рор	ebp
004113AD	C3		retn	
004113AE	ccccccccccccccc+		Align	32
004113C0		L004113C0:		
004113C0	55 8BEC		push	ebp
004113C1 004113C3	81ECCC000000		mov	ebp,esp
004113C3	53		sub push	esp,000000CCh ebx
004113CA	- 53 - 56		push	esi
004113CB	57		push	edi
004113CC	8DBD34FFFFFF		lea	edi,[ebp-000000CCh]
004113D2	B933000000		mov	ecx,00000033h
004113D7	B8CCCCCCC		mov	eax,CCCCCCCh
004113DC	F3AB		rep <sub>.</sub> stosd	00000000
004113DF	6A02		push	99999999



### **Multistep Processing of a User Program**







## Logical vs. Physical Address Space

The concept of a logical address space that is bound to a separate **physical address space** is central to proper memory management

Logical address – generated by the CPU; also referred to as virtual address

Physical address – address seen by the memory unit

Logical and physical addresses are the same in compile-time and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme

Logical address space is the set of all logical addresses generated by a program

Physical address space is the set of all physical addresses generated by a program





## Memory-Management Unit (MMU)

Hardware device that at run time maps virtual to physical address

Many methods possible, covered in the rest of this chapter

To start, consider simple scheme where the value in the relocation register is added to every address generated by a user process at the time it is sent to memory

Base register now called relocation register

MS-DOS on Intel 80x86 used 4 relocation registers

The user program deals with *logical* addresses; it never sees the *real* physical addresses

Execution-time binding occurs when reference is made to location in memory

Logical address bound to physical addresses





#### Dynamic relocation using a relocation register

Routine is not loaded until it is called

Better memory-space utilization; unused routine is never loaded


All routines kept on disk in relocatable load format

Useful when large amounts of code are needed to handle infrequently occurring cases

No special support from the operating system is required

Implemented through program design

OS can help by providing libraries to implement dynamic loading







## **Dynamic Linking**

Static linking – system libraries and program code combined by the loader into the binary program image

Dynamic linking –linking postponed until execution time

Small piece of code, **stub**, used to locate the appropriate memory-resident library routine

Stub replaces itself with the address of the routine, and executes the routine

Operating system checks if routine is in processes' memory address

If not in address space, add to address space

Dynamic linking is particularly useful for libraries

System also known as shared libraries

Consider applicability to patching system libraries

Versioning may be needed





## **Dynamic Linking**


http://eli.thegreenplace.net/2011/11/03/position-independent-code-pic-in-shared-libraries/

http://www.technovelty.org/linux/plt-and-got-the-key-to-code-sharing-and-dynamic-libraries.html

http://www.acsu.buffalo.edu/~charngda/elf.html

Sample code for creating dynamic linking / loading library http://sense.cs.nctu.edu.tw/courses/code/library\_test.tgz





## **Swapping**

A process can be **swapped** temporarily out of memory to a backing store, and then brought back into memory for continued execution

Total physical memory space of processes can exceed physical memory

Backing store – fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images

Roll out, roll in – swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed

Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped

System maintains a **ready queue** of ready-to-run processes which have memory images on disk





## **Swapping (Cont.)**

Does the swapped out process need to swap back in to same physical addresses?

Depends on address binding method


Plus consider pending I/O to / from process memory space Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)

Swapping normally disabled


Started if more than threshold amount of memory allocated

Disabled again once memory demand reduced below threshold





## **Schematic View of Swapping**









### **Context Switch Time including Swapping**

If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process

Context switch time can then be very high

100MB process swapping to hard disk with transfer rate of 50MB/sec

Swap out time of 2000 ms

Plus swap in of same sized process

Total context switch swapping component time of 4000ms (4 seconds)

Can reduce if reduce size of memory swapped – by knowing how much memory really being used

System calls to inform OS of memory use via request\_memory() and release\_memory()





### **Context Switch Time and Swapping (Cont.)**

Other constraints as well on swapping

Pending I/O – can't swap out as I/O would occur to wrong process

Or always transfer I/O to kernel space, then to I/O device

Known as double buffering, adds overhead

Standard swapping not used in modern operating systems

But modified version common

Swap only when free memory extremely low





## **Swapping on Mobile Systems**

Not typically supported

Flash memory based

- Small amount of space
- Limited number of write cycles
- Poor throughput between flash memory and CPU on mobile platform

Instead use other methods to free memory if low

iOS asks apps to voluntarily relinquish allocated memory

- Read-only data thrown out and reloaded from flash if needed
- Failure to free can result in termination

Android terminates apps if low free memory, but first writes application state to flash for fast restart

Both OSes support paging as discussed below





## **Contiguous Allocation**

Main memory must support both OS and user processes

Limited resource, must allocate efficiently

Contiguous allocation is one early method

Main memory usually into two partitions:

Resident operating system, usually held in low memory with interrupt vector

User processes then held in high memory

Each process contained in single contiguous section of memory





## **Contiguous Allocation (Cont.)**

Relocation registers used to protect user processes from each other, and from changing operating-system code and data

Base register contains value of smallest physical address

Limit register contains range of logical addresses – each logical address must be less than the limit register


MMU maps logical address *dynamically* 


Can then allow actions such as kernel code being transient and kernel changing size





#### **Hardware Support for Relocation and Limit Registers**







## Multiple-partition allocation

#### Multiple-partition allocation

Degree of multiprogramming limited by number of partitions

Variable-partition sizes for efficiency (sized to a given process' needs)


**Hole** – block of available memory; holes of various size are scattered throughout memory

When a process arrives, it is allocated memory from a hole large enough to accommodate it

Process exiting frees its partition, adjacent free partitions combined

Operating system maintains information about:

a) allocated partitions b) free partitions (hole)





## **Dynamic Storage-Allocation Problem**

How to satisfy a request of size *n* from a list of free holes?

First-fit: Allocate the *first* hole that is big enough

Best-fit: Allocate the *smallest* hole that is big enough; must search entire list, unless ordered by size

Produces the smallest leftover hole

Worst-fit: Allocate the *largest* hole; must also search entire list Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization





## **Fragmentation**

**External Fragmentation** – total memory space exists to satisfy a request, but it is not contiguous

Internal Fragmentation – allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used

First fit analysis reveals that given *N* blocks allocated, 0.5 *N* blocks lost to fragmentation

1/3 may be unusable -> 50-percent rule





## Fragmentation (Cont.)

Reduce external fragmentation by compaction

Shuffle memory contents to place all free memory together in one large block

Compaction is possible *only* if relocation is dynamic, and is done at execution time

I/O problem

- Latch job in memory while it is involved in I/O
- Do I/O only into OS buffers

Now consider that backing store has same fragmentation problems





## **Segmentation**

Memory-management scheme that supports user view of memory

A program is a collection of segments

A segment is a logical unit such as:

main program

procedure

function

method

object

local variables, global variables


common block

stack


symbol table

arrays






# User's View of a Program









## **Logical View of Segmentation**





physical memory space





## **Segmentation Architecture**

Logical address consists of a two tuple:

<segment-number, offset>,

**Segment table** – maps two-dimensional physical addresses; each table entry has:

base – contains the starting physical address where the segments reside in memory

limit – specifies the length of the segment

Segment-table base register (STBR) points to the segment table's location in memory

Segment-table length register (STLR) indicates number of segments used by a program;

segment number s is legal if s < STLR





## **Segmentation Architecture (Cont.)**

#### **Protection**

With each entry in segment table associate:

- validation bit =  $0 \Rightarrow$  illegal segment
- read/write/execute privileges

Protection bits associated with segments; code sharing occurs at segment level


Since segments vary in length, memory allocation is a dynamic storage-allocation problem

A segmentation example is shown in the following diagram





## **Segmentation Hardware**







# **Paging**

Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available

Avoids external fragmentation

Avoids problem of varying sized memory chunks

Divide physical memory into fixed-sized blocks called frames

Size is power of 2, between 512 bytes and 16 Mbytes

Divide logical memory into blocks of same size called pages

Keep track of all free frames

To run a program of size **N** pages, need to find **N** free frames and load program

Set up a page table to translate logical to physical addresses

Backing store likewise split into pages

Still have Internal fragmentation





## **Address Translation Scheme**

Address generated by CPU is divided into:

Page number (p) – used as an index into a page table which contains base address of each page in physical memory

Page offset (d) – combined with base address to define the physical memory address that is sent to the memory unit


page number	page offset
p	d
m -n	n

For given logical address space  $2^m$  and page size  $2^n$ 






# **Paging Hardware**








### Paging Model of Logical and Physical Memory







# **Paging Example**



n=2 and m=4 32-byte memory and 4-byte pages





# Paging (Cont.)

Calculating internal fragmentation

Page size = 2,048 bytes

Process size = 72,766 bytes

35 pages + 1,086 bytes

Internal fragmentation of 2,048 - 1,086 = 962 bytes

Worst case fragmentation = 1 frame - 1 byte

On average fragmentation = 1 / 2 frame size

So small frame sizes desirable?

But each page table entry takes memory to track

Page sizes growing over time

Solaris supports two page sizes – 8 KB and 4 MB


Process view and physical memory now very different

By implementation process can only access its own memory





## **Free Frames**



Before allocation

After allocation





+000007FEFDC40000

+000007FEFDC70000

+000007FEFDD50000

Image

Image

Image

W 11/2												
Туре	Size	Committed	Private	Total WS	Privat	Sharea	Shared WS	Locked WS	Blocks	Largest		
Total	95,624 K	54,148 K	2,600 K	7,860 K	2,356 K	5,504 K	5,412 K		214			
Image	31,408 K	31,408 K	536 K	3,972 K	400 K	3,572 K	3,500 K		158	13,848 K		
Mapped File	12,700 K	12,700 K		780 K		780 K	768 K		4	9,408 K		
Shareable	29,584 K	7,912 K		1,140 K		1,140 K	1,132 K		21	20,480 K		
Неар	4,352 K	1,468 K	1,404 K	1,360 K	1,352 K	8 K	8 K		17	1,024 K		
Managed Heap												
Stack	512 K	96 K	96 K	44 K	44 K				3	512 K		
Private Data	16,536 K	32 K	32 K	32 K	28 K	4 K	4 K		11	15,360 K		
Page Table	532 K	532 K	532 K	532 K	532 K							
Free 8	8.589.839.436 K								8.	.581.4		
Address	Туре	Size D	etails					Protection	Commi	Private	Total WS	Priva
+00000000025F0000	Shareable	992 K					F	Read	992 K		324 K	
+0000000002700000	Heap (Priva	. 64 K He	eap ID: 4 [	COMPATABILI <sup>*</sup>	TY]		F	Read/Write	8 K	8 K	8 K	8 K
+00000000027D0000	Heap (Priva	. 1,024 KHe	eap ID: 6 [	LOW FRAGMEN	TATION]		F	Read/Write	224 K	224 K	224 K	224 K
+00000000029B0000	Heap (Priva	. 512 K He	eap ID: 7 [	COMPATABILI	TY]		F	Read/Write	196 K	196 K	144 K	144 K
+0000000003300000	Mapped File	9,408 KC:	:\Windows\F	onts\Static	Cache.dat		F	Read	9,408 K		356 K	
+0000000003C30000	Private Data	1,024 K					F	Read/Write	4 K	4 K	4 K	4 K
+0000000077310000	Image	1,148 KC:	:\Windows\S	ystem32\keri	nel32.dll		E	xecute/Read	1,148 K	24 K	288 K	16 K
+0000000077430000	Image	1,000 KC:	:\Windows\S	ystem32\use	r32.dll		E	xecute/Read	1,000 K	20 K	228 K	12 K
+0000000077530000	Image	1,712 KC:	:\Windows\S	ystem32\ntd	11.dll		E	xecute/Read	1,712 K	68 K	640 K	24 K
<b> 1</b> ■ 0000000007EFE0000	Shareable	1,024 K					F	Read	20 K		20 K	
+000000007F0E0000	Private Data	15,360 K					F	Reserved				
+000000007FFE0000	Private Data	64 K					F	Read	4 K	4 K	4 K	
+00000000FFEA0000	Image	212 KC:	:\Windows\S	ystem32\not	epad.exe		E	xecute/Read	212 K	24 K	72 K	12 K
+000007FEF8DE0000	Image	448 KC:	:\Windows\S	ystem32\win	spool.drv		E	xecute/Read	448 K	20 K	84 K	12 K
+000007FEFB7B0000	Image	96 KC:	:\Windows\S	ystem32\dwma	api.dll		E	xecute/Read	96 K	24 K	32 K	8 K
+000007FEFBB90000	Image	344 KC:	:\Windows\S	ystem32\uxtl	heme.dll		E	xecute/Read	344 K	28 K	172 K	16 K
+000007FEFBC40000	Image	2,000 KC:	:\Windows\w	insxs\amd64	_microsoft.	windows.com	mon-conE	xecute/Read	2,000 K	40 K	236 K	24 K
+000007FEFC590000	Image	48 K C	:\Windows\S	ystem32\ver	sion.dll		E	xecute/Read	48 K	12 K	20 K	8 K
<b>+</b> 000007FEFD3C0000	Image	60 KC:	:\Windows\S	ystem32\cryp	ptbase.dll		E	xecute/Read	60 K	12 K	36 K	8 K
+000007FEFD7F0000	Image	428 KC:	:\Windows\S	ystem32\Keri	nelBase.dll		E	xecute/Read	428 K	20 K	244 K	12 K
+000007FEFDB10000	Image	1,208 KC:	:\Windows\S	ystem32\rpc	rt4.dll		E	xecute/Read	1,208 K	20 K	80 K	12 K
	_											

Virtual memory layout of notepad.exe on Windows

184 KC:\Windows\System32\imm32.dll

412 KC:\Windows\System32\gdi32.dll

860 KC:\Windows\System32\oleaut32.dll



44 K

88 K

104 K

12 K

12 K

16 K

24 K

20 K

Execute/Read

Execute/Read

Execute/Read

184 K

860 K

412 K



## Implementation of Page Table

Page table is kept in main memory

Page-table base register (PTBR) points to the page table

Page-table length register (PTLR) indicates size of the page table

In this scheme every data/instruction access requires two memory accesses

One for the page table and one for the data / instruction

The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)





# Implementation of Page Table (Cont.)

Some TLBs store address-space identifiers (ASIDs) in each TLB entry – uniquely identifies each process to provide address-space protection for that process

Otherwise need to flush at every context switch

TLBs typically small (64 to 1,024 entries)

On a TLB miss, value is loaded into the TLB for faster access next time

Replacement policies must be considered

Some entries can be wired down for permanent fast access





# **Associative Memory**

Associative memory – parallel search

Page #	Frame #

Address translation (p, d)


If p is in associative register, get frame # out

Otherwise get frame # from page table in memory






# **Paging Hardware With TLB**







## **Effective Access Time**

Associative Lookup =  $\varepsilon$  time unit

Can be < 10% of memory access time

Hit ratio =  $\alpha$ 

Hit ratio – percentage of times that a page number is found in the associative registers; ratio related to number of associative registers

Consider  $\alpha$  = 80%,  $\epsilon$  = 20ns for TLB search, 100ns for memory access Effective Access Time (EAT)

EAT = 
$$(1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$
  
=  $2 + \varepsilon - \alpha$ 

Consider  $\alpha$  = 80%,  $\epsilon$  = 20ns for TLB search, 100ns for memory access

 $EAT = 0.80 \times 100 + 0.20 \times 200 = 120 \text{ns}$ 

Consider more realistic hit ratio ->  $\alpha$  = 99%,  $\epsilon$  = 20ns for TLB search, 100ns for memory access

$$EAT = 0.99 \times 100 + 0.01 \times 200 = 101 \text{ns}$$





# **Memory Protection**

Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed

Can also add more bits to indicate page execute-only, and so on

Valid-invalid bit attached to each entry in the page table:

"valid" indicates that the associated page is in the process' logical address space, and is thus a legal page

"invalid" indicates that the page is not in the process' logical address space


Or use page-table length register (PTLR)

Any violations result in a trap to the kernel





# Valid (v) or Invalid (i) Bit In A Page Table







# **Shared Pages**

#### **Shared code**

One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)

Similar to multiple threads sharing the same process space

Also useful for interprocess communication if sharing of read-write pages is allowed

#### Private code and data


Each process keeps a separate copy of the code and data

The pages for the private code and data can appear anywhere in the logical address space





# **Shared Pages Example**







# Structure of the Page Table

Memory structures for paging can get huge using straightforward methods

Consider a 32-bit logical address space as on modern computers

Page size of 4 KB (2<sup>12</sup>)

Page table would have 1 million entries (2<sup>32</sup> / 2<sup>12</sup>)

If each entry is 4 bytes -> 4 MB of physical address space / memory for page table alone

- ▶ That amount of memory used to cost a lot
- Don't want to allocate that contiguously in main memory

Hierarchical Paging

Hashed Page Tables

Inverted Page Tables






# **Hierarchical Page Tables**


Break up the logical address space into multiple page tables

A simple technique is a two-level page table We then page the page table





# **Two-Level Page-Table Scheme**







# **Two-Level Paging Example**

A logical address (on 32-bit machine with 1K page size) is divided into:

a page number consisting of 22 bits

a page offset consisting of 10 bits

Since the page table is paged, the page number is further divided into:

a 12-bit page number

a 10-bit page offset

Thus, a logical address is as follows:

page nu	mber	page oπset
$p_1$	$p_2$	d
12	10	10


where  $p_1$  is an index into the outer page table, and  $p_2$  is the displacement within the page of the inner page table


Known as forward-mapped page table





## **Address-Translation Scheme**







# 64-bit Logical Address Space

Even two-level paging scheme not sufficient If page size is 4 KB (2<sup>12</sup>)

Then page table has 2<sup>52</sup> entries

If two level scheme, inner page tables could be 2<sup>10</sup> 4-byte entries

Address would look like

outer page	inner page	page offset	
$p_1$	$\rho_2$	d	
42	10	12	

Outer page table has 2<sup>42</sup> entries or 2<sup>44</sup> bytes

One solution is to add a 2<sup>nd</sup> outer page table

But in the following example the 2<sup>nd</sup> outer page table is still 2<sup>34</sup> bytes in size

And possibly 4 memory access to get to one physical memory location




# **Three-level Paging Scheme**

outer page	inner page	offset
$p_1$	$p_2$	d
42	10	12

2nd outer page	outer page	inner page	offset
$p_1$	$p_2$	$p_3$	d
32	10	10	12











# **Hashed Page Tables**

Common in address spaces > 32 bits

The virtual page number is hashed into a page table

This page table contains a chain of elements hashing to the same location

Each element contains (1) the virtual page number (2) the value of the mapped page frame (3) a pointer to the next element

Virtual page numbers are compared in this chain searching for a match

If a match is found, the corresponding physical frame is extracted

Variation for 64-bit addresses is clustered page tables


Similar to hashed but each entry refers to several pages (such as 16) rather than 1

Especially useful for **sparse** address spaces (where memory references are non-contiguous and scattered)





# **Hashed Page Table**







# **Inverted Page Table**

Rather than each process having a page table and keeping track of all possible logical pages, track all physical pages

One entry for each real page of memory

Entry consists of the virtual address of the page stored in that real memory location, with information about the process that owns that page

Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs


Use hash table to limit the search to one — or at most a few — page-table entries

TLB can accelerate access


But how to implement shared memory?


One mapping of a virtual address to the shared physical address





# **Inverted Page Table Architecture**







### **Oracle SPARC Solaris**

Consider modern, 64-bit operating system example with tightly integrated HW

Goals are efficiency, low overhead

Based on hashing, but more complex

Two hash tables

One kernel and one for all user processes

Each maps memory addresses from virtual to physical memory

Each entry represents a contiguous area of mapped virtual memory,

 More efficient than having a separate hash-table entry for each page

Each entry has base address and span (indicating the number of pages the entry represents)





# **Oracle SPARC Solaris (Cont.)**

TLB holds translation table entries (TTEs) for fast hardware lookups
A cache of TTEs reside in a translation storage buffer (TSB)

Includes an entry per recently accessed page

Virtual address reference causes TLB search

If miss, hardware walks the in-memory TSB looking for the TTE corresponding to the address

- If match found, the CPU copies the TSB entry into the TLB and translation completes
- If no match found, kernel interrupted to search the hash table
  - The kernel then creates a TTE from the appropriate hash table and stores it in the TSB, Interrupt handler returns control to the MMU, which completes the address translation.





### **Example: The Intel 32 and 64-bit Architectures**

Dominant industry chips

Pentium CPUs are 32-bit and called IA-32 architecture

Current Intel CPUs are 64-bit and called IA-64 architecture

Many variations in the chips, cover the main ideas here





### **Example: The Intel IA-32 Architecture**

Supports both segmentation and segmentation with paging

Each segment can be 4 GB

Up to 16 K segments per process


Divided into two partitions

- First partition of up to 8 K segments are private to process (kept in local descriptor table (LDT))
- Second partition of up to 8K segments shared among all processes (kept in global descriptor table (GDT))



# **Example: The Intel IA-32 Architecture**

### Memory Address Translation






### **Example: The Intel IA-32 Architecture (Cont.)**

### CPU generates logical address

Selector given to segmentation unit

Which produces linear addresses




Linear address given to paging unit

- Which generates physical address in main memory
- Paging units form equivalent of MMU
- Pages sizes can be 4 KB or 4 MB





### **Logical to Physical Address Translation in IA-32**




page n	umber	page offset
$p_1$	$p_2$	d
10	10	12






# **Intel IA-32 Segmentation**







# **Intel IA-32 Paging Architecture**







# Intel IA-32 Page Address Extensions


32-bit address limits led Intel to create page address extension (PAE), allowing 32-bit apps access to more than 4GB of memory space

Paging went to a 3-level scheme

Top two bits refer to a page directory pointer table

Page-directory and page-table entries moved to 64-bits in size

Net effect is increasing address space to 36 bits – 64GB of physical memory







### Intel x86-64

Current generation Intel x86 architecture

64 bits is ginormous (> 16 exabytes)

In practice only implement 48 bit addressing

Page sizes of 4 KB, 2 MB, 1 GB

Four levels of paging hierarchy

Can also use PAE so virtual addresses are 48 bits and physical addresses are 52 bits

		page map	pa	ge directory		page		page			
unused		level 4	<sub>l</sub> po	ointer table	'	directory		table		offset	
63	48 4	7	39 38	30	29	21	20		12 11		0





# **Example: ARM Architecture**

Dominant mobile platform chip (Apple iOS and Google Android devices for example)

Modern, energy efficient, 32-bit CPU

4 KB and 16 KB pages

1 MB and 16 MB pages (termed sections)


One-level paging for sections, twolevel for smaller pages

Two levels of TLBs

Outer level has two micro TLBs (one data, one instruction)

Inner is single main TLB

First inner is checked, on miss outers are checked, and on miss page table walk performed by CPU





# **End of Chapter 8**

