


Computer Architecture and Operating Systems Lecture 5: Assembly Programming – Branches and Arrays

Andrei Tatarnikov


<u>atatarnikov@hse.ru</u> <u>@andrewt0301</u>

Program Structure and Memory Layout



Labels


- Labels are symbolic names for addresses (in the .data or .text segment).
- Labels are used by control-flow instructions (branches and jumps).
- Labels are used by load and store instructions.



Addressing

Addresses can be represented in several ways

1. Immediate addressing



Program Counter

- Program Counter (PC) is a special register that stores the address of the currently executed instruction.
- When an instruction is executed, the PC is incremented by the size of the instruction (4 bytes) to point to the next instruction.
- •Branch and jump instructions assign to the PC new addresses to change the control flow.
- Branch instructions use PC-relative addresses (increment or decrement current value by an offset).

Branch Instructions

Branch Instructions

- Branch = beq rs1, rs2, label
- Branch ≠ bne rs1, rs2, label
- ■Branch < blt rs1, rs2, label
- ■Branch ≥ bge rs1, rs2, label
- Branch < Unsigned bltu rs1, rs2, label</p>
- ■Branch ≥ Unsigned bgeu rs1, rs2, label

Branch Pseudoinstructions


Branch Pseudoinstructions

TODO

How Computer Works

Main Parts:

- Control
- Datapath
- Memory
- Input
- Output



Stored Program Concept

- 32-bit instructions and data stored in memory
- Program is a sequence of instructions
- ■To run a new program:
 - Simply load the new program into memory
- Program Execution:
 - CPU fetches (reads) instructions from memory in sequence
 - CPU performs the specified operations

Stored Program Representation

Assembly Code

lw t0, 32 (t1) add s1, s0, s2 addi t0, s3, -12 sub t0, t3, t5

Machine Code

0x02032283 0x012404B3 0xFF498293 0x41EE02B3

Stored Program

Program Counter (PC):

keeps track of current instruction

Memory

AddressInstructions......0x004000000x020322830x004000040x012404B30x004000080xFF4982930x0040000C0x41EE02B3

10

RISC-V Instructions

Name	Description	Version	Status					
Base								
RVWMO	Weak Memory Ordering	2.0	Ratified					
RV32I	Base Integer Instruction Set, 32-bit	2.1	Ratified					
RV64I	Base Integer Instruction Set, 64-bit	2.1	Ratified					
RV128I	Base Integer Instruction Set, 128-bit	1.7	Open					
Extensions								
M	Standard Extension for Integer Multiplication and Division	2.0	Ratified					
Α	Standard Extension for Atomic Instructions	2.1	Ratified					
F	Standard Extension for Single-Precision Floating-Point	2.2	Ratified					
D	Standard Extension for Double-Precision Floating-Point	2.2	Ratified					
G	Shorthand for the base integer set (I) and above extensions (MAFD)	N/A	N/A					
Q	Standard Extension for Quad-Precision Floating-Point	2.2	Ratified					
С	Standard Extension for Compressed Instructions	2.0	Ratified					
ZiCSR	Control and Status Register (CSR)	2.0	Ratified					
Zifencei	Instruction-Fetch Fence	2.0	Ratified					
And more standard and custom extensions								


Design Principles

- Design Principle 1: Simplicity favors regularity
 - Regularity makes implementation simpler
 - Simplicity enables higher performance at lower cost
- Design Principle 2: Make the common case fast
 - Most common cases affect the performance the most
- Design Principle 3: Smaller is faster
 - 32 registers, fewer instructions
- Design Principle 4: Good design demands good compromises
 - Different formats complicate decoding, but allow 32-bit instructions uniformly
 - Keep formats as similar as possible

Six Instruction Formats

- **R-format:** instructions using 3 register inputs
 - add, xor, mul arithmetic/logical ops
- I-format: instructions with immediates, loads
 - addi, lw, jalr, slli
- **S-format:** store instructions
 - sw, sb
- **SB-format:** branch instructions
 - beq, bge
- U-format: instructions with upper immediates
 - lui, auipc upper immediate is 20-bits
- UJ-format: the jump instruction
 - jal


R-format Instructions



$0000\ 0001\ 0101\ 1010\ 0000\ 0100\ 1011\ 0011_{two} = 015A04B3_{16}$

- Arithmetic Instructions
 - opcode: operation code
 - rd: destination register number
 - funct3: 3-bit function code (additional opcode)
 - rs1 and rs2: first and second source register 5-bit numbers
 - funct7: 7-bit function code (additional opcode)

I-format Instructions



$0001\ 0010\ 0011\ 0011\ 0000\ 0010\ 1001\ 0011_{two} = 0x12330293_{16}$

- •Immediate arithmetic and load instructions
 - rs1: source or base address register number
 - immediate: constant operand, or offset added to base address
 - 2s-complement, sign extended


S-format Instructions

imm[11:5]	rs2	rs1	funct3	imm[4:0]	opcode		
7 bits 5 bits		5 bits 3 bits		5 bits	7 bits		
sw t0, 4(t1)							
0	5	6	2	4	35		
0000000	00101	00110	010	00100	100011		

$0000\ 0000\ 0101\ 0011\ 0010\ 0010\ 0010\ 0011_{two} = 0x00532223_{16}$

- Different immediate format for store instructions
 - rs1: base address register number
 - rs2: source operand register number
 - immediate: offset added to base address
 - Split so that rs1 and rs2 fields always in the same place

SB-format Instructions



0000 0000 0001 0000 0000 0010 0110 0011 $_{two}$ = 00100263 $_{16}$

- Branch instructions specify
 - Opcode, two registers, target address
- Most branch targets are near branch
 - Branch range is +/- 4KB
- PC-relative addressing
 - Target address = PC + immediate × 2


U-format Instructions



0001 0010 0011 0100 0101 0010 1011 0111 $_{two}$ = 123452b7 $_{16}$

- Upper-immediate values: 20-bit values shifted left by 12 bits
 - opcode: operation code
 - rd: destination register number
 - imm: 20-bit immediate value

UJ-format Instructions




0000 0000 0100 0000 0000 0010 1110 $1111_{two} = 004002ef_{16}$

- Jump instructions
 - opcode: operation code
 - rd: destination link register
 - imm: signed offset in multiples of 2 bytes added to PC
 - Target address = PC + immediate × 2
 - Jump range is +/- 1MB

RISC-V Addressing Summary


1. Immediate addressing




2. Register addressing



3. Base addressing



4. PC-relative addressing



Macros

Name	Field					Comments	
(Field Size)	7 bits	5 bits	5 bits	3 bits	5 bits	7 bits	
R-type	funct7	rs2	rs1	funct3	rd	opcode	Arithmetic instruction format
I-type	immediate[11:0]		rs1	funct3	rd	opcode	Loads & immediate arithmetic
S-type	immed[11:5]	rs2	rs1	funct3	immed[4:0]	opcode	Stores
SB-type	immed[12,10:5]	rs2	rs1	funct3	immed[4:1,11]	opcode	Conditional branch format
UJ-type	immediate[20,10:1,11,19:12]				rd	opcode	Unconditional jump format
U-type	immediate[31:12]				rd	opcode	Upper immediate format

Any Questions?

```
__start: addi t1, zero, 0x18
addi t2, zero, 0x21

cycle: beg t1, t2, done
slt t0, t1, t2

kne t0, zero, if_less

nop
sub t1, t1, t2

j cycle

nop

if_less: sub t2, t2, t1

j cycle

done: add t3, t1, zero
```