1 Passing Data to Functions on the Stack

Consider the following assembly program:

```
section .data
section .text
        global main
        addTwo:
                 PUSH ebp
                MOV ebp, esp
                 ADD eax, ebx
                 MOV eax, [ebp+8]
                 MOV \text{ ebx}, [ebp+12]
                 ADD eax, ebx
                 POP ebp
                 RET
        main:
                 PUSH 4
                 PUSH 1
                 CALL addTwo
                 MOV ebx, eax
                 MOV eax, 1
                 INT 80h
```

Here, we are trying to implement parameterized functions!!! To implement parameterized functions in x86, we use the stack(pretty much like for calling standard C functions or even user-defined C functions).

In the program, we are implementing an add function which basically adds two integers and returns their sum.

Snippet from the program:

```
main:

PUSH 4

PUSH 1

CALL addTwo

MOV ebx, eax

MOV eax, 1

INT 80h
```

Here, the first two lines push the values 4 and then 1 into the stack. When we call the **addTwo** function using **CALL** instruction then the return address(the address of instruction after the **CALL** instruction that is **MOV ebx, eax** in our case) is pushed into the stack. So the overall stack looks like this:




Figure 1: The stack

In order to access the integer values from the stack in **addTwo**, we use this approach:

```
addTwo:
PUSH ebp
MOV ebp, esp
```

Here, we are pushing the register **EBP** into the stack. This register basically acts as a base of a stack frame. If we called multiple functions inside a function then we will need something to distinguish between everything that is associ-

ated with the first function and everything that is associated with the second function. The **EBP** register is like the divider.

Hence, our stack looks something like this:




Figure 2: **EBP** inside the stack

We also do MOV ebp, esp where we move the value in ESP into EBP so that EBP and ESP both the registers are pointing to the same location.

With this, now, we will be referencing values ${\bf relative}$ to ${\bf EBP}$ that is as shown below:

```
addTwo:

PUSH ebp
MOV ebp, esp

MOV eax, [ebp+8]
MOV ebx, [ebp+12]

ADD eax, ebx
```

So, here we are accessing the values 1 and 4 from the stack (see figure below), and storing them into registers $\mathbf{E}\mathbf{A}\mathbf{X}$ and $\mathbf{E}\mathbf{B}\mathbf{X}$ respectively:




Figure 3: Stack elements relative to EBP

So, we can see that the values are 4 bytes apart from each other.

Now, we cannot return from **addTwo** because right now, **ESP** is pointing to **EBP** which is at the top of the stack(see Figure 3). In order to make **ESP** point to the return address in the stack, we will have to **POP EBP** from the stack.

Hence,

POP ebp

This pops **EBP** from the stack and **ESP** points to the return address which is now the new top of the stack.




Figure 4: \mathbf{EBP} popped from stack

Now, we can return back to the caller.

2 Verification

We will use GDB to see how the values get stored into the stack:

```
0x804917d <main>
                           push
            <main+2>
                           push
> 0x8049181 <main+4>
                                   0x8049170 <addTwo>
                           call
            <main+9>
                           MOV
            <main+11>
                           MOV
            <main+16>
                           add
 0x8049191 <_fini+1>
                           nop
 0x8049194 <_fini+4>
                           push
 0x8049195 <_fini+5>
                           sub
 0x8049198 <_fini+8>
                           call
  0x804919d < fini+13>
                           add
 0x80491a3 <_fini+19>
                           add
 0x80491a6 < fini+22>
                           pop
 0x80491a7 <_fini+23>
                           add
                           add
                           add
                           add
                           add
                           add
                           add
                           add
                           add
                            add
```

Figure 5: GDB

So, we executed the first two lines.

Once we enter **addTwo**, we will view the value in **ESP**.

```
0x8049170 <addTwo>
                           push
            <addTwo+1>
> 0x8049173 <addTwo+3>
                                  0x8(%ebp),%eax
                           MOV
 0x8049176 <addTwo+6>
                                  0xc(%ebp),9
            <addTwo+9>
                           add
            <addTwo+11>
                           рор
            <addTwo+12>
            <main>
                           push
            <main+2>
                           push
            <main+4>
            <main+9>
            <main+11>
            <main+16>
                           add
            <_fini+1>
            <_fini+4>
                           push
           <_fini+5>
                           sub
           <_fini+8>
                           call
 0x804919d <_fini+13>
                           add
 0x80491a3 <_fini+19>
                           add
 0x80491a6 <_fini+22>
                           pop
 0x80491a7 <_fini+23>
                           add
                           add
```

Figure 6: In addTwo

Now, that we are inside **addTwo**, we will check the values of **ESP**, we also pushed **EBP** into the stack and made **EBP** point to the same memory location as **ESP** as shown below:

```
(gdb) info registers esp
esp 0xffffcf3c 0xffffcf3c
(gdb) info registers ebp
ebp 0xffffcf3c 0xffffcf3c
(gdb)
```

Figure 7: Values in **ESP** and **EBP**

Now, we will see what is stored in the address **0xffffcf3c**.




Figure 8: Value in **0xffffcf3c**

The address 0xf7ffd020 is the address in **EBP**. To verify it, we will see 4 slots of memory from the stack:

```
(gdb) x/4x 0xffffcf3c

0xffffcf3c: 0xf7ffd020 0x08049186 0x00000001 0x000000004

(gdb) ■
```

Figure 9: Values in the stack

We can see that the top of the stack contains 0xf7ffd020 which is the address stored in **EBP**. Then we can see the return address 0x08049186 which is the address of the instruction **MOV ebx**, **eax**, after that we can see the value 1 in hexadecimal and finally we see 4 in hex.

Now, we go on executing the instructions in **addTwo**:

```
0x8049170 <addTwo>
                         push
0x8049171 <addTwo+1>
          <addTwo+3>
          <addTwo+6>
          <addTwo+9>
                         add
          <addTwo+11>
                         pop
0x804917c <addTwo+12>
                         ret
          <main>
                         push
          <main+2>
          <main+4>
                         call
          <main+9>
          <main+11>
          <main+16>
                         add
          <_fini+1>
          <_fini+4>
                         push
          <_fini+5>
          <_fini+8>
                         call
0x804919d <_fini+13>
                         add
0x80491a3 <_fini+19>
                         add
0x80491a6 <_fini+22>
                         pop
          <_fini+23>
                         add
                         add
                         add
```

Figure 10: Execution in progress

We can see that we are about to execute the **RET** instruction that is we are about to return back to the caller(main).

Now, we will check what is in the stack:



Figure 11: **EBP** removed from stack

We can see that **EBP** has been removed and **ESP** has been decremented and now the return address is at the top of the stack. Now after executing the **RET** instruction, we will return to the instruction right after the **CALL** instruction in main.

We can also see that the addition was performed and the result is stored in $\mathbf{EAX}:$




Figure 12: \mathbf{EAX} stores result