# 1 Declaring uninitialized data

Let's look at a program:

```
section .bss
num RESB 3

section .text
global _start
_start:
MOV bl, 1
MOV [num], bl
```

- $\mathbf{RESB} \to \text{means reserve bytes}$ .
- $\mathbf{RESW} \to \text{means reserve word}$ .
- $\mathbf{RESD} \to \mathbf{means}$  reserve double words.
- $\mathbf{RESQ} \to \mathbf{means}$  reserve quadwords.

Now, why did we not just do: **MOV** [**num**], **1**? Beacause x86 doesn't know how big **num** is. That's why we need to store a byte in(in this case 1) into a register first so as to provide that setting of having some definite size so that x86 can perform the **MOV** operation on **num**. Basically **num** is actually a byte array that can store 3 bytes. So as we know(from C/C++) in an array, **the array name points to the starting address of the array**. Similarly, **num** points to the first memory location.

Instructions like MOV depend on the size of the operands to know how many bytes to transfer. So, here in the instruction MOV [num], bl we are basically moving the one byte stored in bl to the byte memory slot of num.

As mentioned earlier, **num** points to the first memory location, if we want to get to the second memory location we will write: [**num+1**] and if we want to get to the third memory location we will write [**num+2**]. Now, this offset depends on the type of data we are working with. Here we are working with bytes. If we were working with words, then to get to the second memory location then we will write: [**num+2**](since a word is 2 bytes in size) and to get to the third memory location we will write: [**num+4**].

Let's start debugging the program.

## Layout

Figure 1: Layout

What has changed in the layout?  $\rightarrow$  The instructions are written in intel assembly language syntax. Generally, the instructions are written in AT&T syntax. To use this layout in gdb, we need to run the following command:

```
$ echo "set disassembly-flavor intel" > ~/.gdbinit
```

Basically, here we are configuring GDB to use intel syntax. To stop the intel layout, we can just open the **.gdbinit** file and remove the command("set disassembly-flavor intel" from there.

So, we can see from the figure below that initially 0x804a000 contained 0(the addresses 0x804a000, 0x804a001 and 0x804a002 are addresses of the three memory blocks that were reserved for num).

```
(gdb) x/x 0x804a000
0x804a000: 0x00000000
(gdb) stepi
0x08049008 in _start ()
(gdb) x/x 0x804a000
0x804a000: 0x00000001
(gdb)
```

Figure 2: Value in 0x804a000

After we ran the **stepi** command, the instruction **MOV** [num], **bl** got executed and then the value **0x01** was stored in the address **0x804a000**.

So, as we go on executing the next instruction the value start getting stored into the memory blocks.

```
(gdb) stepi
0x0804900e in _start ()
(gdb) x/x 0x804a000
0x804a000: 0x00000101
(gdb) stepi
0x08049014 in _start ()
(gdb) x/x 0x804a000
0x804a000: 0x00010101
(gdb)
```

Figure 3: Values getting stored

The two values(hex) that we see in the image above(i.e 0x01 and the last  $0x01(1^{st}$  from the left)) get stored in the memory blocks pointed to by the addresses 0x804a001 and 0x804a002 respectively.

## 2 Can we do the same in the data section?

In the data section, we can only define initialized data.

```
section .data
num DB 3 DUP(2)
```

This basically defines **num** as an array of 3 bytes where each byte stores the value 2. **DUP** here means "duplicate". That means 2 is duplicated three times.

## 2.1 Important

An assembly program:

The addresses in the image are 4 bytes apart.

```
B+> 0x8049000 <_start> mov bl,0x1
0x8049000 <_start+2> mov bl,BYTE PTR ds:0x804a000
0x8049008 <_start+8> mov BYTE PTR ds:0x804a004,bl
0x8049004 <_start+14> mov BYTE PTR ds:0x804a005,bl
0x8049014 <_start+20> mov BYTE PTR ds:0x804a006,bl
0x8049016 <_start+26> mov eax,0x1
0x804901f <_start+31> int 0x80
```

Figure 4: The addresses

Now, num2 is points to the first memory location which is 0x804a000(since it's a byte array).

Also, **num** is also a byte array which points to the first memory location which is **0x904a004**.

Now, we allocated only 3 bytes to **num2** then why is the address of the byte array **num** starting from **0x804a004**? It should have started from **0x804a003**.

Two reasons:

## • Memory alignment

- Variables are aligned to addresses that are multiples of their size.
- **num** is 3 bytes long so it will be aligned to a 4-byte boundary i.e the smallest multiple of 4 that is greater than or equal to 3.

## • <u>Section</u>

• **num** and **num2** are placed in different sections.

For example:

```
section .bss
             num DB 3
2
    section .data
             num2 DB 25 DUP(2)
6
    section .text
             global _start
             _start:
9
                      MOV bl, 1
10
                      MOV bl, [num2]
11
                      MOV [num], bl
12
                      MOV [num+1], bl
13
                      MOV [num+2], bl
14
15
16
                      MOV eax, 1
                      INT 80h
17
```

Now, we have initialized 25 bytes for **num2** and **num** is an array of 3 bytes.

Starting address of **num2** is **0x804a000**. We reserved 25 bytes. So, as per memory alignment we need to align to 4-byte boundary. Now, the smallest multiple of 4 that is greater than or equal to 25 is  $28(4\times7)$ . Note that **num** is also aligned since it is only 3 bytes long.  $(28)_{10} = (0x1c)_{16}$ . So **0x804a000** and the starting address of **num** will be 28 bytes apart.

```
(0x804a000)_{16} = (134520832)_{10}
```

Now we will add 134520832 with 28, this gives us 134520860.

```
(134520860)_{10} = (804a01c)_{16}
```

And that is what we see when we run gdb.

```
B+> 0x8049000 <_start> mov bl,0x1
0x8049002 <_start+2> mov bl,BYTE PTR ds:0x804a000
0x8049008 <_start+8> mov BYTE PTR ds:0x804a01c,bl
0x804900e <_start+14> mov BYTE PTR ds:0x804a01d,bl
0x8049014 <_start+20> mov BYTE PTR ds:0x804a01e,bl
0x804901a <_start+26> mov eax,0x1
0x804901f <_start+31> int 0x80
```

Figure 5: The addresses 28 bytes apart