



**Department of Physics,  
Computer Science & Engineering**

CPSC 410 – Operating Systems I

# Virtualizing Memory: Paging

Keith Perkins

Adapted from “CS 537 Introduction to Operating Systems”  
Arpaci-Dusseau

# Questions answered in this lecture:

---

- Review segmentation and fragmentation
- What is paging?
- Where are page tables stored?
- What are advantages and disadvantages of paging?

# Review: Match Description

## DESCRIPTION

---

- █ one process uses RAM at a time
- █ rewrite code and addresses before running
- █ add per-process starting location to virt addr to obtain phys addr
- █ dynamic approach that verifies address is in valid range
- █ several base+bound pairs per process

NAME OF APPROACH  
(COVERED PREVIOUS  
LECTURE):

---

**Segmentation**

**Static Relocation**

**Base**

**Base+Bounds**

**Time Sharing**

# Review: Match Description

## DESCRIPTION


NAME OF APPROACH  
(COVERED PREVIOUS  
LECTURE):

- █ one process uses RAM at a time
- █ rewrite code and addresses before running
- █ add per-process starting location to virt addr to obtain phys addr
- █ dynamic approach that verifies address is in valid range
- █ several base+bound pairs per process

**Segmentation**  
**Static Relocation**  
**Base**  
**Base+Bounds**  
**Time Sharing**

# Review: Segmentation

Assume 14-bit virtual addresses, high 2 bits indicate segment




Where does segment table live ■

All registers MMU

Seg	Base	Bounds
		ffff
		ffff
-		ff

# Review: Memory Accesses



rip

Seg	Base	Bounds
-		

## Physical Memory Accesses ?

1) Fetch instruction at logical addr 0x0010

- Physical addr:

Exec, load from logical addr 0x1100

- Physical addr:

2) Fetch instruction at logical addr 0x0013

- Physical addr:

Exec, no load

3) Fetch instruction at logical addr 0x0019

- Physical addr:

Exec, **store** to logical addr 0x1100

- Physical addr:

Total of memory references instruction fetches

# Problem: Fragmentation


Definition: Free memory that can't be usefully allocated

Why?

- Free memory (hole) is too small and scattered
- Rules for allocating memory prohibit using this free space

## Types of fragmentation

- External: Visible to allocator (e.g., OS)
- Internal: Visible to requester (e.g., if must allocate at some granularity)




# Paging

Goal: Eliminate requirement that address space is contiguous

- Eliminate external fragmentation
- Grow segments as needed

Idea: Divide address spaces and physical memory into fixed-sized pages

- Size:  $2^n$ , Example: 4KB ( $n=12$ )
- Physical page: page frame




# Paging

Goal: Eliminate requirement that address space is contiguous

- Eliminate external fragmentation
- Grow segments as needed

Idea: Divide address spaces and physical memory into fixed-sized pages


- Size:  $2^n$ , Example: 4KB ( $n=12$ )
- Physical page: page frame



# Translation of Page Addresses

## How to translate logical address to physical address?

- High-order bits of address designate page number
- Low-order bits of address designate offset within page



No addition needed just append bits correctly.

How does format of address space determine number of pages and size of pages ■

# Quiz: Address Format

Given known page size■ how many bits are needed in address to specify offset in page■

Page Size      Low Bits      Offset §

Page Size	Low Bits	Offset §
bytes	□	□
KB	□□	□□
MB	□□□	□□□
bytes	□□□□	□□□□
KB	□□□□□	□□□□□

# Quiz: Address Format

Given number of bits in virtual address and bits for offset  
how many bits for virtual page number ■


Page Size	Low Bits Offset	Virt Addr Bits	High Bits Vpn
bytes	□	■	▶
KB	■	□■	■
MB	■□	□	■-
4 bytes	◀	■	▲
4KB	■-	□	■□

# Quiz: Address Format

Given number of bits for vpn [ ] how many virtual pages can there be in an address space ■

Page Size	Low Bits Offset ↴	Virt Addr Bits	High Bits vpn ↴	Virt Pages
↙ bytes	➡	↖	↗	↗➡
↙ KB	↖	↖ ↗	↖	↖ K
↙ MB	↖ ↗	↖ ↗	↖ ↗	↖ ↗ K
↙ - bytes	↖ ↗	↖ ↗	↖ ↗	↖ ↗ - ↘
➡ KB	↖ ↗	↖ ↗	↖ ↗	↖ ↗ MB

# VirtUAL => Physical PAGE Mapping



Number of bits  
virtual address  
format same as  
need to equal  
number of bits in  
physical address  
format

How should OS translate VPN to PPN?


For segmentation, OS used a formula (e.g.,  $\text{phys addr} = \text{virt\_offset} + \text{base\_reg}$ )

For paging, OS needs more general mapping mechanism


What data structure is good?

An Array  $\triangleright$  pagetable

# The Mapping



# Quiz: Fill in Page Table



# Where Are Pagetables Stored?

How big is a typical page table?

- assume **32-bit** address space
- assume 4 KB pages
- assume 4 byte entries per page table row

Final answer:  $2^{(32 - \log(4KB))} * 4 = 4 \text{ MB}$

- Page table size = Num entries \* size of each entry
- Num entries = num virtual pages =  $2^{\text{bits for vpn}}$
- Bits for vpn = 32 – number of bits for page offset  
 $= 32 - \lg(4KB) = 32 - 12 = 20$
- Num entries =  $2^{20} = 1 \text{ MB}$
- Page table size = Num entries \* 4 bytes = 4 MB

Implication: Store each page table in memory

- Hardware finds page table base with register (e.g., CR3 on x86)

What happens on a context-switch?

- Change contents of page table base register to newly scheduled process

# Other PT info

---

What other info is in pagetable entries besides translation?

- valid bit
- protection bits(R/W)
- present bit (is it memory or on disk?)
- reference bit (used for page eviction algorithms)
- dirty bit (has a page changed and thus needs to be rewritten to disk)

Pagetable entries are just bits stored in memory

- Agreement between hw and OS about interpretation

# Memory Accesses with Pages




Assume PT is at phys addr 0x5000

Assume PTE's are 4 bytes

Assume 4KB pages

So how many bits for offset

Simplified view  
of page table



Old ▶ How many mem refs with segmentation ■

◀ ⌂ instrs ⌂ movl ⌂

Physical Memory Accesses with Paging ?

1) Fetch instruction at logical addr 0x0010; vpn ?

- Access page table to get ppn for vpn 0
- Mem ref 1: 0x5000
- Learn vpn 0 is at ppn 2 (0x0010--0x2010)
- Fetch instruction at 0x2010 (Mem ref 2)

Exec, load from logical addr 0x1100; vpn ?

- Access page table to get ppn for vpn 1
- Mem ref 3: 0x5004
- Learn vpn 1 is at ppn 0 (0x1100--0x0100)
- Movl from 0x0100 into reg (Mem ref 4)
- And so on...

Pagetable is slow!!! Doubles memory references

# Advantages of Paging

---

No external fragmentation

- Any page can be placed in any frame in physical memory

Fast to allocate and free

- Alloc: No searching for suitable free space
- Free: Doesn't have to coalesce with adjacent free space
- Just use bitmap to show free/allocated page frames

Simple to swap-out portions of memory to disk (later lecture)

- Page size matches disk block size
- Can run process when some pages are on disk
- Add “present” bit to PTE

# Disadvantages of Paging

Internal fragmentation: Page size may not match size needed by process

- Wasted memory grows with larger pages

Additional memory reference to page table --> Very inefficient

- Page table must be stored in memory
- MMU stores only base address of page table
- Solution: Add TLBs (a fast cache...and a future lecture)

Storage for page tables may be substantial

- Simple page table: Requires PTE for all pages in address space  
↳ Entry needed even if page not allocated
- Problematic with dynamic stack and heap within address space
- Page tables must be allocated contiguously in memory (its an array)
- Solution: Combine paging and segmentation (future lecture)

