

# Department of Physics, Computer Science & Engineering

CPSC 410 – Operating Systems I

# Virtualizing Memory: Smaller Page Tables

#### **Keith Perkins**

Adapted from "CS 537 Introduction to Operating Systems" Arpaci-Dusseau

#### Questions answered in this lecture:

- Review: What are problems with paging?
- Review: How large can page tables be?
- How can large page tables be avoided with different techniques?
  - multilevel page tables
- What happens on a TLB miss?

# Disadvantages of Paging

#### Additional memory reference to look up in page table

- Very inefficient
- Page table must be stored in memory
- MMU stores only base address of page table (processor tells it which page table to use)
- Avoid extra memory reference for lookup with TLBs (previous lecture)

#### 2. Storage for page tables may be substantial

- Simple page table: Requires PTE for all pages in address space
  - Entry needed even if page not allocated
- Problematic with dynamic stack and heap within address space (today)

- 1. PTE's are 2 bytes, and 32 possible virtual page numbers
- 2. PTE's are **2 bytes**, virtual addrs are **24 bits**, pages are **16 bytes**
- 3. PTE's are 4 bytes, virtual addrs are 32 bits, and pages are 4 KB
- 4. PTE's are 8 bytes, virtual addrs are 64 bits, and pages are 4 KB


- 1. PTE's are 2 bytes, and 32 possible virtual page numbers 32 \* 2 bytes = 64 bytes
- 2. PTE's are 2 bytes, virtual addrs are 24 bits, pages are 16 bytes
- 3. PTE's are 4 bytes, virtual addrs are 32 bits, and pages are 4 KB
- 4. PTE's are 8 bytes, virtual addrs are 64 bits, and pages are 4 KB

- 1. PTE's are 2 bytes, and 32 possible virtual page numbers 32 \* 2 bytes = 64 bytes
- 2. PTE's are 2 bytes, virtual addrs are 24 bits, pages are 16 bytes  $2 \text{ bytes} * 2^{(24 \lg 16)} = 2*2^{20} \text{ bytes} = 2 \text{ MB}$
- 3. PTE's are 4 bytes, virtual addrs are 32 bits, and pages are 4 KB
- 4. PTE's are 8 bytes, virtual addrs are 64 bits, and pages are 4 KB

- 1. PTE's are 2 bytes, and 32 possible virtual page numbers 32 \* 2 bytes = 64 bytes
- 2. PTE's are 2 bytes, virtual addrs are 24 bits, pages are 16 bytes  $2 \text{ bytes} * 2^{(24 \lg 16)} = 2*2^20 \text{ bytes} = 2 \text{ MB}$
- PTE's are 4 bytes, virtual addrs are 32 bits, and pages are 4 KB  $_{4}$  bytes \* 2^(32  $_{1}$ g 4K) = 4\*2^20 bytes = 4 MB
- 4. PTE's are 8 bytes, virtual addrs are 64 bits, and pages are 4 KB

- 1. PTE's are 2 bytes, and 32 possible virtual page numbers 32 \* 2 bytes = 64 bytes
- 2. PTE's are 2 bytes, virtual addrs are 24 bits, pages are 16 bytes  $2 \text{ bytes} * 2^{(24 \lg 16)} = 2*2^{20} \text{ bytes} = 2 \text{ MB}$
- 3. PTE's are 4 bytes, virtual addrs are 32 bits, and pages are 4 KB 4 bytes \*  $2^{(32-1g)}$  4K) =  $4*2^{20}$  bytes = 4 MB
- 4. PTE's are 8 bytes, virtual addrs are 64 bits, and pages are 4 KB 8 bytes \*  $2^{(64-1g)}$  4K) =  $2^{3*2}$ (64-12)= $2^{55}$  bytes

### Why ARE Page Tables so Large?



Need 1 entry per physical frame But you are using very few of the entries

# Many invalid PT entries

#### Format of linear page tables:

how to avoid

storing these?

PFN va	alid	protection
10	1	r-x
-	0	-
23	1	rw-
-	0	_
_	0	-
_	1 0 1 0 0 0	_
_	Ô	_
manı		nvalid
IIIaII)	IIIOI E I	IIvaiiu
-	0	-
-	0	-
_	0	-
-	0	_
28	0 0 0 1 1	rw-
28 4	1	rw-
•	-	- **

BTW where is the code?

valid pages

Invalid pages are not used but still are in page table

### Avoid simple linear Page Tables

Use more complex page tables, instead of just big array Any data structure is possible with software-managed TLB

- Hardware looks for vpn in TLB on every memory access
- If TLB does not contain vpn, TLB miss
  - Trap into OS and let OS find vpn->ppn translation
  - OS notifies TLB of vpn->ppn for future accesses

# Approaches

- 1. Segmented Pagetables
- 2. Inverted Page Tables
- 3. Multi-level Pagetables




This is the one that's used so ignore the first 2


- Page the page tables
- Page the page tables of page tables...

### Multilevel Page Tables

# Goal: Allow page tables to be allocated non-contiguously Idea: Page the page tables

- Creates multiple levels of page tables; outer level "page directory"
- Only allocate page tables for pages in use
- Used in x86 architectures (hardware can walk known structure)





page directory		page of PT	page of PT (@PPN:0x3)		page of PT (@PPN:0x92)		
PPN	valid	PPN	valid	PPN	valid		
0x3	1	0x10	1	-	0		
-	0	0x23	1	-	0		
-	0	-	0	-	0	translate 0x01ABC	
-	0	-	0	_	0		
-	0	0x80	1	-	0		
-	0	0x59	1	-	0	t	
-	0	-	0	-	0	translate 0x00000	
-	0	-	0	_	0		
-	0	-	0	-	0		
-	0	-	0	_	0		
-	0	-	0	_	0	translate 0xFEED0	
-	0	-	0	-	0		
_	0	-	0	-	0		
	0	_	0	0x55	1		
0x92	1	-	0	0x45	1		

20-bit address:

outer page (4 bits)

inner page (4 bits)

page offset (12 bits)

page directory		page of PT (@PPN:0x3)		3) page of I	page of PT (@PPN:0x92)		
PPN	valid	PPN	<u>valid</u>	PPN	valid		
0x3	1	0x10	1	-	0		
-	0	0x23	1	_	0		
-	0	-	0	-	0	translate 0x01ABC	
-	0	-	0	-	0		
-	0	$0 \times 80$	1	-	0	0x23ABC	
-	0	0x59	1	-	0	tl-t- 00000	
-	0	-	0	-	0	translate 0x00000	
-	0	-	0	-	0		
_	0	-	0	-	0		
-	0	-	0	-	0		
_	0	-	0	-	0	translate 0xFEED0	
-	0	-	0	-	0		
-	0	-	0	-	0		
	0	-	0	0x55	1		
0x92	1	-	0	0x45	1		

20-bit address:

outer page (4 bits)

inner page (4 bits)

page offset (12 bits)

page directory page of PT (@PPN:0x3) page of PT (@PPN:0x92)

PPN valid PPN valid PPN valid

PPN	valid	PPN	valid	<u>P</u> 1	PN	valid	
0x3	1	0x10	1		-	0	
-	0	0x23	1		-	0	
-	0	-	0		-	0	translate 0x01ABC
-	0	-	0		-	0	
_	0	0x80	1		-	0	0x23ABC
-	0	0x59	1		-	0	t1-t 00000
-	0	-	0		-	0	translate 0x00000
-	0	-	0		-	0	0x10000
-	0	-	0		-	0	OATOOO
_	0	-	0		-	0	
_	0	-	0		-	0	translate 0xFEED0
_	0	-	0		-	0	
_	0	_	0		-	0	
_	0	-	0	02	x55	1	
0x92	1	-	0	02	x45	1	

20-bit address:

outer page (4 bits)

inner page (4 bits)

page offset (12 bits)

page directory		irectory	page of PT	page of PT (@PPN:0x3)		PT (@PP	N:0x92)
	PPN	valid	PPN	valid	PPN	valid	
	0x3	1	0x10	1	-	0	
	-	0	0x23	1	-	0	
	-	0	-	0	-	0	translate 0x01ABC
	-	0	-	0	-	0	0 00 7 7 8
	-	0	0x80	1	-	0	0x23ABC
	-	0	0x59	1	-	0	translata OrrOOOO
	-	0	-	0	-	0	translate 0x00000
	-	0	-	0	-	0	0x10000
	-	0	-	0	-	0	0210000
	-	0	-	0	-	0	
	-	0	-	0	-	0	translate 0xFEED0
	***************************************						

20-bit address:

0x92

outer page (4 bits)

inner page (4 bits)

page offset (12 bits)

0x55

0x45

0x55ED0

### QUIZ: Address format for multilevel Paging

30-bit address:

outer page

inner page

page offset (12 bits)

#### How should logical address be structured?

How many bits for each paging level?

#### Goal?

- Each page table fits within a page
- PTE size \* number PTE = page size
  - Assume PTE size = 4 bytes
  - Page size = 2^12 bytes = 4KB
- ← Want entire page table to fit in 4kb
- 2^2 bytes \* number PTE = 2^12 bytes
- $\rightarrow$  number PTE = 2^10
- can have 1024 4byte rows
- → # bits for selecting inner page = 10

#### Remaining bits for outer page:

• 30 - 10 - 12 = 8 bits

#### Problem with 2 levels?

Problem: page directories (outer level) may not fit in a page

**64-bit** address:

Solution:

outer page?

inner page (10 bits)

page offset (12 bits)

- Split page directories into pieces
- Use another page dir to refer to the page dir pieces.

 $^{ extsf{-}}$  VPN  $^{ extsf{-}}$ 

PD idx 0 PD idx 1

PT idx

**OFFSET** 

How large is virtual address space with 4 KB pages, 4 byte PTEs, each page table fits in page given 1, 2, 3 levels? Assume 10 bits/level (1K)

4KB / 4 bytes -- 1K entries per level

1 level:  $1K * 4K = 2^2 = 4MB$ 

2 levels:  $1K * 1K * 4K = 2^32 \approx 4 \text{ GB}$ 

3 levels:  $1K * 1K * 1K * 4K = 2^42 \approx 4 TB$ 

#### QUIZ: FULL SYSTEM WITH TLBS

On TLB miss: lookups with more levels more expensive

How much does a miss cost?

Assume 3-level page table

Assume 256-byte pages (8 bits)

Assume 16-bit addresses (so 8 bits for 3 levels)

Assume ASID of current process is 211

ASID	VPN	PFN	Valid
211	0xbb	0x91	1
211	0xff	0x23	1
122	0x05	0x91	1
211	0x05	0x12	0

How many physical accesses for each instruction? (Ignore previous ops changing TLB)

(a) 0xAA10: movl 0x1111, %edi

0xaa: (TLB miss -- 3 for addr trans) + 1 instr fetch

0x11: (TLB miss -- 3 for addr trans) + 1 movl

(b) 0xBB13: addl \$0x3, %edi

Oxbb: (TLB hit -- 0 for addr trans) + 1 instr fetch from 0x9113

(c) 0x0519: movl %edi, 0xFF10

0x05: (TLB miss -- 3 for addr trans) + 1 instr fetch

0xff: (TLB hit -- 0 for addr trans) + 1 movl into 0x2310

Total: 8

Total: 1

Total: 5

## Summary: Better PAGE TABLES

#### Problem:

Simple linear page tables require too much contiguous memory

If Hardware handles TLB miss, page tables must follow specific format

- Multi-level page tables used in x86 architecture
- Each page table fits within a page

#### **Next Topic:**

What if desired address spaces do not fit in physical memory?