Protocol Design Assignment

ToDo

• Send file metadata e.g. rights, owner, creation date, ...

Important

- UDP MTU
- Don't create packages with a size of (bit-size mod 8) != 0. It makes it hard on the receiver side to interpret those!

Protocol

General field descriptions

Type [4 Bit]: 0000 => Client-Hello-Handshake 0001 => Server-Hello-Handshake 0010 => File-Creation 0011 => File-Transfer 0100 => File-Status

0101 => ACK

0110 => Ping

0111 => Transfer-Ended

1000 => Auth-Request

1001 => Auth-Result

Client ID [32 Bit]:

An unique client id generated by the client on first contact.

E.g. A random int

Checksum [32 Bit]:

CRC32 Algorithm Wiki Link

Sequence Number [32 bit]:

Like TCP.

FID Length [64 Bit]:

The length of the FID field in bytes.

FID [Defined in the FID Length filed]: The relative path to the file. Includes the file name e.g. folder/file.txt.

FID Part Number [32 Bit]:

The file part number.

Pub Key [32 Bit]:

The client public key for the Diffie Hellman encryption.

Client-Hello-Handshake

The initial connection message that gets send by the client.

Flags [4 Bit]:

```
0000
||||
|||+-> Connect requested
||+--> Reconnect
|+---> *UNUSED*
+---> *UNUSED*
```

Port [16 Bit]:

The port on which the client listens to server messages.

Prime Number [32 Bit]:

The client prime number for the Diffie Hellman encryption.

Primitive Root [32 Bit]:

The client primitive root for the Diffie Hellman encryption.

Username Length [32 Bit]:

Describes how long the the following Username is in byte.

Username [X Byte]:

Defined via the Username Length.

UNUSED [816-X Bit]:

To "prevent" DoS attacks. Ensures the package is a least 1000 Bit long.

Server-Hello-Handshake

Once the server received a Client-Hello-Handshake message he should reply with this message.

Upload-port [16 Bit]:

The Port where the client should send all following messages to.

Flags [4 Bit]:

```
0000
||||
|||+-> Client accepted
||+--> Too many clients - connection revoked
|+---> Client ID taken - connection revoked
+----> Invalid username - connection revoked
```

File-Creation

Marks the start of a file transfer. Tells the server to create the given file with the given path. Replaces existing files.

```
0 4 36 68 72 328 360
424
+----+
-+---+
| Type | Client ID | Sequence Number | File Type | File MD5 | Checksum | FID Length
| FID |
+----+
```

File Type [4 Bit]:

```
0000
||||
|||+-> Folder
||+--> Delete folder
|+---> File
+---> Delete file
```

File MD5 hash [256 Bit]:

The file MD5 hash to check if the file was transmitted correctly. Unused for folders. Wiki Link

File-Transfer

The actual file transfer message containing the file content.

```
0 4 36 68 72 104
+----+-----+
| Type | Client ID | Sequence Number | Flags | FID Part Number |
+----+

104 360 392 456
+-----+
| FID SHA3 256 | Checksum | Content Length | Content |
+-----+
```

Flags [4 Bit]:

```
0000
||||
|||+-> First package for the given file
||+--> File content
|+---> *UNUSED*
+----> Last package for the file
```

FID SHA3 256 [256 Bit]:

The SHA3 256 hash of the FID to identify which file gets.

Content Length [max 900 Bit]:

The length of the Content field.

Content [defined in "Content Length" in Bit]:

The actual file content.

File-Status

Used for requesting and responding the current file status bevor a file gets transfered.

Flags [4 Bit]:

```
0000
||||
|||+-> Request status of FID
||+--> FID status response
```

```
|+---> Restart sending file system
+----> File = 0/Folder = 1
```

Last FID Part Number [32 Bit]: The last received FID Part Number. Ignored if Request status of FID is set.

ACK

For acknowledging Ping, File-Creation and File-Transfer messages.

ACK Sequence Number [32 Bit]:

The acknowledged Sequence Number or Ping Sequence Number.

Transfer-Ended

Gets send by the client once he wants to end the transfer/close the connection.

Flags [4 Bit]:

```
0000
||||
|||+-> Transfer finished
||+--> Cancelled by user
|+---> Error
+---> *UNUSED*
```

Ping

This message is used for ensuring the opponent is still there. The opponent should acknowledge each received Ping message with an Server-ACK. Should get send by each side if there was no message exchange for more than 2 seconds.

It also can be used for package loss and throughput tests with a modified Payload Length.

```
0 4 36 68 100 104 136

+----+
----+
| Type | Ping Sequence Number | Client ID | Checksum | Unused | Payload Length |
```

```
Payload |
+----+
----+
```

Ping Sequence Number [32 Bit]

An unique number for identifying each ping.

Payload Length [32 Bit]:

Describes how long the the following payload is in byte.

Payload [X Byte]:

Defined via the Payload Length.

Auth-Request

Send by the client to authentificate at the server.

Server-Hello-Handshake Sequence Number [32 Bit]:

The sequence number of the Server-Hello-Handshake message.

Password Length [32 Bit]:

Describes how long the the following password is in byte.

Password [X Byte]:

Defined via the Password Length.

Auth-Result

Send by the server with the authentification result.

Flags [4 Bit]:

```
||||
|||+-> Authentification successfull
||+--> *UNUSED*
|+---> *UNUSED*
+----> *UNUSED*
```

Auth-Request Sequence Number [32 Bit]:

The Sequence number of the received ````Auth-Request``` message.

State charts

FileClient



FileServer

The server it selfe is stateless but it has FileServerClient objects with the following state chart:

Process example

```
Client
                 Server
 | Client-Hello-Handshake
 | -----> | The clients starts the connection on the
default port
               | and tells the server the port on which he listens for answers.
               | It also contains ```ClientStartConnection``` key exchange
data.
 | Server-Hello-Handshake
 | <-----| The server responds with an upload port and
                             | ```onServerReceive``` key exchange data.
 | Auth-Request
 | -----> | If the client got accepted he sends his
password via the
                             | now encrypted connection.
 | Auth-Result
authentification.
                            | Now the connection is established.
 | File-Status
   ----> | The client requests the file status.
 | Auth-Result
 | <-----| The server responds with the current file
status.
 | File-Creation
 | -----> | The client sends this message if the server
does not has
                             | the file yet.
 | Server-ACK
 | <-----| The server acks the ```File-Creation```.
```

Key Exhange

Diffie-Hellman algorithm relies on *discrete logarithm problem*. It is very hard for computers to solve discrete logarithm thus it is a good candidate against brute force attacks. This implementation works like this: - Client and server have to have the common values P and G. P is a prime number and G is the primitive root of that number. As connections are initiated by client, both P and G is calculated by client. Before sending P and G, client generates a private key and calculates it's public key. P , G and client's public key are sent to server by the client at the beginning of the connection.

- Server receives P , G , and client's public key. It selects a private key for itself and calculates it own public key. At this calculation, server also successfully calculates the <code>shared key</code> that the encryption will be based on.
- Client receives server's public key and calculates the shared key. At this point both server and the client have the same shared key which has never transmitted through insecure channels.
- Exposed API of Encrypt and Decrypt uses that shared key to encrypt and decrypt messages.

More info can be found at: Wiki Link

File syncronisation

In order to do file sync we check periodically if there were files changed (It's planned to switch to Filsystem watcher to monitor for changes). To detect which files were changed we compare the <u>MD5's</u> of the files to internally saved hashes of them on the last run.

If the files weren't there in the prior run, they get marked for complete transmission.

If the hash changed we chunk the data into 900 Byte blocks. For each block we will calculate the <u>CRC32</u>. Afterward's it all CRC32 will get compared to the corresponding CRC32 of the previous run. If a CRC32 changed, it replaces the old CRC32 and the Part get's marked for transmission. _If nothing changed_, nothing will be send.